

PL/SQL

Packages and Types Reference

10g Release 1 (10.1)

Part No. B10802-01

December 2003

PL/SQL Packages and Types Reference, 10g Release 1 (10.1)

Part No. B10802-01

Copyright © 1998, 2003 Oracle Corporation. All rights reserved.

Primary Author: Den Raphaely

Contributing Authors: Gina Abeles, Cathy Baird, Deanna Bradshaw, Craig Foch, Laurel Hale, Paul Lane, Jeff Levinger, Roza Leyderman, Chuck Murray, Eric Paapanen, Kathy Rich, Vivian Schupmann, Ingrid Stuart, Randy Urbano

Contributors: Ted Burroughs, Shelley, Higgins, Jennifer Polk, Colin McGregor, Chuck Murray, Richard Smith

Graphics Production Specialist: Valarie Moore

The Programs (which include both the software and documentation) contain proprietary information of Oracle; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent and other intellectual and industrial property laws. Reverse engineering, disassembly or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. Oracle does not warrant that this document is error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of Oracle.

If the Programs are delivered to the U.S. Government or anyone licensing or using the programs on behalf of the U.S. Government, the following notice is applicable:

Restricted Rights Notice Programs delivered subject to the DOD FAR Supplement are "commercial computer software" and use, duplication, and disclosure of the Programs, including documentation, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement. Otherwise, Programs delivered subject to the Federal Acquisition Regulations are "restricted computer software" and use, duplication, and disclosure of the Programs shall be subject to the restrictions in FAR 52.227-19, Commercial Computer Software - Restricted Rights (June, 1987). Oracle, 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and Oracle disclaims liability for any damages caused by such use of the Programs.

Oracle is a registered trademark, and ConText, Oracle Store, Oracle7, Oracle8, Oracle8i, Oracle9i, PL/SQL, Pro*C, and SQL*Plus are trademarks or registered trademarks of Oracle Corporation. Other names may be trademarks of their respective owners.

Contents

Send Us Your Comments	xxv
Preface.....	xxvii
Audience	xxviii
Organization.....	xxviii
Related Documentation	xxviii
Conventions.....	xxix
Documentation Accessibility	xxxi
What's New in PL/SQL Packages and Types Reference?.....	xxxiii
Oracle Database 10g Release 1 (10.1) New Features.....	xxxiv
Oracle9i Release 2 (9.2) New Features	xl
Oracle9i Release 1 (9.0.1) New Features.....	xlii
Oracle8i Release 2 (8.1.6) New Features.....	xliii
Oracle8i Release 1 (8.1.5) New Features.....	xliii
This book was new for release 8.1.5.	xliii
1 Introduction	
Package Overview	1-2
Abbreviations for Datetime and Interval Datatypes.....	1-7
Summary of Oracle Supplied PL/SQL Packages	1-7

2	CTX_ADM	
	Documentation of CTX_ADM.....	2-2
3	CTX_CLS	
	Documentation of CTX_CLS	3-2
4	CTX_DDL	
	Documentation of CTX_DDL.....	4-2
5	CTX_DOC	
	Documentation of CTX_DOC.....	5-2
6	CTX_OUTPUT	
	Documentation of CTX_OUTPUT.....	6-2
7	CTX_QUERY	
	Documentation of CTX_QUERY	7-2
8	CTX_REPORT	
	Documentation of CTX_REPORT.....	8-2
9	CTX_THES	
	Documentation of CTX_THES	9-2
10	CTX_ULEXER	
	Documentation of CTX_ULEXER.....	10-2
11	DBMS_ADVANCED_REWRITE	
	Using DBMS_ADVANCED_REWRITE.....	11-2
	Summary of DBMS_ADVANCED_REWRITE Subprograms.....	11-3

12	DBMS_ADVISOR	
	Using DBMS_ADVISOR	12-2
	Summary of DBMS_ADVISOR Subprograms	12-20
13	DBMS_ALERT	
	Using DBMS_ALERT	13-2
	Summary of DBMS_ALERT Subprograms	13-6
14	DBMS_APPLICATION_INFO	
	Using DBMS_APPLICATION_INFO	14-2
	Summary of DBMS_APPLICATION_INFO Subprograms	14-4
15	DBMS_APPLY_ADM	
	Summary of DBMS_APPLY_ADM Subprograms	15-2
16	DBMS_AQ	
	Using DBMS_AQ	16-2
	Summary of DBMS_AQ Subprograms	16-6
17	DBMS_AQADM	
	Using DBMS_AQADM	17-2
	Summary of DBMS_AQADM Subprograms	17-5
18	DBMS_AQELM	
	Summary of DBMS_AQELM Subprograms	18-2
19	DBMS_CAPTURE_ADM	
	Summary of DBMS_CAPTURE_ADM Subprograms	19-2
20	DBMS_CDC_PUBLISH	
	Using DBMS_CDC_PUBLISH	20-3
	Summary of DBMS_CDC_PUBLISH Subprograms	20-5

21	DBMS_CDC_SUBSCRIBE	
	Using DBMS_CDC_SUBSCRIBE.....	21-2
	Summary of DBMS_CDC_SUBSCRIBE Subprograms.....	21-5
22	DBMS_CRYPTO	
	Using the DBMS_CRYPTO Subprograms.....	22-2
	Summary of DBMS_CRYPTO Subprograms.....	22-10
23	DBMS_DATA_MINING	
	Using DBMS_DATA_MINING.....	23-2
	Summary of DBMS_DATA_MINING Subprograms.....	23-19
24	DBMS_DATA_MINING_TRANSFORM	
	Using DBMS_DATA_MINING_TRANSFORM.....	24-2
	Summary of DBMS_DATA_MINING_TRANSFORM Subprograms.....	24-8
25	DBMS_DATAPUMP	
	Using DBMS_DATAPUMP.....	25-2
	Summary of DBMS_DATAPUMP Subprograms.....	25-9
26	DBMS_DDL	
	Using DBMS_DDL.....	26-2
	Summary of DBMS_DDL Subprograms.....	26-3
27	DBMS_DEBUG	
	Using DBMS_DEBUG.....	27-2
	Summary of DBMS_DEBUG Subprograms.....	27-16
28	DBMS_DEFER	
	Documentation of DBMS_DEFER.....	28-2

29	DBMS_DEFER_QUERY	
	Documentation of DBMS_DEFER_QUERY	29-2
30	DBMS_DEFER_SYS	
	Documentation of DBMS_DEFER_SYS	30-2
31	DBMS_DESCRIBE	
	Using DBMS_DESCRIBE	31-2
	Summary of DBMS_DESCRIBE Subprograms	31-8
32	DBMS_DIMENSION	
	Using DBMS_DIMENSION	32-2
	Summary of DBMS_DIMENSION Subprograms	32-3
33	DBMS_DISTRIBUTED_TRUST_ADMIN	
	Using DBMS_DISTRIBUTED_TRUST_ADMIN	33-2
	Summary of DBMS_DISTRIBUTED_TRUST_ADMIN Subprograms	33-5
34	DBMS_FGA	
	Using DBMS_FGA	34-2
	Summary of DBMS_FGA Subprograms	34-3
35	DBMS_FILE_TRANSFER	
	Summary of DBMS_FILE_TRANSFER Subprograms	35-2
36	DBMS_FLASHBACK	
	Using DBMS_FLASHBACK	36-2
	Summary of DBMS_FLASHBACK Subprograms	36-8
37	DBMS_FREQUENT_ITEMSET	
	Summary of DBMS_FREQUENT_ITEMSET Subprograms	37-2

38	DBMS_HS_PASSTHROUGH	
	Summary of DBMS_HS_PASSTHROUGH Subprograms	38-2
39	DBMS_IOT	
	Summary of DBMS_IOT Subprograms	39-2
40	DBMS_JAVA	
	Documentation of DBMS_JAVA	40-2
41	DBMS_JOB	
	Using DBMS_JOB.....	41-2
	Summary of DBMS_JOB Subprograms	41-5
42	DBMS_LDAP	
	Documentation of DBMS_LDAP.....	42-2
43	DBMS_LDAP_UTL	
	Documentation of DBMS_LDAP_UTL	43-2
44	DBMS_LIBCACHE	
	Using DBMS_LIBCACHE.....	44-2
	Summary of DBMS_LIBCACHE Subprograms	44-3
45	DBMS_LOB	
	Using DBMS_LOB.....	45-2
	Summary of DBMS_LOB Subprograms	45-15
46	DBMS_LOCK	
	Using DBMS_LOCK	46-2
	Summary of DBMS_LOCK Subprograms	46-5

47	DBMS_LOGMNR	
	Using DBMS_LOGMNR.....	47-2
	Summary of DBMS_LOGMNR Subprograms	47-6
48	DBMS_LOGMNR_D	
	Using DBMS_LOGMNR_D	48-2
	Summary of DBMS_LOGMNR_D Subprograms.....	48-3
49	DBMS_LOGSTDBY	
	Using DBMS_LOGSTBY	49-2
	Summary of DBMS_LOGSTDBY Subprograms.....	49-3
50	DBMS_METADATA	
	Using DBMS_METADATA.....	50-2
	Summary of DBMS_METADATA Subprograms	50-8
51	DBMS_MGWADM	
	Using DBMS_MGWADM.....	51-2
	Summary of DBMS_MGWADM Subprograms	51-29
52	DBMS_MGWMSG	
	Using DBMS_MGWMSG.....	52-2
	Summary of DBMS_MGWMSG Subprograms.....	52-24
53	DBMS_MONITOR	
	Summary of DBMS_MONITOR Subprograms.....	53-2
54	DBMS_MVIEW	
	Using DBMS_MVIEW	54-2
	Summary of DBMS_MVIEW Subprograms.....	54-3

55	DBMS_OBFUSCATION_TOOLKIT	
	Using DBMS_OBFUSCATION_TOOLKIT	55-2
	Summary of DBMS_OBFUSCATION Subprograms.....	55-6
56	DBMS_ODCI	
	Summary of DBMS_ODCI Subprograms.....	56-2
57	DBMS_OFFLINE_OG	
	Documentation of DBMS_OFFLINE_OG.....	57-2
58	DBMS_OLAP	
	Using DBMS_OLAP	58-3
	Summary of DBMS_OLAP Subprograms	58-10
59	DBMS_OUTLN	
	Using DBMS_OUTLN	59-2
	Summary of DBMS_OUTLN Subprograms	59-3
60	DBMS_OUTLN_EDIT	
	Summary of DBMS_OUTLN_EDIT Subprograms	60-2
61	DBMS_OUTPUT	
	Using DBMS_OUTPUT	61-2
	Summary of DBMS_OUTPUT Subprograms	61-7
62	DBMS_PCLXUTIL	
	Using DBMS_PCLXUTIL	62-2
	Summary of DBMS_PCLXUTIL Subprograms.....	62-5
63	DBMS_PIPE	
	Using DBMS_PIPE	63-2
	Summary of DBMS_PIPE Subprograms	63-18

64	DBMS_PROFILER	
	Using DBMS_PROFILER.....	64-2
	Summary of DBMS_PROFILER Subprograms	64-8
65	DBMS_PROPAGATION_ADM	
	Summary of DBMS_PROPAGATION_ADM Subprograms	65-2
66	DBMS_RANDOM	
	Using DBMS_RANDOM.....	66-2
	Summary of DBMS_RANDOM Subprograms.....	66-3
67	DBMS_RECTIFIER_DIFF	
	Documentation of DBMS_RECTIFIER_DIFF.....	67-2
68	DBMS_REDEFINITION	
	Using DBMS_REDEFINITION	68-2
	Summary of DBMS_REDEFINITION Subprograms.....	68-4
69	DBMS_REFRESH	
	Documentation of DBMS_REFRESH.....	69-2
70	DBMS_REPAIR	
	Using DBMS_REPAIR.....	70-2
	Summary of DBMS_REPAIR Subprograms.....	70-5
71	DBMS_REPCAT	
	Documentation of DBMS_REPCAT.....	71-2
72	DBMS_REPCAT_ADMIN	
	Documentation of DBMS_REPCAT_ADMIN	72-2

73	DBMS_REPCAT_INSTANTIATE	
	Documentation of DBMS_REPCAT_INSTANTIATE.....	73-2
74	DBMS_REPCAT_RGT	
	Documentation of DBMS_REPCAT_RGT.....	74-2
75	DBMS_REPUTIL	
	Documentation of DBMS_REPUTIL.....	75-2
76	DBMS_RESOURCE_MANAGER	
	Using DBMS_RESOURCE_MANAGER.....	76-2
	Summary of DBMS_RESOURCE_MANAGER Subprograms.....	76-8
77	DBMS_RESOURCE_MANAGER_PRIVS	
	Summary of DBMS_RESOURCE_MANAGER_PRIVS Subprograms.....	77-2
78	DBMS_RESUMABLE	
	Using DBMS_RESUMABLE.....	78-2
	Summary of DBMS_RESUMABLE Subprograms.....	78-3
79	DBMS_RLS	
	Using DBMS_RLS.....	79-2
	Summary of DBMS_RLS Subprograms.....	79-4
80	DBMS_ROWID	
	Using DBMS_ROWID.....	80-2
	Summary of DBMS_ROWID Subprograms.....	80-6
81	DBMS_RULE	
	Using DBMS_RULE.....	81-2
	Summary of DBMS_RULE Subprograms.....	81-3

82	DBMS_RULE_ADM	
	Using DBMS_RULE_ADM.....	82-2
	Summary of DBMS_RULE_ADM Subprograms	82-3
83	DBMS_SCHEDULER	
	Using DBMS_SCHEDULER.....	83-2
	Summary of DBMS_SCHEDULER Subprograms	83-3
84	DBMS_SERVER_ALERT	
	Using DBMS_SERVER_ALERT.....	84-2
	Summary of DBMS_SERVER_ALERT Subprograms	84-11
85	DBMS_SERVICE	
	Using DBMS_SERVICE	85-2
	Summary of DBMS_SERVICE Subprograms	85-3
86	DBMS_SESSION	
	Using DBMS_SESSION.....	86-2
	Summary of DBMS_SESSION Subprograms.....	86-3
87	DBMS_SHARED_POOL	
	Using DBMS_SHARED_POOL.....	87-2
	Summary of DBMS_SHARED_POOL Subprograms.....	87-3
88	DBMS_SPACE	
	Using DBMS_SPACE.....	88-2
	Summary of DBMS_SPACE Subprograms.....	88-3
89	DBMS_SPACE_ADMIN	
	Using DBMS_SPACE_ADMIN.....	89-2
	Summary of DBMS_SPACE_ADMIN Subprograms	89-4

90	DBMS_SQL	
	Using DBMS_SQL	90-2
	Summary of DBMS_SQL Subprograms.....	90-25
91	DBMS_SQLTUNE	
	Using DBMS_SQLTUNE.....	91-2
	Summary of DBMS_SQLTUNE Subprograms	91-4
92	DBMS_STAT_FUNCS	
	Summary of DBMS_STAT_FUNCS Subprograms.....	92-2
93	DBMS_STATS	
	Using DBMS_STATS.....	93-2
	Summary of DBMS_STATS Subprograms	93-11
94	DBMS_STORAGE_MAP	
	Using DBMS_STORAGE_MAP	94-2
	Summary of DBMS_STORAGE_MAP Subprograms	94-4
95	DBMS_STREAMS	
	Using DBMS_STREAMS	95-2
	Summary of DBMS_STREAMS Subprograms.....	95-3
96	DBMS_STREAMS_ADM	
	Using DBMS_STREAMS_ADM.....	96-2
	Summary of DBMS_STREAMS_ADM Subprograms	96-11
97	DBMS_STREAMS_AUTH	
	Summary of DBMS_STREAMS_AUTH Subprograms.....	97-2
98	DBMS_STREAMS_MESSAGING	
	Summary of DBMS_STREAMS_MESSAGING Subprograms.....	98-2

99	DBMS_STREAMS_TABLESPACE_ADM	
	Using DBMS_STREAMS_TABLESPACE_ADM.....	99-2
	Summary of DBMS_STREAMS_TABLESPACE_ADM Subprograms	99-5
100	DBMS_TRACE	
	Using DBMS_TRACE.....	100-2
	Summary of DBMS_TRACE Subprograms.....	100-7
101	DBMS_TRANSACTION	
	Using DBMS_TRANSACTION.....	101-2
	Summary of DBMS_TRANSACTION Subprograms	101-3
102	DBMS_TRANSFORM	
	Summary of DBMS_TRANSFORM Subprograms.....	102-2
103	DBMS_TYPES	
	Using DBMS_TYPES	103-2
104	DBMS_UTILITY	
	Using DBMS_UTILITY	104-2
	Summary of DBMS_UTILITY Subprograms.....	104-4
105	DBMS_WARNING	
	Using DBMS_WARNING.....	105-2
	Summary of DBMS_WARNING Subprograms	105-3
106	DBMS_WORKLOAD_REPOSITORY	
	Summary of DBMS_WORKLOAD_REPOSITORY Subprograms.....	106-2
107	DBMS_WM	
	Documentation of DBMS_WM.....	107-2

108	DBMS_XDB	
	Using DBMS_XDB.....	108-2
	Summary of DBMS_XDB Subprograms	108-4
109	DBMS_XDB_VERSION	
	Summary of DBMS_XDB_VERSION Subprograms	109-2
110	DBMS_TTS	
	Using DBMS_TTS	110-2
	Summary of DBMS_TTS Subprograms	110-3
111	DBMS_XDBT	
	Using DBMS_XDBT	111-2
	Summary of DBMS_XDBT Subprograms	111-5
112	DBMS_XDBZ	
	Summary of DBMS_XDBZ Subprograms	112-2
113	DBMS_XMLDOM	
	Using DBMS_XMLDOM	113-2
	Subprogram Groups	113-7
	Summary of DBMS_XMLDOM Subprograms	113-28
114	DBMS_XMLGEN	
	Summary of DBMS_XMLGEN Subprograms.....	114-2
115	DBMS_XMLPARSER	
	Summary of DBMS_XMLPARSER Subprograms.....	115-2
116	DBMS_XMLQUERY	
	Using DBMS_XMLQUERY	116-2
	Summary of DBMS_XMLQUERY Subprograms	116-3

117	DBMS_XMLSAVE	
	Using DBMS_XMLSAVE	117-2
	Summary of DBMS_XMLSAVE Subprograms	117-3
118	DBMS_XMLSCHEMA	
	Constants of DBMS_XMLSCHEMA	118-2
	Summary of DBMS_XMLSCHEMA Subprograms	118-3
	Catalog Views of the DBMS_XMLSCHEMA	118-18
119	DBMS_XMLSTORE	
	Using DBMS_XMLSTORE	119-2
	Summary of DBMS_XMLSTORE Subprograms	119-3
120	DBMS_XPLAN	
	Using DBMS_XPLAN	120-2
	Summary of DBMS_XPLAN Subprograms	120-8
121	DBMS_XSLPROCESSOR	
	Summary of DBMS_XSLPROCESSOR Subprograms	121-2
122	DEBUG_EXTPROC	
	Using DEBUG_EXTPROC	122-2
	Summary of DEBUG_EXTPROC Subprograms	122-4
123	HTF	
	Using HTF	123-2
	Summary of Tags	123-4
	Summary of HTF Subprograms	123-9
124	HTMLDB_CUSTOM_AUTH	
	Documentation of HTMLDB_CUSTOM_AUTH	124-2

125	HTMLDB_APPLICATION	
	Documentation of HTMLDB_APPLICATION	125-2
126	HTMLDB_ITEM	
	Documentation of HTMLDB_ITEM	126-2
127	HTMLDB_UTIL	
	Documentation of HTMLDB_UTIL	127-2
128	HTP	
	Using HTP	128-2
	Summary of Tags	128-4
	Summary of HTP Subprograms	128-9
129	OWA_CACHE	
	Using OWA_CACHE	129-2
	Summary of OWA_CACHE Subprograms	129-3
130	OWA_COOKIE	
	Using OWA_COOKIE	130-2
	Summary of OWA_COOKIE Subprograms	130-3
131	OWA_CUSTOM	
	Using OWA_CUSTOM	131-2
	Summary of OWA_CUSTOM Subprograms	131-3
132	OWA_IMAGE	
	Using OWA_IMAGE	132-2
	Summary of OWA_IMAGE Subprograms	132-3
133	OWA_OPT_LOCK	
	Using OWA_OPT_LOCK	133-2

	Summary of OWA_OPT_LOCK Subprograms.....	133-3
134	OWA_PATTERN	
	Using OWA_PATTERN	134-2
	Summary of OWA_PATTERN Subprograms	134-5
135	OWA_SEC	
	Using OWA_SEC.....	135-2
	Summary of OWA_SEC Subprograms	135-3
136	OWA_TEXT	
	Using OWA_TEXT	136-2
	Summary of OWA_TEXT Subprograms.....	136-3
137	OWA_UTIL	
	Using OWA_UTIL.....	137-2
	Summary of OWA_UTIL Subprograms	137-4
138	SDO_CS	
	Documentation of SDO_CS.....	138-2
139	SDO_GCDR	
	Documentation of SDO_GCDR.....	139-2
140	SDO_GEOM	
	Documentation of SDO_GEOM	140-2
141	SDO_GEOR	
	Documentation of SDO_GEOR.....	141-2
142	SDO_GEOR_UTL	
	Documentation of SDO_GEOR_UTL.....	142-2

143	SDO_LRS	
	Documentation of SDO_LRS	143-2
144	SDO_MIGRATE	
	Documentation of SDO_MIGRATE.....	144-2
145	SDO_NET	
	Documentation of SDO_NET.....	145-2
146	SDO_SAM	
	Documentation of SDO_SAM.....	146-2
147	SDO_TOPO	
	Documentation of SDO_TOPO	147-2
148	SDO_TOPO_MAP	
	Documentation of SDO_TOPO_MAP.....	148-2
149	SDO_TUNE	
	Documentation of SDO_TUNE.....	149-2
150	SDO_UTIL	
	Documentation of SDO_UTIL	150-2
151	UTL_COLL	
	Summary of UTL_COLL Subprograms.....	151-2
152	UTL_COMPRESS	
	Using UTL_COMPRESS.....	152-2
	Summary of UTL_COMPRESS Subprograms	152-4

153	UTL_DBWS	
	Using UTL_DBWS.....	153-2
	Summary of UTL_DBWS Subprograms	153-3
154	UTL_ENCODE	
	Summary of UTL_ENCODE Subprograms	154-2
155	UTL_FILE	
	Using UTL_FILE.....	155-2
	Summary of UTL_FILE Subprograms	155-8
156	UTL_HTTP	
	Using UTL_HTTP	156-2
	Subprogram Groups.....	156-21
	Summary of UTL_HTTP Subprograms.....	156-30
157	UTL_I18N	
	Using UTL_I18n	157-2
	Summary of UTL_I18N Subprograms	157-3
158	UTL_INADDR	
	Using UTL_INADDR.....	158-2
	Summary of UTL_INADDR Subprograms	158-3
159	UTL_LMS	
	Using UTL_LMS	159-2
	Summary of UTL_LMS Subprograms.....	159-3
160	UTL_MAIL	
	Using UTL_MAIL.....	160-2
	Summary of UTL_MAIL Subprograms.....	160-3

161	UTL_RAW	
	Using UTL_RAW	161-2
	Summary of UTL_RAW Subprograms	161-3
162	UTL_RECOMP	
	Using UTL_RECOMP	162-2
	Summary of UTL_RECOMP Subprograms	162-4
163	UTL_REF	
	Using UTL_REF	163-2
	Summary of UTL_REF Subprograms	163-5
164	UTL_SMTP	
	Using UTL_SMTP	164-2
	Summary of UTL_SMTP Subprograms	164-9
165	UTL_TCP	
	Using UTL_TCP	165-2
	Summary of UTL_TCP Subprograms	165-7
166	UTL_URL	
	Using UTL_URL	166-2
	Summary of UTL_URL Subprograms	166-4
167	WPG_DOCLOAD	
	Using WPG_DOCLOAD	167-2
	Summary of WPG_DOCLOAD Subprograms	167-3
168	ANYDATA TYPE	
	Using ANYDATA TYPE	168-2
	Summary of ANYDATA Subprograms	168-5

169	ANYDATASET TYPE	
	Construction.....	169-2
	Summary of ANYDATASET TYPE Subprograms.....	169-3
170	ANYTYPE TYPE	
	Summary of ANYTYPE Subprograms.....	170-2
171	Oracle Streams AQ TYPES	
	Summary of Types.....	171-2
172	Database URI TYPES	
	Summary of URITYPE Supertype Subprograms	172-2
	Summary of HTTPURITYPE Subtype Subprograms.....	172-9
	Summary of DBURITYPE Subtype Subprograms.....	172-18
	Summary of XDBURITYPE Subtype Subprograms	172-27
	Summary of URIFACTORY Package Subprograms	172-36
173	JMS Types	
	Using JMS Types.....	173-2
	Summary of JMS Types.....	173-14
174	Logical Change Record TYPES	
	Summary of Logical Change Record Types.....	174-2
	Common Subprograms for LCR\$_DDL_RECORD and LCR\$_ROW_RECORD	174-33
175	<i>interMedia</i> ORDAudio TYPE	
	Documentation of ORDAudio.....	175-2
176	<i>interMedia</i> ORDDoc TYPE	
	Documentation of ORDDoc	176-2

177	<i>interMedia</i> ORDImage TYPE	
	Documentation of ORDImage	177-2
178	<i>interMedia</i> ORDImageSignature TYPE	
	Documentation of ORDImageSignature.....	178-2
179	<i>interMedia</i> SQL/MM Still Image TYPE	
	Documentation of SQL/MM Still Image.....	179-2
180	<i>interMedia</i> ORDVideo TYPE	
	Documentation of ORDVideo.....	180-2
181	Rule TYPEs	
	Summary of Rule Types.....	181-2
182	XMLTYPE	
	Summary of XMLType Subprograms	182-2

Index

Send Us Your Comments

PL/SQL Packages and Types Reference, 10g Release 1 (10.1)

Part No. B10802-01

Oracle Corporation welcomes your comments and suggestions on the quality and usefulness of this document. Your input is an important part of the information used for revision.

- Did you find any errors?
- Is the information clearly presented?
- Do you need more information? If so, where?
- Are the examples correct? Do you need more examples?
- What features did you like most?

If you find any errors or have any other suggestions for improvement, please indicate the document title and part number, and the chapter, section, and page number (if available). You can send comments to us in the following ways:

- Electronic mail: infodev_us@oracle.com
- FAX: (650) 506-7227 Attn: Server Technologies Documentation Manager
- Postal service:
Oracle Corporation
Server Technologies Documentation
500 Oracle Parkway, Mailstop 4op11
Redwood Shores, CA 94065
USA

If you would like a reply, please give your name, address, telephone number, and (optionally) electronic mail address.

If you have problems with the software, please contact your local Oracle Support Services.

Preface

This reference manual describes the Oracle PL/SQL packages shipped with the Oracle database server. This information applies to versions of the Oracle database server that run on all platforms unless otherwise specified.

This preface contains these topics:

- [Audience](#)
- [Organization](#)
- [Related Documentation](#)
- [Conventions](#)
- [Documentation Accessibility](#)

Audience

PL/SQL Packages and Types Reference is intended for programmers, systems analysts, project managers, and others interested in developing database applications. This manual assumes a working knowledge of application programming and familiarity with SQL to access information in relational database systems. Some sections also assume a knowledge of basic object-oriented programming.

Organization

See [Table 1-1, "Summary of Oracle Supplied PL/SQL Packages"](#) on page 1-8 for information about the organization of this reference.

Related Documentation

For more information, see these Oracle resources:

- *Oracle Database Application Developer's Guide - Fundamentals*
- *PL/SQL User's Guide and Reference*

Many books in the documentation set use the sample schemas of the seed database, which is installed by default when you install Oracle. Refer to *Oracle Database Sample Schemas* for information on how these schemas were created and how you can use them yourself.

Printed documentation is available for sale in the Oracle Store at

<http://oraclestore.oracle.com/>

To download free release notes, installation documentation, white papers, or other collateral, please visit the Oracle Technology Network (OTN). You must register online before using OTN; registration is free and can be done at

<http://otn.oracle.com/admin/account/membership.html>

If you already have a username and password for OTN, then you can go directly to the documentation section of the OTN Web site at

<http://otn.oracle.com/docs/index.htm>

Conventions

This section describes the conventions used in the text and code examples of this documentation set. It describes:

- [Conventions in Text](#)
- [Conventions in Code Examples](#)

Conventions in Text

We use various conventions in text to help you more quickly identify special terms. The following table describes those conventions and provides examples of their use.

Convention	Meaning	Example
Bold	Bold typeface indicates terms that are defined in the text or terms that appear in a glossary, or both.	When you specify this clause, you create an index-organized table .
<i>Italics</i>	Italic typeface indicates book titles, emphasis, syntax clauses, or placeholders.	<i>Oracle Database Concepts</i> Ensure that the recovery catalog and target database do <i>not</i> reside on the same disk.
UPPERCASE monospace (fixed-width font)	Uppercase monospace typeface indicates elements supplied by the system. Such elements include parameters, privileges, datatypes, RMAN keywords, SQL keywords, SQL*Plus or utility commands, packages and methods, as well as system-supplied column names, database objects and structures, user names, and roles.	You can specify this clause only for a NUMBER column. You can back up the database by using the BACKUP command. Query the TABLE_NAME column in the USER_TABLES data dictionary view. Use the DBMS_STATS.GENERATE_STATS procedure.
lowercase monospace (fixed-width font)	Lowercase monospace typeface indicates executables and sample user-supplied elements. Such elements include computer and database names, net service names, and connect identifiers, as well as user-supplied database objects and structures, column names, packages and classes, user names and roles, program units, and parameter values.	Enter <code>sqlplus</code> to open SQL*Plus. The password is specified in the <code>orapwd</code> file. Back up the datafiles and control files in the <code>/disk1/oracle/dbs</code> directory. The <code>department_id</code> , <code>department_name</code> , and <code>location_id</code> columns are in the <code>hr.departments</code> table. The <code>JRepUtil</code> class implements these methods.

Conventions in Code Examples

Code examples illustrate SQL, PL/SQL, SQL*Plus, or other command-line statements. They are displayed in a monospace (fixed-width) font and separated from normal text as shown in this example:

```
SELECT username FROM dba_users WHERE username = 'MIGRATE';
```

The following table describes typographic conventions used in code examples and provides examples of their use.

Convention	Meaning	Example
[]	Brackets enclose one or more optional items. Do not enter the brackets.	DECIMAL (<i>digits</i> [, <i>precision</i>])
{ }	Braces enclose two or more items, one of which is required. Do not enter the braces.	{ENABLE DISABLE}
	A vertical bar represents a choice of two or more options within brackets or braces. Enter one of the options. Do not enter the vertical bar.	{ENABLE DISABLE} [COMPRESS NOCOMPRESS]
...	Horizontal ellipsis points indicate either: <ul style="list-style-type: none"> That we have omitted parts of the code that are not directly related to the example That you can repeat a portion of the code 	CREATE TABLE ... AS <i>subquery</i> ; SELECT <i>col1</i> , <i>col2</i> , ... , <i>coln</i> FROM employees;
. . . .	Vertical ellipsis points indicate that we have omitted several lines of code not directly related to the example.	SQL> SELECT NAME FROM V\$DATAFILE; NAME ----- /fsl/dbs/tbs_01.dbf /fsl/dbs/tbs_02.dbf
Other notation	You must enter symbols other than brackets, braces, vertical bars, and ellipsis points as shown.	acctbal NUMBER(11,2); acct CONSTANT NUMBER(4) := 3;

Convention	Meaning	Example
<i>Italics</i>	Italicized text indicates placeholders or variables for which you must supply particular values.	CONNECT SYSTEM/ <i>system_password</i> DB_NAME = <i>database_name</i>
UPPERCASE	Uppercase typeface indicates elements supplied by the system. We show these terms in uppercase in order to distinguish them from terms you define. Unless terms appear in brackets, enter them in the order and with the spelling shown. However, because these terms are not case sensitive, you can enter them in lowercase.	SELECT last_name, employee_id FROM employees; SELECT * FROM USER_TABLES; DROP TABLE hr.employees;
lowercase	Lowercase typeface indicates programmatic elements that you supply. For example, lowercase indicates names of tables, columns, or files. Note: Some programmatic elements use a mixture of UPPERCASE and lowercase. Enter these elements as shown.	SELECT last_name, employee_id FROM employees; sqlplus hr/hr CREATE USER mjones IDENTIFIED BY ty3MU9;

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible, with good usability, to the disabled community. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For additional information, visit the Oracle Accessibility Program Web site at

<http://www.oracle.com/accessibility/>

Accessibility of Code Examples in Documentation JAWS, a Windows screen reader, may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, JAWS may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

What's New in PL/SQL Packages and Types Reference?

The following sections describe the new features in Oracle PL/SQL Packages and Types Reference:

- [Oracle Database 10g Release 1 \(10.1\) New Features](#)
 - [New Packages](#)
 - [New Types](#)
 - [Updated Packages](#)
 - [Updated Types](#)
- [Oracle9i Release 2 \(9.2\) New Features](#)
- [Oracle9i Release 1 \(9.0.1\) New Features](#)
- [Oracle8i Release 2 \(8.1.6\) New Features](#)
- [Oracle8i Release 1 \(8.1.5\) New Features](#)

Oracle Database 10g Release 1 (10.1) New Features

New Packages

- DBMS_ADVANCED_REWRITE
- DBMS_ADVISOR
- DBMS_CRYPTO
- DBMS_DATAPUMP
- DBMS_DATA_MINING
- DBMS_DATA_MINING_TRANSFORM
- DBMS_DIMENSION
- DBMS_FILE_TRANSFER
- DBMS_FREQUENT_ITEMSET
- DBMS_JAVA
- DBMS_MONITOR
- DBMS_SCHEDULER
- DBMS_SERVER_ALERT
- DBMS_SERVICE
- DBMS_SQLTUNE
- DBMS_STAT_FUNCS
- DBMS_STREAMS_AUTH
- DBMS_STREAMS_MESSAGING
- DBMS_STREAMS_TABLESPACE_ADM
- DBMS_WARNING
- DBMS_WORKLOAD_REPOSITORY
- DBMS_XDBZ
- DBMS_XMLSTORE
- HTF
- HTMLDB_CUSTOM_AUTH

- HTMLDB_APPLICATION
- HTMLDB_ITEM
- HTMLDB_UTIL
- HTP
- OWA_CACHE
- OWA_COOKIE
- OWA_CUSTOM
- OWA_IMAGE
- OWA_OPT_LOCK
- OWA_PATTERN
- OWA_SEC
- OWA_TEXT
- OWA_UTIL
- SDO_GCDR
- SDO_GEOR
- SDO_GEOR_UTL
- SDO_NET
- SDO_SAM
- SDO_TOPO
- SDO_TOPO_MAP
- UTL_COMPRESS
- UTL_DBWS
- UTL_I18N
- UTL_LMS
- UTL_MAIL
- UTL_RECOMP
- WPG_DOCLOAD

New Types

- Database URI TYPES
- XMLTYPE

Updated Packages

- DBMS_APPLICATION_INFO
- DBMS_APPLY_ADM
- DBMS_AQ
- DBMS_AQADM
- DBMS_AQELM
- DBMS_CAPTURE_ADM
- DBMS_CDC_PUBLISH
- DBMS_CDC_SUBSCRIBE
- DBMS_DDL
- DBMS_DESCRIBE
- DBMS_DISTRIBUTED_TRUST_ADMIN
- DBMS_FGA
- DBMS_JOB
- DBMS_LIBCACHE
- DBMS_LOB
- DBMS_LOGMNR
- DBMS_LOGMNR_D
- DBMS_METADATA

- DBMS_MGWADM
- DBMS_MGWMSG
- DBMS_MVIEW
- DBMS_OBFUSCATION_TOOLKIT
- DBMS_OLAP
- DBMS_OUTLN
- DBMS_OUTLN_EDIT
- DBMS_OUTPUT
- DBMS_PROPAGATION_ADM
- DBMS_REDEFINITION
- DBMS_REDEFINITION
- DBMS_RESOURCE_MANAGER
- DBMS_RLS
- DBMS_ROWID
- DBMS_RULE
- DBMS_RULE_ADM

- DBMS_SESSION
- DBMS_SPACE
- DBMS_SQL
- DBMS_STATS
- DBMS_STREAMS
- DBMS_STREAMS_ADM
- DBMS_TTS
- DBMS_TYPES
- DBMS_UTILITY
- DBMS_WM
- DBMS_XDB
- DBMS_XDB_VERSION
- DBMS_XMLGEN
- DBMS_XMLSCHEMA
- DBMS_XPLAN
- DBMS_XSLPROCESSOR
- DBMS_WM
- SDO_CS
- SDO_GEOM
- SDO_LRS
- SDO_MIGRATE
- SDO_TUNE
- SDO_UTIL
- UTL_ENCODE
- UTL_FILE
- UTL_RAW
- UTL_URL

Updated Types

- ANYDATA TYPE
- ANYDATASET TYPE
- Oracle Streams AQ TYPES
- Logical Change Record TYPES
- Rule TYPES

Oracle9i Release 2 (9.2) New Features

This release includes the following new chapters:

- Advanced Queuing Types
- DBMS_APPLY_ADM
- DBMS_CAPTURE_ADM
- DBMS_LOGSTDBY
- DBMS_MGWADM
- DBMS_MGWMSG
- DBMS_PROPAGATION_ADM
- DBMS_RULE
- DBMS_RULE_ADM
- DBMS_STORAGE_MAP
- DBMS_STREAMS
- DBMS_STREAMS_ADM
- DBMS_XDB
- DBMS_XDBT
- DBMS_XDB_VERSION
- DBMS_XMLDOM
- DBMS_XMLPARSER
- DBMS_XPLAN
- DBMS_XSLPROCESSOR
- JMS Types
- Logical Change Record Types
- Rule Types

This release includes changes to the following chapters:

- DBMS_DDL
- DBMS_FLASHBACK
- DBMS_LOB
- DBMS_LOGMNR
- DBMS_LOGMNR_CDC_PUBLISH
- DBMS_LOGMNR_CDC_SUBSCRIBE
- DBMS_LOGMNR_D
- DBMS_METADATA
- DBMS_REDEFINITION
- DBMS_RLS
- DBMS_SPACE_ADMIN
- DBMS_STATS
- DBMS_TRANSFORM
- DBMS_WM
- DBMS_XMLGEN
- DBMS_XMLQUERY
- DBMS_XMLSAVE
- DBMS_XMLSchema
- UTL_FILE
- UTL_HTTP

Oracle9i Release 1 (9.0.1) New Features

This release includes the following new packages:

- DBMS_AQELM
- DBMS_ENCODE
- DBMS_FGA
- DBMS_FLASHBACK
- DBMS_LDAP
- DBMS_LibCache
- DBMS_LOGMNR_CDC_PUBLISH
- DBMS_LOGMNR_CDC_SUBSCRIBE
- DBMS_METADATA
- DBMS_ODCI
- DBMS_OUTLN_EDIT
- DBMS_REDEFINITION
- DBMS_TRANSFORM
- DBMS_URL
- DBMS_WM
- DBMS_XMLGEN
- DBMS_XMLQuery
- DMBS_XMLSave
- UTL_ENCODE

This release includes new information about types:

- DBMS_TYPES
- ANYDATA_TYPE
- ANYDATASET_TYPE
- ANYTYPE_TYPE

This release includes enhancements to the following packages:

- UTL_FILE
- UTL_HTTP
- UTL_RAW

Oracle8i Release 2 (8.1.6) New Features

This release included the following new packages

- DBMS_BACKUP_RESTORE
- DBMS_OBFUSCATION_TOOLKIT
- UTL_INADDR
- UTL_SMTP
- UTL_TCP

This release included enhancements to the following packages:

- DBMS_DEBUG
- DBMS_DISTRIBUTED_TRUST_ADMIN
- DBMS_LOGMINER
- DBMS_LOGMINER_D
- DBMS_PCLXUTIL
- DBMS_PROFILER
- DBMS_REPAIR
- DBMS_RESOURCE_MANAGER
- DBMS_ROWID
- DBMS_SQL
- DBMS_UTILITY
- UTL_HTTP

Oracle8i Release 1 (8.1.5) New Features

This book was new for release 8.1.5.

Introduction

Oracle supplies many PL/SQL packages with the Oracle server to extend database functionality and provide PL/SQL access to SQL features. You can use the supplied packages when creating your applications or for ideas in creating your own stored procedures.

Note: This manual covers the packages provided with the Oracle database server. Packages supplied with other products, such as Oracle Developer or the Oracle Application Server, are not covered.

This chapter contains the following topics:

- [Package Overview](#)
- [Abbreviations for Datetime and Interval Datatypes](#)
- [Summary of Oracle Supplied PL/SQL Packages](#)

See Also: *Oracle Database Application Developer's Guide - Fundamentals* for information on how to create your own packages

Package Overview

A *package* is an encapsulated collection of related program objects stored together in the database. Program objects are procedures, functions, variables, constants, cursors, and exceptions.

Packages have many advantages over standalone procedures and functions. For example, they:

- Let you organize your application development more efficiently.
- Let you grant privileges more efficiently.
- Let you modify package objects without recompiling dependent schema objects.
- Enable Oracle to read multiple package objects into memory at once.
- Let you *overload* procedures or functions. Overloading means creating multiple procedures with the same name in the same package, each taking arguments of different number or datatype.
- Can contain global variables and cursors that are available to all procedures and functions in the package.

Package Components

PL/SQL packages have two parts: the specification and the body, although sometimes the body is unnecessary. The specification is the interface to your application; it declares the types, variables, constants, exceptions, cursors, and subprograms available for use. The body fully defines cursors and subprograms, and so implements the specification.

Unlike subprograms, packages cannot be called, parameterized, or nested. However, the formats of a package and a subprogram are similar:

```
CREATE PACKAGE name AS -- specification (visible part)
    -- public type and item declarations
    -- subprogram specifications
END [name];
```

```
CREATE PACKAGE BODY name AS -- body (hidden part)
    -- private type and item declarations
    -- subprogram bodies
[BEGIN
    -- initialization statements]
```

```
END [name];
```

The specification holds public declarations that are visible to your application. The body holds implementation details and private declarations that are hidden from your application. You can debug, enhance, or replace a package body without changing the specification. You can change a package body without recompiling calling programs because the implementation details in the body are hidden from your application.

Using Oracle Supplied Packages

Most Oracle supplied packages are automatically installed when the database is created and the `CATPROC.SQL` script is run. For example, to create the `DBMS_ALERT` package, the `DBMSALRT.SQL` and `PRVTALRT.PLB` scripts must be run when connected as the user `SYS`. These scripts are run automatically by the `CATPROC.SQL` script.

Certain packages are not installed automatically. Special installation instructions for these packages are documented in the individual chapters.

To call a PL/SQL function from SQL, you must either own the function or have `EXECUTE` privileges on the function. To select from a view defined with a PL/SQL function, you must have `SELECT` privileges on the view. No separate `EXECUTE` privileges are needed to select from the view. Instructions on special requirements for packages are documented in the individual chapters.

Creating New Packages

To create packages and store them permanently in an Oracle database, use the `CREATE PACKAGE` and `CREATE PACKAGE BODY` statements. You can execute these statements interactively from SQL*Plus or Enterprise Manager.

To create a new package, do the following:

1. Create the package specification with the `CREATE PACKAGE` statement.

You can declare program objects in the package specification. Such objects are called *public* objects. Public objects can be referenced outside the package, as well as by other objects in the package.

Note: It is often more convenient to add the `OR REPLACE` clause in the `CREATE PACKAGE` statement.

2. Create the package body with the `CREATE PACKAGE BODY` statement.

You can declare and define program objects in the package body.

- You must define public objects declared in the package specification.
- You can declare and define additional package objects, called *private* objects. Private objects are declared in the package body rather than in the package specification, so they can be referenced only by other objects in the package. They cannot be referenced outside the package.

See Also:

- *PL/SQL User's Guide and Reference*
- *Oracle Database Application Developer's Guide - Fundamentals*

for more information on creating new packages

- *Oracle Database Concepts*

for more information on storing and executing packages

Separating the Specification and Body

The specification of a package declares the public types, variables, constants, and subprograms that are visible outside the immediate scope of the package. The body of a package defines the objects declared in the specification, as well as private objects that are not visible to applications outside the package.

Oracle stores the specification and body of a package separately in the database. Other schema objects that call or reference public program objects depend only on the package specification, not on the package body. Using this distinction, you can change the definition of a program object in the package body without causing Oracle to invalidate other schema objects that call or reference the program object. Oracle invalidates dependent schema objects only if you change the declaration of the program object in the package specification.

Creating a New Package: Example The following example shows a package specification for a package named `EMPLOYEE_MANAGEMENT`. The package contains one stored function and two stored procedures.

```
CREATE PACKAGE employee_management AS
    FUNCTION hire_emp (name VARCHAR2, job VARCHAR2,
        mgr NUMBER, hiredate DATE, sal NUMBER, comm NUMBER,
        deptno NUMBER) RETURN NUMBER;
    PROCEDURE fire_emp (emp_id NUMBER);
```



```

PROCEDURE sal_raise (emp_id NUMBER, sal_incr NUMBER);
END employee_management;

```

The body for this package defines the function and the procedures:

```

CREATE PACKAGE BODY employee_management AS
  FUNCTION hire_emp (name VARCHAR2, job VARCHAR2,
    mgr NUMBER, hiredate DATE, sal NUMBER, comm NUMBER,
    deptno NUMBER) RETURN NUMBER IS

```

The function accepts all arguments for the fields in the employee table except for the employee number. A value for this field is supplied by a sequence. The function returns the sequence number generated by the call to this function.

```

    new_empno    NUMBER(10);

BEGIN
  SELECT emp_sequence.NEXTVAL INTO new_empno FROM dual;
  INSERT INTO emp VALUES (new_empno, name, job, mgr,
    hiredate, sal, comm, deptno);
  RETURN (new_empno);
END hire_emp;

PROCEDURE fire_emp(emp_id IN NUMBER) AS

```

The procedure deletes the employee with an employee number that corresponds to the argument `emp_id`. If no employee is found, then an exception is raised.

```

BEGIN
  DELETE FROM emp WHERE empno = emp_id;
  IF SQL%NOTFOUND THEN
    raise_application_error(-20011, 'Invalid Employee
      Number: ' || TO_CHAR(emp_id));
  END IF;
END fire_emp;

PROCEDURE sal_raise (emp_id IN NUMBER, sal_incr IN NUMBER) AS

```

The procedure accepts two arguments. `Emp_id` is a number that corresponds to an employee number. `Sal_incr` is the amount by which to increase the employee's salary.

```

BEGIN

-- If employee exists, then update salary with increase.

```

```
UPDATE emp
  SET sal = sal + sal_incr
  WHERE empno = emp_id;
IF SQL%NOTFOUND THEN
  raise_application_error(-20011, 'Invalid Employee
    Number: ' || TO_CHAR(emp_id));
END IF;
END sal_raise;
END employee_management;
```

Note: If you want to try this example, then first create the sequence number `emp_sequence`. You can do this using the following SQL*Plus statement:

```
SQL> CREATE SEQUENCE emp_sequence
> START WITH 8000 INCREMENT BY 10;
```

Referencing Package Contents

To reference the types, items, and subprograms declared in a package specification, use the dot notation. For example:

```
package_name.type_name
package_name.item_name
package_name.subprogram_name
```

Abbreviations for Datetime and Interval Datatypes

Many of the datetime and interval datatypes have names that are too long to be used with the procedures and functions in the replication management API. Therefore, you must use abbreviations for these datatypes instead of the full names. The following table lists each datatype and its abbreviation. No abbreviation is necessary for the `DATE` and `TIMESTAMP` datatypes.

Datatype	Abbreviation
<code>TIMESTAMP WITH TIME ZONE</code>	<code>TSTZ</code>
<code>TIMESTAMP LOCAL TIME ZONE</code>	<code>TSLTZ</code>
<code>INTERVAL YEAR TO MONTH</code>	<code>IYM</code>
<code>INTERVAL DAY TO SECOND</code>	<code>IDS</code>

For example, if you want to use the `DBMS_DEFER_QUERY.GET_datatype_ARG` function to determine the value of a `TIMESTAMP LOCAL TIME ZONE` argument in a deferred call, then you substitute `TSLTZ` for *datatype*. Therefore, you run the `DBMS_DEFER_QUERY.GET_TSLTZ_ARG` function.

Summary of Oracle Supplied PL/SQL Packages

[Table 1-1](#) lists the supplied PL/SQL server packages. These packages run as the invoking user, rather than the package owner. Unless otherwise noted, the packages are callable through public synonyms of the same name.

Caution:

- The procedures and functions provided in these packages and their external interfaces are reserved by Oracle and are subject to change.
 - Modifying Oracle supplied packages can cause internal errors and database security violations. Do not modify supplied packages.
-
-

Table 1–1 Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
CTX_ADM	Lets you administer servers and the data dictionary.
CTX_CLS	Lets you generate CTXRULE rules for a set of documents.
CTX_DDL	Lets you create and manage the preferences, section lists and stopgroups required for Text indexes.
CTX_DOC	Lets you request document services.
CTX_OUTPUT	Lets you manage the index log.
CTX_QUERY	Lets you generate query feedback, count hits, and create stored query expressions.
CTX_REPORT	Lets you create various index reports.
CTX_THES	Lets you to manage and browse thesauri.
CTX_ULEXER	For use with the user-lexer.
DBMS_ADVANCED_REWRITE	Contains interfaces for advanced query rewrite users to create, drop, and maintain functional equivalence declarations for query rewrite.
DBMS_ADVISOR	Part of the SQLAccess Advisor, an expert system that identifies and helps resolve performance problems relating to the execution of SQL statements.
DBMS_ALERT	Provides support for the asynchronous notification of database events.
DBMS_APPLICATION_INFO	Lets you register an application name with the database for auditing or performance tracking purposes.
DBMS_APPLY_ADM	Provides administrative procedures to start, stop, and configure an apply process.
DBMS_AQ	Lets you add a message (of a predefined object type) onto a queue or to dequeue a message.
DBMS_AQADM	Lets you perform administrative functions on a queue or queue table for messages of a predefined object type.
DBMS_AQELM	Provides procedures to manage the configuration of Advanced Queuing asynchronous notification by e-mail and HTTP.
DBMS_CAPTURE_ADM	Describes administrative procedures to start, stop, and configure a capture process; used in Streams.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
DBMS_CDC_PUBLISH	Identifies new data that has been added to, modified, or removed from, relational tables and publishes the changed data in a form that is usable by an application.
DBMS_CDC_SUBSCRIBE	Lets you view and query the change data that was captured and published with the <code>DBMS_LOGMNR_CDC_PUBLISH</code> package.
DBMS_CCRYPTO	Lets you encrypt and decrypt stored data, can be used in conjunction with PL/SQL programs running network communications, and supports encryption and hashing algorithms.
DBMS_DATA_MINING	Lets you use data mining to discover hidden patterns and use that knowledge to make predictions.
DBMS_DATA_MINING_TRANSFORM	Provides set of data transformation utilities available for use with the DBMS_DATA_MINING package for preparing mining data.
DBMS_DATAPUMP	Lets you move all, or part of, a database between databases, including both data and metadata.
DBMS_DDL	Provides access to some SQL DDL statements from stored procedures, and provides special administration operations not available as DDLs.
DBMS_DEBUG	Implements server-side debuggers and provides a way to debug server-side PL/SQL program units.
DBMS_DEFER	Provides the user interface to a replicated transactional deferred remote procedure call facility. Requires the Distributed Option.
DBMS_DEFER_QUERY	Permits querying the deferred remote procedure calls (RPC) queue data that is not exposed through views. Requires the Distributed Option.
DMBS_DEFER_SYS	Provides the system administrator interface to a replicated transactional deferred remote procedure call facility. Requires the Distributed Option.
DBMS_DESCRIBE	Describes the arguments of a stored procedure with full name translation and security checking.
DBMS_DIMENSION	Enables you to verify dimension relationships and provides an alternative to the Enterprise Manager Dimension Wizard for displaying a dimension definition

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
DBMS_DISTRIBUTED_TRUST_ADMIN	Maintains the Trusted Database List, which is used to determine if a privileged database link from a particular server can be accepted.
DBMS_FGA	Provides fine-grained security functions.
DBMS_FILE_TRANSFER	Lets you copy a binary file within a database or to transfer a binary file between databases.
DBMS_FLASHBACK	Lets you flash back to a version of the database at a specified wall-clock time or a specified system change number (SCN).
DBMS_FREQUENT_ITEMSET	Enables frequent itemset counting.
DBMS_HS_PASSTHROUGH	Lets you use Heterogeneous Services to send pass-through SQL statements to non-Oracle systems.
DBMS_IOT	Creates a table into which references to the chained rows for an Index Organized Table can be placed using the ANALYZE command.
DBMS_JAVA	Provides a PL/SQL interface for accessing database functionality from Java
DBMS_JOB	Lets you schedule administrative procedures that you want performed at periodic intervals; it is also the interface for the job queue.
DBMS_LDAP	Provides functions and procedures to access data from LDAP servers.
DBMS_LDAP_UTL	Provides the Oracle Extension utility functions for LDAP.
DBMS_LIBCACHE	Prepares the library cache on an Oracle instance by extracting SQL and PL/SQL from a remote instance and compiling this SQL locally without execution.
DBMS_LOB	Provides general purpose routines for operations on Oracle Large Object (LOBs) datatypes - BLOB, CLOB (read/write), and BFILES (read-only).
DBMS_LOCK	Lets you request, convert and release locks through Oracle Lock Management services.
DBMS_LOGMNR	Provides functions to initialize and run the log reader.
DBMS_LOGMNR_D	Queries the dictionary tables of the current database, and creates a text based file containing their contents.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
DBMS_LOGSTDBY	Describes procedures for configuring and managing the logical standby database environment.
DBMS_METADATA	Lets callers easily retrieve complete database object definitions (metadata) from the dictionary.
DBMS_MGWADM	Describes the Messaging Gateway administrative interface; used in Advanced Queuing.
DBMS_MGWMSG	Describes object types—used by the canonical message types to convert message bodies—and helper methods, constants, and subprograms for working with the Messaging Gateway message types; used in Advanced Queuing.
DBMS_MONITOR	Let you use PL/SQL for controlling additional tracing and statistics gathering.
DBMS_MVIEW	Lets you refresh snapshots that are not part of the same refresh group and purge logs. DBMS_SNAPSHOT is a synonym.
DBMS_OBFUSCATION_TOOLKIT	Provides procedures for Data Encryption Standards.
DBMS_ODCI	Returns the CPU cost of a user function based on the elapsed time of the function.
DBMS_OFFLINE_OG	Provides public APIs for offline instantiation of master groups.
DBMS_OLAP	Provides procedures for summaries, dimensions, and query rewrites.
DBMS_OUTLN	Provides the interface for procedures and functions associated with management of stored outlines. Synonymous with OUTLN_PKG
DBMS_OUTLN_EDIT	Lets you edit an invoker's rights package.
DBMS_OUTPUT	Accumulates information in a buffer so that it can be retrieved later.
DBMS_PCLXUTIL	Provides intra-partition parallelism for creating partition-wise local indexes.
DBMS_PIPE	Provides a DBMS pipe service which enables messages to be sent between sessions.
DBMS_PROFILER	Provides a Probe Profiler API to profile existing PL/SQL applications and identify performance bottlenecks.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
DBMS_PROPAGATION_ADM	Provides administrative procedures for configuring propagation from a source queue to a destination queue.
DBMS_RANDOM	Provides a built-in random number generator.
DBMS_RECTIFIER_DIFF	Provides APIs used to detect and resolve data inconsistencies between two replicated sites.
DBMS_REDEFINITION	Lets you perform an online reorganization of tables.
DBMS_REFRESH	Lets you create groups of snapshots that can be refreshed together to a transactionally consistent point in time. Requires the Distributed Option.
DBMS_REPAIR	Provides data corruption repair procedures.
DBMS_REPCAT	Provides routines to administer and update the replication catalog and environment. Requires the Replication Option.
DBMS_REPCAT_ADMIN	Lets you create users with the privileges needed by the symmetric replication facility. Requires the Replication Option.
DBMS_REPCAT_INSTANTIATE	Instantiates deployment templates. Requires the Replication Option.
DBMS_REPCAT_RGT	Controls the maintenance and definition of refresh group templates. Requires the Replication Option.
DBMS_REPUTIL	Provides routines to generate shadow tables, triggers, and packages for table replication.
DBMS_RESOURCE_MANAGER	Maintains plans, consumer groups, and plan directives; it also provides semantics so that you may group together changes to the plan schema.
DBMS_RESOURCE_MANAGER_PRIVS	Maintains privileges associated with resource consumer groups.
DBMS_RESUMABLE	Lets you suspend large operations that run out of space or reach space limits after executing for a long time, fix the problem, and make the statement resume execution.
DBMS_RLS	Provides row level security administrative interface.
DBMS_ROWID	Provides procedures to create rowids and to interpret their contents.
DBMS_RULE	Describes the EVALUATE procedure used in Streams.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
DBMS_RULE_ADM	Describes the administrative interface for creating and managing rules, rule sets, and rule evaluation contexts; used in Streams.
DBMS_SCHEDULER	Provides a collection of scheduling functions that are callable from any PL/SQL program.
DBMS_SERVER_ALERT	Lets you issue alerts when some threshold has been violated.
DBMS_SERVICE	Lets you create, delete, activate and deactivate services for a single instance.
DBMS_SESSION	Provides access to SQL ALTER SESSION statements, and other session information, from stored procedures.
DBMS_SHARED_POOL	Lets you keep objects in shared memory, so that they will not be aged out with the normal LRU mechanism.
DBMS_SPACE	Provides segment space information not available through standard SQL.
DBMS_SPACE_ADMIN	Provides tablespace and segment space administration not available through the standard SQL.
DBMS_SQL	Lets you use dynamic SQL to access the database.
DBMS_SQLTUNE	Provides the interface to tune SQL statements.
DBMS_STAT_FUNCS	Provides statistical functions.
DBMS_STATS	Provides a mechanism for users to view and modify optimizer statistics gathered for database objects.
DBMS_STORAGE_MAP	Communicates with FMON to invoke mapping operations.
DBMS_STREAMS	Describes the interface to convert SYS.AnyData objects into LCR objects and an interface to annotate redo entries generated by a session with a binary tag.
DBMS_STREAMS_ADMIN	Describes administrative procedures for adding and removing simple rules, without transformations, for capture, propagation, and apply at the table, schema, and database level.
DBMS_STREAMS_AUTH	Provides interfaces for granting privileges to Streams administrators and revoking privileges from Streams administrators.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
DBMS_STREAMS_MESSAGING	Provides interfaces to enqueue messages into and dequeue messages from a SYS.AnyData queue.
DBMS_STREAMS_TABLESPACE_ADM	Provides administrative procedures for copying tablespaces between databases and moving tablespaces from one database to another.
DBMS_TRACE	Provides routines to start and stop PL/SQL tracing.
DBMS_TRANSACTION	Provides access to SQL transaction statements from stored procedures and monitors transaction activities.
DBMS_TRANSFORM	Provides an interface to the message format transformation features of Oracle Advanced Queuing.
DBMS_TTS	Checks if the transportable set is self-contained.
DBMS_TYPES	Consists of constants, which represent the built-in and user-defined types.
DBMS_UTILITY	Provides various utility routines.
DBMS_WARNING	Provides the interface to query, modify and delete current system or session settings.
DBMS_WORKLOAD_REPOSITORY	lets you manage the Workload Repository, performing operations such as managing snapshots and baselines.
DBMS_WM	Describes how to use the programming interface to Oracle Database Workspace Manager to work with long transactions.
DBMS_XDB	Describes Resource Management and Access Control APIs for PL/SQL
DBMS_XDB_VERSION	Describes versioning APIs
DBMS_XDBT	Describes how an administrator can create a ConText index on the XML DB hierarchy and configure it for automatic maintenance
DBMS_XDBZ	Controls the Oracle XML DB repository security, which is based on Access Control Lists (ACLs).
DBMS_XMLGEN	Converts the results of a SQL query to a canonical XML format.
DBMS_XMLDOM	Explains access to XMLType objects
DBMS_XMLPARSER	Explains access to the contents and structure of XML documents.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
DMBS_XMLQUERY	Provides database-to-XMLType functionality.
DBMS_XMLSAVE	Provides XML-to-database-type functionality.
DBMS_XMLSCHEMA	Explains procedures to register and delete XML schemas.
DBMS_XMLSTORE	Provides the ability to store XML data in relational tables.
DBMS_XPLAN	Describes how to format the output of the EXPLAIN PLAN command.
DBMS_XSLPROCESSOR	Explains access to the contents and structure of XML documents.
DEBUG_EXTPROC	Lets you debug external procedures on platforms with debuggers that attach to a running process.
HTF	Hypertext functions generate HTML tags.
HTMLDB_APPLICATION	Enables users to take advantage of global variables
HTMLDB_CUSTOM_AUTH	Enables users to create form elements dynamically based on a SQL query instead of creating individual items page by page.
HTMLDB_ITEM	Enables users to create form elements dynamically based on a SQL query instead of creating individual items page by page.
HTMLDB_UTIL	Provides utilities for getting and setting session state, getting files, checking authorizations for users, resetting different states for users, and also getting and setting preferences for users.
HTP	Hypertext procedures generate HTML tags.
OWA_CACHE	Provides an interface that enables the PL/SQL Gateway cache to improve the performance of PL/SQL web applications.
OWA_COOKIE	Provides an interface for sending and retrieving HTTP cookies from the client's browser.
OWA_CUSTOM	Provides a Global PLSQL Agent Authorization callback function
OWA_IMAGE	Provides an interface to access the coordinates where a user clicked on an image.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
OWA_OPT_LOCK	Contains subprograms that impose optimistic locking strategies so as to prevent lost updates.
OWA_PATTERN	Provides an interface to locate text patterns within strings and replace the matched string with another string.
OWA_SEC	Provides an interface for custom authentication.
OWA_TEXT	Contains subprograms used by OWA_PATTERN for manipulating strings. They are externalized so you can use them directly.
OWA_UTIL	Contains utility subprograms for performing operations such as getting the value of CGI environment variables, printing the data that is returned to the client, and printing the results of a query in an HTML table.
SDO_CS	Provides functions for coordinate system transformation.
SDO_GCDR	Contains the Oracle Spatial geocoding subprograms, which let you geocode unformatted postal addresses.
SDO_GEOM	Provides functions implementing geometric operations on spatial objects.
SDO_GEOR	Contains functions and procedures for the Spatial GeoRaster feature, which lets you store, index, query, analyze, and deliver raster image data and its associated Spatial vector geometry data and metadata.
SDO_GEOR_UTL	Contains utility functions and procedures for the Spatial GeoRaster feature, including those related to using triggers with GeoRaster data.
SDO_LRS	Provides functions for linear referencing system support.
SDO_MIGRATE	Provides functions for migrating spatial data from previous releases.
SDO_NET	Provides functions and procedures for working with data modeled as nodes and links in a network.
SDO_SAM	Contains functions and procedures for spatial analysis and data mining.
SDO_TOPO	Provides procedures for creating and managing Spatial topologies.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
SDO_TOPO_MAP	Contains subprograms for editing Spatial topologies using a cache (TopoMap object).
SDO_TUNE	Provides functions for selecting parameters that determine the behavior of the spatial indexing scheme used in Oracle Spatial.
SDO_UTIL	Provides utility functions and procedures for Oracle Spatial.
UTL_COLL	Enables PL/SQL programs to use collection locators to query and update.
UTL_COMPRESS	Provides a set of data compression utilities.
UTL_DBWS	Provides database web services.
UTL_ENCODE	Provides functions that encode RAW data into a standard encoded format so that the data can be transported between hosts.
UTL_FILE	Enables your PL/SQL programs to read and write operating system text files and provides a restricted version of standard operating system stream file I/O.
UTL_HTTP	Enables HTTP callouts from PL/SQL and SQL to access data on the Internet or to call Oracle Web Server Cartridges.
UTL_I18N	Provides a set of services (Oracle Globalization Service) that help developers build multilingual applications.
UTL_INADDR	Provides a procedure to support internet addressing.
UTL_LMS	Retrieves and formats error messages in different languages.
UTL_MAIL	A utility for managing email which includes commonly used email features, such as attachments, CC, BCC, and return receipt.
UTL_RAW	Provides SQL functions for RAW datatypes that concat, substr to and from RAWs .
UTL_RECOMP	Recompiles invalid PL/SQL modules, Java classes, indextypes and operators in a database, either sequentially or in parallel.
UTL_REF	Enables a PL/SQL program to access an object by providing a reference to the object.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
UTL SMTP	Provides PL/SQL functionality to send emails.
UTL TCP	Provides PL/SQL functionality to support simple TCP/IP-based communications between servers and the outside world.
UTL URL	Provides escape and unescape mechanisms for URL characters.
WPG_DOCLOAD	Provides an interface to download files, BLOBs and BFILEs.
ANYDATA TYPE	A self-describing data instance type containing an instance of the type plus a description
ANYDATASET TYPE	Contains a description of a given type plus a set of data instances of that type
ANYTYPE TYPE	Contains a type description of any persistent SQL type, named or unnamed, including object types and collection types; or, it can be used to construct new transient type descriptions
Oracle Streams AQ Types	Describes the types used in Advanced Queuing
Database URI Type	Contains URI Support, UriType Super Type, HttpUriType Subtype, DBUriType Subtype, XDBUriType Subtype, UriFactory Package
JMS TYPES	Describes JMS types so that a PL/SQL application can use JMS queues of JMS types
LOGICAL CHANGE RECORD TYPES	Describes LCR types, which are message payloads that contain information about changes to a database, used in Streams
interMedia ORDAudio Type	Supports the storage and management of audio data.
interMedia ORDDoc Type	Supports the storage and management of heterogeneous media data including image, audio, and video.
interMedia ORDImage Type	Supports the storage, management, and manipulation of image data.
interMedia ORDImageSignature Type	Supports content-based retrieval of images (image matching).
interMedia SQL/MM Still Image Type	Provides support for the SQL/MM Still Image Standard, which lets you store, retrieve, and modify images in the database and locate images using visual predicates.

Table 1–1 (Cont.) Summary of Oracle Supplied PL/SQL Packages

Package Name	Description
interMedia ORDVideo Type	Supports the storage and management of video data.
RULES TYPES	Describes the types used with rules, rule sets, and evaluation contexts
XMLType	Describes the types and functions used for native XML support in the server.

This Oracle Text package lets you administer servers and the data dictionary. Note that you must install this package in order to use it.

- [Documentation of CTX_ADM](#)

Documentation of CTX_ADM

For a complete description of this package within the context of Oracle Text, see `CTX_ADM` in the *Oracle Text Reference*.

This Oracle Text package enables generation of CTXRULE rules for a set of documents.

- [Documentation of CTX_CLS](#)

Documentation of CTX_CLS

For a complete description of this package within the context of Oracle Text, see `CTX_CLS` in the *Oracle Text Reference*.

This Oracle Text package lets you create and manage the preferences, section groups, and stoplists required for Text indexes. Note that you must install this package in order to use it.

- [Documentation of CTX_DDL](#)

Documentation of CTX_DDL

For complete description of this package within the context of Oracle Text, see CTX_DDL in the *Oracle Text Reference*.

This Oracle Text package lets you request document services. Note that you must install this package in order to use it.

- [Documentation of CTX_DOC](#)

Documentation of CTX_DOC

For a complete description of this package within the context of Oracle Text, see `CTX_DOC` in the *Oracle Text Reference*.

CTX_OUTPUT

This Oracle Text package lets you manage the index log. Note that you must install this package in order to use it.

- [Documentation of CTX_OUTPUT](#)

Documentation of CTX_OUTPUT

For a complete description of this package within the context of Oracle Text, see `CTX_OUTPUT` in the *Oracle Text Reference*.

CTX_QUERY

This Oracle Text package lets you generate query feedback, count hits, and create stored query expressions. Note that you must install this package in order to use it.

- [Documentation of CTX_QUERY](#)

Documentation of CTX_QUERY

For a complete description of this package within the context of Oracle Text, see `CTX_QUERY` in the *Oracle Text Reference*.

CTX_REPORT

This Oracle Text package lets you create various index reports. Note that you must install this package in order to use it.

- [Documentation of CTX_REPORT](#)

Documentation of CTX_REPORT

For a complete description of this package within the context of Oracle Text, see `CTX_REPORT` in the *Oracle Text Reference*.

This Oracle Text package lets you to manage and browse thesauri. Note that you must install this package in order to use it.

- [Documentation of CTX_THES](#)

Documentation of CTX_THES

For a complete description of this package within the context of Oracle Text, see `CTX_THES` in the *Oracle Text Reference*.

10

CTX_ULEXER

This Oracle Text package is for use with the user-lexer. Note that you must install this package in order to use it.

- [Documentation of CTX_ULEXER](#)

Documentation of CTX_ULEXER

For a complete description of this package within the context of Oracle Text, see `CTX_ULEXER` in the *Oracle Text Reference*.

DBMS_ADVANCED_REWRITE

DBMS_ADVANCED_REWRITE contains interfaces for advanced query rewrite users. Using this package, you can create, drop, and maintain functional equivalence declarations for query rewrite.

See Also: *Oracle Data Warehousing Guide* for more information about query rewrite

This chapter contains the following topics:

- [Using DBMS_ADVANCED_REWRITE](#)
 - [Security Model](#)
- [Summary of DBMS_ADVANCED_REWRITE Subprograms](#)

Using DBMS_ADVANCED_REWRITE

- [Security Model](#)

Security Model

No privileges to access these procedures are granted to anyone by default. To gain access to these procedures, you must connect as `SYSDBA` and explicitly grant execute access to the desired database administrators.

You can control security on this package by granting the `EXECUTE` privilege to selected database administrators or roles. For example, the user `er` can be given access to use this package by the following statement, executed as `SYSDBA`:

```
GRANT EXECUTE ON DBMS_ADVANCED_REWRITE TO er;
```

You may want to write a separate cover package on top of this package for restricting the alert names used. Instead of granting the `EXECUTE` privilege on the `DBMS_ADVANCED_REWRITE` package directly, you can then grant it to the cover package.

Summary of DBMS_ADVANCED_REWRITE Subprograms

Table 11–1 DBMS_ADVANCED_REWRITE Package Subprograms

Subprogram	Description
ALTER_REWRITE_EQUIVALENCE Procedure on page 11-4	Changes the mode of the rewrite equivalence declaration to the mode you specify
DECLARE_REWRITE_EQUIVALENCE Procedures on page 11-5	Creates a declaration indicating that <code>source_stmt</code> is functionally equivalent to <code>destination_stmt</code> for as long as the equivalence declaration remains enabled, and that <code>destination_stmt</code> is more favorable in terms of performance
DROP_REWRITE_EQUIVALENCE Procedure on page 11-8	Drops the specified rewrite equivalence declaration
VALIDATE_REWRITE_EQUIVALENCE Procedure on page 11-9	Validates the specified rewrite equivalence declaration using the same validation method as described with the <code>validate</code> parameter

ALTER_REWRITE_EQUIVALENCE Procedure

This procedure changes the mode of the rewrite equivalence declaration to the mode you specify.

Syntax

```
DBMS_ADVANCED_REWRITE.ALTER_REWRITE_EQUIVALENCE (
    name          VARCHAR2,
    mode          VARCHAR2);
```

Parameters

Table 11–2 ALTER_REWRITE_EQUIVALENCE Procedure Parameters

Parameter	Description
name	A name for the equivalence declaration to alter. The name can be of the form <code>owner.name</code> , where <code>owner</code> complies with the rules for a schema name, and <code>name</code> complies with the rules for a table name. Alternatively, a simple name that complies with the rules for a table name can be specified. In this case, the rewrite equivalence is altered in the current schema. The invoker must have the appropriate alter materialized view privileges to alter an equivalence declaration outside their own schema.
mode	<p>The following modes are supported, in increasing order of power:</p> <p><code>disabled</code>: Query rewrite does not use the equivalence declaration. Use this mode to temporarily disable use of the rewrite equivalence declaration.</p> <p><code>text_match</code>: Query rewrite uses the equivalence declaration only in its text match modes. This mode is useful for simple transformations.</p> <p><code>general</code>: Query rewrite uses the equivalence declaration in all of its transformation modes against the incoming request queries. However, query rewrite makes no attempt to rewrite the specified <code>destination_query</code>.</p> <p><code>recursive</code>: Query rewrite uses the equivalence declaration in all of its transformation modes against the incoming request queries. Moreover, query rewrite further attempts to rewrite the specified <code>destination_query</code> for further performance enhancements whenever it uses the equivalence declaration.</p> <p>Oracle recommends you use the least powerful mode that is sufficient to solve your performance problem.</p>

DECLARE_REWRITE_EQUIVALENCE Procedures

This procedure creates a declaration indicating that `source_stmt` is functionally equivalent to `destination_stmt` for as long as the equivalence declaration remains enabled, and that `destination_stmt` is more favorable in terms of performance. The scope of the declaration is system wide. The query rewrite engine uses such declarations to perform rewrite transformations in `QUERY_REWRITE_INTEGRITY=trusted` and `stale_tolerated` modes.

Syntax

```
DBMS_ADVANCED_REWRITE.DECLARE_REWRITE_EQUIVALENCE (
    name          VARCHAR2,
    source_stmt   VARCHAR2,
    destination_stmt VARCHAR2,
    validate      BOOLEAN    := TRUE,
    mode          VARCHAR2   := 'TEXT_MATCH');
```

```
DBMS_ADVANCED_REWRITE.DECLARE_REWRITE_EQUIVALENCE (
    name          VARCHAR2,
    source_stmt   CLOB,
    destination_stmt CLOB,
    validate      BOOLEAN    := TRUE,
    mode          VARCHAR2   := 'TEXT_MATCH');
```

Parameters

Table 11–3 DECLARE_REWRITE_EQUIVALENCE Procedure Parameters

Parameter	Description
<code>name</code>	A name for the equivalence declaration. The name can be of the form <code>owner.name</code> , where <code>owner</code> complies with the rules for a schema name, and <code>name</code> complies with the rules for a table name. Alternatively, a simple name that complies with the rules for a table name can be specified. In this case, the rewrite equivalence is created in the current schema. The invoker must have the appropriate <code>CREATE MATERIALIZED VIEW</code> privileges to alter an equivalence declaration.
<code>source_stmt</code>	A sub- <code>SELECT</code> expression in either <code>VARCHAR2</code> or <code>CLOB</code> format. This is the query statement that is the target of optimization.
<code>destination_stmt</code>	A sub- <code>SELECT</code> expression in either <code>VARCHAR2</code> or <code>CLOB</code> format.

Table 11–3 DECLARE_REWRITE_EQUIVALENCE Procedure Parameters

Parameter	Description
validate	A Boolean indicating whether to validate that the specified <code>source_stmt</code> is functionally equivalent to the specified <code>destination_stmt</code> . If <code>validate</code> is specified as <code>TRUE</code> , <code>DECLARE_REWRITE_EQUIVALENCE</code> evaluates the two sub- <code>SELECT</code> s and compares their results. If the results are not the same, <code>DECLARE_REWRITE_EQUIVALENCE</code> does not create the rewrite equivalence and returns an error condition. If <code>FALSE</code> , <code>DECLARE_REWRITE_EQUIVALENCE</code> does not validate the equivalence.
mode	The following modes are supported, in increasing order of power: <code>disabled</code> : Query rewrite does not use the equivalence declaration. Use this mode to temporarily disable use of the rewrite equivalence declaration. <code>text_match</code> : Query rewrite uses the equivalence declaration only in its text match modes. This mode is useful for simple transformations. <code>general</code> : Query rewrite uses the equivalence declaration in all of its transformation modes against the incoming request queries. However, query rewrite makes no attempt to rewrite the specified <code>destination_query</code> . <code>recursive</code> : Query rewrite uses the equivalence declaration in all of its transformation modes against the incoming request queries. Moreover, query rewrite further attempts to rewrite the specified <code>destination_query</code> for further performance enhancements whenever it uses the equivalence declaration. Oracle recommends you use the least powerful mode that is sufficient to solve your performance problem.

Usage Notes

Query rewrite using equivalence declarations occurs simultaneously and in concert with query rewrite using materialized views. The same query rewrite engine is used for both. The query rewrite engine uses the same rewrite rules to rewrite queries using both equivalence declarations and materialized views. Because the rewrite equivalence represents a specific rewrite crafted by a sophisticated user, the query rewrite engine gives priority to rewrite equivalences over materialized views when it is possible to perform a rewrite with either a materialized view or a rewrite equivalence. For this same reason, the cost-based optimizer (specifically, cost-based rewrite) will not choose an unrewritten query plan over a query plan that is rewritten to use a rewrite equivalence even if the cost of the un-rewritten plan appears more favorable. Query rewrite matches properties of the incoming request query against the equivalence declaration's `source_stmt` or the materialized

view's defining statement, respectively, and derives an equivalent relational expression in terms of the equivalence declaration's `destination_stmt` or the materialized view's container table, respectively.

DROP_REWRITE_EQUIVALENCE Procedure

This procedure drops the specified rewrite equivalence declaration.

Syntax

```
DBMS_ADVANCED_REWRITE.DROP_REWRITE_EQUIVALENCE (  
    name          VARCHAR2);
```

Parameters

Table 11–4 *DROP_REWRITE_EQUIVALENCE Procedure Parameters*

Parameter	Description
name	A name for the equivalence declaration to drop. The name can be of the form <code>owner.name</code> , where <code>owner</code> complies with the rules for a schema name, and <code>name</code> complies with the rules for a table name. Alternatively, a simple name that complies with the rules for a table name can be specified. In this case, the rewrite equivalence is dropped in the current schema. The invoker must have the appropriate drop materialized view privilege to drop an equivalence declaration outside their own schema.

VALIDATE_REWRITE_EQUIVALENCE Procedure

This procedure validates the specified rewrite equivalence declaration using the same validation method as described with the `VALIDATE` parameter in "[VALIDATE_REWRITE_EQUIVALENCE Procedure](#)" on page 11-9.

Syntax

```
DBMS_ADVANCED_REWRITE.VALIDATE_REWRITE_EQUIVALENCE (
    name          VARCHAR2);
```

Parameters

Table 11–5 *VALIDATE_REWRITE_EQUIVALENCE Procedure Parameters*

Parameter	Description
name	A name for the equivalence declaration to validate. The name can be of the form owner.name, where owner complies with the rules for a schema name, and name complies with the rules for a table name. Alternatively, a simple name that complies with the rules for a table name can be specified. In this case, the rewrite equivalence is validated in the current schema. The invoker must have sufficient privileges to execute both the <code>source_stmt</code> and <code>destination_stmt</code> of the specified equivalence declaration.

DBMS_ADVISOR

DBMS_ADVISOR is part of the Server Manageability suite of Advisors, a set of expert systems that identifies and helps resolve performance problems relating to the various database server components.

See Also:

- *Oracle Data Warehousing Guide* for information regarding the SQLAccess Advisor
- *Oracle Database Administrator's Guide* for information regarding the Segment Advisor
- *Oracle Database Performance Tuning Guide* for information regarding the SQLTuning Advisor
- *Oracle 2 Day DBA* for information regarding the Undo Advisor

This chapter contains the following topics:

- [Using DBMS_ADVISOR](#)
 - [Security Model](#)
 - [Subprograms Used in All Advisors](#)
 - [Subprograms Used in SQLAccess Advisor](#)
 - [Parameters](#)
- [Summary of DBMS_ADVISOR Subprograms](#)

Using DBMS_ADVISOR

- [Security Model](#)
- [Subprograms Used in All Advisors](#)
- [Subprograms Used in SQLAccess Advisor](#)
- [Parameters](#)

Security Model

Security on this package can be controlled by granting `EXECUTE` on this package to selected users or roles. You might want to write a cover package on top of this one that restricts the alert names used. `EXECUTE` privilege on this cover package can then be granted rather than on this package. In addition, there is an `ADVISOR` privilege, which is required by `DBMS_ADVISOR` procedures.

Subprograms Used in All Advisors

[Table 12-1](#) lists `DBMS_ADVISOR` procedures that are used in all Advisors.

Table 12-1 *DBMS_ADVISOR Generic Subprograms*

Subprogram	Description
CANCEL_TASK Procedure on page 12-27	Cancels a currently executing task operation
CREATE_FILE Procedure on page 12-28	Creates an external file from a PL/SQL CLOB variable, which is useful for creating scripts and reports
CREATE_OBJECT Procedure on page 12-30	Creates a new task object
CREATE_TASK Procedures on page 12-34	Creates a new Advisor task in the repository
DELETE_TASK Procedure on page 12-40	Deletes the specified task from the repository
EXECUTE_TASK Procedure on page 12-41	Executes the specified task

Table 12–1 DBMS_ADVISOR Generic Subprograms(Cont.)

Subprogram	Description
GET_REC_ATTRIBUTES Procedure on page 12-42	Retrieves specific recommendation attributes from a task
GET_TASK_SCRIPT Procedure on page 12-45	Creates and returns an executable SQL script of the Advisor task's recommendations in a buffer
INTERRUPT_TASK Procedure on page 12-57	Stops a currently executing task, ending its operations as it would at a normal exit
MARK_RECOMMENDATION Procedure on page 12-58	Sets the <code>annotation_status</code> for a particular recommendation
QUICK_TUNE Procedure on page 12-60	Performs an analysis on a single SQL statement
RESET_TASK Procedure on page 12-63	Resets a task to its initial state
SET_DEFAULT_TASK_PARAMETER Procedures on page 12-66	Modifies a default task parameter
SET_TASK_PARAMETER Procedures on page 12-69	Sets the specified task parameter value
UPDATE_OBJECT Procedure on page 12-74	Updates a task object
UPDATE_REC_ATTRIBUTES Procedure on page 12-76	Updates an existing recommendation for the specified task
UPDATE_TASK_ATTRIBUTES Procedure on page 12-82	Updates a task's attributes

Subprograms Used in SQLAccess Advisor

Table 12–2 lists DBMS_ADVISOR procedures that are used in the SQLAccess Advisor.

Table 12–2 DBMS_ADVISOR SQLAccess Advisor Subprograms

Subprogram	Description
ADD_SQLWKLD_REF Procedure on page 12-23	Adds a workload reference to an Advisor task
ADD_SQLWKLD_STATEMENT Procedure on page 12-24	Adds a single statement to a workload

Table 12–2 DBMS_ADVISOR SQLAccess Advisor Subprograms(Cont.)

Subprogram	Description
CREATE_SQLWKLD Procedure on page 12-32	Creates a new workload object
DELETE_SQLWKLD Procedure on page 12-36	Deletes an entire workload object
DELETE_SQLWKLD_REF Procedure on page 12-37	Deletes an entire workload object
DELETE_SQLWKLD_STATEMENT Procedure on page 12-38	Deletes one or more statements from a workload
IMPORT_SQLWKLD_SCHEMA Procedure on page 12-47	Imports data into a workload from the current SQL cache
IMPORT_SQLWKLD_SQLCACHE Procedure on page 12-49	Imports data into a workload from the current SQL cache
IMPORT_SQLWKLD_STS Procedure on page 12-51	Imports data into a workload from a SQL Tuning Set into a SQL workload data object
IMPORT_SQLWKLD_SUMADV Procedure on page 12-53	Imports data into a workload from the current SQL cache
IMPORT_SQLWKLD_USER Procedure on page 12-55	Imports data into a workload from the current SQL cache
SET_DEFAULT_SQLWKLD_PARAMETER Procedure on page 12-64	Imports data into a workload from schema evidence
SET_SQLWKLD_PARAMETER Procedure on page 12-67	Sets the value of a workload parameter
TUNE_MVIEW Procedure on page 12-71	Shows how to decompose a materialized view into two or more materialized views or to restate the materialized view in a way that is more advantageous for fast refresh and query rewrite
UPDATE_SQLWKLD_ATTRIBUTES Procedure on page 12-78	Updates a workload object
UPDATE_SQLWKLD_STATEMENT Procedure on page 12-80	Updates one or more SQL statements in a workload

Parameters

The Oracle Database includes a number of advisors for different subsystems in the database to automatically determine how the operation of the corresponding subcomponents could be further optimized. The SQL Tuning and SQLAccess Advisor, for example, provide recommendations for running SQL statements faster. Memory advisors help size the various memory components without resorting to trial-and-error techniques. The Segment Advisor handles all space-related issues, such as recommending wasted-space reclamation, predicting the sizes of new tables and indexes, and analyzing growth trends, and the Undo Advisor lets you size the undo tablespace. You should see the specific documentation for each Advisor for details regarding how parameters are used.

This section includes:

- [Generic Advisor Parameters](#)
- [SQLAccess Advisor Task Parameters](#)
- [SQL Workload Object Parameters](#)
- [Segment Advisor Parameters](#)

Generic Advisor Parameters

The generic Advisor parameters are the following:

- DAYS_TO_EXPIRE
- END_SNAPSHOT
- END_TIME
- INSTANCE
- JOURNALING
- MODE
- START_SNAPSHOT
- START_TIME
- TARGET_OBJECTS
- TIME_LIMIT

See your Advisor-specific documentation for further information.

SQLAccess Advisor Task Parameters

Table 12-3 lists SQLAccess Advisor task parameters.

Table 12-3 SQLAccess Advisor Task Parameters

Parameter	Datatype	Description
ACTION_LIST	STRINGLIST	<p>Contains a fully qualified list of actions that are eligible for processing in a SQL Workload object. The list elements are comma-delimited, and quoted names are supported.</p> <p>An action can be any string. If an action is not quoted, it will be changed to uppercase lettering and stripped of leading and trailing spaces. An action string is not scanned for correctness.</p> <p>During a task execution, if a SQL statement's action does not match a name in the action list, it will not be processed by the task. An action name is case sensitive.</p> <p>Possible values are:</p> <p>Single action</p> <p>Comma-delimited action list</p> <p>ADVISOR_UNUSED (default)</p>
COMMENTED_FILTER_LIST	NUMBER	<p>Comma-delimited list of strings. When set, SQLAccess Advisor will filter out any SQL statement that contain any of the specified strings in the first 20 characters of its text.</p>
CREATION_COST	STRING	<p>When set to <code>true</code> (default), the SQL Access Advisor will weigh the cost of creation of the access structure (index or materialized view) against the frequency of the query and potential improvement in the query execution time. When set to <code>false</code>, the cost of creation is ignored.</p>
DAYS_TO_EXPIRE	NUMBER	<p>Specifies the expiration time in days for the current SQLAccess Advisor task. The value is relative to the last modification date. Once the task expires, it will become a candidate for removal by an automatic purge operation.</p> <p>Specifies the expiration time in days for the current Access Advisor task. The value is relative to the last modification date.</p> <p>Once the task expires, it will become a candidate for removal by an automatic purge operation.</p> <p>Possible values are:</p> <p>An integer in the range of 0 to 2147483647</p> <p>ADVISOR_UNLIMITED</p> <p>ADVISOR_UNUSED</p> <p>The default value is 30.</p>

Table 12–3 SQLAccess Advisor Task Parameters(Cont.)

Parameter	Datatype	Description
DEF_INDEX_ OWNER	STRING	<p>Specifies the default owner for new index recommendations. When a script is created, this value will be used to qualify the index name.</p> <p>Possible values are:</p> <p>Existing schema name. Quoted identifiers are supported.</p> <p>ADVISOR_UNUSED (default)</p>
DEF_INDEX_ TABLESPACE	STRING	<p>Specifies the default tablespace for new index recommendations. When a script is created, this value will be used to specify a tablespace clause.</p> <p>Possible values are:</p> <p>Existing tablespace name. Quoted identifiers are supported.</p> <p>ADVISOR_UNUSED. No tablespace clause will be present in the script for indexes. The default value is ADVISOR_UNUSED.</p>
DEF_MVIEW_ OWNER	STRING	<p>Specifies the default owner for new materialized view recommendations. When a script is created, this value will be used to qualify the materialized view name.</p> <p>Possible values are:</p> <p>Existing schema name. Quoted identifiers are supported.</p> <p>ADVISOR_UNUSED (default)</p>
DEF_MVIEW_ TABLESPACE	STRING	<p>Specifies the default tablespace for new materialized view recommendations. When a script is created, this value will be used to specify a tablespace clause.</p> <p>Possible values are:</p> <p>Existing tablespace name. Quoted identifiers are supported.</p> <p>ADVISOR_UNUSED. No tablespace clause will be present in the script for materialized views. The default value is ADVISOR_UNUSED.</p>
DEF_MVLOG_ TABLESPACE	STRING	<p>Specifies the default tablespace for new materialized view log recommendations. When a script is created, this value will be used to specify a tablespace clause.</p> <p>Possible values are:</p> <p>Existing tablespace name. Quoted identifiers are supported.</p> <p>ADVISOR_UNUSED. No tablespace clause will be present in the script for materialized view logs. The default value is ADVISOR_UNUSED.</p>

Table 12–3 SQLAccess Advisor Task Parameters(Cont.)

Parameter	Datatype	Description
DML_ VOLATILITY	STRING	<p>When set to <code>TRUE</code>, the SQLAccess advisor will consider the impact of index maintenance and materialized view refresh in determining the recommendations. It will limit the access structure recommendations involving columns or tables that are frequently updated. For example, if there are too many DMLs on a column, it may favor a Btree index over a bitmap index on that column. For this process to be effective, the workload must include DML (insert/update/delete/merge/direct path inserts) statements that represent the update behavior of the application.</p> <p>See the related parameter <code>refresh_mode</code>.</p>
END_TIME	STRING	<p>Specifies an end time for selecting SQL statements. If the statement did not execute on or before the specified time, it will not be processed.</p> <p>Each date must be in the standard Oracle form of MM-DD-YYY HH24:MI:SS, where:</p> <p>DD is the numeric date MM is the numeric month YYYY is the numeric year HH is the hour in 24 hour format MI is the minute SS is the second</p>
EVALUATION_ ONLY	STRING	<p>If set to <code>TRUE</code>, causes SQLAccess Advisor to analyze the workload, but only comment on how well the current configuration is supporting it. No tuning recommendations will be generated.</p> <p>Possible values are:</p> <p><code>FALSE</code> (default) and <code>TRUE</code></p>
EXECUTION_ TYPE	STRINGLIST	<p>The type of recommendations that is desired. Possible values:</p> <p><code>FULL</code> All supported recommendation types will be considered.</p> <p><code>INDEX_ONLY</code> The SQLAccess Advisor will only consider index solutions as recommendations.</p> <p><code>MVIEW_ONLY</code> The SQLAccess Advisor will consider materialized view and materialized view log solutions as recommendations.</p> <p><code>MVIEW_LOG_ONLY</code> The SQLAccess Advisor will only consider materialized view log solutions as recommendations.</p> <p>The default value is <code>FULL</code>.</p>

Table 12–3 SQLAccess Advisor Task Parameters(Cont.)

Parameter	Datatype	Description
INDEX_NAME_ TEMPLATE	STRING	<p>Specifies the method by which new index names are formed.</p> <p>If the <i>TASK_ID</i> is omitted from the template, names generated by two concurrently executing SQLAccess Advisor tasks may conflict and cause undesirable effects. So it is recommended that you include the <i>TASK_ID</i> in the template. Once formatted, the maximum size of a name is 30 characters.</p> <p>Valid keywords are:</p> <p>Any literal value up to 22 characters.</p> <p><i>TABLE</i></p> <p>Causes the parent table name to be substituted into the index name. If the name is too long, it will be trimmed to fit.</p> <p><i>TASK_ID</i></p> <p>Causes the current task identifier number to be inserted in hexadecimal form.</p> <p><i>SEQ</i></p> <p>Causes a sequence number to be inserted in hexadecimal form. Because this number is used to guarantee uniqueness, it is a required token.</p> <p>The default template is:</p> <p><i>TABLE_IDX\$\$_TASK_IDSEQ</i></p>
JOURNALING	NUMBER	<p>Controls the logging of messages to the journal (<i>USER_ADVISOR_JOURNAL</i> view). The higher the setting, the more information is logged to the journal.</p> <p>Valid settings are:</p> <p>0: no journal messages</p> <p>1: informational messages only</p> <p>2: warning messages</p> <p>3: explanation of errors</p> <p>4: explanation of fatal errors (default)</p> <p>5-9: debug messages</p>

Table 12–3 SQLAccess Advisor Task Parameters(Cont.)

Parameter	Datatype	Description
MODE	STRING	<p>Specifies the mode by which Access Advisor will operate during an analysis.</p> <p>Valid values are:</p> <p>LIMITED Indicates the Advisor will attempt to a quick job by limiting the search-space of candidate recommendations, and correspondingly, the results may be of a low quality.</p> <p>COMPREHENSIVE Indicates the Advisor will search a large pool of candidates that may take long to run, but the resulting recommendations will be of the highest quality.</p> <p>The default value is COMPREHENSIVE.</p>
MODULE_LIST	STRINGLIST	<p>Contains a fully qualified list of application modules that are eligible for processing in a SQL Workload object. The list elements are comma-delimited, and quoted names are supported.</p> <p>A module can be any string. If a module is not quoted, it will be changed to uppercase lettering and stripped of leading and trailing spaces. A module string is not scanned for correctness.</p> <p>During a workload import operation, if a SQL statement's application module does not match a name in the module list, it will not be stored in the workload object.</p> <p>Possible values are:</p> <p>Single application</p> <p>Comma-delimited module list</p> <p>ADVISOR_UNUSED (default)</p>
MVIEW_NAME_TEMPLATE	STRING	<p>Specifies the method by which new materialized view names are formed.</p> <p>If the <i>TASK_ID</i> is omitted from the template, names generated by two concurrently executing SQLAccess Advisor tasks may conflict and cause undesirable effects. So it is recommended that you include the <i>TASK_ID</i> in the template.</p> <p>The format is any combination of keyword tokens and literals. However, once formatted, the maximum size of a name is 30 characters.</p> <p>Valid tokens are:</p> <p>Any literal value up to 22 characters.</p> <p><i>TASK_ID</i> Causes the current task identifier number to be inserted in hexadecimal form.</p> <p><i>SEQ</i> Causes a sequence number to be inserted in hexadecimal form. Because this number is used to guarantee uniqueness, it is a required token.</p> <p>The default template is: <code>MV\$\$_TASK_IDSEQ</code></p>

Table 12–3 SQL Access Advisor Task Parameters(Cont.)

Parameter	Datatype	Description
ORDER_LIST	STRINGLIST	<p>Contains the primary natural order in which the Access Advisor processes workload elements during the analysis operation. To determine absolute natural order, Access Advisor sorts the workload using ORDER_LIST values. A comma must separate multiple order keys.</p> <p>Possible values are:</p> <p>BUFFER_GETS Sets the order using the SQL statement's buffer-get count value.</p> <p>CPU_TIME Sets the order using the SQL statement's CPU time value.</p> <p>DISK_READS Sets the order using the SQL statement's disk-read count value.</p> <p>ELAPSED_TIME Sets the order using the SQL statement's elapsed time value.</p> <p>EXECUTIONS Sets the order using the SQL statement's execution frequency value.</p> <p>OPTIMIZER_COST Sets the order using the SQL statement's optimizer cost value.</p> <p>I/O Sets the order using the SQL statement's I/O count value.</p> <p>PRIORITY Sets the order using the user-supplied business priority value.</p> <p>All values are accessed in descending order, where a high value is considered more interesting than a low value.</p> <p>The default value is PRIORITY, OPTIMIZER_COST.</p>
REFRESH_MODE	STRING	<p>Specifies whether materialized views are refreshed ON_DEMAND or ON_COMMIT. This will be used to weigh the impact of materialized view refresh when the parameter dml_volatility is set to TRUE.</p> <p>Possible values are:</p> <p>ON_DEMAND (default) and ON_COMMIT</p>
REPORT_DATE_FORMAT	STRING	<p>This is the default date and time formatting template. The default format is DD/MM/YYYYHH24:MI.</p>

Table 12–3 SQLAccess Advisor Task Parameters(Cont.)

Parameter	Datatype	Description
SQL_LIMIT	NUMBER	<p>Specifies the number of SQL statements to be analyzed. The <code>SQL_LIMIT</code> filter is applied after all other filters have been applied. For example, if only statements referencing the table <code>foo.bar</code> are to be accepted, the <code>SQL_LIMIT</code> value will be only apply to those statements.</p> <p>When used in conjunction with the parameter <code>ORDER_LIST</code>, SQLAccess Advisor will process the most interesting SQL statements by ordering the statements according to the specified sort keys.</p> <p>Possible values:</p> <p>An integer in the range of 1 to 2147483647</p> <p><code>ADVISOR_UNLIMITED</code></p> <p><code>ADVISOR_UNUSED</code> (default)</p>
START_TIME	STRING	<p>Specifies a start time for selecting SQL statements. If the statement did not execute on or before the specified time, it will not be processed.</p> <p>Each date must be in the standard Oracle form of <code>MM-DD-YYY HH24:MI:SS</code>, where:</p> <p>DD is the numeric date MM is the numeric month YYYY is the numeric year HH is the hour in 24 hour format MI is the minute SS is the second</p>
STORAGE_CHANGE	NUMBER	<p>Contains the amount of space adjustment that can be consumed by SQLAccess Advisor recommendations. Zero or negative values are only permitted if the workload type is marked as <code>FULL</code>.</p> <p>When the SQLAccess Advisor produces a set of recommendations, the resultant physical structures must be able to fit into the budgeted space. A space budget is computed by adding the <code>STORAGE_CHANGE</code> value to the space quantity currently used by existing access structures. A negative <code>STORAGE_CHANGE</code> value may force SQLAccess Advisor to remove existing structures in order to shrink space demand.</p> <p>Possible values:</p> <p>Any valid integer including negative values, zero and positive values. The default value is <code>ADVISOR_UNLIMITED</code>.</p>

Table 12–3 SQLAccess Advisor Task Parameters(Cont.)

Parameter	Datatype	Description
USERNAME_ LIST	STRINGLIST	<p>Contains a fully qualified list of usernames that are eligible for processing in a workload object. The list elements are comma-delimited, and quoted names are supported.</p> <p>During a task execution, if a SQL statement's username does not match a name in the username list, it will not be processed by the task. A username is not case sensitive unless it is quoted.</p> <p>Possible values:</p> <p>Single username</p> <p>comma-delimited username list</p> <p>ADVISOR_UNUSED</p> <p>The default value is <code>ADVISOR_UNUSED</code>.</p>
VALID_TABLE_ LIST	TABLELIST	<p>Contains a fully qualified list of tables that are eligible for tuning. The list elements are comma-delimited, and quoted identifiers are supported. Wildcard specifications are supported for tables. The default value is all tables within the user's scope are eligible for tuning. Supported wildcard character is <code>%</code>. A <code>%</code> wildcard matches any set of consecutive characters.</p> <p>When a SQL statement is processed, it will not be accepted unless at least one referenced table is specified in the valid table list. If the list is unused, then all table references within a SQL statement are considered valid.</p> <p>Valid syntax for a table reference is:</p> <p><code>schema.table</code></p> <p><code>schema</code></p> <p><code>schema.%</code> (equivalent to <code>schema</code>)</p> <p>Possible values:</p> <p>Single table reference</p> <p>comma-delimited table reference list</p> <p>ADVISOR_UNUSED</p> <p>The default value is <code>ADVISOR_UNUSED</code>.</p>
WORKLOAD_ SCOPE	STRING	<p>Describes the level of application coverage the workload represents. Possible values are <code>FULL</code> and <code>PARTIAL</code>.</p> <p><code>FULL</code> Should be used if the workload contains all interesting application SQL statements for the targeted tables.</p> <p><code>PARTIAL</code> (default) Should be used if the workload contains anything less than a full representation of the interesting application SQL statements for the targeted tables.</p>

SQL Workload Object Parameters

[Table 12–4](#) lists SQLAccess Advisor object parameters.

Table 12–4 SQL Workload Object Parameters

Name	Datatype	Description
ACTION_LIST	STRINGLIST	<p>Contains a fully qualified list of actions that are eligible for saving in a workload.</p> <p>An action can be any string. If an action is not quoted, it will be changed to uppercase lettering and stripped of leading and trailing spaces. An action string is not scanned for correctness.</p> <p>During a workload import operation, if a SQL statements action does not match a name in the action list, it will not be stored in the workload object. An action name is case sensitive.</p> <p>Possible values:</p> <p>Single action</p> <p>comma-delimited action list</p> <p>ADVISOR_UNUSED</p> <p>The default value is ADVISOR_UNUSED.</p>
COMMENTED_FILTER_LIST	NUMBER	<p>Comma-delimited list of strings. When set, SQLAccess Advisor will filter out any SQL statement that contain any of the specified strings in the first 20 characters of its text.</p>
DAYS_TO_EXPIRE	NUMBER	<p>Specifies the expiration time in days for the current SQL Workload object. The value is relative to the last modification date.</p> <p>Once the data expires, it will become a candidate for removal by an automatic purge operation.</p> <p>Possible values:</p> <p>An integer in the range of 0 to 2147483647</p> <p>ADVISOR_UNLIMITED</p> <p>ADVISOR_UNUSED</p> <p>The default value is 30.</p>

Table 12–4 SQL Workload Object Parameters(Cont.)

Name	Datatype	Description
END_TIME	STRING	<p>Specifies an end time for selecting SQL statements. If the statement did not execute on or before the specified time, it will not be processed.</p> <p>Each date must be in the standard Oracle form of MM-DD-YYY HH24:MI:SS, where:</p> <p>DD is the numeric date MM is the numeric month YYYY is the numeric year HH is the hour in 24 hour format MI is the minute SS is the second</p>
INVALID_ TABLE_LIST	TABLELIST	<p>Contains a fully qualified list of tables that are not eligible for tuning. The list elements are comma-delimited, and quoted identifiers are supported. Wildcard specifications are supported for both schemas and tables. The default value is all tables within the users scope are eligible for tuning. The supported wildcard character is %. A % wildcard matches any set of consecutive characters.</p> <p>When a SQL statement is processed, it will not be accepted if any referenced table matches an entry in the invalid table list.</p> <p>Valid syntax for a table reference is:</p> <pre>schema.table schema schema.% (Equivalent to schema)</pre> <p>Possible values:</p> <p>Single table reference comma-delimited table reference list ADVISOR_UNUSED</p> <p>The default value is ADVISOR_UNUSED.</p> <p>Note that SQLAccess Advisor maintains an internal list of non-tunable tables regardless of the contents of the INVALID_TABLE_LIST parameter. No table that is owned by SYS, SYSTEM or any other pre-defined Oracle schema can be tuned.</p>

Table 12–4 SQL Workload Object Parameters(Cont.)

Name	Datatype	Description
JOURNALING	NUMBER	<p>Controls the logging of messages to the journal (USER_ADVISOR_JOURNAL view). The higher the setting, the more information is logged to the journal.</p> <p>Valid settings are:</p> <ul style="list-style-type: none"> 0: no journal messages 1: informational messages only 2: warning messages 3: explanation of errors 4: explanation of fatal errors (default) 5-9: debug messages
MODULE_LIST	STRINGLIST	<p>Contains a fully qualified list of application modules that are eligible for saving in a SQL Workload object. The list elements are comma-delimited, and quoted names are supported.</p> <p>A module can be any string. If a module is not quoted, it will be changed to uppercase lettering and stripped of leading and trailing spaces. A module string is not scanned for correctness.</p> <p>During a workload import operation, if a SQL statements application module does not match a name in the module list, it will not be stored in the workload objecttask.</p> <p>Possible values:</p> <ul style="list-style-type: none"> Single module comma-delimited module list ADVISOR_UNUSED <p>The default value is ADVISOR_UNUSED.</p>
ORDER_LIST	STRING	<p>Contains the primary natural order in which the SQLAccess Advisor processes workload elements during the import operation.</p> <p>Possible values are: BUFFER_GETS, OPTIMIZER_COST, CPU_TIME, DISK_READS, ELAPSED_TIME, EXECUTIONS, and PRIORITY .</p>
REPORT_DATE_FORMAT		This parameter is not used.

Table 12–4 SQL Workload Object Parameters(Cont.)

Name	Datatype	Description
SQL_LIMIT	NUMBER	<p>Specifies the maximum number of SQL statements to be saved during a workload import operation. The <code>SQL_LIMIT</code> filter is applied after all other filters have been applied. For example, if only statements referencing the table <code>foo.bar</code> are to be accepted, the <code>SQL_LIMIT</code> value will be only apply to those statements.</p> <p>When used in conjunction with the parameter <code>ORDER_LIST</code>, Access Advisor will process and save the most interesting SQL statements by ordering the statements according to the specified sort keys.</p> <p>Possible values:</p> <p>An integer in the range of 1 to 2147483647</p> <p><code>ADVISOR_UNLIMITED</code></p> <p><code>ADVISOR_UNUSED</code></p> <p>The default value is <code>ADVISOR_UNLIMITED</code>.</p>
START_TIME	STRING	<p>Specifies a start time for selecting SQL statements. If the statement did not execute on or before the specified time, it will not be processed.</p> <p>Each date must be in the standard Oracle form of MM-DD-YYYY HH24:MI:SS, where:</p> <p>DD is the numeric date MM is the numeric month YYYY is the numeric year HH is the hour in 24 hour format MI is the minute SS is the second</p>
USERNAME_LIST	STRINGLIST	<p>Contains a fully qualified list of usernames that are eligible for processing in a SQL Workload object. The list elements are comma-delimited, and quoted names are supported.</p> <p>During a workload import operation, if a SQL statements username does not match a name in the username list, it will not be stored in the workload object. A Username is not case sensitive unless it is quoted.</p> <p>Possible values:</p> <p>Single username</p> <p>comma-delimited username list</p> <p><code>ADVISOR_UNUSED</code></p> <p>The default value is <code>ADVISOR_UNUSED</code>.</p>

Table 12–4 SQL Workload Object Parameters(Cont.)

Name	Datatype	Description
VALID_TABLE_LIST	TABLELIST	<p>Contains a fully qualified list of tables that are eligible for tuning. The list elements are comma-delimited, and quoted identifiers are supported. Wildcard specifications are supported for tables. The default value is all tables within the user's scope are eligible for tuning. The supported wildcard character is %. A % wildcard matches any set of consecutive characters.</p> <p>When a SQL statement is processed, it will not be accepted unless at least one referenced table is specified in the valid table list. If the list is unused, then all table references within a SQL statement are considered valid.</p> <p>When using the <code>IMPORT_SQLWKLD_SCHEMA</code> procedure, the <code>valid_table_list</code> parameter cannot contain wildcards such as <code>SCO%</code> or <code>SCOTT.EMP%</code>. The only form of wildcards supported is <code>SCOTT.%</code>, which specifies all tables in a given schema.</p> <p>Valid syntax for a table reference is:</p> <pre>schema.table schema schema.% (Equivalent to schema)</pre> <p>Possible values:</p> <ul style="list-style-type: none"> Single table reference comma-delimited table reference list ADVISOR_UNUSED <p>The default value is <code>ADVISOR_UNUSED</code>.</p>

Segment Advisor Parameters

[Table 12–5](#) lists the input task parameters that can be set in the Segment Advisor using the `SET_TASK_PARAMETER` procedure.

Table 12–5 Segment Advisor Task Parameters

Parameter	Default Value	Possible Values	Description
MODE	COMPREHENSIVE	<p>LIMITED: Analysis restricted to statistics available in Automatic Workload Repository.</p> <p>COMPREHENSIVE: Comprehensive analysis based on sampling and Automatic Workload Repository statistics.</p>	The data to use for analysis.

Table 12–5 Segment Advisor Task Parameters(Cont.)

Parameter	Default Value	Possible Values	Description
TIME_LIST	UNLIMITED	UNLIMITED	The time limit for which the Advisor should run. Specified in seconds.
RECOMMEND_ ALL	TRUE	TRUE: Generate recommendations on all segments specified by the user. FALSE: Generate recommendations for only those objects that are eligible for shrink.	Whether to generate recommendations for all segments.

Summary of DBMS_ADVISOR Subprograms

Table 12–6 DBMS_ADVISOR Package Subprograms

Subprogram	Description	Used in
ADD_SQLWKLD_REF Procedure on page 12-23	Adds a workload reference to an Advisor task	SQLAccess Advisor only
ADD_SQLWKLD_STATEMENT Procedure on page 12-24	Adds a single statement to a workload	SQLAccess Advisor only
CANCEL_TASK Procedure on page 12-27	Cancels a currently executing task operation	All Advisors
CREATE_FILE Procedure on page 12-28	Creates an external file from a PL/SQL CLOB variable, which is useful for creating scripts and reports	All Advisors
CREATE_OBJECT Procedure on page 12-30	Creates a new task object	All Advisors
CREATE_SQLWKLD Procedure on page 12-32	Creates a new workload object	SQLAccess Advisor only
CREATE_TASK Procedures on page 12-34	Creates a new Advisor task in the repository	All Advisors
DELETE_SQLWKLD Procedure on page 12-36	Deletes an entire workload object	SQLAccess Advisor only
DELETE_SQLWKLD_REF Procedure on page 12-37	Deletes an entire workload object	SQLAccess Advisor only
DELETE_SQLWKLD_STATEMENT Procedure on page 12-38	Deletes one or more statements from a workload	SQLAccess Advisor only
DELETE_TASK Procedure on page 12-40	Deletes the specified task from the repository	All Advisors
EXECUTE_TASK Procedure on page 12-41	Executes the specified task	All Advisors
GET_REC_ATTRIBUTES Procedure on page 12-42	Retrieves specific recommendation attributes from a task	All Advisors

Table 12-6 DBMS_ADVISOR Package Subprograms

Subprogram	Description	Used in
GET_TASK_SCRIPT Procedure on page 12-45	Creates and returns an executable SQL script of the Advisor task's recommendations in a buffer	All Advisors
IMPORT_SQLWKLD_SCHEMA Procedure on page 12-47	Imports data into a workload from the current SQL cache	SQLAccess Advisor only
IMPORT_SQLWKLD_SQLCACHE Procedure on page 12-49	Imports data into a workload from the current SQL cache	SQLAccess Advisor only
IMPORT_SQLWKLD_STS Procedure on page 12-51	Imports data into a workload from a SQL Tuning Set into a SQL workload data object	SQLAccess Advisor only
IMPORT_SQLWKLD_SUMADV Procedure on page 12-53	Imports data into a workload from the current SQL cache	SQLAccess Advisor only
IMPORT_SQLWKLD_USER Procedure on page 12-55	Imports data into a workload from the current SQL cache	SQLAccess Advisor only
INTERRUPT_TASK Procedure on page 12-57	Stops a currently executing task, ending its operations as it would at a normal exit	All Advisors
MARK_RECOMMENDATION Procedure on page 12-58	Sets the <code>annotation_status</code> for a particular recommendation	All Advisors
QUICK_TUNE Procedure on page 12-60	Performs an analysis on a single SQL statement	All Advisors
RESET_TASK Procedure on page 12-63	Resets a task to its initial state	All Advisors
SET_DEFAULT_SQLWKLD_PARAMETER Procedure on page 12-64	Imports data into a workload from schema evidence	SQLAccess Advisor only
SET_DEFAULT_TASK_PARAMETER Procedures on page 12-66	Modifies a default task parameter	All Advisors
SET_SQLWKLD_PARAMETER Procedure on page 12-67	Sets the value of a workload parameter	SQLAccess Advisor only

Table 12–6 DBMS_ADVISOR Package Subprograms

Subprogram	Description	Used in
SET_TASK_PARAMETER Procedures on page 12-69	Sets the specified task parameter value	All Advisors
TUNE_MVIEW Procedure on page 12-71	Shows how to decompose a materialized view into two or more materialized views or to restate the materialized view in a way that is more advantageous for fast refresh and query rewrite	SQLAccess Advisor only
UPDATE_OBJECT Procedure on page 12-74	Updates a task object	All Advisors
UPDATE_REC_ATTRIBUTES Procedure on page 12-76	Updates an existing recommendation for the specified task	All Advisors
UPDATE_SQLWKLD_ATTRIBUTES Procedure on page 12-78	Updates a workload object	SQLAccess Advisor only
UPDATE_SQLWKLD_STATEMENT Procedure on page 12-80	Updates one or more SQL statements in a workload	SQLAccess Advisor only
UPDATE_TASK_ATTRIBUTES Procedure on page 12-82	Updates a task's attributes	All Advisors

ADD_SQLWKLD_REF Procedure

This procedure establishes a link between the current SQLAccess Advisor task and a SQL Workload object. The link allows an advisor task to access interesting data for doing an analysis. The link also provides a stable view of the data. Once a connection between a SQLAccess Advisor task and a SQL Workload object is made, the workload is protected from removal or modification.

Syntax

```
DBMS_ADVISOR.ADD_SQLWKLD_REF (
    task_name          IN VARCHAR2,
    workload_name     IN VARCHAR2);
```

Parameters

Table 12–7 ADD_SQLWKLD_REF Procedure Parameters

Parameter	Description
task_name	The SQLAccess task name that uniquely identifies an existing task.
workload_name	The name of the workload object to be linked. Once a object has been linked to a task, it becomes read-only and cannot be deleted. There is no limit to the number of links to workload objects. To remove the link to the workload object, use the procedure DELETE_REFERENCE.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    workload_name VARCHAR2(30);
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
END;
/
```

ADD_SQLWKLD_STATEMENT Procedure

This procedure adds a single statement to the specified workload.

Syntax

```
DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT (
  workload_name      IN VARCHAR2,
  module             IN VARCHAR2,
  action             IN VARCHAR2,
  cpu_time           IN NUMBER := 0,
  elapsed_time       IN NUMBER := 0,
  disk_reads         IN NUMBER := 0,
  buffer_gets        IN NUMBER := 0,
  rows_processed     IN NUMBER := 0,
  optimizer_cost     IN NUMBER := 0,
  executions         IN NUMBER := 1,
  priority           IN NUMBER := 2,
  last_execution_date IN DATE := 'SYSDATE',
  stat_period        IN NUMBER := 0,
  username           IN VARCHAR2,
  sql_text           IN CLOB);
```

Parameters

Table 12–8 ADD_SQLWKLD_STATEMENT Procedure Parameters

Parameter	Description
workload_name	The workload name that uniquely identifies an existing workload.
module	An optional business application module that will be associated with the SQL statement.
action	An optional application action that will be associated with the SQL statement.
cpu_time	The total CPU time in seconds that is consumed by SQL statement over the population time window.
elapsed_time	The total elapsed time in seconds that is consumed by SQL statement over the population time window.
disk_reads	The total disk-read operations that are consumed by SQL statement over the population time window.

Table 12–8 ADD_SQLWKLD_STATEMENT Procedure Parameters

Parameter	Description
buffer_gets	The total buffer-get operations that are consumed by SQL statement over the population time window.
rows_processed	The average number of rows processed by the statement over the population time window.
optimizer_cost	The optimizer's calculated cost value.
executions	The total execution count by the SQL statement over the population time window.
priority	The relative priority of the SQL statement. The value must be one of the following: 1-HIGH, 2-MEDIUM, or 3-LOW.
last_execution_date	The date and time at which the SQL statement last executed. If the value is NULL, then the current date and time will be used.
stat_period	Time interval in seconds from which statement statistics were calculated.
username	The Oracle user name that executed the SQL statement. Because a username is an Oracle identifier, the username value must be entered exactly as it is stored in the server. For example, if the user SCOTT is the executing user, then you must provide the user identifier SCOTT in all uppercase letters. It will not recognize the user scott as a match for SCOTT.
sql_text	The complete SQL statement. To increase the quality of a recommendation, the SQL statement should not contain bind variables.

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See ["RESET_TASK Procedure"](#) on page 12-63 for directions on setting a task to its initial state.

Examples

```

DECLARE
    workload_name VARCHAR2(30);
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',

```

```
100,400,5041,103,640445,680000,2,  
1,SYSDATE,1,'SH','SELECT avg(amount_sold)  
FROM sh.sales');  
END;  
/
```

CANCEL_TASK Procedure

This procedure causes a currently executing operation to terminate. This call does a soft interrupt. It will not break into a low-level database access call like a hard interrupt such as Ctrl-C. The SQLAccess Advisor periodically checks for soft interrupts and acts appropriately. As a result, this operation may take a few seconds to respond to a call.

Syntax

```
DBMS_ADVISOR.CANCEL_TASK (
    task_name      IN VARCHAR2);
```

Parameters

Table 12–9 CANCEL_TASK Procedure Parameter

Parameter	Description
task_name	A valid Advisor task name that uniquely identifies an existing task.

Usage Notes

A cancel command effective restores the task to its condition prior to the start of the cancelled operation. Therefore, a cancelled task or data object cannot be resumed.

Because all Advisor task procedures are synchronous, to cancel an operation, you must use a separate database session.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    workload_name VARCHAR2(30);
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CANCEL_TASK('My Task');
END;
/
```

CREATE_FILE Procedure

This procedure creates an external file from a PL/SQL CLOB variable, which is used for creating scripts and reports. `CREATE_FILE` accepts a CLOB input parameter and writes the character string contents to the specified file.

Syntax

```
DBMS_ADVISOR.CREATE_FILE (  
    buffer      IN  CLOB,  
    location   IN  VARCHAR2,  
    filename   IN  VARCHAR2);
```

Parameters

Table 12–10 *CREATE_FILE Procedure Parameters*

Parameter	Description
<code>buffer</code>	A CLOB buffer containing report or script information.
<code>location</code>	Specifies the directory that will contain the new file. You must use the directory alias as defined by the <code>CREATE DIRECTORY</code> statement. The Advisor will translate the alias into the actual directory location.
<code>filename</code>	Specifies the output file to receive the script commands. The filename can only contain the name and an optional file type of the form <code>filename.filetype</code> .

Usage Notes

All formatting must be embedded within the CLOB.

The Oracle server restricts file access within Oracle Stored Procedures. This means that file locations and names must adhere to the known file permissions in the server.

Examples

```
CREATE DIRECTORY MY_DIR as '/homedir/user4/gssmith';  
GRANT READ,WRITE ON DIRECTORY MY_DIR TO PUBLIC;  
  
DECLARE  
    task_id NUMBER;  
    task_name VARCHAR2(30);  
    workload_name VARCHAR2(30);
```



```
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                        100,400,5041,103,640445,680000,2,
                                        1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales');
    DBMS_ADVISOR.EXECUTE_TASK(task_name);
    DBMS_ADVISOR.CREATE_FILE(DBMS_ADVISOR.GET_TASK_SCRIPT(task_name),
        'MY_DIR','script.sql');

END;
/
```

CREATE_OBJECT Procedure

This procedure creates a new task object.

Syntax

```
DBMS_ADVISOR.CREATE_TASK (  
    task_name          IN VARCHAR2,  
    object_type        IN VARCHAR2,  
    attr1              IN VARCHAR2 := NULL,  
    attr2              IN VARCHAR2 := NULL,  
    attr3              IN VARCHAR2 := NULL,  
    attr4              IN CLOB := NULL,  
    attr5              IN VARCHAR2 := NULL,  
    object_id          OUT NUMBER);
```

Parameters

Table 12–11 CREATE_OBJECT Procedure Parameters

Parameter	Description
task_name	A valid advisor task name that uniquely identifies an existing task.
object_type	Specifies the external object type.
attr1	Advisor-specific data.
attr2	Advisor-specific data.
attr3	Advisor-specific data.
attr4	Advisor-specific data.
attr5	Advisor-specific data.
object_id	The advisor-assigned object identifier.

The attribute parameters have different values depending upon the object type. See *Oracle Database Administrator's Guide* for details regarding these parameters and object types.

Return Values

Returns the new object identifier.

Usage Notes

Task objects are typically used as input data for a particular advisor. Segment advice can be generated at the object, segment, or tablespace level. If for the object level, advice is generated on all partitions of the object (if the object is partitioned). The advice is not cascaded to any dependent objects. If for the segment level, advice can be obtained on a single segment, such as the partition or subpartition of a table, index, or lob column. If for a tablespace level, target advice for every segment in the tablespace will be generated.

See *Oracle Database Administrator's Guide* for further information regarding the Segment Advisor.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    obj_id NUMBER;
BEGIN
    task_name := 'My Task';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_OBJECT (task_name, 'SQL', NULL, NULL, NULL,
                                'SELECT * FROM SH.SALES', obj_id);
END;
/
```

CREATE_SQLWKLD Procedure

This procedure creates a new private SQL Workload object for the user. A SQL Workload object manages a SQL workload on behalf of the SQLAccess Advisor. A SQL Workload object must exist prior to performing any other SQL Workload operations, such as importing or updating SQL statements.

Syntax

```
DBMS_ADVISOR.CREATE_SQLWKLD (
  workload_name          IN VARCHAR2,
  description            IN VARCHAR2 := NULL,
  template              IN VARCHAR2 := NULL,
  is_template           IN VARCHAR2 := 'FALSE');
```

Parameters

Table 12–12 CREATE_SQLWKLD Procedure Parameters

Parameter	Description
<code>workload_name</code>	A name that uniquely identifies the created workload. If not specified, the system will generate a unique name. Names can be up to 30 characters long.
<code>description</code>	Specifies an optional workload description. Descriptions can be up to 256 characters.
<code>template</code>	An optional SQL Workload name of an existing workload data object or data object template.
<code>is_template</code>	An optional value that enables you to set the newly created workload as a template. Valid values are <code>TRUE</code> and <code>FALSE</code> .

Return Values

The SQLAccess Advisor returns a unique workload object identifier number that must be used for subsequent activities within the new SQL Workload object.

Usage Notes

By default, workload objects are created using built-in default settings. To create a workload using the parameter settings of an existing workload or workload template, the user may specify an existing workload name.

Once a SQL Workload object is present, it can then be referenced by one or more SQLAccess Advisor tasks using the `ADD_SQLWKLD_REF` procedure.

Examples

```
DECLARE
    workload_name VARCHAR2(30);
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
END;
/
```

CREATE_TASK Procedures

This procedure creates a new Advisor task in the repository.

Syntax

```
DBMS_ADVISOR.CREATE_TASK (
  advisor_name      IN VARCHAR2 NOT NULL,
  task_name         IN VARCHAR2,
  task_desc         IN VARCHAR2 := NULL,
  task_or_template  IN VARCHAR2 := NULL,
  is_template       IN VARCHAR2 := 'FALSE');
```

```
DBMS_ADVISOR.CREATE_TASK (
  advisor_name      IN VARCHAR2 NOT NULL,
  task_id           OUT NUMBER,
  task_name         IN OUT VARCHAR2,
  task_desc         IN VARCHAR2 := NULL,
  task_or_template  IN VARCHAR2 := NULL,
  is_template       IN VARCHAR2 := 'FALSE');
```

Parameters

Table 12–13 CREATE_TASK Procedure Parameters

Parameter	Description
advisor_name	Specifies the unique advisor name as defined in the view DBA_ADVISOR_DEFINITIONS.
task_id	A number that uniquely identifies the created task. The number is generated by the procedure and returned to the user.
task_name	Specifies a new task name. Names must be unique among all tasks for the user. For version 2 of CREATE_TASK, the system can generate a unique name. Names can be up to 30 characters long.
task_desc	Specifies an optional task description. Descriptions can be up to 256 characters in length.
task_or_template	An optional task name of an existing task or task template. To specify built-in SQLAccess Advisor templates, use the template name as described earlier.

Table 12–13 CREATE_TASK Procedure Parameters

Parameter	Description
<code>is_template</code>	An optional value that allows the user to set the newly created task as template. Valid values are: <code>TRUE</code> and <code>FALSE</code> .

Return Values

Returns a unique task ID number and a unique task name if one is not specified.

Usage Notes

A task must be associated with an advisor, and once the task has been created, it is permanently associated with the original advisor. By default, tasks are created using built-in default settings. To create a task using the parameter settings of an existing task or task template, the user may specify an existing task name.

For the SQLAccess Advisor, use the identifier `DBMS_ADVISOR.SQLACCESS_ADVISOR` as the `advisor_name`.

The SQLAccess Advisor provides three built-in task templates, using the following constants:

- `DBMS_ADVISOR.SQLACCESS_OLTP`
Parameters are preset to favor an OLTP application environment.
- `DBMS_ADVISOR.SQLACCESS_WAREHOUSE`
Parameters are preset to favor a data warehouse application environment.
- `DBMS_ADVISOR.SQLACCESS_GENERAL`
Parameters are preset to favor a hybrid application environment where both OLTP and data warehouse operations may occur. For the SQLAccess Advisor, this is the default template.

Examples

```

DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
BEGIN
    task_name := 'My Task';
    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
END;
/

```

DELETE_SQLWKLD Procedure

This procedure deletes an existing SQL Workload object from the repository.

Syntax

```
DBMS_ADVISOR.DELETE_SQLWKLD (  
    workload_name          IN VARCHAR2);
```

Parameters

Table 12–14 *DELETE_SQLWKLD Procedure Parameters*

Parameter	Description
workload_name	The workload object name that uniquely identifies an existing workload. The wildcard % is supported as a WORKLOAD_NAME. The rules of use are identical to the LIKE operator. For example, to delete all tasks for the current user, use the wildcard % as the WORKLOAD_NAME. If a wildcard is provided, the DELETE_SQLWKLD operation will not delete any workloads marked as READ_ONLY or TEMPLATE.

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See the ["RESET_TASK Procedure"](#) on page 12-63 to set a task to its initial state.

Examples

```
DECLARE  
    workload_name VARCHAR2(30);  
BEGIN  
    workload_name := 'My Workload';  
  
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');  
    DBMS_ADVISOR.DELETE_SQLWKLD(workload_name);  
END;  
/
```


DELETE_SQLWKLD_REF Procedure

This procedure removes a link between the current SQLAccess task and a SQL Workload data object.

Syntax

```
DBMS_ADVISOR.DELETE_SQLWKLD_REF (
    task_name          IN VARCHAR2,
    workload_name      IN NUMBER);
```

Parameters

Table 12–15 *DELETE_SQLWKLD_REF Procedure Parameters*

Parameter	Description
task_name	The SQLAccess task name that uniquely identifies an existing task.
workload_name	The name of the workload object to be unlinked. The wildcard % is supported as a workload_name. The rules of use are identical to the LIKE operator. For example, to remove all links to workload objects, use the wildcard % as the workload_name.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    workload_name VARCHAR2(30);
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
        100,400,5041,103,640445,680000,2,
        1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales');
    DBMS_ADVISOR.DELETE_SQLWKLD_REF(task_name, workload_name);
END;
/
```

DELETE_SQLWKLD_STATEMENT Procedure

This procedure deletes one or more statements from a workload.

Syntax

```
DBMS_ADVISOR.DELETE_SQLWKLD_STATEMENT (
  workload_name      IN VARCHAR2,
  sql_id             IN VARCHAR2);
```

```
DBMS_ADVISOR.DELETE_SQLWKLD_STATEMENT (
  workload_name      IN VARCHAR2,
  search             IN VARCHAR2,
  deleted            OUT NUMBER);
```

Parameters

Table 12–16 *DELETE_SQLWKLD_STATEMENT Procedure Parameters*

Parameter	Description
workload_name	The workload object name that uniquely identifies an existing workload.
sql_id	The Advisor-generated identifier number that is assigned to the statement. To specify all workload statements, use the constant <code>ADVISOR_ALL</code> .
search	An optional SQL predicate that allows the user to refine the workload entries that will be deleted. The <code>WHERE</code> keyword should not be included in the text.
deleted	Returns the number of statements deleted by the searched deleted operation.

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See the ["RESET_TASK Procedure"](#) on page 12-63 to set a task to its initial state.

Examples

```
DECLARE
  workload_name VARCHAR2(30);
  deleted NUMBER;
  id NUMBER;
```

```
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                         100,400,5041,103,640445,680000,2,
                                         1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales');
    DBMS_ADVISOR.ADD_SQLWKLKLD_STATEMENT(workload_name, 'YEARLY', 'ROLLUP',
                                         100,400,5041,103,640445,680000,2,
                                         1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales');

    DBMS_ADVISOR.DELETE_SQLWKLKLD_STATEMENT(workload_name,'module =
    'MONTHLY'',deleted);

    SELECT min(sql_id) INTO id FROM USER_ADVISOR_SQLW_STMTS
    WHERE workload_name = 'My Workload';

    DBMS_ADVISOR.DELETE_SQLWKLKLD_STATEMENT(workload_name, id);
END;
/
```

DELETE_TASK Procedure

This procedure deletes an existing task from the repository.

Syntax

```
DBMS_ADVISOR.DELETE_TASK (  
    task_name          IN VARCHAR2);
```

Parameters

Table 12–17 *DELETE_TASK Procedure Parameters*

Parameter	Description
task_name	A single Advisor task name that will be deleted from the repository. The wildcard % is supported as a TASK_NAME. The rules of use are identical to the LIKE operator. For example, to delete all tasks for the current user, use the wildcard % as the TASK_NAME. If a wildcard is provided, the DELETE_TASK operation will not delete any tasks marked as READ_ONLY or TEMPLATE.

Examples

```
DECLARE  
    task_id NUMBER;  
    task_name VARCHAR2(30);  
BEGIN  
    task_name := 'My Task';  
  
    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);  
    DBMS_ADVISOR.DELETE_TASK(task_name);  
END;  
/
```

EXECUTE_TASK Procedure

This procedure performs the Advisor analysis or evaluation for the specified task.

Syntax

```
DBMS_ADVISOR.EXECUTE_TASK (
    task_name          IN VARCHAR2);
```

Parameters

Table 12–18 EXECUTE_TASK Procedure Parameters

Parameter	Description
task_name	The task name that uniquely identifies an existing task.

Usage Notes

Task execution is a synchronous operation. Control will not be returned to the caller until the operation has completed, or a user-interrupt was detected.

Upon return, you can check the DBA_ADVISOR_LOG table for the execution status.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    workload_name VARCHAR2(30);
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                        100,400,5041,103,640445,680000,2,
                                        1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales');
    DBMS_ADVISOR.EXECUTE_TASK(task_name);
END;
/
```

GET_REC_ATTRIBUTES Procedure

This procedure retrieves a specified attribute of a new object as recommended by Advisor analysis.

Syntax

```
DBMS_ADVISOR.GET_REC_ATTRIBUTES (  
    workload_name      IN VARCHAR2,  
    rec_id             IN NUMBER,  
    action_id         IN NUMBER,  
    attribute_name     IN VARCHAR2,  
    value              OUT VARCHAR2);
```

Parameters

Table 12–19 *GET_REC_ATTRIBUTES Procedure Parameters*

Parameter	Description
task_name	The task name that uniquely identifies an existing task.
rec_id	The Advisor-generated identifier number that is assigned to the recommendation.
action_id	The Advisor-generated action identifier that is assigned to the particular command.
attribute_name	Specifies the attribute to change.
value	The buffer to receive the requested attribute value.

Return Values

The requested attribute value is returned in the `VALUE` argument.

Usage Notes

This will name and assign ownership to new objects such as indexes and materialized views during the analysis operation. However, it will not necessarily choose appropriate names, so you can manually set the owner, name and tablespace values for new objects.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    workload_name VARCHAR2(30);
    attribute VARCHAR2(100);
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                        100,400,5041,103,640445,680000,2,
                                        1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales WHERE promo_id = 10');
    DBMS_ADVISOR.EXECUTE_TASK(task_name);

    DBMS_ADVISOR.GET_REC_ATTRIBUTES(task_name, 1, 1, 'NAME', attribute);
END;
/
```

GET_TASK_REPORT Procedure

This procedure creates and returns an XML report for the specified task.

Syntax

```
DBMS_ADVISOR.GET_TASK_REPORT (  
    task_name      IN VARCHAR2,  
    type           IN VARCHAR2 := 'TEXT',  
    level          IN VARCHAR2 := 'TYPICAL',  
    section        IN VARCHAR2 := 'ALL',  
    owner_name     IN VARCHAR2 := NULL)  
RETURN CLOB;
```

Parameters

Table 12–20 *GET_TASK_REPORT Procedure Parameters*

Parameter	Description
task_name	The name of the task from which the script will be created.
type	The possible values are: TEXT, HTML, and XML.
level	The possible values are BASIC, TYPICAL, and ALL.
section	Advisor-specific report sections.
owner_name	Owner of the task. If specified, the system will check to see if the current user has read privileges to the task data.

Return Values

Returns the buffer receiving the script.

GET_TASK_SCRIPT Procedure

This procedure creates a SQL*Plus-compatible SQL script and sends the output to file. The script will contain all of the accepted recommendations from the specified task.

Syntax

```
DBMS_ADVISOR.GET_TASK_SCRIPT (
    task_name          IN VARCHAR2
    type               IN VARCHAR2 := 'IMPLEMENTATION',
    rec_id             IN NUMBER := NULL,
    action_id          IN NUMBER := NULL)
RETURN CLOB;
```

Parameters

Table 12-21 *GET_TASK_SCRIPT Procedure Parameters*

Parameter	Description
task_name	The task name that uniquely identifies an existing task.
type	Specifies the type of script to generate. The possible values are: IMPLEMENTATION and UNDO
rec_id	An optional recommendation identifier number that can be used to extract a subset of the implementation script. A zero or the value DBMS_ADVISOR.ADVISOR_ALL indicates all accepted recommendations would be included. The default is to include all accepted recommendations for the task.
action_id	Optional action identifier number that can be used to extract a single action as a DDL command. A zero or the value DBMS_ADVISOR.ADVISOR_ALL indicates all actions for the recommendation would be included. The default is to include all actions for a recommendation.

Return Values

Returns the script as a CLOB buffer.

Usage Notes

Though the script is ready to execute, Oracle recommends that the user review the script for acceptable locations for new materialized views and indexes.

For a recommendation to appear in a generated script, it must be marked as accepted.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    workload_name VARCHAR2(30);
    buf CLOB;
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                        100,400,5041,103,640445,680000,2,
                                        1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales');
    DBMS_ADVISOR.EXECUTE_TASK(task_name);
    buf := DBMS_ADVISOR.GET_TASK_SCRIPT(task_name);
END;
/
```

IMPORT_SQLWKLD_SCHEMA Procedure

This procedure constructs and loads a SQL workload based on schema evidence. The workload is also referred to as a hypothetical workload.

Syntax

```
DBMS_ADVISOR.IMPORT_SQLWKLD_SCHEMA (
  workload_name      IN VARCHAR2,
  import_mode        IN VARCHAR2,
  priority            NUMBER := 2,
  saved_rows         OUT NUMBER,
  failed_rows        OUT NUMBER);
```

Parameters

Table 12–22 *IMPORT_SQLWKLD_SCHEMA Procedure Parameters*

Parameter	Description
workload_name	The workload object name that uniquely identifies an existing workload.
import_mode	Specifies the action to be taken when storing the workload. Possible values are: APPEND Indicates that the collected workload will be added to any existing workload in the task. NEW Indicates that the collected workload will be the exclusive workload for the task. If an existing workload is found, an exception will be thrown. REPLACE Indicates the collected workload will be the exclusive workload for the task. If an existing workload is found, it will be deleted prior to saving the new workload. The default value is NEW .
priority	Specifies the application priority for each statement that is saved in the workload object. The value must be one of the following: 1-HIGH, 2-MEDIUM, or 3-LOW.
total_rows	Returns the number of rows processed.
saved_rows	Returns the number of rows actually saved in the repository.

Return Values

This call returns the number of rows processed and the number of rows saved and failed as output parameters.

Usage Notes

To successfully import a hypothetical workload, the target schemas must contain dimension or primary/foreign key information.

If the `VALID_TABLE_LIST` parameter is not set, the search space may become very large and require a significant amount of time to complete. Oracle recommends that you limit your search space to specific set of tables.

If a task contains valid recommendations from a prior run, adding or modifying task will mark the task as invalid, preventing the viewing and reporting of potentially valuable recommendation data.

Examples

```
DECLARE
  workload_name VARCHAR2(30);
  saved NUMBER;
  failed NUMBER;
BEGIN
  workload_name := 'My Workload';

  DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
  DBMS_ADVISOR.SET_SQLWKLD_PARAMETER(workload_name, 'VALID_TABLE_LIST', 'SH.%');
  DBMS_ADVISOR.IMPORT_SQLWKLD_SCHEMA(workload_name, 'REPLACE', 1, saved,
    failed);
END;
/
```

IMPORT_SQLWKLD_SQLCACHE Procedure

This procedure creates a SQL workload from the current contents of the server's SQL cache.

Syntax

```
DBMS_ADVISOR.IMPORT_SQLWKLD_SQLCACHE (
  workload_name      IN VARCHAR2,
  import_mode        IN VARCHAR2,
  priority           IN NUMBER := 2,
  saved_rows         OUT NUMBER,
  failed_rows        OUT NUMBER);
```

Parameters

Table 12–23 *IMPORT_SQLWKLD_SQLCACHE Procedure Parameters*

Parameter	Description
workload_name	The workload object name that uniquely identifies an existing workload.
import_mode	Specifies the action to be taken when storing the workload. Possible values are: APPEND Indicates that the collected workload will be added to any existing workload in the task. NEW Indicates that the collected workload will be the exclusive workload for the task. If an existing workload is found, an exception will be thrown. REPLACE Indicates the collected workload will be the exclusive workload for the task. If an existing workload is found, it will be deleted prior to saving the new workload. The default value is NEW .
priority	Specifies the application priority for each statement that is saved in the workload object. The value must be one of the following: 1-HIGH, 2-MEDIUM, or 3-LOW.
saved_rows	Returns number of rows processed and the number of rows saved as output parameters.
failed_rows	Returns the number of rows that were not saved due to syntax or validation errors.

Return Values

This call returns the number of rows processed and the number of rows saved and failed as output parameters.

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See ["RESET_TASK Procedure"](#) on page 12-63 to set a task to its initial state.

Examples

```
DECLARE
    workload_name VARCHAR2(30);
    saved NUMBER;
    failed NUMBER;
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.SET_SQLWKLD_PARAMETER(workload_name, 'VALID_TABLE_LIST', 'SH.%');
    DBMS_ADVISOR.IMPORT_SQLWKLD_SQLCACHE(workload_name, 'REPLACE', 1, saved,
        failed);
END;
/
```

IMPORT_SQLWKLD_STS Procedure

This procedure loads a SQL workload from an existing SQL Tuning Set. A SQL Tuning Set is typically created from the server workload repository using various time and data filters.

Syntax

```
DBMS_ADVISOR.IMPORT_SQLWKLD_STS (
  workload_name      IN VARCHAR2,
  sqlset_name        IN VARCHAR2,
  import_mode        IN VARCHAR2,
  priority            IN NUMBER := 2,
  saved_rows         OUT NUMBER,
  failed_rows        OUT NUMBER);
```

Parameters

Table 12–24 *IMPORT_SQLWKLD_STS Procedure Parameters*

Parameter	Description
workload_name	The workload object name that uniquely identifies an existing workload.
sqlset_name	The name of an existing SQL Tuning Set workload from which the data will be imported.
import_mode	Specifies the action to be taken when storing the workload. Possible values are: APPEND Indicates that the collected workload will be added to any existing workload in the task. NEW Indicates that the collected workload will be the exclusive workload for the task. If an existing workload is found, an exception will be thrown. REPLACE Indicates the collected workload will be the exclusive workload for the task. If an existing workload is found, it will be deleted prior to saving the new workload. The default value is NEW.
priority	Specifies the application priority for each statement that is saved in the workload object. The value must be one of the following: 1-HIGH, 2-MEDIUM, or 3-LOW. The default value is 2.
saved_rows	Returns the number of rows actually saved in the repository.

Table 12-24 *IMPORT_SQLWKLD_STS Procedure Parameters(Cont.)*

Parameter	Description
failed_rows	Returns the number of rows that were not saved due to syntax or validation errors.

Return Values

This call returns the number of rows processed and the number of rows saved and failed as output parameters.

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See "[RESET_TASK Procedure](#)" on page 12-63 to set a task to its initial state.

Examples

```
DECLARE
  workload_name VARCHAR2(30);
  saved NUMBER;
  failed NUMBER;
BEGIN
  workload_name := 'My Workload';

  DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
  DBMS_ADVISOR.SET_SQLWKLD_PARAMETER(workload_name, 'VALID_TABLE_LIST', 'SH.%');
  DBMS_ADVISOR.IMPORT_SQLWKLD_STS(workload_name, 'MY_SQLSET', 'REPLACE', 1,
    saved, failed);
END;
/
```


IMPORT_SQLWKLD_SUMADV Procedure

This procedure collects a SQL workload from a Summary Advisor workload. This procedure is intended to assist 9i Summary Advisor users in the migration to SQLAccess Advisor.

Syntax

```
DBMS_ADVISOR.IMPORT_SQLWKLD_SUMADV (
  workload_name      IN VARCHAR2,
  import_mode        IN VARCHAR2,
  priority            IN NUMBER := 2,
  sumadv_id          IN NUMBER,
  saved_rows         OUT NUMBER,
  failed_rows        OUT NUMBER);
```

Parameters

Table 12–25 *IMPORT_SQLWKLD_SUMADV Procedure Parameters*

Parameter	Description
workload_name	The workload object name that uniquely identifies an existing workload.
import_mode	Specifies the action to be taken when storing the workload. Possible values are: APPEND Indicates that the collected workload will be added to any existing workload in the task. NEW Indicates that the collected workload will be the exclusive workload for the task. If an existing workload is found, an exception will be thrown. REPLACE Indicates the collected workload will be the exclusive workload for the task. If an existing workload is found, it will be deleted prior to saving the new workload. The default value is NEW .
priority	Specifies the default application priority for each statement that is saved in the workload object. If a Summary Advisor workload statement contains a priority of zero, the default priority will be applied. If the workload statement contains a valid priority, then the Summary Advisor priority will be converted to a comparable SQLAccess Advisor priority. The value must be one of the following: 1-HIGH, 2-MEDIUM, or 3-LOW.
sumadv_id	Specifies the Summary Advisor workload identifier number.

Table 12-25 *IMPORT_SQLWKLD_SUMADV Procedure Parameters(Cont.)*

Parameter	Description
saved_rows	Returns the number of rows actually saved in the repository.
failed_rows	Returns the number of rows that were not saved due to syntax or validation errors.

Return Values

This call returns the number of rows processed and the number of rows saved and failed as output parameters.

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See ["RESET_TASK Procedure"](#) on page 12-63 to set a task to its initial state.

Examples

```
DECLARE
    workload_name VARCHAR2(30);
    saved NUMBER;
    failed NUMBER;
    sumadv_id NUMBER;
BEGIN
    workload_name := 'My Workload';
    sumadv_id := 394;

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.SET_SQLWKLD_PARAMETER(workload_name, 'VALID_TABLE_LIST', 'SH.%');
    DBMS_ADVISOR.IMPORT_SQLWKLD_SUMADV(workload_name, 'REPLACE', 1, sumadv_id,
        saved, failed);
END;
/
```

IMPORT_SQLWKLD_USER Procedure

This procedure collects a SQL workload from a specified user table.

Syntax

```
DBMS_ADVISOR.IMPORT_SQLWKLD_USER (
  workload_name      IN VARCHAR2,
  import_mode        IN VARCHAR2,
  owner              IN VARCHAR2,
  table              IN VARCHAR2,
  saved_rows         OUT NUMBER,
  failed_rows        OUT NUMBER);
```

Parameters

Table 12–26 *IMPORT_SQLWKLD_USER Procedure Parameters*

Parameter	Description
workload_name	The workload object name that uniquely identifies an existing workload.
import_mode	Specifies the action to be taken when storing the workload. Possible values are: APPEND Indicates that the collected workload will be added to any existing workload in the task. NEW Indicates that the collected workload will be the exclusive workload for the task. If an existing workload is found, an exception will be thrown. REPLACE Indicates the collected workload will be the exclusive workload for the task. If an existing workload is found, it will be deleted prior to saving the new workload. The default value is <code>NEW</code> .
owner	Specifies the owner name of the table or view from which workload data will be collected.
table	Specifies the name of the table or view from which workload data will be collected.
saved_rows	Returns the number of rows actually saved in the workload object.

Table 12–26 *IMPORT_SQLWKLD_USER Procedure Parameters*

Parameter	Description
failed_rows	Returns the number of rows that were not saved due to syntax or validation errors.

Return Values

This call returns the number of rows processed and the number of rows saved and failed as output parameters.

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See ["RESET_TASK Procedure"](#) on page 12-63 to set a task to its initial state.

Examples

```

DECLARE
    workload_name VARCHAR2(30);
    saved NUMBER;
    failed NUMBER;
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.SET_SQLWKLD_PARAMETER(workload_name, 'VALID_TABLE_LIST', 'SH.%');
    DBMS_ADVISOR.IMPORT_SQLWKLD_USER(workload_name, 'REPLACE', 'SH',
        'USER_WORKLOAD',
                                saved, failed);
END;
/

```

INTERRUPT_TASK Procedure

This procedure stops a currently executing task. The task will end its operations as it would at a normal exit. The user will be able to access any recommendations that exist to this point.

Syntax

```
DBMS_ADVISOR.INTERRUPT_TASK (  
    task_name          IN VARCHAR2);
```

Parameters

Table 12–27 *INTERRUPT_TASK Procedure Parameters*

Parameter	Description
task_name	A single Advisor task name that will be interrupted.

Examples

```
DECLARE  
    task_id NUMBER;  
    task_name VARCHAR2(30);  
BEGIN  
    task_name := 'My Task';  
  
    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);  
    DBMS_ADVISOR.INTERRUPT_TASK('My Task');  
END;  
/
```

MARK_RECOMMENDATION Procedure

This procedure marks a recommendation for import or implementation.

Syntax

```
DBMS_ADVISOR.MARK_RECOMMENDATION (  
    task_name          IN VARCHAR2  
    id                 IN NUMBER,  
    action             IN VARCHAR2);
```

Parameters

Table 12–28 *MARK_RECOMMENDATION Procedure Parameters*

Parameter	Description
task_name	Name of the task.
id	The recommendation identifier number assigned by the Advisor.
action	The recommendation action setting. The possible actions are: ACCEPT: Marks the recommendation as accepted. With this setting, the recommendation will appear in implementation and undo scripts. IGNORE: Marks the recommendation as ignore. With this setting, the recommendation will not appear in an implementation or undo script. IMPLEMENTED: Marks the recommendation as implemented. With this setting, a user can manage which recommendations have been successfully implemented. The implementation script can also set this value. REJECT: Marks the recommendation as rejected. With this setting, the recommendation will not appear in any implementation or undo scripts.

Usage Notes

For a recommendation to be implemented, it must be marked as accepted. By default, all recommendations are considered accepted and will appear in any generated scripts.

Examples

```
DECLARE  
    task_id NUMBER;  
    task_name VARCHAR2(30);  
    workload_name VARCHAR2(30);
```

```
attribute VARCHAR2(100);
rec_id NUMBER;
BEGIN
  task_name := 'My Task';
  workload_name := 'My Workload';

  DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
  DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
  DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
  DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                     100,400,5041,103,640445,680000,2,
                                     1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales WHERE promo_id = 10');
  DBMS_ADVISOR.EXECUTE_TASK(task_name);

  rec_id := 1;

  DBMS_ADVISOR.MARK_RECOMMENDATION(task_name, rec_id, 'REJECT');
END;
/
```

QUICK_TUNE Procedure

This procedure performs an analysis and generates recommendations for a single SQL statement.

This provides a shortcut method of all necessary operations to analyze the specified SQL statement. The operation creates a task using the specified task name. The task will be created using a specified Advisor task template. Finally, the task will be executed and the results will be saved in the repository.

Syntax

```
DBMS_ADVISOR.QUICK_TUNE (  
    advisor_name      IN VARCHAR2,  
    task_name         IN VARCHAR2,  
    attr1             IN CLOB,  
    attr2             IN VARCHAR2 := NULL,  
    attr3             IN NUMBER := NULL,  
    task_or_template  IN VARCHAR2 := NULL);
```

Parameters

Table 12–29 QUICK_TUNE Procedure Parameters

Parameter	Description
advisor_name	Name of the Advisor that will perform the analysis.
task_name	Name of the task.
attr1	Advisor-specific attribute in the form of a CLOB variable.
attr2	Advisor-specific attribute in the form of a VARCHAR2 variable.
attr3	Advisor-specific attribute in the form of a NUMBER.
task_or_template	An optional task name of an existing task or task template.

Usage Notes

If indicated by the user, the final recommendations can be implemented by the procedure.

The task will be created using either a specified SQLAccess task template or the built-in default template of `SQLACCESS_GENERAL`. The workload will only contain the specified statement, and all task parameters will be defaulted.

attr1 must be the single SQL statement to tune.

Examples

```
DECLARE
  task_name VARCHAR2(30);
BEGIN
  task_name := 'My Task';

  DBMS_ADVISOR.QUICK_TUNE(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_name,
    'SELECT avg(amount_sold) FROM sh.sales WHERE promo_id=10');
END;
/
```

RESET_SQLWKLD Procedure

This procedure resets a workload to its initial starting point. This has the effect of removing all journal messages, log messages, and recalculating necessary volatility and usage statistics.

Syntax

```
DBMS_ADVISOR.RESET_SQLWKLD (
    workload_name      IN VARCHAR2);
```

Parameters

Table 12–30 *RESET_SQLWKLD Procedure Parameters*

Parameter	Description
workload_name	The SQL Workload object name that uniquely identifies an existing workload.

Usage Notes

RESET_SQLWKLD should be executed after any workload adjustments such as adding or removing SQL statements.

Examples

```
DECLARE
    workload_name VARCHAR2(30);
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
        100,400,5041,103,640445,680000,2,
        1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales WHERE promo_id = 10');

    DBMS_ADVISOR.RESET_SQLWKLD(workload_name);
END;
/
```

RESET_TASK Procedure

This procedure resets a task to its initial state. All intermediate and recommendation data will be removed from the task. The task status will be set to INITIAL.

Syntax

```
DBMS_ADVISOR.RESET_TASK (
    task_name          IN VARCHAR2);
```

Parameters

Table 12–31 *RESET_TASK Procedure Parameters*

Parameter	Description
task_name	The task name that uniquely identifies an existing task.

Examples

```
DECLARE
    task_id NUMBER;
    task_name VARCHAR2(30);
    workload_name VARCHAR2(30);
BEGIN
    task_name := 'My Task';
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                        100,400,5041,103,640445,680000,2,
                                        1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales WHERE promo_id = 10');
    DBMS_ADVISOR.EXECUTE_TASK(task_name);

    DBMS_ADVISOR.RESET_TASK(task_name);
END;
/
```

SET_DEFAULT_SQLWKLD_PARAMETER Procedure

This procedure modifies the default value for a user parameter within a SQL Workload object or SQL Workload object template. A user parameter is a simple variable that stores various attributes that affect workload collection, tuning decisions and reporting. When a default value is changed for a parameter, workload objects will inherit the new value when they are created.

Syntax

```
DBMS_ADVISOR.SET_DEFAULT_SQLWKLD_PARAMETER (
    parameter          IN VARCHAR2,
    value              IN VARCHAR2);
```

```
DBMS_ADVISOR.SET_DEFAULT_SQLWKLD_PARAMETER (
    parameter          IN VARCHAR2,
    value              IN NUMBER);
```

Parameters

Table 12–32 SET_DEFAULT_SQLWKLD_PARAMETER Procedure Parameters

Parameter	Description
parameter	The name of the data parameter to be modified. Parameter names are not case sensitive. Parameter names are unique to the workload object type, but not necessarily unique to all workload object types. Various object types may use the same parameter name for different purposes.
value	The value of the specified parameter. The value can be specified as a string or a number. If the value is <code>DBMS_ADVISOR.DEFAULT</code> , the value will be reset to the default value.

Usage Notes

A parameter will only affect operations that modify the workload collection. Therefore, parameters should be set prior to importing or adding new SQL statements to a workload. If a parameter is set after data has been placed in a workload object, it will have no effect on the existing data.

Examples

```
BEGIN
DBMS_ADVISOR.SET_DEFAULT_SQLWKLD_PARAMETER('VALID_TABLE_LIST','SH.%');
```

END;
/

SET_DEFAULT_TASK_PARAMETER Procedures

This procedure modifies the default value for a user parameter within a task or a template. A user parameter is a simple variable that stores various attributes that affect various Advisor operations. When a default value is changed for a parameter, tasks will inherit the new value when they are created.

Syntax

```
DBMS_ADVISOR.SET_DEFAULT_TASK_PARAMETER (  
    advisor_name      IN VARCHAR2  
    parameter         IN VARCHAR2,  
    value             IN VARCHAR2);
```

```
DBMS_ADVISOR.SET_DEFAULT_TASK_PARAMETER (  
    advisor_name      IN VARCHAR2  
    parameter         IN VARCHAR2,  
    value             IN NUMBER);
```

Parameters

Table 12–33 SET_DEFAULT_TASK_PARAMETER Procedure Parameters

Parameter	Description
advisor_name	Specifies the unique advisor name as defined in the view DBA_ADVISOR_DEFINITIONS.
parameter	The name of the task parameter to be modified. Parameter names are not case sensitive. Parameter names are unique to the task type, but not necessarily unique to all task types. Various task types may use the same parameter name for different purposes
value	The value of the specified task parameter. The value can be specified as a string or a number.

Examples

```
BEGIN  
DBMS_ADVISOR.SET_DEFAULT_TASK_PARAMETER(DBMS_ADVISOR.SQLACCESS_ADVISOR,  
    'VALID_TABLE_LIST', 'SH.%');  
END;  
/
```

SET_SQLWKLD_PARAMETER Procedure

This procedure modifies a user parameter within a SQL Workload object or SQL Workload object template. A user parameter is a simple variable that stores various attributes that affect workload collection, tuning decisions and reporting.

Syntax

```
DBMS_ADVISOR.SET_SQLWKLD_PARAMETER (
  workload_name      IN VARCHAR2,
  parameter          IN VARCHAR2,
  value              IN VARCHAR2);
```

```
DBMS_ADVISOR.SET_SQLWKLD_PARAMETER (
  workload_name      IN VARCHAR2,
  parameter          IN VARCHAR2,
  value              IN NUMBER);
```

Parameters

Table 12–34 SET_SQLWKLD_PARAMETER Procedure Parameters

Parameter	Description
workload_name	The SQL Workload object name that uniquely identifies an existing workload.
parameter	The name of the data parameter to be modified. Parameter names are not case sensitive.
value	The value of the specified parameter. The value can be specified as a string or a number. If the value is DBMS_ADVISOR.DEFAULT, the value will be reset to the default value.

Usage Notes

A parameter will only affect operations that modify the workload collection. Therefore, parameters should be set prior to importing or adding new SQL statements to a workload. If a parameter is set after data has been placed in a workload object, it will have no effect on the existing data.

Examples

```
DECLARE
  workload_name VARCHAR2(30);
```

```
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.SET_SQLWKLD_PARAMETER(workload_name, 'VALID_TABLE_LIST', 'SH.%.');
END;
/
```


SET_TASK_PARAMETER Procedures

This procedure modifies a user parameter within an Advisor task or a template. A user parameter is a simple variable that stores various attributes that affect workload collection, tuning decisions and reporting.

Syntax

```
DBMS_ADVISOR.SET_TASK_PARAMETER (
  task_name          IN VARCHAR2
  parameter          IN VARCHAR2 ,
  value              IN VARCHAR2);
```

```
DBMS_ADVISOR.SET_TASK_PARAMETER (
  task_name          IN VARCHAR2
  parameter          IN VARCHAR2 ,
  value              IN NUMBER);
```

Parameters

Table 12–35 *SET_TASK_PARAMETER Procedure Parameters*

Parameter	Description
task_name	The Advisor task name that uniquely identifies an existing task.
parameter	The name of the task parameter to be modified. Parameter names are not case sensitive. Parameter names are unique to the task type, but not necessarily unique to all task types. Various task types may use the same parameter name for different purposes.
value	The value of the specified task parameter. The value can be specified as a string or a number. If the value is <code>DEFAULT</code> , the value will be reset to the default value.

Usage Notes

A task cannot be modified unless it is in its initial state. See "[RESET_TASK Procedure](#)" on page 12-63 to set a task to its initial state. See your Advisor-specific documentation for further information on using this procedure.

Examples

```
DECLARE
  task_id NUMBER;
```

SET_TASK_PARAMETER Procedures

```
    task_name VARCHAR2(30);
BEGIN
    task_name := 'My Task';

    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
    DBMS_ADVISOR.SET_TASK_PARAMETER(task_name, 'VALID_TABLELIST',
        'SH.%,SCOTT.EMP');
END;
/
```

TUNE_MVIEW Procedure

This procedure shows how to decompose a materialized view into two or more materialized views and to restate the materialized view in a way that is more advantageous for fast refresh and query rewrite. It also shows how to fix materialized view logs and to enable query rewrite.

Syntax

```
DBMS_ADVISOR.TUNE_MVIEW (
  task_name IN OUT VARCHAR2,
  mv_create_stmt IN [CLOB | VARCHAR2]);
```

Parameters

Table 12–36 TUNE_MVIEW Procedure Parameters

Parameter	Description
task_name	The task name for looking up the results in a catalog view. If not specified, the system will generate a name and return.
mv_create_stmt	The original materialized view creation statement.

See Also: *Oracle Data Warehousing Guide* for more information about using the TUNE_MVIEW procedure

Usage Notes

Executing TUNE_MVIEW generates two sets of output results: one is for CREATE implementation and the other is for undoing the CREATE MATERIALIZED VIEW implementation. The output results are accessible through USER_TUNE_MVIEW and DBA_TUNE_MVIEW views. You can also use DBMS_ADVISOR.GET_TASK_SCRIPT and DBMS_ADVISOR.CREATE_FILE to output the TUNE_MVIEW results into a script file for later execution.

USER_TUNE_MVIEW and DBA_TUNE_MVIEW Views

These views are to get the result after executing the TUNE_MVIEW procedure.

Table 12–37 USER_TUNE_MVIEW and DBA_TUNE_MVIEW Views

Column Name	Column Description
OWNER	The materialized view owner's name
TASK_NAME	The task name as a key to access the set of recommendations
SCRIPT_TYPE	Recommendation ID used to indicate the row is for IMPLEMENTATION or UNDO script.
ACTION_ID	Action ID used as the command order number
STATEMENT	For TUNE_MVIEW output, this column represents the following statements, and includes statement properties such as REFRESH and REWRITE options: CREATE MATERIALIZED VIEW LOG ALTER MATERIALIZED VIEW LOG FORCE [CREATE DROP] MATERIALIZED VIEW

Examples

```
name VARCHAR2(30);
DBMS_ADVISOR.TUNE_MVIEW.(name, 'SELECT AVG(C1) FROM my_fact_table WHERE c10 =
7');
```

The following is an example to show how to use TUNE_MVIEW to optimize a CREATE MATERIALIZED VIEW statement:

```
NAME VARCHAR2(30) := 'my_tune_mview_task';
EXECUTE DBMS_ADVISOR.TUNE_MVIEW (name, 'CREATE MATERIALIZED VIEW MY_MV
REFRESH FAST AS SELECT C2, AVG(C1) FROM MY_FACT_TABLE WHERE C10 = 7
GROUP BY C2');
```

You can view the CREATE output results by querying USER_TUNE_MVIEW or DBA_TUNE_MVIEW as the following example:

```
SELECT * FROM USER_TUNE_MVIEW WHERE TASK_NAME='my_tune_mview_task' AND
SCRIPT_TYPE='CREATE';
```

Alternatively, you can save the output results in an external script file as in the following example:

```
CREATE DIRECTORY TUNE_RESULTS AS '/myscript_dir' ;
GRANT READ, WRITE ON DIRECTORY TUNE_RESULTS TO PUBLIC;
EXECUTE DBMS_ADVISOR.CREATE_FILE(DBMS_ADVISOR.GET_TASK_SCRIPT('my_tune_mview_
task'), -
```

```
 '/homes/tune', 'my_tune_mview_create.sql' );
```

The preceding statement will save the CREATE output results in /myscript_dir/my_tune_mview_create.sql.

UPDATE_OBJECT Procedure

This procedure updates an existing task object. Task objects are typically used as input data for a particular advisor. Segment advice can be generated at the object, segment, or tablespace level.

Syntax

```
DBMS_ADVISOR.UPDATE_OBJECT (  
    task_name      IN VARCHAR2  
    object_id      IN NUMBER,  
    attr1          IN VARCHAR2 := NULL,  
    attr2          IN VARCHAR2 := NULL,  
    attr3          IN VARCHAR2 := NULL,  
    attr4          IN CLOB := NULL,  
    attr5          IN VARCHAR2 := NULL);
```

Parameters

Table 12–38 UPDATE_OBJECT Procedure Parameters

Parameter	Description
task_name	A valid advisor task name that uniquely identifies an existing task.
object_id	The advisor-assigned object identifier.
attr1	Advisor-specific data. If set to NULL, there will be no effect on the target object.
attr2	Advisor-specific data. If set to NULL, there will be no effect on the target object.
attr3	Advisor-specific data. If set to NULL, there will be no effect on the target object.
attr4	Advisor-specific data. If set to NULL, there will be no effect on the target object.
attr5	Advisor-specific data. If set to null, there will be no effect on the target object.

The attribute parameters have different values depending upon the object type. See *Oracle Database Administrator's Guide* for details regarding these parameters and object types.

Usage Notes

If for the object level, advice is generated on all partitions of the object (if the object is partitioned). The advice is not cascaded to any dependent objects. If for the segment level, advice can be obtained on a single segment, such as the partition or subpartition of a table, index, or lob column. If for a tablespace level, target advice for every segment in the tablespace will be generated.

See *Oracle Database Administrator's Guide* for further information regarding the Segment Advisor.

Examples

```
DECLARE
  task_id NUMBER;
  task_name VARCHAR2(30);
  obj_id NUMBER;
BEGIN
  task_name := 'My Task';

  DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
  DBMS_ADVISOR.CREATE_OBJECT (task_name, 'SQL', NULL, NULL, NULL,
                             'SELECT * FROM SH.SALES', obj_id);
  DBMS_ADVISOR.UPDATE_OBJECT (task_name, obj_id, NULL, NULL, NULL,
                             'SELECT count(*) FROM SH.SALES');

END;
/
```

UPDATE_REC_ATTRIBUTES Procedure

This procedure updates the owner, name, and tablespace for a recommendation.

Syntax

```
DBMS_ADVISOR.UPDATE_REC_ATTRIBUTES (  
    task_name          IN VARCHAR2  
    rec_id             IN NUMBER,  
    action_id         IN NUMBER,  
    attribute_name     IN VARCHAR2,  
    value              IN VARCHAR2);
```

Parameters

Table 12–39 UPDATE_REC_ATTRIBUTES Procedure Parameters

Parameter	Description
task_name	The task name that uniquely identifies an existing task.
rec_id	The Advisor-generated identifier number that is assigned to the recommendation.
action_id	The Advisor-generated action identifier that is assigned to the particular command.
attribute_name	Name of the attribute to be changed. The valid values are: owner The new owner of the object. name The new name of the object. tablespace The new tablespace for the object.
value	Specifies the new value for the recommendation attribute.

Usage Notes

Recommendation attributes cannot be modified unless the task has successfully executed.

Examples

```
DECLARE  
    task_id NUMBER;  
    task_name VARCHAR2(30);  
    workload_name VARCHAR2(30);
```



```
attribute VARCHAR2(100);
BEGIN
  task_name := 'My Task';
  workload_name := 'My Workload';

  DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);
  DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
  DBMS_ADVISOR.ADD_SQLWKLD_REF(task_name, workload_name);
  DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                     100,400,5041,103,640445,680000,2,
                                     1,SYSDATE,1,'SH','SELECT avg(amount_sold)
FROM sh.sales WHERE promo_id = 10');
  DBMS_ADVISOR.EXECUTE_TASK(task_name);

  attribute := 'SH';

  DBMS_ADVISOR.UPDATE_REC_ATTRIBUTES(task_name, 1, 3, 'OWNER', attribute);
END;
/
```

UPDATE_SQLWKLD_ATTRIBUTES Procedure

This procedure changes various attributes of a SQL Workload object or template.

Syntax

```
DBMS_ADVISOR.UPDATE_SQLWKLD_ATTRIBUTES (
    workload_name      IN VARCHAR2,
    new_name           IN VARCHAR2 := NULL,
    description        IN VARCHAR2 := NULL,
    read_only          IN VARCHAR2 := NULL,
    is_template        IN VARCHAR2 := NULL,
    source             IN VARCHAR2 := NULL);
```

Parameters

Table 12–40 UPDATE_SQLWKLD_ATTRIBUTES Procedure Parameters

Parameter	Description
<code>workload_name</code>	The workload object name that uniquely identifies an existing workload.
<code>new_name</code>	The new workload object name. If the value is <code>NULL</code> or contains the value <code>ADVISOR_UNUSED</code> , the workload will not be renamed. A task name can be up to 30 characters long.
<code>description</code>	A new workload description. If the value is <code>NULL</code> or contains the value <code>ADVISOR_UNUSED</code> , the description will not be changed. Names can be up to 256 characters long.
<code>read_only</code>	Set to <code>TRUE</code> so it cannot be changed.
<code>is_template</code>	<code>TRUE</code> if workload is to be used as a template.
<code>source</code>	Indicates a source application name that initiated the workload creation. If the value is <code>NULL</code> or contains the value <code>ADVISOR_UNUSED</code> , the source will not be changed.

Examples

```
DECLARE
    workload_name VARCHAR2(30);
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
```

```
DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                     100,400,5041,103,640445,680000,2,
                                     1,SYSDATE,1,'SH','SELECT AVG(amount_sold)
FROM sh.sales WHERE promo_id = 10');
DBMS_ADVISOR.UPDATE_SQLWKLD_ATTRIBUTES(workload_name,'New workload name');
END;
/
```

UPDATE_SQLWKLD_STATEMENT Procedure

This procedure updates an existing SQL statement in a specified SQL workload.

Syntax

```
DBMS_ADVISOR.UPDATE_SQLWKLD_STATEMENT (
  workload_name      IN VARCHAR2,
  updated            OUT NUMBER,
  action             IN VARCHAR2,
  priority           IN NUMBER,
  username           IN VARCHAR2,
  search             IN VARCHAR2);
```

```
DBMS_ADVISOR.UPDATE_SQLWKLD_STATEMENT (
  workload_name      IN VARCHAR2,
  sql_id             IN NUMBER,
  module             IN VARCHAR2,
  action             IN VARCHAR2,
  priority           IN NUMBER,
  username           IN VARCHAR2);
```

Parameters

Table 12–41 UPDATE_SQLWKLD_STATEMENT Procedure Parameters

Parameter	Description
workload_name	The SQL Workload object name that uniquely identifies an existing workload.
sql_id	The Advisor-generated identifier number that is assigned to the statement. To specify all workload statements, use the constant <code>DBMS_ADVISOR.ADVISOR_ALL</code> .
updated	Returns the number of statements changed by a searched update.
module	Specifies a business application name that will be associated with the SQL statement. If the value is <code>NULL</code> or contains the value <code>ADVISOR_UNUSED</code> , then the column will not be updated in the repository.
action	Specifies the application action for the statement. If the value is <code>NULL</code> or contains the value <code>ADVISOR_UNUSED</code> , then the column will not be updated in the repository.

Table 12–41 UPDATE_SQLWKLD_STATEMENT Procedure Parameters(Cont.)

Parameter	Description
priority	<p>The relative priority of the SQL statement. The value must be one of the following:</p> <p>1 - HIGH, 2 - MEDIUM, or 3 - LOW</p> <p>If the value is NULL or contains the value <code>ADVISOR_UNUSED</code>, then the column will not be updated in the repository.</p>
username	<p>The Oracle user name that executed the SQL statement. If the value is NULL or contains the value <code>ADVISOR_UNUSED</code>, then the column will not be updated in the repository.</p> <p>Because a username is an Oracle identifier, the username value must be entered exactly like it is stored in the server. For example, if the user <code>SCOTT</code> is the executing user, then you must provide the user identifier <code>SCOTT</code> in all uppercase letters. It will not recognize the user <code>scott</code> as a match for <code>SCOTT</code>.</p>
search	<p>An optional SQL predicate that allows the user to refine the workload entries that will be updated. The <code>WHERE</code> keyword should not be included in the text.</p>

Usage Notes

A workload cannot be modified or deleted if it is currently referenced by an active task. A task is considered active if it is not in its initial state. See ["RESET_TASK Procedure"](#) on page 12-63 to set a task to its initial state.

Examples

```

DECLARE
    workload_name VARCHAR2(30);
    updated NUMBER;
BEGIN
    workload_name := 'My Workload';

    DBMS_ADVISOR.CREATE_SQLWKLD(workload_name, 'My Workload');
    DBMS_ADVISOR.ADD_SQLWKLD_STATEMENT(workload_name, 'MONTHLY', 'ROLLUP',
                                        100,400,5041,103,640445,680000,2,
                                        1,SYSDATE,1,'SH','SELECT AVG(amount_sold)
FROM sh.sales WHERE promo_id = 10');

    DBMS_ADVISOR.UPDATE_SQLWKLD_STATEMENT(workload_name, 'module = 'MONTHLY'',
        updated, 'YEARLY', NULL, NULL,NULL);
END;
/

```

UPDATE_TASK_ATTRIBUTES Procedure

This procedure changes various attributes of a task or a task template.

Syntax

```
DBMS_ADVISOR.UPDATE_TASK_ATTRIBUTES (
  task_name      IN VARCHAR2
  new_name       IN VARCHAR2 := NULL,
  description    IN VARCHAR2 := NULL,
  read_only      IN VARCHAR2 := NULL,
  is_template    IN VARCHAR2 := NULL,
  source         IN VARCHAR2 := NULL);
```

Parameters

Table 12–42 UPDATE_TASK_ATTRIBUTES Procedure Parameters

Parameter	Description
task_name	The Advisor task name that uniquely identifies an existing task.
new_name	The new Advisor task name. If the value is NULL or contains the value ADVISOR_UNUSED, the task will not be renamed. A task name can be up to 30 characters long.
description	A new task description. If the value is NULL or contains the value ADVISOR_UNUSED, the description will not be changed. Names can be up to 256 characters long.
read_only	Sets the task to read-only. Possible values are: TRUE and FALSE If the value is NULL or contains the value ADVISOR_UNUSED, the setting will not be changed.
is_template	Marks the task as a template. Physically, there is no difference between a task and a template; however, a template cannot be executed. Possible values are: TRUE and FALSE. If the value is NULL or contains the value ADVISOR_UNUSED, the setting will not be changed.
source	Indicates a source application name that initiated the task creation. If the value is NULL or contains the value ADVISOR_UNUSED, the source will not be changed.

Examples

```
DECLARE
  task_id NUMBER;
```

```
task_name VARCHAR2(30);  
BEGIN  
    task_name := 'My Task';  
  
    DBMS_ADVISOR.CREATE_TASK(DBMS_ADVISOR.SQLACCESS_ADVISOR, task_id, task_name);  
    DBMS_ADVISOR.UPDATE_TASK_ATTRIBUTES(task_name, 'New Task Name');  
    DBMS_ADVISOR.UPDATE_TASK_ATTRIBUTES('New Task Name', NULL, 'New description');  
END;  
/
```


DBMS_ALERT supports asynchronous notification of database events (alerts). By appropriate use of this package and database triggers, an application can notify itself whenever values of interest in the database are changed.

This chapter contains the following topics:

- [Using DBMS_ALERT](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Restrictions](#)
 - [Exceptions](#)
 - [Restrictions](#)
 - [Examples](#)
- [Summary of DBMS_ALERT Subprograms](#)

Using DBMS_ALERT

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Restrictions](#)
- [Exceptions](#)
- [Restrictions](#)
- [Examples](#)

Overview

Suppose a graphics tool is displaying a graph of some data from a database table. The graphics tool can, after reading and graphing the data, wait on a database alert (`WAITONE`) covering the data just read. The tool automatically wakes up when the data is changed by any other user. All that is required is that a trigger be placed on the database table, which performs a signal (`SIGNAL`) whenever the trigger is fired.

Security Model

Security on this package can be controlled by granting `EXECUTE` on this package to selected users or roles. You might want to write a cover package on top of this one that restricts the alert names used. `EXECUTE` privilege on this cover package can then be granted rather than on this package.

Constants

```
maxwait constant integer := 86400000; -- 1000 days
```

The maximum time to wait for an alert (this is essentially forever).

Restrictions

Because database alerters issue commits, they cannot be used with Oracle Forms. For more information on restrictions on calling stored procedures while Oracle Forms is active, refer to your Oracle Forms documentation.

Exceptions

DBMS_ALERT raises the application error -20000 on error conditions. [Table 13-1](#) shows the messages and the procedures that can raise them.

Operational Notes

The following notes relate to general and specific applications:

- Alerts are transaction-based. This means that the waiting session is not alerted until the transaction signalling the alert commits. There can be any number of concurrent signalers of a given alert, and there can be any number of concurrent waiters on a given alert.
- A waiting application is blocked in the database and cannot do any other work.
- An application can register for multiple events and can then wait for any of them to occur using the `WAITANY` procedure.
- An application can also supply an optional `timeout` parameter to the `WAITONE` or `WAITANY` procedures. A `timeout` of 0 returns immediately if there is no pending alert.
- The signalling session can optionally pass a message that is received by the waiting session.
- Alerts can be signalled more often than the corresponding application wait calls. In such cases, the older alerts are discarded. The application always gets the latest alert (based on transaction commit times).
- If the application does not require transaction-based alerts, the `DBMS_PIPE` package may provide a useful alternative.

See Also: [Chapter 63, "DBMS_PIPE"](#)

- If the transaction is rolled back after the call to `SIGNAL`, no alert occurs.

- It is possible to receive an alert, read the data, and find that no data has changed. This is because the data changed after the *prior* alert, but before the data was read for that *prior* alert.
- Usually, Oracle is event-driven; this means that there are no polling loops. There are two cases where polling loops can occur:
 - Shared mode. If your database is running in shared mode, a polling loop is required to check for alerts from another instance. The polling loop defaults to one second and can be set by the `SET_DEFAULTS` procedure.
 - `WAITANY` procedure. If you use the `WAITANY` procedure, and if a signalling session does a signal but does not commit within one second of the signal, a polling loop is required so that this uncommitted alert does not camouflage other alerts. The polling loop begins at a one second interval and exponentially backs off to 30-second intervals.

Table 13–1 DBMS_ALERT Error Messages

Error Message	Procedure
ORU-10001 lock request error, status: N	SIGNAL
ORU-10015 error: N waiting for pipe status	WAITANY
ORU-10016 error: N sending on pipe 'X'	SIGNAL
ORU-10017 error: N receiving on pipe 'X'	SIGNAL
ORU-10019 error: N on lock request	WAIT
ORU-10020 error: N on lock request	WAITANY
ORU-10021 lock request error; status: N	REGISTER
ORU-10022 lock request error, status: N	SIGNAL
ORU-10023 lock request error; status N	WAITONE
ORU-10024 there are no alerts registered	WAITANY
ORU-10025 lock request error; status N	REGISTER
ORU-10037 attempting to wait on uncommitted signal from same session	WAITONE

Examples

Suppose you want to graph average salaries by department, for all employees. Your application needs to know whenever EMP is changed. Your application would look similar to this code:

```
DBMS_ALERT.REGISTER('emp_table_alert');
  <<readagain>>:
  /* ... read the emp table and graph it */
  DBMS_ALERT.WAITONE('emp_table_alert', :message, :status);
  if status = 0 then goto <<readagain>>; else
  /* ... error condition */
```

The EMP table would have a trigger similar to this:

```
CREATE TRIGGER emptrig AFTER INSERT OR UPDATE OR DELETE ON emp
  BEGIN
    DBMS_ALERT.SIGNAL('emp_table_alert', 'message_text');
  END;
```

When the application is no longer interested in the alert, it makes this request:

```
DBMS_ALERT.REMOVE('emp_table_alert');
```

This reduces the amount of work required by the alert signaller. If a session exits (or dies) while registered alerts exist, the alerts are eventually cleaned up by future users of this package.

The example guarantees that the application always sees the latest data, although it may not see every intermediate value.

Summary of DBMS_ALERT Subprograms

Table 13–2 *DBMS_ALERT Package Subprograms*

Subprogram	Description
REGISTER Procedure on page 13-7	Receives messages from an alert
REMOVE Procedure on page 13-8	Disables notification from an alert
REMOVEALL Procedure on page 13-9	Removes all alerts for this session from the registration list
SET_DEFAULTS Procedure on page 13-10	Sets the polling interval
SIGNAL Procedure on page 13-11	Signals an alert (send message to registered sessions)
WAITANY Procedure on page 13-12	Waits <code>timeout</code> seconds to receive alert message from an alert registered for session
WAITONE Procedure on page 13-13	Waits <code>timeout</code> seconds to receive message from named alert

REGISTER Procedure

This procedure lets a session register interest in an alert.

Syntax

```
DBMS_ALERT.REGISTER (  
    name IN VARCHAR2);
```

Parameters

Table 13–3 REGISTER Procedure Parameters

Parameter	Description
name	Name of the alert in which this session is interested.

Caution: Alert names beginning with 'ORAS' are reserved for use for products provided by Oracle. Names must be 30 bytes or less. The name is case insensitive.

Usage Notes

A session can register interest in an unlimited number of alerts. Alerts should be deregistered when the session no longer has any interest, by calling `REMOVE`.

REMOVE Procedure

This procedure enables a session that is no longer interested in an alert to remove that alert from its registration list. Removing an alert reduces the amount of work done by signalers of the alert.

Syntax

```
DBMS_ALERT.REMOVE (  
    name IN VARCHAR2);
```

Parameters

Table 13–4 REMOVE Procedure Parameters

Parameter	Description
name	Name of the alert (case-insensitive) to be removed from registration list.

Usage Notes

Removing alerts is important because it reduces the amount of work done by signalers of the alert. If a session dies without removing the alert, that alert is eventually (but not immediately) cleaned up.

REMOVEALL Procedure

This procedure removes all alerts for this session from the registration list. You should do this when the session is no longer interested in any alerts.

This procedure is called automatically upon first reference to this package during a session. Therefore, no alerts from prior sessions which may have terminated abnormally can affect this session.

This procedure always performs a commit.

Syntax

```
DBMS_ALERT.REMOVEALL;
```

SET_DEFAULTS Procedure

In case a polling loop is required, use the `SET_DEFAULTS` procedure to set the polling interval.

Syntax

```
DBMS_ALERT.SET_DEFAULTS (  
    sensitivity IN NUMBER);
```

Parameters

Table 13–5 *SET_DEFAULTS Procedure Parameters*

Parameter	Description
<code>sensitivity</code>	Polling interval, in seconds, to sleep between polls. The default interval is five seconds.

SIGNAL Procedure

This procedure signals an alert. The effect of the `SIGNAL` call only occurs when the transaction in which it is made commits. If the transaction rolls back, `SIGNAL` has no effect.

All sessions that have registered interest in this alert are notified. If the interested sessions are currently waiting, they are awakened. If the interested sessions are not currently waiting, they are notified the next time they do a wait call.

Multiple sessions can concurrently perform signals on the same alert. Each session, as it signals the alert, blocks all other concurrent sessions until it commits. This has the effect of serializing the transactions.

Syntax

```
DBMS_ALERT.SIGNAL (  
    name      IN  VARCHAR2,  
    message   IN  VARCHAR2);
```

Parameters

Table 13–6 *SIGNAL Procedure Parameters*

Parameter	Description
<code>name</code>	Name of the alert to signal.
<code>message</code>	Message, of 1800 bytes or less, to associate with this alert. This message is passed to the waiting session. The waiting session might be able to avoid reading the database after the alert occurs by using the information in the message.

WAITANY Procedure

Call this procedure to wait for an alert to occur for any of the alerts for which the current session is registered.

Syntax

```
DBMS_ALERT.WAITANY (
    name      OUT  VARCHAR2,
    message   OUT  VARCHAR2,
    status    OUT  INTEGER,
    timeout   IN   NUMBER DEFAULT MAXWAIT);
```

Parameters

Table 13–7 WAITANY Procedure Parameters

Parameter	Description
name	Returns the name of the alert that occurred.
message	Returns the message associated with the alert. This is the message provided by the <code>SIGNAL</code> call. If multiple signals on this alert occurred before <code>WAITANY</code> , the message corresponds to the most recent <code>SIGNAL</code> call. Messages from prior <code>SIGNAL</code> calls are discarded.
status	Values returned: 0 - alert occurred 1 - timeout occurred
timeout	Maximum time to wait for an alert. If no alert occurs before <code>timeout</code> seconds, this returns a status of 1.

Usage Notes

An implicit `COMMIT` is issued before this procedure is executed. The same session that waits for the alert may also first signal the alert. In this case remember to commit after the signal and before the wait; otherwise, `DBMS_LOCK.REQUEST` (which is called by `DBMS_ALERT`) returns status 4.

Exceptions

-20000, ORU-10024: there are no alerts registered.

WAITONE Procedure

This procedure waits for a specific alert to occur. An implicit `COMMIT` is issued before this procedure is executed. A session that is the first to signal an alert can also wait for the alert in a subsequent transaction. In this case, remember to commit after the signal and before the wait; otherwise, `DBMS_LOCK.REQUEST` (which is called by `DBMS_ALERT`) returns status 4.

Syntax

```
DBMS_ALERT.WAITONE (
    name      IN   VARCHAR2,
    message   OUT  VARCHAR2,
    status    OUT  INTEGER,
    timeout   IN   NUMBER DEFAULT MAXWAIT);
```

Parameters

Table 13–8 *WAITONE Procedure Parameters*

Parameter	Description
name	Name of the alert to wait for.
message	Returns the message associated with the alert. This is the message provided by the <code>SIGNAL</code> call. If multiple signals on this alert occurred before <code>WAITONE</code> , the message corresponds to the most recent <code>SIGNAL</code> call. Messages from prior <code>SIGNAL</code> calls are discarded.
status	Values returned: 0 - alert occurred 1 - timeout occurred
timeout	Maximum time to wait for an alert. If the named alert does not occur before <code>timeout</code> seconds, this returns a status of 1.

DBMS_APPLICATION_INFO

Application developers can use the `DBMS_APPLICATION_INFO` package with Oracle Trace and the SQL trace facility to record names of executing modules or transactions in the database for later use when tracking the performance of various modules and debugging.

This chapter contains the following topics:

- [Using DBMS_APPLICATION_INFO](#)
 - [Overview](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_APPLICATION_INFO Subprograms](#)

Using DBMS_APPLICATION_INFO

- [Overview](#)
- [Security Model](#)
- [Operational Notes](#)

Overview

Registering the application allows system administrators and performance tuning specialists to track performance by module. System administrators can also use this information to track resource use by module. When an application registers with the database, its name and actions are recorded in the `V$SESSION` and `V$SQLAREA` views.

Security Model

Note: The public synonym for `DBMS_APPLICATION_INFO` is not dropped before creation so that you can redirect the public synonym to point to your own package.

No further privileges are required. The `DBMSAPIN.SQL` script is already run by `catproc`.

Operational Notes

Your applications should set the name of the module and name of the action automatically each time a user enters that module. The module name could be the name of a form in an Oracle Forms application, or the name of the code segment in an Oracle Precompilers application. The action name should usually be the name or description of the current transaction within a module.

If you want to gather your own statistics based on module, you can implement a wrapper around this package by writing a version of this package in another schema that first gathers statistics and then calls the `SYS` version of the package.

The public synonym for `DBMS_APPLICATION_INFO` can then be changed to point to the DBA's version of the package.

Summary of DBMS_APPLICATION_INFO Subprograms

Table 14–1 *DBMS_APPLICATION_INFO Package Subprograms*

Subprogram	Description
READ_CLIENT_INFO Procedure on page 14-5	Reads the value of the <code>client_info</code> field of the current session
READ_MODULE Procedure on page 14-6	Reads the values of the <code>module</code> and <code>action</code> fields of the current session
SET_ACTION Procedure on page 14-8	Sets the name of the current action within the current module
SET_CLIENT_INFO Procedure on page 14-10	Sets the <code>client_info</code> field of the session
SET_MODULE Procedure on page 14-11	Sets the name of the module that is currently running to a new module
SET_SESSION_LONGOPS Procedure on page 14-13	Sets a row in the <code>V\$SESSION_LONGOPS</code> table

READ_CLIENT_INFO Procedure

This procedure reads the value of the `client_info` field of the current session.

Syntax

```
DBMS_APPLICATION_INFO.READ_CLIENT_INFO (  
    client_info OUT VARCHAR2);
```

Parameters

Table 14–2 *READ_CLIENT_INFO Procedure Parameters*

Parameter	Description
<code>client_info</code>	Last client information value supplied to the <code>SET_CLIENT_INFO</code> procedure.

READ_MODULE Procedure

This procedure reads the values of the module and action fields of the current session.

Syntax

```
DBMS_APPLICATION_INFO.READ_MODULE (
    module_name OUT VARCHAR2,
    action_name OUT VARCHAR2);
```

Parameters

Table 14–3 READ_MODULE Procedure Parameters

Parameter	Description
module_name	Last value that the module name was set to by calling SET_MODULE.
action_name	Last value that the action name was set to by calling SET_ACTION or SET_MODULE.

Usage Notes

Module and action names for a registered application can be retrieved by querying V\$SQLAREA or by calling the READ_MODULE procedure. Client information can be retrieved by querying the V\$SESSION view, or by calling the [READ_CLIENT_INFO Procedure](#).

Examples

The following sample query illustrates the use of the MODULE and ACTION column of the V\$SQLAREA.

```
SELECT sql_text, disk_reads, module, action
FROM v$sqlarea
WHERE module = 'add_employee';

SQL_TEXT DISK_READS MODULE ACTION
-----
INSERT INTO emp 1 add_employee insert into emp
(ename, empno, sal, mgr, job, hiredate, comm, deptno)
VALUES
(name, next.emp_seq, manager, title, SYSDATE, commission, department)
```

1 row selected.

SET_ACTION Procedure

This procedure sets the name of the current action within the current module.

Syntax

```
DBMS_APPLICATION_INFO.SET_ACTION (  
    action_name IN VARCHAR2);
```

Parameters

Table 14–4 SET_ACTION Procedure Parameters

Parameter	Description
action_name	The name of the current action within the current module. When the current action terminates, call this procedure with the name of the next action if there is one, or NULL if there is not. Names longer than 32 bytes are truncated.

Usage Notes

The action name should be descriptive text about the current action being performed. You should probably set the action name before the start of every transaction.

Set the transaction name to NULL after the transaction completes, so that subsequent transactions are logged correctly. If you do not set the transaction name to NULL, subsequent transactions may be logged with the previous transaction's name.

Example

The following is an example of a transaction that uses the registration procedure:

```
CREATE OR REPLACE PROCEDURE bal_tran (amt IN NUMBER(7,2)) AS  
BEGIN  
  
    -- balance transfer transaction  
  
    DBMS_APPLICATION_INFO.SET_ACTION(  
        action_name => 'transfer from chk to sav');  
    UPDATE chk SET bal = bal + :amt  
        WHERE acct# = :acct;  
    UPDATE sav SET bal = bal - :amt  
        WHERE acct# = :acct;
```

```
COMMIT;  
DBMS_APPLICATION_INFO.SET_ACTION(null);  
  
END;
```

SET_CLIENT_INFO Procedure

This procedure supplies additional information about the client application.

Syntax

```
DBMS_APPLICATION_INFO.SET_CLIENT_INFO (  
    client_info IN VARCHAR2);
```

Parameters

Table 14–5 SET_CLIENT_INFO Procedure Parameters

Parameter	Description
client_info	Supplies any additional information about the client application. This information is stored in the V\$SESSION view. Information exceeding 64 bytes is truncated.

Note: CLIENT_INFO is readable and writable by any user. For storing secured application attributes, you can use the application context feature.

SET_MODULE Procedure

This procedure sets the name of the current application or module.

Syntax

```
DBMS_APPLICATION_INFO.SET_MODULE (
    module_name IN VARCHAR2,
    action_name IN VARCHAR2);
```

Parameters

Table 14–6 SET_MODULE Procedure Parameters

Parameter	Description
module_name	Name of module that is currently running. When the current module terminates, call this procedure with the name of the new module if there is one, or NULL if there is not. Names longer than 48 bytes are truncated.
action_name	Name of current action within the current module. If you do not want to specify an action, this value should be NULL. Names longer than 32 bytes are truncated.

Usage Notes

Example

```
CREATE or replace PROCEDURE add_employee(
    name VARCHAR2,
    salary NUMBER,
    manager NUMBER,
    title VARCHAR2,
    commission NUMBER,
    department NUMBER) AS
BEGIN
    DBMS_APPLICATION_INFO.SET_MODULE(
        module_name => 'add_employee',
        action_name => 'insert into emp');
    INSERT INTO emp
        (ename, empno, sal, mgr, job, hiredate, comm, deptno)
        VALUES (name, emp_seq.nextval, salary, manager, title, SYSDATE,
            commission, department);
```

```
        DBMS_APPLICATION_INFO.SET_MODULE(null,null);  
    END;
```

SET_SESSION_LONGOPS Procedure

This procedure sets a row in the `V$SESSION_LONGOPS` view. This is a view that is used to indicate the on-going progress of a long running operation. Some Oracle functions, such as parallel execution and Server Managed Recovery, use rows in this view to indicate the status of, for example, a database backup.

Applications may use the `SET_SESSION_LONGOPS` procedure to advertise information on the progress of application specific long running tasks so that the progress can be monitored by way of the `V$SESSION_LONGOPS` view.

Syntax

```
DBMS_APPLICATION_INFO.SET_SESSION_LONGOPS (
  rindex      IN OUT BINARY_INTEGER,
  slno        IN OUT BINARY_INTEGER,
  op_name     IN      VARCHAR2         DEFAULT NULL,
  target      IN      BINARY_INTEGER  DEFAULT 0,
  context     IN      BINARY_INTEGER  DEFAULT 0,
  sofar       IN      NUMBER           DEFAULT 0,
  totalwork   IN      NUMBER           DEFAULT 0,
  target_desc IN      VARCHAR2         DEFAULT 'unknown target',
  units       IN      VARCHAR2         DEFAULT NULL)

set_session_longops_nohint constant BINARY_INTEGER := -1;
```

Parameters

Table 14-7 *SET_SESSION_LONGOPS Procedure Parameters*

Parameter	Description
<code>rindex</code>	A token which represents the <code>v\$session_longops</code> row to update. Set this to <code>set_session_longops_nohint</code> to start a new row. Use the returned value from the prior call to reuse a row.
<code>slno</code>	Saves information across calls to <code>set_session_longops</code> : It is for internal use and should not be modified by the caller.
<code>op_name</code>	Specifies the name of the long running task. It appears as the <code>OPNAME</code> column of <code>v\$session_longops</code> . The maximum length is 64 bytes.

Table 14-7 SET_SESSION_LONGOPS Procedure Parameters

Parameter	Description
target	Specifies the object that is being worked on during the long running operation. For example, it could be a table ID that is being sorted. It appears as the TARGET column of v\$session_longops.
context	Any number the client wants to store. It appears in the CONTEXT column of v\$session_longops.
sofar	Any number the client wants to store. It appears in the SOFAR column of v\$session_longops. This is typically the amount of work which has been done so far.
totalwork	Any number the client wants to store. It appears in the TOTALWORK column of v\$session_longops. This is typically an estimate of the total amount of work needed to be done in this long running operation.
target_desc	Specifies the description of the object being manipulated in this long operation. This provides a caption for the target parameter. This value appears in the TARGET_DESC field of v\$session_longops. The maximum length is 32 bytes.
units	Specifies the units in which <code>sofar</code> and <code>totalwork</code> are being represented. It appears as the UNITS field of v\$session_longops. The maximum length is 32 bytes.

Example

This example performs a task on 10 objects in a loop. As the example completes each object, Oracle updates V\$SESSION_LONGOPS on the procedure's progress.

```

DECLARE
    rindex    BINARY_INTEGER;
    slno      BINARY_INTEGER;
    totalwork number;
    sofar     number;
    obj       BINARY_INTEGER;

BEGIN
    rindex := dbms_application_info.set_session_longops_nohint;
    sofar := 0;
    totalwork := 10;

    WHILE sofar < 10 LOOP
        -- update obj based on sofar

```

```
-- perform task on object target

sofar := sofar + 1;
dbms_application_info.set_session_longops(rindex, slno,
    "Operation X", obj, 0, sofar, totalwork, "table", "tables");
END LOOP;
END;
```

DBMS_APPLY_ADM

The DBMS_APPLY_ADM package, one of a set of Streams packages, provides administrative interfaces to start, stop, and configure an apply process. This package includes subprograms for configuring apply handlers, setting enqueue destinations for events, and specifying execution directives for events. This package also provides administrative subprograms that set the instantiation SCN for objects at a destination database. This package also includes subprograms for managing apply errors.

See Also: *Oracle Streams Concepts and Administration* and *Oracle Streams Replication Administrator's Guide* for more information about this package and apply processes

This chapter contains the following topic:

- [Summary of DBMS_APPLY_ADM Subprograms](#)

Summary of DBMS_APPLY_ADM Subprograms

Table 15–1 DBMS_APPLY_ADM Package Subprograms

Subprogram	Description
ALTER_APPLY Procedure on page 15-4	Alters an apply process
COMPARE_OLD_VALUES Procedure on page 15-12	Specifies whether to compare old value of one or more columns in a row LCR with the current value of the corresponding columns at the destination site during apply
CREATE_APPLY Procedure on page 15-14	Creates an apply process
DELETE_ALL_ERRORS Procedure on page 15-22	Deletes all the error transactions for the specified apply process
DELETE_ERROR Procedure on page 15-23	Deletes the specified error transaction
DROP_APPLY Procedure on page 15-24	Drops an apply process
EXECUTE_ALL_ERRORS Procedure on page 15-26	Reexecutes the error transactions for the specified apply process.
EXECUTE_ERROR Procedure on page 15-27	Reexecutes the specified error transaction
GET_ERROR_MESSAGE Functions on page 15-28	Returns the message payload from the error queue for the specified message number and transaction identifier
SET_DML_HANDLER Procedure on page 15-30	Alters operation options for a specified object with a specified apply process
SET_ENQUEUE_DESTINATION Procedure on page 15-36	Sets the queue where an event that satisfies the specified rule is enqueued automatically by an apply process
SET_EXECUTE Procedure on page 15-38	Specifies whether an event that satisfies the specified rule is executed by an apply process
SET_GLOBAL_INSTANTIATION_SCN Procedure on page 15-40	Records the specified instantiation SCN for the specified source database and, optionally, for the schemas at the source database and the tables owned by these schemas

Table 15–1 DBMS_APPLY_ADM Package Subprograms

Subprogram	Description
SET_KEY_COLUMNS Procedures on page 15-43	Records the set of columns to be used as the substitute primary key for local apply purposes and removes existing substitute primary key columns for the specified object if they exist
SET_PARAMETER Procedure on page 15-45	Sets an apply parameter to the specified value
SET_SCHEMA_INSTANTIATION_SCN Procedure on page 15-49	Records the specified instantiation SCN for the specified schema in the specified source database and, optionally, for the tables owned by the schema at the source database
SET_TABLE_INSTANTIATION_SCN Procedure on page 15-52	Records the specified instantiation SCN for the specified table in the specified source database
SET_UPDATE_CONFLICT_HANDLER Procedure on page 15-54	Adds, updates, or drops an update conflict handler for the specified object
START_APPLY Procedure on page 15-58	Directs the apply process to start applying events
STOP_APPLY Procedure on page 15-59	Stops the apply process from applying any events and rolls back any unfinished transactions being applied

Note: All procedures and functions commit unless specified otherwise.

ALTER_APPLY Procedure

This procedure alters an apply process.

Syntax

```
DBMS_APPLY_ADM.ALTER_APPLY(  
  apply_name           IN  VARCHAR2,  
  rule_set_name       IN  VARCHAR2  DEFAULT NULL,  
  remove_rule_set     IN  BOOLEAN   DEFAULT false,  
  message_handler     IN  VARCHAR2  DEFAULT NULL,  
  remove_message_handler IN  BOOLEAN  DEFAULT false,  
  ddl_handler         IN  VARCHAR2  DEFAULT NULL,  
  remove_ddl_handler  IN  BOOLEAN   DEFAULT false,  
  apply_user          IN  VARCHAR2  DEFAULT NULL,  
  apply_tag           IN  RAW        DEFAULT NULL,  
  remove_apply_tag    IN  BOOLEAN   DEFAULT false,  
  precommit_handler   IN  VARCHAR2  DEFAULT NULL,  
  remove_precommit_handler IN  BOOLEAN  DEFAULT false,  
  negative_rule_set_name IN  VARCHAR2  DEFAULT NULL,  
  remove_negative_rule_set IN  BOOLEAN  DEFAULT false);
```

Parameters

Table 15–2 ALTER_APPLY Procedure Parameters

Parameter	Description
apply_name	The name of the apply process being altered. You must specify an existing apply process name. Do not specify an owner.

Table 15–2 ALTER_APPLY Procedure Parameters (Cont.)

Parameter	Description
rule_set_name	<p>The name of the positive rule set for the apply process. The positive rule set contains the rules that instruct the apply process to apply events.</p> <p>If you want to use a positive rule set for the apply process, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a positive rule set in the <code>hr</code> schema named <code>job_apply_rules</code>, enter <code>hr.job_apply_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code> and the <code>remove_rule_set</code> parameter is set to <code>false</code>, then retains any existing positive rule set. If you specify <code>NULL</code> and the <code>remove_rule_set</code> parameter is set to <code>true</code>, then removes any existing positive rule set.</p>
remove_rule_set	<p>If <code>true</code>, then removes the positive rule set for the specified apply process. If you remove the positive rule set for an apply process, and the apply process does not have a negative rule set, then the apply process dequeues all events in its queue.</p> <p>If you remove the positive rule set for an apply process, and a negative rule set exists for the apply process, then the apply process dequeues all events in its queue that are not discarded by the negative rule set.</p> <p>If <code>false</code>, then retains the positive rule set for the specified apply process.</p> <p>If the <code>rule_set_name</code> parameter is non-<code>NULL</code>, then this parameter should be set to <code>false</code>.</p>

Table 15–2 ALTER_APPLY Procedure Parameters (Cont.)

Parameter	Description
<code>message_handler</code>	<p>A user-defined procedure that processes non-LCR messages in the queue for the apply process. You must specify an existing procedure in one of the following forms:</p> <ul style="list-style-type: none"> ■ <code>[schema_name .] procedure_name</code> ■ <code>[schema_name .] package_name . procedure_name</code> <p>If the procedure is in a package, then the <code>package_name</code> must be specified. For example, to specify a procedure in the <code>apply_pkg</code> package in the <code>hr</code> schema named <code>process_msgs</code>, enter <code>hr.apply_pkg.process_msgs</code>. An error is returned if the specified procedure does not exist.</p> <p>The user who invokes the <code>ALTER_APPLY</code> procedure must have <code>EXECUTE</code> privilege on a specified message handler. Also, if the <code>schema_name</code> is not specified, then the user who invokes the <code>ALTER_APPLY</code> procedure is the default.</p>
<code>remove_message_handler</code>	<p>If <code>true</code>, then removes the message handler for the specified apply process.</p> <p>If <code>false</code>, then retains any message handler for the specified apply process.</p> <p>If the <code>message_handler</code> parameter is non-NULL, then this parameter should be set to <code>false</code>.</p>
<code>ddl_handler</code>	<p>A user-defined procedure that processes DDL LCRs in the queue for the apply process. You must specify an existing procedure in the form <code>[schema_name .] procedure_name</code>. For example, to specify a procedure in the <code>hr</code> schema named <code>process_ddls</code>, enter <code>hr.process_ddls</code>. An error is returned if the specified procedure does not exist.</p> <p>The user who invokes the <code>ALTER_APPLY</code> procedure must have <code>EXECUTE</code> privilege on a specified DDL handler. Also, if the <code>schema_name</code> is not specified, then the user who invokes the <code>ALTER_APPLY</code> procedure is the default.</p> <p>All applied DDL LCRs commit automatically. Therefore, if a DDL handler calls the <code>EXECUTE</code> member procedure of a DDL LCR, then a commit is performed automatically.</p>

Table 15–2 ALTER_APPLY Procedure Parameters (Cont.)

Parameter	Description
<code>remove_ddl_handler</code>	<p>If <code>true</code>, then removes the DDL handler for the specified apply process.</p> <p>If <code>false</code>, then retains any DDL handler for the specified apply process.</p> <p>If the <code>ddl_handler</code> parameter is non-NULL, then this parameter should be set to <code>false</code>.</p>
<code>apply_user</code>	<p>The user who applies all DML and DDL changes that satisfy the apply process rule sets and who runs user-defined apply handlers. If NULL, then the apply user is not changed.</p> <p>To change the apply user, the user who invokes the <code>ALTER_APPLY</code> procedure must be granted DBA role. Only the SYS user can set the <code>apply_user</code> to SYS.</p> <p>If you change the apply user, then this procedure grants the new apply user dequeue privilege on the queue used by the apply process and configures the user as a secure queue user of the queue. In addition, make sure the apply user has the following privileges:</p> <ul style="list-style-type: none"> ▪ Execute privilege on the rule sets used by the apply process ▪ Execute privilege on all rule-based transformation functions used in the rule set ▪ Execute privilege on all apply handler procedures ▪ Execute privilege on all packages, including Oracle-supplied packages, that are invoked in subprograms run by the apply process <p>These privileges must be granted directly to the apply user. They cannot be granted through roles.</p> <p>By default, this parameter is set to the user who created the apply process by running either the <code>CREATE_APPLY</code> procedure in this package or one of the following procedures in the <code>DBMS_STREAMS_ADM</code> package with the <code>streams_type</code> parameter set to <code>apply</code>: <code>ADD_GLOBAL_RULES</code>, <code>ADD_SCHEMA_RULES</code>, <code>ADD_TABLE_RULES</code>, and <code>ADD_SUBSET_RULES</code>.</p> <p>Note: If the specified user is dropped using <code>DROP USER . . . CASCADE</code>, then the <code>apply_user</code> for the apply process is set to NULL automatically. You must specify an apply user before the apply process can run.</p>

Table 15–2 ALTER_APPLY Procedure Parameters (Cont.)

Parameter	Description
apply_tag	<p>A binary tag that is added to redo entries generated by the specified apply process. The tag is a binary value that can be used to track LCRs.</p> <p>The tag is relevant only if a capture process at the database where the apply process is running will capture changes made by the apply process. If so, then the captured changes will include the tag specified by this parameter.</p> <p>If <code>NULL</code>, the default, then the apply tag for the apply process is not changed.</p> <p>The following is an example of a tag with a hexadecimal value of 17:</p> <pre>HEXTORAW('17')</pre>
remove_apply_tag	<p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p> <p>If <code>true</code>, then sets the apply tag for the specified apply process to <code>NULL</code>, and the apply process generates redo entries with <code>NULL</code> tags.</p> <p>If <code>false</code>, then retains any apply tag for the specified apply process.</p> <p>If the <code>apply_tag</code> parameter is non-<code>NULL</code>, then this parameter should be set to <code>false</code>.</p>

Table 15–2 ALTER_APPLY Procedure Parameters (Cont.)

Parameter	Description
<code>precommit_handler</code>	<p>A user-defined procedure that can receive internal commit directives in the queue for the apply process before they are processed by the apply process. Typically, precommit handlers are used for auditing commit information for transactions processed by an apply process.</p> <p>An internal commit directive is enqueued into a queue when a capture process captures the commit directive for a transaction that contains row LCRs that were captured, and when a user or application enqueues messages into a queue and then issues a <code>COMMIT</code> statement. For a captured row LCR, a commit directive contains the commit SCN of the transaction from the source database, but for a user-enqueued event, the commit SCN is generated by the apply process.</p> <p>You must specify an existing procedure in the form <code>[schema_name.]procedure_name</code>. For example, to specify a procedure in the <code>hr</code> schema named <code>process_commits</code>, enter <code>hr.process_commits</code>. An error is returned if the specified procedure does not exist.</p> <p>The user who invokes the <code>ALTER_APPLY</code> procedure must have <code>EXECUTE</code> privilege on a specified precommit handler. Also, if the <code>schema_name</code> is not specified, then the user who invokes the <code>ALTER_APPLY</code> procedure is the default.</p> <p>The precommit handler procedure must conform to the following restrictions:</p> <ul style="list-style-type: none"> ■ Any work that commits must be an autonomous transaction. ■ Any rollback must be to a named savepoint created in the procedure. <p>If a precommit handler raises an exception, then the entire apply transaction is rolled back, and all of the events in the transaction are moved to the error queue.</p>
<code>remove_precommit_handler</code>	<p>If <code>true</code>, then removes the precommit handler for the specified apply process.</p> <p>If <code>false</code>, then retains any precommit handler for the specified apply process.</p> <p>If the <code>precommit_handler</code> parameter is non-NULL, then this parameter should be set to <code>false</code>.</p>

Table 15–2 ALTER_APPLY Procedure Parameters (Cont.)

Parameter	Description
<code>negative_rule_set_name</code>	<p>The name of the negative rule set for the apply process. The negative rule set contains the rules that instruct the apply process to discard events.</p> <p>If you want to use a negative rule set for the apply process, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a negative rule set in the <code>hr</code> schema named <code>neg_apply_rules</code>, enter <code>hr.neg_apply_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code> and the <code>remove_negative_rule_set</code> parameter is set to <code>false</code>, then retains any existing negative rule set. If you specify <code>NULL</code> and the <code>remove_negative_rule_set</code> parameter is set to <code>true</code>, then removes any existing negative rule set.</p> <p>If you specify both a positive and a negative rule set for an apply process, then the negative rule set is always evaluated first.</p>
<code>remove_negative_rule_set</code>	<p>If <code>true</code>, then removes the negative rule set for the specified apply process. If you remove the negative rule set for an apply process, and the apply process does not have a positive rule set, then the apply process dequeues all events in its queue.</p> <p>If you remove the negative rule set for an apply process, and a positive rule set exists for the apply process, then the apply process dequeues all events in its queue that are not discarded by the positive rule set.</p> <p>If <code>false</code>, then retains the negative rule set for the specified apply process.</p> <p>If the <code>negative_rule_set_name</code> parameter is non-<code>NULL</code>, then this parameter should be set to <code>false</code>.</p>

Usage Notes

An apply process is stopped and restarted automatically when you change the value of one or more of the following `ALTER_APPLY` procedure parameters:

- message_handler
- ddl_handler
- apply_user
- apply_tag
- precommit_handler

COMPARE_OLD_VALUES Procedure

This procedure specifies whether to compare the old value of one or more columns in a row LCR with the current value of the corresponding columns at the destination site during apply. This procedure is relevant only for UPDATE and DELETE operations because only these operations result in old column values in row LCRs. The default is to compare old values for all columns.

See Also: *Oracle Streams Replication Administrator's Guide* for more information about conflict detection and resolution in a Streams environment

Syntax

```
DBMS_APPLY_ADM.COMPARE_OLD_VALUES(
  object_name          IN VARCHAR2,
  { column_list        IN VARCHAR2,
  | column_table        IN DBMS_UTILITY.LNAME_ARRAY, }
  operation            IN VARCHAR2 DEFAULT 'UPDATE',
  compare              IN BOOLEAN  DEFAULT true,
  apply_database_link IN VARCHAR2 DEFAULT NULL);
```

Note: This procedure is overloaded. The `column_list` and `column_table` parameters are mutually exclusive.

Parameters

Table 15–3 COMPARE_OLD_VALUES Procedure Parameters

Parameter	Description
<code>object_name</code>	The name of the source table specified as [<i>schema_name</i> .] <i>object_name</i> . For example, <code>hr.employees</code> . If the schema is not specified, then the current user is the default.
<code>column_list</code>	A comma-delimited list of the columns in the table. There must be no spaces between entries. Specify <code>*</code> to include all nonkey columns.

Table 15–3 COMPARE_OLD_VALUES Procedure Parameters

Parameter	Description
<code>column_table</code>	Instead of a list, you can use a PL/SQL index-by table of type <code>DBMS_UTILITY.LNAME_ARRAY</code> to contain the column names. The first column name should be at position 1, the second at position 2, and so on. The table does not need to be <code>NULL</code> terminated.
<code>operation</code>	The name of the operation, which can be specified as: <ul style="list-style-type: none"> ■ <code>UPDATE</code> for <code>UPDATE</code> operations ■ <code>DELETE</code> for <code>DELETE</code> operations ■ <code>*</code> for both <code>UPDATE</code> and <code>DELETE</code> operations
<code>compare</code>	If <code>compare</code> is <code>true</code> , the old values of the specified columns are compared during apply. If <code>compare</code> is <code>false</code> , the old values of the specified columns are not compared during apply.
<code>apply_database_link</code>	The name of the database link to a non-Oracle database. This parameter should be set only when the destination database is a non-Oracle database.

Usage Notes

By default, an apply process uses the old column values in a row LCR to detect conflicts. You may choose not to compare old column values to avoid conflict detection for specific tables. For example, if you use a time column for conflict detection, then an apply process does not need to check old values for nonkey and non time columns.

Note: An apply process always compares old values for key columns when they are present in a row LCR. This procedure raises an error if a key column is specified and the `compare` parameter is set to `false`.

CREATE_APPLY Procedure

This procedure creates an apply process.

Syntax

```
DBMS_APPLY_ADM.CREATE_APPLY(
    queue_name          IN  VARCHAR2,
    apply_name          IN  VARCHAR2,
    rule_set_name       IN  VARCHAR2  DEFAULT NULL,
    message_handler     IN  VARCHAR2  DEFAULT NULL,
    ddl_handler         IN  VARCHAR2  DEFAULT NULL,
    apply_user          IN  VARCHAR2  DEFAULT NULL,
    apply_database_link IN  VARCHAR2  DEFAULT NULL,
    apply_tag           IN  RAW        DEFAULT '00',
    apply_captured      IN  BOOLEAN   DEFAULT false,
    precommit_handler  IN  VARCHAR2  DEFAULT NULL,
    negative_rule_set_name IN VARCHAR2  DEFAULT NULL,
    source_database     IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 15–4 CREATE_APPLY Procedure Parameters

Parameter	Description
queue_name	The name of the queue from which the apply process dequeues LCRs and user messages. You must specify an existing queue in the form [<i>schema_name</i> .] <i>queue_name</i> . For example, to specify a queue in the hr schema named streams_queue, enter hr.streams_queue. If the schema is not specified, then the current user is the default. Note: The queue_name setting cannot be altered after the apply process is created.
apply_name	The name of the apply process being created. A NULL specification is not allowed. Do not specify an owner. The specified name must not match the name of an existing apply process or messaging client. Note: The apply_name setting cannot be altered after the apply process is created.

Table 15–4 CREATE_APPLY Procedure Parameters (Cont.)

Parameter	Description
<code>rule_set_name</code>	<p>The name of the positive rule set for the apply process. The positive rule set contains the rules that instruct the apply process to apply events.</p> <p>If you want to use a positive rule set for the apply process, then you must specify an existing rule set in the form <code>[schema_name .] rule_set_name</code>. For example, to specify a positive rule set in the <code>hr</code> schema named <code>job_apply_rules</code>, enter <code>hr . job_apply_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>If you specify <code>NULL</code>, and no negative rule set is specified, then the apply process applies either all captured events or all user-enqueued events in the queue, depending on the setting of the <code>apply_captured</code> parameter.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p>
<code>message_handler</code>	<p>A user-defined procedure that processes non-LCR messages in the queue for the apply process. You must specify an existing procedure in one of the following forms:</p> <ul style="list-style-type: none"> ▪ <code>[schema_name .] procedure_name</code> ▪ <code>[schema_name .] package_name . procedure_name</code> <p>If the procedure is in a package, then the <code>package_name</code> must be specified. For example, to specify a procedure in the <code>apply_pkg</code> package in the <code>hr</code> schema named <code>process_msgs</code>, enter <code>hr . apply_pkg . process_msgs</code>. An error is returned if the specified procedure does not exist.</p> <p>The user who invokes the <code>CREATE_APPLY</code> procedure must have <code>EXECUTE</code> privilege on a specified message handler. Also, if the <code>schema_name</code> is not specified, then the user who invokes the <code>CREATE_APPLY</code> procedure is the default.</p> <p>See "Usage Notes" on page 15-20 for more information about a message handler procedure.</p>

Table 15–4 CREATE_APPLY Procedure Parameters (Cont.)

Parameter	Description
ddl_handler	<p>A user-defined procedure that processes DDL LCRs in the queue for the apply process. You must specify an existing procedure in one of the following forms:</p> <ul style="list-style-type: none"> ■ [<i>schema_name</i> .] <i>procedure_name</i> ■ [<i>schema_name</i> .] <i>package_name</i> . <i>procedure_name</i> <p>If the procedure is in a package, then the <i>package_name</i> must be specified. For example, to specify a procedure in the <i>apply_pkg</i> package in the <i>hr</i> schema named <i>process_ddls</i>, enter <i>hr.apply_pkg.process_ddls</i>. An error is returned if the specified procedure does not exist.</p> <p>The user who invokes the <code>CREATE_APPLY</code> procedure must have <code>EXECUTE</code> privilege on a specified DDL handler. Also, if the <i>schema_name</i> is not specified, then the user who invokes the <code>CREATE_APPLY</code> procedure is the default.</p> <p>All applied DDL LCRs commit automatically. Therefore, if a DDL handler calls the <code>EXECUTE</code> member procedure of a DDL LCR, then a commit is performed automatically.</p> <p>See "Usage Notes" on page 15-20 for more information about a DDL handler procedure.</p>
apply_user	<p>The user who applies all DML and DDL changes that satisfy the apply process rule sets and who runs user-defined apply handlers. If <code>NULL</code>, then the user who runs the <code>CREATE_APPLY</code> procedure is used.</p> <p>Only a user who is granted <code>DBA</code> role can set an apply user. Only the <code>SYS</code> user can set the <code>apply_user</code> to <code>SYS</code>.</p> <p>Note: If the specified user is dropped using <code>DROP USER . . . CASCADE</code>, then the <code>apply_user</code> setting for the apply process is set to <code>NULL</code> automatically. You must specify an apply user before the apply process can run.</p>
apply_database_link	<p>The database at which the apply process applies messages. This parameter is used by an apply process when applying changes from Oracle to non-Oracle systems, such as Sybase. Set this parameter to <code>NULL</code> to specify that the apply process applies messages at the local database.</p> <p>Note: The <code>apply_database_link</code> setting cannot be altered after the apply process is created.</p>

Table 15–4 CREATE_APPLY Procedure Parameters (Cont.)

Parameter	Description
apply_tag	<p>A binary tag that is added to redo entries generated by the specified apply process. The tag is a binary value that can be used to track LCRs.</p> <p>The tag is relevant only if a capture process at the database where the apply process is running will capture changes made by the apply process. If so, then the captured changes will include the tag specified by this parameter.</p> <p>By default, the tag for an apply process is the hexadecimal equivalent of '00' (double zero).</p> <p>The following is an example of a tag with a hexadecimal value of 17:</p> <pre data-bbox="729 652 896 673">HEXTORAW('17')</pre> <p>If NULL, then the apply process generates redo entries with NULL tags.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>
apply_captured	<p>Either true or false.</p> <p>If true, then the apply process applies only the events in a queue that were captured by a Streams capture process.</p> <p>If false, then the apply process applies only the user-enqueued events in a queue. These events are user messages that were not captured by a Streams capture process. These messages may or may not contain a user-created LCR.</p> <p>To apply both captured and user-enqueued events in a queue, you must create at least two apply processes.</p> <p>Note: The apply_captured setting cannot be altered after the apply process is created.</p> <p>See Also: <i>Oracle Streams Concepts and Administration</i> for more information about processing captured or user-enqueued events with an apply process</p>

Table 15–4 CREATE_APPLY Procedure Parameters (Cont.)

Parameter	Description
<code>precommit_handler</code>	<p>A user-defined procedure that can receive internal commit directives in the queue for the apply process before they are processed by the apply process. Typically, precommit handlers are used for auditing commit information for transactions processed by an apply process.</p> <p>An internal commit directive is enqueued into a queue when a capture process captures the commit directive for a transaction that contains row LCRs that were captured, and when a user or application enqueues messages into a queue and then issues a <code>COMMIT</code> statement. For a captured row LCR, a commit directive contains the commit SCN of the transaction from the source database, but for a user-enqueued event, the commit SCN is generated by the apply process.</p> <p>You must specify an existing procedure in one of the following forms:</p> <ul style="list-style-type: none"> ■ <code>[schema_name.]procedure_name</code> ■ <code>[schema_name.]package_name.procedure_name</code> <p>If the procedure is in a package, then the <code>package_name</code> must be specified. For example, to specify a procedure in the <code>apply_pkg</code> package in the <code>hr</code> schema named <code>process_commits</code>, enter <code>hr.apply_pkg.process_commits</code>. An error is returned if the specified procedure does not exist.</p> <p>The user who invokes the <code>CREATE_APPLY</code> procedure must have <code>EXECUTE</code> privilege on a specified precommit handler. Also, if the <code>schema_name</code> is not specified, then the user who invokes the <code>CREATE_APPLY</code> procedure is the default.</p> <p>If a precommit handler raises an exception, then the entire apply transaction is rolled back, and all of the events in the transaction are moved to the error queue.</p> <p>The precommit handler procedure must conform to the following restrictions:</p> <ul style="list-style-type: none"> ■ Any work that commits must be an autonomous transaction. ■ Any rollback must be to a named savepoint created in the procedure. <p>See "Usage Notes" on page 15-20 for more information about a precommit handler procedure.</p>

Table 15–4 CREATE_APPLY Procedure Parameters (Cont.)

Parameter	Description
negative_rule_set_name	<p>The name of the negative rule set for the apply process. The negative rule set contains the rules that instruct the apply process to discard events.</p> <p>If you want to use a negative rule set for the apply process, then you must specify an existing rule set in the form <code>[schema_name .] rule_set_name</code>. For example, to specify a negative rule set in the <code>hr</code> schema named <code>neg_apply_rules</code>, enter <code>hr.neg_apply_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>If you specify <code>NULL</code>, and no positive rule set is specified, then the apply process applies either all captured events or all user-enqueued events in the queue, depending on the setting of the <code>apply_captured</code> parameter.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify both a positive and a negative rule set for an apply process, then the negative rule set is always evaluated first.</p>
source_database	<p>The global name of the source database of the changes that will be applied by the apply process. The source database is the database where the changes originated. If an apply process applies captured events, then the apply process can apply events from only one capture process at one source database.</p> <p>If <code>NULL</code>, then the source database name of the first LCR received by the apply process is used for the source database.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p> <p>The rules in the apply process rule sets determine which events are dequeued by the apply process. If the apply process dequeues an LCR with a source database that is different than the source database for the apply process, then an error is raised. You can determine the source database for an apply process by querying the <code>DBA_APPLY_PROGRESS</code> data dictionary view.</p>

Usage Notes

The user who invokes this procedure must be granted DBA role.

The `apply_user` parameter specifies the user who applies changes that satisfy the apply process rule sets and who runs user-defined apply handlers. This user must have the necessary privileges to apply changes. This procedure grants the apply user dequeue privilege on the queue used by the apply process and configures the user as a secure queue user of the queue.

In addition, make sure the apply user has the following privileges:

- The necessary privileges to perform DML and DDL changes on the apply objects
- Execute privilege on the rule sets used by the apply process
- Execute privilege on all rule-based transformation functions used in the rule set
- Execute privilege on all apply handler procedures
- Execute privilege on all packages, including Oracle-supplied packages, that are invoked in subprograms run by the apply process

These privileges must be granted directly to the apply user. They cannot be granted through roles.

The following sections describe the PL/SQL procedures that are specified as message handlers, DDL handlers, and precommit handlers.

Message Handler and DDL Handler Procedure

The procedure specified in both the `message_handler` parameter and the `ddl_handler` parameter must have the following signature:

```
PROCEDURE handler_procedure (  
    parameter_name IN SYS.AnyData);
```

Here, *handler_procedure* stands for the name of the procedure and *parameter_name* stands for the name of the parameter passed to the procedure. For the message handler, the parameter passed to the procedure is a `SYS.AnyData` encapsulation of a user message. For the DDL handler procedure, the parameter passed to the procedure is a `SYS.AnyData` encapsulation of a DDL LCR.

See Also: [Chapter 174, "Logical Change Record TYPES"](#) for information about DDL LCRs

Precommit Handler Procedure

The procedure specified in the `precommit_handler` parameter must have the following signature:

```
PROCEDURE handler_procedure (  
    parameter_name IN NUMBER);
```

Here, *handler_procedure* stands for the name of the procedure and *parameter_name* stands for the name of the parameter passed to the procedure. The parameter passed to the procedure is the commit SCN of a commit directive.

DELETE_ALL_ERRORS Procedure

This procedure deletes all the error transactions for the specified apply process.

Syntax

```
DBMS_APPLY_ADM.DELETE_ALL_ERRORS(  
    apply_name IN VARCHAR2 DEFAULT NULL);
```

Parameter

Table 15-5 *DELETE_ALL_ERRORS Procedure Parameter*

Parameter	Description
apply_name	The name of the apply process that raised the errors while processing the transactions. Do not specify an owner. If <code>NULL</code> , then all error transactions for all apply processes are deleted.

DELETE_ERROR Procedure

This procedure deletes the specified error transaction.

Syntax

```
DBMS_APPLY_ADM.DELETE_ERROR(  
    local_transaction_id IN VARCHAR2);
```

Parameter

Table 15–6 *DELETE_ERROR Procedure Parameter*

Parameter	Description
local_transaction_id	The identification number of the error transaction to delete. If the specified transaction does not exist in the error queue, then an error is raised.

DROP_APPLY Procedure

This procedure drops an apply process.

Syntax

```
DBMS_APPLY_ADM.DROP_APPLY(  
    apply_name          IN VARCHAR2,  
    drop_unused_rule_sets IN BOOLEAN DEFAULT false);
```

Parameters

Table 15–7 *DROP_APPLY Procedure Parameters*

Parameter	Description
<code>apply_name</code>	The name of the apply process being dropped. You must specify an existing apply process name. Do not specify an owner.
<code>drop_unused_rule_sets</code>	If <code>true</code> , then drops any rule sets, positive and negative, used by the specified apply process if these rule sets are not used by any other Streams client, which includes capture processes, propagations, apply processes, and messaging clients. If this procedure drops a rule set, then this procedure also drops any rules in the rule set that are not in another rule set. If <code>false</code> , then does not drop the rule sets used by the specified apply process, and the rule sets retain their rules.

Usage Notes

When you use this procedure to drop an apply process, information about rules created for the apply process using the `DBMS_STREAMS_ADM` package is removed from the data dictionary views for Streams rules. Information about such a rule is removed even if the rule is not in either rule set for the apply process. The following are the data dictionary views for Streams rules:

- `ALL_STREAMS_GLOBAL_RULES`
- `DBA_STREAMS_GLOBAL_RULES`
- `ALL_STREAMS_MESSAGE_RULES`
- `DBA_STREAMS_MESSAGE_RULES`

- ALL_STREAMS_SCHEMA_RULES
- DBA_STREAMS_SCHEMA_RULES
- ALL_STREAMS_TABLE_RULES
- DBA_STREAMS_TABLE_RULES

See Also: *Oracle Streams Concepts and Administration* for more information about Streams data dictionary views

EXECUTE_ALL_ERRORS Procedure

This procedure reexecutes the error transactions for the specified apply process.

The transactions are reexecuted in commit SCN order. Error reexecution stops if an error is raised.

Syntax

```
DBMS_APPLY_ADM.EXECUTE_ALL_ERRORS(  
    apply_name      IN VARCHAR2 DEFAULT NULL,  
    execute_as_user IN BOOLEAN  DEFAULT false);
```

Parameters

Table 15–8 EXECUTE_ALL_ERRORS Procedure Parameters

Parameter	Description
<code>apply_name</code>	The name of the apply process that raised the errors while processing the transactions. Do not specify an owner. If <code>NULL</code> , then all error transactions for all apply processes are reexecuted.
<code>execute_as_user</code>	If <code>true</code> , then reexecutes the transactions in the security context of the current user. If <code>false</code> , then reexecutes each transaction in the security context of the original receiver of the transaction. The original receiver is the user who was processing the transaction when the error was raised. The <code>DBA_APPLY_ERROR</code> data dictionary view lists the original receiver for each error transaction. The user who executes the transactions must have privileges to perform DML and DDL changes on the apply objects and to run any apply handlers. This user must also have dequeue privileges on the queue used by the apply process.

EXECUTE_ERROR Procedure

This procedure reexecutes the specified error transaction.

Syntax

```
DBMS_APPLY_ADM.EXECUTE_ERROR(
    local_transaction_id IN VARCHAR2,
    execute_as_user      IN BOOLEAN  DEFAULT false);
```

Parameters

Table 15–9 EXECUTE_ERROR Procedure Parameters

Parameter	Description
local_transaction_id	The identification number of the error transaction to execute. If the specified transaction does not exist in the error queue, then an error is raised.
execute_as_user	If <code>true</code> , then reexecutes the transaction in the security context of the current user. If <code>false</code> , then reexecutes the transaction in the security context of the original receiver of the transaction. The original receiver is the user who was processing the transaction when the error was raised. The <code>DBA_APPLY_ERROR</code> data dictionary view lists the original receiver for each error transaction. The user who executes the transaction must have privileges to perform DML and DDL changes on the apply objects and to run any apply handlers. This user must also have dequeue privileges on the queue used by the apply process.

GET_ERROR_MESSAGE Functions

This function returns the message payload from the error queue for the specified message number and transaction identifier. The message is an event, which may be a logical change record (LCR) or a non-LCR event.

One version of this function contains two OUT parameters. These OUT parameters contain the destination queue into which the event should be enqueued, if one exists, and whether or not the event should be executed. The destination queue is specified using the `SET_ENQUEUE_DESTINATION` procedure, and the execution directive is specified using the `SET_EXECUTE` procedure.

See Also:

- ["SET_ENQUEUE_DESTINATION Procedure"](#) on page 15-36
- ["SET_EXECUTE Procedure"](#) on page 15-38

Syntax

```
DBMS_APPLY_ADM.GET_ERROR_MESSAGE(  
    message_number      IN    NUMBER,  
    local_transaction_id IN  VARCHAR2,  
    destination_queue_name OUT VARCHAR2,  
    execute              OUT  BOOLEAN)  
RETURN SYS.AnyData;
```

Note: This function is overloaded. One version of this function contains two OUT parameters, and the other does not.

Parameters

Table 15–10 *GET_ERROR_MESSAGE Function Parameters*

Parameter	Description
<code>message_number</code>	The identification number of the message. This number identifies the position of the message in the transaction. Query the <code>DBA_APPLY_ERROR</code> data dictionary view to view the message number of each apply error.
<code>local_transaction_id</code>	Identifier of the error transaction for which to return a message

Table 15–10 *GET_ERROR_MESSAGE Function Parameters*

Parameter	Description
<code>destination_queue_name</code>	Contains the name of the queue into which the message should be enqueued. If the message should not be enqueued into a queue, then contains <code>NULL</code> .
<code>execute</code>	Contains <code>true</code> if the message should be executed Contains <code>false</code> if the message should not be executed

SET_DML_HANDLER Procedure

This procedure sets a user procedure as a DML handler for a specified operation on a specified object. The user procedure alters the apply behavior for the specified operation on the specified object.

Syntax

```
DBMS_APPLY_ADM.SET_DML_HANDLER(  
    object_name      IN  VARCHAR2,  
    object_type      IN  VARCHAR2,  
    operation_name   IN  VARCHAR2,  
    error_handler    IN  BOOLEAN  DEFAULT false,  
    user_procedure   IN  VARCHAR2,  
    apply_database_link IN  VARCHAR2  DEFAULT NULL,  
    apply_name       IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 15–11 SET_DML_HANDLER Procedure Parameters

Parameter	Description
object_name	The name of the source object specified as [<i>schema_name</i> .] <i>object_name</i> . For example, hr.employees. If the schema is not specified, then the current user is the default. The specified object does not need to exist in the local destination database when you run this procedure.
object_type	The type of the source object. Currently, TABLE is the only possible source object type.

Table 15–11 SET_DML_HANDLER Procedure Parameters (Cont.)

Parameter	Description
<code>operation_name</code>	<p>The name of the operation, which can be specified as:</p> <ul style="list-style-type: none"> ■ INSERT ■ UPDATE ■ DELETE ■ LOB_UPDATE <p>For example, suppose you run this procedure twice for the <code>hr.employees</code> table. In one call, you set <code>operation_name</code> to <code>UPDATE</code> and <code>user_procedure</code> to <code>employees_update</code>. In another call, you set <code>operation_name</code> to <code>INSERT</code> and <code>user_procedure</code> to <code>employees_insert</code>. Both times, you set <code>error_handler</code> to <code>false</code>.</p> <p>In this case, the <code>employees_update</code> procedure is run for <code>UPDATE</code> operations on the <code>hr.employees</code> table, and the <code>employees_insert</code> procedure is run for <code>INSERT</code> operations on the <code>hr.employees</code> table.</p>
<code>error_handler</code>	<p>If <code>true</code>, then the specified user procedure is run when a row LCR involving the specified operation on the specified object raises an apply process error. The user procedure may try to resolve possible error conditions, or it may simply notify administrators of the error or log the error.</p> <p>If <code>false</code>, then the handler being set is run for all row LCRs involving the specified operation on the specified object.</p> <p>Note: Currently, error handlers are not supported when applying changes to a non-Oracle database.</p>
<code>user_procedure</code>	<p>A user-defined procedure that is invoked during apply for the specified operation on the specified object. If the procedure is a DML handler, then it is invoked instead of the default apply performed by Oracle. If the procedure is an error handler, then it is invoked when the apply process encounters an error.</p> <p>Specify <code>NULL</code> to unset a DML handler that is set for the specified operation on the specified object.</p>
<code>apply_database_link</code>	<p>The name of the database link to a non-Oracle database. This parameter should be set only when the destination database is a non-Oracle database.</p>

Table 15–11 SET_DML_HANDLER Procedure Parameters (Cont.)

Parameter	Description
<code>apply_name</code>	<p>The name of the apply process that uses the DML handler or error handler.</p> <p>If <code>NULL</code>, then sets the DML handler or error handler as a general handler for all apply processes in the database.</p> <p>If the <code>user_procedure</code> parameter is set to <code>NULL</code> to unset a handler, and the handler being unset is set for a specific apply process, then use the <code>apply_name</code> parameter to specify the apply process to unset the handler.</p>

Usage Notes

Run this procedure at the destination database. The `SET_DML_HANDLER` procedure provides a way for users to apply logical change records containing DML changes (row LCRs) using a customized apply.

If the `error_handler` parameter is set to `true`, then it specifies that the user procedure is an error handler. An error handler is invoked only when a row LCR raises an apply process error. Such an error may result from a data conflict if no conflict handler is specified or if the update conflict handler cannot resolve the conflict. If the `error_handler` parameter is set to `false`, then the user procedure is a DML handler, not an error handler, and a DML handler is always run instead of performing the specified operation on the specified object.

This procedure either sets a DML handler or an error handler for a particular operation on an object. It cannot set both a DML handler and an error handler for the same object and operation.

If the `apply_name` parameter is non-`NULL`, then the DML handler or error handler is set for the specified apply process. In this case, this handler is not invoked for other apply processes at the local destination database. If the `apply_name` parameter is `NULL`, the default, then the handler is set as a general handler for all apply processes at the destination database. When a handler is set for a specific apply process, then this handler takes precedence over any general handlers. For example, consider the following scenario:

- A DML handler named `handler_hr` is specified for an apply process named `apply_hr` for `UPDATE` operations on the `hr.employees` table.
- A general DML handler named `handler_gen` also exists for `UPDATE` operations on the `hr.employees` table.

In this case, the `apply_hr` apply process uses the `handler_hr` DML handler for UPDATE operations on the `hr.employees` table.

At the source database, you must specify an unconditional supplemental log group for the columns needed by a DML or error handler.

Attention: Do not modify LONG, LONG RAW or LOB column data in an LCR. This includes DML handlers, error handlers, and rule-based transformation functions.

Note: Currently, setting an error handler for an apply process that is applying changes to a non-Oracle database is not supported.

The `SET_DML_HANDLER` procedure can be used to set either a DML handler or an error handler for row LCRs that perform a specified operation on a specified object. The following sections describe the signature of a DML handler procedure and the signature of an error handler procedure.

In either case, you must specify the full procedure name for the `user_procedure` parameter in one of the following forms:

- `[schema_name.]package_name.procedure_name`
- `[schema_name.]procedure_name`

If the procedure is in a package, then the `package_name` must be specified. The user who invokes the `SET_DML_HANDLER` procedure must have EXECUTE privilege on the specified procedure. Also, if the `schema_name` is not specified, then the user who invokes the `SET_DML_HANDLER` procedure is the default.

For example, suppose the `procedure_name` has the following properties:

- `hr` is the `schema_name`.
- `apply_pkg` is the `package_name`.
- `employees_default` is the `procedure_name`.

In this case, specify the following:

```
hr.apply_pkg.employees_default
```

The following restrictions apply to the user procedure:

- Do not execute `COMMIT` or `ROLLBACK` statements. Doing so may endanger the consistency of the transaction that contains the LCR.
- If you are manipulating a row using the `EXECUTE` member procedure for the row LCR, then do not attempt to manipulate more than one row in a row operation. You must construct and execute manually any DML statements that manipulate more than one row.
- If the command type is `UPDATE` or `DELETE`, then row operations resubmitted using the `EXECUTE` member procedure for the LCR must include the entire key in the list of old values. The key is the primary key or the smallest unique index that has at least one `NOT NULL` column, unless a substitute key has been specified by the `SET_KEY_COLUMNS` procedure. If there is no specified key, then the key consists of all non `LOB`, non `LONG`, and non `LONG RAW` columns.
- If the command type is `INSERT`, then row operations resubmitted using the `EXECUTE` member procedure for the LCR should include the entire key in the list of new values. Otherwise, duplicate rows are possible. The key is the primary key or the smallest unique index that has at least one `NOT NULL` column, unless a substitute key has been specified by the `SET_KEY_COLUMNS` procedure. If there is no specified key, then the key consists of all non `LOB`, non `LONG`, and non `LONG RAW` columns.

See Also: *Oracle Streams Replication Administrator's Guide* for information about and restrictions regarding DML handlers and `LOB`, `LONG`, and `LONG RAW` datatypes

Signature of a DML Handler Procedure

The procedure specified in the `user_procedure` parameter must have the following signature:

```
PROCEDURE user_procedure (  
    parameter_name IN SYS.AnyData);
```

Here, `user_procedure` stands for the name of the procedure and `parameter_name` stands for the name of the parameter passed to the procedure. The parameter passed to the procedure is a `SYS.AnyData` encapsulation of a row LCR.

See Also: [Chapter 174, "Logical Change Record TYPES"](#) for more information about LCRs

Signature of an Error Handler Procedure

The procedure you create for error handling must have the following signature:


```
PROCEDURE user_procedure (  
    message           IN  SYS.AnyData,  
    error_stack_depth IN  NUMBER,  
    error_numbers     IN  DBMS_UTILITY.NUMBER_ARRAY,  
    error_messages    IN  emsg_array);
```

If you want to retry the DML operation within the error handler, then have the error handler procedure run the `EXECUTE` member procedure for the LCR. The last error raised is on top of the error stack. To specify the error message at the top of the error stack, use `error_numbers(1)` and `error_messages(1)`.

Note:

- Each parameter is required and must have the specified datatype. However, you can change the names of the parameters.
 - The `emsg_array` value must be a user-defined array that is a table of type `VARCHAR2` with at least 76 characters.
-
-

Running an error handler results in one of the following outcomes:

- The error handler successfully resolves the error and returns control to the apply process.
- The error handler fails to resolve the error, and the error is raised. The raised error causes the transaction to be rolled back and placed in the error queue.

SET_ENQUEUE_DESTINATION Procedure

This procedure sets the queue where an event that satisfies the specified rule is enqueued automatically by an apply process.

This procedure modifies the specified rule's action context to specify the queue. A rule action context is optional information associated with a rule that is interpreted by the client of the rules engine after the rule evaluates to `TRUE` for an event. In this case, the client of the rules engine is a Streams apply process. The information in an action context is an object of type `SYS.RE$NV_LIST`, which consists of a list of name-value pairs.

A queue destination specified by this procedure always consists of the following name-value pair in an action context:

- The name is `APPLY$_ENQUEUE`.
- The value is a `SYS.AnyData` instance containing the queue name specified as a `VARCHAR2`.

Syntax

```
DBMS_APPLY_ADM.SET_ENQUEUE_DESTINATION(
    rule_name           IN VARCHAR2,
    destination_queue_name IN VARCHAR2);
```

Parameters

Table 15–12 SET_ENQUEUE_DESTINATION Procedure Parameters

Parameter	Description
<code>rule_name</code>	The name of the rule, specified as <code>[schema_name.]rule_name</code> . For example, to specify a rule named <code>hr5</code> in the <code>hr</code> schema, enter <code>hr.hr5</code> for this parameter. If the schema is not specified, then the current user is the default.

Table 15–12 SET_ENQUEUE_DESTINATION Procedure Parameters

Parameter	Description
<code>destination_queue_name</code>	<p>The name of the queue into which the apply process should enqueue the event. Specify the queue in the form [<i>schema_name</i>.]<i>queue_name</i>. Only local queues can be specified.</p> <p>For example, to specify a queue in the <code>hr</code> schema named <code>streams_queue</code>, enter <code>hr.streams_queue</code>. If the schema is not specified, then the current user is the default.</p> <p>If <code>NULL</code>, then an existing name-value pair with the name <code>APPLY\$_ENQUEUE</code> is removed. If no name-value pair exists with the name <code>APPLY\$_ENQUEUE</code> for the rule, then no action is taken.</p> <p>If non-<code>NULL</code> and a name-value pair already exists for the rule with the name <code>APPLY\$_ENQUEUE</code>, then it is removed, and a new name-value pair with the value specified by this parameter is added.</p>

Usage Notes

If an apply handler, such as a DML handler, DDL handler, or message handler, processes an event that is also enqueued into a destination queue, then the apply handler processes the event before it is enqueued.

The following are considerations for using this procedure:

- This procedure does not verify that the specified queue exists. If the queue does not exist, then an error is raised when an apply process tries to enqueue an event into it.
- Streams capture processes, propagations, and messaging clients ignore the action context created by this procedure.
- The apply user of the apply processes using the specified rule must have the necessary privileges to enqueue events into the specified queue. If the queue is a secure queue, then the apply user must be a secure queue user of the queue.
- The specified rule must be in the positive rule set for an apply process. If the rule is in the negative rule set for an apply process, then the apply process does not enqueue the event into the destination queue.
- If the commit SCN for an event is less than or equal to the relevant instantiation SCN for the event, then the event is not enqueued into the destination queue, even if the event satisfies the apply process rule sets.

SET_EXECUTE Procedure

This procedure specifies whether an event that satisfies the specified rule is executed by an apply process.

This procedure modifies the specified rule's action context to specify event execution. A rule action context is optional information associated with a rule that is interpreted by the client of the rules engine after the rule evaluates to `TRUE` for an event. In this case, the client of the rules engine is a Streams apply process. The information in an action context is an object of type `SYS.RE$NV_LIST`, which consists of a list of name-value pairs.

An event execution directive specified by this procedure always consists of the following name-value pair in an action context:

- The name is `APPLY$_EXECUTE`.
- The value is a `SYS.AnyData` instance that contains `NO` as a `VARCHAR2`. When the value is `NO`, then an apply process does not execute the event and does not send the event to any apply handler.

Syntax

```
DBMS_APPLY_ADM.SET_EXECUTE(
  rule_name IN VARCHAR2,
  execute   IN BOOLEAN);
```

Parameters

Table 15–13 SET_EXECUTE Procedure Parameters

Parameter	Description
<code>rule_name</code>	The name of the rule, specified as <code>[schema_name .] rule_name</code> . For example, to specify a rule named <code>hr5</code> in the <code>hr</code> schema, enter <code>hr.hr5</code> for this parameter. If the schema is not specified, then the current user is the default.

Table 15–13 SET_EXECUTE Procedure Parameters

Parameter	Description
execute	<p>If <code>true</code>, then removes the name-value pair with the name <code>APPLY\$_EXECUTE</code> for the specified rule. Removing the name-value pair means that the apply process executes events that satisfy the rule. If no name-value pair with name <code>APPLY\$_EXECUTE</code> exists for the rule, then no action is taken.</p> <p>If <code>false</code>, then adds a name-value pair to the rule's action context. The name is <code>APPLY\$_EXECUTE</code> and the value is <code>NO</code>. An apply process does not execute an event that satisfies the rule and does not send the event to any apply handler. If a name-value pair already exists for the rule with the name <code>APPLY\$_EXECUTE</code>, then it is removed, and a new one with the value <code>NO</code> is added.</p> <p>If <code>NULL</code>, then an error is raised.</p>

Usage Notes

If the event is a logical change record (LCR) and the event is not executed, then the change encapsulated in the LCR is not made to the relevant local database object. Also, if the event is not executed, then it is not sent to any apply handler.

Note:

- Streams capture processes, propagations, and messaging clients ignore the action context created by this procedure.
 - The specified rule must be in the positive rule set for an apply process for the apply process to follow the execution directive. If the rule is in the negative rule set for an apply process, then the apply process ignores the execution directive for the rule.
-
-

SET_GLOBAL_INSTANTIATION_SCN Procedure

This procedure records the specified instantiation SCN for the specified source database and, optionally, for the schemas at the source database and the tables owned by these schemas. This procedure overwrites any existing instantiation SCN for the database, and, if it sets the instantiation SCN for a schema or a table, then it overwrites any existing instantiation SCN for the schema or table.

This procedure gives you precise control over which DDL LCRs from a source database are ignored and which DDL LCRs are applied by an apply process.

Syntax

```
DBMS_APPLY_ADM.SET_GLOBAL_INSTANTIATION_SCN(
  source_database_name  IN  VARCHAR2,
  instantiation_scn     IN  NUMBER,
  apply_database_link   IN  VARCHAR2  DEFAULT NULL,
  recursive             IN  BOOLEAN   DEFAULT false);
```

Parameters

Table 15-14 SET_GLOBAL_INSTANTIATION_SCN Procedure Parameters

Parameter	Description
source_database_name	The global name of the source database. For example, DBS1.NET. If you do not include the domain name, then the local domain is appended to the database name automatically. For example, if you specify DBS1 and the local domain is .NET, then DBS1.NET is specified automatically.
instantiation_scn	The instantiation SCN. Specify NULL to remove the instantiation SCN metadata for the source database from the data dictionary.
apply_database_link	The name of the database link to a non-Oracle database. This parameter should be set only when the destination database of a local apply process is a non-Oracle database.

Table 15–14 *SET_GLOBAL_INSTANTIATION_SCN Procedure Parameters (Cont.)*

Parameter	Description
<code>recursive</code>	<p>If <code>true</code>, then sets the instantiation SCN for the source database, all schemas in the source database, and all tables owned by the schemas in the source database. This procedure selects the schemas and tables from the <code>ALL_USERS</code> and <code>ALL_TABLES</code> data dictionary views, respectively, at the source database under the security context of the current user.</p> <p>If <code>false</code>, then sets the global instantiation SCN for the source database, but does not set the instantiation SCN for any schemas or tables</p> <p>Note: If <code>recursive</code> is set to <code>true</code>, then a database link from the destination database to the source database is required. This database link must have the same name as the global name of the source database and must be accessible to the current user. Also, a table must be accessible to the current user in either the <code>ALL_TABLES</code> or <code>DBA_TABLES</code> data dictionary view at the source database for this procedure to set the instantiation SCN for the table at the destination database.</p>

Usage Notes

If the commit SCN of a DDL LCR for a database object from a source database is less than or equal to the instantiation SCN for that source database at a destination database, then the apply process at the destination database disregards the DDL LCR. Otherwise, the apply process applies the DDL LCR.

The global instantiation SCN specified by this procedure is used for a DDL LCR only if the DDL LCR does not have `object_owner`, `base_table_owner`, and `base_table_name` specified. For example, the global instantiation SCN set by this procedure is used for DDL LCRs with a `command_type` of `CREATE USER`.

If the `recursive` parameter is set to `true`, then this procedure sets the instantiation SCN for each schema at a source database and for the tables owned by these schemas. This procedure uses the `SET_SCHEMA_INSTANTIATION_SCN` procedure to set the instantiation SCN for each schema, and it uses the `SET_TABLE_INSTANTIATION_SCN` procedure to set the instantiation SCN for each table. Each schema instantiation SCN is used for DDL LCRs on the schema, and each table instantiation SCN is used for DDL LCRs and row LCRs on the table.

If the `recursive` parameter is set to `false`, then this procedure does not set the instantiation SCN for any schemas or tables.

Note:

- Any instantiation SCN specified by this procedure is used only for LCRs captured by a capture process. It is not used for user-created LCRs.
 - The instantiation SCN is not set for the SYS or SYSTEM schemas.
-
-

See Also:

- ["SET_SCHEMA_INSTANTIATION_SCN Procedure"](#) on page 15-49
- ["SET_TABLE_INSTANTIATION_SCN Procedure"](#) on page 15-52
- ["LCR\\$_DDL_RECORD Type"](#) on page 174-3 for more information about DDL LCRs
- *Oracle Streams Replication Administrator's Guide*

SET_KEY_COLUMNS Procedures

This procedure records the set of columns to be used as the substitute primary key for apply purposes and removes existing substitute primary key columns for the specified object if they exist. Unlike true primary keys, these columns may contain NULLs.

Syntax

```
DBMS_APPLY_ADM.SET_KEY_COLUMNS(
  object_name          IN  VARCHAR2,
  { column_list       IN  VARCHAR2, |
    column_table      IN  DBMS_UTILITY.NAME_ARRAY, }
  apply_database_link IN  VARCHAR2  DEFAULT NULL);
```

Note: This procedure is overloaded. The `column_list` and `column_table` parameters are mutually exclusive.

Parameters

Table 15–15 *SET_KEY_COLUMNS Procedure Parameters*

Parameter	Description
<code>object_name</code>	The name of the table specified as <code>[schema_name.]object_name</code> . For example, <code>hr.employees</code> . If the schema is not specified, then the current user is the default. If the apply process is applying changes to a non-Oracle database in a heterogeneous environment, then the object name is not verified.
<code>column_list</code>	A comma-delimited list of the columns in the table that you want to use as the substitute primary key, with no spaces between the column names. If the <code>column_list</code> parameter is empty or NULL, then the current set of key columns is removed.
<code>column_table</code>	A PL/SQL index-by table of type <code>DBMS_UTILITY.NAME_ARRAY</code> of the columns in the table that you want to use as the substitute primary key. The index for <code>column_table</code> must be 1-based, increasing, dense, and terminated by a NULL. If the <code>column_table</code> parameter is empty or NULL, then the current set of key columns is removed.

Table 15–15 SET_KEY_COLUMNS Procedure Parameters

Parameter	Description
<code>apply_database_link</code>	The name of the database link to a non-Oracle database. This parameter should be set only when the destination database is a non-Oracle database.

Usage Notes

When not empty, this set of columns takes precedence over any primary key for the specified object. Do not specify substitute key columns if the object already has primary key columns and you want to use those primary key columns as the key.

Run this procedure at the destination database. At the source database, you must specify an unconditional supplemental log group for the substitute key columns.

Note:

- Oracle recommends that each column you specify as a substitute key column be a `NOT NULL` column. You should also create a single index that includes all of the columns in a substitute key. Following these guidelines improves performance for updates, deletes, and piecewise updates to LOBs because Oracle can locate the relevant row more efficiently.
 - You should not permit applications to update the primary key or substitute key columns of a table. This ensures that Oracle can identify rows and preserve the integrity of the data.
 - If there is neither a primary key, nor a unique index that has at least one `NOT NULL` column, nor a substitute key for a table, then the key consists of all non `LOB`, non `LONG`, and non `LONG RAW` columns.
-
-

SET_PARAMETER Procedure

This procedure sets an apply parameter to the specified value.

Syntax

```
DBMS_APPLY_ADM.SET_PARAMETER (  
    apply_name IN VARCHAR2,  
    parameter  IN VARCHAR2,  
    value      IN VARCHAR2);
```

Parameters

Table 15–16 *SET_PARAMETER Procedure Parameters*

Parameter	Description
apply_name	The apply process name. Do not specify an owner.
parameter	The name of the parameter you are setting. See " Apply Process Parameters " on page 15-45 for a list of these parameters.
value	The value to which the parameter is set

Apply Process Parameters

The following table lists the parameters for the apply process.

Table 15–17 Apply Process Parameters

Parameter Name	Possible Values	Default	Description
<code>commit_serialization</code>	<code>full</code> or <code>none</code>	<code>full</code>	<p>The order in which applied transactions are committed.</p> <p>If <code>full</code>, then the apply process commits applied transactions in the order in which they were committed at the source database.</p> <p>If <code>none</code>, then the apply process may commit transactions may commit in any order. Performance is best if you specify <code>none</code>.</p> <p>Regardless of the specification, applied transactions may execute in parallel subject to data dependencies and constraint dependencies.</p> <p>Logical standby environments typically specify <code>full</code>.</p>
<code>disable_on_error</code>	<code>Y</code> or <code>N</code>	<code>Y</code>	<p>If <code>Y</code>, then the apply process is disabled on the first unresolved error, even if the error is not fatal.</p> <p>If <code>N</code>, then the apply process continues regardless of unresolved errors.</p>
<code>disable_on_limit</code>	<code>Y</code> or <code>N</code>	<code>N</code>	<p>If <code>Y</code>, then the apply process is disabled if the apply process terminates because it reached a value specified by the <code>time_limit</code> parameter or <code>transaction_limit</code> parameter.</p> <p>If <code>N</code>, then the apply process is restarted immediately after stopping because it reached a limit.</p>
<code>maximum_scn</code>	A valid SCN or <code>infinite</code>	<code>infinite</code>	<p>The apply process is disabled before applying a transaction with a commit SCN greater than or equal to the value specified.</p> <p>If <code>infinite</code>, then the apply process runs regardless of the SCN value.</p>

Table 15–17 Apply Process Parameters (Cont.)

Parameter Name	Possible Values	Default	Description
parallelism	A positive integer	1	<p>The number of transactions that may be concurrently applied</p> <p>Note:</p> <ul style="list-style-type: none"> ▪ When you change the value of this parameter, the apply process is stopped and restarted automatically. This may take some time depending on the size of the transactions currently being applied. ▪ Setting the parallelism parameter to a number higher than the number of available parallel execution servers may disable the apply process. Make sure the PROCESSES and PARALLEL_MAX_SERVERS initialization parameters are set appropriately when you set the parallelism apply process parameter.
startup_seconds	0, a positive integer, or infinite	0	<p>The maximum number of seconds to wait for another instantiation of the same apply process to finish. If the other instantiation of the same apply process does not finish within this time, then the apply process does not start.</p> <p>If <i>infinite</i>, then an apply process does not start until another instantiation of the same apply process finishes.</p>
time_limit	A positive integer or infinite	<i>infinite</i>	<p>The apply process stops as soon as possible after the specified number of seconds since it started.</p> <p>If <i>infinite</i>, then the apply process continues to run until it is stopped explicitly.</p>

Table 15–17 Apply Process Parameters (Cont.)

Parameter Name	Possible Values	Default	Description
<code>trace_level</code>	0 or a positive integer	0	Set this parameter only under the guidance of Oracle Support Services.
<code>transaction_limit</code>	A positive integer or <code>infinite</code>	<code>infinite</code>	The apply process stops after applying the specified number of transactions. If <code>infinite</code> , then the apply process continues to run regardless of the number of transactions applied.
<code>write_alert_log</code>	Y or N	Y	If Y, then the apply process writes a message to the alert log on exit. If N, then the apply process does not write a message to the alert log on exit. The message specifies the reason why the apply process stopped.

Usage Notes

When you alter a parameter value, a short amount of time may pass before the new value for the parameter takes effect.

Note:

- For all parameters that are interpreted as positive integers, the maximum possible value is 4,294,967,295. Where applicable, specify `infinite` for larger values.
 - For parameters that require an SCN setting, any valid SCN value can be specified.
-
-

SET_SCHEMA_INSTANTIATION_SCN Procedure

This procedure records the specified instantiation SCN for the specified schema in the specified source database and, optionally, for the tables owned by the schema at the source database. This procedure overwrites any existing instantiation SCN for the schema, and, if it sets the instantiation SCN for a table, it overwrites any existing instantiation SCN for the table.

This procedure gives you precise control over which DDL LCRs for a schema are ignored and which DDL LCRs are applied by an apply process.

Syntax

```
DBMS_APPLY_ADM.SET_SCHEMA_INSTANTIATION_SCN(
    source_schema_name    IN  VARCHAR2,
    source_database_name  IN  VARCHAR2,
    instantiation_scn     IN  NUMBER,
    apply_database_link   IN  VARCHAR2  DEFAULT NULL,
    recursive             IN  BOOLEAN   DEFAULT false);
```

Parameters

Table 15–18 SET_SCHEMA_INSTANTIATION_SCN Procedure Parameters

Parameter	Description
source_schema_name	The name of the source schema. For example, hr.
source_database_name	The global name of the source database. For example, DBS1.NET. If you do not include the domain name, then the local is appended to the database name automatically. For example, if you specify DBS1 and the local domain is .NET, then DBS1.NET is specified automatically.
instantiation_scn	The instantiation SCN. Specify NULL to remove the instantiation SCN metadata for the source schema from the data dictionary.
apply_database_link	The name of the database link to a non-Oracle database. This parameter should be set only when the destination database of a local apply process is a non-Oracle database.

Table 15–18 SET_SCHEMA_INSTANTIATION_SCN Procedure Parameters (Cont.)

Parameter	Description
<code>recursive</code>	<p>If <code>true</code>, then sets the instantiation SCN for the specified schema and all tables owned by the schema in the source database. This procedure selects the tables owned by the specified schema from the <code>ALL_TABLES</code> data dictionary view at the source database under the security context of the current user.</p> <p>If <code>false</code>, then sets the instantiation SCN for specified schema, but does not set the instantiation SCN for any tables</p> <p>Note: If <code>recursive</code> is set to <code>true</code>, then a database link from the destination database to the source database is required. This database link must have the same name as the global name of the source database and must be accessible to the current user. Also, a table must be accessible to the current user in either the <code>ALL_TABLES</code> or <code>DBA_TABLES</code> data dictionary view at the source database for this procedure to set the instantiation SCN for the table at the destination database.</p>

Usage Notes

If the commit SCN of a DDL LCR for a database object in a schema from a source database is less than or equal to the instantiation SCN for that database object at a destination database, then the apply process at the destination database disregards the DDL LCR. Otherwise, the apply process applies the DDL LCR.

The schema instantiation SCN specified by this procedure is used on the following types of DDL LCRs:

- DDL LCRs with a `command_type` of `CREATE TABLE`
- DDL LCRs with a non-NULL `object_owner` specified and no `base_table_owner` nor `base_table_name` specified.

For example, the schema instantiation SCN set by this procedure is used for a DDL LCR with a `command_type` of `CREATE TABLE` and `ALTER USER`.

The schema instantiation SCN specified by this procedure is not used for DDL LCRs with a `command_type` of `CREATE USER`. A global instantiation SCN is needed for such DDL LCRs.

If the `recursive` parameter is set to `TRUE`, then this procedure sets the table instantiation SCN for each table at the source database owned by the schema. This procedure uses the `SET_TABLE_INSTANTIATION_SCN` procedure to set the

instantiation SCN for each table. Each table instantiation SCN is used for DDL LCRs and row LCRs on the table.

If the `recursive` parameter is set to `false`, then this procedure does not set the instantiation SCN for any tables.

Note: Any instantiation SCN specified by this procedure is used only for LCRs captured by a capture process. It is not used for user-created LCRs.

See Also:

- ["SET_GLOBAL_INSTANTIATION_SCN Procedure"](#) on page 15-40
- ["SET_TABLE_INSTANTIATION_SCN Procedure"](#) on page 15-52
- ["LCR\\$_DDL_RECORD Type"](#) on page 174-3 for more information about DDL LCRs
- *Oracle Streams Replication Administrator's Guide*

SET_TABLE_INSTANTIATION_SCN Procedure

This procedure records the specified instantiation SCN for the specified table in the specified source database. This procedure overwrites any existing instantiation SCN for the particular table.

This procedure gives you precise control over which LCRs for a table are ignored and which LCRs are applied by an apply process.

Syntax

```
DBMS_APPLY_ADM.SET_TABLE_INSTANTIATION_SCN(  
    source_object_name    IN  VARCHAR2,  
    source_database_name  IN  VARCHAR2,  
    instantiation_scn     IN  NUMBER,  
    apply_database_link   IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 15–19 SET_TABLE_INSTANTIATION_SCN Procedure Parameters

Parameter	Description
source_object_name	The name of the source object specified as [<i>schema_name</i> .] <i>object_name</i> . For example, hr.employees. If the schema is not specified, then the current user is the default.
source_database_name	The global name of the source database. For example, DBS1.NET. If you do not include the domain name, then the local domain name is appended to the database name automatically. For example, if you specify DBS1 and the global domain is .NET, then DBS1.NET is specified automatically.
instantiation_scn	The instantiation SCN. Specify NULL to remove the instantiation SCN metadata for the source table from the data dictionary.
apply_database_link	The name of the database link to a non-Oracle database. This parameter should be set only when the destination database of a local apply process is a non-Oracle database.

Usage Notes

If the commit SCN of an LCR for a table from a source database is less than or equal to the instantiation SCN for that table at some destination database, then the apply process at the destination database disregards the LCR. Otherwise, the apply process applies the LCR.

The table instantiation SCN specified by this procedure is used on the following types of LCRs:

- Row LCRs for the table
- DDL LCRs that have a non-NULL `base_table_owner` and `base_table_name` specified, except for DDL LCRs with a `command_type` of `CREATE TABLE`

For example, the table instantiation SCN set by this procedure is used for DDL LCRs with a `command_type` of `ALTER TABLE` or `CREATE TRIGGER`.

Note: The instantiation SCN specified by this procedure is used only for LCRs captured by a capture process. It is not used for user-created LCRs.

See Also:

- ["SET_GLOBAL_INSTANTIATION_SCN Procedure"](#) on page 15-40
- ["SET_SCHEMA_INSTANTIATION_SCN Procedure"](#) on page 15-49
- ["LCR\\$_ROW_RECORD Type"](#) on page 174-14 for more information about row LCRs
- ["LCR\\$_DDL_RECORD Type"](#) on page 174-3 for more information about DDL LCRs
- *Oracle Streams Replication Administrator's Guide*

SET_UPDATE_CONFLICT_HANDLER Procedure

This procedure adds, modifies, or removes an update conflict handler for the specified object.

Syntax

```
DBMS_APPLY_ADM.SET_UPDATE_CONFLICT_HANDLER(  
    object_name          IN  VARCHAR2,  
    method_name         IN  VARCHAR2,  
    resolution_column   IN  VARCHAR2,  
    column_list        IN  DBMS_UTILITY.NAME_ARRAY,  
    apply_database_link IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 15–20 SET_UPDATE_CONFLICT_HANDLER Procedure Parameters

Parameter	Description
object_name	<p>The schema and name of the table, specified as [<i>schema_name</i>.]<i>object_name</i>, for which an update conflict handler is being added, modified, or removed.</p> <p>For example, if an update conflict handler is being added for table <code>employees</code> owned by user <code>hr</code>, then specify <code>hr.employees</code>. If the schema is not specified, then the current user is the default.</p>

Table 15–20 SET_UPDATE_CONFLICT_HANDLER Procedure Parameters (Cont.)

Parameter	Description
method_name	<p>Type of update conflict handler to create.</p> <p>You can specify one of the built-in handlers, which determine whether the column list from the source database is applied for the row or whether the values in the row at the destination database are retained:</p> <ul style="list-style-type: none"> ■ MAXIMUM: Applies the column list from the source database if it has the greater value for the resolution column. Otherwise, retains the values at the destination database. ■ MINIMUM: Applies the column list from the source database if it has the lesser value for the resolution column. Otherwise, retains the values at the destination database. ■ OVERWRITE: Applies the column list from the source database, overwriting the column values at the destination database ■ DISCARD: Retains the column list from the destination database, discarding the column list from the source database <p>If NULL, then removes any existing update conflict handler with the same <code>object_name</code>, <code>resolution_column</code>, and <code>column_list</code>. If non-NULL, then replaces any existing update conflict handler with the same <code>object_name</code> and <code>resolution_column</code>.</p>
resolution_column	<p>Name of the column used to uniquely identify an update conflict handler. For the MAXIMUM and MINIMUM prebuilt methods, the resolution column is also used to resolve the conflict. The resolution column must be one of the columns listed in the <code>column_list</code> parameter.</p> <p>NULL is not allowed for this parameter. For the OVERWRITE and DISCARD prebuilt methods, you can any column in the column list.</p>

Table 15–20 SET_UPDATE_CONFLICT_HANDLER Procedure Parameters (Cont.)

Parameter	Description
<code>column_list</code>	<p>List of columns for which the conflict handler is called.</p> <p>If a conflict occurs for one or more of the columns in the list when an apply process tries to apply a row LCR, then the conflict handler is called to resolve the conflict. The conflict handler is not called if a conflict occurs only for columns that are not in the list.</p> <p>Note: Prebuilt update conflict handlers do not support LOB, LONG, LONG RAW, and user-defined type columns. Therefore, you should not include these types of columns in the <code>column_list</code> parameter.</p>
<code>apply_database_link</code>	<p>The name of the database link to a non-Oracle database. This parameter should be set only when the destination database is a non-Oracle database.</p> <p>Note: Currently, conflict handlers are not supported when applying changes to a non-Oracle database.</p>

Usage Notes

If you want to modify an existing update conflict handler, then you specify the table and resolution column of an the existing update conflict handler. You can modify the prebuilt method or the column list.

If you want to remove an existing update conflict handler, then specify `NULL` for the prebuilt method and specify the table, column list, and resolution column of the existing update conflict handler.

If an update conflict occurs, then Oracle completes the following series of actions:

1. Calls the appropriate update conflict handler to resolve the conflict
2. If no update conflict handler is specified or if the update conflict handler cannot resolve the conflict, then calls the appropriate error handler for the apply process, table, and operation to handle the error
3. If no error handler is specified or if the error handler cannot resolve the error, then raises an error and moves the transaction containing the row LCR that caused the error to the error queue

Note: Currently, setting an update conflict handler for an apply process that is applying to a non-Oracle database is not supported.

See Also:

- ["Signature of an Error Handler Procedure"](#) on page 15-34 for information about setting an error handler
- *Oracle Streams Replication Administrator's Guide*

Examples

The following is an example for setting an update conflict handler for the `employees` table in the `hr` schema:

```
DECLARE
  cols DBMS_UTILITY.NAME_ARRAY;
BEGIN
  cols(1) := 'salary';
  cols(2) := 'commission_pct';
  DBMS_APPLY_ADM.SET_UPDATE_CONFLICT_HANDLER(
    object_name      => 'hr.employees',
    method_name      => 'MAXIMUM',
    resolution_column => 'salary',
    column_list      => cols);
END;
/
```

This example sets a conflict handler that is called if a conflict occurs for the `salary` or `commission_pct` column in the `hr.employees` table. If such a conflict occurs, then the `salary` column is evaluated to resolve the conflict. If a conflict occurs only for a column that is not in the column list, such as the `job_id` column, then this conflict handler is not called.

START_APPLY Procedure

This procedure directs the apply process to start applying events.

Syntax

```
DBMS_APPLY_ADM.START_APPLY(  
    apply_name IN VARCHAR2);
```

Parameter

Table 15–21 START_APPLY Procedure Parameter

Parameter	Description
apply_name	The apply process name. A NULL setting is not allowed. Do not specify an owner.

Usage Notes

The start status is persistently recorded. Hence, if the status is `START`, then the apply process is started upon database instance startup. Each apply process is an Oracle background process and is prefixed by `AP`.

The enqueue and dequeue state of `DBMS_AQADM.START_QUEUE` and `DBMS_AQADM.STOP_QUEUE` have no effect on the start status of an apply process.

You can create the apply process using the following procedures:

- `DBMS_APPLY_ADM.CREATE_APPLY`
- `DBMS_STREAMS_ADM.ADD_GLOBAL_RULES`
- `DBMS_STREAMS_ADM.ADD_SCHEMA_RULES`
- `DBMS_STREAMS_ADM.ADD_TABLE_RULES`
- `DBMS_STREAMS_ADM.ADD_SUBSET_RULES`

See Also: [Chapter 96, "DBMS_STREAMS_ADM"](#)

STOP_APPLY Procedure

This procedure stops the apply process from applying events and rolls back any unfinished transactions being applied.

Syntax

```
DBMS_APPLY_ADM.STOP_APPLY(
  apply_name IN VARCHAR2,
  force      IN BOOLEAN  DEFAULT false);
```

Parameters

Table 15–22 STOP_APPLY Procedure Parameters

Parameter	Description
apply_name	The apply process name. A NULL setting is not allowed. Do not specify an owner.
force	<p>If <code>true</code>, then stops the apply process as soon as possible.</p> <p>If <code>false</code>, then stops the apply process after ensuring that there are no gaps in the set of applied transactions.</p> <p>The behavior of the apply process depends on the setting specified for the <code>force</code> parameter and the setting specified for the <code>commit_serialization</code> apply process parameter. See "Usage Notes" for more information.</p>

Usage Notes

The stop status is persistently recorded. Hence, if the status is `STOP`, then the apply process is not started upon database instance startup.

The enqueue and dequeue state of `DBMS_AQADM.START_QUEUE` and `DBMS_AQADM.STOP_QUEUE` have no effect on the `STOP` status of an apply process.

The following table describes apply process behavior for each setting of the `force` parameter in the `STOP_APPLY` procedure and the `commit_serialization` apply process parameter. In all cases, the apply process rolls back any unfinished transactions when it stops.

force	commit_serialization	Apply Process Behavior
true	full	The apply process stops immediately and does not apply any unfinished transactions.
true	none	When the apply process stops, some transactions that have been applied locally may have committed at the source database at a later point in time than some transactions that have not been applied locally.
false	full	The apply process stops after applying the next uncommitted transaction in the commit order, if any such transaction is in progress.
false	none	Before stopping, the apply process applies all of the transactions that have a commit time that is earlier than the applied transaction with the most recent commit time.

For example, assume that the `commit_serialization` apply process parameter is set to `none` and there are three transactions: transaction 1 has the earliest commit time, transaction 2 is committed after transaction 1, and transaction 3 has the latest commit time. Also assume that an apply process has applied transaction 1 and transaction 3 and is in the process of applying transaction 2 when the `STOP_APPLY` procedure is run. Given this scenario, if the `force` parameter is set to `true`, then transaction 2 is not applied, and the apply process stops (transaction 2 is rolled back). If, however, the `force` parameter is set to `false`, then transaction 2 is applied before the apply process stops.

A different scenario would result if the `commit_serialization` apply process parameter is set to `full`. For example, assume that the `commit_serialization` apply process parameter is set to `full` and there are three transactions: transaction A has the earliest commit time, transaction B is committed after transaction A, and transaction C has the latest commit time. In this case, the apply process has applied transaction A and is in the process of applying transactions B and C when the `STOP_APPLY` procedure is run. Given this scenario, if the `force` parameter is set to `true`, then transactions B and C are not applied, and the apply process stops (transactions B and C are rolled back). If, however, the `force` parameter is set to `false`, then transaction B is applied before the apply process stops, and transaction C is rolled back.

See Also: "[SET_PARAMETER Procedure](#)" on page 15-45 for more information about the `commit_serialization` apply process parameter

The `DBMS_AQ` package provides an interface to Oracle Streams Advanced Queuing (AQ).

See Also:

- *Oracle Streams Advanced Queuing User's Guide and Reference*
- [Oracle Streams AQ TYPES](#) for information about TYPES to use with `DBMS_AQ`.

This chapter contains the following topics:

- [Using DBMS_AQ](#)
 - [Constants](#)
 - [Data Structures](#)
 - [Operational Notes](#)
- [Summary of DBMS_AQ Subprograms](#)

Using DBMS_AQ

- [Constants](#)
- [Data Structures](#)
- [Operational Notes](#)

Constants

When using enumerated constants such as `BROWSE`, `LOCKED`, or `REMOVE`, the PL/SQL constants must be specified with the scope of the packages defining it. All types associated with the operational interfaces have to be prepended with `DBMS_AQ`. For example: `DBMS_AQ.BROWSE`. [Table 16-1](#) lists the PL/SQL enumerated constants that require the prefix, `DBMS_AQ`.

Table 16-1 Enumerated Constants

Parameter	Options
<code>visibility</code>	<code>IMMEDIATE</code> , <code>ON_COMMIT</code>
<code>dequeue mode</code>	<code>BROWSE</code> , <code>LOCKED</code> , <code>REMOVE</code> , <code>REMOVE_NODATA</code>
<code>navigation</code>	<code>FIRST_MESSAGE</code> , <code>NEXT_MESSAGE</code> , <code>NEXT_TRANSACTION</code>
<code>state</code>	<code>WAITING</code> , <code>READY</code> , <code>PROCESSED</code> , <code>EXPIRED</code>
<code>sequence_deviation</code>	<code>BEFORE</code> , <code>TOP</code>
<code>wait</code>	<code>FOREVER</code> , <code>NO_WAIT</code>
<code>delay</code>	<code>NO_DELAY</code>
<code>expiration</code>	<code>NEVER</code>
<code>namespace</code>	<code>NAMESPACE_AQ</code> , <code>NAMESPACE_ANONYMOUS</code>

Data Structures

Table 16-2 DBMS_AQ Data Structures

Data Structures	Description
Object Name on page 16-3	Names database objects

Table 16–2 (Cont.) DBMS_AQ Data Structures

Data Structures	Description
Type Name on page 16-3	Defines queue types
Oracle Streams AQ PL/SQL Callback on page 16-4	Specifies the user-defined PL/SQL procedure, defined in the database to be invoked on message notification

Object Name

The `object_name` data structure names database objects. It applies to queues, queue tables, agent names, and object types.

Syntax

```
object_name := VARCHAR2;
object_name := [schema_name.]name;
```

Usage Notes

Names for objects are specified by an optional schema name and a name. If the schema name is not specified, the current schema is assumed. The name must follow object name guidelines in *Oracle Database SQL Reference* with regard to reserved characters. Schema names, agent names, and object type names can be up to 30 bytes long. Queue names and queue table names can be up to 24 bytes long.

Type Name

The `type_name` data structure defines queue types.

Syntax

```
type_name := VARCHAR2;
type_name := object_type | "RAW";
```

Attributes

Table 16–3 Type Name Attributes

Attribute	Description
<code>object_type</code>	Maximum number of attributes in the object type is limited to 900.

Table 16–3 (Cont.) Type Name Attributes

Attribute	Description
"RAW"	<p>To store payload of type RAW, Oracle Streams AQ creates a queue table with a LOB column as the payload repository. The theoretical maximum size of the message payload is the maximum amount of data that can be stored in a LOB column. However, the maximum size of the payload is determined by which programmatic environment you use to access Oracle Streams AQ. For PL/SQL, Java and precompilers the limit is 32K; for the OCI the limit is 4G. Because the PL/SQL enqueue and dequeue interfaces accept RAW buffers as the payload parameters you will be limited to 32K bytes. In OCI, the maximum size of your RAW data will be limited to the maximum amount of contiguous memory (as an OCIRaw is simply an array of bytes) that the OCI Object Cache can allocate. Typically, this will be at least 32K bytes and much larger in many cases.</p> <p>Because LOB columns are used for storing RAW payload, the Oracle Streams AQ administrator can choose the LOB tablespace and configure the LOB storage by constructing a LOB storage string in the <code>storage_clause</code> parameter during queue table creation time.</p>

Oracle Streams AQ PL/SQL Callback

The `plsqcallback` data structure specifies the user-defined PL/SQL procedure, defined in the database to be invoked on message notification.

Syntax

If a notification message is expected for a RAW payload enqueue, then the PL/SQL callback must have the following signature:

```
procedure plsqcallback(
  context IN RAW,
  reginfo IN SYS.AQ$_REG_INFO,
  descr IN SYS.AQ$_DESCRIPTOR,
  payload IN RAW,
  payloadl IN NUMBER);
```

Attributes

Table 16–4 Oracle Streams AQ PL/SQL Callback Attributes

Attribute	Description
<code>context</code>	Specifies the context for the callback function that was passed by <code>dbms_aq.register</code> . See AQ\$_REG_INFO Type on page 171-10.

Table 16–4 (Cont.) Oracle Streams AQ PL/SQL Callback Attributes

Attribute	Description
reginfo	See AQ\$_REG_INFO Type on page 171-10
descr	See AQ\$_DESCRIPTOR Type on page 171-5
payload	If a notification message is expected for a raw payload enqueue then this contains the raw payload that was enqueued into a non persistent queue. In case of a persistent queue with raw payload this parameter will be null.
payload1	Specifies the length of <code>payload</code> . If <code>payload</code> is null, <code>payload1 = 0</code> .

If the notification message is expected for an ADT payload enqueue, the PL/SQL callback must have the following signature:

```
procedure plsqlcallback(
    context    IN RAW,
    reginfo   IN SYS.AQ$_REG_INFO,
    descr     IN SYS.AQ$_DESCRIPTOR,
    payload   IN VARCHAR2,
    payload1  IN NUMBER);
```

Operational Notes

- [DBMS_AQ and DBMS_AQADM Java Classes](#)

DBMS_AQ and DBMS_AQADM Java Classes

Java interfaces are available for `DBMS_AQ` and `DBMS_AQADM`. The Java interfaces are provided in the `$ORACLE_HOME/rdbms/jlib/aqapi.jar`. Users are required to have `EXECUTE` privileges on the `DBMS_AQIN` package to use these interfaces.

Summary of DBMS_AQ Subprograms

Table 16–5 DBMS_AQ Package Subprograms

Subprograms	Description
BIND_AGENT Procedure on page 16-7	Creates an entry for an Oracle Streams AQ agent in the LDAP directory
DEQUEUE Procedure on page 16-8	Dequeues a message from the specified queue
DEQUEUE_ARRAY Function on page 16-11	Dequeues an array of messages from the specified queue
ENQUEUE Procedure on page 16-13	Adds a message to the specified queue
ENQUEUE_ARRAY Function on page 16-15	Adds an array of messages to the specified queue
LISTEN Procedure on page 16-16	Listen to one or more queues on behalf of a list of agents
POST Procedure on page 16-18	Posts to a anonymous subscription which allows all clients who are registered for the subscription to get notifications
REGISTER Procedure on page 16-19	Registers for message notifications
UNBIND_AGENT Procedure on page 16-20	Removes an entry for an Oracle Streams AQ agent from the LDAP directory
UNREGISTER Procedure on page 16-21	Unregisters a subscription which turns off notification

Note: DBMS_AQ does not have a purity level defined; therefore, you cannot call any procedure in this package from other procedures that have RNDS, WNDS, RNPS or WNPS constraints defined.

BIND_AGENT Procedure

This procedure creates an entry for an Oracle Streams AQ agent in the LDAP server.

Syntax

```
DBMS_AQ.BIND_AGENT(  
    agent          IN SYS.AQ$_AGENT,  
    certificate    IN VARCHAR2 default NULL);
```

Parameters

Table 16–6 *BIND_AGENT Procedure Parameters*

Parameter	Description
agent	Agent that is to be registered in LDAP server.
certificate	Location (LDAP distinguished name) of the "organizationalperson" entry in LDAP whose digital certificate (attribute <code>usercertificate</code>) is to be used for this agent. Example: "cn=OE, cn=ACME, cn=com" is a distinguished name for a <code>OrganizationalPerson</code> OE whose certificate will be used with the specified agent.

Usage Notes

In the LDAP server, digital certificates are stored as an attribute (`usercertificate`) of the `OrganizationalPerson` entity. The distinguished name for this `OrganizationalPerson` must be specified when binding the agent.

DEQUEUE Procedure

This procedure dequeues a message from the specified queue.

Syntax

```
DBMS_AQ.DEQUEUE (
    queue_name          IN          VARCHAR2,
    dequeue_options    IN          dequeue_options_t,
    message_properties OUT          message_properties_t,
    payload             OUT          type_name,
    msgid              OUT          RAW);
```

Parameters

Table 16–7 DEQUEUE Procedure Parameters

Parameter	Description
queue_name	Specifies the name of the queue.
dequeue_options	See DEQUEUE_OPTIONS_T Type on page 171-14.
message_properties	See " MESSAGE_PROPERTIES_T Type " on page 171-18.
payload	Not interpreted by Oracle Streams AQ. The payload must be specified according to the specification in the associated queue table. For the definition of <i>type_name</i> refer to Type Name on page 16-3.
msgid	System generated identification of the message.

Usage Notes

The search criteria for messages to be dequeued is determined by the following parameters in `dequeue_options`:

- `consumer_name`
- `msgid`

Msgid uniquely identifies the message to be dequeued. Only messages in the READY state are dequeued unless `msgid` is specified.
- `correlation`

Correlation identifiers are application-defined identifiers that are not interpreted by Oracle Streams AQ.

- `deq_condition`

Dequeue condition is an expression based on the message properties, the message data properties and PL/SQL functions. A `deq_condition` is specified as a Boolean expression using syntax similar to the `WHERE` clause of a SQL query. This Boolean expression can include conditions on message properties, user data properties (object payloads only), and PL/SQL or SQL functions (as specified in the `where` clause of a SQL query). Message properties include `priority`, `corrid` and other columns in the queue table.

To specify dequeue conditions on a message payload (object payload), use attributes of the object type in clauses. You must prefix each attribute with `tab.user_data` as a qualifier to indicate the specific column of the queue table that stores the payload.

Example: `tab.user_data.orderstatus='EXPRESS'`

The dequeue order is determined by the values specified at the time the queue table is created unless overridden by the `msgid` and correlation ID in `dequeue_options`.

The database-consistent read mechanism is applicable for queue operations. For example, a `BROWSE` call may not see a message that is enqueued after the beginning of the browsing transaction.

The default `NAVIGATION` parameter during dequeue is `NEXT_MESSAGE`. This means that subsequent dequeues will retrieve the messages from the queue based on the snapshot obtained in the first dequeue. In particular, a message that is enqueued after the first dequeue command will be processed only after processing all the remaining messages in the queue. This is usually sufficient when all the messages have already been enqueued into the queue, or when the queue does not have a priority-based ordering. However, applications must use the `FIRST_MESSAGE` navigation option when the first message in the queue needs to be processed by every dequeue command. This usually becomes necessary when a higher priority message arrives in the queue while messages already-enqueued are being processed.

Note: It may be more efficient to use the `FIRST_MESSAGE` navigation option when messages are concurrently enqueued. If the `FIRST_MESSAGE` option is not specified, Oracle Streams AQ continually generates the snapshot as of the first dequeue command, leading to poor performance. If the `FIRST_MESSAGE` option is specified, then Oracle Streams AQ uses a new snapshot for every dequeue command.

Messages enqueued in the same transaction into a queue that has been enabled for message grouping will form a group. If only one message is enqueued in the transaction, then this will effectively form a group of one message. There is no upper limit to the number of messages that can be grouped in a single transaction.

In queues that have not been enabled for message grouping, a dequeue in `LOCKED` or `REMOVE` mode locks only a single message. By contrast, a dequeue operation that seeks to dequeue a message that is part of a group will lock the entire group. This is useful when all the messages in a group need to be processed as an atomic unit.

When all the messages in a group have been dequeued, the dequeue returns an error indicating that all messages in the group have been processed. The application can then use the `NEXT_TRANSACTION` to start dequeuing messages from the next available group. In the event that no groups are available, the dequeue will time out after the specified `WAIT` period.

Using Secure Queues

For secure queues, you must specify `consumer_name` in the `dequeue_options` parameter. See [DEQUEUE_OPTIONS_T Type](#) on page 171-14 for more information about `consumer_name`.

When you use secure queues, the following are required:

- You must have created a valid Oracle Streams AQ agent using `DBMS_AQADM.CREATE_AQ_AGENT`. See [CREATE_AQ_AGENT Procedure](#) on page 17-18.
- You must map the Oracle Streams AQ agent to a database user with dequeue privileges on the secure queue. Use `DBMS_AQADM.ENABLE_DB_ACCESS` to do this. See [ENABLE_DB_ACCESS Procedure](#) on page 17-35.

See Also: *Oracle Streams Concepts and Administration* for information about secure queues

DEQUEUE_ARRAY Function

This function dequeues an array of messages and returns them in the form of an array of payloads, an array of message properties and an array of message IDs. This function returns the number of messages successfully dequeued.

Syntax

```
DBMS_AQ.DEQUEUE_ARRAY (
    queue_name           IN    VARCHAR2,
    dequeue_options     IN    dequeue_options_t,
    array_size          IN    pls_integer,
    message_properties_array OUT message_properties_array_t,
    payload_array       OUT    "<COLLECTION_1>",
    msgid_array         OUT    msgid_array_t)
RETURN pls_integer;
```

Parameters

Table 16–8 DEQUEUE_ARRAY Function Parameters

Parameter	Description
queue_name	The queue name from which messages are dequeued (same as single-row dequeue).
dequeue_options	The set of options which will be applied to all messages in the array (same as single-row dequeue).
array_size	The number of elements to dequeue.
message_properties_array	A record containing an array corresponding to each message property. Each payload element has a corresponding set of message properties. See MESSAGE_PROPERTIES_ARRAY_T Type on page 171-22.
payload_array	An array of dequeued payload data. "<COLLECTION_1>" can be an associative array, varray or nested table in its PL/SQL representation.
msgid_array	An array of message IDs of the dequeued messages. See MSGID_ARRAY_T Type on page 171-23.

Usage Notes

A nonzero wait time, as specified in `dequeue_options`, is recognized only when there are no messages in the queue. If the queue contains messages that are eligible

for dequeue, then the `DEQUEUE_ARRAY` function will dequeue up to `array_size` messages and return immediately.

Dequeue by `message_id` is not supported. See [DEQUEUE Procedure](#) on page 16-8 for more information on the `navigation` parameter. Existing `NAVIGATION` modes are supported. In addition, two new `NAVIGATION` modes are supported for queues enabled for message grouping:

- `FIRST_MESSAGE_MULTI_GROUP`
- `NEXT_MESSAGE_MULTI_GROUP`

See Also: [DEQUEUE_OPTIONS_T Type](#) on page 171-14

For transaction grouped queues and `ONE_GROUP` navigation, messages are dequeued from a single transaction group only, subject to the `array_size` limit. In `MULTI_GROUP` navigation, messages are dequeued across multiple transaction groups, still subject to the `array_size` limit. `ORA-25235` is returned to indicate the end of a transaction group.

ENQUEUE Procedure

This procedure adds a message to the specified queue.

Syntax

```
DBMS_AQ.ENQUEUE (
    queue_name          IN          VARCHAR2,
    enqueue_options    IN          enqueue_options_t,
    message_properties IN          message_properties_t,
    payload            IN          "type_name",
    msgid              OUT         RAW);
```

Parameters

Table 16–9 ENQUEUE Procedure Parameters

Parameter	Description
queue_name	Specifies the name of the queue to which this message should be enqueued. The queue cannot be an exception queue.
enqueue_options	See ENQUEUE_OPTIONS_T Type on page 171-17.
message_properties	See MESSAGE_PROPERTIES_T Type on page 171-18.
payload	Not interpreted by Oracle Streams AQ. The payload must be specified according to the specification in the associated queue table. NULL is an acceptable parameter. For the definition of <i>type_name</i> refer to Type Name on page 16-3.
msgid	System generated identification of the message. This is a globally unique identifier that can be used to identify the message at dequeue time.

Usage Notes

The `sequence_deviation` parameter in `enqueue_options` can be used to change the order of processing between two messages. The identity of the other message, if any, is specified by the `enqueue_options` parameter `relative_msgid`. The relationship is identified by the `sequence_deviation` parameter.

Specifying `sequence_deviation` for a message introduces some restrictions for the delay and priority values that can be specified for this message. The delay of this message must be less than or equal to the delay of the message before which

this message is to be enqueued. The priority of this message must be greater than or equal to the priority of the message before which this message is to be enqueued.

If a message is enqueued to a multiconsumer queue with no recipient, and if the queue has no subscribers (or rule-based subscribers that match this message), then Oracle error `ORA_24033` is raised. This is a warning that the message will be discarded because there are no recipients or subscribers to whom it can be delivered.

Using Secure Queues

For secure queues, you must specify the `sender_id` in the `messages_properties` parameter. See [MESSAGE_PROPERTIES_T Type](#) on page 171-18 for more information about `sender_id`.

When you use secure queues, the following are required:

- You must have created a valid Oracle Streams AQ agent using `DBMS_AQADM.CREATE_AQ_AGENT`. See [CREATE_AQ_AGENT Procedure](#) on page 17-18.
- You must map `sender_id` to a database user with enqueue privileges on the secure queue. Use `DBMS_AQADM.ENABLE_DB_ACCESS` to do this. See [ENABLE_DB_ACCESS Procedure](#) on page 17-35.

See Also: *Oracle Streams Concepts and Administration* for information about secure queues

ENQUEUE_ARRAY Function

This function enqueues an array of payloads using a corresponding array of message properties. The output will be an array of message IDs of the enqueued messages.

Syntax

```
DBMS_AQ.ENQUEUE_ARRAY (
    queue_name          IN    VARCHAR2,
    enqueue_options    IN    enqueue_options_t,
    array_size         IN    pls_integer,
    message_properties_array IN message_properties_array_t,
    payload_array      IN    "<COLLECTION_1>",
    msgid_array        OUT   msgid_array_t)
RETURN pls_integer;
```

Parameters

Table 16–10 ENQUEUE_ARRAY Function Parameters

Parameter	Description
queue_name	The queue name in which messages are enqueued (same as single-row enqueue).
enqueue_options	See ENQUEUE_OPTIONS_T Type on page 171-17.
array_size	The number of elements to enqueue.
message_properties_array	A record containing an array corresponding to each message property. For each property, the user must allocate <code>array_size</code> elements. See MESSAGE_PROPERTIES_ARRAY_T Type on page 171-22.
payload_array	An array of payload data. "<COLLECTION_1>" can be an associative array, VARRAY, or nested table in its PL/SQL representation.
msgid_array	An array of message IDs for the enqueued messages. If an error occurs for a particular message, then its corresponding message ID is null. See MSGID_ARRAY_T Type on page 171-23.

LISTEN Procedure

This procedure listens on one or more queues on behalf of a list of agents. The address field of the agent indicates the queue the agent wants to monitor. Only local queues are supported as addresses. Protocol is reserved for future use.

Syntax

```
DBMS_AQ.LISTEN (  
  agent_list IN    aq$_agent_list_t,  
  wait        IN    BINARY_INTEGER DEFAULT DBMS_AQ.FOREVER,  
  agent       OUT   sys.aq$_agent);
```

```
TYPE aq$_agent_list_t IS TABLE of aq$_agent INDEXED BY BINARY_INTEGER;
```

Parameters

Table 16–11 LISTEN Procedure Parameters

Parameter	Description
agent_list	List of agents to listen for.
wait	Time out for the listen call in seconds. By default, the call will block forever.
agent	Agent with a message available for consumption.

Usage Notes

If agent-address is a multiconsumer queue, then agent-name is mandatory. For single-consumer queues, agent-name must not be specified.

This procedure takes a list of agents as an argument. You specify the queue to be monitored in the address field of each agent listed. You also must specify the name of the agent when monitoring multiconsumer queues. For single-consumer queues, an agent name must not be specified. Only local queues are supported as addresses. Protocol is reserved for future use.

This is a blocking call that returns when there is a message ready for consumption for an agent in the list. If there are messages for more than one agent, only the first agent listed is returned. If there are no messages found when the wait time expires, an error is raised.

A successful return from the listen call is only an indication that there is a message for one of the listed agents in one the specified queues. The interested agent must still dequeue the relevant message.

Note: You cannot call listen on nonpersistent queues.

POST Procedure

This procedure posts to a list of anonymous subscriptions that allows all clients who are registered for the subscriptions to get notifications.

Syntax

```
DBMS_AQ.POST (  
  post_list IN SYS.AQ$_POST_INFO_LIST,  
  count     IN NUMBER);
```

Parameters

Table 16–12 *POST Procedure Parameters*

Parameter	Description
<code>post_list</code>	Specifies the list of anonymous subscriptions to which you want to post. It is a list of AQ\$_POST_INFO Type.
<code>count</code>	Specifies the number of entries in the <code>post_list</code> .

Usage Notes

This procedure is used to post to anonymous subscriptions which allows all clients who are registered for the subscriptions to get notifications. Several subscriptions can be posted to at one time.

REGISTER Procedure

This procedure registers an e-mail address, user-defined PL/SQL procedure, or HTTP URL for message notification.

Syntax

```
DBMS_AQ.REGISTER (
  reg_list IN SYS.AQ$_REG_INFO_LIST,
  count    IN NUMBER);
```

Parameters

Table 16–13 REGISTER Procedure Parameters

Parameter	Description
<code>reg_list</code>	Specifies the list of subscriptions to which you want to register for message notifications. It is a list of AQ\$_REG_INFO Type.
<code>count</code>	Specifies the number of entries in the <code>reg_list</code> .

Usage Notes

This procedure is used to register for notifications. You can specify an e-mail address to which message notifications are sent, register a procedure to be invoked on a notification, or register an HTTP URL to which the notification is posted. Interest in several subscriptions can be registered at one time.

If you register for e-mail notifications, you should set the host name and port name for the SMTP server that will be used by the database to send e-mail notifications. If required, you should set the send-from e-mail address, which is set by the database as the `sent from` field. You need a Java-enabled database to use this feature.

If you register for HTTP notifications, you may want to set the host name and port number for the proxy server and a list of no-proxy domains that will be used by the database to post HTTP notifications.

See Also: [Chapter 18, "DBMS_AQELM"](#) for more information on e-mail and HTTP notifications

UNBIND_AGENT Procedure

This procedure removes the entry for an Oracle Streams AQ agent from the LDAP server.

Syntax

```
DBMS_AQ.UNBIND_AGENT(  
    agent    IN SYS.AQ$_AGENT);
```

Parameters

Table 16–14 *UNBIND_AGENT Procedure Parameters*

Parameter	Description
agent	Agent that is to be removed from the LDAP server

UNREGISTER Procedure

This procedure unregisters a subscription which turns off notifications.

Syntax

```
DBMS_AQ.UNREGISTER (  
    reg_list IN SYS.AQ$_REG_INFO_LIST,  
    count    IN NUMBER);
```

Parameters

Table 16–15 UNREGISTER Procedure Parameters

Parameter	Description
<code>reg_list</code>	Specifies the list of subscriptions to which you want to register for message notifications. It is a list of AQ\$_REG_INFO Type.
<code>count</code>	Specifies the number of entries in the <code>reg_list</code> .

Usage Notes

This procedure is used to unregister a subscription which turns off notifications. Several subscriptions can be unregistered from at one time.

The DBMS_AQADM package provides procedures to manage Oracle Streams Advanced Queuing (AQ) configuration and administration information.

See Also:

- *Oracle Streams Advanced Queuing User's Guide and Reference*
- [Chapter 171, "Oracle Streams AQ TYPES"](#) for information about the TYPES to use with DBMS_AQADM

This chapter contains the following topics:

- [Using DBMS_AQADM](#)
 - [Constants](#)
 - [Queue Table Subprograms](#)
 - [Privilege Subprograms](#)
 - [Queue Subprograms](#)
 - [Subscriber Subprograms](#)
 - [Notification Subprograms](#)
 - [Propagation Subprograms](#)
 - [Oracle Streams AQ Agent Subprograms](#)
 - [Alias Subprograms](#)
- [Using DBMS_AQADM](#)

Using DBMS_AQADM

- [Constants](#)
- [Queue Table Subprograms](#)
- [CREATE_QUEUE Procedure](#)
- [GRANT_SYSTEM_PRIVILEGE Procedure](#)
- [ADD_SUBSCRIBER Procedure](#)
- [SCHEDULE_PROPAGATION Procedure](#)
- [CREATE_AQ_AGENT Procedure](#)
- [Alias Subprograms](#)

Constants

When using enumerated constants, such as `INFINITE`, `TRANSACTIONAL`, or `NORMAL_QUEUE`, the symbol must be specified with the scope of the packages defining it. All types associated with the administrative interfaces must be prepended with `DBMS_AQADM`. For example: `DBMS_AQADM.NORMAL_QUEUE`.

Table 17–1 *Enumerated Types in the Administrative Interface*

Parameter	Options
<code>retention</code>	0, 1, 2... <code>INFINITE</code>
<code>message_grouping</code>	<code>TRANSACTIONAL</code> , <code>NONE</code>
<code>queue_type</code>	<code>NORMAL_QUEUE</code> , <code>EXCEPTION_QUEUE</code> , <code>NON_PERSISTENT_QUEUE</code>

See Also: For more information on the Java classes and data structures used in both `DBMS_AQ` and `DBMS_AQADM`, see the [DBMS_AQ](#) package.

Queue Table Subprograms

- [CREATE_QUEUE_TABLE Procedure](#)
- [ALTER_QUEUE_TABLE Procedure](#)

- DROP_QUEUE_TABLE Procedure
- PURGE_QUEUE_TABLE Procedure
- MIGRATE_QUEUE_TABLE Procedure
- ENABLE_JMS_TYPES Procedure

Privilege Subprograms

- GRANT_SYSTEM_PRIVILEGE Procedure
- REVOKE_SYSTEM_PRIVILEGE Procedure
- GRANT_QUEUE_PRIVILEGE Procedure
- REVOKE_QUEUE_PRIVILEGE Procedure

Queue Subprograms

- CREATE_QUEUE Procedure
- CREATE_NP_QUEUE Procedure
- ALTER_QUEUE Procedure
- DROP_QUEUE Procedure
- START_QUEUE Procedure
- STOP_QUEUE Procedure
- QUEUE_SUBSCRIBERS Function

Subscriber Subprograms

- ADD_SUBSCRIBER Procedure
- ALTER_SUBSCRIBER Procedure
- REMOVE_SUBSCRIBER Procedure

Notification Subprograms

- GET_WATERMARK Procedure

- [SET_WATERMARK Procedure](#)

Propagation Subprograms

- [SCHEDULE_PROPAGATION Procedure](#)
- [UNSCHEDULE_PROPAGATION Procedure](#)
- [VERIFY_QUEUE_TYPES Procedure](#)
- [ALTER_PROPAGATION_SCHEDULE Procedure](#)
- [ENABLE_PROPAGATION_SCHEDULE Procedure](#)
- [DISABLE_PROPAGATION_SCHEDULE Procedure](#)

Oracle Streams AQ Agent Subprograms

- [CREATE_AQ_AGENT Procedure](#)
- [ALTER_AQ_AGENT Procedure](#)
- [DROP_AQ_AGENT Procedure](#)
- [ENABLE_DB_ACCESS Procedure](#)
- [DISABLE_DB_ACCESS Procedure](#)

Alias Subprograms

- [ADD_ALIAS_TO_LDAP Procedure](#)
- [DEL_ALIAS_FROM_LDAP Procedure](#)

Summary of DBMS_AQADM Subprograms

Table 17–2 DBMS_AQ ADM Package Subprograms

Subprograms	Description
ADD_ALIAS_TO_LDAP Procedure on page 17-8	Creates an alias for a queue, agent, or a JMS ConnectionFactory in LDAP
ADD_SUBSCRIBER Procedure on page 17-9	Adds a default subscriber to a queue
ALTER_AQ_AGENT Procedure on page 17-11	Alters an agent registered for Oracle Streams AQ Internet access, and an Oracle Streams AQ agent that accesses secure queues
ALTER_PROPAGATION_SCHEDULE Procedure on page 17-12	Alters parameters for a propagation schedule
ALTER_QUEUE Procedure on page 17-14	Alters existing properties of a queue
ALTER_QUEUE_TABLE Procedure on page 17-16	Alters the existing properties of a queue table
ALTER_SUBSCRIBER Procedure on page 17-17	Alters existing properties of a subscriber to a specified queue
CREATE_AQ_AGENT Procedure on page 17-18	Registers an agent for Oracle Streams AQ Internet access using HTTP/SMTP protocols, and creates an Oracle Streams AQ agent to access secure queues
CREATE_NP_QUEUE Procedure on page 17-20	Creates a nonpersistent RAW queue
CREATE_QUEUE Procedure on page 17-22	Creates a queue in the specified queue table
CREATE_QUEUE_TABLE Procedure on page 17-25	Creates a queue table for messages of a predefined type
DEL_ALIAS_FROM_LDAP Procedure on page 17-29	Drops an alias for a queue, agent, or JMS ConnectionFactory in LDAP
DISABLE_DB_ACCESS Procedure on page 17-30	Revokes the privileges of a specific database user from an Oracle Streams AQ Internet agent

Table 17-2 (Cont.) DBMS_AQ ADM Package Subprograms

Subprograms	Description
DISABLE_PROPAGATION_SCHEDULE Procedure on page 17-31	Disables a propagation schedule
DROP_AQ_AGENT Procedure on page 17-32	Drops an agent that was previously registered for Oracle Streams AQ Internet access
DROP_QUEUE Procedure on page 17-33	Drops an existing queue
DROP_QUEUE_TABLE Procedure on page 17-34	Drops an existing queue table
ENABLE_DB_ACCESS Procedure on page 17-35	Grants an Oracle Streams AQ Internet agent the privileges of a specific database user
ENABLE_JMS_TYPES Procedure on page 17-36	A precondition for the enqueue of JMS types and XML types
ENABLE_PROPAGATION_SCHEDULE Procedure on page 17-37	Enables a previously disabled propagation schedule
GET_WATERMARK Procedure on page 17-38	Retrieves the value of watermark set by the <code>SET_WATERMARK Procedure</code>
GRANT_QUEUE_PRIVILEGE Procedure on page 17-39	Grants privileges on a queue to users and roles
GRANT_SYSTEM_PRIVILEGE Procedure on page 17-40	Grants Oracle Streams AQ system privileges to users and roles
MIGRATE_QUEUE_TABLE Procedure on page 17-41	Upgrades an 8.0-compatible queue table to an 8.1-compatible or higher queue table, or downgrades an 8.1-compatible or higher queue table to an 8.0-compatible queue table
PURGE_QUEUE_TABLE Procedure on page 17-42	Purges messages from queue tables
QUEUE_SUBSCRIBERS Function on page 17-44	Returns the subscribers to an 8.0-compatible multiconsumer queue in the PL/SQL index by table collection type <code>DBMS_AQADM.AQ\$_subscriber_list_t</code>
REMOVE_SUBSCRIBER Procedure on page 17-45	Removes a default subscriber from a queue

Table 17–2 (Cont.) DBMS_AQ ADM Package Subprograms

Subprograms	Description
REVOKE_QUEUE_PRIVILEGE Procedure on page 17-46	Revokes privileges on a queue from users and roles
REVOKE_SYSTEM_PRIVILEGE Procedure on page 17-47	Revokes Oracle Streams AQ system privileges from users and roles
SCHEDULE_PROPAGATION Procedure on page 17-48	Schedules propagation of messages from a queue to a destination identified by a specific database link
SET_WATERMARK Procedure on page 17-50	Used for Oracle Streams AQ notification to specify and limit memory use
START_QUEUE Procedure on page 17-51	Enables the specified queue for enqueueing or dequeuing
STOP_QUEUE Procedure on page 17-52	Disables enqueueing or dequeuing on the specified queue
UNSCHEDULE_PROPAGATION Procedure on page 17-53	Unscheduled previously scheduled propagation of messages from a queue to a destination identified by a specific database link
VERIFY_QUEUE_TYPES Procedure on page 17-54	Verifies that the source and destination queues have identical types

ADD_ALIAS_TO_LDAP Procedure

This procedure creates an alias for a queue, agent, or a JMS ConnectionFactory in LDAP. The alias will be placed directly under the database server's distinguished name in LDAP hierarchy.

Syntax

```
DBMS_AQADM.ADD_ALIAS_TO_LDAP(  
    alias          IN VARCHAR2,  
    obj_location  IN VARCHAR2);
```

Parameters

Table 17-3 ADD_ALIAS_TO_LDAP Procedure Parameters

Parameter	Description
alias	Name of the alias. Example: west_shipping.
obj_location	The distinguished name of the object (queue, agent or connection factory) to which alias refers.

Usage Notes

This method can be used to create aliases for Queues, Agents, and JMS ConnectionFactory objects. These object must exist before the alias is created. These aliases can be used for JNDI lookup in JMS and Oracle Streams AQ Internet access.

ADD_SUBSCRIBER Procedure

This procedure adds a default subscriber to a queue.

Syntax

```
DBMS_AQADM.ADD_SUBSCRIBER (
  queue_name      IN      VARCHAR2,
  subscriber      IN      sys.aq$_agent,
  rule            IN      VARCHAR2 DEFAULT NULL,
  transformation  IN      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 17–4 ADD_SUBSCRIBER Procedure Parameters

Parameter	Description
queue_name	Name of the queue.
subscriber	Agent on whose behalf the subscription is being defined.
rule	A conditional expression based on the message properties, the message data properties and PL/SQL functions. A rule is specified as a Boolean expression using syntax similar to the WHERE clause of a SQL query. This Boolean expression can include conditions on message properties, user data properties (object payloads only), and PL/SQL or SQL functions (as specified in the where clause of a SQL query). Currently supported message properties are <code>priority</code> and <code>corrid</code> . To specify rules on a message payload (object payload), use attributes of the object type in clauses. You must prefix each attribute with <code>tab.user_data</code> as a qualifier to indicate the specific column of the queue table that stores the payload. The rule parameter cannot exceed 4000 characters.
transformation	Specifies a transformation that will be applied when this subscriber dequeues the message. The source type of the transformation must match the type of the queue. If the subscriber is remote, then the transformation is applied before propagation to the remote queue.

Usage Notes

A program can enqueue messages to a specific list of recipients or to the default list of subscribers. This operation only succeeds on queues that allow multiple consumers. This operation takes effect immediately, and the containing transaction

is committed. Enqueue requests that are executed after the completion of this call will reflect the new behavior.

Any string within the rule must be quoted:

```
rule => 'PRIORITY <= 3 AND CORRID = ''FROM JAPAN'''
```

Note that these are all single quotation marks.

ALTER_AQ_AGENT Procedure

This procedure alters an agent registered for Oracle Streams AQ Internet access. It is also used to alter an Oracle Streams AQ agent that accesses secure queues.

See Also: *Oracle Streams Concepts and Administration* for information about secure queues

Syntax

```
DBMS_AQADM.ALTER_AQ_AGENT (
  agent_name           IN VARCHAR2,
  certificate_location IN VARCHAR2 DEFAULT NULL,
  enable_http         IN BOOLEAN DEFAULT FALSE,
  enable_smtp         IN BOOLEAN DEFAULT FALSE,
  enable_anyp         IN BOOLEAN DEFAULT FALSE )
```

Parameters

Table 17–5 ALTER_AQ_AGENT Procedure Parameters

Parameter	Description
agent_name	Specifies the username of the Oracle Streams AQ Internet agent.
certification_location	Agent's certificate location in LDAP (default is NULL). If the agent is allowed to access Oracle Streams AQ through SMTP, then its certificate must be registered in LDAP. For access through HTTP, the certificate location is not required.
enable_http	TRUE means the agent can access Oracle Streams AQ through HTTP. FALSE means the agent cannot access Oracle Streams AQ through HTTP.
enable_smtp	TRUE means the agent can access Oracle Streams AQ through SMTP (e-mail). FALSE means the agent cannot access Oracle Streams AQ through SMTP.
enable_anyp	TRUE means the agent can access Oracle Streams AQ through any protocol (HTTP or SMTP).

ALTER_PROPAGATION_SCHEDULE Procedure

This procedure alters parameters for a propagation schedule.

Syntax

```
DBMS_AQADM.ALTER_PROPAGATION_SCHEDULE (  
    queue_name      IN      VARCHAR2,  
    destination     IN      VARCHAR2 DEFAULT NULL,  
    duration        IN      NUMBER  DEFAULT NULL,  
    next_time       IN      VARCHAR2 DEFAULT NULL,  
    latency         IN      NUMBER  DEFAULT 60);
```

Parameters

Table 17–6 ALTER_PROPAGATION_SCHEDULE Procedure Parameters

Parameter	Description
queue_name	Name of the source queue whose messages are to be propagated, including the schema name. If the schema name is not specified, then it defaults to the schema name of the user.
destination	Destination database link. Messages in the source queue for recipients at this destination are propagated. If it is <code>NULL</code> , then the destination is the local database and messages are propagated to other queues in the local database. The length of this field is currently limited to 128 bytes, and if the name is not fully qualified, then the default domain name is used.
duration	Duration of the propagation window in seconds. A <code>NULL</code> value means the propagation window is forever or until the propagation is unscheduled.

Table 17–6 (Cont.) ALTER_PROPAGATION_SCHEDULE Procedure Parameters

Parameter	Description
next_time	Date function to compute the start of the next propagation window from the end of the current window. If this value is <code>NULL</code> , then propagation is stopped at the end of the current window. For example, to start the window at the same time every day, <code>next_time</code> should be specified as <code>SYSDATE + 1 - duration/86400</code> .
latency	<p>Maximum wait, in seconds, in the propagation window for a message to be propagated after it is enqueued. The default value is 60. Caution: if latency is not specified for this call, then latency will over-write any existing value with the default value.</p> <p>For example, if the latency is 60 seconds and there are no messages to be propagated during the propagation window, then messages from that queue for the destination are not propagated for at least 60 more seconds. It will be at least 60 seconds before the queue will be checked again for messages to be propagated for the specified destination. If the latency is 600, then the queue will not be checked for 10 minutes and if the latency is 0, then a job queue process will be waiting for messages to be enqueued for the destination and as soon as a message is enqueued it will be propagated.</p>

ALTER_QUEUE Procedure

This procedure alters existing properties of a queue. The parameters `max_retries`, `retention_time`, and `retry_delay` are not supported for nonpersistent queues.

Syntax

```
DBMS_AQADM.ALTER_QUEUE (
    queue_name      IN      VARCHAR2,
    max_retries     IN      NUMBER   DEFAULT NULL,
    retry_delay     IN      NUMBER   DEFAULT NULL,
    retention_time  IN      NUMBER   DEFAULT NULL,
    auto_commit     IN      BOOLEAN  DEFAULT TRUE,
    comment         IN      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 17–7 ALTER_QUEUE Procedure Parameters

Parameter	Description
<code>queue_name</code>	Name of the queue that is to be altered
<code>max_retries</code>	Limits the number of times a dequeue with <code>REMOVE</code> mode can be attempted on a message. The maximum value of <code>max_retries</code> is $2^{31} - 1$. A message is moved to an exception queue if <code>RETRY_COUNT</code> is greater than <code>MAX_RETRIES</code> . <code>RETRY_COUNT</code> is incremented when the application issues a rollback after executing the dequeue. If a dequeue transaction fails because the server process dies (including <code>ALTER SYSTEM KILL SESSION</code>) or <code>SHUTDOWN ABORT</code> on the instance, then <code>RETRY_COUNT</code> is not incremented. Note that <code>max_retries</code> is supported for all single consumer queues and 8.1-compatible or higher multiconsumer queues but not for 8.0-compatible multiconsumer queues.
<code>retry_delay</code>	Delay time in seconds before this message is scheduled for processing again after an application rollback. The default is <code>NULL</code> , which means that the value will not be altered. Note that <code>retry_delay</code> is supported for single consumer queues and 8.1-compatible or higher multiconsumer queues but not for 8.0-compatible multiconsumer queues.

Table 17–7 (Cont.) ALTER_QUEUE Procedure Parameters

Parameter	Description
retention_time	Retention time in seconds for which a message is retained in the queue table after being dequeued. The default is <code>NULL</code> , which means that the value will not be altered.
auto_commit	<code>TRUE</code> causes the current transaction, if any, to commit before the <code>ALTER_QUEUE</code> operation is carried out. The <code>ALTER_QUEUE</code> operation become persistent when the call returns. This is the default. <code>FALSE</code> means the operation is part of the current transaction and becomes persistent only when the caller enters a commit. Caution: This parameter has been deprecated.
comment	User-specified description of the queue. This user comment is added to the queue catalog. The default value is <code>NULL</code> , which means that the value will not be changed.

ALTER_QUEUE_TABLE Procedure

This procedure alters the existing properties of a queue table.

Syntax

```
DBMS_AQADM.ALTER_QUEUE_TABLE (  
    queue_table      IN  VARCHAR2,  
    comment          IN  VARCHAR2      DEFAULT NULL,  
    primary_instance IN  BINARY_INTEGER DEFAULT NULL,  
    secondary_instance IN BINARY_INTEGER DEFAULT NULL);
```

Parameters

Table 17–8 ALTER_QUEUE_TABLE Procedure Parameters

Parameter	Description
queue_table	Name of a queue table to be created.
comment	Modifies the user-specified description of the queue table. This user comment is added to the queue catalog. The default value is NULL which means that the value will not be changed.
primary_instance	This is the primary owner of the queue table. Queue monitor scheduling and propagation for the queues in the queue table will be done in this instance. The default value is NULL, which means that the current value will not be changed.
secondary_instance	The queue table fails over to the secondary instance if the primary instance is not available. The default value is NULL, which means that the current value will not be changed.

ALTER_SUBSCRIBER Procedure

This procedure alters existing properties of a subscriber to a specified queue. Only the rule can be altered.

Syntax

```
DBMS_AQADM.ALTER_SUBSCRIBER (
    queue_name      IN    VARCHAR2,
    subscriber      IN    sys.aq$_agent,
    rule            IN    VARCHAR2
    transformation IN    VARCHAR2);
```

Parameters

Table 17–9 ALTER_SUBSCRIBER Procedure Parameters

Parameter	Description
queue_name	Name of the queue.
subscriber	Agent on whose behalf the subscription is being altered. See " AQS_AGENT Type " on page 171-3.
rule	A conditional expression based on the message properties, the message data properties and PL/SQL functions. The rule parameter cannot exceed 4000 characters. To eliminate the rule, set the rule parameter to NULL.
transformation	Specifies a transformation that will be applied when this subscriber dequeues the message. The source type of the transformation must match the type of the queue. If the subscriber is remote, then the transformation is applied before propagation to the remote queue.

Usage Notes

This procedure alters both the rule and the transformation for the subscriber. If you want to retain the existing value for either of them, you must specify its old value. The current values for rule and transformation for a subscriber can be obtained from the `schema.AQ$queue_table_R` and `schema.AQ$queue_table_S` views.

CREATE_AQ_AGENT Procedure

This procedure registers an agent for Oracle Streams AQ Internet access using HTTP/SMTP protocols. It is also used to create an Oracle Streams AQ agent to access secure queues.

See Also: *Oracle Streams Concepts and Administration* for information about secure queues

Syntax

```
DBMS_AQADM.CREATE_AQ_AGENT (
  agent_name          IN VARCHAR2,
  certificate_location IN VARCHAR2 DEFAULT NULL,
  enable_http        IN BOOLEAN DEFAULT FALSE,
  enable_smtp        IN BOOLEAN DEFAULT FALSE,
  enable_anyp        IN BOOLEAN DEFAULT FALSE )
```

Parameters

Table 17–10 *CREATE_AQ_AGENT Procedure Parameters*

Parameter	Description
agent_name	Specifies the username of the Oracle Streams AQ Internet agent.
certification_location	Agent's certificate location in LDAP (default is NULL). If the agent is allowed to access Oracle Streams AQ through SMTP, then its certificate must be registered in LDAP. For access through HTTP, the certificate location is not required.
enable_http	TRUE means the agent can access Oracle Streams AQ through HTTP. FALSE means the agent cannot access Oracle Streams AQ through HTTP.
enable_smtp	TRUE means the agent can access Oracle Streams AQ through SMTP (e-mail). FALSE means the agent cannot access Oracle Streams AQ through SMTP.
enable_anyp	TRUE means the agent can access Oracle Streams AQ through any protocol (HTTP or SMTP).

Usage Notes

The `SYS.AQ$INTERNET_USERS` view has a list of all Oracle Streams AQ Internet agents.

CREATE_NP_QUEUE Procedure

This procedure creates a nonpersistent RAW queue.

Syntax

```
DBMS_AQADM.CREATE_NP_QUEUE (
    queue_name          IN          VARCHAR2,
    multiple_consumers IN          BOOLEAN DEFAULT FALSE,
    comment             IN          VARCHAR2 DEFAULT NULL);
```

Parameters

Table 17–11 CREATE_NP_QUEUE Procedure Parameters

Parameter	Description
queue_name	Name of the nonpersistent queue that is to be created. The name must be unique within a schema and must follow object name guidelines in <i>Oracle Database SQL Reference</i> .
multiple_consumers	FALSE means queues created in the table can only have one consumer for each message. This is the default. TRUE means queues created in the table can have multiple consumers for each message. Note that this parameter is distinguished at the queue level, because a nonpersistent queue does not inherit this characteristic from any user-created queue table.
comment	User-specified description of the queue. This user comment is added to the queue catalog.

Usage Notes

The queue may be either single-consumer or multiconsumer queue. All queue names must be unique within a schema. The queues are created in a 8.1-compatible or higher system-created queue table (AQ\$_MEM_SC or AQ\$_MEM_MC) in the same schema as that specified by the queue name.

If the queue name does not specify a schema name, the queue is created in the login user's schema. After a queue is created with CREATE_NP_QUEUE, it can be enabled by calling START_QUEUE. By default, the queue is created with both enqueue and dequeue disabled.

You cannot dequeue from a nonpersistent queue. The only way to retrieve a message from a nonpersistent queue is by using the OCI notification mechanism. You cannot invoke the `listen` call on a nonpersistent queue.

CREATE_QUEUE Procedure

This procedure creates a queue in the specified queue table.

Syntax

```
DBMS_AQADM.CREATE_QUEUE (
    queue_name          IN          VARCHAR2,
    queue_table         IN          VARCHAR2,
    queue_type          IN          BINARY_INTEGER DEFAULT NORMAL_QUEUE,
    max_retries         IN          NUMBER          DEFAULT NULL,
    retry_delay         IN          NUMBER          DEFAULT 0,
    retention_time      IN          NUMBER          DEFAULT 0,
    dependency_tracking IN          BOOLEAN         DEFAULT FALSE,
    comment             IN          VARCHAR2       DEFAULT NULL,
    auto_commit         IN          BOOLEAN         DEFAULT TRUE);
```

Parameters

Table 17–12 CREATE_QUEUE Procedure Parameters

Parameter	Description
queue_name	Name of the queue that is to be created. The name must be unique within a schema and must follow object name guidelines in <i>Oracle Database SQL Reference</i> with regard to reserved characters.
queue_table	Name of the queue table that will contain the queue.
queue_type	Specifies whether the queue being created is an exception queue or a normal queue. <code>NORMAL_QUEUE</code> means the queue is a normal queue. This is the default. <code>EXCEPTION_QUEUE</code> means it is an exception queue. Only the dequeue operation is allowed on the exception queue.

Table 17–12 (Cont.) CREATE_QUEUE Procedure Parameters

Parameter	Description
max_retries	<p>Limits the number of times a dequeue with the REMOVE mode can be attempted on a message. The maximum value of max_retries is $2^{31} - 1$.</p> <p>A message is moved to an exception queue if RETRY_COUNT is greater than MAX_RETRIES. RETRY_COUNT is incremented when the application issues a rollback after executing the dequeue. If a dequeue transaction fails because the server process dies (including ALTER SYSTEM KILL SESSION) or SHUTDOWN ABORT on the instance, then RETRY_COUNT is not incremented.</p> <p>Note that max_retries is supported for all single consumer queues and 8.1-compatible or higher multiconsumer queues but not for 8.0-compatible multiconsumer queues.</p>
retry_delay	<p>Delay time, in seconds, before this message is scheduled for processing again after an application rollback.</p> <p>The default is 0, which means the message can be retried as soon as possible. This parameter has no effect if max_retries is set to 0. Note that retry_delay is supported for single consumer queues and 8.1-compatible or higher multiconsumer queues but not for 8.0-compatible multiconsumer queues.</p>
retention_time	<p>Number of seconds for which a message is retained in the queue table after being dequeued from the queue. INFINITE means the message is retained forever. NUMBER is the number of seconds for which to retain the messages. The default is 0, no retention.</p>
dependency_tracking	<p>Reserved for future use. FALSE is the default. TRUE is not permitted in this release.</p>
comment	<p>User-specified description of the queue. This user comment is added to the queue catalog.</p>
auto_commit	<p>TRUE causes the current transaction, if any, to commit before the CREATE_QUEUE operation is carried out. The CREATE_QUEUE operation becomes persistent when the call returns. This is the default. FALSE means the operation is part of the current transaction and becomes persistent only when the caller enters a commit.</p> <p>Caution: This parameter has been deprecated.</p>

Usage Notes

All queue names must be unique within a schema. After a queue is created with `CREATE_QUEUE`, it can be enabled by calling `START_QUEUE`. By default, the queue is created with both `enqueue` and `dequeue` disabled.

CREATE_QUEUE_TABLE Procedure

This procedure creates a queue table for messages of a predefined type.

Syntax

```
DBMS_AQADM.CREATE_QUEUE_TABLE (
    queue_table          IN      VARCHAR2,
    queue_payload_type  IN      VARCHAR2,
    [storage_clause     IN      VARCHAR2          DEFAULT NULL, ]
    sort_list           IN      VARCHAR2          DEFAULT NULL,
    multiple_consumers IN      BOOLEAN           DEFAULT FALSE,
    message_grouping   IN      BINARY_INTEGER   DEFAULT NONE,
    comment             IN      VARCHAR2         DEFAULT NULL,
    auto_commit         IN      BOOLEAN           DEFAULT TRUE,
    primary_instance   IN      BINARY_INTEGER   DEFAULT 0,
    secondary_instance IN      BINARY_INTEGER   DEFAULT 0,
    compatible         IN      VARCHAR2         DEFAULT NULL,
    secure              IN      BOOLEAN           DEFAULT FALSE);
```

Parameters

Table 17–13 CREATE_QUEUE_TABLE Procedure Parameters

Parameter	Description
queue_table	Name of a queue table to be created
queue_payload_type	Type of the user data stored. See Type Name on page 16-3 for valid values for this parameter.
storage_clause	Storage parameter. The storage parameter is included in the CREATE TABLE statement when the queue table is created. The storage_clause argument can take any text that can be used in a standard CREATE TABLE storage_clause argument. The storage parameter can be made up of any combinations of the following parameters: PCTFREE, PCTUSED, INITRANS, MAXTRANS, TABLESPACE, LOB, and a table storage clause. If a tablespace is not specified here, then the queue table and all its related objects are created in the default user tablespace. If a tablespace is specified here, then the queue table and all its related objects are created in the tablespace specified in the storage clause. See <i>Oracle Database SQL Reference</i> for the usage of these parameters.

Table 17–13 (Cont.) CREATE_QUEUE_TABLE Procedure Parameters

Parameter	Description
<code>sort_list</code>	<p>The columns to be used as the sort key in ascending order. This parameter has the following format:</p> <pre>'sort_column_1,sort_column_2'</pre> <p>The allowed column names are <code>priority</code> and <code>enq_time</code>. If both columns are specified, then <code>sort_column_1</code> defines the most significant order.</p> <p>After a queue table is created with a specific ordering mechanism, all queues in the queue table inherit the same defaults. The order of a queue table cannot be altered after the queue table has been created.</p> <p>If no sort list is specified, then all the queues in this queue table are sorted by the enqueue time in ascending order. This order is equivalent to FIFO order.</p> <p>Even with the default ordering defined, a dequeuer is allowed to choose a message to dequeue by specifying its <code>msgid</code> or <code>correlation</code>. <code>msgid</code>, <code>correlation</code>, and <code>sequence_deviation</code> take precedence over the default dequeuing order, if they are specified.</p>
<code>multiple_consumers</code>	<p><code>FALSE</code> means queues created in the table can only have one consumer for each message. This is the default. <code>TRUE</code> means queues created in the table can have multiple consumers for each message.</p>
<code>message_grouping</code>	<p>Message grouping behavior for queues created in the table. <code>NONE</code> means each message is treated individually. <code>TRANSACTIONAL</code> means messages enqueued as part of one transaction are considered part of the same group and can be dequeued as a group of related messages.</p>
<code>comment</code>	<p>User-specified description of the queue table. This user comment is added to the queue catalog.</p>
<code>auto_commit</code>	<p><code>TRUE</code> causes the current transaction, if any, to commit before the <code>CREATE_QUEUE_TABLE</code> operation is carried out. The <code>CREATE_QUEUE_TABLE</code> operation becomes persistent when the call returns. This is the default. <code>FALSE</code> means the operation is part of the current transaction and becomes persistent only when the caller enters a commit.</p> <p>Note: This parameter has been deprecated.</p>

Table 17–13 (Cont.) CREATE_QUEUE_TABLE Procedure Parameters

Parameter	Description
primary_instance	<p>The primary owner of the queue table. Queue monitor scheduling and propagation for the queues in the queue table are done in this instance.</p> <p>The default value for primary instance is 0, which means queue monitor scheduling and propagation will be done in any available instance.</p>
secondary_instance	<p>The queue table fails over to the secondary instance if the primary instance is not available. The default value is 0, which means that the queue table will fail over to any available instance.</p>
compatible	<p>The lowest database version with which the queue is compatible. Currently the possible values are either 8.0, 8.1, or 10.0. If the database is in 10.1-compatible mode, the default value is 10.0. If the database is in 8.1-compatible or 9.2-compatible mode, the default value is 8.1. If the database is in 8.0 compatible mode, the default value is 8.0.</p>
secure	<p>This parameter must be set to TRUE if you want to use the queue table for secure queues. Secure queues are queues for which AQ agents must be associated explicitly with one or more database users who can perform queue operations, such as enqueue and dequeue. The owner of a secure queue can perform all queue operations on the queue, but other users cannot perform queue operations on a secure queue, unless they are configured as secure queue users.</p>

Usage Notes

The sort keys for dequeue ordering, if any, must be defined at table creation time. The following objects are created at this time:

- `aq$_queue_table_name_e`, a default exception queue associated with the queue table
- `aq$queue_table_name`, a read-only view, which is used by Oracle Streams AQ applications for querying queue data
- `aq$_queue_table_name_t`, an index (or an index organized table (IOT) in the case of multiple consumer queues) for the queue monitor operations
- `aq$_queue_table_name_i`, an index (or an index organized table in the case of multiple consumer queues) for dequeue operations

For 8.1-compatible or higher queue tables, the following index-organized tables are created:

- `aq$_queue_table_name_s`, a table for storing information about the subscribers
- `aq$_queue_table_name_r`, a table for storing information about rules on subscriptions

`aq$_queue_table_name_h`, an index-organized table for storing the dequeue history data

CLOB, BLOB, and BFILE are valid attributes for Oracle Streams AQ object type payloads. However, only CLOB and BLOB can be propagated using Oracle Streams AQ propagation in Oracle8i release 8.1.5 or later. See the *Oracle Streams Advanced Queuing User's Guide and Reference* for more information.

The default value of the `compatible` parameter depends on the database compatibility mode in the `init.ora`. If the database is in 10.1-compatible mode, the default value is 10.0. If the database is in 8.1-compatible or 9.2-compatible mode, the default value is 8.1. If the database is in 8.0 compatible mode, the default value is 8.0

You can specify and modify the `primary_instance` and `secondary_instance` only in 8.1-compatible or higher mode. You cannot specify a secondary instance unless there is a primary instance.

DEL_ALIAS_FROM_LDAP Procedure

This procedure drops an alias for a queue, agent, or JMS ConnectionFactory in LDAP.

Syntax

```
DBMS_AQ.DEL_ALIAS_FROM_LDAP(  
    alias IN VARCHAR2);
```

Parameters

Table 17–14 *DEL_ALIAS_FROM_LDAP Procedure Parameters*

Parameter	Description
alias	The alias to be removed.

DISABLE_DB_ACCESS Procedure

This procedure revokes the privileges of a specific database user from an Oracle Streams AQ Internet agent.

Syntax

```
DBMS_AQADM.DISABLE_DB_ACCESS (  
  agent_name           IN VARCHAR2,  
  db_username          IN VARCHAR2)
```

Parameters

Table 17–15 *DISABLE_DB_ACCESS Procedure Parameters*

Parameter	Description
agent_name	Specifies the username of the Oracle Streams AQ Internet agent.
db_username	Specifies the database user whose privileges are to be revoked from the Oracle Streams AQ Internet agent.

Usage Notes

The Oracle Streams AQ Internet agent should have been previously granted those privileges using the [ENABLE_DB_ACCESS Procedure](#).

DISABLE_PROPAGATION_SCHEDULE Procedure

This procedure disables a propagation schedule.

Syntax

```
DBMS_AQADM.DISABLE_PROPAGATION_SCHEDULE (
    queue_name      IN      VARCHAR2,
    destination     IN      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 17–16 *DISABLE_PROPAGATION_SCHEDULE Procedure Parameters*

Parameter	Description
queue_name	Name of the source queue whose messages are to be propagated, including the schema name. If the schema name is not specified, then it defaults to the schema name of the user.
destination	Destination database link. Messages in the source queue for recipients at this destination are propagated. If it is NULL, then the destination is the local database and messages are propagated to other queues in the local database. The length of this field is currently limited to 128 bytes, and if the name is not fully qualified, then the default domain name is used.

DROP_AQ_AGENT Procedure

This procedure drops an agent that was previously registered for Oracle Streams AQ Internet access.

Syntax

```
DBMS_AQADM.DROP_AQ_AGENT (  
    agent_name           IN VARCHAR2)
```

Parameters

Table 17–17 *DROP_AQ_AGENT Procedure Parameters*

Parameter	Description
agent_name	Specifies the username of the Oracle Streams AQ Internet agent

DROP_QUEUE Procedure

This procedure drops an existing queue.

Syntax

```
DBMS_AQADM.DROP_QUEUE (
    queue_name      IN    VARCHAR2,
    auto_commit     IN    BOOLEAN DEFAULT TRUE);
```

Parameters

Table 17–18 *DROP_QUEUE Procedure Parameters*

Parameter	Description
queue_name	Name of the queue that is to be dropped.
auto_commit	TRUE causes the current transaction, if any, to commit before the DROP_QUEUE operation is carried out. The DROP_QUEUE operation becomes persistent when the call returns. This is the default. FALSE means the operation is part of the current transaction and becomes persistent only when the caller enters a commit. Caution: This parameter has been deprecated.

Usage Notes

DROP_QUEUE is not allowed unless STOP_QUEUE has been called to disable the queue for both enqueueing and dequeuing. All the queue data is deleted as part of the drop operation.

DROP_QUEUE_TABLE Procedure

This procedure drops an existing queue table.

Syntax

```
DBMS_AQADM.DROP_QUEUE_TABLE (  
    queue_table      IN    VARCHAR2,  
    force            IN    BOOLEAN DEFAULT FALSE,  
    auto_commit      IN    BOOLEAN DEFAULT TRUE);
```

Parameters

Table 17–19 *DROP_QUEUE_TABLE Procedure Parameters*

Parameter	Description
queue_table	Name of a queue table to be dropped.
force	FALSE means the operation does not succeed if there are any queues in the table. This is the default. TRUE means all queues in the table are stopped and dropped automatically.
auto_commit	TRUE causes the current transaction, if any, to commit before the DROP_QUEUE_TABLE operation is carried out. The DROP_QUEUE_TABLE operation becomes persistent when the call returns. This is the default. FALSE means the operation is part of the current transaction and becomes persistent only when the caller enters a commit. Caution: This parameter has been deprecated.

Usage Notes

All the queues in a queue table must be stopped and dropped before the queue table can be dropped. You must do this explicitly unless the `force` option is used, in which case this is done automatically.

ENABLE_DB_ACCESS Procedure

This procedure grants an Oracle Streams AQ Internet agent the privileges of a specific database user.

Syntax

```
DBMS_AQADM.ENABLE_DB_ACCESS (
    agent_name          IN VARCHAR2,
    db_username         IN VARCHAR2)
```

Parameters

Table 17–20 *ENABLE_DB_ACCESS Procedure Parameters*

Parameter	Description
agent_name	Specifies the username of the Oracle Streams AQ Internet agent.
db_username	Specified the database user whose privileges are to be granted to the Oracle Streams AQ Internet agent.

Usage Notes

The Oracle Streams AQ Internet agent should have been previously created using the [CREATE_AQ_AGENT Procedure](#).

For secure queues, the sender and receiver agent of the message must be mapped to the database user performing the enqueue or dequeue operation.

See Also: *Oracle Streams Concepts and Administration* for information about secure queues

The `SYS.AQ$INTERNET_USERS` view has a list of all Oracle Streams AQ Internet agents and the names of the database users whose privileges are granted to them.

ENABLE_JMS_TYPES Procedure

Enqueue of JMS types and XML types does not work with Oracle Streams `Sys.Anydata` queues unless you call this procedure after `DBMS_STREAMS_ADM.SET_UP_QUEUE`. Enabling an Oracle Streams queue for these types may affect import/export of the queue table.

Syntax

```
DBMS_AQADM.ENABLE_JMS_TYPES (  
    queue_table IN VARCHAR2);
```

Parameters

Table 17–21 *ENABLE_JMS_TYPES Procedure Parameters*

Parameter	Description
<code>queue_table</code>	Specifies name of the queue table to be enabled for JMS and XML types.

ENABLE_PROPAGATION_SCHEDULE Procedure

This procedure enables a previously disabled propagation schedule.

Syntax

```
DBMS_AQADM.ENABLE_PROPAGATION_SCHEDULE (
    queue_name      IN      VARCHAR2,
    destination     IN      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 17–22 *ENABLE_PROPAGATION_SCHEDULE Procedure Parameters*

Parameter	Description
queue_name	Name of the source queue whose messages are to be propagated, including the schema name. If the schema name is not specified, then it defaults to the schema name of the user.
destination	Destination database link. Messages in the source queue for recipients at this destination are propagated. If it is NULL, then the destination is the local database and messages are propagated to other queues in the local database. The length of this field is currently limited to 128 bytes, and if the name is not fully qualified, then the default domain name is used.

GET_WATERMARK Procedure

This procedure retrieves the value of watermark set by SET_WATERMARK.

Syntax

```
DBMS_AQADM.GET_WATERMARK (  
    wmvalue      OUT      NUMBER);
```

Parameters

Table 17–23 GET_WATERMARK Procedure Parameter

Parameter	Description
wmvalue	Watermark value in megabytes.

GRANT_QUEUE_PRIVILEGE Procedure

This procedure grants privileges on a queue to users and roles. The privileges are `ENQUEUE` or `DEQUEUE`. Initially, only the queue table owner can use this procedure to grant privileges on the queues.

Syntax

```
DBMS_AQADM.GRANT_QUEUE_PRIVILEGE (
  privilege      IN   VARCHAR2,
  queue_name     IN   VARCHAR2,
  grantee        IN   VARCHAR2,
  grant_option   IN   BOOLEAN := FALSE);
```

Parameters

Table 17–24 GRANT_QUEUE_PRIVILEGE Procedure Parameters

Parameter	Description
<code>privilege</code>	The Oracle Streams AQ queue privilege to grant. The options are <code>ENQUEUE</code> , <code>DEQUEUE</code> , and <code>ALL</code> . <code>ALL</code> means both <code>ENQUEUE</code> and <code>DEQUEUE</code> .
<code>queue_name</code>	Name of the queue.
<code>grantee</code>	Grantee(s). The grantee(s) can be a user, a role, or the <code>PUBLIC</code> role.
<code>grant_option</code>	Specifies if the access privilege is granted with the <code>GRANT</code> option or not. If the privilege is granted with the <code>GRANT</code> option, then the grantee is allowed to use this procedure to grant the access privilege to other users or roles, regardless of the ownership of the queue table. The default is <code>FALSE</code> .

GRANT_SYSTEM_PRIVILEGE Procedure

This procedure grants Oracle Streams AQ system privileges to users and roles. The privileges are `ENQUEUE_ANY`, `DEQUEUE_ANY`, and `MANAGE_ANY`. Initially, only `SYS` and `SYSTEM` can use this procedure successfully.

Syntax

```
DBMS_AQADM.GRANT_SYSTEM_PRIVILEGE (  
    privilege      IN    VARCHAR2,  
    grantee       IN    VARCHAR2,  
    admin_option  IN    BOOLEAN := FALSE);
```

Parameters

Table 17-25 GRANT_SYSTEM_PRIVILEGE Procedure Parameters

Parameter	Description
<code>privilege</code>	The Oracle Streams AQ system privilege to grant. The options are <code>ENQUEUE_ANY</code> , <code>DEQUEUE_ANY</code> , and <code>MANAGE_ANY</code> . <code>ENQUEUE_ANY</code> means users granted this privilege are allowed to enqueue messages to any queues in the database. <code>DEQUEUE_ANY</code> means users granted this privilege are allowed to dequeue messages from any queues in the database. <code>MANAGE_ANY</code> means users granted this privilege are allowed to run <code>DBMS_AQADM</code> calls on any schemas in the database.
<code>grantee</code>	Grantee(s). The grantee(s) can be a user, a role, or the <code>PUBLIC</code> role.
<code>admin_option</code>	Specifies if the system privilege is granted with the <code>ADMIN</code> option or not. If the privilege is granted with the <code>ADMIN</code> option, then the grantee is allowed to use this procedure to grant the system privilege to other users or roles. The default is <code>FALSE</code> .

MIGRATE_QUEUE_TABLE Procedure

This procedure upgrades an 8.0-compatible queue table to an 8.1-compatible or higher queue table, or downgrades an 8.1-compatible or higher queue table to an 8.0-compatible queue table.

Syntax

```
DBMS_AQADM.MIGRATE_QUEUE_TABLE (  
    queue_table IN VARCHAR2,  
    compatible  IN VARCHAR2);
```

Parameters

Table 17–26 *MIGRATE_QUEUE_TABLE Procedure Parameters*

Parameter	Description
queue_table	Specifies name of the queue table to be migrated.
compatible	Set this to 8.1 to upgrade an 8.0-compatible queue table, or set this to 8.0 to downgrade an 8.1-compatible queue table.

PURGE_QUEUE_TABLE Procedure

This procedure purges messages from queue tables. You can perform various purge operations on both single-consumer and multiconsumer queue tables for persistent queues.

Syntax

```
DBMS_AQADM.PURGE_QUEUE_TABLE (
    queue_table      IN  VARCHAR2,
    purge_condition  IN  VARCHAR2,
    purge_options    IN  aq$_purge_options_t);
```

where type `aq$_purge_options_t` is described in [Chapter 171, "Oracle Streams AQ TYPES"](#).

Parameters

Table 17-27 *PURGE_QUEUE_TABLE Procedure Parameters*

Parameter	Description
<code>queue_table</code> (IN VARCHAR2)	Specifies the name of the queue table to be purged.
<code>purge_condition</code> (IN VARCHAR2)	Specifies the purge condition to use when purging the queue table. The purge condition must be in the format of a SQL <code>WHERE</code> clause, and it is case-sensitive. The condition is based on the columns of <code>aq\$queue_table</code> view. To purge all queues in a queue table, set <code>purge_condition</code> to either <code>NULL</code> (a bare null word, no quotes) or <code>' '</code> (two single quotes).
<code>purge_options</code> IN <code>aq\$_purge_options_t</code>	Type <code>aq\$_purge_options_t</code> contains a <code>block</code> parameter. If <code>block</code> is <code>TRUE</code> , then an exclusive lock on all the queues in the queue table is held while purging the queue table. This will cause concurrent enqueueers and dequeuers to block while the queue table is purged. The purge call always succeeds if <code>block</code> is <code>TRUE</code> . The default for <code>block</code> is <code>FALSE</code> . This will not block enqueueers and dequeuers, but it can cause the purge to fail with an error during high concurrency times.

Usage Notes

You can purge selected messages from the queue table by specifying additional parameters in the API call. [Table 17-27](#) describes these parameters. Messages can be enqueued to and dequeued from the queue table while the queue table is being purged.

A trace file is generated in the udump destination when you run this procedure. It details what the procedure is doing. The procedure commits after it has processed all the messages.

QUEUE_SUBSCRIBERS Function

This function returns the subscribers to an 8.0-compatible multiconsumer queue in the PL/SQL index by table collection type `DBMS_AQADM.AQ$_subscriber_list_t`. Each element of the collection is of type `sys.aq$_agent`. This functionality is provided for 8.1-compatible queues by the `AQ$queue_table_name_S` view.

Syntax

```
DBMS_AQADM.QUEUE_SUBSCRIBERS (
    queue_name          IN          VARCHAR2);
RETURN aq$_subscriber_list_t IS
```

Parameters

Table 17–28 *QUEUE_SUBSCRIBERS Function Parameters*

Parameter	Description
<code>queue_name</code>	Specifies the queue whose subscribers are to be printed.

REMOVE_SUBSCRIBER Procedure

This procedure removes a default subscriber from a queue. This operation takes effect immediately, and the containing transaction is committed. All references to the subscriber in existing messages are removed as part of the operation.

Syntax

```
DBMS_AQADM.REMOVE_SUBSCRIBER (  
    queue_name      IN      VARCHAR2,  
    subscriber      IN      sys.aq$_agent);
```

Parameters

Table 17–29 REMOVE_SUBSCRIBER Procedure Parameters

Parameter	Description
queue_name	Name of the queue.
subscriber	Agent who is being removed. See " AQ\$_AGENT Type " on page 171-3.

REVOKE_QUEUE_PRIVILEGE Procedure

This procedure revokes privileges on a queue from users and roles. The privileges are ENQUEUE or DEQUEUE.

Syntax

```
DBMS_AQADM.REVOKE_QUEUE_PRIVILEGE (  
    privilege          IN      VARCHAR2,  
    queue_name        IN      VARCHAR2,  
    grantee           IN      VARCHAR2);
```

Parameters

Table 17-30 REVOKE_QUEUE_PRIVILEGE Procedure Parameters

Parameter	Description
privilege	The Oracle Streams AQ queue privilege to revoke. The options are ENQUEUE, DEQUEUE, and ALL. ALL means both ENQUEUE and DEQUEUE.
queue_name	Name of the queue.
grantee	Grantee(s). The grantee(s) can be a user, a role, or the PUBLIC role. If the privilege has been propagated by the grantee through the GRANT option, then the propagated privilege is also revoked.

Usage Notes

To revoke a privilege, the revoker must be the original grantor of the privilege. The privileges propagated through the GRANT option are revoked if the grantor's privileges are revoked.

REVOKE_SYSTEM_PRIVILEGE Procedure

This procedure revokes Oracle Streams AQ system privileges from users and roles. The privileges are `ENQUEUE_ANY`, `DEQUEUE_ANY` and `MANAGE_ANY`. The `ADMIN` option for a system privilege cannot be selectively revoked.

Syntax

```
DBMS_AQADM.REVOKE_SYSTEM_PRIVILEGE (
  privilege      IN  VARCHAR2,
  grantee       IN  VARCHAR2);
```

Parameters

Table 17–31 *REVOKE_SYSTEM_PRIVILEGE Procedure Parameters*

Parameter	Description
<code>privilege</code>	The Oracle Streams AQ system privilege to revoke. The options are <code>ENQUEUE_ANY</code> , <code>DEQUEUE_ANY</code> , and <code>MANAGE_ANY</code> . The <code>ADMIN</code> option for a system privilege cannot be selectively revoked.
<code>grantee</code>	Grantee(s). The grantee(s) can be a user, a role, or the <code>PUBLIC</code> role.

SCHEDULE_PROPAGATION Procedure

This procedure schedules propagation of messages from a queue to a destination identified by a specific database link.

Syntax

```
DBMS_AQADM.SCHEDULE_PROPAGATION (  
    queue_name      IN      VARCHAR2,  
    destination     IN      VARCHAR2 DEFAULT NULL,  
    start_time      IN      DATE      DEFAULT SYSDATE,  
    duration        IN      NUMBER   DEFAULT NULL,  
    next_time       IN      VARCHAR2 DEFAULT NULL,  
    latency         IN      NUMBER   DEFAULT 60);
```

Parameters

Table 17–32 *SCHEDULE_PROPAGATION Procedure Parameters*

Parameter	Description
queue_name	Name of the source queue whose messages are to be propagated, including the schema name. If the schema name is not specified, then it defaults to the schema name of the administrative user.
destination	Destination database link. Messages in the source queue for recipients at this destination are propagated. If it is NULL, then the destination is the local database and messages are propagated to other queues in the local database. The length of this field is currently limited to 128 bytes, and if the name is not fully qualified, then the default domain name is used.
start_time	Initial start time for the propagation window for messages from the source queue to the destination.
duration	Duration of the propagation window in seconds. A NULL value means the propagation window is forever or until the propagation is unscheduled.

Table 17–32 (Cont.) SCHEDULE_PROPAGATION Procedure Parameters

Parameter	Description
next_time	Date function to compute the start of the next propagation window from the end of the current window. If this value is <code>NULL</code> , then propagation is stopped at the end of the current window. For example, to start the window at the same time every day, next_time should be specified as <code>SYSDATE + 1 - duration/86400</code> .
latency	<p>Maximum wait, in seconds, in the propagation window for a message to be propagated after it is enqueued.</p> <p>For example, if the latency is 60 seconds and there are no messages to be propagated during the propagation window, then messages from that queue for the destination are not propagated for at least 60 more seconds.</p> <p>It is at least 60 seconds before the queue is checked again for messages to be propagated for the specified destination. If the latency is 600, then the queue is not checked for 10 minutes, and if the latency is 0, then a job queue process will be waiting for messages to be enqueued for the destination. As soon as a message is enqueued, it is propagated.</p>

Usage Notes

Messages may also be propagated to other queues in the same database by specifying a `NULL` destination. If a message has multiple recipients at the same destination in either the same or different queues, then the message is propagated to all of them at the same time.

SET_WATERMARK Procedure

This procedure is used for Oracle Streams AQ notification to specify and limit memory use.

Syntax

```
DBMS_AQADM.SET_WATERMARK (  
    wmvalue      IN      NUMBER);
```

Parameters

Table 17–33 *SET_WATERMARK Procedure Parameter*

Parameter	Description
wmvalue	Watermark value in megabytes.

START_QUEUE Procedure

This procedure enables the specified queue for enqueueing or dequeuing.

Syntax

```
DBMS_AQADM.START_QUEUE (
    queue_name      IN      VARCHAR2,
    enqueue         IN      BOOLEAN DEFAULT TRUE,
    dequeue         IN      BOOLEAN DEFAULT TRUE);
```

Parameters

Table 17–34 *START_QUEUE Procedure Parameters*

Parameter	Description
queue_name	Name of the queue to be enabled
enqueue	Specifies whether ENQUEUE should be enabled on this queue. TRUE means enable ENQUEUE. This is the default. FALSE means do not alter the current setting.
dequeue	Specifies whether DEQUEUE should be enabled on this queue. TRUE means enable DEQUEUE. This is the default. FALSE means do not alter the current setting.

Usage Notes

After creating a queue, the administrator must use `START_QUEUE` to enable the queue. The default is to enable it for both `ENQUEUE` and `DEQUEUE`. Only dequeue operations are allowed on an exception queue. This operation takes effect when the call completes and does not have any transactional characteristics.

STOP_QUEUE Procedure

This procedure disables enqueueing or dequeuing on the specified queue.

Syntax

```
DBMS_AQADM.STOP_QUEUE (  
    queue_name      IN   VARCHAR2,  
    enqueue         IN   BOOLEAN DEFAULT TRUE,  
    dequeue         IN   BOOLEAN DEFAULT TRUE,  
    wait            IN   BOOLEAN DEFAULT TRUE);
```

Parameters

Table 17–35 STOP_QUEUE Procedure Parameters

Parameter	Description
queue_name	Name of the queue to be disabled
enqueue	Specifies whether ENQUEUE should be disabled on this queue. TRUE means disable ENQUEUE. This is the default. FALSE means do not alter the current setting.
dequeue	Specifies whether DEQUEUE should be disabled on this queue. TRUE means disable DEQUEUE. This is the default. FALSE means do not alter the current setting.
wait	Specifies whether to wait for the completion of outstanding transactions. TRUE means wait if there are any outstanding transactions. In this state no new transactions are allowed to enqueue to or dequeue from this queue. FALSE means return immediately either with a success or an error.

Usage Notes

By default, this call disables both ENQUEUE and DEQUEUE. A queue cannot be stopped if there are outstanding transactions against the queue. This operation takes effect when the call completes and does not have any transactional characteristics.

UNSCHEDULE_PROPAGATION Procedure

This procedure unschedules previously scheduled propagation of messages from a queue to a destination identified by a specific database link.

Syntax

```
DBMS_AQADM.UNSCHEDULE_PROPAGATION (
  queue_name      IN  VARCHAR2,
  destination     IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 17–36 UNSCHEDULE_PROPAGATION Procedure Parameters

Parameter	Description
queue_name	Name of the source queue whose messages are to be propagated, including the schema name. If the schema name is not specified, then it defaults to the schema name of the administrative user.
destination	Destination database link. Messages in the source queue for recipients at this destination are propagated. If it is NULL, then the destination is the local database and messages are propagated to other queues in the local database. The length of this field is currently limited to 128 bytes, and if the name is not fully qualified, then the default domain name is used.

VERIFY_QUEUE_TYPES Procedure

This procedure verifies that the source and destination queues have identical types. The result of the verification is stored in the table `sys.aq$_message_types`, overwriting all previous output of this command.

Syntax

```
DBMS_AQADM.VERIFY_QUEUE_TYPES (
    src_queue_name    IN    VARCHAR2,
    dest_queue_name   IN    VARCHAR2,
    destination       IN    VARCHAR2 DEFAULT NULL,
    rc                OUT   BINARY_INTEGER);
```

Parameters

Table 17-37 VERIFY_QUEUE_TYPES Procedure Parameters

Parameter	Description
<code>src_queue_name</code>	Name of the source queue whose messages are to be propagated, including the schema name. If the schema name is not specified, then it defaults to the schema name of the user.
<code>dest_queue_name</code>	Name of the destination queue where messages are to be propagated, including the schema name. If the schema name is not specified, then it defaults to the schema name of the user.
<code>destination</code>	Destination database link. Messages in the source queue for recipients at this destination are propagated. If it is <code>NULL</code> , then the destination is the local database and messages are propagated to other queues in the local database. The length of this field is currently limited to 128 bytes, and if the name is not fully qualified, then the default domain name is used.
<code>rc</code>	Return code for the result of the procedure. If there is no error, and if the source and destination queue types match, then the result is 1. If they do not match, then the result is 0. If an Oracle error is encountered, then it is returned in <code>rc</code> .

The DBMS_AQELM package provides procedures to manage the configuration of Oracle Streams Advanced Queuing (AQ) asynchronous notification by e-mail and HTTP.

See Also: *Oracle Streams Advanced Queuing User's Guide and Reference* for detailed information about DBMS_AQELM

This chapter contains the following topic:

- [Summary of DBMS_AQELM Subprograms](#)

Summary of DBMS_AQELM Subprograms

Table 18–1 DBMS_ALERT Package Subprograms

Subprogram	Description
GET_MAILHOST Procedure on page 18-3	Gets the host name set by DBMS_AQELM.SET_MAILHOST for the SMTP server
GET_MAILPORT Procedure on page 18-4	Gets the port number for the SMTP server set by the DBMS_AQELM.SET_MAILPORT procedure or the default value, which is 25
GET_PROXY Procedure on page 18-5	Gets the proxy server name and no_proxy_domains set by DBMS_AQELM.SET_PROXY for HTTP notifications
GET_SENDFROM Procedure on page 18-6	Gets the sent-from e-mail address set by DBMS_AQELM.SET_SENDFROM procedure
SET_MAILHOST Procedure on page 18-7	Sets the host name for the SMTP server that the database will use to send out e-mail notifications
SET_MAILPORT Procedure on page 18-8	Sets the port number for the SMTP server
GET_MAILHOST Procedure on page 18-3	Gets the host name set by DBMS_AQELM.SET_MAILHOST for the SMTP server
SET_PROXY Procedure on page 18-9	Sets the proxy server name to be used for requests of HTTP protocol, excluding requests for hosts that belong to the domain specified in no_proxy_domains
SET_SENDFROM Procedure on page 18-11	Sets the sent-from e-mail address

GET_MAILHOST Procedure

This procedure gets the host name set by DBMS_AQELM.SET_MAILHOST for the SMTP server.

Syntax

```
DBMS_AQELM.GET_MAILHOST (  
    mailhost OUT VARCHAR2);
```

Parameters

Table 18–2 *GET_MAILHOST Procedure Parameters*

Parameter	Description
mailhost	SMTP server host name.

GET_MAILPORT Procedure

This procedure gets the port number for the SMTP server set by the DBMS_AQELM.SET_MAILPORT procedure or the default value, which is 25.

Syntax

```
DBMS_AQELM.GET_MAILPORT (  
    mailport OUT NUMBER);
```

Parameters

Table 18–3 *GET_MAILPORT Procedure Parameters*

Parameter	Description
mailport	SMTP server port number.

GET_PROXY Procedure

This procedure gets the proxy server name and `no_proxy_domains` set by `DBMS_AQELM.SET_PROXY` for HTTP notifications.

Syntax

```
DBMS_AQELM.GET_PROXY (  
    proxy          OUT VARCHAR2,  
    no_proxy_domains OUT VARCHAR2);
```

Parameters

Table 18–4 *GET_PROXY Procedure Parameters*

Parameter	Description
<code>proxy</code>	Proxy server host and port number.
<code>no_proxy_domains</code>	List of no-proxy domains or hosts.

GET_SENDFROM Procedure

This procedure gets the sent-from e-mail address set by DBMS_AQELM.SET_SENDFROM procedure.

Syntax

```
DBMS_AQELM.GET_SENDFROM (  
    sendfrom OUT VARCHAR2);
```

Parameters

Table 18–5 *GET_SENDFROM Procedure Parameters*

Parameter	Description
sendfrom	The sent-from e-mail address.

SET_MAILHOST Procedure

This procedure sets the host name for the SMTP server. The database uses this SMTP server host name to send out e-mail notifications.

Syntax

```
DBMS_AQELM.SET_MAILHOST (  
    mailhost IN VARCHAR2);
```

Parameters

Table 18–6 *SET_MAILHOST Procedure Parameters*

Parameter	Description
mailhost	SMTP server host name.

Usage Notes

As part of the configuration for e-mail notifications, a user with AQ_ADMINISTRATOR_ROLE or with EXECUTE permissions on the DBMS_AQELM package needs to set the host name before registering for e-mail notifications.

SET_MAILPORT Procedure

This procedure sets the port number for the SMTP server.

Syntax

```
DBMS_AQELM.SET_MAILPORT (  
    mailport IN NUMBER);
```

Parameters

Table 18–7 *SET_MAILPORT Procedure Parameters*

Parameter	Description
mailport	SMTP server port number.

Usage Notes

As part of the configuration for e-mail notifications, a user with AQ_ADMINISTRATOR_ROLE or with EXECUTE permissions on DBMS_AQELM package needs to set the port number before registering for e-mail notifications. The database uses this SMTP server port number to send out e-mail notifications. If not set, the SMTP mailport defaults to 25

SET_PROXY Procedure

This procedure sets the proxy server name to be used for requests of HTTP protocol, excluding requests for hosts that belong to the domain specified in `no_proxy_domains`.

Syntax

```
DBMS_AQELM.SET_PROXY (
    proxy          IN VARCHAR2,
    no_proxy_domains IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 18–8 *SET_PROXY Procedure Parameters*

Parameter	Description
<code>proxy</code>	Proxy server host and port number. The syntax is "[http://]host[:port][/]". For example, "www-proxy.my-company.com:80".
<code>no_proxy_domains</code>	List of no-proxy domains or hosts. The syntax is a list of host or domains, with optional port numbers separated by a comma, a semi-colon, or a space. For example, "corp.my-company.com, eng.my-company.com:80".

Usage Notes

The proxy server name can include an optional TCP/IP port number at which the proxy server listens. If the port is not specified for the proxy server, port 80 is assumed.

`no_proxy_domains` is a list of domains or hosts for which HTTP requests should be sent directly to the destination HTTP server instead of going through a proxy server. Optionally, a port number can be specified for each domain or host. If the port number is specified, the no-proxy restriction is only applied to the request at that port of the particular domain or host. When `no_proxy_domains` is NULL and the proxy server is set, all requests go through the proxy server. When the proxy server is not set, `http_send` sends the requests to the target Web servers directly.

As part of the configuration for HTTP notifications, a user with `AQ_ADMINISTRATOR_ROLE` or with `EXECUTE` permissions on the `DBMS_AQELM` package can choose to set the proxy server name and a list of `no_proxy_domains`,

if required, before registering for HTTP notifications. The database will use this information to post HTTP notifications.

SET_SENDFROM Procedure

This procedure sets the sent-from e-mail address. This e-mail address is used in the sent-from field in all the e-mail notifications sent out by the database to the registered e-mail addresses.

Syntax

```
DBMS_AQELM.SET_SENDFROM (  
    sendfrom IN VARCHAR2);
```

Parameters

Table 18–9 *SET_SENDFROM Procedure Parameters*

Parameter	Description
sendfrom	The sent-from e-mail address.

Usage Notes

As part of the configuration for e-mail notifications, a user with AQ_ADMINISTRATOR_ROLE or with EXECUTE permissions on the DBMS_AQELM package should set the sent-from address before registering for e-mail notifications

DBMS_CAPTURE_ADM

The `DBMS_CAPTURE_ADM` package, one of a set of Streams packages, provides administrative interfaces for starting, stopping, and configuring a capture process. The source of the captured changes is the redo logs, and the repository for the captured changes is a queue (created using the `DBMS_STREAMS_ADM.SET_UP_QUEUE` procedure or the `DBMS_AQADM` package).

See Also: *Oracle Streams Concepts and Administration* and *Oracle Streams Replication Administrator's Guide* for more information about this package and capture processes

This chapter contains the following topic:

- [Summary of DBMS_CAPTURE_ADM Subprograms](#)

Summary of DBMS_CAPTURE_ADM Subprograms

Table 19–1 DBMS_CAPTURE_ADM Package Subprograms

Subprogram	Description
ABORT_GLOBAL_INSTANTIATION Procedure on page 19-4	Reverses the effects of running the <code>PREPARE_GLOBAL_INSTANTIATION</code> procedure
ABORT_SCHEMA_INSTANTIATION Procedure on page 19-5	Reverses the effects of running the <code>PREPARE_SCHEMA_INSTANTIATION</code> procedure
ABORT_TABLE_INSTANTIATION Procedure on page 19-6	Reverses the effects of running the <code>PREPARE_TABLE_INSTANTIATION</code> procedure
ALTER_CAPTURE Procedure on page 19-7	Alters a capture process
BUILD Procedure on page 19-14	Extracts the data dictionary of the current database to the redo logs and automatically specifies database supplemental logging for all primary key and unique key columns
CREATE_CAPTURE Procedure on page 19-16	Creates a capture process
DROP_CAPTURE Procedure on page 19-23	Drops a capture process
INCLUDE_EXTRA_ATTRIBUTE Procedure on page 19-25	Includes or excludes an extra attribute in logical change records (LCRs) captured by the specified capture process
PREPARE_GLOBAL_INSTANTIATION Procedure on page 19-27	Performs the synchronization necessary for instantiating all the tables in the database at another database
PREPARE_SCHEMA_INSTANTIATION Procedure on page 19-28	Performs the synchronization necessary for instantiating all tables in the schema at another database
PREPARE_TABLE_INSTANTIATION Procedure on page 19-29	Performs the synchronization necessary for instantiating the table at another database
SET_PARAMETER Procedure on page 19-30	Sets a capture process parameter to the specified value

Table 19–1 (Cont.) DBMS_CAPTURE_ADM Package Subprograms

Subprogram	Description
START_CAPTURE Procedure on page 19-33	Starts the capture process, which mines redo logs and enqueues the mined redo information into the associated queue
STOP_CAPTURE Procedure on page 19-34	Stops the capture process from mining redo logs

Note: All procedures commit unless specified otherwise.

ABORT_GLOBAL_INSTANTIATION Procedure

This procedure reverses the effects of running the `PREPARE_GLOBAL_INSTANTIATION` procedure. Specifically, running this procedure removes data dictionary information related to the database instantiation.

Syntax

```
DBMS_CAPTURE_ADM.ABORT_GLOBAL_INSTANTIATION( );
```

ABORT_SCHEMA_INSTANTIATION Procedure

This procedure reverses the effects of running the `PREPARE_SCHEMA_INSTANTIATION` procedure. Specifically, running this procedure removes data dictionary information related to the schema instantiation.

Syntax

```
DBMS_CAPTURE_ADM.ABORT_SCHEMA_INSTANTIATION(  
    schema_name IN VARCHAR2);
```

Parameter

Table 19–2 *ABORT_SCHEMA_INSTANTIATION Procedure Parameter*

Parameter	Description
schema_name	The name of the schema for which to abort the effects of preparing instantiation.

ABORT_TABLE_INSTANTIATION Procedure

This procedure reverses the effects of running the `PREPARE_TABLE_INSTANTIATION` procedure. Specifically, running this procedure removes data dictionary information related to the table instantiation.

Syntax

```
DBMS_CAPTURE_ADM.ABORT_TABLE_INSTANTIATION(  
    table_name IN VARCHAR2);
```

Parameter

Table 19–3 *ABORT_TABLE_INSTANTIATION Procedure Parameter*

Parameter	Description
<code>table_name</code>	The name of the table for which to abort the effects of preparing instantiation, specified as [<i>schema_name</i> .] <i>object_name</i> . For example, <code>hr.employees</code> . If the schema is not specified, then the current user is the default.

ALTER_CAPTURE Procedure

This procedure alters a capture process.

See Also: *Oracle Streams Concepts and Administration* for more information about altering a capture process

Syntax

```
DBMS_CAPTURE_ADM.ALTER_CAPTURE(
  capture_name          IN VARCHAR2,
  rule_set_name         IN VARCHAR2 DEFAULT NULL,
  remove_rule_set      IN BOOLEAN  DEFAULT false,
  start_scn             IN NUMBER   DEFAULT NULL,
  use_database_link    IN BOOLEAN  DEFAULT NULL,
  first_scn            IN NUMBER   DEFAULT NULL,
  negative_rule_set_name IN VARCHAR2 DEFAULT NULL,
  remove_negative_rule_set IN BOOLEAN  DEFAULT false,
  capture_user         IN VARCHAR2  DEFAULT NULL);
```

Parameters

Table 19–4 ALTER_CAPTURE Procedure Parameters

Parameter	Description
capture_name	The name of the capture process being altered. You must specify an existing capture process name. Do not specify an owner.

Table 19–4 (Cont.) ALTER_CAPTURE Procedure Parameters

Parameter	Description
<code>rule_set_name</code>	<p>The name of the positive rule set for the capture process. The positive rule set contains the rules that instruct the capture process to capture changes.</p> <p>If you want to use a positive rule set for the capture process, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a positive rule set in the HR schema named <code>job_capture_rules</code>, enter <code>hr.job_capture_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code> and the <code>remove_rule_set</code> parameter is set to <code>false</code>, then retains any existing positive rule set. If you specify <code>NULL</code> and the <code>remove_rule_set</code> parameter is set to <code>true</code>, then removes any existing positive rule set.</p> <p>See Also: <i>Oracle Streams Concepts and Administration</i> for more information about the changes that can be captured by a capture process</p>
<code>remove_rule_set</code>	<p>If <code>true</code>, then removes the positive rule set for the specified capture process. If you remove a positive rule set for a capture process, and the capture process does not have a negative rule set, then the capture process captures all supported changes to all objects in the database, excluding database objects in the <code>SYS</code> and <code>SYSTEM</code> schemas.</p> <p>If you remove a positive rule set for a capture process, and the capture process has a negative rule set, then the capture process captures all supported changes that are not discarded by the negative rule set.</p> <p>If <code>false</code>, then retains the positive rule set for the specified capture process.</p> <p>If the <code>rule_set_name</code> parameter is non-<code>NULL</code>, then this parameter should be set to <code>false</code>.</p>

Table 19–4 (Cont.) ALTER_CAPTURE Procedure Parameters

Parameter	Description
<code>start_scn</code>	A valid SCN for the database from which the capture process should start capturing changes. The SCN value specified must be greater than or equal to the first SCN for the capture process. An error is returned if an invalid SCN is specified.
<code>use_database_link</code>	<p>If <code>true</code>, then specifies that the capture process at a downstream database uses a database link to the source database for administrative purposes relating to the capture process. If you want a capture process that is not using a database link currently to begin using a database link, then specify <code>true</code>. In this case, a database link with the same name as the global name of the source database must exist at the downstream database.</p> <p>If <code>false</code>, then specifies either that the capture process is running on the source database or that the capture process at a downstream database does not use a database link to the source database. If you want a capture process that is using a database link currently to stop using a database link, then specify <code>false</code>. In this case, you must prepare source database objects for instantiation manually when you add or change capture process rules that pertain to these objects.</p> <p>If <code>NULL</code>, then the current value of this parameter for the capture process is not changed.</p>

Table 19–4 (Cont.) ALTER_CAPTURE Procedure Parameters

Parameter	Description
<code>first_scn</code>	<p>Specifies the lowest SCN in the redo log from which a capture process can capture changes. If you specify a new first SCN for the capture process, then the specified first SCN must meet the following requirements:</p> <ul style="list-style-type: none">■ It must be greater than the current first SCN for the capture process.■ It must be less than or equal to the current applied SCN for the capture process. However, this requirement does not apply if the current applied SCN for the capture process is zero.■ It must be less than or equal to the required checkpoint SCN for the capture process. <p>An error is returned if the specified SCN does not meet the first three requirements. See "Usage Notes" on page 19-13 for information about determining an SCN value that meets all of these conditions.</p> <p>When the first SCN is modified, the capture process purges information from its LogMiner data dictionary that is required to restart it at an earlier SCN.</p> <p>Also, if the specified first SCN is higher than the current start SCN for the capture process, then the start SCN is set automatically to the new value of the first SCN.</p>

Table 19–4 (Cont.) ALTER_CAPTURE Procedure Parameters

Parameter	Description
negative_rule_set_name	<p>The name of the negative rule set for the capture process. The negative rule set contains the rules that instruct the capture process to discard changes.</p> <p>If you want to use a negative rule set for the capture process, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a negative rule set in the <code>hr</code> schema named <code>neg_capture_rules</code>, enter <code>hr.neg_capture_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code> and the <code>remove_negative_rule_set</code> parameter is set to <code>false</code>, then retains any existing negative rule set. If you specify <code>NULL</code> and the <code>remove_negative_rule_set</code> parameter is set to <code>true</code>, then removes any existing negative rule set.</p> <p>If you specify both a positive and a negative rule set for a capture process, then the negative rule set is always evaluated first.</p>
remove_negative_rule_set	<p>If <code>true</code>, then removes the negative rule set for the specified capture process. If you remove a negative rule set for a capture process, and the capture process does not have a positive rule set, then the capture process captures all supported changes to all objects in the database, excluding database objects in the <code>SYS</code> and <code>SYSTEM</code> schemas.</p> <p>If you remove a negative rule set for a capture process, and a positive rule set exists for the capture process, then the capture process captures all changes that are not discarded by the positive rule set.</p> <p>If <code>false</code>, then retains the negative rule set for the specified capture process.</p> <p>If the <code>negative_rule_set_name</code> parameter is non-<code>NULL</code>, then this parameter should be set to <code>false</code>.</p>

Table 19–4 (Cont.) ALTER_CAPTURE Procedure Parameters

Parameter	Description
capture_user	<p>The user who captures DML and DDL changes that satisfy the capture process rule sets. If NULL, then the capture user is not changed.</p> <p>To change the capture user, the user who invokes the ALTER_CAPTURE procedure must be granted DBA role. Only the SYS user can set the capture_user to SYS.</p> <p>If you change the capture user, then this procedure grants the new capture user enqueue privilege on the queue used by the capture process and configures the user as a secure queue user of the queue. In addition, make sure the capture user has the following privileges:</p> <ul style="list-style-type: none"> ■ Execute privilege on the rule sets used by the capture process ■ Execute privilege on all rule-based transformation functions used in the rule set ■ Execute privilege on all packages, including Oracle-supplied packages, that are invoked in rule-based transformations run by the capture process <p>These privileges must be granted directly to the capture user. They cannot be granted through roles.</p> <p>By default, this parameter is set to the user who created the capture process by running either the CREATE_CAPTURE procedure in this package or one of the following procedures in the DBMS_STREAMS_ADM package with the streams_type parameter set to capture:</p> <ul style="list-style-type: none"> ■ ADD_GLOBAL_RULES ■ ADD_SCHEMA_RULES ■ ADD_TABLE_RULES ■ ADD_SUBSET_RULES <p>Note: If the specified user is dropped using DROP USER . . . CASCADE, then the capture_user setting for the capture process is set to NULL automatically. You must specify a capture user before the capture process can run.</p>

Usage Notes

If you want to alter the first SCN for a capture process, then value specified must meet the conditions in the description for the `first_scn` parameter. The following query determines the current first SCN, applied SCN, and required checkpoint SCN for each capture process in a database:

```
SELECT CAPTURE_NAME, FIRST_SCN, APPLIED_SCN, REQUIRED_CHECKPOINT_SCN
       FROM DBA_CAPTURE;
```

Also, a capture process is stopped and restarted automatically when you change the value of one or more of the following `ALTER_CAPTURE` procedure parameters:

- `start_scn`
- `capture_user`

BUILD Procedure

This procedure extracts the data dictionary of the current database to the redo log and automatically specifies database supplemental logging by running the following SQL statement:

```
ALTER DATABASE ADD SUPPLEMENTAL LOG DATA;
```

Syntax

```
DBMS_CAPTURE_ADM.BUILD(  
    first_scn OUT NUMBER);
```

Note: This procedure is overloaded. One version of this procedure contains the OUT parameter `first_scn`, and the other does not.

Parameters

Table 19–5 *BUILD Procedure Parameter*

Parameter	Description
<code>first_scn</code>	Contains the lowest SCN value corresponding to the data dictionary extracted to the redo log that can be specified as a first SCN for a capture process

Usage Notes

You can run this procedure multiple times at a source database.

If you plan to capture changes originating at a source database with a capture process, then this procedure must be executed at the source database at least once. When the capture process is started, either at a local source database or at a downstream database, the capture process uses the extracted information in the redo log to create a LogMiner data dictionary.

After executing this procedure, you can query the `FIRST_CHANGE#` column of the `V$ARCHIVED_LOG` dynamic performance view where the `DICTIONARY_BEGIN` column is `YES` to determine the lowest SCN value for the database that can be specified as a first SCN for a capture process. The first SCN for a capture process is the lowest SCN in the redo log from which the capture process can capture changes. You can specify the first SCN for a capture process when you run the

`CREATE_CAPTURE` or `ALTER_CAPTURE` **procedure in the** `DBMS_CAPTURE_ADM` **package.**

CREATE_CAPTURE Procedure

This procedure creates a capture process.

See Also:

- *Oracle Streams Concepts and Administration* for more information about creating a capture process
- [Chapter 82, "DBMS_RULE_ADM"](#) for more information about rules and rule sets

Syntax

```
DBMS_CAPTURE_ADM.CREATE_CAPTURE(
  queue_name          IN  VARCHAR2,
  capture_name       IN  VARCHAR2,
  rule_set_name      IN  VARCHAR2  DEFAULT NULL,
  start_scn          IN  NUMBER    DEFAULT NULL,
  source_database    IN  VARCHAR2  DEFAULT NULL,
  use_database_link  IN  BOOLEAN   DEFAULT false,
  first_scn          IN  NUMBER    DEFAULT NULL,
  logfile_assignment IN  VARCHAR2  DEFAULT 'implicit',
  negative_rule_set_name IN VARCHAR2  DEFAULT NULL,
  capture_user       IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 19–6 CREATE_CAPTURE Procedure Parameters

Parameter	Description
queue_name	The name of the queue into which the capture process enqueues changes. You must specify an existing queue in the form [<i>schema_name</i> .] <i>queue_name</i> . For example, to specify a queue in the hr schema named streams_queue, enter hr.streams_queue. If the schema is not specified, then the current user is the default. Note: The queue_name setting cannot be altered after the capture process is created.
capture_name	The name of the capture process being created. A NULL specification is not allowed. Do not specify an owner. Note: The capture_name setting cannot be altered after the capture process is created.

Table 19–6 (Cont.) CREATE_CAPTURE Procedure Parameters

Parameter	Description
rule_set_name	<p>The name of the positive rule set for the capture process. The positive rule set contains the rules that instruct the capture process to capture changes.</p> <p>If you want to use a positive rule set for the capture process, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a positive rule set in the <code>hr</code> schema named <code>job_capture_rules</code>, enter <code>hr.job_capture_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code>, and no negative rule set is specified, then the capture process captures all supported changes to all objects in the database, excluding database objects in the <code>SYS</code> and <code>SYSTEM</code> schemas.</p> <p>If you specify <code>NULL</code>, and a negative rule set exists for the capture process, then the capture process captures all changes that are not discarded by the negative rule set.</p> <p>See Also: <i>Oracle Streams Concepts and Administration</i> for more information about the changes that can be captured by a capture process</p>
start_scn	<p>A valid SCN for the database from which the capture process should start capturing changes. If the specified value is lower than the current SCN of the source database, then either the <code>first_scn</code> should be specified, or the SCN value specified for <code>start_scn</code> must be greater than or equal to the first SCN of an existing capture process which has taken at least one checkpoint.</p> <p>If <code>start_scn</code> is <code>NULL</code> and no value is specified for the <code>first_scn</code> parameter, then the database's current SCN is used as start SCN. If <code>start_scn</code> is <code>NULL</code> and a non-<code>NULL</code> value is specified for the <code>first_scn</code> parameter, then the <code>first_scn</code> value is used.</p> <p>If a value is specified for both <code>start_scn</code> and <code>first_scn</code>, then the <code>start_scn</code> value must be greater than or equal to the <code>first_scn</code> value.</p> <p>An error is returned if an invalid SCN is specified.</p>

Table 19–6 (Cont.) CREATE_CAPTURE Procedure Parameters

Parameter	Description
<code>source_database</code>	<p>The global name of the source database. The source database is where the changes to be captured originated.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p> <p>If <code>NULL</code>, or if the specified name is the same as the global name of the current database, then local capture is assumed and only the default values for <code>use_database_link</code> and <code>first_scn</code> can be specified.</p>
<code>use_database_link</code>	<p>If <code>true</code>, then specifies that the capture process at a downstream database uses a database link to the source database for administrative purposes relating to the capture process. The capture process uses the database link to prepare database objects for instantiation at the source database and run the <code>DBMS_CAPTURE_ADM.BUILD</code> procedure at the source database, if necessary.</p> <p>If <code>false</code>, then specifies either that the capture process is running on the source database or that the capture process at a downstream database does not use a database link to the source database. In this case, you must perform the following administrative tasks manually:</p> <ul style="list-style-type: none">■ Run the <code>DBMS_CAPTURE_ADM.BUILD</code> procedure at the source database to extract the data dictionary at the source database to the redo log when a capture process is created■ Obtain the first SCN for the downstream capture process if the first SCN is not specified during capture process creation. The first SCN is needed to create and maintain a capture process.■ Prepare source database objects for instantiation

Table 19–6 (Cont.) CREATE_CAPTURE Procedure Parameters

Parameter	Description
<code>first_scn</code>	<p>Specifies the lowest SCN in the redo log from which a capture process can capture changes. A non-NULL value for this parameter is valid only if the <code>DBMS_CAPTURE_ADM.BUILD</code> procedure has been run at least once at the source database.</p> <p>You can query the <code>FIRST_CHANGE#</code> column of the <code>V\$ARCHIVED_LOG</code> dynamic performance view where the <code>DICTIONARY_BEGIN</code> column is <code>YES</code> to determine whether the <code>DBMS_CAPTURE_ADM.BUILD</code> procedure has been run on a source database. Any of the values returned by such a query can be used as a <code>first_scn</code> value if the redo log containing that SCN value is still available.</p>
<code>logfile_assignment</code>	<p>If <code>implicit</code>, the default, then the capture process at a downstream database scans all redo log files added by log transport services or manually from the source database to the downstream database.</p> <p>If <code>explicit</code>, then a redo log file is scanned by a capture process at a downstream database only if the capture process name is specified in the <code>FOR logminer_session_name</code> clause when the redo log file is added manually to the downstream database. If <code>explicit</code>, then log transport services cannot be used to add redo log files to the capture process being created.</p> <p>If you specify <code>explicit</code> for this parameter for a local capture process, then the local capture process cannot use the online redo log to find changes. In this case, the capture process must use the archived redo log.</p> <p>See Also: "Usage Notes" on page 19-20 for information about adding redo log files manually</p>

Table 19–6 (Cont.) CREATE_CAPTURE Procedure Parameters

Parameter	Description
<code>negative_rule_set_name</code>	<p>The name of the negative rule set for the capture process. The negative rule set contains the rules that instruct the capture process to discard changes.</p> <p>If you want to use a negative rule set for the capture process, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a negative rule set in the <code>hr</code> schema named <code>neg_capture_rules</code>, enter <code>hr.neg_capture_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>If you specify <code>NULL</code>, and no positive rule set is specified, then the capture process captures all supported changes to all objects in the database, excluding database objects in the <code>SYS</code> and <code>SYSTEM</code> schemas.</p> <p>If you specify <code>NULL</code>, and a positive rule set exists for the capture process, then the capture process captures all changes that are not discarded by the positive rule set.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify both a positive and a negative rule set for a capture process, then the negative rule set is always evaluated first.</p>
<code>capture_user</code>	<p>The user who captures DML and DDL changes that satisfy the capture process rule sets. If <code>NULL</code>, then the user who runs the <code>CREATE_CAPTURE</code> procedure is used.</p> <p>Only a user who is granted <code>DBA</code> role can set a capture user. Only the <code>SYS</code> user can set the <code>capture_user</code> to <code>SYS</code>.</p> <p>Note: If the specified user is dropped using <code>DROP USER . . . CASCADE</code>, then the <code>capture_user</code> setting for the capture process is set to <code>NULL</code> automatically. You must specify a capture user before the capture process can run.</p>

Usage Notes

The user who invokes this procedure must be granted `DBA` role.

The `capture_user` parameter specifies the user who captures changes that satisfy the capture process rule sets. This user must have the necessary privileges to capture changes. This procedure grants the capture user `enqueue` privilege on the

queue used by the capture process and configures the user as a secure queue user of the queue.

In addition, make sure the capture user has the following privileges:

- Execute privilege on the rule sets used by the capture process
- Execute privilege on all rule-based transformation functions used in the rule set
- Execute privilege on all packages, including Oracle-supplied packages, that are invoked in rule-based transformations run by the capture process

These privileges must be granted directly to the capture user. They cannot be granted through roles.

Note:

- A capture user does not require privileges on a database object to capture changes to the database object. The capture process may pass these changes to a rule-based transformation function. Therefore, make sure you consider security implications when you configure a capture process.
 - Creation of the first capture process in a database may take some time because the data dictionary is duplicated during this creation.
-
-

If you specify `explicit` for the `logfile_assignment` parameter, then you add a redo log file manually to a downstream database using the following statement:

```
ALTER DATABASE REGISTER LOGICAL LOGFILE  
  file_name FOR capture_process;
```

Here, *file_name* is the name of the redo log file being added and *capture_process* is the name of the capture process that will use the redo log file at the downstream database. The *capture_process* is equivalent to the *logminer_session_name* and must be specified. The redo log file must be present at the site running the downstream database. You must transfer this file manually to the site running the downstream database using the `DBMS_FILE_TRANSFER` package, FTP, or some other transfer method.

See Also: *Oracle Database SQL Reference* for more information about the ALTER DATABASE statement and *Oracle Data Guard Concepts and Administration* for more information registering redo log files

DROP_CAPTURE Procedure

This procedure drops a capture process.

See Also:

- ["STOP_CAPTURE Procedure"](#) on page 19-34
- *Oracle Streams Concepts and Administration* for more information about Streams data dictionary views

Syntax

```
DBMS_CAPTURE_ADM.DROP_CAPTURE(
  capture_name          IN VARCHAR2,
  drop_unused_rule_sets IN BOOLEAN DEFAULT false);
```

Parameters

Table 19–7 DROP_CAPTURE Procedure Parameters

Parameter	Description
capture_name	The name of the capture process being dropped. Specify an existing capture process name. Do not specify an owner.
drop_unused_rule_sets	If <code>true</code> , then drops any rule sets, positive and negative, used by the specified capture process if these rule sets are not used by any other Streams client, which includes capture processes, propagations, apply processes, and messaging clients. If this procedure drops a rule set, then this procedure also drops any rules in the rule set that are not in another rule set. If <code>false</code> , then does not drop the rule sets used by the specified capture process, and the rule sets retain their rules.

Usage Notes

When you use this procedure to drop a capture process, information about rules created for the capture process using the `DBMS_STREAMS_ADM` package is removed from the data dictionary views for Streams rules. Information about such a rule is removed even if the rule is not in either rule set for the capture process.

The following are the data dictionary views for Streams rules:

- `ALL_STREAMS_GLOBAL_RULES`

- DBA_STREAMS_GLOBAL_RULES
- ALL_STREAMS_MESSAGE_RULES
- DBA_STREAMS_MESSAGE_RULES
- ALL_STREAMS_SCHEMA_RULES
- DBA_STREAMS_SCHEMA_RULES
- ALL_STREAMS_TABLE_RULES
- DBA_STREAMS_TABLE_RULES

Note: A capture process must be stopped before it can be dropped.

INCLUDE_EXTRA_ATTRIBUTE Procedure

This procedure includes or excludes an extra attribute in logical change records (LCRs) captured by the specified capture process.

Syntax

```
DBMS_CAPTURE_ADM.INCLUDE_EXTRA_ATTRIBUTE(  
    capture_name    IN  VARCHAR2,  
    attribute_name  IN  VARCHAR2,  
    include         IN  BOOLEAN  DEFAULT true);
```

Parameters

Table 19–8 *INCLUDE_EXTRA_ATTRIBUTE Procedure Parameters*

Parameter	Description
capture_name	The name of the capture process. Specify an existing capture process name. Do not specify an owner.

Table 19–8 INCLUDE_EXTRA_ATTRIBUTE Procedure Parameters

Parameter	Description
<code>attribute_name</code>	<p>The name of the attribute to be included in or excluded from LCRs captured by the capture process. The following names are valid settings:</p> <ul style="list-style-type: none"> ■ <code>row_id</code> The rowid of the row changed in a row LCR. This attribute is not included in DDL LCRs, nor in row LCRs for index-organized tables. The type is <code>VARCHAR2</code>. ■ <code>serial#</code> The serial number of the session that performed the change captured in the LCR. The type is <code>NUMBER</code>. ■ <code>session#</code> The identifier of the session that performed the change captured in the LCR. The type is <code>NUMBER</code>. ■ <code>thread#</code> The thread number of the instance in which the change captured in the LCR was performed. Typically, the thread number is relevant only in a Real Application Clusters environment. The type is <code>NUMBER</code>. ■ <code>tx_name</code> The name of the transaction that includes the LCR. The type is <code>VARCHAR2</code>. ■ <code>username</code> The name of the user who performed the change captured in the LCR. The type is <code>VARCHAR2</code>.
<code>include</code>	<p>If <code>true</code>, then the specified attribute is included in LCRs captured by the capture process</p> <p>If <code>false</code>, then the specified attribute is excluded from LCRs captured by the capture process</p>

Usage Notes

The redo log contains information about each change made to a database, and some of this information is not captured by a capture process unless you use this procedure to instruct a capture process to capture it. This procedure enables you to specify extra information in the redo log that a capture process should capture. If you want to exclude an extra attribute that is being captured by a capture process, then specify the attribute and specify `false` for the `include` parameter.

PREPARE_GLOBAL_INSTANTIATION Procedure

This procedure performs the synchronization necessary for instantiating all the tables in the database at another database.

This procedure records the lowest SCN of each object in the database for instantiation. SCNs subsequent to the lowest SCN for an object can be used for instantiating the object. Running this procedure prepares all current and future objects in the database for instantiation.

Syntax

```
DBMS_CAPTURE_ADM.PREPARE_GLOBAL_INSTANTIATION;
```

Usage Notes

Run this procedure at the source database.

If you use a capture process to capture all of the changes to a database, then use this procedure to prepare the tables in the database for instantiation after the capture process has been configured.

PREPARE_SCHEMA_INSTANTIATION Procedure

This procedure performs the synchronization necessary for instantiating all tables in the schema at another database.

This procedure records the lowest SCN of each object in the schema for instantiation. SCNs subsequent to the lowest SCN for an object can be used for instantiating the object. Running this procedure prepares all current and future objects in the schema for instantiation.

Syntax

```
DBMS_CAPTURE_ADM.PREPARE_SCHEMA_INSTANTIATION(  
    schema_name IN VARCHAR2);
```

Parameter

Table 19–9 *PREPARE_SCHEMA_INSTANTIATION Procedure Parameter*

Parameter	Description
schema_name	The name of the schema. For example, hr.

Usage Notes

Run this procedure at the source database. If you use a capture process to capture all of the changes to schema, then use this procedure to prepare the tables in the schema for instantiation after the capture process has been configured.

PREPARE_TABLE_INSTANTIATION Procedure

This procedure performs the synchronization necessary for instantiating the table at another database.

This procedure records the lowest SCN of the table for instantiation. SCNs subsequent to the lowest SCN for an object can be used for instantiating the object.

Syntax

```
DBMS_CAPTURE_ADM.PREPARE_TABLE_INSTANTIATION(  
    table_name IN VARCHAR2);
```

Parameters

Table 19–10 *PREPARE_TABLE_INSTANTIATION Procedure Parameter*

Parameter	Description
table_name	The name of the table specified as [<i>schema_name</i> .] <i>object_name</i> . For example, <i>hr.employees</i> . If the schema is not specified, then the current user is the default.

Usage Notes

Run this procedure at the source database. If you use a capture process to capture all of the changes to schema, then use this procedure to prepare the tables in the schema for instantiation after the capture process has been configured.

SET_PARAMETER Procedure

This procedure sets a capture process parameter to the specified value.

Syntax

```
DBMS_CAPTURE_ADM.SET_PARAMETER(  
    capture_name IN VARCHAR2,  
    parameter    IN VARCHAR2,  
    value        IN VARCHAR2);
```

Parameters

Table 19–11 SET_PARAMETER Procedure Parameters

Parameter	Description
capture_name	The name of the capture process. Do not specify an owner. The capture process uses LogMiner to capture changes from the redo logs.
parameter	The name of the parameter you are setting. See " Capture Process Parameters " on page 19-30 for a list of these parameters.
value	The value to which the parameter is set

Usage Notes

When you alter a parameter value, a short amount of time may pass before the new value for the parameter takes effect.

Capture Process Parameters

The following table lists the parameters for the capture process.

Table 19–12 Capture Process Parameters

Parameter Name	Possible Values	Default	Description
<code>disable_on_limit</code>	Y or N	N	<p>If Y, then the capture process is disabled if the capture process terminates because it reached a value specified by the <code>time_limit</code> parameter or <code>message_limit</code> parameter.</p> <p>If N, then the capture process is restarted immediately after stopping because it reached a limit.</p>
<code>maximum_scn</code>	A valid SCN or <code>infinite</code>	<code>infinite</code>	<p>The capture process is disabled before capturing a change record with an SCN greater than or equal to the value specified.</p> <p>If <code>infinite</code>, then the capture process runs regardless of the SCN value.</p>
<code>message_limit</code>	A positive integer or <code>infinite</code>	<code>infinite</code>	<p>The capture process stops after capturing the specified number of messages.</p> <p>If <code>infinite</code>, then the capture process continues to run regardless of the number of messages captured.</p>
<code>parallelism</code>	A positive integer	1	<p>The number of parallel execution servers that may concurrently mine the redo log</p> <p>Note:</p> <ul style="list-style-type: none"> ■ When you change the value of this parameter, the capture process is stopped and restarted automatically. ■ Setting the <code>parallelism</code> parameter to a number higher than the number of available parallel execution servers may disable the capture process. Make sure the <code>PROCESSES</code> and <code>PARALLEL_MAX_SERVERS</code> initialization parameters are set appropriately when you set the <code>parallelism</code> capture process parameter.

Table 19–12 (Cont.) Capture Process Parameters

Parameter Name	Possible Values	Default	Description
startup_seconds	0, a positive integer, or infinite	0	<p>The maximum number of seconds to wait for another instantiation of the same capture process to finish. If the other instantiation of the same capture process does not finish within this time, then the capture process does not start. This parameter is useful only if you are starting the capture process manually.</p> <p>If <i>infinite</i>, then a capture process does not start until another instantiation of the same capture process finishes.</p>
time_limit	A positive integer or infinite	infinite	<p>The capture process stops as soon as possible after the specified number of seconds since it started.</p> <p>If <i>infinite</i>, then the capture process continues to run until it is stopped explicitly.</p>
trace_level	0 or a positive integer	0	Set this parameter only under the guidance of Oracle Support Services.
write_alert_log	Y or N	Y	<p>If <i>Y</i>, then the capture process writes a message to the alert log on exit.</p> <p>If <i>N</i>, then the capture process does not write a message to the alert log on exit.</p> <p>The message specifies the reason the capture process stopped.</p>

Note:

- For all parameters that are interpreted as positive integers, the maximum possible value is 4,294,967,295. Where applicable, specify *infinite* for larger values.
- For parameters that require an SCN setting, any valid SCN value can be specified.

START_CAPTURE Procedure

This procedure starts the capture process, which mines redo logs and enqueues the mined redo information into the associated queue.

The start status is persistently recorded. Hence, if the status is `ENABLED`, then the capture process is started upon database instance startup.

The capture process is a background Oracle process and is prefixed by `c`.

The enqueue and dequeue state of `DBMS_AQADM.START_QUEUE` and `DBMS_AQADM.STOP_QUEUE` have no effect on the start status of a capture process.

See Also: [Chapter 96, "DBMS_STREAMS_ADM"](#)

Syntax

```
DBMS_CAPTURE_ADM.START_CAPTURE(
    capture_name IN VARCHAR2);
```

Parameters

Table 19–13 *START_CAPTURE Procedure Parameter*

Parameter	Description
<code>capture_name</code>	The name of the capture process. Do not specify an owner. The capture process uses LogMiner to capture changes in the redo information. A <code>NULL</code> setting is not allowed.

Usage Notes

You can create the capture process using the following procedures:

- `DBMS_CAPTURE_ADM.CREATE_CAPTURE`
- `DBMS_STREAMS_ADM.ADD_GLOBAL_RULES`
- `DBMS_STREAMS_ADM.ADD_SCHEMA_RULES`
- `DBMS_STREAMS_ADM.ADD_TABLE_RULES`

STOP_CAPTURE Procedure

This procedure stops the capture process from mining redo logs.

The stop status is persistently recorded. Hence, if the status is `DISABLED`, then the capture process is not started upon database instance startup.

The enqueue and dequeue state of `DBMS_AQADM.START_QUEUE` and `DBMS_AQADM.STOP_QUEUE` have no effect on the stop status of a capture process.

Syntax

```
DBMS_CAPTURE_ADM.STOP_CAPTURE(  
    capture_name IN VARCHAR2,  
    force        IN BOOLEAN DEFAULT false);
```

Parameters

Table 19–14 *STOP_CAPTURE Procedure Parameters*

Parameter	Description
<code>capture_name</code>	The name of the capture process. A <code>NULL</code> setting is not allowed. Do not specify an owner.
<code>force</code>	This parameter is reserved for future use. In the current release, valid <code>BOOLEAN</code> settings are ignored.

DBMS_CDC_PUBLISH

The `DBMS_CDC_PUBLISH` package is used by a publisher to set up an Oracle Change Data Capture system to capture and publish change data from one or more Oracle relational source tables.

Change Data Capture captures and publishes only committed data. Oracle Change Data Capture identifies new data that has been added to, updated in, or removed from relational tables, and publishes the change data in a form that is usable by subscribers.

Typically, a Change Data Capture system has one **publisher** who captures and publishes changes for any number of Oracle relational source tables. The publisher then provides subscribers (applications or individuals) with access to the published data.

Note: In previous releases, this package was named `DBMS_LOGMNR_CDC_PUBLISH`. Beginning with release 10g, the `LOGMNR` string has been removed from the name, resulting in the name `DBMS_CDC_PUBLISH`. Although both variants of the name are still supported, the variant with the `LOGMNR` string has been deprecated and may not be supported in a future release

See Also: *Oracle Data Warehousing Guide* for more information about Oracle Change Data Capture and [DBMS_CDC_SUBSCRIBE](#) for information on the package used to subscribe to published change data

This chapter contains the following topics:

- [Using DBMS_CDC_PUBLISH](#)
 - [Overview](#)
 - [Security Model](#)
 - [Deprecated Subprograms](#)
- [Summary of DBMS_CDC_PUBLISH Subprograms](#)

Using DBMS_CDC_PUBLISH

- [Overview](#)
- [Security Model](#)
- [Deprecated Subprograms](#)

Overview

Through the `DBMS_CDC_PUBLISH` package, the publisher creates and maintains change sources, change sets, and change tables, and eventually drops them when they are no longer useful.

The publisher, typically a database administrator, is concerned primarily with the source of the data and with creating the schema objects that describe the structure of the capture system: change sources, change sets, and change tables.

Most Change Data Capture systems have one publisher and many subscribers. The publisher accomplishes the following main objectives:

1. Determines which source table changes need to be published.
2. Decides whether to capture changes asynchronously or synchronously.
3. Uses the procedures in the `DBMS_CDC_PUBLISH` package to capture change data from the source tables and make it available by creating and administering the change source, change set, and change table objects.
4. Allows controlled access to subscribers by using the SQL `GRANT` and `REVOKE` statements to grant and revoke the `SELECT` privilege on change tables for users and roles. (This is necessary to allow the subscribers to subscribe to the change data using the `DBMS_CDC_SUBSCRIBE` package.)

Security Model

To use the `DBMS_CDC_PUBLISH` package, the publisher must have the `EXECUTE_CATALOG_ROLE` privilege.

Deprecated Subprograms

The following subprograms have been deprecated beginning with release 10g:

- `DBMS_CDC_PUBLISH.DROP_SUBSCRIBER_VIEW`

Dropping a subscriber view is now performed automatically by Change Data Capture.

- `DBMS_CDC_PUBLISH.DROP_SUBSCRIPTION` with a subscription handle

When dropping a subscription, the publisher should now specify the name of the subscription to be dropped, not the subscription handle.

Summary of DBMS_CDC_PUBLISH Subprograms

Table 20–1 describes the subprograms in the DBMS_CDC_PUBLISH supplied package and the mode or modes with which each can be used. A value of *All* in Mode column of **Table 20–1** indicates that the subprogram can be used with synchronous and both modes of asynchronous Change Data Capture.

Table 20–1 DBMS_CDC_PUBLISH Package Subprograms

Subprogram	Mode	Description
ALTER_AUTOLOG_CHANGE_SOURCE Procedure on page 20-7	Asynchronous	Changes one or more properties of an existing AutoLog change source
ALTER_CHANGE_SET Procedure on page 20-9	All	Changes one or more of the properties of an existing change set
ALTER_CHANGE_TABLE Procedure on page 20-13	All	Adds or drops columns for an existing change table, or changes the properties of an existing change table
CREATE_AUTOLOG_CHANGE_SOURCE Procedure on page 20-16	Asynchronous	Creates an AutoLog change source
CREATE_CHANGE_SET Procedure on page 20-19	All	Creates a change set
CREATE_CHANGE_TABLE Procedure on page 20-22	All	Creates a change table in a specified schema
DROP_CHANGE_SET Procedure on page 20-27	All	Drops an existing change set
DROP_CHANGE_SOURCE Procedure on page 20-28	Asynchronous	Drops an existing AutoLog change source
DROP_CHANGE_TABLE Procedure on page 20-29	All	Drops an existing change table
DROP_SUBSCRIPTION Procedure on page 20-31	All	Allows a publisher to drop a subscription that was created by a subscriber

Table 20–1 (Cont.) DBMS_CDC_PUBLISH Package Subprograms

Subprogram	Mode	Description
PURGE Procedure on page 20-33	All	Removes unneeded rows from all change tables in the staging database
PURGE_CHANGE_SET Procedure on page 20-34	All	Removes unneeded rows from all change tables in a specified change set
PURGE_CHANGE_TABLE Procedure on page 20-35	All	Removes unneeded rows from a specified change table

ALTER_AUTOLOG_CHANGE_SOURCE Procedure

This procedure changes the properties of an existing AutoLog change source.

Syntax

```
DBMS_CDC_PUBLISH.ALTER_AUTOLOG_CHANGE_SOURCE(
    change_source_name  IN VARCHAR2,
    description         IN VARCHAR2 DEFAULT NULL,
    remove_description  IN VARCHAR2 DEFAULT 'N',
    first_scn           IN NUMBER DEFAULT NULL);
```

Parameters

Table 20–2 ALTER_AUTOLOG_CHANGE_SOURCE Procedure Parameters

Parameter	Description
change_source_name	Name of an existing change source. Change source names follow Oracle schema object naming rules.
description	New description of the change source. The description must be specified using 255 or fewer characters.
remove_description	A value of 'Y' or 'N'. If the value is 'Y', then the current description is changed to NULL. If the value is 'N', then the current description is unchanged. Do not specify the description parameter with this parameter.
first_scn	New first SCN.

Exceptions

Table 20–3 ALTER_AUTOLOG_CHANGE_SOURCE Procedure Exceptions

Exception	Description
ORA-31401	Specified change source is not an existing change source
ORA-31452	Invalid value for parameter, expecting: Y or N
ORA-31497	Invalid value specified for first_scn
ORA-31498	The description and remove_description parameters cannot both be specified

Table 20–3 (Cont.) ALTER_AUTOLOG_CHANGE_SOURCE Procedure Exceptions

Exception	Description
ORA-31499	Null value specified for required parameter
ORA-31501	Specified change source is not an AutoLog change source
ORA-31504	Cannot alter or drop predefined change source
ORA-31507	Specified parameter value longer than maximum length

Usage Notes

- Properties supplied to this procedure with a NULL value are unchanged.
- This procedure can be used to change more than one property at a time.
- This procedure can be used in determining which redo logs are no longer needed for an asynchronous AutoLog change set.

See Also: The section on asynchronous Change Data Capture and redo log files in *Oracle Data Warehousing Guide* for information on how the publisher can use the ALTER_AUTOLOG_CHANGE_SOURCE procedure in determining which redo log files are no longer needed for an asynchronous AutoLog change set

ALTER_CHANGE_SET Procedure

This procedure changes the properties of an existing change set that was created with the CREATE_CHANGE_SET procedure.

Syntax

```
DBMS_CDC_PUBLISH.ALTER_CHANGE_SET(
    change_set_name      IN VARCHAR2,
    description          IN VARCHAR2 DEFAULT NULL,
    remove_description   IN CHAR DEFAULT 'N',
    enable_capture       IN CHAR DEFAULT NULL,
    recover_after_error  IN CHAR DEFAULT NULL,
    remove_ddl          IN CHAR DEFAULT NULL,
    stop_on_ddl         IN CHAR DEFAULT NULL);
```

Parameters

Table 20–4 ALTER_CHANGE_SET Procedure Parameters

Parameter	Description
change_set_name	Name of an existing change set. Change set names follow the Oracle schema object naming rules.
description	New description of the change set. Specify using 255 or fewer characters.
remove_description	A value of 'Y' or 'N'. If the value is 'Y', then the current description is changed to NULL. If the value is 'N', then the current description is unchanged. Do not specify the description parameter with this parameter.
enable_capture	A value of 'Y' or 'N'. If the value is 'Y', then change data capture is enabled for this change set. If the value is 'N', then change data capture is disabled for this change set. Synchronous change sets are created with change data capture enabled and cannot be disabled. Asynchronous change sets are created with change data capture disabled.

Table 20–4 (Cont.) ALTER_CHANGE_SET Procedure Parameters

Parameter	Description
recover_after_error	<p>A value of 'Y' or 'N'.</p> <p>If the value is 'Y', then Change Data Capture will attempt to recover from earlier capture errors.</p> <p>If the value is 'N', then Change Data Capture will not attempt to recover from earlier capture errors.</p>
remove_ddl	<p>A value of 'Y' or 'N'.</p> <p>If the value is 'Y' and the value of the <code>recover_after_error</code> parameter is 'Y', then any DDL records that may have caused capture errors will be filtered out during recovery.</p> <p>If the value is 'N', then DDL records that may have caused capture errors will not be filtered out during recovery.</p> <p>This parameter has meaning only when the <code>recover_after_error</code> parameter is specified with a value of 'Y'.</p>
stop_on_ddl	<p>A value of 'Y' or 'N'.</p> <p>If the value is 'Y', then Change Data Capture stops when a DDL event is detected.</p> <p>If the value is 'N', then Change Data Capture continues when a DDL event is detected.</p> <p>See the Usage Notes for additional information about this parameter.</p>

Exceptions

Table 20–5 ALTER_CHANGE_SET Procedure Exceptions

Exception	Description
ORA-31410	Specified change set is not an existing change set
ORA-31452	Invalid value for parameter, expecting: Y or N
ORA-31455	Invalid lock handle while acquiring lock
ORA-31469	Cannot enable Change Data Capture for change set
ORA-31498	The <code>description</code> and <code>remove_description</code> parameters cannot both be specified
ORA-31499	Null value specified for required parameter
ORA-31505	Cannot alter or drop predefined change set

Table 20–5 (Cont.) ALTER_CHANGE_SET Procedure Exceptions

Exception	Description
ORA-31507	Specified parameter value longer than maximum length
ORA-31514	Change set disabled due to capture error

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture. However, the predefined synchronous change set, `SYNC_SET`, cannot be altered, and the following parameters cannot be altered for publisher-defined synchronous change sets: `enable_capture`, `recover_after_error`, `remove_ddl`, and `stop_on_ddl`.
- Properties supplied to this procedure with a NULL value are unchanged.
- This procedure can alter more than one parameter at a time.
- The effect of the `stop_on_ddl` parameter is as follows:
 - When the `stop_on_ddl` parameter is set to 'Y', asynchronous Change Data Capture stops if DDL is encountered during change data capture. Some DDL statements can adversely affect capture, such as a statement that drops a source table column that is being captured. The publisher has an opportunity to analyze and adjust to DDL changes that may adversely affect change tables while capture is stopped, thereby preventing possible errors during capture.

Because these statements do not affect the column data itself, Change Data Capture does not stop capturing change data when the `stop_on_ddl` parameter is set to 'Y' and any of the following statements is encountered:

- * ANALYZE TABLE
- * LOCK TABLE
- * GRANT privileges to access a table
- * REVOKE privileges to access a table
- * COMMENT on a table
- * COMMENT on a column

These statements can be issued on the source database without concern for their impact on Change Data Capture processing.

- When the `stop_on_ddl` parameter is set to 'N', Change Data Capture does not stop if DDL is encountered during change data capture. If a change set does not stop on DDL, but a DDL change occurs that affects change tables, that change can result in a capture error. (There are also system conditions that can cause capture errors, such as being out of disk space.)

See Also: The Change Data Capture chapter in *Oracle Data Warehousing Guide* for information on the effects of, and how to recover from, a capture error

Whenever a DDL statement causes processing to stop, a message is written to the alert log indicating for which change set processing has been stopped and the DDL statement that caused it to be stopped. Similarly, whenever DDL statements are ignored by Change Data Capture and processing continues, a message is written to the alert log indicating which DDL statement was ignored.

- The publisher can attempt to recover an asynchronous change set after a capture error by specifying 'Y' for the `recover_after_error` parameter. Capture errors can occur when any of the following is true:
 - The `stop_on_ddl` parameter is set to 'Y' and there is a DDL record in the change data. In this case, to recover from the error, the publisher must also specify 'Y' for the `remove_ddl` parameter.
 - The `stop_on_ddl` parameter is set to 'N' and there is a DDL record that affects capture. For example, if the publisher drops and re-creates a change table, it causes an error the next time that Change Data Capture attempts to add change data to the named change table.
 - A miscellaneous error occurs, such as running out of disk space, or a redo log file error (such as ORA-01688: unable to extend table *string.string* partition *string* by *string* in tablespace *string*).

See Also: The Change Data Capture chapter in *Oracle Data Warehousing Guide* for more information on how to recover from a capture error

ALTER_CHANGE_TABLE Procedure

This procedure adds columns to, or drops columns from, or changes the properties of, a change table that was created with the CREATE_CHANGE_TABLE procedure.

Syntax

```
DBMS_CDC_PUBLISH.ALTER_CHANGE_TABLE(
    owner                IN VARCHAR2,
    change_table_name    IN VARCHAR2,
    operation             IN VARCHAR2,
    column_list          IN VARCHAR2,
    rs_id                IN CHAR,
    row_id               IN CHAR,
    user_id              IN CHAR,
    timestamp            IN CHAR,
    object_id            IN CHAR,
    source_colmap        IN CHAR,
    target_colmap        IN CHAR);
```

Parameters

Table 20–6 ALTER_CHANGE_TABLE Procedure Parameters

Parameter	Description
owner	The schema that owns the change table.
change_table_name	The change table that is being altered. Change table names follow the Oracle schema object naming rules.
operation	Either the value ADD or DROP to indicate whether to add or drop the user columns specified with the column_list parameter and any control columns specified by other parameters.
column_list	User column names and datatypes for each column of the source table that should be added to, or dropped from, the change table. The list is comma-delimited.

Table 20–6 (Cont.) ALTER_CHANGE_TABLE Procedure Parameters

Parameter	Description
rs_id	Each listed parameter specifies a particular control column, as follows:
row_id	
user_id	
timestamp	
object_id	
source_colmap	
target_colmap	
	<ul style="list-style-type: none"> ▪ The <code>rs_id</code> parameter specifies the <code>RSID\$</code> control column. ▪ The <code>row_id</code> parameter specifies the <code>ROW_ID\$</code> control column. ▪ The <code>user_id</code> parameter specifies the <code>USERNAME\$</code> control column. ▪ The <code>timestamp</code> parameter specifies the <code>TIMESTAMP\$</code> control column. ▪ The <code>object_id</code> parameter specifies the <code>SYS_NC_OID\$</code> control column. ▪ The <code>source_colmap</code> parameter specifies the <code>SOURCE_COLMAP\$</code> control column. ▪ The <code>target_colmap</code> parameter specifies the <code>TARGET_COLMAP\$</code> control column.
	Each parameter must have a value of either 'Y' or 'N', where:
	<ul style="list-style-type: none"> ▪ 'Y': Adds the specified control column to, or drops it from the change table, as indicated by the <code>operation</code> parameter. ▪ 'N': Neither adds the specified control column, nor drops it from the change table.

See Also: The Change Data Capture chapter in *Oracle Data Warehousing Guide* for a complete description of control columns

Exceptions

Table 20–7 ALTER_CHANGE_TABLE Procedure Exceptions

Exception	Description
ORA-31403	Specified change table already contains the specified column
ORA-31409	One or more values for input parameters are incorrect
ORA-31415	Specified change set does not exist
ORA-31416	Invalid <code>SOURCE_COLMAP</code> value
ORA-31417	Column list contains control column <i>control-column-name</i>

Table 20–7 (Cont.) ALTER_CHANGE_TABLE Procedure Exceptions

Exception	Description
ORA-31421	Change table does not exist
ORA-31422	Specified owner schema does not exist
ORA-31423	Specified change table does not contain the specified column
ORA-31454	Invalid value specified for operation parameter, expecting ADD or DROP
ORA-31455	Nothing to alter
ORA-31456	Error executing a procedure in the DBMS_CDC_UTILITY package
ORA-31459	System triggers for DBMS_CDC_PUBLISH package are not installed
ORA-31471	Invalid OBJECT_ID value

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- The publisher cannot add and drop user columns in the same call to the ALTER_CHANGE_TABLE procedure; these schema changes require separate calls.
- The publisher must not specify the name of the control columns in the column_list parameter.
- When altering an asynchronous change table, the publisher must accept the default value or specify 'N' for the source_colmap and object_id parameters.

See Also: *Oracle Data Warehousing Guide* for information about the impact on subscriptions when a publisher adds a column to a change table

CREATE_AUTOLOG_CHANGE_SOURCE Procedure

This procedure creates an AutoLog change source. An AutoLog change source is based on of a set of redo log files automatically copied by log transport services to the system on which the staging database resides.

Syntax

```
DBMS_CDC_PUBLISH.CREATE_AUTOLOG_CHANGE_SOURCE(
    change_source_name IN VARCHAR2,
    description         IN VARCHAR2 DEFAULT NULL,
    source_database    IN VARCHAR2,
    first_scn          IN NUMBER);
```

Parameters

Table 20–8 CREATE_AUTOLOG_CHANGE_SOURCE Procedure Parameters

Parameter	Description
change_source_name	Name of the change source. Change source names follow the Oracle schema object naming rules.
description	Description of the change source. Specify using 255 or fewer characters.
source_database	Global name of the change source's source database instance.
first_scn	The SCN of the start of a LogMiner dictionary that is in the change source's archived redo log files.

Exceptions

Table 20–9 CREATE_AUTOLOG_CHANGE_SOURCE Procedure Exceptions

Exception	Description
ORA-31436	Duplicate change source specified
ORA-31497	Invalid value specified for first_scn
ORA-31499	Null value specified for required parameter
ORA-31507	Specified parameter value is longer than the maximum length
ORA-31508	Invalid parameter value for synchronous change set

Usage Notes

- The publisher can use this procedure for asynchronous Change Data Capture only.
- The publisher must take care when specifying a value for the `source_database` parameter. Change Data Capture does not validate this value when creating the change source. The publisher can query the `GLOBAL_NAME` column in the `GLOBAL_NAME` view at the source database for the `source_database` parameter value.
- The publisher must configure log transport services to automatically copy the log files to the system on which the staging database resides.

See Also: The section on performing asynchronous AutoLog publishing in *Oracle Data Warehousing Guide* for information on configuring log transport services to automatically copy the log files to the system on which the staging database resides

- An AutoLog change source must begin with an archived redo log file that contains a LogMiner dictionary. The `CREATE_AUTOLOG_CHANGE_SOURCE` `first_scn` parameter indicates the SCN for this dictionary extraction and is the point at which the change source can begin capturing changes. The publisher can determine the value for the `first_scn` parameter using either of the following methods:

- Direct `DBMS_CAPTURE_ADM.BUILD` to return the value when the dictionary is built:

```
SET SERVEROUTPUT ON
VARIABLE FSCN NUMBER;
BEGIN
  :FSCN := 0;
  DBMS_CAPTURE_ADM.BUILD(:FSCN);
  DBMS_OUTPUT.PUT_LINE('The first_scn value is ' || :FSCN);
END;
/
The first_scn value is 207722
```

- Make the following query on the source database. If this query returns multiple distinct values for `first_change#`, then the data dictionary has been extracted more than once and the publisher should choose the `first_change#` value that is the most appropriate to the change source.

```
SELECT DISTINCT FIRST_CHANGE#, NAME
```

```
FROM V$ARCHIVED_LOG  
WHERE DICTIONARY_BEGIN = 'YES';
```

See Also: The section on performing asynchronous AutoLog publishing in *Oracle Data Warehousing Guide* for information on archived redo log files and the LogMiner dictionary

- For the asynchronous mode of Change Data Capture, the amount of change data captured is dependent on the level of supplemental logging enabled at the source database.

See Also: The Change Data Capture chapter in *Oracle Data Warehousing Guide* for information about supplemental logging

CREATE_CHANGE_SET Procedure

This procedure allows the publisher to create a change set. For asynchronous Change Data Capture, the publisher can optionally provide beginning and ending date values at which to begin and end change data capture.

Syntax

```
DBMS_CDC_PUBLISH.CREATE_CHANGE_SET(
    change_set_name      IN VARCHAR2,
    description          IN VARCHAR2 DEFAULT NULL,
    change_source_name  IN VARCHAR2,
    stop_on_ddl         IN CHAR DEFAULT 'N',
    begin_date          IN DATE DEFAULT NULL,
    end_date            IN DATE DEFAULT NULL);
```

Parameters

Table 20–10 CREATE_CHANGE_SET Procedure Parameters

Parameter	Description
change_set_name	Name of the change set. Change set names follow the Oracle schema object naming rules.
description	Description of the change set. Specify using 255 or fewer characters.
change_source_name	Name of the existing change source to contain this change set.
stop_on_ddl	A value of 'Y' or 'N'. If the value is 'Y', then Change Data Capture stops when a DDL event is detected. If the value is 'N', then Change Data Capture continues when a DDL event is detected. See the Usage Notes for additional information about this parameter.
begin_date	Date on which the publisher wants the change set to begin capturing changes. A value for this parameter is valid for the asynchronous mode of Change Data Capture only.
end_date	Date on which the publisher wants the change set to stop capturing changes. A value for this parameter is valid for the asynchronous mode of Change Data Capture only.

Exceptions

Table 20–11 *CREATE_CHANGE_SET Procedure Exceptions*

Exception	Description
ORA-31401	Specified change source is not an existing change source
ORA-31407	The <code>end_date</code> must be greater than the <code>begin_date</code>
ORA-31437	Duplicate change set specified
ORA-31452	Invalid value for parameter, expecting: Y or N
ORA-31499	Null value specified for required parameter
ORA-31503	Invalid date supplied for <code>begin_date</code> or <code>end_date</code>
ORA-31507	Specified parameter value longer than maximum length
ORA-31508	Invalid parameter value for synchronous change set

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture. However, the default values for the following parameters are the only supported values for synchronous change sets: `begin_date`, `end_date`, and `stop_on_ddl`.
- The `begin_date` and `end_date` parameters are optional. The publisher can specify neither of them, one of them, or both. The effect of these parameters is as follows:
 - When a `begin_date` is specified, changes from transactions that begin on or after that date are captured.
 - When a `begin_date` is not specified, capture starts with the earliest available change data.
 - When an `end_date` is specified, changes from transactions that are committed on or before that date are captured.
 - When an `end_date` is not specified, Change Data Capture continues indefinitely.
- The effect of the `stop_on_ddl` parameter is as follows:
 - When the `stop_on_ddl` parameter is set to 'Y', asynchronous Change Data Capture stops if DDL is encountered during change data capture. Some DDL statements can adversely affect capture, such as a statement that drops

a source table column that is being captured. The publisher has an opportunity to analyze and adjust to DDL changes that may adversely affect change tables while capture is stopped, thereby preventing possible errors during capture.

Because these statements do not affect the column data itself, Change Data Capture does not stop capturing change data when the `stop_on_ddl` parameter is set to 'Y' and any of the following statements is encountered:

- * ANALYZE TABLE
- * LOCK TABLE
- * GRANT privileges to access a table
- * REVOKE privileges to access a table
- * COMMENT on a table
- * COMMENT on a column

These statements can be issued on the source database without concern for their impact on Change Data Capture processing.

- When the `stop_on_ddl` parameter is set to 'N', Change Data Capture does not stop if DDL is encountered during change data capture. If a change set does not stop on DDL, but a DDL change occurs that affects capture, that change can result in a capture error.

See Also: The Change Data Capture chapter in *Oracle Data Warehousing Guide* for information on the effects of, and how to recover from, a capture error

Whenever a DDL statement causes processing to stop, a message is written to the alert log indicating for which change set processing has been terminated and the DDL statement that caused it to be terminated. Similarly, whenever DDL statements are ignored by Change Data Capture and processing continues, a message is written to the alert log indicating which DDL statement was ignored.

CREATE_CHANGE_TABLE Procedure

This procedure creates a change table in a specified schema.

Note: Oracle recommends that the publisher be certain that the source table that will be referenced in a `CREATE_CHANGE_TABLE` procedure has been created prior to calling this procedure, particularly if the change set that will be specified in the procedure has the `stop_on_ddl` parameter set to 'Y'.

Syntax

```
DBMS_CDC_PUBLISH.CREATE_CHANGE_TABLE(
    owner                IN VARCHAR2,
    change_table_name   IN VARCHAR2,
    change_set_name     IN VARCHAR2,
    source_schema       IN VARCHAR2,
    source_table        IN VARCHAR2,
    column_type_list    IN VARCHAR2,
    capture_values      IN VARCHAR2,
    rs_id               IN CHAR,
    row_id              IN CHAR,
    user_id             IN CHAR,
    timestamp           IN CHAR,
    object_id           IN CHAR,
    source_colmap       IN CHAR,
    target_colmap       IN CHAR,
    options_string      IN VARCHAR2);
```

Parameters

Table 20–12 *CREATE_CHANGE_TABLE Procedure Parameters*

Parameter	Description
<code>owner</code>	Name of the schema that owns the change table.
<code>change_table_name</code>	Name of the change table that is being created. Change table names follow the Oracle schema object naming rules.
<code>change_set_name</code>	Name of the change set in which this change table resides.
<code>source_schema</code>	The schema where the source table is located.

Table 20–12 (Cont.) CREATE_CHANGE_TABLE Procedure Parameters

Parameter	Description
source_table	The source table from which the change records are captured.
column_type_list	The user columns and datatypes that are being tracked. Specify using a comma-delimited list.
capture_values	One of the following capture values for update operations: <ul style="list-style-type: none"> ■ OLD: Captures the original values from the source table. ■ NEW: Captures the changed values from the source table. ■ BOTH: Captures the original and changed values from the source table.
rs_id	<p>Each listed parameter specifies a particular control column as follows:</p> <ul style="list-style-type: none"> ■ The <code>rs_id</code> parameter specifies the <code>RSID\$</code> control column. ■ The <code>row_id</code> parameter specifies the <code>ROW_ID\$</code> control column. ■ The <code>user_id</code> parameter specifies the <code>USERNAME\$</code> control column. ■ The <code>timestamp</code> parameter specifies the <code>TIMESTAMP\$</code> control column. ■ The <code>object_id</code> parameter specifies the <code>SYS_NC_OID\$</code> control column. ■ The <code>source_colmap</code> parameter specifies the <code>SOURCE_COLMAP\$</code> control column. ■ The <code>target_colmap</code> parameter specifies the <code>TARGET_COLMAP\$</code> control column. <p>Each parameter can have a value of 'Y' or 'N', where:</p> <ul style="list-style-type: none"> ■ 'Y': Adds the specified control column to the change table. ■ 'N': Does not add the specified control column to the change table.
row_id	
user_id	
timestamp	
object_id	
source_colmap	
target_colmap	
options_string	The syntactically correct options to be passed to a <code>CREATE TABLE DDL</code> statement. The options string is appended to the generated <code>CREATE TABLE DDL</code> statement after the closing parenthesis that defines the columns of the table. See the Usage Notes for more information.

See Also: The Change Data Capture chapter in *Oracle Data Warehousing Guide* for a complete description of control columns

Exceptions

Table 20–13 CREATE_CHANGE_TABLE Procedure Exceptions

Exception	Description
ORA-31402	Unrecognized parameter specified
ORA-31409	One or more values for input parameters are incorrect
ORA-31415	Specified change set does not exist
ORA-31416	Invalid SOURCE_COLMAP value
ORA-31417	Column list contains control column <i>control-column-name</i>
ORA-31418	Specified source schema does not exist
ORA-31419	Specified source table does not exist
ORA-31420	Unable to submit the purge job
ORA-31421	Change table does not exist
ORA-31422	Owner schema does not exist
ORA-31438	Duplicate change table
ORA-31447	Cannot create change tables in the SYS schema
ORA-31450	Invalid value for change_table_name
ORA-31451	Invalid value for capture_values, expecting: OLD, NEW, or BOTH
ORA-31452	Invalid value for parameter, expecting: Y or N
ORA-31459	System triggers for DBMS_CDC_PUBLISH package are not installed
ORA-31467	No column found in the source table
ORA-31471	Invalid OBJECT_ID value

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- A change table is a database table that contains the change data resulting from DML statements (INSERT, UPDATE, and DELETE) made to a source table. A given change table can capture changes from only one source table.

- A change table is a database table that contains the change data in these two types of columns:
 - User columns, which are copies of actual columns of source tables that reside in the change table.
 - Control columns, which maintain special metadata for each change row in the change table. Information such as the DML operation performed, the capture time (time stamp), and changed column vectors are examples of control columns. The publisher must not specify the name of the control columns in the user column list.
- The publisher must not attempt to control a change table's partitioning properties. Change Data Capture automatically manages the change table partitioning as part of its change table management.
- When creating a change table for asynchronous Change Data Capture, the publisher must accept the default value or specify 'N' for the `source_colmap` and `object_id` parameters.
- When the publisher specifies the `rs_id` parameter, the `RSID$` column is added to the change table. The `RSID$` column value reflects an operation's capture order within a transaction, but not across transactions. The publisher cannot use the `RSID$` column value by itself to order committed operations across transactions; it must be used in conjunction with the `CSCN$` column value.
- The publisher can control a change table's physical properties, tablespace properties, and so on, by specifying the `options_string` parameter. With the `options_string` parameter, the publisher can set any option that is valid for the `CREATE TABLE` DDL statement (except for partitioning properties).

Note: How the publisher defines the `options_string` parameter can have an effect on the performance and operations in a Change Data Capture system. For example, if the publisher places several constraints in the options column, it can have a noticeable effect on performance. Also, if the publisher uses `NOT NULL` constraints and a particular column is not changed in an incoming change row, then the constraint can cause the `INSERT` operation to fail and the transaction that contains the `INSERT` operation to be rolled back.

- Oracle recommends that change tables not be created in system tablespaces. This can be accomplished if the publisher's default tablespace is not the system

tablespace or if the publisher specifies a tablespace in the `options_string` parameter. If a tablespace is not specified by the publisher, and the publisher's default table space is the system tablespace, then Change Data Capture creates change tables in the system tablespace.

See Also: The Change Data Capture chapter in *Oracle Data Warehousing Guide* for more information on, and examples of, creating change tables in tablespaces managed by the publisher

DROP_CHANGE_SET Procedure

This procedure drops an existing change set that was created with the CREATE_CHANGE_SET procedure.

Syntax

```
DBMS_CDC_PUBLISH.DROP_CHANGE_SET(
    change_set_name    IN VARCHAR2);
```

Parameters

Table 20–14 DROP_CHANGE_SET Procedure Parameters

Parameter	Description
change_set_name	Name of the change set to be dropped. Change set names follow the Oracle schema object naming rules.

Exceptions

Table 20–15 DROP_CHANGE_SET Procedure Exceptions

Exception	Description
ORA-31410	Specified change set is not an existing change set
ORA-31411	Specified change set is referenced by a change table
ORA-31499	Null value specified for required parameter
ORA-31505	Cannot alter or drop predefined change set
ORA-31507	Specified parameter value is longer than maximum length

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- The change set to be dropped cannot contain any change tables.
- The predefined synchronous change set, SYNC_SET, cannot be dropped.

DROP_CHANGE_SOURCE Procedure

This procedure drops an existing AutoLog change source that was created with the CREATE_AUTOLOG_CHANGE_SOURCE procedure.

Syntax

```
DBMS_CDC_PUBLISH.DROP_CHANGE_SOURCE(  
    change_source_name    IN VARCHAR2);
```

Parameters

Table 20–16 DROP_CHANGE_SOURCE Procedure Parameters

Parameter	Description
change_source_name	Name of the change source to be dropped. Change source names follow the Oracle schema object naming rules.

Exceptions

Table 20–17 DROP_CHANGE_SOURCE Procedure Exceptions

Exception	Description
ORA-31401	Specified change source is not an existing change source
ORA-31406	Specified change source is referenced by a change set
ORA-31499	Null value specified for required parameter
ORA-31504	Cannot alter or drop predefined change source
ORA-31507	Specified parameter value longer than maximum length

Usage Notes

- The change source to be dropped cannot contain any change sets.
- The predefined change sources, HOTLOG_SOURCE and SYNC_SOURCE, cannot be dropped.

DROP_CHANGE_TABLE Procedure

This procedure drops an existing change table that was created with the `CREATE_CHANGE_TABLE` procedure.

Syntax

```
DBMS_CDC_PUBLISH.DROP_CHANGE_TABLE(
    owner           IN VARCHAR2,
    change_table_name IN VARCHAR2,
    force_flag      IN CHAR);
```

Parameters

Table 20–18 *DROP_CHANGE_TABLE Procedure Parameters*

Parameter	Description
owner	Name of the schema that owns the change table.
change_table_name	Name of the change table to be dropped. Change table names follow the Oracle schema object naming rules.
force_flag	Drops the change table, depending on whether or not there are subscriptions to it, as follows: <ul style="list-style-type: none"> ▪ Y: Drops the change table even if there are subscriptions to it. ▪ N: Drops the change table only if there are no subscriptions to it.

Exceptions

Table 20–19 *DROP_CHANGE_TABLE Procedure Exceptions*

Exception	Description
ORA-31421	Change table does not exist
ORA-31422	Specified owner schema does not exist
ORA-31424	Change table has active subscriptions
ORA-31441	Table is not a change table

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- If the publisher wants to drop a change table while there are active subscriptions to that table, he or she must call the `DROP_CHANGE_TABLE` procedure using the `force_flag => 'Y'` parameter. This tells Change Data Capture to override its normal safeguards and allow the change table to be dropped despite active subscriptions. The subscriptions that include the dropped table will no longer be valid, and subscribers will lose access to the change data.

DROP_SUBSCRIPTION Procedure

This procedure allows a publisher to drop a subscription that was created by a subscriber with a prior call to the `DBMS_CDC_SUBSCRIBE.CREATE_SUBSCRIPTION` procedure.

Syntax

```
DBMS_CDC_PUBLISH.DROP_SUBSCRIPTION(
    subscription_name IN VARCHAR2);
```

Parameters

Table 20–20 *DROP_SUBSCRIPTION Procedure Parameters*

Parameter	Description
<code>subscription_name</code>	Name of the subscription that was specified by a previous call to the <code>DBMS_CDC_SUBSCRIBE.CREATE_SUBSCRIPTION</code> procedure. Subscription names follow the Oracle schema object naming rules.

Exceptions

Table 20–21 *DROP_SUBSCRIPTION Procedure Exceptions*

Exception	Description
ORA-31409	One or more values for input parameters are incorrect
ORA-31425	Subscription does not exist
ORA-31432	Invalid source table

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- This procedure works the same way as the `DBMS_CDC_SUBSCRIBE.DROP_SUBSCRIPTION` procedure.
- This procedure provides the publisher with a way to drop subscriptions that have not been dropped by the subscriber. It is possible that a subscription that is no longer needed still exists and is holding change data in a change table

indefinitely. The publisher can use this procedure to remove such a subscription so that a purge operation can clean up its change data. Oracle recommends that the publisher attempt to verify that the subscription is not needed prior to dropping it. If that is not possible, the publisher should inform the subscription owner that the subscription has been dropped. (Ideally, subscribers drop subscriptions that are no longer needed using the `DBMS_CDC_SUBSCRIBE.DROP_SUBSCRIPTION` procedure and the publisher need not use the `DBMS_CDC_SUBSCRIBE.DROP_SUBSCRIPTION` procedure.)

PURGE Procedure

This procedure monitors change table usage by all subscriptions, determines which rows are no longer needed by any subscriptions, and removes the unneeded rows to prevent change tables from growing indefinitely. When called, this procedure purges all change tables on the staging database.

Syntax

```
DBMS_CDC_PUBLISH.PURGE;
```

Exceptions

Only standard Oracle exceptions (for example, a privilege violation) are returned during a purge operation.

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- The publisher can run this procedure manually or automatically:
 - The publisher can run this procedure manually from the command line to purge data from change tables.
 - The publisher can run this procedure in a script to routinely perform a purge operation and control the growth of change tables.
- Note that the `DBMS_CDC_PUBLISH.PURGE` procedure (used by the publisher and the Change Data Capture default purge job) is distinct from the `DBMS_CDC_SUBSCRIBE.PURGE_WINDOW` procedure (used by subscribers). A call to the `DBMS_CDC_PUBLISH.PURGE` procedure physically removes unneeded rows from change tables. A call to the `DBMS_CDC_SUBSCRIBE.PURGE_WINDOW` procedure, logically removes change rows from a subscription window, but does not physically remove rows from the underlying change tables.

PURGE_CHANGE_SET Procedure

This procedure removes unneeded rows from all change tables in the named change set. This procedure allows a finer granularity purge operation than the basic `PURGE` procedure.

Syntax

```
DBMS_CDC_PUBLISH.PURGE_CHANGE_SET(  
    change_set_name in VARCHAR2);
```

Parameters

Table 20–22 *PURGE_CHANGE_SET Procedure Parameters*

Parameter	Description
<code>change_set_name</code>	Name of an existing change set. Change set names follow the Oracle schema object naming rules.

Exceptions

Table 20–23 *PURGE_CHANGE_SET Procedure Exceptions*

Exception	Description
ORA-31410	Change set is not an existing change set

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- The publisher can run this procedure manually from the command line or in a script to purge unneeded rows from change tables in a specific change set.
- Note that the `DBMS_CDC_PUBLISH.PURGE_CHANGE_SET` procedure (used by the publisher) is distinct from the `DBMS_CDC_SUBSCRIBE.PURGE_WINDOW` procedure (used by subscribers). A call to the `DBMS_CDC_PUBLISH.PURGE_CHANGE_SET` procedure physically removes unneeded rows from change tables in the specified change set. A call to the `DBMS_CDC_SUBSCRIBE.PURGE_WINDOW` procedure, logically removes change rows from a subscription window, but does not physically remove rows from the underlying change tables.

PURGE_CHANGE_TABLE Procedure

This procedure removes unneeded rows from the named change table. This procedure allows a finer granularity purge operation than the basic PURGE procedure or the PURGE_CHANGE_SET procedure.

Syntax

```
DBMS_CDC_PUBLISH.PURGE_CHANGE_TABLE(
    owner          in VARCHAR2,
    change_table_name in VARCHAR2);
```

Parameters

Table 20–24 *PURGE_CHANGE_TABLE Procedure Parameters*

Parameter	Description
owner	Owner of the named change table.
change_table_name	Name of an existing change table. Change table names follow the Oracle schema object naming rules.

Exceptions

Table 20–25 *PURGE_CHANGE_TABLE Procedure Exceptions*

Exception	Description
ORA-31421	Change table does not exist

Usage Notes

- The publisher can use this procedure for asynchronous and synchronous Change Data Capture.
- The publisher can run this procedure manually from the command line or in a script to purge unneeded rows from a specified change table.
- Note that the DBMS_CDC_PUBLISH.PURGE_CHANGE_TABLE procedure (used by the publisher) is distinct from the DBMS_CDC_SUBSCRIBE.PURGE_WINDOW procedure (used by subscribers). A call to the DBMS_CDC_PUBLISH.PURGE_CHANGE_TABLE procedure physically removes unneeded rows from the specified change table. A call to the DBMS_CDC_SUBSCRIBE.PURGE_WINDOW

procedure, logically removes change rows from a subscription window, but does not physically remove rows from the underlying change tables.

DBMS_CDC_SUBSCRIBE

The `DBMS_CDC_SUBSCRIBE` package lets subscribers view and query change data that was captured and published with the `DBMS_CDC_PUBLISH` package.

A Change Data Capture system usually has one publisher and many subscribers. The **subscribers** (applications or individuals), use the Oracle supplied package, `DBMS_CDC_SUBSCRIBE`, to access published data.

Be aware that Change Data Capture grants `EXECUTE` privileges to `PUBLIC` on the `DBMS_CDC_SUBSCRIBE` procedure.

Note: In previous releases, this package was named `DBMS_LOGMNR_CDC_SUBSCRIBE`. Beginning with release 10g, the `LOGMNR` string has been removed from the name, resulting in the name `DBMS_CDC_SUBSCRIBE`. Although both variants of the name are still supported, the variant with the `LOGMNR` string has been deprecated and may not be supported in a future release.

See Also: *Oracle Data Warehousing Guide* for more information about Oracle Change Data Capture and [DBMS_CDC_PUBLISH](#) for information on the package for publishing change data.

This chapter contains the following topics:

- [Using DBMS_CDC_SUBSCRIBE](#)
 - [Overview](#)
 - [Deprecated Subprograms](#)
- [Summary of DBMS_CDC_SUBSCRIBE Subprograms](#)

Using DBMS_CDC_SUBSCRIBE

- [Overview](#)
- [Deprecated Subprograms](#)

Overview

The primary role of the subscriber is to use the change data. Through the `DBMS_CDC_SUBSCRIBE` package, each subscriber registers interest in a set of source tables by subscribing to them.


Once the publisher sets up the system to capture data into change tables (which are viewed as publications by subscribers) and grants subscribers access to the change tables, subscribers can access and query the published change data for any of the source tables of interest. Using the procedures in the `DBMS_CDC_SUBSCRIBE` package, the subscriber accomplishes the following main objectives:

1. Indicates the change data of interest by creating a subscription and associated subscriber views on published source tables and source columns
2. Activates the subscription to indicate that the subscriber is ready to receive change data
3. Extends the subscription window to receive a new set of change data
4. Uses SQL `SELECT` statements to retrieve change data from the subscriber views
5. Purges the subscription window when finished processing a block of changes
6. Drops the subscription when finished with the subscription

[Figure 21–1](#) provides a graphical flowchart of the information provided in [Table 21–1](#). The flowchart shows the order in which subscribers most typically use the procedures in the `DBMS_CDC_SUBSCRIBE` package. A subscriber would typically create a subscription, subscribe to one or more source tables and columns, activate the subscription, extend the subscription window, query the subscriber views, purge the subscription window, and then either extend the subscription window again or drop the subscription.

Note: If a subscriber uses the `PURGE_WINDOW` procedure immediately after using an `EXTEND_WINDOW` procedure, then change data may be lost without ever being processed.

Figure 21–1 Subscription Flow



Deprecated Subprograms

The following `DBMS_CDC_SUBSCRIBE` procedures have been deprecated beginning with release 10g:

- `GET_SUBSCRIPTION_HANDLE`

Subscribers no longer explicitly specify subscription handles. Subscribers should use the `CREATE_SUBSCRIPTION` procedure instead to specify a subscription name.

- `PREPARE_SUBSCRIBER_VIEW`

Subscribers no longer need to prepare subscriber views. This work is now done automatically by Change Data Capture.

- `DROP_SUBSCRIBER_VIEW`

Subscribers no longer need to drop subscriber views. This work is now done automatically by Change Data Capture.

If an existing application uses these deprecated `DBMS_CDC_SUBSCRIBE` procedures with release 10g, note the following changes in behavior:

- Subscriber views are persistent for the life of the subscription.
- Some error conditions, particularly with regard to subscriber view management, no longer occur.
- If a publisher alters a publication such that it contains different control columns, the subscriber must call `DBMS_CDC_SUBSCRIBE.EXTEND_WINDOW` to see the new column structure.

Note: Oracle recommends that you do not use deprecated procedures in new applications. Support for deprecated features is for backward compatibility only.

In addition, the use of the `subscription_handle` parameter with the following `DBMS_CDC_SUBSCRIBE` procedures has been deprecated beginning with release 10g:

- `SUBSCRIBE`
- `ACTIVATE_SUBSCRIPTION`
- `EXTEND_WINDOW`
- `PURGE_WINDOW`
- `DROP_SUBSCRIPTION`

Summary of DBMS_CDC_SUBSCRIBE Subprograms

Table 21–1 DBMS_CDC_SUBSCRIBE Package Procedures

Procedures	Description
ACTIVATE_SUBSCRIPTION Procedure on page 21-6	Indicates that a subscription is ready to start accessing change data
CREATE_SUBSCRIPTION Procedure on page 21-8	Creates a subscription and associates it with one change set
DROP_SUBSCRIPTION Procedure on page 21-10	Drops a subscription that was created with a prior call to the <code>CREATE_SUBSCRIPTION</code> procedure
EXTEND_WINDOW Procedure on page 21-11	Sets a subscription window high boundary so that new change data can be seen
PURGE_WINDOW Procedure on page 21-13	Sets the low boundary for a subscription window to notify Change Data Capture that the subscriber is finished processing a set of change data
SUBSCRIBE Procedure on page 21-15	Specifies a source table and the source columns for which the subscriber wants to access change data and specifies the subscriber view through which the subscriber sees change data for the source table

ACTIVATE_SUBSCRIPTION Procedure

This procedure indicates that a subscription is ready to start accessing change data.

Syntax

```
DBMS_CDC_SUBSCRIBE.ACTIVATE_SUBSCRIPTION(  
    subscription_name IN VARCHAR2);
```

Parameters

Table 21–2 *ACTIVATE_SUBSCRIPTION Procedure Parameters*

Parameter	Description
subscription_name	The name of the subscription that was specified for a previous call to the CREATE_SUBSCRIPTION procedure. Subscription names follow the Oracle schema object naming rules.

Exceptions

Table 21–3 *ACTIVATE_SUBSCRIPTION Procedure Exceptions*

Exception	Description
ORA-31409	One or more values for input parameters are incorrect
ORA-31425	Subscription does not exist
ORA-31426	Cannot modify active subscriptions
ORA-31469	Cannot enable Change Data Capture for change set
ORA-31514	Change set disabled due to capture error

Usage Notes

- The ACTIVATE_SUBSCRIPTION procedure indicates that the subscriber is finished subscribing to tables, and the subscription is ready to start accessing change data.
- Once the subscriber activates the subscription:
 - No additional source tables can be added to the subscription.
 - Change Data Capture holds the available data for the source tables and sets the subscription window to empty.

- The subscriber must use the `EXTEND_WINDOW` procedure to see the initial set of change data.
- The subscription cannot be activated again.
- A subscription cannot be activated if the underlying change set has reached its `end_date` parameter value.

CREATE_SUBSCRIPTION Procedure

This procedure creates a subscription that is associated with one change set. This procedure replaces the deprecated `GET_SUBSCRIPTION_HANDLE` procedure.

Syntax

```
DBMS_CDC_SUBSCRIBE.CREATE_SUBSCRIPTION(
    change_set_name      IN  VARCHAR2,
    description          IN  VARCHAR2,
    subscription_name    IN  VARCHAR2);
```

Parameters

Table 21–4 *CREATE_SUBSCRIPTION Procedure Parameters*

Parameter	Description
<code>change_set_name</code>	The name of an existing change set to which the subscriber subscribes.
<code>description</code>	A description of the subscription (which might include, for example, the purpose for which it is used). The description must be specified using 255 or fewer characters.
<code>subscription_name</code>	A unique name for a subscription that must consist of 30 characters or fewer and cannot have a prefix of <code>CDC\$</code> . Subscription names follow the Oracle schema object naming rules.

Exceptions

Table 21–5 *CREATE_SUBSCRIPTION Procedure Exceptions*

Exception	Description
ORA-31409	One or more values for input parameters are incorrect
ORA-31415	Specified change set does not exist
ORA-31449	Invalid value for <code>change_set_name</code>
ORA-31457	Maximum length of description field exceeded
ORA-31469	Cannot enable Change Data Capture for change set

Table 21–5 (Cont.) CREATE_SUBSCRIPTION Procedure Exceptions

Exception	Description
ORA-31506	Duplicate subscription name specified
ORA-31510	Name uses reserved prefix CDC\$
ORA-31511	Name exceeds maximum length of 30 characters

Usage Notes

- The `CREATE_SUBSCRIPTION` procedure allows a subscriber to register interest in a change set associated with source tables of interest.
- A subscriber can query the `ALL_PUBLISHED_COLUMNS` view to see all the published source tables for which the subscriber has privileges and the change sets in which the source table columns are published.
- Subscriptions are not shared among subscribers; rather, each subscription name is validated against a given subscriber's login ID.
- Subscriptions cannot be created if the underlying change set has reached its `end_date` parameter value.

DROP_SUBSCRIPTION Procedure

This procedure drops a subscription.

Syntax

```
DBMS_CDC_SUBSCRIBE.DROP_SUBSCRIPTION(  
    subscription_name IN VARCHAR2);
```

Parameters

Table 21–6 *DROP_SUBSCRIPTION Procedure Parameters*

Parameter	Description
subscription_name	The name of the subscription that was specified for a previous call to the CREATE_SUBSCRIPTION procedure. Subscription names follow the Oracle schema object naming rules.

Exceptions

Table 21–7 *DROP_SUBSCRIPTION Procedure Exceptions*

Exception	Description
ORA-31409	One or more values for input parameters are incorrect
ORA-31425	Subscription does not exist

Usage Notes

Subscribers should be diligent about dropping subscriptions that are no longer needed so that change data will not be held in the change tables unnecessarily.

EXTEND_WINDOW Procedure

This procedure sets the subscription window high boundary so that new change data can be seen.

Syntax

```
DBMS_CDC_SUBSCRIBE.EXTEND_WINDOW(
    subscription_name IN VARCHAR2);
```

Parameters

Table 21–8 *EXTEND_WINDOW Procedure Parameters*

Parameter	Description
subscription_name	The unique name of the subscription that was specified by a previous call to the CREATE_SUBSCRIPTION procedure. Subscription names follow the Oracle schema object naming rules.

Exceptions

Table 21–9 *EXTEND_WINDOW Procedure Exceptions*

Exception	Description
ORA-31409	One or more values for input parameters are incorrect
ORA-31425	Subscription does not exist
ORA-31429	Subscription has not been activated
ORA-31432	Invalid source table
ORA-31469	Cannot enable Change Data Capture for change set
ORA-31509	Publication does not exist
ORA-31514	Change set disabled due to capture error

Usage Notes

- Until the subscriber calls the EXTEND_WINDOW procedure to begin receiving change data, the subscription window remains empty.

- The first time that the subscriber calls the `EXTEND_WINDOW` procedure, it establishes the initial boundaries for the subscription window.
- Subsequent calls to the `EXTEND_WINDOW` procedure extend the high boundary of the subscription window so that new change data can be seen.
- Oracle recommends that subscribers not view change tables directly. Instead, subscribers should use the `DBMS_CDC_SUBSCRIBE` package and access data through subscriber views only. Control column values are guaranteed to be consistent only when viewed through subscriber views that have been updated with a call to the `EXTEND_WINDOW` procedure.
- When the underlying change set for a subscription has reached its `end_date` parameter value, subsequent calls to the `EXTEND_WINDOW` procedure will not raise the high boundary.

PURGE_WINDOW Procedure

This procedure sets the low boundary of the subscription window so that the subscription no longer sees any change data, effectively making the subscription window empty. The subscriber calls this procedure to notify Change Data Capture that the subscriber is finished processing a block of change data.

Syntax

```
DBMS_CDC_SUBSCRIBE.PURGE_WINDOW(
    subscription_name IN VARCHAR2);
```

Parameters

Table 21–10 *PURGE_WINDOW Procedure Parameters*

Parameter	Description
subscription_name	The name of the subscription that was specified for a previous call to the CREATE_SUBSCRIPTION procedure. Subscription names follow the Oracle schema object naming rules.

Exceptions

Table 21–11 *PURGE_WINDOW Procedure Exceptions*

Exception	Description
ORA-31409	One or more values for input parameters are incorrect
ORA-31425	Subscription does not exist
ORA-31429	Subscription has not been activated
ORA-31432	Invalid source table
ORA-31469	Cannot enable Change Data Capture for change set
ORA-31514	Change set disabled due to capture error

Usage Notes

- When finished with a set of changes, the subscriber purges the subscription window with the PURGE_WINDOW procedure. By this action, the subscriber performs the following functions:

- Informs Change Data Capture that the subscriber is finished with the current set of change data.
- Enables Change Data Capture to remove change data that is no longer needed by any subscribers.

Change Data Capture manages the change data to ensure that it is available as long as there are subscribers who need it.

- When the underlying change set for a subscription has reached its `end_date` parameter value, subsequent calls to the `PURGE_WINDOW` procedure will not move the low boundary.

SUBSCRIBE Procedure

This procedure specifies a source table and the source columns for which the subscriber wants to access change data. In addition, it specifies the subscriber view through which the subscriber sees change data for the source table.

Syntax

There are two versions of syntax for the `SUBSCRIBE` procedure, as follow:

- Using source schema and source table

When this syntax is used, Change Data Capture will attempt to find a single publication ID that contains the specified `source_table` and `column_list`. If such a publication cannot be found, then Change Data Capture returns an error.

```
DBMS_CDC_SUBSCRIBE.SUBSCRIBE(  
    subscription_name    IN VARCHAR2,  
    source_schema       IN VARCHAR2,  
    source_table        IN VARCHAR2,  
    column_list         IN VARCHAR2,  
    subscriber_view     IN VARCHAR2);
```

- Using publication IDs

When this syntax is used, Change Data Capture will use the publication ID to identify the change table. If the columns specified in the `column_list` parameter are not in the identified change table, then Change Data Capture returns an error.

```
DBMS_CDC_SUBSCRIBE.SUBSCRIBE(  
    subscription_name    IN VARCHAR2,  
    publication_id       IN NUMBER,  
    column_list         IN VARCHAR2,  
    subscriber_view     IN VARCHAR2);
```

Parameters

Table 21–12 *SUBSCRIBE Procedure Parameters*

Parameter	Description
subscription_name	The name of a subscription that was specified for, or returned by, a previous call to the <code>CREATE_SUBSCRIPTION</code> procedure. Subscription names follow the Oracle schema object naming rules.
source_schema	The name of the schema where the source table resides.
source_table	The name of a published source table.
column_list	A comma-delimited list of columns from the published source table or publication.
subscriber_view	Unique name for the subscriber view for this source table or publication that must consist of 30 or fewer characters and must not have a prefix of <code>CDC\$</code> . Subscriber view names follow the Oracle schema object naming rules.
publication_id	A valid <code>publication_id</code> , which the subscriber can obtain from the <code>ALL_PUBLISHED_COLUMNS</code> view.

Exceptions

Table 21–13 *SUBSCRIBE Procedure Exceptions*

Exception	Description
ORA-31409	One or more values for input parameters are incorrect
ORA-31425	Subscription does not exist
ORA-31426	Cannot modify active subscriptions
ORA-31427	Specified source table already subscribed
ORA-31428	No publication contains all the specified columns
ORA-31432	Invalid source table
ORA-31466	No publications found
ORA-31469	Cannot enable Change Data Capture for change set
ORA-31510	Name uses reserved prefix <code>CDC\$</code>
ORA-31511	Name exceeds maximum length of 30 characters

Usage Notes

- The `SUBSCRIBE` procedure allows a subscriber to subscribe to one or more published source tables and to specific columns in each source table. Each call to the `SUBSCRIBE` procedure can specify only a single source table or publication ID. The subscriber can make multiple calls to the `SUBSCRIBE` procedure to include multiple source tables or publications IDs in a subscription.
- If the columns of interest are all in a single publication, the subscriber can call the `SUBSCRIBE` procedure using the `source_schema` and `source_table` parameters or using the `publication_id` parameter. However, if there are multiple publications on a single source table and these publications share some columns, and if any of the shared columns will be used by a single subscription, then the subscriber should call the `SUBSCRIBE` procedure using the `publication_id` parameter.
- The subscriber can subscribe to any valid publication ID on which the subscriber has privileges to access. The subscriber can find valid publication IDs on which the subscriber has access by querying the `ALL_PUBLISHED_COLUMNS` view.
- A subscriber can query the `ALL_PUBLISHED_COLUMNS` view to see all the published source table columns accessible to the subscriber.
- Subscriptions must be created before a subscriber calls the `SUBSCRIBE` procedure. Change Data Capture does not guarantee that there will be any change data available at the moment the subscription is created.
- Subscribers can subscribe only to published columns from the source table. All of the columns specified in a single call to the `SUBSCRIBE` procedure must come from the same publication. Any control columns associated with the underlying change table are added to the subscription automatically.
- All specified source tables or publications must be in the change set that is associated with the named subscription.
- A single source table can have more than one publication defined on it. A subscriber can subscribe to one or more of these publications. However a subscriber can subscribe to a particular publication only once.
- Each publication in a subscription has its own subscriber view. Subscriber views are used to query the change data encompassed by the subscription's current window. Subscriber views are created in the schema of the subscriber.

- A subscriber cannot subscribe to a publication within a change set that has reached its `end_date` parameter value.

DBMS_CRYPTO provides an interface to encrypt and decrypt stored data, and can be used in conjunction with PL/SQL programs running network communications. It provides support for several industry-standard encryption and hashing algorithms, including the Advanced Encryption Standard (AES) encryption algorithm. AES has been approved by the National Institute of Standards and Technology (NIST) to replace the Data Encryption Standard (DES).

See Also: *Oracle Database Security Guide* for further information about using this package and about encrypting data in general.

This chapter contains the following topics:

- [Using the DBMS_CRYPTO Subprograms](#)
 - [Overview](#)
 - [Security Model](#)
 - [Types](#)
 - [Algorithms](#)
 - [Restrictions](#)
 - [Exceptions](#)
 - [Operational Notes](#)
- [Summary of DBMS_CRYPTO Subprograms](#)

Using the DBMS_CRYPT0 Subprograms

- [Overview](#)
- [Security Model](#)
- [Types](#)
- [Algorithms](#)
- [Restrictions](#)
- [Exceptions](#)
- [Operational Notes](#)

Overview

DBMS_CRYPT0 contains basic cryptographic functions and procedures. To use this package correctly and securely, a general level of security expertise is assumed.

The DBMS_CRYPT0 package enables encryption and decryption for common Oracle datatypes, including RAW and large objects (LOBs), such as images and sound. Specifically, it supports BLOBs and CLOBs. In addition, it provides Globalization Support for encrypting data across different database character sets.

The following cryptographic algorithms are supported:

- Data Encryption Standard (DES), Triple DES (3DES, 2-key and 3-key)
- Advanced Encryption Standard (AES)
- MD5, MD4, and SHA-1 cryptographic hashes
- MD5 and SHA-1 Message Authentication Code (MAC)

Block cipher modifiers are also provided with DBMS_CRYPT0. You can choose from several padding options, including PKCS (Public Key Cryptographic Standard) #5, and from four block cipher chaining modes, including Cipher Block Chaining (CBC).

Table 22-1 lists the DBMS_CRYPT0 package features in comparison to the other PL/SQL encryption package, the DBMS_OBFUSCATION_TOOLKIT.

Table 22–1 DBMS_CRYPT0 and DBMS_OBFUSCATION_TOOLKIT Feature Comparison

Package Feature	DBMS_CRYPT0	DBMS_OBFUSCATION_TOOLKIT
Cryptographic algorithms	DES, 3DES, AES, RC4, 3DES_2KEY	DES, 3DES
Padding forms	PKCS5, zeroes	none supported
Block cipher chaining modes	CBC, CFB, ECB, OFB	CBC
Cryptographic hash algorithms	MD5, SHA-1, MD4	MD5
Keyed hash (MAC) algorithms	HMAC_MD5, HMAC_SH1	none supported
Cryptographic pseudo-random number generator	RAW, NUMBER, BINARY_INTEGER	RAW, VARCHAR2
Database types	RAW, CLOB, BLOB	RAW, VARCHAR2

DBMS_CRYPT0 is intended to replace the DBMS_OBFUSCATION_TOOLKIT, providing greater ease of use and support for a range of algorithms to accommodate new and existing systems. Specifically, 3DES_2KEY and MD4 are provided for backward compatibility. It is not recommended that you use these algorithms because they do not provide the same level of security as provided by 3DES, AES, MD5, or SHA-1.

Security Model

Oracle Database installs this package in the SYS schema. You can then grant package access to existing users and roles as needed.

Types

Parameters for the DBMS_CRYPT0 subprograms use these datatypes:

Table 22–2 DBMS_CRYPT0 Datatypes

Type	Description
BLOB	A source or destination binary LOB
CLOB	A source or destination character LOB (excluding NCLOB)
PLS_INTEGER	Specifies a cryptographic algorithm type (used with BLOB, CLOB, and RAW datatypes)
RAW	A source or destination RAW buffer

Algorithms

The following cryptographic algorithms, modifiers, and cipher suites are predefined in this package.

Table 22–3 *DBMS_CRYPTO Cryptographic Hash Functions*

Name	Description
HASH_MD4	Produces a 128-bit hash, or message digest of the input message
HASH_MD5	Also produces a 128-bit hash, but is more complex than MD4
HASH_SH1	Secure Hash Algorithm (SHA). Produces a 160-bit hash.

Table 22–4 *DBMS_CRYPTO MAC (Message Authentication Code) Functions*

Name	Description
HMAC_MD5 ¹	Same as MD5 hash function, except it requires a secret key to verify the hash value.
HMAC_SH1 ¹	Same as SHA hash function, except it requires a secret key to verify the hash value.

¹ Complies with IETF RFC 2104 standard

Table 22–5 *DBMS_CRYPTO Encryption Algorithms*

Name	Description
ENCRYPT_DES	Data Encryption Standard. Block cipher. Uses key length of 56 bits.
ENCRYPT_3DES_2KEY	Data Encryption Standard. Block cipher. Operates on a block 3 times with 2 keys. Effective key length of 112 bits.
ENCRYPT_3DES	Data Encryption Standard. Block cipher. Operates on a block 3 times.
ENCRYPT_AES128	Advanced Encryption Standard. Block cipher. Uses 128-bit key size.
ENCRYPT_AES192	Advanced Encryption Standard. Block cipher. Uses 192-bit key size.
ENCRYPT_AES256	Advanced Encryption Standard. Block cipher. Uses 256-bit key size.
ENCRYPT_RC4	Stream cipher. Uses a secret, randomly generated key unique to each session.

Table 22–6 DBMS_CRYPT0 Block Cipher Suites

Name	Description
DES_CBC_PKCS5	ENCRYPT_DES ¹ + CHAIN_CBC ² + PAD_PKCS5 ³
DES3_CBC_PKCS5	ENCRYPT_3DES ¹ + CHAIN_CBC ² + PAD_PKCS5 ³

¹ See Table 22–5, "DBMS_CRYPT0 Encryption Algorithms"

² See Table 22–7, "DBMS_CRYPT0 Block Cipher Chaining Modifiers"

³ See Table 22–8, "DBMS_CRYPT0 Block Cipher Padding Modifiers"

Table 22–7 DBMS_CRYPT0 Block Cipher Chaining Modifiers

Name	Description
CHAIN_ECB	Electronic Codebook. Encrypts each plaintext block independently.
CHAIN_CBC	Cipher Block Chaining. Plaintext is XORed with the previous ciphertext block before it is encrypted.
CHAIN_CFB	Cipher-Feedback. Enables encrypting units of data smaller than the block size.
CHAIN_OFB	Output-Feedback. Enables running a block cipher as a synchronous stream cipher. Similar to CFB, except that <i>n</i> bits of the previous output block are moved into the right-most positions of the data queue waiting to be encrypted.

Table 22–8 DBMS_CRYPT0 Block Cipher Padding Modifiers

Name	Description
PAD_PKCS5	Provides padding which complies with the PKCS #5: Password-Based Cryptography Standard
PAD_NONE	Provides option to specify no padding. Caller must ensure that blocksize is correct, else the package returns an error.
PAD_ZERO	Provides padding consisting of zeroes.

Restrictions

The VARCHAR2 datatype is not directly supported by DBMS_CRYPT0. Before you can perform cryptographic operations on data of the type VARCHAR2, you must convert it to the uniform database character set AL32UTF8, and then convert it to

the RAW datatype. After performing these conversions, you can then encrypt it with the DBMS_CRYPTO package.

See Also: ["Conversion Rules"](#) on page 22-8 for information about converting datatypes.

Exceptions

[Table 22-9](#) lists exceptions that have been defined for DBMS_CRYPTO.

Table 22-9 DBMS_CRYPTO Exceptions

Exception	Code	Description
CipherSuiteInvalid	28827	The specified cipher suite is not defined.
CipherSuiteNull	28829	No value has been specified for the cipher suite to be used.
KeyNull	28239	The encryption key has not been specified or contains a NULL value.
KeyBadSize	28234	<ul style="list-style-type: none"> ■ DES keys: Specified key size is too short. DES keys must be at least 8 bytes (64 bits). ■ AES keys: Specified key size is not supported. AES keys must be 128, 192, or 256 bits in length.
DoubleEncryption	28233	Source data was previously encrypted.

Operational Notes

- [When to Use Encrypt and Decrypt Procedures or Functions](#)
- [When to Use Hash or Message Authentication Code \(MAC\) Functions](#)
- [About Generating and Storing Encryption Keys](#)
- [Conversion Rules](#)

When to Use Encrypt and Decrypt Procedures or Functions

This package includes both ENCRYPT and DECRYPT procedures and functions. The procedures are used to encrypt or decrypt LOB datatypes (overloaded for CLOB and BLOB datatypes). In contrast, the ENCRYPT and DECRYPT functions are used to

encrypt and decrypt RAW datatypes. Data of type VARCHAR2 must be converted to RAW before you can use DBMS_CRYPTO functions to encrypt it.

When to Use Hash or Message Authentication Code (MAC) Functions

This package includes two different types of one-way hash functions: the HASH function and the MAC function. Hash functions operate on an arbitrary-length input message, and return a fixed-length hash value. One-way hash functions work in one direction only. It is easy to compute a hash value from an input message, but it is extremely difficult to generate an input message that hashes to a particular value. Note that hash values should be at least 128 bits in length to be considered secure.

You can use hash values to verify whether data has been altered. For example, before storing data, Laurel runs DBMS_CRYPTO.HASH against the stored data to create a hash value. When she retrieves the stored data at a later date, she can again run the hash function against it, using the same algorithm. If the second hash value is identical to the first one, then the data has not been altered. Hash values are similar to "file fingerprints" and are used to ensure data integrity.

The HASH function included with DBMS_CRYPTO, is a one-way hash function that you can use to generate a hash value from either RAW or LOB data. The MAC function is also a one-way hash function, but with the addition of a secret key. It works the same way as the DBMS_CRYPTO.HASH function, except only someone with the key can verify the hash value.

MACs can be used to authenticate files between users. They can also be used by a single user to determine if her files have been altered, perhaps by a virus. A user could compute the MAC of his files and store that value in a table. If the user did not use a MAC function, then the virus could compute the new hash value after infection and replace the table entry. A virus cannot do that with a MAC because the virus does not know the key.

About Generating and Storing Encryption Keys

The DBMS_CRYPTO package can generate random material for encryption keys, but it does not provide a mechanism for maintaining them. Application developers must take care to ensure that the encryption keys used with this package are securely generated and stored. Also note that the encryption and decryption operations performed by DBMS_CRYPTO occur on the server, not on the client. Consequently, if the key is sent over the connection between the client and the server, the connection must be protected by using network encryption. Otherwise, the key is vulnerable to capture over the wire.

Although `DBMS_CCRYPTO` cannot generate keys on its own, it does provide tools you can use to aid in key generation. For example, you can use the `RANDOMBYTES` function to generate random material for keys. (Calls to the `RANDOMBYTES` function behave like calls to the `DESGETKEY` and `DES3GETKEY` functions of the `DBMS_OBFUSCATION_TOOLKIT` package.)

When generating encryption keys for DES, it is important to remember that some numbers are considered weak and semiweak keys. Keys are considered weak or semiweak when the pattern of the algorithm combines with the pattern of the initial key value to produce ciphertext that is more susceptible to cryptanalysis. To avoid this, filter out the known weak DES keys. Lists of the known weak and semiweak DES keys are available on several public Internet sites.

See Also:

- *Oracle Advanced Security Administrator's Guide* for information about configuring network encryption and SSL.
- ["Key Management"](#) on page 55-3 for a full discussion about securely storing encryption keys
- ["RANDOMBYTES Function"](#) on page 22-21

Conversion Rules

- To convert `VARCHAR2` to `RAW`, use the `UTL_I18N.STRING_TO_RAW` function to perform the following steps:
 1. Convert `VARCHAR2` in the current database character set to `VARCHAR2` in the `AL32UTF8` database character.
 2. Convert `VARCHAR2` in the `AL32UTF8` database character set to `RAW`.

Syntax example:

```
UTL_I18N.STRING_TO_RAW (string, 'AL32UTF8');
```

- To convert `RAW` to `VARCHAR2`, use the `UTL_I18N.RAW_TO_CHAR` function to perform the following steps:
 1. Convert `RAW` to `VARCHAR2` in the `AL32UTF8` database character set.
 2. Convert `VARCHAR2` in the `AL32UTF8` database character set to `VARCHAR2` in the database character set you wish to use.

Syntax example:

```
UTL_I18N.RAW_TO_CHAR (data, 'AL32UTF8');
```

See Also: [Chapter 157, "UTL_I18N"](#) for information about using the UTL_I18N PL/SQL package.

- If you want to store encrypted data of the RAW datatype in a VARCHAR2 database column, then use RAWTOHEX or UTL_ENCODE.BASE64_ENCODE to make it suitable for VARCHAR2 storage. These functions expand data size by 2 and 4/3, respectively.

Summary of DBMS_CRYPT0 Subprograms

Table 22–10 DBMS_CRYPT0 Package Subprograms

Subprogram	Description
DECRYPT Function on page 22-11	Decrypts RAW data using a stream or block cipher with a user supplied key and optional IV (initialization vector)
DECRYPT Procedures on page 22-13	Decrypts LOB data using a stream or block cipher with a user supplied key and optional IV
ENCRYPT Function on page 22-14	Encrypts RAW data using a stream or block cipher with a user supplied key and optional IV
ENCRYPT Procedures on page 22-16	Encrypts LOB data using a stream or block cipher with a user supplied key and optional IV
HASH Function on page 22-17	Applies one of the supported cryptographic hash algorithms (MD4, MD5, or SHA-1) to data
MAC Function on page 22-19	Applies Message Authentication Code algorithms (MD5 or SHA-1) to data to provide keyed message protection
RANDOMBYTES Function on page 22-21	Returns a RAW value containing a cryptographically secure pseudo-random sequence of bytes, and can be used to generate random material for encryption keys
RANDOMINTEGER Function on page 22-22	Returns a random BINARY_INTEGER
RANDOMNUMBER Function on page 22-23	Returns a random 128-bit integer of the NUMBER datatype

DECRYPT Function

This function decrypts RAW data using a stream or block cipher with a user supplied key and optional IV (initialization vector).

Syntax

```
DBMS_CRYPT0.DECRYPT(
  src IN RAW,
  typ IN PLS_INTEGER,
  key IN RAW,
  iv  IN RAW          DEFAULT NULL)
RETURN RAW;
```

Pragmas

```
pragma restrict_references(decrypt,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 22–11 DECRYPT Function Parameters

Parameter Name	Description
src	RAW data to be decrypted.
typ	Stream or block cipher type and modifiers to be used.
key	Key to be used for decryption.
iv	Optional initialization vector for block ciphers. Default is NULL.

Usage Notes

- To retrieve original plaintext data, DECRYPT must be called with the same cipher, modifiers, key, and IV that was used to encrypt the data originally.

See Also: ["Usage Notes"](#) for the ENCRYPT function on page 22-14 for additional information about the ciphers and modifiers available with this package.

- If VARCHAR2 data is converted to RAW before encryption, then it must be converted back to the appropriate database character set by using the UTL_I18N package.

See Also: ["Conversion Rules"](#) on page 22-8 for a discussion of the VARCHAR2 to RAW conversion process.

DECRYPT Procedures

These procedures decrypt LOB data using a stream or block cipher with a user supplied key and optional IV (initialization vector).

Syntax

```
DBMS_CRYPTO.DECRYPT(
  dst IN OUT NOCOPY BLOB,
  src IN           BLOB,
  typ IN           PLS_INTEGER,
  key IN           RAW,
  iv IN           RAW          DEFAULT NULL);

DBMS_CRYPT.DECRYPT(
  dst IN OUT NOCOPY CLOB          CHARACTER SET ANY_CS,
  src IN           BLOB,
  typ IN           PLS_INTEGER,
  key IN           RAW,
  iv IN           RAW          DEFAULT NULL);
```

Pragmas

```
pragma restrict_references(decrypt,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 22–12 *DECRYPT Procedure Parameters*

Parameter Name	Description
dst	LOB locator of output data. The value in the output LOB <dst> will be overwritten.
src	LOB locator of input data.
typ	Stream or block cipher type and modifiers to be used.
key	Key to be used for decryption.
iv	Optional initialization vector for block ciphers. Default is all zeroes.

ENCRYPT Function

This function encrypts RAW data using a stream or block cipher with a user supplied key and optional IV (initialization vector).

Syntax

```
DBMS_CRYPTO.ENCRYPT(
  src IN RAW,
  typ IN PLS_INTEGER,
  key IN RAW,
  iv IN RAW          DEFAULT NULL)
RETURN RAW;
```

Pragmas

```
pragma restrict_references(encrypt,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 22–13 ENCRYPT Function Parameters

Parameter Name	Description
src	RAW data to be encrypted.
typ	Stream or block cipher type and modifiers to be used.
key	Encryption key to be used for encrypting data.
iv	Optional initialization vector for block ciphers. Default is NULL.

Usage Notes

- Block ciphers may be modified with chaining and padding type modifiers. The chaining and padding type modifiers are added to the block cipher to produce a cipher suite. Cipher Block Chaining (CBC) is the most commonly used chaining type, and PKCS #5 is the recommended padding type. See [Table 22–7](#) and [Table 22–8](#) on page 22-5 for block cipher chaining and padding modifier constants that have been defined for this package.
- To improve readability, you can define your own package-level constants to represent the cipher suites you use for encryption and decryption. For example, the following example defines a cipher suite that uses DES, cipher block chaining mode, and no padding:


```
DES_CBC_NONE CONSTANT PLS_INTEGER := DBMS_CRYPTO.ENCRYPT_DES
                                     + DBMS_CRYPTO.CHAIN_CBC
                                     + DBMS_CRYPTO.PAD_NONE;
```

See [Table 22-6](#) on page 22-5 for the block cipher suites already defined as constants for this package.

- To encrypt `VARCHAR2` data, it should first be converted to the AL32UTF8 character set.

See Also: "[Conversion Rules](#)" on page 22-8 for a discussion of the conversion process.

- Stream ciphers, such as RC4, are not recommended for stored data encryption.

ENCRYPT Procedures

These procedures encrypt LOB data using a stream or block cipher with a user supplied key and optional IV (initialization vector).

Syntax

```
DBMS_CRYPTO.ENCRYPT(
  dst IN OUT NOCOPY BLOB,
  src IN          BLOB,
  typ IN          PLS_INTEGER,
  key IN          RAW,
  iv IN          RAW          DEFAULT NULL);
```

```
DBMS_CRYPTO.ENCRYPT(
  dst IN OUT NOCOPY BLOB,
  src IN          CLOB          CHARACTER SET ANY_CS,
  typ IN          PLS_INTEGER,
  key IN          RAW,
  iv IN          RAW          DEFAULT NULL);
```

Pragmas

```
pragma restrict_references(encrypt, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 22–14 ENCRYPT Procedure Parameters

Parameter Name	Description
dst	LOB locator of output data. The value in the output LOB <dst> will be overwritten.
src	LOB locator of input data.
typ	Stream or block cipher type and modifiers to be used.
key	Encryption key to be used for encrypting data.
iv	Optional initialization vector for block ciphers. Default is NULL.

Usage Notes

See "[Conversion Rules](#)" on page 22-8 for usage notes about using the ENCRYPT procedure.

HASH Function

A one-way hash function takes a variable-length input string, the data, and converts it to a fixed-length (generally smaller) output string called a *hash value*. The hash value serves as a unique identifier (like a fingerprint) of the input data. You can use the hash value to verify whether data has been changed or not.

Note that a one-way hash function is a hash function that works in one direction. It is easy to compute a hash value from the input data, but it is hard to generate data that hashes to a particular value. Consequently, one-way hash functions work well to ensure data integrity. Refer to ["When to Use Hash or Message Authentication Code \(MAC\) Functions"](#) on page 22-7 for more information about using one-way hash functions.

This function applies to data one of the supported cryptographic hash algorithms listed in [Table 22-3](#) on page 22-4.

Syntax

```
DBMS_CRYPT0.Hash (  
    src IN RAW,  
    typ IN PLS_INTEGER)  
RETURN RAW;  
  
DBMS_CRYPT0.Hash (  
    src IN BLOB,  
    typ IN PLS_INTEGER)  
RETURN RAW;  
  
DBMS_CRYPT0.Hash (  
    src IN CLOB CHARACTER SET ANY_CS,  
    typ IN PLS_INTEGER)  
RETURN RAW;
```

Pragmas

```
pragma restrict_references(hash,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 22–15 *HASH Function Parameters*

Parameter Name	Description
<code>src</code>	The source data to be hashed.
<code>typ</code>	The hash algorithm to be used.

Usage Note

Oracle recommends that you use the SHA-1 (Secure Hash Algorithm), specified with the constant, `HASH_SH1`, because it is more resistant to brute-force attacks than MD4 or MD5. If you must use a Message Digest algorithm, then MD5 provides greater security than MD4.

MAC Function

A Message Authentication Code, or MAC, is a key-dependent one-way hash function. MACs have the same properties as the one-way hash function described in ["HASH Function"](#) on page 22-17, but they also include a key. Only someone with the identical key can verify the hash. Also refer to ["When to Use Hash or Message Authentication Code \(MAC\) Functions"](#) on page 22-7 for more information about using MACs.

This function applies MAC algorithms to data to provide keyed message protection. See [Table 22-4](#) on page 22-4 for a list of MAC algorithms that have been defined for this package.

Syntax

```
DBMS_CRYPT0.MAC (
    src IN RAW,
    typ IN PLS_INTEGER,
    key IN RAW)
RETURN RAW;

DBMS_CRYPT0.MAC (
    src IN BLOB,
    typ IN PLS_INTEGER
    key IN RAW)
RETURN RAW;

DBMS_CRYPT0.MAC (
    src IN CLOB CHARACTER SET ANY_CS,
    typ IN PLS_INTEGER
    key IN RAW)
RETURN RAW;
```

Pragmas

```
pragma restrict_references(mac,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 22-16 MAC Function Parameters

Parameter Name	Description
src	Source data to which MAC algorithms are to be applied.

Table 22–16 *MAC Function Parameters*

Parameter Name	Description
<code>typ</code>	MAC algorithm to be used.
<code>key</code>	Key to be used for MAC algorithm.

RANDOMBYTES Function

This function returns a RAW value containing a cryptographically secure pseudo-random sequence of bytes, which can be used to generate random material for encryption keys. The RANDOMBYTES function is based on the RSA X9.31 PRNG (Pseudo-Random Number Generator), and it draws its entropy (seed) from the `sqlnet.ora` file parameter `SQLNET.CRYPTO_SEED`.

Syntax

```
DBMS_CRYPTO.RANDOMBYTES (
    number_bytes IN POSITIVE)
RETURN RAW;
```

Pragmas

```
pragma restrict_references(randombytes,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 22–17 *RANDOMBYTES Function Parameter*

Parameter Name	Description
<code>number_bytes</code>	The number of pseudo-random bytes to be generated.

Usage Note

- The `number_bytes` value should not exceed the maximum length of a RAW variable.
- The `SQLNET.CRYPTO_SEED` parameter can be set by entering 10 to 70 random characters with the following syntax in the `sqlnet.ora` file:

```
SQLNET.CRYPTO_SEED = <10 to 70 random characters>
```

See Also: *Oracle Advanced Security Administrator's Guide* for more information about the `SQLNET.CRYPTO_SEED` parameter and its use.

RANDOMINTEGER Function

This function returns an integer in the complete range available for the Oracle `BINARY_INTEGER` datatype.

Syntax

```
DBMS_CRYPTO.RANDOMINTEGER  
RETURN BINARY_INTEGER;
```

Pragmas

```
pragma restrict_references(randominteger,WNDS,RNDS,WNPS,RNPS);
```


RANDOMNUMBER Function

This function returns an integer in the Oracle NUMBER datatype in the range of $[0..2^{128}-1]$.

Syntax

```
DBMS_CRYPT0.RandomNumber  
RETURN NUMBER;
```

Pragmas

```
pragma restrict_references(randomnumber,WNDS,RNDS,WNPS,RNPS);
```

DBMS_DATA_MINING

Oracle Data Mining (ODM) is designed for programmers, systems analysts, project managers, and others interested in developing database applications that use data mining to discover hidden patterns and use that knowledge to make predictions.

This chapter contains the following topics:

- [Using DBMS_DATA_MINING](#)
 - [Overview](#)
 - [Constants](#)
 - [Data Types](#)
 - [Exceptions](#)
 - [User Views](#)
 - [Constants](#)
- [Summary of DBMS_DATA_MINING Subprograms](#)

Using DBMS_DATA_MINING

- [Overview](#)
- [Constants](#)
- [Data Types](#)
- [Exceptions](#)
- [User Views](#)
- [Constants](#)

Overview

Oracle Data Mining (ODM) embeds data mining in the Oracle database. The data never leaves the database — the data, its preparation, model building, and model scoring activities all remain in the database. This enables Oracle to provide an infrastructure for data analysts and application developers to integrate data mining seamlessly with database applications.

ODM provides two interfaces that support in-database data mining: a Java interface and a PL/SQL interface. The Java interface is described in *Oracle Data Mining Application Developer's Guide*.

You can use the package to build a mining model, test the model, and apply this model to your data to obtain predictive and descriptive information. For detailed examples of how to perform these tasks, see the sample programs in *Oracle Data Mining Application Developer's Guide*. The sample code is in the demo directory.

General information about both the Java and the PL/SQL interface is contained in *Oracle Data Mining Application Developer's Guide*. See *Oracle Data Mining Concepts for a discussion of data mining concepts*.

This chapter contains an overview of the development methodology, followed by information on data types, settings, and constants, as well as detailed descriptions of the PL/SQL subprograms. The [DBMS_DATA_MINING_TRANSFORM](#) package supports data pre-processing for data mining.

Constants

Table 23–1 through Table 23–8 list the constants to be used for various settings in the settings table.

Table 23–1 DBMS_DATA_MINING Constants Summary: Mining Function

Constant	Purpose
association	Parameter value for <i>mining function</i> in CREATE_MODEL, representing association mining function.
attribute_importance	Parameter value for <i>mining function</i> in CREATE_MODEL, representing attribute importance mining function.
classification	Parameter value for <i>mining function</i> in CREATE_MODEL, representing classification mining function.
regression	Parameter value for <i>mining function</i> in CREATE_MODEL, representing regression mining function.
clustering	Parameter value for <i>mining function</i> in CREATE_MODEL, representing clustering mining function.
feature_extraction	Parameter value for <i>mining function</i> in CREATE_MODEL, representing feature extraction mining function.

Table 23–2 DBMS_DATA_MINING Constants Summary: Function Settings

Constant	Purpose
clas_priors_table_name	Setting name representing prior probability table name for classification function.
clus_num_clusters	Setting name representing number of clusters for clustering function.
feat_num_features	Setting name representing number of features for feature selection function.
asso_max_rule_length	Setting name representing maximum rule length.
asso_min_confidence	Setting name representing minimum confidence.
asso_min_support	Setting name representing minimum support.

Table 23–3 DBMS_DATA_MINING Constants Summary: Algorithm Settings

Constant	Purpose
algo_name	Setting name representing the mining algorithm.
algo_apriori_association_rules	Setting value for Apriori algorithm for association rules.
algo_naive_bayes	Setting value for Naive Bayes (NB) algorithm for classification.
algo_support_vector_machines	Setting value for Support Vector Machines (SVM) algorithm for classification or regression.
algo_nonnegative_matrix_factor	Setting value for Non-Negative Matrix Factorization (NMF) for feature selection.
algo_kmeans	Setting value for <i>k</i> -Means (KM) for clustering.
algo_ai_md1	Setting value for Minimum Description Length based algorithm for Attribute Importance.

Table 23–4 DBMS_DATA_MINING Constants Summary: Adaptive Bayes Network

Constant	Purpose
abns_model_type	Setting name representing ABN model type.
abns_single_feature	Setting value representing single feature ABN model.
abns_multi_feature	Setting value representing multi feature ABN model.
abns_naive_bayes	Setting value representing Naive Bayes ABN model.
abns_max_build_minutes	Setting name representing maximum time threshold to complete an ABN model build.
abns_max_nb_predictors	Setting name representing the maximum number of Naive Bayes predictors to be considered for building an ABN model of type abns_naive_bayes.

Table 23–5 DBMS_DATA_MINING Constants Summary: Naive Bayes

Constant	Purpose
nabs_singleton_threshold	Setting value for singleton threshold for Naive Bayes.
nabs_pairwise_threshold	Setting value for pair-wise threshold for Naive Bayes.

Table 23–6 DBMS_DATA_MINING Constants Summary: Support Vector Machines

Constant	Purpose
svms_kernel_function	Setting name representing the kernel function for SVM.
svms_linear	Setting value for Linear Kernel for SVM.
svms_guassian	Setting value for Gaussian Kernel for SVM.
svms_kernel_cache_size	Setting name representing for Kernel Cache Size for SVM.
svms_conv_tolerance	Setting name representing tolerance for SVM.
svms_std_dev	Setting name representing standard deviation for SVM.
svms_complexity_factor	Setting name representing complexity factor for SVM.
svms_epsilon	Setting name representing epsilon for SVM Regression.

Table 23–7 DBMS_DATA_MINING Constants Summary: Non-Negative Matrix Factorization

Constant	Purpose
nmfs_num_iterations	Setting name representing number of iterations.
nmfs_conv_tolerance	Setting name representing convergence tolerance.
nmfs_random_seed	Setting name representing random seed for NMF.

Table 23–8 DBMS_DATA_MINING Constants Summary: k-Means

Constant	Purpose
kmns_distance	Setting name representing distance function.
kmns_euclidean	Setting value representing Euclidean distance function.
kmns_cosine	Setting value representing cosine distance function.
kmns_fast_cosine	Setting value representing fast cosine distance function.
kmns_iterations	Setting name representing number of iterations.
kmns_conv_tolerance	Setting name representing convergence tolerance.
kmns_split_criterion	Setting name representing split criterion.
kmns_variance	Setting value representing variance as the split criterion.

Table 23–8 (Cont.) DBMS_DATA_MINING Constants Summary: k-Means

Constant	Purpose
kmns_size	Setting value representing size as the split criterion.
kmns_block_growth	Setting name representing growth factor for memory allocated to hold cluster data.
kmns_num_bins	Setting value for number of histogram bins.
kmns_min_pct_attr_support	Setting value for minimum percentage report required for attributes in rules.

Data Types

The `DBMS_DATA_MINING` and the `DBMS_DATA_MINING_TRANSFORM` packages use the data types shown in [Table 23–9](#).

Table 23–9 DBMS_DATA_MINING Summary of Data Types

Data Type	Purpose
DM_ABN_Detail	This type represents each row of the model detail output generated by <code>GET_MODEL_DETAILS_ABN</code> .
DM_ABN_Details	This type represents the ABN model details generated by <code>GET_MODEL_DETAILS_ABN</code> .
DM_Centroid	This type represents the centroid of a cluster. It is used when retrieving cluster details using <code>GET_MODEL_DETAILS_KM</code> .
DM_Child	This type represents each child node of a cluster.
DM_Children	This type represents a set of children nodes for a given cluster identifier.
DM_Cluster	This type represents a cluster retrieved using <code>GET_MODEL_DETAILS_KM</code> .
DM_Clusters	This type represents a set of clusters.
DM_Conditional	This type represents each conditional probability from a set of conditional probabilities associated with each mining attribute used in a Naive Bayes or Adaptive Bayes Network model.
DM Conditionals	This type represents conditional probabilities associated with a given mining attribute used in a Naive Bayes or Adaptive Bayes Network model. It is used when retrieving model details using <code>GET_MODEL_DETAILS_NB</code> or <code>GET_MODEL_DETAILS_ABN</code> respectively.

Table 23–9 DBMS_DATA_MINING Summary of Data Types

Data Type	Purpose
DM_Histogram_Bin	This type represents a histogram associated with a cluster identifier. It is used when retrieving cluster details using GET_MODEL_DETAILS_KM.
DM_Histograms	This type represents a set of histograms.
DM_Item	This type represents an item in a set of items.
DM_Items	This type represents the set of items in an ItemSet.
DM_ItemSet	This type represents an ItemSet.
DM_ItemSets	This type represents frequent itemsets in Association models.
DM_Model_Settings	This type represents the algorithm settings retrieved using the GET_MODEL_SETTINGS function.
DM_Model_Signature	This type represents a list of model signature attributes generated by GET_MODEL_SIGNATURE.
DM_Modelname_List	This type represents a list of model names provided as input for the parameter model_names in EXPORT_MODEL and IMPORT_MODEL procedures.
DM_NB_Detail	This type represents the each row of the model detail output generated by GET_MODEL_DETAILS_NB.
DM_NB_Details	This type represents the NB model details generated by GET_MODEL_DETAILS_NB.
DM_Nested_Categoricals	This type represents a nested table of categorical attributes, used for representing wide data.
DM_Nested_Numericals	This type represents a nested table of numerical attributes, used for representing wide data.
DM_NMF_Attribute	This type represents each attribute in an attribute set for NMF model details.
DM_NMF_Attribute_Set	This type represents a set of attributes that correspond to a feature identifier, returned by GET_MODEL_DETAILS_NMF.
DM_NMF_Feature	This type represents a feature in a NMF model.
DM_NMF_Feature_Set	This type represents a set of features returned by GET_MODEL_DETAILS_NMF.
DM_Predicate	This type represents each predicate in the set of predicates in a rule.

Table 23–9 DBMS_DATA_MINING Summary of Data Types

Data Type	Purpose
DM_Predicates	This type represents a set of predicates that constitute either the antecedent or the consequent of a rule.
DM_Ranked_Attribute	This type represents an entry in the set of ranked attribute returned by GET_MODEL_DETAILS_AI, ranked by the attribute's importance.
DM_Ranked_Attributes	This type represents a list of ranked attributes returned by GET_MODEL_DETAILS_AI.
DM_Rule	This type represents each rule in a list of rules generated by either GET_ASSOCIATION_RULES or GET_MODEL_DETAILS_KM.
DM_Rules	This type represents rules retrieved for Association Rules or <i>k</i> -means models using GET_ASSOCIATION_RULES and GET_MODEL_DETAILS_KM respectively.
DM_SVM_Attribute	This type represents each attribute in an attribute set for SVM model details.
DM_SVM_Attribute_Set	This type represents a set of attributes returned by GET_MODEL_DETAILS_SVM for a linear model.
DM_SVM_Linear_Coeff	This type represents an entry in the set of linear coefficients returned by GET_MODEL_DETAILS_SVM.
DM_SVM_Linear_Coeff_Set	This type represents the set of linear coefficients returned by GET_MODEL_DETAILS_SVM for an SVM model built using the linear kernel.

Exceptions

Table 23–10 lists the errors generated by DBMS_DATA_MINING.

Table 23–10 *DBMS DATA_MINING Errors Summary*

Oracle Error	Description
ORA-40201	Invalid input parameter %s.
ORA-40202	Column %s does not exist in the input table %s.
ORA-40203	Model %s does not exist.
ORA-40204	Model %s already exists.
ORA-40205	Invalid setting name %s.
ORA-40206	Invalid setting value for setting name %s.
ORA-40207	Duplicate or multiple function settings.
ORA-40208	Duplicate or multiple algorithm settings for function %s.
ORA-40209	Invalid setting: %s for function %s.
ORA-40211	Algorithm name: %s is invalid.
ORA-40212	Invalid target data type in input data for function: %.
ORA-40213	Contradictory values for settings: %s, %s.
ORA-40214	Duplicate setting: %s.
ORA-40215	Model %s is incompatible with current operation.
ORA-40216	Feature not supported.
ORA-40219	Apply result table %s is incompatible with current operation.
ORA-40220	Maximum number of attributes exceeded.
ORA-40221	Maximum target cardinality exceeded.
ORA-40222	Data mining model export failed, job name=%s, error=%s.
ORA-40223	Data mining model import failed, job name=%s, error=%s.
ORA-40225	Model is currently in use by another process.
ORA-40251	No support vectors were found.
ORA-40252	No target values were found.
ORA-40253	No target counter examples were found.
ORA-40261	Input data for model build contains negative values.

Table 23–10 (Cont.) DBMS_DATA_MINING Errors Summary

Oracle Error	Description
ORA-40262	NMF: number of features not between [1, %s].
ORA-40271	No statistically significant features were found.
ORA-40272	Apply rules prohibited for this model mode.
ORA-40273	Invalid model type %s for Adaptive Bayes Network algorithm.

User Views

[Table 23–11](#) lists the user views provided by Oracle to obtain information about the models generated using `DBMS_DATA_MINING`

Table 23–11 DBMS_DATA_MINING Summary of User Views

User View	Purpose
<code>DM_USER_MODELS</code>	Lists all models in a given user's schema.

Operational Notes

The development methodology for data mining using the `DBMS_DATA_MINING` interface is divided into two phases.

The first phase includes your application data analysis and design, where you perform the following two steps:

1. Analyze your problem, and choose the mining function and algorithm.
2. Analyze the data to be used for building mining models (build data), testing predictive models (test data), and the new data on which the model will be applied (scoring data).

The second phase involves developing a mining application using `DBMS_DATA_MINING` and `DBMS_DATA_MINING_TRANSFORM` packages.

3. Prepare the build, test, and scoring data using the `DBMS_DATA_MINING_TRANSFORM` package or other third-party tool or direct SQL or PL/SQL utility scripts in a manner suitable for the chosen mining function and algorithm. An important caveat is that the three datasets referred to earlier have to be prepared in an identical manner for mining results to be meaningful. This is an optional step, required only if your data is not prepared for mining.

4. Prepare a settings table that overrides the default mining algorithm for a given mining function, and the default algorithm settings. This is also an optional step.
5. Build a mining model for the given training dataset.
6. For predictive models (classification and regression), test the model for its accuracy and measures of performance. This amounts to applying the model on the test data (that is, scoring the test data), and computing various metrics on the apply results.
7. Retrieve the model signature to determine the mining attributes that will be used by a given model for scoring. This information will help ascertain that the scoring data is suitable for a given model. This is an optional step.
8. Apply a classification, regression, clustering, or feature extraction model to new data to generate predictions and/or descriptive summaries and patterns about the data.
9. Retrieve the model details to understand why a model scored the data in a particular manner. This is an optional step.
10. Repeat steps 3 through 9 until you obtain satisfactory results.

See *Oracle Data Mining Application Developer's Guide* for more general discussion of the PL/SQL interface to Oracle Data Mining.

Settings Table

The settings table is a simple relational table with a *fixed* schema. You can choose the name of the settings table, but the column names and their types must be defined as specified:

```
(setting_name VARCHAR2(30),
 setting_value VARCHAR2(128))
```

The values provided in the settings table override the default values assumed by the system. The values inserted into the *setting_name* column are one or more of several constants defined in the DBMS_DATA_MINING package. Depending on what the setting name denotes, the value for the *setting_value* column can be a predefined constant or the actual numerical or string value corresponding to the setting itself. The *setting_value* column is defined to be VARCHAR2, so you must cast numerical inputs to string using the TO_CHAR function before input into the settings table.

[Table 23–12](#) through [Table 23–17](#) list the various setting names and the valid setting values, with a brief explanation of each setting

Table 23–12 DBMS_DATA_MINING Function Settings

Algorithm Settings	Setting Value (with Permissible Value Ranges)
<code>algo_name</code>	Classification: One of: <code>algo_naive_bayes</code> <code>algo_support_vector_machines</code> <code>algo_adaptive_bayes_network</code> Regression: <code>algo_support_vector_machines</code> Association Rules: <code>algo_apriori_association_rules</code> Clustering: <code>algo_kmeans</code> Feature Extraction: <code>algo_non_negative_matrix_factor</code> Attribute Importance: <code>algo_ai_md1</code>
<code>clas_priors_table_name</code>	VARCHAR2 string denoting the name of a relational table of fixed schema containing prior probabilities. The schema of this table is provided in on page 23-17 . This input is applicable only for classification algorithms. The prior probabilities table must be present in the current user's schema.
<code>clus_num_clusters</code>	TO_CHAR(<i>numeric_expr</i> >= 1) Number of clusters generated by a clustering algorithm. Default value is 10.
<code>feat_num_features</code>	TO_CHAR(<i>numeric_expr</i> >= 1) Number of features to be extracted. Default value estimated from the data by the algorithm.
<code>asso_max_rule_length</code>	TO_CHAR(2 <= <i>numeric_expr</i> <= 20) Maximum rule length for AR algorithm. Default value is 4.

Table 23–12 DBMS_DATA_MINING Function Settings

Algorithm Settings	Setting Value (with Permissible Value Ranges)
asso_min_confidence	TO_CHAR(0 <= <i>numeric_expr</i> <= 1) Minimum confidence value for AR algorithm. Default value is 0.1.
asso_min_support	TO_CHAR(0 <= <i>numeric_expr</i> <= 1) Minimum support value for AR algorithm. Default value is 0.1.

Table 23–13 Algorithm Settings for Adaptive Bayes Network

Setting Name	Setting Value (with Permissible Value Ranges)
abns_model_type	Model type for Adaptive Bayes Network: <ul style="list-style-type: none"> ■ abns_single_feature ■ abns_multi_feature ■ abns_naive_bayes Default value is abns_multi_feature.
abns_max_build_minutes	TO_CHAR(<i>numeric_expr</i> >= 0) The maximum time threshold for completion of model build. Default value is 0, which implies no time limit.
abns_max_nb_predictors	TO_CHAR(<i>numeric_expr</i> > 0) Maximum number of Naive Bayes predictors to be considered for model build, when the model type is chosen to be abns_naive_bayes. Default value is 10.
abns_max_predictors	TO_CHAR(<i>numeric_expr</i> > 0) Default is 25.

Table 23–14 Algorithm Settings for Naive Bayes

Setting Name	Setting Value (with Permissible Value Ranges)
nabs_singleton_threshold	TO_CHAR (0 <= <i>numeric_expr</i> <=1) Value of singleton threshold for NB algorithm. Default value is 0.01.

Table 23–14 (Cont.) Algorithm Settings for Naive Bayes

Setting Name	Setting Value (with Permissible Value Ranges)
nabs_pairwise_threshold	TO_CHAR (0 <= <i>numeric_expr</i> <=1) Value of pairwise threshold for NB algorithm. Default value is 0.01.

Table 23–15 Algorithm Settings for Support Vector Machines

Setting Name	Setting Value (with Permissible Value Ranges)
svms_kernel_function	Kernel for Support Vector Machines: <ul style="list-style-type: none"> ■ svms_linear (for Linear Kernel) ■ svms_gaussian (for Gaussian Kernel) Default value is svms_linear.
svms_kernel_cache_size	TO_CHAR(<i>numeric_expr</i> > 0) Value of kernel cache size for SVM algorithm. Applies to Gaussian kernel only. Default value is 50000000 bytes.
svms_conv_tolerance	TO_CHAR(<i>numeric_expr</i> > 0) Convergence tolerance for SVM algorithm. Default value is 0.001.
svms_std_dev	TO_CHAR(<i>numeric_expr</i> > 0) Value of standard deviation for SVM algorithm. This is applicable only for Gaussian kernel. Default value estimated from the data by the algorithm.
svms_complexity_factor	TO_CHAR(<i>numeric_expr</i> > 0) Value of complexity factor for SVM algorithm. Default value estimated from the data by the algorithm.
svms_epsilon	TO_CHAR(<i>numeric_expr</i> > 0) Value of epsilon factor for SVM Regression. Default value estimated from the data by the algorithm.

Table 23–16 Algorithm Settings for Non-Negative Matrix Factorization

Setting Name	Setting Value (with Permissible Value Ranges)
nmfs_random_seed	TO_CHAR(<i>numeric_expr</i>) Seed for random generator. Default value is -1.
nmfs_num_iterations	TO_CHAR(1 <= <i>numeric_expr</i> <= 500) Maximum number of iterations for NMF algorithm. Default value is 50.
nmfs_conv_tolerance	TO_CHAR(0 < <i>numeric_expr</i> <= 0.5) Convergence tolerance for NMF algorithm. Default value is 0.05.

Table 23–17 Algorithm Settings for k-Means

Setting Name	Setting Value (with Permissible Value Ranges)
kmns_distance	Distance Function for <i>k</i> -Means Clustering: <ul style="list-style-type: none"> ■ kmns_euclidean ■ kmns_cosine ■ kmns_fast_cosine Default value is kmns_euclidean.
kmns_iterations	TO_CHAR(0 < <i>numeric_expr</i> <= 20) Number of iterations for <i>k</i> -Means algorithm. Default value is 3.
kmns_conv_tolerance	TO_CHAR(0 < <i>numeric_expr</i> <= 0.5) Convergence tolerance for <i>k</i> -Means algorithm. Default value is 0.01.
kmns_split_criterion	Split criterion for <i>k</i> -Means Clustering: <ul style="list-style-type: none"> ■ kmns_variance ■ kmns_size Default value is kmns_variance.

Table 23–17 (Cont.) Algorithm Settings for *k*-Means

Setting Name	Setting Value (with Permissible Value Ranges)
<code>kmns_num_bins</code>	<p>Number of histogram bins. Specifies the number of bins in the attribute histogram produced by <i>k</i>-Means. The bin boundaries for each attribute are computed globally on the entire training data set. The binning method is equi-width. All attributes have the same number of bins with the exception of attributes with a single value that have only one bin.</p> <p>Range > 0.</p> <p>Default value is 10.</p>
<code>kmns_block_growth</code>	<p><code>TO_CHAR(1 < <i>numeric_expr</i> <= 5)</code></p> <p>Growth factor for memory allocated to hold cluster data.</p> <p>Default value is 2.</p>
<code>kmns_min_pct_attr_support</code>	<p>Minimum percentage support required for attributes in rules. Specifies the minimum percentage of values for an attribute in a given cluster required to include this attribute in the rule description of the cluster. That is, if the required support level is not met, the attribute would be omitted from the rule. This would allow retaining in the rule only the well-represented attributes. Setting the parameter value too high in data with missing values can result in very short or even empty rules.</p> <p>Range >= 0 and <= 1.</p> <p>Default is 0.1.</p>

You can create a settings table as shown in the example that follows for an SVM classification model, and edit the individual values using SQL DML.

```
CREATE TABLE drugstore_settings (
    setting_name VARCHAR2(30),
    setting_value VARCHAR2(128))

BEGIN
    -- override the default for convergence tolerance for SVM Classification
    INSERT INTO drugstore_model_settings (setting_name, setting_value)
    VALUES (dbms_data_mining.svms_conv_tolerance, TO_CHAR(0.081));
COMMIT;
END;
```

The table function `GET_DEFAULT_SETTINGS` provides you all the default settings for mining functions and algorithms. If you intend to override all the default settings, you can create a seed settings table and edit them using SQL DML.

```
BEGIN
CREATE TABLE drug_store_settings AS
SELECT setting_name, setting_value
      FROM TABLE (DBMS_DATA_MINING.GET_DEFAULT_SETTINGS
                  WHERE setting_name LIKE 'SVMS_%');
-- update the values using appropriate DML
END;
```

You can also create a settings table based on another model's settings using `GET_MODEL_SETTINGS`, as shown in the following example:

```
BEGIN
CREATE TABLE my_new_model_settings AS
SELECT setting_name, setting_value
      FROM TABLE (DBMS_DATA_MINING.GET_MODEL_SETTINGS('my_other_
model'));
END;
```

Prior Probabilities Table

Consult *Oracle Data Mining Concepts* for an explanation of the prior probabilities table. You can specify a prior probabilities table as an optional function setting when building classification models.

You must create the prior probabilities table using the fixed schema shown in the following code samples. For numerical targets, use the following schema:

```
target_value      NUMBER
prior_probability NUMBER
```

For categorical targets, use the following schema:

```
target_value      VARCHAR2
prior_probability NUMBER
```

Next, provide the name of the prior probabilities table as input to the *setting_value* column in the settings table, with the corresponding value for the *setting_name* column to be `DBMS_DATA_MINING.class_priors_table_name`, as shown:

```
BEGIN
INSERT INTO drugstore_settings (setting_name, setting_value)
VALUES (DBMS_DATA_MINING.class_priors_table_name, 'census_priors');
```

```
COMMIT;
END;
```

Cost Matrix Table

Consult *Oracle Data Mining Concepts* for an explanation of the cost matrix. You must create a cost matrix table with the fixed schema shown in the following code samples. For numerical targets, use the following schema:

```
actual_target_value    NUMBER
predicted_target_value NUMBER
cost                   NUMBER
```

For categorical targets, use the following schema:

```
actual_target_value    VARCHAR2
predicted_target_value VARCHAR2
cost                   NUMBER
```

The `DBMS_DATA_MINING` package enables you to evaluate the cost of predictions from classification models in an iterative manner during the experimental phase of mining, and to eventually apply the optimal cost matrix to predictions on the actual scoring data in a production environment.

The data input to each `COMPUTE` procedure in the package is the result generated from applying the model on test data. In addition, if you also provide a cost matrix as an input, the `COMPUTE` procedure generates test results taking the cost matrix into account. This enables you to experiment with various costs for a given prediction against the same `APPLY` results, without rebuilding the model and applying it against the same test data for every iteration.

Once you arrive at an optimal cost matrix, you can then input this cost matrix to the `RANK_APPLY` procedure along with the results of `APPLY` on your scoring data. `RANK_APPLY` will provide your new data ranked by cost.

Summary of DBMS_DATA_MINING Subprograms

Table 23–18 DBMS_DATA_MINING Package Subprograms

Data Type	Purpose
APPLY Procedure on page 23-21	Applies a model to scoring data
CREATE_MODEL Procedure on page 23-24	Creates (builds) a mining model
COMPUTE_CONFUSION_MATRIX Procedure on page 23-27	Computes the confusion matrix from the <code>APPLY</code> results on test data for a classification model; also provides the accuracy of the model
COMPUTE_LIFT Procedure on page 23-31	Computes lift for a given positive target value from the <code>APPLY</code> results on test data for a classification model
COMPUTE_ROC Procedure on page 23-35	Computes Receiver Operating Characteristic for target attributes with binary class from the <code>APPLY</code> results on test data for a classification model
DROP_MODEL Procedure on page 23-40	Drops a model
EXPORT_MODEL Procedure on page 23-41	Exports one or more models from a schema
GET_ASSOCIATION_RULES Function on page 23-45	This table function returns the rules from an Association model
GET_DEFAULT_SETTINGS Function on page 23-48	This table function returns all the default settings for all mining functions and algorithms
GET_FREQUENT_ITEMSETS Function on page 23-50	Returns a set of rows that represent the frequent itemsets from an Association model
GET_MODEL_DETAILS_ABN Function on page 23-52	Provides the details of an Adaptive Bayes Network model
GET_MODEL_DETAILS_KM Function on page 23-54	Provides the details of a <i>k</i> -Means model
GET_MODEL_DETAILS_NB Function on page 23-58	Provides the details of a Naive Bayes model
GET_MODEL_DETAILS_NMF Function on page 23-60	Provides the details of an NMF model

Table 23–18 (Cont.) DBMS_DATA_MINING Package Subprograms

Data Type	Purpose
GET_MODEL_DETAILS_SVM Function on page 23-62	Provides the details of a SVM model with a linear kernel
GET_MODEL_SETTINGS Function on page 23-64	Provides the settings used to build a model
GET_MODEL_SIGNATURE Function on page 23-66	Provides the signature of a model
IMPORT_MODEL Procedure on page 23-68	Imports one or more models into the current schema
RANK_APPLY Procedure on page 23-72	Ranks the predictions from the APPLY results for a classification model
RENAME_MODEL Procedure on page 23-75	Renames a model

APPLY Procedure

This procedure applies a mining model to the data to be scored, and generates the APPLY results in a table. This operation is applicable for predictive models (classification, regression) and also for descriptive models (clustering, feature extraction).

Syntax

```
DBMS_DATA_MINING.APPLY (
    model_name           IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    case_id_column_name IN VARCHAR2,
    result_table_name   IN VARCHAR2,
    data_schema_name    IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23–19 *APPLY Procedure Parameters*

Parameter	Description
model_name	Name of the model (see Rules and Limitations).
data_table_name	Name of table or view representing data to be scored.
case_id_column_name	Name of the case identifier column.
result_table_name	Name of the table to store apply results.
data_schema_name	Name of the schema containing the data to be scored.

Usage Notes

The data provided for APPLY should match the data provided to CREATE_MODEL in terms of the schema definition and relevant content. The GET_MODEL_SIGNATURE function provides this information. If the data provided as input to CREATE_MODEL has been pre-processed, then the data input to APPLY must also be pre-processed using the statistics from the CREATE_MODEL data pre-processing. The case identifier is not considered to be a mining attribute during APPLY.

You must provide the name of the table in which the results of the apply operation are to be stored. APPLY creates a table with an algorithm-specific fixed schema in the user schema that owns the model.

The behavior of an `APPLY` operation is analogous to a `SQL` query operation, even though it is packaged as a procedure. It does not update the model contents and does not have any contention with `CREATE_MODEL`, `DROP_MODEL`, or `RENAME_MODEL` operations. The corollary is that if you potentially drop or rename a model while a model is being applied to scoring data, the `APPLY` operation may discontinue with partial or unpredictable results.

The schema for the apply results from each of the supported algorithms is listed in subsequent sections. The `case_id` column will match the case identifier column name provided by you. The type of incoming `case-id` column is preserved in Apply output.

Classification Algorithms

The table containing the `APPLY` results for all classification models has the same schema. For numerical targets, the results table will have the schema as shown:

```
case_id      VARCHAR2/NUMBER
prediction   NUMBER
probability  NUMBER
```

For categorical targets, the results table will have the following schema:

```
case_id      VARCHAR2/NUMBER
prediction   VARCHAR2
probability  NUMBER
```

Regression using Support Vector Machines

The results table will have the following schema:

```
case_id      VARCHAR2/NUMBER
prediction   NUMBER
```

Clustering using *k*-Means

Clustering is an unsupervised mining function, and hence there are no targets. The results of an `APPLY` operation will contain simply the cluster identifier corresponding to a case, and the associated probability. The results table will have the schema as shown:

```
case_id      VARCHAR2/NUMBER
cluster_id   NUMBER
probability  NUMBER
```

Feature Extraction using NMF

Feature extraction is also an unsupervised mining function, and hence there are no targets. The results of an `APPLY` operation will contain simply the feature identifier

corresponding to a case, and the associated match quality. The results table will have the schema as shown:

```

case_id      VARCHAR2/NUMBER
feature_id   NUMBER
match_quality NUMBER

```

Examples

```

BEGIN
/* build a model with name census_model.
 * (See example under CREATE_MODEL)
 */

/* if build data was pre-processed in any manner,
 * perform the same pre-processing steps on the
 * scoring data also.
 * (See examples in the section on DBMS_DATA_MINING_TRANSFORM)
 */

/* apply the model to data to be scored */
dbms_data_mining.apply(
  model_name => 'census_model',
  data_table_name => 'census_2d_apply',
  case_id_column_name => 'person_id',
  result_table_name => 'census_apply_result');
END;
/

-- View Apply Results
SELECT case_id, prediction, probability
       FROM census_apply_result;

```

CREATE_MODEL Procedure

This procedure creates a mining model for a given mining function using a specified mining algorithm.

Syntax

```
DBMS_DATA_MINING.CREATE_MODEL (
    model_name           IN VARCHAR2,
    mining_function      IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    case_id_column_name IN VARCHAR2,
    target_column_name  IN VARCHAR2 DEFAULT NULL,
    settings_table_name IN VARCHAR2 DEFAULT NULL,
    data_schema_name    IN VARCHAR2 DEFAULT NULL,
    settings_schema_name IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23–20 CREATE_MODEL Procedure Parameters

Parameter	Description
model_name	Name of the model (see Rules and Limitations).
mining_function	Constant representing the mining function.
data_table_name	Name of the table or view containing the training data.
case_id_column_name	Name of the case identifier column.
target_column_name	Name of the target column — NULL for descriptive models.
settings_table_name	Name of the table or view containing algorithm settings.
data_schema_name	Name of the schema hosting the training data.
settings_schema_name	Name of the schema hosting the settings table/view.

Usage Notes

The data provided to all subsequent operations such as APPLY must match the data provided to CREATE_MODEL in schema and relevant content. If the data provided as input to CREATE_MODEL has been pre-processed, then the data input to subsequent operations such as APPLY must also be pre-processed using the statistics from the CREATE_MODEL data pre-processing. The case identifier column is not considered to be a mining attribute during CREATE_MODEL.

You can view the default settings for each algorithm through `GET_DEFAULT_SETTINGS`. You can override the defaults by providing a settings table specifying your choice of mining algorithm and relevant overriding algorithm settings.

Once a model has been built, information about the attributes used for model build can be obtained from `GET_MODEL_SIGNATURE`. To inspect or review model contents, you can use any of the algorithm-specific `GET_MODEL_DETAILS` functions.

The behavior of the `CREATE_MODEL` is analogous to a SQL DDL `CREATE` operation. It contends with `RENAME_MODEL` and `DROP_MODEL` operations.

Note: The `CREATE_MODEL` operation creates a set of system tables in the owner's schema to store the patterns and information that constitutes a mining model for a particular algorithm. The names of these tables have the prefix `DM$`. The number, schema, and content of these tables is Oracle proprietary and may change from release to release. You must not direct any queries or updates against these system tables.

Examples

Assume that you need to build a classification model using Support Vector Machines algorithm.

```

/* prepare a settings table to override default
 * settings (Naive Bayes is the default classifier)
 */
CREATE TABLE census_settings (
    setting_name VARCHAR2(30),
    setting_value VARCHAR2(128));

BEGIN
/* indicate that SVM is the chosen classifier */
INSERT INTO census_settings VALUES (
dbms_data_mining.algo_name, dbms_data_mining.algo_support_vector_machines);

/* override the default value for complexity factor */
INSERT INTO census_settings (setting_name, setting_value)
VALUES (dbms_data_mining.svms_complexity_factor, TO_CHAR(0.081));
COMMIT;

/* build a model with name census_model */
dbms_data_mining.create_model(
    model_name => 'census_model',
    mining_function => DBMS_DATA_MINING.CLASSIFICATION,
    data_table_name => 'census_2d_build',

```

CREATE_MODEL Procedure

```
    case_id_column_name => 'person_id',  
    target_column_name => 'class',  
    settings_table_name => 'census_settings');  
END;  
/
```

COMPUTE_CONFUSION_MATRIX Procedure

This procedure computes the confusion matrix for a classification model and also provides the accuracy of the model. See *Oracle Data Mining Concepts* for a description of confusion matrix.

The inputs are a table containing the results of applying the model on the test data, and a table that contains only the target and case identifier columns from the test data.

Syntax

```
DBMS_DATA_MINING.COMPUTE_CONFUSION_MATRIX (
    accuracy                OUT NUMBER,
    apply_result_table_name IN  VARCHAR2,
    target_table_name       IN  VARCHAR2,
    case_id_column_name     IN  VARCHAR2,
    target_column_name      IN  VARCHAR2,
    confusion_matrix_table_name IN VARCHAR2,
    score_column_name       IN  VARCHAR2 DEFAULT 'PREDICTION',
    score_criterion_column_name IN VARCHAR2 DEFAULT 'PROBABILITY',
    cost_matrix_table_name  IN  VARCHAR2 DEFAULT NULL,
    apply_result_schema_name IN  VARCHAR2 DEFAULT NULL,
    target_schema_name      IN  VARCHAR2 DEFAULT NULL,
    cost_matrix_schema_name IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23–21 COMPUTE_CONFUSION_MATRIX Procedure Parameters

Parameter	Description
accuracy	Accuracy of the model.
apply_result_table_name	Name of the table or view containing the results of an APPLY operation on the test dataset (see Usage Notes).
target_table_name	Name of the table or view containing only the case identifier column and target column values (see Usage Notes for required schema specification).
case_id_column_name	Name of the case identifier column in the test data set. This must be common across the targets table and the apply results table.
target_column_name	Name of the target column.

Table 23–21 (Cont.) COMPUTE_CONFUSION_MATRIX Procedure Parameters

Parameter	Description
confusion_matrix_table_name	Name of the table into which the confusion matrix is to be generated.
score_column_name	Name of the column representing the score from the apply results table. In the fixed schema table generated by <code>APPLY</code> , this column has the name <code>PREDICTION</code> , which is the default.
score_criterion_column_name	Name of the column representing the ranking factor for the score from the apply results table. In the fixed schema table generated by <code>APPLY</code> for classification models, this column has the name <code>PROBABILITY</code> , which is the default. Values in this column must be represented numerically.
cost_matrix_table_name	Name of the fixed-schema cost matrix table.
apply_result_schema_name	Name of the schema hosting the <code>APPLY</code> results table.
target_schema_name	Name of the schema hosting the targets table.
cost_matrix_schema_name	Name of the schema hosting the cost matrix table.

Usage Notes

You can also provide a cost matrix as an optional input in order to have the cost of predictions reflected in the results.

It is important to note that the data inputs to `COMPUTE_CONFUSION_MATRIX` do not always have to be generated using `APPLY`. As long as the schema of the two input tables matches the ones discussed in this section, with appropriate content, the procedure can provide the confusion matrix and accuracy as outputs. The quality of the results is dependent on the quality of the data.

The data provided for testing your classification model must match the data provided to `CREATE_MODEL` in schema and relevant content. If the data provided as input to `CREATE_MODEL` has been pre-processed, then the data input to `APPLY` must also be pre-processed using the statistics from the `CREATE_MODEL` data pre-processing.

Before you use the `COMPUTE_CONFUSION_MATRIX` procedure, you must prepare two data input streams from your test data.

First, you must **APPLY** the model on your test data. The parameter `apply_result_table_name` in the `COMPUTE_CONFUSION_MATRIX` procedure represents the table that will be generated in your schema as a result of the `APPLY` operation.

Next, you must create a table or view containing only the case identifier column and the target column in its schema. The parameter `target_table_name` reflects this input. The schema for this view or table name for a numerical target attribute is:

```
(case_identifier_column_name  VARCHAR2/NUMBER,
 target_column_name          NUMBER)
```

The schema for this view or table name for a categorical target attribute is:

```
(case_identifier_column_name  VARCHAR2/NUMBER,
 target_column_name          NUMBER)
```

You must provide the name of the table in which the confusion matrix is to be generated. The resulting fixed schema table will always be created in the schema owning the model.

For numerical target attributes, the confusion matrix table will have the schema:

```
(actual_target_value  NUMBER,
 predicted_target_value  NUMBER,
 value                NUMBER)
```

For categorical target attributes, the confusion matrix table will have the schema:

```
actual_target_value  VARCHAR2,
 predicted_target_value  VARCHAR2,
 value                NUMBER
```

Examples

Assume that you have built a classification model `census_model` using the Naive Bayes algorithm, and you have been provided the test data in a table called `census_2d_test`, with case identifier column name `person_id`, and the target column name `class`.

```
DECLARE
  v_sql_stmt VARCHAR2(4000);
  v_accuracy NUMBER;
BEGIN

  /* apply the model census_model on test data */
  dbms_data_mining.apply(
    model_name => 'census_model',
```

COMPUTE_CONFUSION_MATRIX Procedure

```
    data_table_name => 'census_2d_test',
    case_id_column_name => 'person_id',
    result_table_name => 'census_test_result');
CREATE VIEW census_2d_test_view as select person_id, class from census_2d_test;

/* now compute the confusion matrix from the two
 * data streams, also providing a cost matrix as input.
 */
dbms_data_mining.compute_confusion_matrix (
    accuracy => v_accuracy,
    apply_result_table_name => 'census_test_result',
    target_table_name => 'census_2d_test_view',
    case_id_column_name => 'person_id',
    target_column_name => 'class',
    confusion_matrix_table_name => 'census_confusion_matrix',
    cost_matrix_table_name => 'census_cost_matrix');
dbms_output.put_line('Accuracy of the model: ' || v_accuracy);
END;
/

-- View the confusion matrix using Oracle SQL
SELECT actual_target_value, predicted_target_value, value
FROM census_confusion_matrix;
```


COMPUTE_LIFT Procedure

This procedure computes a lift table for a given positive target for a classification model. See *Oracle Data Mining Concepts* for a description of lift.

The inputs are a table containing the results of applying the model on the test data, and a table that contains only the target and case identifier columns from the test data.

Syntax

```
DBMS_DATA_MINING.COMPUTE_LIFT (
    apply_result_table_name      IN VARCHAR2,
    target_table_name           IN VARCHAR2,
    case_id_column_name         IN VARCHAR2,
    target_column_name          IN VARCHAR2,
    lift_table_name             IN VARCHAR2,
    positive_target_value       IN VARCHAR2,
    score_column_name           IN VARCHAR2 DEFAULT 'PREDICTION',
    score_criterion_column_name IN VARCHAR2 DEFAULT 'PROBABILITY',
    num_quantiles               IN NUMBER DEFAULT 10,
    cost_matrix_table_name      IN VARCHAR2 DEFAULT NULL,
    apply_result_schema_name    IN VARCHAR2 DEFAULT NULL,
    target_schema_name          IN VARCHAR2 DEFAULT NULL,
    cost_matrix_schema_name     IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23–22 COMPUTE_LIFT Procedure Parameters

Parameter	Description
apply_result_table_name	Name of the table or view containing the results of an APPLY operation on the test dataset (see Usage Notes).
target_table_name	Name of the table or view containing only the case identifier column and target column values (see Usage Notes for required schema specification).
case_id_column_name	Name of the case identifier column in the test data set. This must be common across the targets table and the apply results table.
target_column_name	Name of the target column.

Table 23–22 (Cont.) COMPUTE_LIFT Procedure Parameters

Parameter	Description
<code>lift_table_name</code>	Name of the table into which the lift table is to be generated.
<code>positive_target_value</code>	Value of the positive target. If the target column is of NUMBER type, use <code>TO_CHAR()</code> operator to provide the value as a string.
<code>score_column_name</code>	Name of the column representing the score in the apply results table. In the fixed schema table generated by <code>APPLY</code> , this column has the name <code>PREDICTION</code> , which is the default.
<code>score_criterion_column_name</code>	Name of the column representing the ranking factor for the score in the apply results table. In the fixed schema table generated by <code>APPLY</code> for classification models, this column has the name <code>PROBABILITY</code> , which is the default. Values in this column must be represented numerically.
<code>num_quantiles</code>	Number of quantiles required in the lift table.
<code>cost_matrix_table_name</code>	Name of the cost matrix table.
<code>apply_result_schema_name</code>	Name of the schema hosting the <code>APPLY</code> results table.
<code>target_schema_name</code>	Name of the schema hosting the targets table.
<code>cost_matrix_schema_name</code>	Name of the schema hosting the cost matrix table.

Usage Notes

You can also provide a cost matrix as an optional input to have the cost of predictions reflected in the results.

It is important to note that the data inputs to `COMPUTE_LIFT` do not always have to be generated using `APPLY`. As long as the schema of the two input tables matches the ones discussed in this section, with appropriate content, the procedure can provide the lift table as output. The quality of the results depends on the quality of the data.

The data provided for testing your classification model must match the data provided to `CREATE_MODEL` in schema and relevant content. If the data provided as input to `CREATE_MODEL` has been pre-processed, then the data input to `APPLY` must also be pre-processed using the statistics from the `CREATE_MODEL` data pre-processing.

Before you use the `COMPUTE_LIFT` procedure, you must prepare two data input streams from your test data.

First, you must `APPLY` the model on your test data. The parameter `apply_result_table_name` in the `COMPUTE_LIFT` procedure represents the table that will be generated in your schema as a result of the `APPLY` operation.

Next, you must create a table or view containing only the case identifier column and the target column in its schema. The parameter `target_table_name` reflects this input. The schema for this view or table name for a numerical target attribute is:

```
(case_identifier_column_name  VARCHAR2/NUMBER,
 target_column_name           NUMBER)
```

The schema for this view or table name for a categorical target attribute is:

```
(case_identifier_column_name  VARCHAR2/NUMBER,
 target_column_name           NUMBER)
```

You must provide the name of the table in which the lift table is to be generated. The resulting fixed schema table is always created in the schema that owns the model.

The resulting lift table will have the following schema:

```
(quantile_number              NUMBER,
 quantile_total_count         NUMBER,
 quantile_target_count        NUMBER,
 percent_records_cumulative   NUMBER,
 lift_cumulative              NUMBER,
 target_density_cumulative    NUMBER,
 targets_cumulative           NUMBER,
 non_targets_cumulative       NUMBER,
 lift_quantile                 NUMBER,
 target_density                NUMBER)
```

The output columns are explained in *Oracle Data Mining Concepts*.

Examples

Assume that you have built a classification model `census_model` using the Naive Bayes algorithm, and you have been provided the test data in a table called `census_2d_test`, with case identifier column name `person_id`, and the target column name `class`.

```
DECLARE
  v_sql_stmt VARCHAR2(4000);
```

COMPUTE_LIFT Procedure

```
BEGIN

/* apply the model census_model on test data */
dbms_data_mining.apply(
    model_name => 'census_model',
    data_table_name => 'census_2d_test',
    case_id_column_name => 'person_id',
    result_table_name => 'census_test_result');

/* next create a view from test data that projects
 * only the case identifier and target column
 */

/* now compute lift with the default 10 quantiles
 * from the two data streams
 */
dbms_data_mining.compute_lift (
    apply_result_table_name => 'census_test_result',
    target_table_name => 'census_2d_test_view',
    case_id_column_name => 'person_id',
    target_column_name => 'class',
    lift_table_name => 'census_lift',
    positive_target_value => '1',
    cost_matrix_table_name => 'census_cost_matrix');
END;
/

-- View the lift table contents using SQL
SELECT *
    FROM census_lift;
```

COMPUTE_ROC Procedure

This procedure computes the receiver operating characteristic (ROC) for a binary classification model. See *Oracle Data Mining Concepts* for a description of receiver operating characteristic.

The inputs are a table containing the results of applying the model on the test data, and a table that contains only the target and case identifier columns from the test data.

Syntax

```
DBMS_DATA_MINING.COMPUTE_ROC (
    roc_area_under_curve          OUT NUMBER,
    apply_result_table_name      IN  VARCHAR2,
    target_table_name            IN  VARCHAR2,
    case_id_column_name         IN  VARCHAR2,
    target_column_name          IN  VARCHAR2,
    roc_table_name              IN  VARCHAR2,
    positive_target_value       IN  VARCHAR2,
    score_column_name           IN  VARCHAR2 DEFAULT 'PREDICTION',
    score_criterion_column_name IN  VARCHAR2 DEFAULT 'PROBABILITY',
    apply_result_schema_name    IN  VARCHAR2 DEFAULT NULL,
    target_schema_name          IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23-23 COMPUTE_ROC Procedure Parameters

Parameter	Description
roc_area_under_the_curve	A measure of model accuracy, specifically, the probability that the model will correctly rank a randomly chosen pair of rows of opposite classes.
apply_result_table_name	Name of the table or view containing the results of an APPLY operation on the test dataset (see Usage Notes).
target_table_name	Name of the table or view containing only the case identifier column and target column values (see Usage Notes for required schema specification).
case_id_column_name	Name of the case identifier column in the test data set.

Table 23–23 (Cont.) COMPUTE_ROC Procedure Parameters

Parameter	Description
<code>roc_table_name</code>	Name of the table into which ROC results are to be generated.
<code>score_column_name</code>	Name of the column representing the score in the apply results table. In the fixed schema table generated by <code>APPLY</code> , this column has the name <code>PREDICTION</code> , which is the default.
<code>score_criterion_column_name</code>	Name of the column representing the ranking factor for the score in the apply results table. In the fixed schema table generated by <code>APPLY</code> for classification models, this column has the name <code>PROBABILITY</code> , which is the default. Values in this column must be represented numerically.
<code>apply_result_schema_name</code>	Name of the schema hosting the <code>APPLY</code> results table.
<code>target_schema_name</code>	Name of the schema hosting the targets table.

Usage Notes

It is important to note that the data inputs to `COMPUTE_ROC` do not always have to be generated using `APPLY`. As long as the schema of the two input tables matches the ones discussed in this section, with appropriate content, the procedure can provide the ROC table as output. The quality of the results depends on the quality of the data.

The data provided for testing your classification model must match the data provided to `CREATE_MODEL` in schema and relevant content. If the data provided as input to `CREATE_MODEL` has been pre-processed, then the data input to `APPLY` must also be pre-processed using the statistics from the `CREATE_MODEL` data pre-processing.

Before you use the `COMPUTE_ROC` procedure, you must prepare two data input streams from your test data.

First, you must `APPLY` the model on your test data. The parameter `apply_result_table_name` in the `COMPUTE_ROC` procedure represents the table that will be generated in your schema as a result of the `APPLY` operation.

Next, you must create a table or view containing only the case identifier column and the target column in its schema. The parameter `target_table_name` reflects this input. The schema for this view or table name for a numerical target attribute is:

```
case_identifier_column_name VARCHAR2/NUMBER,
```

```
target_column_name          NUMBER
```

The schema for this view or table name for a categorical target attribute is:

```
case_identifier_column_name  VARCHAR2/NUMBER,
target_column_name          VARCHAR2
```

You must provide the name of the table in which the ROC table is to be generated. The resulting fixed schema table will always be created in the schema that owns the model. The resulting ROC table will have the following schema:

```
(probability                NUMBER,
 true_positives              NUMBER,
 false_negatives             NUMBER,
 false_positives             NUMBER,
 true_negatives              NUMBER,
 true_positive_fraction      NUMBER,
 false_positive_fraction     NUMBER)
```

The output columns are explained in [Table 23-24](#).

Table 23-24 COMPUTE_ROC Output

Output Column	Description
probability	Minimum predicted positive class probability resulting in a positive class prediction. Thus, different threshold values result in different hit rates and false_alarm_rates.
true_negatives	Negative cases in the test data with predicted probabilities below the probability_threshold (correctly predicted).
true_positives	Positive cases in the test data with predicted probabilities above the probability_threshold (correctly predicted).
false_negatives	Positive cases in the test data with predicted probabilities below the probability_threshold (incorrectly predicted).
false_positives	Negative cases in the test data with predicted probabilities above the probability_threshold (incorrectly predicted).
true_positive_fraction	$\text{true_positives} / (\text{true_positives} + \text{false_negatives})$
false_positive_fraction	$\text{false_positives} / (\text{false_positives} + \text{true_negatives})$

The typical use scenario is to examine the `true_positive_fraction` and `false_positive_fraction` to determine the most desirable `probability_threshold`. This threshold is then used to predict class values in subsequent apply operations. For example, to identify positively predicted cases in probability rank order from an apply result table, given a `probability_threshold`:

```
select case_id_column_name from apply_result_table_name where probability >
probability_threshold order by probability DESC;
```

There are two procedures one might use to identify the most desirable `probability_threshold`. One procedure applies when the relative cost of positive class versus negative class prediction errors are known to the user. The other applies when such costs are not well known to the user. In the first instance, one can apply the relative costs to the ROC table to compute the minimum cost `probability_threshold`. Suppose the relative cost ratio, Positive Class Error Cost / Negative Class Error Cost = 20. Then execute a query like:

```
WITH cost AS (
  SELECT probability_threshold, 20 * false_negatives + false_positives cost
  FROM ROC_table
  GROUP BY probability_threshold),
  minCost AS (
    SELECT min(cost) minCost
    FROM cost)
  SELECT max(probability_threshold)probability_threshold
  FROM cost, minCost
  WHERE cost = minCost;
```

If relative costs are not well known, the user simply scans the values in the table (in sorted order) and makes a determination about which of the displayed trade-offs (misclassified positives versus misclassified negatives) is most desirable:

```
select * from ROC_table order by probability_threshold
```

Examples

Assume that you have built a classification model `census_model` using the SVM algorithm, and you have been provided the test data in a table called `census_2d_test`, with case identifier column name `person_id`, and the target column name `class`.

```
DECLARE
  v_sql_stmt VARCHAR2(4000);
  v_accuracy NUMBER;
BEGIN
```



```

/* apply the model census_model on test data */
DBMS_DATA_MINING.apply(
  model_name => 'census_model',
  data_table_name => 'census_2d_test',
  case_id_column_name => 'person_id',
  result_table_name => 'census_test_result');

/* next create a view from test data that projects
 * only the case identifier and target column
 */
v_sql_stmt :=
'CREATE VIEW census_2d_test_view AS ' ||
'SELECT person_id, class FROM census_2d_test';
EXECUTE IMMEDIATE v_sql_stmt;

/* now compute the receiver operating characteristics from
 * the two data streams, also providing a cost matrix
 * as input.
 */
DBMS_DATA_MINING.compute_roc (
  accuracy => v_accuracy,
  apply_result_table_name => 'census_test_result',
  target_table_name => 'census_2d_test_view',
  case_id_column_name => 'person_id',
  target_column_name => 'class',
  roc_table_name => 'census_roc',
  cost_matrix_table_name => 'census_cost_matrix');
END;
/

-- View the ROC results using Oracle SQL
SELECT *
  FROM census_roc;

```

DROP_MODEL Procedure

This procedure drops an existing mining model from the user's schema.

Syntax

```
DBMS_DATA_MINING.DROP_MODEL (model_name IN VARCHAR2);
```

Parameters

Table 23–25 DROP_MODEL Procedure Parameters

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Usage Notes

You can use `DROP_MODEL` to drop an existing mining model.

The behavior of the `DROP_MODEL` is similar to a SQL DDL `DROP` operation. It blocks `RENAME_MODEL` and `CREATE_MODEL` operations. It does not block or block on `APPLY`, which is a SQL query-like operation that does not update any model data.

If an `APPLY` operation is using a model, and you attempt to drop the model during that time, the `DROP` will succeed and `APPLY` will return indeterminate results. This is in line with the conventional behavior in the RDBMS, where DDL operations do not block on Query operations.

Examples

Assume the existence of a model `census_model`. The following example shows how to drop this model.

```
BEGIN
  DBMS_DATA_MINING.drop_model(model_name => 'census_model');
END;
/
```

EXPORT_MODEL Procedure

This procedure exports specified data mining models into a dump file set.

Syntax

```
DBMS_DATA_MINING.EXPORT_MODEL (
    filename          IN VARCHAR2,
    directory         IN VARCHAR2,
    model_filter      IN VARCHAR2 DEFAULT NULL,
    filesize          IN VARCHAR2 DEFAULT NULL,
    operation         IN VARCHAR2 DEFAULT NULL,
    remote_link       IN VARCHAR2 DEFAULT NULL,
    jobname           IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23–26 EXPORT_MODEL Procedure Parameters

Parameter	Description
filename	Name of the dump file set must be unique in the directory. A dump file set may contain one or more files. The number of files in a file set is determined by the size of the exporting data and the specified file size (see <i>filesize</i>). If only one file is created, it is named <i>filename>01.dmp</i> . If multiple files are created, they are named sequentially as <i>filename01.dmp</i> , <i>filename02.dmp</i> , and so forth.
directory	Name of the directory object where the dump file set is to be located. The directory object must be created before export. You must have <code>WRITE</code> privileges on the directory object and the corresponding file system directory.
model_filter	Filter that specifies models to be exported. See Usage Notes for details.
filesize	Size of the dump file; may be specified in bytes, kilobytes (K), megabytes (M), or gigabytes (G). Defaults to 50 MB.
operation	Use one of the literals 'EXPORT' / 'ESTIMATE'; defaults to 'EXPORT';.
remote_link	A valid DB link or <code>NULL</code> . When a DB link is provided, exporting DM models from a remote database is allowed. Defaults to <code>NULL</code> for local operations, namely, exporting models in the current database.

Table 23–26 (Cont.) EXPORT_MODEL Procedure Parameters

Parameter	Description
jobname	Name of the export job, limited to 30 characters. Must be unique to that schema, that is, there is no active job using the same name. If not supplied, a default name is provided in the form of <code>username_exp_datapump_job_id<dm_seq></code> , for example, <code>SCOTT_exp_13410</code> . A log file is created in the dump file with name <code>jobname.log</code> .

Usage Notes

Use `EXPORT_MODEL` to export all or specific data mining models from the source. This procedure creates a dump file set that includes one or more files. The location of the dump files is specified by parameter `directory`, which is the name of a directory object created before this procedure is called. The user must have `WRITE` privileges on this directory object. The dump file name must be unique. When the export operation completes successfully, the dump file name is automatically expanded to `filename01.dmp` even if there is only one file in the dump set.

A log file is created for every successful export operation in the directory mapped by `directory`. If `jobname` is specified, the log is named `jobname.log`. If `jobname` is set to `NULL` (the default), the log is named as `USERNAME_exp_nnnn.log`, where `nnnn` is a number. If `jobname` is provided, it must be unique. Parameter `model_filter` is used to specify models to be exported; its use is indicated in the following table:

Table 23–27 Table MODEL_FILTER for Export

Value	Meaning	Notes
<code>NULL</code>	Default. Export all models from the user schema.	<code>none</code>
<code>ALL</code>	Export all models from the user schema.	Same as <code>NULL</code> ; useful to improve code readability.
A valid <code>WHERE</code> clause, such as:	Specify which models are to be exported.	Any string that can be appended to <code>'select name from dm_user_models where'</code> and make it a valid SQL query.

Table 23–27 (Cont.) Table MODEL_FILTER for Export

Value	Meaning	Notes
'name= "super_model"'	Export the named model.	none
'name IN ("model1", "model2", "model3")'	Export 3 named models.	none
'ALGORITHM_NAME= "NAIVE_BAYES"'	Export all NB models.	none
'FUNCTION_NAME= "CLASSIFICATION"'	Export all classification models.	none
'name LIKE "NB_MODEL%"ESCAPE"\''	Export all models whose names start with "NB_MODEL".	none

EXPORT_MODEL is not mutually exclusive with the DDL-like operations such as CREATE_MODEL, DROP_MODEL, and RENAME_MODEL. In other words, if an export operation is currently underway and the model is dropped at that time, then the results in the exported dump file are unpredictable.

Examples

The following example shows exporting one model from the current user schema into a dump file. The dump file will be located in operating system directory /home/models, which is mapped to a directory object DM_DUMP. The directory object DM_DUMP must be created before executing the sample, and the user must be granted WRITE privileges on it.

```

DECLARE
  job_name          VARCHAR2(32) := 'model_exp_001';
  filename          VARCHAR2(32);
BEGIN
  filename := job_name;
  DBMS_DATA_MINING.export_model(
    filename => filename,
    directory => 'DM_DUMP',
    metadata_filter => 'name=' 'NB_MODEL_01' ''',
    remote_link => NULL,
    filesize => '30M',
    operation => 'EXPORT',
    job_name => job_name);
  dbms_output.put_line(
    'Export_model ' || job_name || ' completed sucessfully!');

```

EXPORT_MODEL Procedure

```
END;  
/
```

GET_ASSOCIATION_RULES Function

This table function returns the rules from an Association model. The rows are an enumeration of the rules generated during the creation of the model.

Syntax

```
DBMS_DATA_MINING.GET_ASSOCIATION_RULES (
    model_name          IN VARCHAR2)
RETURN DM_Rules pipelined;
```

Parameters

Table 23–28 *GET_ASSOCIATION_RULES Function Parameters*

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–29 *GET_ASSOCIATION_RULES Function Return Values*

Return Value	Description
DM_Rules	Represents a set of rows with schema: (rule_id INTEGER, antecedent DM_Predicates, consequent DM_Predicates, rule_support NUMBER, rule_confidence NUMBER)
DM_Predicates	Is a nested table with schema: (attribute_name VARCHAR2(30), conditional_operatoar CHAR(2), attribute_num_value NUMBER, attribute_str_value VARCHAR2(4000), attribute_support NUMBER, attribute_confidence NUMBER)

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

The table function *pipes* out rows with the schema:

rule_id	INTEGER,
antecedent	DM_Predicates,
consequent	DM_Predicates,
rule_support	NUMBER,
rule_confidence	NUMBER

`DM_Predicates` is a collection of `DM_Predicate` objects. When un-nested, each object maps to a row of the form:

attribute_name	INTEGER,
conditional_operator	CHAR(2),
attribute_num_value	NUMBER,
attribute_str_value	VARCHAR2,
attribute_support	NUMBER,
attribute_confidence	NUMBER

The significance of piped output is that each row is materialized by the table function as soon as it is read from model storage, without any latency or wait for the generation of the complete `DM_Rules` object. All `GET` operations use pipelining. For more information on pipelined, parallel table functions, consult the *PL/SQL User's Guide and Reference*.

The examples shown in this section describe how to un-nest the values from each of the columns discussed earlier.

Examples

The following example demonstrates an Association model build followed by an invocation of `GET_ASSOCIATION_RULES` table function from Oracle SQL.

```
-- prepare a settings table to override default settings
CREATE TABLE market_settings AS
SELECT *
  FROM TABLE(DBMS_DATA_MINING.GET_DEFAULT_SETTINGS)
 WHERE setting_name LIKE 'ASSO_%';
BEGIN
-- update the value of the minimum confidence
UPDATE census_settings
```



```
        SET setting_value = TO_CHAR(0.081)
        WHERE setting_name = DBMS_DATA_MINING.asso_min_confidence;

/* build an AR model */
DBMS_DATA_MINING.CREATE_MODEL(
    model_name => 'market_model',
    function => DBMS_DATA_MINING.ASSOCIATION,
    data_table_name => 'market_build',
    case_id_column_name => 'item_id',
    target_column_name => NULL,
    settings_table_name => 'census_settings');
END;
/

-- View the (unformatted) rules from SQL/Plus
SELECT rule_id, antecedent, consequent, rule_support,
       rule_confidence
   FROM GET_ASSOCIATION_RULES('market_model');

-- see ardemo.sql for retrieving formatted rules
/
```

GET_DEFAULT_SETTINGS Function

This table function returns all the default settings for all mining functions and algorithms supported in the DBMS_DATA_MINING package.

Syntax

```
DBMS_DATA_MINING.GET_DEFAULT_SETTINGS;
```

Return Values

Table 23–30 GET_ASSOCIATION_RULES Function Return Values

Return Value	Description
DM_Model_Settings	Represents a set of rows with schema: <pre>(setting_name VARCHAR2(30), setting_value VARCHAR2(128))</pre>

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

The table function pipes out rows with the schema:

```
(setting_name VARCHAR2(30),
 setting_value VARCHAR2(128))
```

This function is particularly useful if you do not know what settings are associated with a particular function or algorithm, and you want to override some or all of them.

Examples

For example, if you want to override some or all of *k*-Means clustering settings, you can create a settings table as shown, and update individual settings as required.

```
BEGIN
  CREATE TABLE mysettings AS
  SELECT *
  FROM TABLE(DBMS_DATA_MINING.GET_DEFAULT_SETTINGS)
```

```
WHERE setting_name LIKE 'KMNS%';  
-- now update individual settings as required  
UPDATE mysettings  
    SET setting_value = 0.02  
    WHERE setting_name = dbms_data_mining.kmns_min_pct_attr_support;  
END;  
/
```

GET_FREQUENT_ITEMSETS Function

This table function returns a set of rows that represent the frequent itemsets from an Association model. The rows are an enumeration of the frequent itemsets generated during the creation of the model. For a detailed description of frequent itemsets, consult *Oracle Data Mining Concepts*.

Syntax

```
DBMS_DATA_MINING.GET_FREQUENT_ITEMSETS (
    model_name          IN VARCHAR2)
RETURN DM_ItemSets pipelined;
```

Parameters

Table 23–31 GET_MODEL_DETAILS_ABN Function Parameters

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–32 GET_FREQUENT_ITEMSETS Function Return Values

Return Value	Description								
DM_ItemSets	Represents a set of rows with schema: <table border="0" style="margin-left: 20px;"> <tr> <td>(itemsets_id</td> <td>NUMBER,</td> </tr> <tr> <td>items</td> <td>DM_items,</td> </tr> <tr> <td>support</td> <td>NUMBER,</td> </tr> <tr> <td>number_of_items</td> <td>NUMBER)</td> </tr> </table>	(itemsets_id	NUMBER,	items	DM_items,	support	NUMBER,	number_of_items	NUMBER)
(itemsets_id	NUMBER,								
items	DM_items,								
support	NUMBER,								
number_of_items	NUMBER)								

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

The table function *pipes* out rows with the schema:

```
(itemsets_id    NUMBER,
 items         DM_items,
```

```

support          NUMBER,
number_of_items  NUMBER)

```

DM_Items is a nested table of VARCHAR2 strings representing individual item names.

The examples shown in this section describe how to un-nest the values from each of the columns discussed in the preceding sections.

Examples

The following example demonstrates an Association model build followed by an invocation of GET_FREQUENT_ITEMSETS table function from Oracle SQL.

```

-- prepare a settings table to override default settings
CREATE TABLE market_settings AS
SELECT *
  FROM TABLE(DBMS_DATA_MINING.GET_DEFAULT_SETTINGS)
 WHERE setting_name LIKE 'ASSO_%';
BEGIN
-- update the value of the minimum confidence
UPDATE census_settings
   SET setting_value = TO_CHAR(0.081)
 WHERE setting_name = DBMS_DATA_MINING.asso_min_confidence;

/* build a AR model */
DBMS_DATA_MINING.CREATE_MODEL(
  model_name => 'market_model',
  function => DBMS_DATA_MINING.ASSOCIATION,
  data_table_name => 'market_build',
  case_id_column_name => 'item_id',
  target_column_name => NULL,
  settings_table_name => 'census_settings');
END;
/

-- View the (unformatted) Itemsets from SQL/Plus
SELECT itemset_id, items, support, number_of_items
  FROM TABLE(DBMS_DATA_MINING.GET_FREQUENT_ITEMSETS('market_model'));

```

GET_MODEL_DETAILS_ABN Function

This table function returns a set of rows that provide the details of an Adaptive Bayes Network model.

Syntax

```
DBMS_DATA_MINING.GET_MODEL_DETAILS_ABN (
    model_name          IN VARCHAR2)
RETURN DM_ABN_Details
```

Parameters

Table 23–33 *GET_MODEL_DETAILS_ABN Function Parameters*

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–34 *GET_MODEL_DETAILS_ABN Function Return Values*

Return Value	Description										
DM_ABN_Details	Represents a set of rows with schema: <table border="0" style="margin-left: 20px;"> <tr> <td>attribute_name</td> <td>VARCHAR2(30),</td> </tr> <tr> <td>attribute_num_value</td> <td>NUMBER</td> </tr> <tr> <td>attribute_str_val</td> <td>VARCHAR2(4000),</td> </tr> <tr> <td>probability</td> <td>NUMBER,</td> </tr> <tr> <td>conditionals</td> <td>DM_Conditionals)</td> </tr> </table>	attribute_name	VARCHAR2(30),	attribute_num_value	NUMBER	attribute_str_val	VARCHAR2(4000),	probability	NUMBER,	conditionals	DM_Conditionals)
attribute_name	VARCHAR2(30),										
attribute_num_value	NUMBER										
attribute_str_val	VARCHAR2(4000),										
probability	NUMBER,										
conditionals	DM_Conditionals)										
DM_Conditionals	Represents a set of rows DM_Conditional with schema: <table border="0" style="margin-left: 20px;"> <tr> <td>attribute_name</td> <td>VARCHAR2(30),</td> </tr> <tr> <td>attribute_num_value</td> <td>NUMBER,</td> </tr> <tr> <td>attribute_str_value</td> <td>VARCHAR2(4000),</td> </tr> <tr> <td>conditional_probability</td> <td>NUMBER)</td> </tr> </table>	attribute_name	VARCHAR2(30),	attribute_num_value	NUMBER,	attribute_str_value	VARCHAR2(4000),	conditional_probability	NUMBER)		
attribute_name	VARCHAR2(30),										
attribute_num_value	NUMBER,										
attribute_str_value	VARCHAR2(4000),										
conditional_probability	NUMBER)										

Pragmas

RNDS, WNDS, RNPS, WNPS.

Usage Notes

The table function *pipes* out rows with the schema:

The examples shown in this section describe how to un-nest the values from each of the columns discussed earlier.

This function returns details only for 'single feature' ABN model.

Examples

The following example demonstrates an ABN model build followed by an invocation of GET_MODEL_DETAILS_ABN table function from Oracle SQL.

```
BEGIN
  -- prepare a settings table to override default algorithm
  CREATE TABLE abn_settings (setting_name VARCHAR2(30),
    setting_value
  VARCHAR2(128));
  INSERT INTO abn_settings VALUES (dbms_data_mining.algo_name,
    dbms_data_mining.algo_adaptive_bayes_network);

  -- create a model
  DBMS_DATA_MINING.CREATE_MODEL (
    model_name => 'abn_model',
    function => DBMS_DATA_MINING.CLASSIFICATION,
    data_table_name => 'abn_build',
    case_id_column_name => 'id',
    target_column_name => NULL,
    settings_table_name => 'abn_settings');
END;
/
-- View the (unformatted) results from SQL/Plus
SELECT *
  FROM TABLE(DBMS_DATA_MINING.GET_MODEL_DETAILS_ABN('abn_model'));
```

GET_MODEL_DETAILS_KM Function

This table function returns a set of rows that provide the details of a *k*-Means clustering model. The rows are an enumeration of the clustering patterns generated during the creation of the model.

Syntax

```
DBMS_DATA_MINING.GET_MODEL_DETAILS_KM (
    model_name          IN VARCHAR2)
RETURN DM_Clusters pipelined;
```

Parameters

Table 23–35 *GET_MODEL_DETAILS_KM Function Parameters*

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–36 *GET_MODEL_DETAILS_KM Function Return Values*

Return Value	Description
DM_Clusters	Represents a set of rows of DM_Cluster with schema: (id INTEGER, record_count NUMBER, parent NUMBER, tree_level NUMBER, dispersion NUMBER, child DM_Children) centroid DM_Centroids, histogram DM_Histogram, rule DM_Rule)
DM_Children	Is a nested table of DM_Child with schema: (id NUMBER)

Table 23–36 (Cont.) GET_MODEL_DETAILS_KM Function Return Values

Return Value	Description
DM_Centroids	Is a nested table of DM_Centroid with schema: <pre>(attribute_name VARCHAR2(30) mean NUMBER, mode_value VARCHAR2(30), variance NUMBER);</pre>
DM_Histograms	Is a nested table of DM_Histogram_bin with schema: <pre>(attribute_name VARCHAR2(30), bin_id NUMBER, lower_bound NUMBER, upper_bound NUMBER, label VARCHAR2(4000), count NUMBER)</pre>
DM_Rule	Is an object with schema: <pre>(rule_id INTEGER, antecedent DM_Predicates, consequent DM_Predicates, rule_support NUMBER, rule_confidence NUMBER)</pre>
DM_Predicates	Is a nested table of DM_Predicate with schema: <pre>(attribute_name VARCHAR2(30), conditional_operator CHAR(2), attribute_num_value NUMBER, attribute_str_value VARCHAR2(4000), attribute_support NUMBER, attribute_confidence NUMBER)</pre>

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

The table function *pipes* out rows with the schema:

```
(id           INTEGER,
 record_count NUMBER,
 parent       NUMBER,
 tree_level   NUMBER,
 dispersion   NUMBER,
```

GET_MODEL_DETAILS_KM Function

```
child          DM_Children,  
centroid      DM_Centroids,  
histogram     DM_Histograms,  
rule          DM_Rule)
```

Each `DM_Children` value is a nested table of id's.

Each `DM_Centroid` value is itself as nested table that, when un-nested, can return rows of the form:

```
(attribute_name  VARCHAR2(30)  
mean            NUMBER,  
mode_value     VARCHAR2(30),  
variance       NUMBER);
```

Each `DM_Histogram` value is itself a nested table that, when un-nested, can return rows of the form:

```
(attribute_name  VARCHAR2(30),  
bin_id          NUMBER,  
lower_bound     NUMBER,  
upper_bound     NUMBER,  
label           VARCHAR2(4000),  
count           NUMBER)
```

Each `DM_Rule` value is an object with two nested `DM_Predicate` columns:

```
(rule_id        INTEGER,  
antecedent     DM_Predicates,  
consequent     DM_Predicates,  
rule_support   NUMBER,  
rule_confidence NUMBER)
```

`DM_Predicates` is a collection of `DM_Predicate` objects. When un-nested, each object maps to a row of the form:

```
(attribute_name  VARCHAR2(30),  
conditional_operator CHAR(2) ,  
attribute_num_value NUMBER,  
attribute_str_value VARCHAR2(4000),  
attribute_support NUMBER,  
attribute_confidence NUMBER)
```

The examples shown in this section describe how to un-nest the values from each of the columns discussed earlier.

Examples

The following example demonstrates a *k*-Means clustering model build followed by an invocation of GET_MODEL_DETAILS_KM table function from Oracle SQL.

```
BEGIN
-- create a settings table
UPDATE cluster_settings
   SET setting_value = 3
   WHERE setting_name = DBMS_DATA_MINING.kmeans_block_growth;

/* build a k-Means clustering model */
DBMS_DATA_MINING.CREATE_MODEL(
  model_name => 'eight_clouds',
  function => DBMS_DATA_MINING.CLUSTERING,
  data_table_name => 'eight_clouds_build',
  case_id_column_name => 'id',
  target_column_name => NULL,
  settings_table_name => 'cluster_settings');
END;
/

-- View the (unformatted) rules from SQL/Plus
SELECT id, record_count, parent, tree_level, dispersion,
       child, centroid, histogram, rule
   FROM TABLE(DBMS_DATA_MINING.GET_MODEL_DETAILS_KM('eight_clouds'));
```

GET_MODEL_DETAILS_NB Function

This table function returns a set of rows that provide the details of a Naive Bayes model. The rows are an enumeration of the patterns generated during the creation of the model.

Syntax

```
DBMS_DATA_MINING.GET_MODEL_DETAILS_NB (
    model_name      IN      VARCHAR2)
RETURN DM_NB_Details pipelined;
```

Parameters

Table 23–37 GET_MODEL_DETAILS_NB Function Parameters

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–38 GET_MODEL_DETAILS_NB Function Return Values

Return Value	Description
DM_NB_Details	Represents a set of rows DM_NB_Detail with schema: (target_attr_name VARCHAR2(30), target_attr_num_value NUMBER, target_attr_str_value VARCHAR2(4000), prior_probability NUMBER, conditionals
DM_Conditionals	Represents a set of rows DM_Conditional with schema: (attribute_name VARCHAR2(30), attribute_num_value NUMBER, attribute_str_value VARCHAR2(4000), conditional_probability NUMBER)

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

The table function *pipes* out rows with the schema:

```
(target_attr_name      VARCHAR2(30),
target_attr_num_value  NUMBER,
target_attr_str_value  VARCHAR2(4000),
prior_probability      NUMBER,
conditionals           DM_Conditionals)
```

Each `DM_Conditionals` value is itself as nested table that, when un-nested, can return rows of type `DM_Conditional`, of the form:

```
(attribute_name        VARCHAR2(30),
attribute_num_value    NUMBER,
attribute_str_value    VARCHAR2(4000),
conditional_probability NUMBER)
```

The examples shown in this section describe how to un-nest the values from each of the columns discussed earlier.

Examples

Assume that you have built a classification model `census_model` using the Naive Bayes algorithm. You can retrieve the model details as shown in this example.

```
-- You can view the Naive Bayes model details in many ways
-- Consult the Oracle Application Developer's Guide -
-- Object-Relational Features for different ways of
-- accessing Oracle Objects.

-- View the (unformatted) details from SQL/Plus
SELECT attribute_name, attribute_num_value, attribute_str_value,
       prior_probability, conditionals,
FROM TABLE(DBMS_DATA_MINING.GET_MODEL_DETAILS_NB('census_model'));
```

See `nbdemo.sql` for generation of formatted rules.

GET_MODEL_DETAILS_NMF Function

This table function returns a set of rows that provide the details of a Non-Negative Matrix Factorization model.

Syntax

```
DBMS_DATA_MINING.GET_MODEL_DETAILS_NMF (
    model_name          IN          VARCHAR2)
RETURN DM_NMF_Details pipelined;
```

Parameters

Table 23–39 GET_MODEL_DETAILS_NMF Function Parameters

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–40 GET_MODEL_DETAILS_NMF Function Return Values

Return Value	Description
DM_NMF_Feature_set	Represents a set of rows of DM_NMF_Feature with schema: (feature_id INTEGER, attribute_set DM_NMF_Attribute_Set)
DM_NMF_Attribute_Set	Is a nested table of DM_NMF_Attribute with schema: (attribute_name VARCHAR2, attribute_value VARCHAR2(4000), coefficient NUMBER)

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

The table function *pipes* out rows with the schema:

```
(feature_id      INTEGER,
 attribute_set   DM_NMF_Attribute_Set)
```

Each DM_NMF_Feature_Set value is itself as nested table that, when un-nested, can return rows of the form:

```
(attribute_name) VARCHAR2,
 attribute_value  VARCHAR2(4000),
 coefficient      NUMBER)
```

The examples shown in this section describe how to un-nest the values from each of the columns discussed earlier.

Examples

Assume you have built an NMF model called `my_nmf_model`. You can retrieve model details as shown:

```
--View (unformatted) details from SQL/Plus
SELECT feature_id, attribute_set
FROM TABLE(DBMS_DATA_MINING.GET_MODEL_DETAILS_NMF(
           'my_nmf_model'));
```

GET_MODEL_DETAILS_SVM Function

This table function returns a set of rows that provide the details of a Support Vector Machines model. This is applicable only for classification or regression models built using a linear kernel. For any other kernel, the table function returns ORA-40215.

Syntax

```
DBMS_DATA_MINING.GET_MODEL_DETAILS_SVM (
  model_name      IN      VARCHAR2)
RETURN DM_SVM_Linear_Coeff pipelined;
```

Parameters

Table 23–41 GET_MODEL_DETAILS_SVM Function Parameters

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–42 GET_MODEL_DETAILS_SVM Function Return Values

Return Value	Description
DM_SVM_Linear_Coeff_Set	Represents a set of rows of DM_SVM_Linear_Coeff with schema: <div style="margin-left: 40px;">(class VARCHAR2(4000), attribute_set DM_SVM_Attribute_Set)</div>
DM_SVM_Attribute_Set	Is a nested table of DM_SVM_Attribute with schema: <div style="margin-left: 40px;">(attribute_name VARCHAR2(30), attribute_value VARCHAR2(4000), coefficient NUMBER)</div>

Usage Notes

The table function *pipes* out rows with the schema:

```
(class                    VARCHAR2(4000),
attribute_set            DM_SVM_Attribute_Set)
```


`class` represents classification target values. For regression targets, `class` is `NULL`. For each classification target value for classification models or once only for regression models, the `DM_SVM_Attribute_Set` value is itself a nested table that, when un-nested, can return rows of the form:

```
(attribute_name  VARCHAR2(30),
 attribute_value VARCHAR2(4000),
 coefficient     NUMBER)
```

The examples shown in this section describe how to un-nest the values from each of the columns discussed earlier.

Examples

The following example demonstrates an SVM model build followed by an invocation of `GET_MODEL_DETAILS_SVM` table function from Oracle SQL:

```
-- Create SVM model
BEGIN
  dbms_data_mining.create_model(
    model_name => 'SVM_Clas_sample',
    mining_function => dbms_data_mining.classification,
    data_table_name => 'svmc_sample_build_prepared',
    case_id_column_name => 'id',
    target_column_name => 'affinity_card',
    settings_table_name => 'svmc_sample_settings');
END;
/
-- Display model details
SELECT *
  FROM TABLE(dbms_data_mining.get_model_details_svm('SVM_Clas_sample'))
 ORDER BY class;
```

GET_MODEL_SETTINGS Function

This table function returns the list of settings that were used to build the model.

Syntax

```
DBMS_DATA_MINING.GET_MODEL_SETTINGS(
    model_name          IN VARCHAR2)
RETURN DM_Model_Settings pipelined;
```

Parameters

Table 23–43 *GET_MODEL_SETTINGS Function Parameters*

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–44 *GET_MODEL_SETTINGS Function Return Values*

Return Value	Description
DM_Model_Settings	Represents a set of rows with schema: <pre>(setting_name VARCHAR2(30), setting_value VARCHAR2(128))</pre>

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

You can use this table function to determine the settings that were used to build the model. This is purely for informational purposes only — you cannot alter the model to adopt new settings.

Examples

Assume that you have built a classification model `census_model` using the Naive Bayes algorithm. You can retrieve the model settings using Oracle SQL as follows:

```
SELECT setting_name, setting_value
FROM TABLE(DBMS_DATA_MINING.GET_MODEL_SETTINGS('census_model'));
```

GET_MODEL_SIGNATURE Function

This table function returns the model signature, which is a set of rows that provide the name and type of each attribute required as input to the APPLY operation.

The case identifier is not considered a mining attribute. For classification and regression models, the target attribute is also not considered part of the model signature.

Syntax

```
DBMS_DATA_MINING.GET_MODEL_SIGNATURE(
    model_name          IN VARCHAR2)
RETURN DM_Model_Signature pipelined;
```

Parameters

Table 23–45 GET_MODEL_SIGNATURE Function Parameters

Parameter	Description
model_name	Name of the model (see Rules and Limitations).

Return Values

Table 23–46 GET_MODEL_SIGNATURE Function Return Values

Return Value	Description
DM_Model_Signature	Represents a set of rows with schema: <div style="margin-left: 40px;"> (attribute_name VARCHAR2(30), attribute_type VARCHAR2(106)) </div>

Pragmas

RNDS, WNDS, RNPS, WNPS

Usage Notes

You can use this table function to get the list of attributes used for building the model. This is particularly helpful to describe a model when an APPLY operation on test or scoring data is done a significant time period after the model is built, or after it is imported into another schema.

Examples

Assume that you have built a classification model `census_model` using the Naive Bayes algorithm. You can retrieve the model details using Oracle SQL as follows:

```
SELECT attribute_name, attribute_type
FROM TABLE(DBMS_DATA_MINING.GET_MODEL_SIGNATURE('census_model'));
```

IMPORT_MODEL Procedure

This procedure imports specified data mining models from a dump file set or from a remote database.

Syntax

```
DBMS_DATA_MINING.IMPORT_MODEL (
  filename           IN  VARCHAR2,
  directory          IN  VARCHAR2,
  model_names       IN  VARCHAR2 DEFAULT NULL,
  operation         IN  VARCHAR2 DEFAULT NULL,
  remote_link       IN  VARCHAR2 DEFAULT NULL,
  jobname           IN  VARCHAR2 DEFAULT NULL,
  schema_remap     IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23–47 *IMPORT_MODEL Procedure Parameters*

Parameter	Description
filename	Name of the dump file set. If there are multiple files in the set, you may use "%U" to specify the file set. See Usage Notes for details.
directory	Name of the directory object where the dump file is located. The directory object must be created before the import operation and you must be granted both READ and WRITE privileges.
model_names	Specify the names of models to be imported. See Usage Notes for details.
operation	Use one of the literals 'IMPORT' / 'SQL_FILE'; defaults to 'IMPORT'. When set to 'SQL_FILE', DDLs that create those database objects in the dump file set are generated in a text file in the dump directory. The DDL file is named <i>job_name.sql</i> .
remote_link	A valid DB link or NULL. When a DB link is provided, this allows moving DM models from the remote database to the local database. Default value is NULL for importing into the current database from a dump file set.

Table 23–47 (Cont.) IMPORT_MODEL Procedure Parameters

Parameter	Description
job_name	Name of the import job, limited to 30 characters. It must be unique to that schema, that is, there is no active import job using the same name. If not supplied, a default name is provided in the form of <code>username_imp_nnnn</code> . For example, "SCOTT_imp_76102".
schema_remap	Specify schema remapping. Must be specified when importing from a dump file set created by a different user. It must be specified in the form of 'FROM_NAME:TO_NAME'. For example, to remap schema from SCOTT to MARY, set <code>schema_remap=>'SCOTT:MARY'</code> . You need <code>IMP_FULL_DATABASE</code> privileges to do schema remapping if you do not have a SYS role.

Usage Notes

Use `IMPORT_MODEL` to import all or specific data mining models from a dump or from a remote database by means of a DB link.

The dump file set must be created by `expdp` or `EXPORT_MODEL` procedure. The dump files must be located in the directory mapped by the `directory` object. The user must have `READ` and `WRITE` privileges on the directory object. In order to import models from a dump created by another user, you must have `IMP_FULL_DATABASE` privilege or have SYS role.

When import operation completes successfully, a log is created in the directory mapped by `directory` object. If `jobname` is provided, the log is named `jobname.log`. If `jobname` is `NULL` (the default) the log is named `username_imp_nnnn.log`, where `nnnn` is a number. If the dump file set contains multiple files, you can use "%U" in the filename. For example, if your dump file set contains 3 files, `archive01.dmp`, `archive02.dmp`, and `archive03.dmp`, you may specify `filename=>'archive%U'`.

Use the parameter `model_names` to specify which models to import. The use of `model_names` is dependent on the operation, whether the source is a dump file set or a remote database. When importing from dump files, `model_names` are the sole useful reference. In this case, you can either assign `model_names` with comma-delimited model names or a `WHERE` clause with names explicitly specified. When importing from a remote database, `model_names` can be specified in the same fashion as in the `EXPORT_MODEL` procedure. Details are listed in [Table 23–48](#).

Table 23–48 Table MODEL_FILTER for Import

Value	Source*	Meaning	Notes
NULL	dump/remote	Default. Import all models from the user schema.	---
'ALL'	dump/remote	Import all models from the user schema.	Same as NULL; useful to improve code readability.
Comma-separated model names	dump/remote	Import named models.	Examples: 'mymodel' or 'model1, model2, model3
A valid WHERE clause, such as:	----	Specify which models are to be imported.	Any string that can be appended to 'select name from dm_user_models where' and make it a valid SQL query.
'name=' 'super_model''	dump/remote	Import super_model.	----
'name IN ("model1","model2","model3")'	dump/remote	Import model model1,model2, and model3.	----
'ALGORITHM_NAME="NAIVE_BAYES"'	remote	Import all NB models.	----
'FUNCTION_NAME="CLASSIFICATION"'	remote	Import all classification models.	----
'name LIKE "NB_MODEL%" ESCAPE "\' "'	remote	Import all models whose name start with 'NB_MODEL'.	----

IMPORT_MODEL is not mutually exclusive with the DDL-like operations such as CREATE_MODEL, DROP_MODEL, and RENAME_MODEL. In other words, if an import operation is underway, models with the same name are dropped at that time, and the results in the schema are unpredictable.

Examples

The following example shows user MARY imports all models from a dump file, model_exp_001.dmp, created by user SCOTT. The dump file is located in the file system directory mapped to a directory object called DM_DUMP. Note that if user MARY does not have IMP_FULL_DATABASE privileges, IMPORT_MODEL will raise an error.

```
-- import all models
declare
  file_name      VARCHAR2(40);
BEGIN
  file_name := 'model_exp_001.dmp';
  DBMS_DATA_MINING.import_model(
    filename=>file_name,
    directory=>'DM_DUMP',
    schema_remap=>'SCOTT:MARY');
  dbms_output.put_line(
'DBMS_DATA_MINING.import_model of all models from SCOTT done!');
END;
/
```

RANK_APPLY Procedure

This procedure ranks the results of an `APPLY` operation based on a top-N specification for predictive and descriptive model results. For classification models, you can provide a cost matrix as input, and obtain the ranked results with costs applied to the predictions.

Syntax

```
DBMS_DATA_MINING.RANK_APPLY (
    apply_result_table_name    IN VARCHAR2,
    case_id_column_name       IN VARCHAR2,
    ranked_apply_result_tab_name IN VARCHAR2,
    top_N                     IN INTEGER DEFAULT 1,
    cost_matrix_table_name    IN VARCHAR2 DEFAULT NULL,
    apply_result_schema_name  IN VARCHAR2 DEFAULT NULL,
    cost_matrix_schema_name   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 23–49 *RANK_APPLY Procedure Parameters*

Parameter	Description
<code>apply_result_table_name</code>	Name of the table or view containing the results of an <code>APPLY</code> operation on the test dataset (see Usage Notes).
<code>case_id_column_name</code>	Name of the case identifier column. This must be the same as the one used for generating <code>APPLY</code> results.
<code>ranked_apply_result_tab_name</code>	Name of the table containing the ranked apply results.
<code>top_N</code>	Top N predictions to be considered from the <code>APPLY</code> results for precision recall computation.
<code>cost_matrix_table_name</code>	Name of the cost matrix table.
<code>apply_result_schema_name</code>	Name of the schema hosting the <code>APPLY</code> results table.
<code>cost_matrix_schema_name</code>	Name of the schema hosting the cost matrix table.

Usage Notes

You can use `RANK_APPLY` to generate ranked apply results, based on a top-N filter and also with application of cost for predictions, if a cost matrix is provided.

The behavior of `RANK_APPLY` is similar to that of `APPLY` with respect to other DDL-like operations such as `CREATE_MODEL`, `DROP_MODEL`, and `RENAME_MODEL`. The procedure does not depend on the model; the only input of relevance is the apply results generated in a fixed schema table from `APPLY`.

The main intended use of `RANK_APPLY` is for the generation of the final `APPLY` results against the scoring data in a production setting. You can apply the model against test data using `APPLY`, compute various test metrics against various cost matrix tables, and use the candidate cost matrix for `RANK_APPLY`.

The schema for the apply results from each of the supported algorithms is listed in subsequent sections. The `case_id` column will be the same case identifier column as that of the apply results.

Classification Models — NB, ABN, SVM

For numerical targets, the ranked results table will have the schema as shown:

```
(case_id      VARCHAR2/NUMBER,
 prediction   NUMBER,
 probability  NUMBER,
 cost        NUMBER,
 rank        INTEGER)
```

For categorical targets, the ranked results table will have the following schema:

```
(case_id      VARCHAR2/NUMBER,
 prediction   VARCHAR2,
 probability  NUMBER,
 cost        NUMBER,
 rank        INTEGER)
```

Clustering using *k*-Means

Clustering is an unsupervised mining function, and hence there are no targets. The results of an `APPLY` operation contains simply the cluster identifier corresponding to a case, and the associated probability. Cost matrix is not considered here. The ranked results table will have the schema as shown, and contains the cluster ids ranked by top-N.

```
(case_id      VARCHAR2/NUMBER,
 cluster_id   NUMBER,
 probability  NUMBER,
```

RANK_APPLY Procedure

```
rank          INTEGER)
```

Feature Extraction using NMF

Feature extraction is also an unsupervised mining function, and hence there are no targets. The results of an `APPLY` operation contains simply the feature identifier corresponding to a case, and the associated match quality. Cost matrix is not considered here. The ranked results table will have the schema as shown, and contains the feature ids ranked by `top-N`.

```
(case_id      VARCHAR2/NUMBER,  
feature_id    NUMBER,  
match_quality NUMBER,  
rank          INTEGER)
```

Examples

```
BEGIN  
/* build a model with name census_model.  
 * (See example under CREATE_MODEL)  
 */  
  
/* if build data was pre-processed in any manner,  
 * perform the same pre-processing steps on apply  
 * data also.  
 * (See examples in the section on DBMS_DATA_MINING_TRANSFORM)  
 */  
  
/* apply the model to data to be scored */  
DBMS_DATA_MINING.rank_apply(  
  apply_result_table_name => 'census_apply',  
  case_id_column_name => 'person_id',  
  ranked_apply_result_tab_name => 'census_ranked_apply',  
  top_N => 3,  
  cost_matrix_table_name => 'census_cost_matrix');  
END;  
/  
  
-- View Apply Results  
SELECT *  
  FROM census_ranked_apply;
```

RENAME_MODEL Procedure

This procedure renames a mining model to a specified new name.

Syntax

```
DBMS_DATA_MINING.RENAME_MODEL (
    model_name          IN VARCHAR2,
    new_model_name      IN VARCHAR2);
```

Parameters

Table 23–50 *RENAME_MODEL Procedure Parameters*

Parameter	Description
model_name	Old name of the model (see Rules and Limitations).
new_model_name	New name of the model (see Rules and Limitations).

Usage Notes

You can use `RENAME_MODEL` to rename an existing mining model.

The behavior of the `RENAME_MODEL` is similar to a SQL DDL `RENAME` operation. It blocks `DROP_MODEL` and `CREATE_MODEL` operations. It does not block `APPLY`, which is a SQL query-like operation that does not update any model data.

If an `APPLY` operation is using a model, and you attempt to rename the model during that time, the `RENAME` will succeed and `APPLY` will return indeterminate results. This is in line with the conventional behavior in the RDBMS, where DDL operations do not block on query operations.

Examples

Assume the existence of a model `census_model`. The following example shows how to rename this model.

```
BEGIN
  DBMS_DATA_MINING.rename_model(
    model_name => 'census_model',
    new_model_name => 'census_new_model');
END;
/
```

RENAME_MODEL Procedure

DBMS_DATA_MINING_TRANSFORM

The `DBMS_DATA_MINING_TRANSFORM` package is a set of data transformation utilities available for use with the `DBMS_DATA_MINING` package for preparing mining data.

This chapter contains the following topics:

- [Using DBMS_DATA_MINING_TRANSFORM](#)
 - [Overview](#)
 - [Types](#)
 - [Supported Transformation Methods](#)
 - [Transformation Operations](#)
 - [Transformation Methodology](#)
- [Summary of DBMS_DATA_MINING_TRANSFORM Subprograms](#)

Using DBMS_DATA_MINING_TRANSFORM

Overview

The DBMS_DATA_MINING_TRANSFORM package has two motivations:

- It is a basic utility package for preprocessing mining data before providing it as input to routines in the DBMS_DATA_MINING package.
- It is a learning tool that shows how to use SQL to perform common mining transforms. The inputs and outputs for this package are simple views and tables that are not Oracle proprietary. You can study these objects to help you create data transforms that are specific to your application data. The source code for this package is in `dbmsdmxf.sql` (for UNIX, the path is `$ORACLE_HOME/dm/admin/dbmsdmxf.sql`) and is available for inspection.

The main principle behind the design of this package is the fact that SQL has enough power to perform most of the common mining transforms efficiently. For example, binning can be done using CASE expression or DECODE function, and linear normalization is a simple algebraic expression of the form $(x - shift) / scale$ where x is the data value that is being transformed.

However, the queries that perform the transforms can be rather lengthy. So it is desirable to have some convenience routines that will help in generating queries. Thus, the goal of this package is to provide query generation services for the most common mining transforms, as well as to provide a framework that can be easily extended for implementing other transforms.

Note: Use of this package for preprocessing data input to DBMS_DATA_MINING operations is not mandatory. You can use any third-party tool or any home-grown utilities that are customized for your application.

Types

Table 24–1 Summary of Data Types

Data Type	Purpose
Column_List	List of column names representing mining attributes, defined to be VARRAY(1000) OF VARCHAR2(32);

Supported Transformation Methods

The DBMS_DATA_MINING_TRANSFORM package supports the following transformations for *numerical* and *categorical* attributes, which map to the NUMBER and VARCHAR2/CHAR Oracle data types respectively.

Binning

Binning involves mapping both continuous and discrete values to discrete values of reduced cardinality. For example, the age of persons can be binned into discrete numeric bins: 1-20 to 1, 21-40 to 2, and so on. Popular car manufacturers such as Ford, Chrysler, BMW, Volkswagen can be binned into discrete categorical bins: {Ford, Chrysler} to US_Car_Makers, and {BMW, Volkswagen} to European_Car_Makers. The package supports binning for both categorical and numerical attributes.

Note: This chapter uses standard interval notation for number sets: $[a,b]$ is the set of all real numbers greater than or equal to a and less than or equal to b ; $[a,b)$ is the set of all real numbers greater than or equal to a and less than b . (b is in the set $[a,b]$; b is not in the set $[a,b)$.)

Top-N Frequency Categorical Binning

The bin definition for each attribute is computed based on the occurrence frequency of values that are computed from the data. The user specifies a particular number of bins, say N . Each of the bins bin_1, \dots, bin_N corresponds to the values with top frequencies. The bin bin_{N+1} corresponds to all remaining values.

Equi-Width Numerical Binning

The bin definition for each attribute is computed based on the *min* and *max* values that are computed from the data. The user specifies a particular number of bins, say N . Each of the bins bin_1, \dots, bin_N span ranges of equal width of size $inc = (max - min)/N$, and bin_0 spans range $(-inf, min)$ and bin_{N+1} range $(max, +inf)$.

Quantile Numerical Binning

The definition for each relevant column is computed based on the *min* values for each quantile, where quantiles are computed from the data using NTILE function. Bins bin_1, \dots, bin_{N-1} span ranges $[min_T, min_{T+1})$ and bin_N range $[min_N, max_N]$. Bins with equal left and right boundaries are collapsed.

Normalization

Normalization involves scaling continuous values down to specific range — as in -1.0 to 1.0 or 0.0 to 1.0 such that $x_{new} = (x_{old} - shift) / scale$. It applies only to numerical attributes.

Min-Max Normalization

The normalization definition for each attribute is computed based on the *min* and *max* values that are computed from the data. The values for *shift* and *scale* are computed to be $shift = min$, and $scale = (max - min)$ respectively.

Z-Score Normalization

The normalization definition for each attribute is computed based on the values for *mean* and *standard deviation* that are computed from the data. The values for *shift* and *scale* are computed to be $shift = mean$, and $scale = standard\ deviation$ respectively.

Winsorizing and Trimming (Clipping)

Some computations on attribute values can be significantly affected by extreme values. One approach to achieving a more robust computation is to winsorize or trim the data as a preprocessing step. Winsorizing involves setting the tail values of a particular attribute to some specified quantile of the data, while trimming removes the tails. In other words, trimmed values are ignored in further computations. This is achieved by setting the tails to NULL. For example, for a 90% winsorization, the bottom 5% are set equal to the minimum value in the 6th percentile, while the upper 5% are set equal to the value corresponding to the maximum value in the 95th percentile.

Transformation Operations

The package provides three classes of convenience routines. The first two classes of routines define the transformation, and the last class of routines generate the queries that provide the transformed data.

- Create the transform definition table using CREATE routines. The generated table is a transform-specific and has a pre-defined fixed schema. Each routine is equivalent to the SQL statement `CREATE TABLE table (...)`
- Define the transform — that is, populate the transform definition table — using INSERT routines. Each routine is equivalent to the SQL statement `INSERT INTO table SELECT ...`

- Generate the query for transformation using XFORM routines. Each routine is equivalent to the SQL statement `CREATE VIEW view AS SELECT ...`

Creating a Transform Definition Table

You must use `CREATE_BIN_NUM` or `CREATE_BIN_CAT` routines to create the bin definition tables. You must use `CREATE_NORM_LIN` to create the normalization definition table. You must use `CREATE_CLIP` to create the clipping definition table.

Usually, the consistency and integrity of transform definition tables is guaranteed by the creation process. Alternatively, it can be achieved by leveraging an integrity constraints mechanism. This can be done either by altering the tables created with `CREATE` routines, or by creating the tables manually with the necessary integrity constraints.

Defining the Transform

The most common way of defining the transform (populating the transform definition tables) for each attribute is based on data inspection using some predefined methods (also known as automatic transform definition). Some of the most popular methods have been captured by the `INSERT` routines in the package. For example, the z-score normalization method estimates mean and standard deviation from the data to be used as a shift and scale parameters of the linear normalization transform.

You can bin numerical attributes using `INSERT_BIN_NUM_EQWIDTH` or `INSERT_BIN_NUM_QTILE` and categorical attributes using `INSERT_BIN_CAT_FREQ`. You can normalize numerical attributes using `INSERT_NORM_LIN_ZSCORE` or `INSERT_NORM_LIN_MINMAX`. You can either winsorize numerical attributes using `INSERT_CLIP_WINZOR_TAIL` or trim them using `INSERT_CLIP_TRIM_TAIL`. You can invoke these routines several times to transform all relevant attributes from various data sources till the definition table fully represents all mining attributes for a given problem.

After performing automatic transform definition, some or all of the definitions can be adjusted by issuing SQL DML statements against the transform definition tables, thus providing virtually infinite flexibility in defining custom transforms.

The `INSERT` routines enable flexible transform definitions in several ways:

- The data provided to the `INSERT` routines do not necessarily have to be the data used for a particular model creation. It can be any data that contains adequate representation of the mining attributes.

- The `INSERT` routines can be called any number of times against the same or different dataset until all the attributes have their transformations defined. You can selectively exclude one or more attributes for a particular iteration of the `INSERT`. In the most extreme case, each individual attribute can potentially have a unique transformation definition.
- You do not have to separately feed in numerical and categorical attributes, since categorical binning automatically skips over `NUMBER` columns in your table, and numerical binning and the normalization and clipping routines skip over `VARCHAR2/CHAR` columns in your input data.

Generating the Query for the Transform

Query generation is driven by the simple transform-specific definition tables with a predefined schema. Query generation routines should be viewed as macros, and transform definition tables as parameters used in macro expansions. Similar to using `#define` macros in the C language, the invoker is responsible for ensuring the correctness of the expanded macro, that is, that the result is a valid SQL query.

You can generate the views representing the transformation queries for binning using `XFORM_BIN_CAT` and `XFORM_BIN_NUM`, and for normalization using `XFORM_NORM_LIN`, and for clipping using `XFORM_CLIP`.

If your data contains a combination of numerical and categorical attributes, you must essentially feed the results of one transformation step to the next step. For example, the results of `XFORM_BIN_CAT` can be fed to `XFORM_BIN_NUM` or vice versa. The order is irrelevant since numerical and categorical transforms work on disjoint sets of attributes.

Transformation Methodology

Given a dataset for a particular mining problem, any preprocessing and transformations on the mining data must be uniform across all mining operations. In other words, if the build data is preprocessed according to a particular transform definition, then it follows that the test data and the scoring data must be preprocessed using the same definition.

The general usage of routines in this package can be explained using this example. Assume that your input table for model build contains *both* numerical and categorical data that require to be binned. A possible sequence of operations will be:

- Invoke `CREATE_BIN_NUM` to generate a numerical bin definition table.

- Invoke `INSERT_BIN_NUM_EQWIDTH` to define the transforms for all numerical attributes in the build data input (For the sake of simplicity, let us assume that all numericals are to be binned into 10 bins.)
- Next invoke `XFORM_BIN_NUM` with the numerical bin table and the build data table as inputs. The resulting object is a view that represents a SQL query against the build data table that performs numerical binning. Assume that you have named this result object `build_bin_num_view`.
- Since you still have the categorical attributes to be binned, invoke `CREATE_BIN_CAT` to create a categorical bin definition table.
- Next, invoke `INSERT_BIN_CAT_FREQ` to define the transforms for all categorical attributes. (For the sake of simplicity, let us assume that all categorical attributes are to be binned into 10 bins.)
- As the final step, invoke `XFORM_BIN_CAT` with the categorical bin table and the view name provided by `XFORM_BIN_NUM`, namely `build_bin_num_view`, as the inputs. This essentially amounts to combining the transformations from both stages.
- The object resulting from this operation is a view that represents a SQL query against your build data table, influenced by the contents of the categorical bin boundary table also. Provide this view name as the data input to the `CREATE_MODEL` procedure in the `DBMS_DATA_MINING` package.

If this happens to be a classification model, and you want to `APPLY` this model to scoring data, you must prepare the scoring data similar to the build data. You can achieve this in two simple steps:

- First, call `XFORM_BIN_NUM` with the scoring data table and the numerical bin boundary table as inputs. The resulting object is a view that represents an SQL query against your scoring data table, influenced by the contents of the numerical bin boundary table. Assume that you have named this result object `apply_bin_num_view`.
- As the next and final step, invoke `XFORM_BIN_CAT` with the categorical bin table and the view name provided by `XFORM_BIN_NUM`, namely `apply_bin_num_view`, as the inputs.
- The object resulting from this operation is now a view that represents an SQL query against your scoring data table, influenced by the contents of the categorical bin boundary table also. Provide this view name as the data input to the `APPLY` procedure in the `DBMS_DATA_MINING` package.

Summary of DBMS_DATA_MINING_TRANSFORM Subprograms

Table 24–2 DBMS_DATA_MINING_TRANSFORM Package Subprograms

Subprogram	Purpose
CREATE_BIN_CAT Procedure on page 24-10	Creates a categorical bin definition table
CREATE_BIN_NUM Procedure on page 24-11	Creates a numerical bin definition table
CREATE_CLIP Procedure on page 24-12	Creates a clipping definition table
CREATE_NORM_LIN Procedure on page 24-13	Creates a normalization definition table
INSERT_BIN_CAT_FREQ Procedure on page 24-14	Populates the categorical bin definition table, applying frequency-based binning on the categorical input data
INSERT_BIN_NUM_EQWIDTH Procedure on page 24-16	Populates the numerical bin definition table, applying equi-width binning on the numerical input data
INSERT_BIN_NUM_QTILE Procedure on page 24-18	Populates the numerical bin definition table, applying quantile binning on the numerical input data
INSERT_CLIP_TRIM_TAIL Procedure on page 24-20	Populates the clipping definition table, applying trimming based on tail fraction on the numerical input data
INSERT_CLIP_WINSOR_TAIL Procedure on page 24-22	Populates the clipping definition table, applying winsorizing based on tail fraction on the numerical input data
INSERT_NORM_LIN_ZSCORE Procedure on page 24-24	Populates the normalization definition table applying z-score normalization on the numerical input data
INSERT_NORM_LIN_MINMAX Procedure on page 24-26	Populates the normalization definition table, applying min-max normalization on the numerical input data
XFORM_BIN_CAT Procedure on page 24-28	Creates the view representing the transformed output with binned categorical data

Table 24–2 (Cont.) DBMS_DATA_MINING_TRANSFORM Package Subprograms

Subprogram	Purpose
XFORM_BIN_NUM Procedure on page 24-31	Creates the view representing the transformed output with binned numerical data
XFORM_CLIP Procedure on page 24-34	Creates the view representing the transformed output with clipped numerical data
XFORM_NORM_LIN Procedure on page 24-36	Creates the view representing the transformed output with normalized numerical data

CREATE_BIN_CAT Procedure

This procedure creates a categorical binning definition table. This table is used as input to `INSERT_BIN_CAT_FREQ` and `XFORM_BIN_CAT` procedures.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.CREATE_BIN_CAT (
    bin_table_name      IN VARCHAR2,
    bin_schema_name    IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–3 *CREATE_BIN_CAT Procedure Parameters*

Parameter	Description
<code>bin_table_name</code>	Name of the bin definition table.
<code>bin_schema_name</code>	Name of the schema hosting the bin definition table.

Usage Notes

The generated bin definition table will have the predefined schema:

```
col VARCHAR2(30)
val VARCHAR2(4000)
bin VARCHAR2(4000)
```

Examples

```
BEGIN
    DBMS_DATA_MINING_TRANSFORM.CREATE_BIN_CAT('build_bin_cat_table');
END;
```


CREATE_BIN_NUM Procedure

This procedure creates a numerical binning definition table. This table is used as input to INSERT_BIN_NUM_EQWIDTH, INSERT_BIN_NUM_QTILE, and XFORM_BIN_NUM procedures.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.CREATE_BIN_NUM (
    bin_table_name    IN VARCHAR2,
    bin_schema_name  IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–4 CREATE_BIN_NUM Procedure Parameters

Parameter	Description
bin_table_name	Name of the bin definition table.
bin_schema_name	Name of the schema hosting the bin definition table.

Usage Notes

The generated bin definition table will have the predefined schema:

```
col  VARCHAR2(30)
val  NUMBER
bin  VARCHAR2(4000)
```

Examples

```
BEGIN
    DBMS_DATA_MINING_TRANSFORM.CREATE_BIN_NUM('build_bin_num_table');
END;
```

CREATE_CLIP Procedure

This procedure creates a clipping definition table. This table is used as input to `INSERT_CLIP_WINSOR_TAIL`, `INSERT_CLIP_TRIM_TAIL`, and `XFORM_CLIP` procedures.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.CREATE_CLIP (
    clip_table_name    IN VARCHAR2,
    clip_schema_name  IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–5 *CREATE_CLIP Procedure Parameters*

Parameter	Description
<code>clip_table_name</code>	Name of the clipping definition table.
<code>clip_schema_name</code>	Name of the schema hosting the clipping definition table.

Usage Notes

The generated clipping definition table will have the predefined schema:

```
col    VARCHAR2(30)
lcut   NUMBER
lval   NUMBER
rcut   NUMBER
rval   NUMBER
```

Examples

```
BEGIN
    DBMS_DATA_MINING_TRANSFORM.CREATE_CLIP('build_clip_table');
END;
```

CREATE_NORM_LIN Procedure

This procedure creates a linear normalization definition table. This table is used as input to `INSERT_NORM_LIN_MINMAX`, `INSERT_NORM_LIN_ZSCORE`, `XFORM_NORM_LIN` procedures.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.CREATE_NORM_LIN (
    norm_table_name      IN VARCHAR2,
    norm_schema_name     IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–6 CREATE_NORMALIZE_LIN Procedure Parameters

Parameter	Description
<code>norm_table_name</code>	Name of the normalization definition table.
<code>norm_schema_name</code>	Name of the schema hosting the normalization definition table.

Usage Notes

The generated normalization table will have the predefined schema:

```
col      VARCHAR2(30)
shift   NUMBER
scale   NUMBER
```

Examples

```
BEGIN
    DBMS_DATA_MINING_TRANSFORM.CREATE_NORM_LIN('build_norm_table');
END;
```

INSERT_BIN_CAT_FREQ Procedure

This procedure finds the categorical binning definition for every VARCHAR2, CHAR column in the data table that is not specified in the exclusion list and inserts the definition into the categorical binning definition table created using CREATE_BIN_CAT.

Definition for each relevant column is computed based on the occurrence frequency of column values that are computed from the data table. Each of the $bin_num(N)$ bins bin_1, \dots, bin_N corresponds to the values with top frequencies when $N > 0$ or bottom frequencies when $N < 0$, and bin_{N+1} to all remaining values, where $bin_I = I$. Ordering ties among identical frequencies are broken by ordering on column values (ASC for $N > 0$ or DESC for $N < 0$). When the number of distinct values $C < N$ only $C+1$ bins will be created.

The parameter $default_num(D)$ is used for pruning based on the number of values that fall into the default bin. When $D > 0$ only columns that have at least D defaults are kept while others are ignored. When $D < 0$ only columns that have at most D values are kept. No pruning is done when D is NULL or $D = 0$. Parameter $bin_support(SUP)$ is used for restricting bins to frequent ($SUP > 0$) values $frq \geq SUP * tot$, or infrequent ($SUP < 0$) ones $frq \leq -SUP * tot$, where frq is a given value count and tot is a sum of all counts as computed from the data. No support filtering is done when SUP is NULL or when $SUP = 0$.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.INSERT_BIN_CAT_FREQ (
    bin_table_name      IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    bin_num             IN PLS_INTEGER DEFAULT 9,
    exclude_list        IN Column_List DEFAULT NULL,
    default_num         IN PLS_INTEGER DEFAULT 2,
    bin_support         NUMBER DEFAULT NULL,
    bin_schema_name     IN VARCHAR2 DEFAULT NULL,
    data_schema_name    IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–7 *INSERT_BIN_CAT_FREQ Procedure Parameters*

Parameter	Description
<code>bin_table_name</code>	Name of the categorical bin table generated using <code>CREATE_BIN_CAT</code> procedure.
<code>data_table_name</code>	Name of the table containing the data.
<code>bin_num</code>	Number of bins.
<code>exclude_list</code>	List of columns (attributes) to be excluded from this iteration of the binning process.
<code>default_num</code>	Number of default values.
<code>bin_support</code>	Bin support as a fraction.
<code>bin_schema_name</code>	Name of the schema hosting the bin definition table.
<code>data_schema_name</code>	Name of the schema hosting the table with data.

Usage Notes

For a given input table, you can iteratively call this routine several times with different specifications for number of bins for a given input table. For each iteration, you can selectively exclude attributes (that is, column names) using the `exclude_list` parameter for a particular binning specification.

Columns with all NULLs are ignored. No bin definitions are populated when `bin_num = 0`, or `bin_num` is NULL.

Examples

The simplest invocation of this routine populates bin definitions in the `cat_bin_table` for all the categorical attributes found in `build_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.INSERT_BIN_NUM(
    'cat_bin_table', 'build_table');
END;
/
```

INSERT_BIN_NUM_EQWIDTH Procedure

This procedure finds the numerical binning definition for every `NUMBER` column in the data table that is not specified in the exclusion list and inserts the definition into the numerical binning definition table that was created using `CREATE_BIN_NUM`.

Definition for each relevant column is computed based on the *min* and *max* values that are computed from the data table. Each of the `bin_num(N)` bins bin_1, \dots, bin_N span ranges of equal width $inc = (max - min) / N$ where $bin_I = I$ when $N > 0$ or $bin_I = N+1-I$ when $N < 0$, and $bin_0 = bin_{N+1} = NULL$. The values of *val* column are rounded to `round_num` significant digits prior to scoring them in the definition table.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.INSERT_BIN_NUM_EQWIDTH (
    bin_table_name      IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    bin_num             IN PLS_INTEGER DEFAULT 10,
    exclude_list       IN Column_List DEFAULT NULL,
    round_num          IN PLS_INTEGER DEFAULT 6,
    bin_schema_name    IN VARCHAR2 DEFAULT NULL,
    data_schema_name   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–8 *INSERT_BIN_EQWIDTH Procedure Parameters*

Parameter	Description
<code>bin_table_name</code>	Name of the categorical bin table generated using <code>CREATE_BIN_NUM</code> procedure.
<code>data_table_name</code>	Name of the table containing the data.
<code>bin_num</code>	Number of bins.
<code>exclude_list</code>	List of columns (attributes) to be excluded from this iteration of the binning process.
<code>round_num</code>	Number of significant digits.
<code>bin_schema_name</code>	Name of the schema hosting the bin definition table.
<code>data_schema_name</code>	Name of the schema hosting the table with data.

Usage Notes

For a given input table, you can iteratively call this routine several times with different specifications for number of bins for a given input table. For each iteration, you can selectively exclude attributes (that is, column names) using the `exclude_list` parameter for a particular binning specification.

Columns with all NULLs or only one unique value are ignored. No bin definitions are populated when `bin_num = 0`, or `bin_num` is NULL.

For example, when `N=2`, `col='mycol'`, `min=10`, and `max = 21`, the following three rows are inserted into the definition table (`inc = 5.5`):

COL	VAL	BIN
-----	-----	-----
mycol	10	NULL
mycol	15.5	1
mycol	21	2

Examples

The simplest invocation of this routine populates bin definitions in the `num_bin_table` for all the numerical attributes found in `build_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.INSERT_BIN_NUM(
    'num_bin_table', 'build_table');
END;
/
```

INSERT_BIN_NUM_QTILE Procedure

This procedure finds a numerical binning definition for every NUMBER column in the data table that is not specified in the exclusion list and inserts the definition into the binning definition table that was created using CREATE_BIN_NUM.

The definition for each relevant column is computed based on the *min* values for each quantile, where quantiles are computed from the data using NTILE function. Bins bin_1, \dots, bin_{N-1} span ranges $[min_I, min_{I+1})$ and bin_N range $[min_N, max_N]$ with $bin_I = I$ when $N > 0$ or $bin_I = N+1-I$ when $N < 0$, and $bin_0 = bin_{N+1} = NULL$. Bins with equal left and right boundaries are collapsed.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.INSERT_BIN_NUM_QTILE (
    bin_table_name      IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    bin_num             IN PLS_INTEGER DEFAULT 10,
    exclude_list        IN Column_List DEFAULT NULL,
    bin_schema_name     IN VARCHAR2 DEFAULT NULL,
    data_schema_name    IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–9 INSERT_BIN_NUM_QTILE Procedure Parameters

Parameter	Description
bin_table_name	Name of the numerical binning definition table generated using the CREATE_BIN_NUM procedure.
data_table_name	Name of the table containing the data.
bin_num	Number of bins.
exclude_list	List of columns (attributes) to be excluded from this iteration of the binning process.
bin_schema_name	Name of the schema hosting the numerical binning definition table.
data_schema_name	Name of the schema hosting the table with data.

Usage Notes

For a given input table, you can iteratively call this routine several times with different specifications for `bin_num` for a given input table. For each iteration, you can selectively exclude attributes (that is, column names) using the `exclude_list` parameter for a particular specification. Columns with all NULLs are ignored.

Example 1. When `N = 4`, `col = 'mycol'`, and data is `{1, 2, 2, 2, 2, 3, 4}`, the following three rows are inserted into the definition table:

COL	VAL	BIN
-----	-----	-----
mycol	1	NULL
mycol	2	1
mycol	4	2

Here quantities are `{1, 2}`, `{2, 2}`, `{2, 3}`, `{4}` and `min(1) = 1`, `min(2) = 2`, `min(3) = 2`, `min(4) = 4`, `max(4) = 4`, and ranges are `[1, 2)`, `[2, 2)`, `[2, 4)`, `[4, 4]`. After collapsing `[1, 2)`, `[2, 4]`.

Examples

The simplest invocation of this routine populates numerical binning definitions in the `num_bin_table` for all the numerical attributes found in `build_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.INSERT_BIN_NUM_QTILE(
    'num_bin_table', 'build_table');
END;
```

INSERT_CLIP_TRIM_TAIL Procedure

This procedure finds the trimming definition for every NUMBER column in the data table that is not specified in the exclusion list and inserts the definition into the clipping definition table that was created using CREATE_CLIP.

The definition for each relevant column is computed based on the non-NULL values sorted in ascending order such that $val(1) < val(2) < \dots < val(N)$, where N is a total number of non-NULL values in a column:

```
lcut = val(1+floor(N*q))
lval = NULL
rcut = val(N-floor(*N*q))
rval = NULL
```

where $q = ABS(NVL(tail_frac, 0))$. Nothing is done when $q \geq 0.5$.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.INSERT_CLIP_TRIM_TAIL (
  clip_table_name      IN VARCHAR2,
  data_table_name      IN VARCHAR2,
  tail_frac            IN NUMBER DEFAULT 0.025,
  exclude_list         IN Column_List DEFAULT NULL,
  clip_schema_name     IN VARCHAR2 DEFAULT NULL,
  data_schema_name     IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–10 INSERT_CLIP_TRIM_TAIL Procedure Parameters

Parameter	Description
clip_table_name	Name of the clipping definition table generated using the CREATE_CLIP procedure.
data_table_name	Name of the table containing the data.
tail_frac	Tail fraction.
exclude_list	List of columns (attributes) to be excluded from this iteration of the clipping process.
clip_schema_name	Name of the schema hosting the clipping definition table.
data_schema_name	Name of the schema hosting the table with data.

Usage Notes

For a given input table, you can iteratively call this routine several times with different specifications for `tail_frac` for a given input table. For each iteration, you can selectively exclude attributes (that is, column names) using the `exclude_list` parameter for a particular specification.

Example 1. When $q = 0.2$, `col = 'mycol'`, and data is $\{1, 2, 2, 2, 3, 4, 4\}$, the following row is inserted into the definition table:

COL	LCUT	LVAL	RCUT	RVAL
-----	-----	-----	-----	-----
mycol	2	NULL	4	NULL

Here $1 + \text{floor}(N \cdot q) = 1 + \text{floor}(7 \cdot 0.2) = 2$, `lcut = val(2) = 2`.

$N - \text{floor}(N \cdot q) = 7 - \text{floor}(7 \cdot 0.2) = 6$, `rcut = val(6) = 4`.

Examples

The simplest invocation of this routine populates clipping definitions in the `clip_table` for all the numerical attributes found in `build_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.INSERT_CLIP_TRIM_TAIL(
    'clip_table', 'build_table');
END;
```

INSERT_CLIP_WINSOR_TAIL Procedure

This procedure finds winsorizing definition for every NUMBER column in the data table that is not specified in the exclusion list and inserts the definition into the clipping definition table that was created using CREATE_CLIP.

Definition for each relevant column is computed based on the non-NULL values sorted in ascending order such that $val(1) < val(2) < \dots < val(N)$, where N is a total number of non-NULL values in a column:

```
lcut = val(1+floor(N*q))
lval = lcut
rcut = val(N-floor(N*q))
rval = rcut
```

where $q = \text{ABS}(\text{NVL}(\text{tail_frac}, 0))$. Nothing is done when $q \geq 0.5$.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.INSERT_CLIP_WINSOR_TAIL (
  clip_table_name      IN VARCHAR2,
  data_table_name      IN VARCHAR2,
  tail_frac            IN NUMBER DEFAULT 0.025,
  exclude_list         IN Column_List DEFAULT NULL,
  clip_schema_name     IN VARCHAR2 DEFAULT NULL,
  data_schema_name     IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–11 INSERT_CLIP_WINSOR_TAIL Procedure Parameters

Parameter	Description
clip_table_name	Name of the clipping definition table generated using CREATE_CLIP procedure.
data_table_name	Name of the table containing the data.
tail_frac	Tail fraction.
exclude_list	List of columns (attributes) to be excluded from this iteration of the clipping process.
clip_schema_name	Name of the schema hosting the clipping definition table.
data_schema_name	Name of the schema hosting the table with data.

Usage Notes

For a given input table, you can iteratively call this routine several times with different specifications for `tail_frac` for a given input table. For each iteration, you can selectively exclude attribute (that is, column names using the `exclude_list` parameter for a particular specification. Columns with all NULLs are ignored.

Example 1. When $q = 0.2$, `col = 'mycol'`, and data is $\{1, 2, 2, 2, 3, 4, 4\}$, the following row is inserted into the definition table:

COL	LCUT	LVAL	RCUT	RVAL
mycol	2	2	4	4

Here $1 + \text{floor}(N \cdot q) = 1 + \text{floor}(7 \cdot 0.2) = 2$, `lcut = val(2) = 2`.

$N - \text{floor}(N \cdot q) = 7 - \text{floor}(7 \cdot 0.2) = 6$, `rcut = val(6) = 4`.

Examples

The simplest invocation of this routine populates clipping definitions in the `clip_table` for all the numerical attributes found in `build_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.INSERT_CLIP_WINSOR_TAIL(
    'clip_table', 'build_table');
END;
```

INSERT_NORM_LIN_ZSCORE Procedure

This procedure finds the normalization definition for every NUMBER column in the data table that is not specified in the exclusion list and inserts the definition based on z-score normalization into the table that was created using CREATE_NORM_LIN.

Definition for each relevant column is computed based on the *min* and *max* values that are computed from the data table, such that $shift = min$ and $scale = max - min$. The values of *shift* and *scale* are rounded to *round_num* significant digits prior to storing them in the definition table.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.INSERT_NORM_LIN_ZSCORE (
    norm_table_name      IN VARCHAR2,
    data_table_name      IN VARCHAR2,
    exclude_list         IN Column_List DEFAULT NULL,
    round_num            IN PLS_INTEGER DEFAULT 6,
    norm_schema_name     IN VARCHAR2 DEFAULT NULL,
    data_schema_name     IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–12 INSERT_BIN_NORM_LIN_ZSCORE Procedure Parameters

Parameter	Description
norm_table_name	Name of the normalization table generated using CREATE_NORM_LIN procedure.
data_table_name	Name of the table containing the data.
exclude_list	List of columns (attributes) to be excluded from this iteration of the normalization process.
round_num	Number of significant digits.
norm_schema_name	Name of the schema hosting the normalization definition table.
data_schema_name	Name of the schema hosting the table with data.

Usage Notes

For a given input table, you can iteratively call this routine several times with selective exclusion of attributes (that is, column names) using the `exclude_list` parameter for a particular binning specification.

Columns with all NULLs or only one unique value are ignored.

Examples

The simplest invocation of this routine populates normalization definitions in the `norm_zscore_table` for all the numerical attributes found in `build_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.INSERT_NORM_LIN_ZSCORE(
    'norm_zscore_table', 'build_table');
END;
/
```

INSERT_NORM_LIN_MINMAX Procedure

This procedure finds the normalization definition for every `NUMBER` column in the data table that is not specified in the exclusion list and inserts the definition based on min-max normalization into the table that was created using `CREATE_NORM_LIN`.

Definition for each relevant column is computed based on the mean and standard deviation that are computed from the data table, such that $shift = mean$ and $scale = stddev$. The values of $shift$ and $scale$ are rounded to `round_num` significant digits prior to storing them in the definition table.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.INSERT_NORM_LIN_MINMAX (
    norm_table_name      IN VARCHAR2,
    data_table_name      IN VARCHAR2,
    exclude_list         IN Column_List DEFAULT NULL,
    round_num            IN PLS_INTEGER DEFAULT 6,
    norm_schema_name     IN VARCHAR2 DEFAULT NULL,
    data_schema_name     IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–13 *INSERT_NORM_LIN_MINMAX Procedure Parameters*

Parameter	Description
<code>norm_table_name</code>	Name of the normalization table generated using <code>CREATE_NORM_LIN</code> procedure.
<code>data_table_name</code>	Name of the table containing the data.
<code>exclude_list</code>	List of columns (attributes) to be excluded from this iteration of the normalization process.
<code>round_num</code>	Number of significant digits.
<code>norm_schema_name</code>	Name of the schema hosting the normalization definition table.
<code>data_schema_name</code>	Name of the schema hosting the table with data.

Usage Notes

For a given input table, you can iteratively call this routine several times with selective exclusion of attributes (that is, column names) using the `exclude_list` parameter for a particular normalization specification.

Columns with all NULLs or only one unique value are ignored.

Examples

The simplest invocation of this routine populates normalization definitions in the `norm_minmax_table` for all the numerical attributes found in `build_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.INSERT_NORM_LIN_MINMAX(
    'norm_minmax_table', 'build_table');
END;
```

XFORM_BIN_CAT Procedure

This procedure creates the view that performs categorical binning. Only the columns that are specified in the definition table are transformed; the remaining columns do not change.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.XFORM_BIN_CAT (
    bin_table_name      IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    xform_view_name     IN VARCHAR2,
    literal_flag        IN BOOLEAN DEFAULT FALSE,
    bin_schema_name     IN VARCHAR2 DEFAULT NULL,
    data_schema_name    IN VARCHAR2 DEFAULT NULL,
    xform_schema_name   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–14 XFORM_BIN_CAT Procedure Parameters

Parameter	Description
<code>bin_table_name</code>	Name of the categorized binning definition table generated using <code>CREATE_BIN_CAT</code> procedure.
<code>data_table_name</code>	Name of the table containing the data.
<code>xform_view_name</code>	View representing the transformed output.
<code>literal_flag</code>	Literal flag.
<code>bin_schema_name</code>	Name of the schema hosting the bin definition table.
<code>data_schema_name</code>	Name of the schema hosting the data table.
<code>xform_schema_name</code>	Name of the schema hosting the view representing the transformed output.

Usage Notes

The bin table created by `CREATE_BIN_CAT` and populated with bin definitions by `INSERT_BIN_CAT_FREQ` is used to guide the query generation process to construct categorical binning expressions of the following form:

```
DECODE("col", val1, bin1,
      ...
```

```

valN, binN,
NULL, NULL,
binN+1) "col"

```

This expression maps values val_1, \dots, val_N into N bins bin_1, \dots, bin_N , and other values into bin_{N+1} , while `NULL` values remain unchanged. bin_{N+1} is optional. If not specified, it defaults to `NULL`. To specify bin_{N+1} provide a row with val set to `NULL`.

The `literal_flag` parameter indicates whether the values in bin are valid SQL literals. When the flag is set to `TRUE`, the value of bin is used as is in query generation; otherwise it is converted into a valid text literal (surrounded by quotes and each single quote is replaced by two single quotes). By default, the flag is set to `FALSE`. One example of when it can be set to `TRUE` is in cases when all bin are numbers. In that case the transformed column will be numeric as opposed to textual (default behavior).

Note that col is case-sensitive since it generates quoted identifiers. In cases when there are multiple entries with the same col, val combination with different bin , the behavior is undefined — any one of the bin values might be used.

Examples

Example 1. bin_cat contains four rows with $col = 'mycol'$:

```

{col = 'mycol', val = 'Waltham',      bin = 'MA'}
{col = 'mycol', val = 'Burlington',  bin = 'MA'}
{col = 'mycol', val = 'Redwood Shores', bin = 'CA'}
{col = 'mycol', val = NULL,          bin = 'OTHER'}

```

the following expression is generated:

```

DECODE("mycol", 'Waltham',      'MA',
          'Burlington',      'MA',
          'Redwood Shores',  'CA',
          NULL,              NULL,
          'OTHER') "mycol"

```

Example 2. bin_cat contains three rows with $col = 'mycol'$:

```

{col = 'mycol', val = 'Waltham',      bin = 'MA'}
{col = 'mycol', val = 'Burlington',  bin = 'MA'}
{col = 'mycol', val = 'Redwood Shores', bin = 'CA'}

```

the following expression is generated:

```

DECODE("mycol", 'Waltham',      'MA',

```

```
'Burlington',      'MA',
'Redwood Shores', 'CA') "mycol"
```

Example 3. For the definition:

```
COL  VAL          BIN
-----
mycol Waltham      1
mycol Burlington  1
mycol Redwood Shores 2
```

the following expression is generated when the literal flag is set to FALSE:

```
DECODE ("mycol", 'Waltham',      '1',
          'Burlington'         '1',
          'Redwood Shores', '2') "mycol"
```

and when the flag is set to TRUE:

```
DECODE("mycol", 'Waltham',      1,
          'Burlington',         1,
          'Redwood Shores', 2) "mycol"
```

The simplest invocation of this routine generates a view `build_view` that represents the transformation query on `build_table` based on bin definitions in the `cat_bin_table`.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.XFORM_BIN_CAT(
    'cat_bin_table', 'build_table', 'build_view');
END;
/
```

XFORM_BIN_NUM Procedure

This procedure creates the view that performs numerical binning. Only the columns that are specified in the definition table are transformed; the remaining columns do not change.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.XFORM_BIN_NUM (
    bin_table_name      IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    xform_view_name     IN VARCHAR2,
    literal_flag        IN BOOLEAN DEFAULT FALSE,
    bin_schema_name     IN VARCHAR2 DEFAULT NULL,
    data_schema_name    IN VARCHAR2 DEFAULT NULL,
    xform_schema_name   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–15 XFORM_BIN_NUM Procedure Parameters

Parameter	Description
bin_table_name	Name of the numerical binning definition table generated using CREATE_BIN_NUM procedure.
data_table_name	Name of the table containing the data.
xform_view_name	View representing the transformed output.
literal_flag	Literal flag.
bin_schema_name	Name of the schema hosting the bin definition table.
data_schema_name	Name of the schema hosting the data table.
xform_schema_name	Name of the schema hosting the view representing the transformed output.

Usage Notes

The bin table created by CREATE_BIN_NUM and populated with bin definitions by INSERT_BIN_NUM_EQWIDTH or INSERT_BIN_NUM_QTILE is used to guide the query generation process to construct numerical binning expressions of the following form:

```
CASE WHEN "col" < val0 THEN 'bin0'
```

```

    WHEN "col" <= val1 THEN 'bin1'
    ...
    WHEN "col" <= valN THEN 'binN'
    WHEN "col" IS NOT NULL THEN 'binN+1'
END "col"

```

This expression maps values in the range $[val_0; val_N]$ into N bins bin_1, \dots, bin_N , values outside of this range into bin_0 or bin_{N+1} , such that

```

(-inf; val0) -> bin0
[val0; val1) -> bin1
...
(valN-1; valN] -> binN
(valN; +inf) -> binN+1

```

NULL values remain unchanged. bin_{N+1} is optional. If it is not specified, the values ($"col" > val_N$) are mapped to NULL. To specify bin_{N+1} , provide a row with val set to NULL. The order of the WHEN ... THEN pairs is based on the ascending order of val for a given col .

The `literal_flag` parameter indicates whether the values in bin are valid SQL literals. When the flag is set to TRUE, the value of bin is used as is in query generation; otherwise it is converted into a valid text literal (surrounded by quotes and each single quote is replaced by two single quotes). By default, the flag is set to FALSE. One example of when it can be set to TRUE is in cases when all bin are numbers. In that case the transformed column will be numeric as opposed to textual (default behavior).

Note that col is case-sensitive since it generates quoted identifiers. In cases where there are multiple entries with the same col, val combination with different bin , the behavior is undefined — any one of the bin values might be used.

Examples

Example 1. bin_num contains four rows with $col = 'mycol'$:

```

{col = 'mycol', val = 15.5, bin = 'small'}
{col = 'mycol', val = 10,   bin = 'tiny'}
{col = 'mycol', val = 20,   bin = 'large'}
{col = 'mycol', val = NULL, bin = 'huge'}

```

the following expression is generated:

```

CASE WHEN "mycol" < 10      THEN 'tiny'
      WHEN "mycol" <= 15.5 THEN 'small'
      WHEN "mycol" <= 20   THEN 'large'

```

```

        WHEN "mycol" IS NOT NULL THEN 'huge'
    END "mycol"

```

Example 2. *bin_num* contains three rows with *col* = 'mycol':

```

{col = 'mycol', val = 15.5, bin = NULL}
{col = 'mycol', val = 10,   bin = 'tiny'}
{col = 'mycol', val = 20,   bin = 'large'}

```

the following expression is generated:

```

CASE WHEN "mycol" < 10   THEN NULL
      WHEN "mycol" <= 15.5 THEN 'small'
      WHEN "mycol" <= 20   THEN 'large'
END "mycol"

```

Example 3. For the definition:

```

COL   VAL   BIN
-----
mycol  10  NULL
mycol 15.5  1
mycol  21  2

```

the following expression is generated when the literal flag is set to FALSE:

```

CASE WHEN "mycol" < 10   THEN NULL
      WHEN "mycol" <= 15.5 THEN '1'
      WHEN "mycol" <= 20   THEN '2'
END "mycol"

```

and when the flag is set to TRUE:

```

CASE WHEN "mycol" < 10   THEN NULL
      WHEN "mycol" <= 15.5 THEN 1
      WHEN "mycol" <= 20   THEN 2
END "mycol"

```

The simplest invocation of this routine generates a view *build_view* that represents the transformation query on *build_table* based on transform definitions in *bin* definitions in the *num_bin_table*.

```

BEGIN
    DBMS_DATA_MINING_TRANSFORM.XFORM_BIN_NUM(
        'num_bin_table', 'build_table', 'build_view');
END;
/

```

XFORM_CLIP Procedure

This procedure creates the view that performs clipping. Only the columns that are specified in the transform definition are clipped; the remaining columns do not change.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.XFORM_CLIP (
    clip_table_name      IN VARCHAR2,
    data_table_name      IN VARCHAR2,
    xform_view_name      IN VARCHAR2,
    clip_schema_name     IN VARCHAR2 DEFAULT NULL,
    data_schema_name     IN VARCHAR2,DEFAULT NULL,
    xform_schema_name    IN VARCHAR2,DEFAULT NULL;
```

Parameters

Table 24–16 XFORM_CLIP Procedure Parameters

Parameter	Description
clip_table_name	Name of the clipping definition table generated using CREATE_CLIP.
data_table_name	Name of the table containing the data.
xform_view_name	View representing the transformed output.
clip_schema_name	Name of the schema hosting the clipping definition table.
data_schema_name	Name of the schema hosting the data table.
xform_schema_name	Name of the schema hosting the view representing the transformed output.

Usage Notes

The clipping definition table created by CREATE_CLIP and populated with clipping definitions by INSERT_CLIP_WINSOR_TAIL or INSERT_CLIP_TRIM_TAIL is used to guide query generation process to construct clipping expressions of the following form:

```
CASE WHEN "col" < lcut THEN lval
      WHEN "col" > rcut THEN rval
      ELSE "col"
```



```
END "col"
```

Note that *col* is case-sensitive since it generates quoted identifiers. When there are multiple entries in the transform definition table for the same *col*, the behavior is undefined. Any one of the definitions may be used in query generation. NULL values remain unchanged.

Example 1 (Winsorizing). When *col* = 'my_col', *lcut* = -1.5, *lval* = -1.5, and *rcut* = 4.5 and *rval* = 4.5, the following expression is generated:

```
CASE WHEN "my_col" < -1.5 THEN NULL
      WHEN "my_col" > 4.5 THEN NULL
      ELSE "my_col"
END "my_col"
```

Examples

The simplest invocation of this routine generates a view object *build_view* that represents the transformation query on *build_table* based on transform definitions in clipping definitions in the *clip_table*.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.XFORM_CLIP(
    'clip_table', 'build_table', 'build_view');
END;
```

XFORM_NORM_LIN Procedure

This procedure creates the view that performs linear normalization. Only the columns that are specified in the definition table are transformed; the remaining columns do not change.

Syntax

```
DBMS_DATA_MINING_TRANSFORM.XFORM_NORM_LIN (
    norm_table_name      IN VARCHAR2,
    data_table_name     IN VARCHAR2,
    xform_view_name     IN VARCHAR2,
    norm_schema_name    IN VARCHAR2 DEFAULT NULL,
    data_schema_name    IN VARCHAR2 DEFAULT NULL,
    xform_schema_name   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 24–17 XFORM_NORM_LIN Procedure Parameters

Parameter	Description
norm_table_name	Name of the normalization definition table generated using CREATE_NORM_LIN procedure.
data_table_name	Name of the table containing the data.
xform_view_name	View representing the transformed output.
norm_schema_name	Name of the schema hosting the normalization definition table.
data_schema_name	Name of the schema hosting the data table.
xform_schema_name	Name of the schema hosting the view representing the transformed output.

Usage Notes

The normalization table created by CREATE_NORM_LIN and populated with definitions by either INSERT_NORM_LIN_ZSCORE or INSERT_NORM_LIN_MINMAX is used to guide the query generation process to construct normalization expressions of the following form:

```
("col" - shift)/scale "col"
```

Note that *col* is case-sensitive since it generates quoted identifiers. When there are multiple entries in the transform definition table for the same *col*, the behavior is undefined. Any one of the definitions may be used in query generation. NULL values remain unchanged.

For example, when *col* = 'my_col', *shift* = -1.5, and *scale* = 20. The following expression is generated:

```
("my_col" - (-1.5))/20 "my_col"
```

Examples

The simplest invocation of this routine generates a view *build_view* that represents the transformation query on *build_table* based on normalization definitions in the *norm_minmax_table*.

```
BEGIN
  DBMS_DATA_MINING_TRANSFORM.XFORM_NORM_LIN(
    'norm_minmax_table', 'build_table', 'build_view');
END;
```

XFORM_NORM_LIN Procedure

DBMS_DATAPUMP

The `DBMS_DATAPUMP` package is used to move all, or part of, a database between databases, including both data and metadata.

See Also: *Oracle Database Utilities* for more information on the concepts behind the `DBMS_DATAPUMP` API, how it works, and how it is implemented in the Data Pump Export and Import utilities

This chapter contains the following topics:

- [Using DBMS_DATAPUMP](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Types](#)
- [Summary of DBMS_DATAPUMP Subprograms](#)

Using DBMS_DATAPUMP

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Types](#)

Overview

The support and functionality provided by DBMS_DATAPUMP is as follows:

- The source and target databases can have different hardware, operating systems, character sets, and time zones.
- All object types and datatypes existing in Oracle Database 10g are supported.
- Data and metadata can be transferred between databases without using any intermediary files.
- A subset of a database can be moved based upon object type and names of objects.
- Schema names, datafile names, and tablespace names can be transformed at import time.
- Previously aborted export and import jobs can be restarted without duplicating or omitting any data or metadata from the original job.
- The resources applied to an export or import job can be modified.
- Data in an Oracle proprietary format can be unloaded and loaded.

Security Model

Security for the DBMS_DATAPUMP package is implemented through roles.

Roles

The existing EXP_FULL_DATABASE and IMP_FULL_DATABASE roles will be used to allow privileged users to take full advantage of the API. The Data Pump API will

use these roles to determine whether privileged application roles should be assigned to the processes comprising the job.

EXP_FULL_DATABASE

The `EXP_FULL_DATABASE` role affects only Export operations. It allows users running these operations to do the following:

- Perform the operation outside of the scope of their schema
- Monitor jobs that were initiated by another user
- Export objects (for example, TABLESPACE definitions) that unprivileged users cannot reference

Although the `SYS` schema does not have the `EXP_FULL_DATABASE` role assigned to it, all security checks performed by Data Pump that require the `EXP_FULL_DATABASE` role will also grant access to the `SYS` schema.

IMP_FULL_DATABASE

The `IMP_FULL_DATABASE` role affects only Import and `SQL_FILE` operations. It allows users running these operations to do the following:

- Perform the operation outside of the scope of their schema
- Monitor jobs that were initiated by another user
- Import objects (for example, DIRECTORY definitions) that unprivileged users cannot create

Although the `SYS` schema does not have the `IMP_FULL_DATABASE` role assigned to it, all security checks performed by Data Pump that require the `IMP_FULL_DATABASE` role will also grant access to the `SYS` schema.

Constants

There are several public constants defined for use with the `DBMS_DATAPUMP.GET_STATUS` procedure. All such constants are defined as part of the `DBMS_DATAPUMP` package. Any references to these constants must be prefixed by `DBMS_DATAPUMP.` and followed by the symbols in the following lists:

Mask Bit Definitions

The following mask bit definitions are used for controlling the return of data through the `DBMS_DATAPUMP.GET_STATUS` procedure.

- `KU$_STATUS_WIP` `CONSTANT BINARY_INTEGER := 1;`

- `KU$_STATUS_JOB_DESC` `CONSTANT BINARY_INTEGER := 2;`
- `KU$_STATUS_JOB_STATUS` `CONSTANT BINARY_INTEGER := 4;`
- `KU$_STATUS_JOB_ERROR` `CONSTANT BINARY_INTEGER := 8;`

Dump File Type Definitions

The following definitions are used for identifying types of dump files returned through the `DBMS_DATAPUMP.GET_STATUS` procedure.

- `KU$_DUMPFILTYPE_DISK` `CONSTANT BINARY_INTEGER := 0;`
- `KU$_DUMPFILTYPE_TEMPLATE` `CONSTANT BINARY_INTEGER := 3;`

Types

The types described in this section are defined in the `SYS` schema for use by the `GET_STATUS` function. *The way in which these types are defined and used may be different than what you are accustomed to. Be sure to read this section carefully.*

The collection of types defined for use with the `GET_STATUS` procedure are version-specific and include version information in the names of the types. Once introduced, these types will always be provided and supported in future versions of Oracle Database and will not change. However, in future releases of Oracle Database, new versions of these types might be created that provide new or different information. The new versions of these types will have different version information embedded in the type names.

For example, in Oracle Database 10g, release 1 (10.1), there is a `sys.ku$_Status1010` type, and in the next Oracle Database release, there could be a `sys.ku$_Status1110` type defined. Both types could be used with the `GET_STATUS` procedure.

Public synonyms have been defined for each of the types used with the `GET_STATUS` procedure. This makes it easier to use the types and means that you do not have to be concerned with changes to the actual type names or schemas where they reside. Oracle recommends that you use these synonyms whenever possible.

For each of the types, there is a version-specific synonym and a generic synonym. For example, the version-specific synonym `ku$_Status1010` is defined for the `sys.ku$_Status1010` type.

The generic synonym always describes the latest version of that type. For example, in Oracle Database 10g, release 1, the generic synonym `ku$_Status` is defined as

ku\$_Status1010. In a future release, there might be a ku\$_Status1110 synonym for sys.ku\$Status1110. Because the ku\$_Status generic synonym always points to the latest definition, it would now point to ku\$_Status1110 rather than to ku\$_Status1010.

The choice of whether to use version-specific synonyms or generic synonyms makes a significant difference in how you work. Using version-specific names protects your code from changes in future releases of Oracle Database because those types will continue to exist and be supported. However, access to new information will require code changes to use new synonym names for each of the types. Using the generic names implies that you always want the latest definition of the types and are prepared to deal with changes in different releases of Oracle Database.

When the version of Oracle Database that you are using changes, any C code that accesses types through generic synonym names will need to be recompiled.

Note: Languages other than PL/SQL must ensure that their type definitions are properly aligned with the version-specific definitions.

See Also: [GET_STATUS Procedure](#) on page 25-20 for additional information about how types are used

Worker Status Types

The worker status types describe what each worker process in a job is doing. The schema, object name, and object type of an object being processed will be provided. For workers processing user data, the partition name for a partitioned table (if any), the number of bytes processed in the partition, and the number of rows processed in the partition are also returned. Workers processing metadata provide status on the last object that was processed. No status for idle threads is returned.

The `percent_done` refers to the amount completed for the current data item being processed. It is not updated for metadata objects.

The worker status types are defined as follows:

```
CREATE TYPE sys.ku$_WorkerStatus1010 AS OBJECT (
worker_number      NUMBER,
process_name       VARCHAR2(30),
state              VARCHAR2(30),
schema             VARCHAR2(30),
name               VARCHAR2(4000),
```

```
object_type      VARCHAR2(200),
partition        VARCHAR2(30),
completed_objects NUMBER,
total_objects    NUMBER,
completed_rows   NUMBER,
completed_bytes  NUMBER,
percent_done     NUMBER )
/
CREATE PUBLIC SYNONYM ku$WorkerStatus1010 FOR sys.ku$WorkerStatus1010;
CREATE TYPE sys.ku$WorkerStatusList1010 AS TABLE OF sys.ku$WorkerStatus1010
/
CREATE PUBLIC SYNONYM ku$WorkerStatusList1010 FOR sys.ku$WorkerStatusList1010;
```

Log Entry and Error Types

These types provide informational and error text to attached clients and the log stream. The `ku$LogLine.errorNumber` type is set to `NULL` for informational messages but is specified for error messages. Each log entry may contain several lines of text messages.

The log entry and error types are defined as follows:

```
CREATE TYPE sys.ku$LogLine1010 AS OBJECT (
logLineNumber    NUMBER,
errorNumber      NUMBER,
LogText          VARCHAR2(2000) )
/
CREATE PUBLIC SYNONYM ku$LogLine1010 FOR sys.ku$LogLine1010;
CREATE TYPE sys.ku$LogEntry1010 AS TABLE OF sys.ku$LogLine1010
/
CREATE PUBLIC SYNONYM ku$LogEntry1010 FOR sys.ku$LogEntry1010;
```

Job Status Types

The job status type returns status about a job. Usually, the status concerns a running job but it could also be about a stopped job when a client attaches. It is typically requested at attach time, when the client explicitly requests status from interactive mode and every N seconds when the client has requested status periodically.

The job status types are defined as follows (`percent_done` applies to data only):

```
CREATE TYPE sys.ku$DumpFile1010 AS OBJECT (
file_name        VARCHAR2(4000),
file_type        NUMBER,
file_size        NUMBER,
file_bytes_written NUMBER)
```

```

CREATE TYPE sys.ku$_DumpFileSet1010 AS TABLE OF sys.ku$_DumpFile1010;

CREATE TYPE sys.ku$_JobStatus1010 AS OBJECT (
  job_name          VARCHAR2(30),
  operation         VARCHAR2(30),
  job_mode         VARCHAR2(30),
  bytes_processed  NUMBER,
  total_bytes      NUMBER,
  percent_done     NUMBER,
  degree          NUMBER,
  error_count     NUMBER,
  state          VARCHAR2(30),
  phase          NUMBER,
  restart_count  NUMBER,
  worker_status_list ku$_WorkerStatusList1010,
  files          ku$_DumpFileSet1010)

CREATE PUBLIC SYNONYM ku$_JobStatus1010
FOR sys.ku$_JobStatus1010;

```

Job Description Types

The job description type holds all the environmental information about the job such as parameter settings and dump file set members. There are a couple of subordinate types required as well.

The job description types are defined as follows:

```

CREATE TYPE sys.ku$_ParamValue1010 AS OBJECT (
  param_name  VARCHAR2(30),
  param_op   VARCHAR2(30),
  param_type  VARCHAR2(30),
  param_length NUMBER,
  param_value_n NUMBER,
  param_value_t VARCHAR2(2000) );

CREATE TYPE sys.ku$_ParamValues1010 AS TABLE OF sys.ku$_ParamValue1010;

CREATE TYPE sys.ku$_JobDesc1010 AS OBJECT (
  job_name  VARCHAR2(30),
  guid     RAW(16),
  operation VARCHAR2(30),
  job_mode VARCHAR2(30),
  remote_link VARCHAR2(4000),
  owner    VARCHAR2(30),

```

```
instance      VARCHAR2(16),
db_version    VARCHAR2(30),
creator_privs VARCHAR2(30),
start_time    DATE,
max_degree    NUMBER,
log_file      VARCHAR2(4000),
sql_file      VARCHAR2(4000),
params        ku$_ParamValues1010)
```

Status Types

The status type is an aggregate of some of the previous types defined and is the return value for the `GET_STATUS` call. The mask attribute indicates which types of information are being returned to the caller. It is created by a client's shadow process from information it retrieves off the status queue or directly from the master table.

For errors, the `ku$_LogEntry` that is returned has already had its log lines ordered for proper output. That is, the original `ku$_LogEntry` objects have been ordered from outermost context to innermost.

The status types are defined as follows:

```
CREATE TYPE sys.ku$_Status1010 AS OBJECT
(
  mask          NUMBER,          /* Indicates which status types are present*/
  wip           ku$_LogEntry1010, /* Work-In-Progress: std. exp/imp msgs */
  job_description ku$_JobDesc1010, /* Complete job description */
  job_status    ku$_JobStatus1010, /* Detailed job status + per-worker sts */
  error        ku$_LogEntry1010 /* Multi-level contextual errors */
)
```

Summary of DBMS_DATAPUMP Subprograms

Table 25–1 DBMS_DATAPUMP Package Subprograms

Subprogram	Description
ADD_FILE Procedure on page 25-10	Adds dump files to the dump file set for an Export, Import, or SQL_FILE operation. In addition to dump files, other types of files can also be added by using the FILETYPE parameter provided with this procedure
ATTACH Function on page 25-14	Used to gain access to a Data Pump job that is in the Defining, Executing, Idling, or Stopped state
DATA_FILTER Procedures on page 25-16	Specifies restrictions on the rows that are to be retrieved
DETACH Procedure on page 25-19	Specifies that the user has no further interest in using the handle
GET_STATUS Procedure on page 25-20	Monitors the status of a job or waits for the completion of a job or for more details on API errors
LOG_ENTRY Procedure on page 25-23	Inserts a message into the log file
METADATA_FILTER Procedure on page 25-25	Provides filters that allow you to restrict the items that are included in a job
METADATA_TRANSFORM Procedure on page 25-31	Specifies transformations to be applied to objects as they are processed in the specified job
METADATA_REMAP Procedure on page 25-28	Specifies a remapping to be applied to objects as they are processed in the specified job
OPEN Function on page 25-34	Declares a new job using the Data Pump API, the handle returned being used as a parameter for calls to all other procedures except ATTACH
SET_PARALLEL Procedure on page 25-38	Adjusts the degree of parallelism within a job
SET_PARAMETER Procedures on page 25-40	Specifies job-processing options
START_JOB Procedure on page 25-45	Begins or resumes execution of a job
STOP_JOB Procedure on page 25-47	Terminates a job, but optionally, preserves the state of the job

ADD_FILE Procedure

This procedure adds files to the dump file set for an Export, Import, or SQL_FILE operation or specifies the log file or the output file for a SQL_FILE operation.

Syntax

```
DBMS_DATAPUMP.ADD_FILE (
    handle      IN NUMBER,
    filename    IN VARCHAR2,
    directory   IN VARCHAR2,
    filesize    IN VARCHAR2 DEFAULT NULL,
    filetype    IN NUMBER DEFAULT DBMS_DATAPUMP.KU$_FILE_TYPE_DUMP_FILE);
```

Parameters

Table 25–2 ADD_FILE Procedure Parameters

Parameter	Description
handle	The handle of a job. The current session must have previously attached to the handle through an OPEN or ATTACH call.
filename	The name of the file being added. <code>filename</code> must be a simple filename without any directory path information. For dump files, the <code>filename</code> can include a substitution variable, <code>%U</code> , which indicates that multiple files may be generated with the specified <code>filename</code> as a template. The <code>%U</code> is expanded in the resulting file names into a two-character, fixed-width, incrementing integer starting at 01. For example, the dump filename of <code>export%U</code> would cause <code>export01</code> , <code>export02</code> , <code>export03</code> , ... to be created depending on how many files are needed to perform the export. For filenames containing the <code>%</code> character, the <code>%</code> must be represented as <code>%%</code> to avoid ambiguity. Any <code>%</code> in a filename must be followed by either a <code>%</code> or a <code>U</code> .
directory	The name of a directory object within the database that is used to locate <code>filename</code> . A <code>directory</code> must be specified. See the Data Pump Export chapter in <i>Oracle Database Utilities</i> for information about the <code>DIRECTORY</code> command-line parameter.

Table 25–2 (Cont.) ADD_FILE Procedure Parameters

Parameter	Description
filesize	The size of the dump file that is being added. It may be specified as the number of bytes, number of kilobytes (if followed by K), number of megabytes (if followed by M) or number of gigabytes (if followed by G). An Export operation will write no more than the specified number of bytes to the file. Once the file is full, it will be closed. If there is insufficient space on the device to write the specified number of bytes, the Export operation will fail, but it can be restarted. If not specified, filesize will default to an unlimited size. For Import and SQL_FILE operations, filesize is ignored. The minimum value for filesize is ten times the default Data Pump block size, which is 4 kilobytes. filesize may only be specified for dump files.
filetype	The type of the file to be added. The legal values are as follows and must be preceded by DBMS_DATAPUMP.: <ul style="list-style-type: none"> ■ KUS_FILE_TYPE_DUMP_FILE (dump file for a job) ■ KUS_FILE_TYPE_LOG_FILE (log file for a job) ■ KUS_FILE_TYPE_SQL_FILE (output for SQL_FILE job)

Exceptions

- INVALID_HANDLE. The specified handle is not attached to a Data Pump job.
- INVALID_ARGVAL. An invalid value was supplied for an input parameter.
- INVALID_STATE. The job is completing, or the job is past the defining state for an import or SQL_FILE job or is past the defining state for LOG and SQL files.
- FILE_ERROR. Oracle does not have the requested operating system access to the specified file or the file has already been specified for the current operation.
- INVALID_OPERATION. A dump file was specified for a Network Import or ESTIMATE_ONLY export operation.
- SUCCESS_WITH_INFO. The procedure succeeded, but further information is available through the GET_STATUS procedure.
- NO_SUCH_JOB. The specified job does not exist.

Usage Notes

- Adds files to a Data Pump job. Three types of files may be added to jobs: Dump files to contain the data that is being moved, log files to record the messages associated with an operation, and SQL files to record the output of a SQL_FILE

operation. Log and SQL files will overwrite previously existing files. Dump files will never overwrite previously existing files. Instead, an error will be generated.

- Import and SQL_FILE operations require that all dump files be specified during the definition phase of the job. For Export operations, dump files can be added at any time. For example, if the user ascertains that the file space is running low during an Export, additional dump files may be added through this API. If the specified dump file already exists for an Export operation, an error will be returned.
- For Export operations, the parallelism setting should be less than or equal to the number of dump files in the dump file set. If there are not enough dump files, the job will not be able to maximize parallelism to the degree specified by the SET_PARALLEL procedure.
- For Import operations, the parallelism setting should also be less than or equal to the number of dump files in the dump file set. If there are not enough dump files, the performance will not be optimal as multiple threads of execution try to access the same dump file.
- If the substitution variable (%U) is included in a filename, multiple dump files may be specified through a single call to ADD_FILE. For Export operations, the new dump files will be created as they are needed. Enough dump files will be created to allow all of the processes specified by the current SET_PARALLEL value to be active. If one of the dump files fills, it will be closed and a new dump file (with a new generated name) will be created to take its place. If multiple ADD_FILES with substitution variables have been specified for dump files in a job, they will be used to generate dump files in a round robin fashion. For example, if `expa%U`, `expb%U` and `expc%U` were all specified for a job having a parallelism of 6, the initial dump files created would look like: `expa01`, `expb01`, `expc01`, `expa02`, `expb02`, and `expc02`.
- If presented with dump file specifications, `expa%U`, `expb%U` and `expc%U`, an Import or SQL_FILE operation will begin by attempting to open the dump files, `expa01`, `expb01`, and `expc01`. If the dump file containing the master table is not found in this set, the operation will expand its search for dump files by incrementing the substitution variable and looking up the new filenames (for example, `expa02`, `expb02`, and `expc02`). The DataPump API will keep expanding the search until it locates the dump file containing the master table. If the DataPump API determines that the dump file does not exist or is not part of the current dump set at any iteration, the DataPump API will stop incrementing the substitution variable for the dump file specification that was

in error. Once the master table is found, the master table will be used to ascertain when all of dump files in the dump file set have been located.

ATTACH Function

This function gains access to a previously-created job.

Syntax

```
DBMS_DATAPUMP.ATTACH(  
    job_name     IN VARCHAR2 DEFAULT NULL,  
    job_owner    IN VARCHAR2 DEFAULT NULL)  
RETURN NUMBER;
```

Parameters

Table 25–3 *ATTACH Function Parameters*

Parameter	Description
job_name	The name of the job. The default is the job name owned by the user who is specified in the job_owner parameter (assuming that user has only one job in the Defining, Executing, or Idling states).
job_owner	The user who originally started the job. If NULL, the value defaults to the owner of the current session. To specify a job owner other than yourself, you must have either the EXP_FULL_DATABASE role (for export operations) or the IMP_FULL_DATABASE role (for import and SQL_FILE operations). Being a privileged user allows you to monitor another user's job, but you cannot restart another user's job.

Return Values

An opaque handle for the job. This handle is used as input to the following procedures: ADD_FILE, DATA_FILTER, DETACH, STOP_JOB, GET_STATUS, LOG_ENTRY, METADATA_FILTER, METADATA_REMAP, METADATA_TRANSFORM, SET_PARALLEL, and START_JOB.

Exceptions

- INVALID_ARGVAL. An invalid value was supplied for an input parameter.
- SUCCESS_WITH_INFO. The procedure succeeded, but further information is available through the GET_STATUS procedure.
- NO_SUCH_JOB. The specified job does not exist.
- INVALID_OPERATION. The specified operation is not valid in this context.

Usage Notes

- If the job was in the Stopped state, the job is placed into the Idling state. Once the `ATTACH` succeeds, you can monitor the progress of the job or control the job. The stream of `KU$_STATUS_WIP` and `KU$_STATUS_JOB_ERROR` messages returned through the `GET_STATUS` procedure will be returned to the newly attached job starting at the approximate time of the client's attachment. There will be no repeating of status and error messages that were processed before the client attached to a job.
- If you want to perform a second attach to a job, you must do so from a different session.
- If the `ATTACH` fails, use a null handle in a subsequent call to `GET_STATUS` for more information about the failure.

DATA_FILTER Procedures

This procedure specifies restrictions on the rows that are to be retrieved.

Syntax

```
DBMS_DATAPUMP.DATA_FILTER (
    handle      IN NUMBER,
    name        IN VARCHAR2,
    value       IN NUMBER,
    table_name  IN VARCHAR2 DEFAULT NULL,
    schema_name IN VARCHAR2 DEFAULT NULL);
```

```
DBMS_DATAPUMP.DATA_FILTER(
    handle      IN NUMBER,
    name        IN VARCHAR2,
    value       IN VARCHAR2,
    table_name  IN VARCHAR2 DEFAULT NULL,
    schema_name IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 25–4 DATA_FILTER Procedure Parameters

Parameter	Description
handle	The handle that is returned from the OPEN procedure.
name	The name of the filter.
value	The value of the filter.
table_name	The name of the table on which the data filter is applied. If no table name is supplied, the filter applies to all tables in the job.
schema_name	The name of the schema that owns the table on which the filter is applied. If no schema name is specified, the filter applies to all schemas in the job. If you supply a schema name you must also supply a table name.

Exceptions

- INVALID_HANDLE. The specified handle is not attached to a Data Pump job.
- INVALID_ARGVAL. There can be several reasons for this message:
 - A bad filter name is specified

- The mode is `TRANSPORTABLE`, which does not support data filters
- The specified table does not exist
- The filter has already been set for the specified values of `schema_name` and `table_name`
- `INVALID_STATE`. The user called `DATA_FILTER` when the job was not in the Defining state.
- `INCONSISTENT_ARGS`. The `value` parameter is missing or its datatype does not match the filter name. Or a schema name was supplied, but not a table name.
- `PRIVILEGE_ERROR`. A schema name was supplied, but the user did not have the `EXP_FULL_DATABASE` or `IMP_FULL_DATABASE` role.
- `SUCCESS_WITH_INFO`. The procedure succeeded, but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- Each data filter can only appear once in each table (for example, you cannot supply multiple `SUBQUERY` filters to a table) or once in each job. If different filters using the same `name` are applied to both a particular table and to the whole job, the filter parameter supplied for the specific table will take precedence.

With the exception of the `INCLUDE_ROWS` filter, data filters are not supported on tables having nested tables or domain indexes defined upon them. Data filters are not supported in jobs performed in Transportable Tablespace mode.

The available data filters are described in [Table 25-5](#).

Table 25-5 Data Filters

Name	Datatype	Operations that Support Filter	Description
<code>INCLUDE_ROWS</code>	number	<code>EXPORT</code> , <code>IMPORT</code>	If nonzero, this filter specifies that user data for the specified table should be included in the job. The default is 1.

Table 25–5 (Cont.) Data Filters

Name	Datatype	Operations that Support Filter	Description
PARTITION_ EXPR	text	EXPORT, IMPORT	<p>For Export jobs, this filter specifies which partitions are unloaded from the database. For Import jobs, it specifies which table partitions are loaded into the database. Partition names are included in the job if their names satisfy the specified expression. Double quotation marks around partition names are required only if the partition names contain special characters.</p> <p>PARTITION_EXPR is not supported on jobs across a network link.</p> <p>Default=All partitions are processed.</p>
SUBQUERY	text	EXPORT, IMPORT	<p>Specifies a subquery that is added to the end of the SELECT statement for the table. If you specify a WHERE clause in the subquery, you can restrict the rows that are selected. Specifying an ORDER BY clause orders the rows dumped in the export which improves performance when migrating from heap-organized tables to index-organized tables.</p>

DETACH Procedure

This procedure specifies that the user has no further interest in using the handle.

Syntax

```
DBMS_DATAPUMP.DETACH(
    handle IN NUMBER);
```

Parameters

Table 25–6 *DETACH Procedure Parameters*

Parameter	Description
handle	The handle of the job. The current session must have previously attached to the handle through an <code>OPEN</code> or <code>ATTACH</code> call.

Exceptions

- `INVALID_HANDLE`. The specified handle is not attached to a Data Pump job.
- `SUCCESS_WITH_INFO`. The procedure succeeded, but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- Through this call, you specify that you have no further interest in using the handle. Resources associated with a completed job cannot be reclaimed until all users are detached from the job. An implicit detach from a handle is performed when the user's session is exited or aborted. An implicit detach from a handle is also performed upon the expiration of the timeout associated with a `STOP_JOB` that was applied to the job referenced by the handle. All previously allocated `DBMS_DATAPUMP` handles are released when an instance is restarted.

GET_STATUS Procedure

This procedure monitors the status of a job or wait for the completion of a job.

Syntax

```
DBMS_DATAPUMP.GET_STATUS(
  handle      IN NUMBER,
  mask        IN BINARY_INTEGER,
  timeout     IN NUMBER DEFAULT NULL,
  job_state   OUT VARCHAR2,
  status      OUT ku$_Status1010);
```

Parameters

Table 25–7 GET_STATUS Procedure Parameters

Parameter	Description
handle	The handle of a job. The current session must have previously attached to the handle through an <code>OPEN</code> or <code>ATTACH</code> call. A null handle can be used to retrieve error information after <code>OPEN</code> and <code>ATTACH</code> failures.
mask	A bit mask that indicates which of four types of information to return: <ul style="list-style-type: none"> ▪ <code>KU\$_STATUS_WIP</code> ▪ <code>KU\$_STATUS_JOB_DESC</code> ▪ <code>KU\$_STATUS_JOB_STATUS</code> ▪ <code>KU\$_STATUS_JOB_ERROR</code> Each status has a numerical value. You can request multiple types of information by adding together different combinations of values. See Types on page 25-4.
timeout	Maximum number of seconds to wait before returning to the user. A value of 0 requests an immediate return. A value of -1 requests an infinite wait. If <code>KU\$_STATUS_WIP</code> or <code>KU\$_STATUS_JOB_ERROR</code> information is requested and becomes available during the timeout period, then the procedure returns before the timeout period is over.
job_state	Current state of the job. If only job state is needed, it is much more efficient to use this parameter than to retrieve the full <code>ku\$_Status1010</code> structure.

Table 25–7 (Cont.) GET_STATUS Procedure Parameters

Parameter	Description
status	A ku\$_Status is returned. The ku\$_Status mask indicates what kind of information is included. This could be none if only KU\$_STATUS_WIP or KU\$_STATUS_JOB_ERROR information is requested and the timeout period expires.

Exceptions

- INVALID_HANDLE. The specified handle is not attached to a Data Pump job.
- INVALID_VALUE. The mask or timeout contains an illegal value.
- SUCCESS_WITH_INFO. The procedure succeeded, but further information is available through the GET_STATUS procedure.
- NO_SUCH_JOB. The specified job does not exist.

Usage Notes

The GET_STATUS procedure is used to monitor the progress of an ongoing job and to receive error notification. You can request various type of information using the mask parameter. The KU\$_STATUS_JOB_DESC and KU\$_STATUS_JOB_STATUS values are classified as synchronous information because the information resides in the master table. The KU\$_STATUS_WIP and KU\$_STATUS_JOB_ERROR values are classified as asynchronous because the messages that embody these types of information can be generated at any time by various layers in the Data Pump architecture.

- If synchronous information *only* is requested, the timeout is ignored.
- If asynchronous information is requested, the interface will wait a *maximum* of timeout seconds before returning to the client. If a message of the requested asynchronous information type is received, the call will complete prior to timeout seconds. If synchronous information was also requested, it will be returned whenever the procedure returns.
- The job state is always returned, as long as it can be determined.

Error Handling

There are two types of error scenarios that need to be handled using the GET_STATUS procedure:

- Errors resulting from other procedure calls: For example, the `SET_PARAMETER` procedure may produce an `INCONSISTENT_ARGS` exception. The client should immediately call `GET_STATUS` with `mask=8` (errors) and `timeout=0`. The returned `ku$_Status.error` will contain a `ku$_LogEntry` that describes the inconsistency in more detail.
- Errors resulting from events asynchronous to the client(s): An example might be `Table already exists` when trying to create a table. The `ku$_Status.error` will contain a `ku$_LogEntry` with all error lines (from all processing layers that added context about the error) properly ordered.

After a job has begun, a client's main processing loop will typically consist of a call to `GET_STATUS` with an infinite timeout (-1) "listening" for `KU$_STATUS_WIP` and `KU$_STATUS_JOB_ERROR` messages. If status was requested, then `JOB_STATUS` information will also be in the request.

When the `ku$_Status` is interpreted, the following guidelines should be used:

- `ku$_Status.ku$_JobStatus.percent_done` refers only to the amount of data that has been processed in a job. Metadata is not considered in the calculation. It is determined using the following formulas:
 - `EXPORT` or `network IMPORT`-- $(\text{bytes_processed}/\text{estimated_bytes}) * 100$
 - `IMPORT`-- $(\text{bytes_processed}/\text{total_expected_bytes}) * 100$
 - `SQL_FILE` or `estimate-only EXPORT`--0.00 if not done or 100.00 if done

The effects of the `QUERY` and `PARTITION_EXPR` data filters are not considered in computing `percent_done`.

It is expected that the status returned will be transformed by the caller into more user-friendly status. For example, when percent done is not zero, an estimate of completion time could be produced using the following formula:

```
((SYSDATE - start time) / ku$_Status.ku$_JobStatus.percent_done) * 100
```

- The caller should not use `ku$_Status.ku$_JobStatus.percent_done` for determining whether the job has completed. Instead, the caller should only rely on the state of the job as found in `job_state`.

LOG_ENTRY Procedure

This procedure inserts a message into the log file.

Syntax

```
DBMS_DATAPUMP.LOG_ENTRY(
    handle IN NUMBER,
    message IN VARCHAR2
    log_file_only IN NUMBER DEFAULT 0);
```

Parameters

Table 25–8 LOG_ENTRY Procedure Parameters

Parameter	Description
handle	The handle of a job. The current session must have previously attached to the handle through an OPEN or ATTACH call.
message	A text line to be added to the log file.
log_file_only	Specified text should be written only to the log file. It should not be returned in GET_STATUS work-in-progress (KUS_STATUS_WIP) messages.

Exceptions

- INVALID_HANDLE. The specified handle is not attached to a Data Pump job.
- SUCCESS_WITH_INFO. The procedure succeeded, but further information is available through the GET_STATUS procedure.
- NO_SUCH_JOB. The specified job does not exist.

Usage Notes

The message is added to the log file. If `log_file_only` is zero (the default), the message is also broadcast as a `KUS_STATUS_WIP` message through the `GET_STATUS` procedure to all users attached to the job.

The `LOG_ENTRY` procedure allows applications to tailor the log stream to match the abstractions provided by the application. For example, the command-line interface supports `INCLUDE` and `EXCLUDE` parameters defined by the user. Identifying these values as calls to the underlying `METADATA_FILTER` procedure would be

confusing to users. Instead, the command-line interface can enter text into the log describing the settings for the `INCLUDE` and `EXCLUDE` parameters.

Lines entered in the log stream from `LOG_ENTRY` are prefixed by the string, "`;;;` "

METADATA_FILTER Procedure

This procedure provides filters that allow you to restrict the items that are included in a job.

Syntax

```
DBMS_DATAPUMP.METADATA_FILTER(
  handle      IN NUMBER,
  name        IN VARCHAR2,
  value       IN VARCHAR2,
  object_path IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 25–9 *METADATA_FILTER Procedure Parameters*

Parameter	Description
handle	The handle returned from the OPEN procedure.
name	The name of the filter. See Table 25–10 for descriptions of the available filters.
value	The value of the filter.
object_path	The object path to which the filter applies. If the default is used, the filter applies to all applicable objects. Lists of the object paths supported for each mode are contained in the catalog views for DATABASE_EXPORT_OBJECTS, SCHEMA_EXPORT_OBJECTS, and TABLE_EXPORT_OBJECTS. (Note that the TABLE_EXPORT_OBJECTS view is applicable to both Table and Tablespace mode because their object paths are the same.) For an import operation, object paths reference the mode used to create the dump file rather than the mode being used for the import.

[Table 25–10](#) describes the name, object type, datatype, operations that support the filter, and the meaning of the filters available with the METADATA_FILTER procedure. The datatype for all the filters is a text expression. All operations support all filters.

Table 25–10 Filters Provided by METADATA_FILTER Procedure

Name	Object Type	Meaning
INCLUDE_ NAME_EXPR and EXCLUDE_ NAME_EXPR	Named objects	Defines which object names are included in (INCLUDE_ NAME_EXPR), or excluded from (EXCLUDE_NAME_EXPR), the job. You use the <code>object_type</code> parameter to limit the filter to a particular object type. For Table mode, identifies which tables are to be processed.
SCHEMA_EXPR	Schema objects	Restricts the job to objects whose owning schema name is satisfied by the expression. For Table mode, only a single SCHEMA_EXPR filter is supported. If specified, it must only specify a single schema (for example, 'IN ('SCOTT')'). For Schema mode, identifies which users are to be processed.
TABLESPACE_ EXPR	TABLE, CLUSTER, INDEX, ROLLBACK_ SEGMENT	Restricts the job to objects stored in a tablespace whose name is satisfied by the expression. For Tablespace mode, identifies which tablespaces are to be processed. If a partition of an object is stored in the tablespace, the entire object is added to the job. For Transportable mode, identifies which tablespaces are to be processed. If a table has a single partition in the tablespace set, all partitions must be in the tablespace set. An index is not included within the tablespace set unless all of its partitions are in the tablespace set. A domain index is not included in the tablespace set unless all of its secondary objects are included in the tablespace set.
INCLUDE_ PATH_EXPR and EXCLUDE_ PATH_EXPR	All	Defines which object paths are included in, or excluded from, the job. You use these filters to select only certain object types from the database or dump file set. Objects of paths satisfying the condition are included (INCLUDE_PATH_EXPR) or excluded (EXCLUDE_PATH_ EXPR) from the operation. The <code>object_path</code> parameter is not supported for these filters.

Exceptions

- INVALID_HANDLE. The specified handle is not attached to a Data Pump job.
- INVALID_ARGVAL. This exception can indicate any of the following conditions:
 - An `object_path` was specified for an INCLUDE_PATH_EXPR or EXCLUDE_PATH_EXPR filter.

- The specified `object_path` is not supported for the current mode.
- The `SCHEMA_EXPR` filter specified multiple schemas for a Table mode job.
- `INVALID_STATE`. The user called the `METADATA_FILTER` procedure after the job left the defining state.
- `INCONSISTENT_ARGS`. The filter value is of the wrong datatype or is missing.
- `SUCCESS_WITH_INFO`. The procedure succeeded but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- Metadata filters identify a set of objects to be included or excluded from a Data Pump operation. Except for `EXCLUDE_PATH_EXPR` and `INCLUDE_PATH_EXPR`, dependent objects of an identified object will be processed along with the identified object. For example, if an index is identified for inclusion by a filter, grants upon that index will also be included by the filter. Likewise, if a table is excluded by a filter, then indexes, constraints, grants and triggers upon the table will also be excluded by the filter.
- Filters allow a user to restrict the items that are included in a job. For example, a user could request a full export, but without Package Specifications or Package Bodies.
- If multiple filters are specified for a object type, they are implicitly 'ANDed' together (that is, objects participating in the job must pass all of the filters applied to their object types).
- The same filter name can be specified multiple times within a job. For example, specifying `NAME_EXPR` as `'!='EMP''` and `NAME_EXPR` as `'!='DEPT''` on a TABLE-mode export would produce a file set containing all of the tables except for `EMP` and `DEPT`.

METADATA_REMAP Procedure

This procedure specifies a remapping to be applied to objects as they are processed in the specified job.

Syntax

```
DBMS_DATAPUMP.METADATA_REMAP (
    handle      IN NUMBER,
    name        IN VARCHAR2,
    old_value   IN VARCHAR2,
    value       IN VARCHAR2,
    object_type IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 25–11 METADATA_REMAP Procedure Parameters

Parameter	Description
handle	The handle for the current job. The current session must have previously attached to the handle through a call to the OPEN procedure.
name	The name of the remap. See Table 25–12 for descriptions of the available remaps.
old_value	Specifies which value in the dump file set should be reset to value.
value	The value of the parameter for the remap. This signifies the new value that old_value should be translated into.
object_type	Designates the object type to which the remap applies. The list of object types supported for each mode are contained in the DATABASE_EXPORT_OBJECTS, SCHEMA_EXPORT_OBJECTS, TABLE_EXPORT_OBJECTS, and TABLESPACE_EXPORT_OBJECTS catalog views. By default, the remap applies to all applicable objects within the job. The object_type parameter allows a caller to specify different parameters for different object types within a job. Remaps that explicitly specify an object type override remaps that apply to all object types.

[Table 25–12](#) describes the remaps provided by the METADATA_REMAP procedure.

Table 25–12 Remaps Provided by the METADATA_REMAP Procedure

Name	Datatype	Object Type	Meaning
REMAP_ SCHEMA	Text	Schema objects	Any schema object in the job that matches the <code>object_type</code> parameter and was located in the <code>old_value</code> schema will be moved to the <code>value</code> schema.
REMAP_ TABLESPACE	Text	TABLE, INDEX, ROLLBACK_ SEGMENT, MATERIALIZED_ VIEW, MATERIALIZED_ VIEW_ LOG, TABLE_ SPACE	Any storage segment in the job that matches the <code>object_type</code> parameter and was located in the <code>old_value</code> tablespace will be relocated to the <code>value</code> tablespace.
REMAP_ DATAFILE	Text	LIBRARY, TABLESPACE, DIRECTORY	Any datafile reference in the job that matches the <code>object_type</code> parameter and referenced the <code>old_value</code> datafile will be redefined to use the <code>value</code> datafile.

Exceptions

- `INVALID_HANDLE`. The specified handle is not attached to a Data Pump job.
- `INVALID_ARGVAL`. This message can indicate any of the following:
 - The job's mode does not include the specified `object_type`.
 - The remap has already been specified for the specified `old_value` and `object_type`.
- `INVALID_OPERATION`. Remaps are only supported for `SQL_FILE` and Import operations. The job's operation was Export, which does not support the use of metadata remaps.
- `INVALID_STATE`. The user called `METADATA_REMAP` after the job had started (that is, the job was not in the defining state).
- `INCONSISTENT_ARGS`. There was no `value` supplied or it was of the wrong datatype for the remap.
- `SUCCESS_WITH_INFO`. The procedure succeeded, but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- The `METADATA_REMAP` procedure is only supported for `Import` and `SQL_FILE` operations. It enables you to apply commonly desired, predefined remappings to the definition of objects as part of the transfer. If you need remaps that are not supported within this procedure, you should do a preliminary `SQL_FILE` operation to produce a SQL script corresponding to the dump file set. By editing the DDL directly and then executing it, you can produce any remappings that you need.
- Transforms for the DataPump API are a subset of the remaps implemented by the `DBMS_METADATA.SET_TRANSFORM_PARAMETER` API. Multiple remaps can be defined for a single job. However, each remap defined must be unique according its parameters. That is, two remaps cannot specify conflicting or redundant remaps.

METADATA_TRANSFORM Procedure

This procedure specifies transformations to be applied to objects as they are processed in the specified job.

Syntax

```
DBMS_DATAPUMP.METADATA_TRANSFORM (
    handle      IN NUMBER,
    name        IN VARCHAR2,
    value       IN VARCHAR2,
    object_type IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 25–13 *METADATA_TRANSFORM Procedure Parameters*

Parameter	Description
handle	The handle for the current job. The current session must have previously attached to the handle through a call to the <code>OPEN</code> procedure.
name	The name of the transformation. See Table 25–14 for descriptions of the available transforms.
value	The value of the parameter for the transform.
object_type	Designates the object type to which the transform applies. The list of object types supported for each mode are contained in the <code>DATABASE_EXPORT_OBJECTS</code> , <code>SCHEMA_EXPORT_OBJECTS</code> , <code>TABLE_EXPORT_OBJECTS</code> , and <code>TABLESPACE_EXPORT_OBJECTS</code> catalog views. By default, the transform applies to all applicable objects within the job. The <code>object_type</code> parameter allows a caller to specify different transform parameters for different object types within a job. Transforms that explicitly specify an object type override transforms that apply to all object types.

[Table 25–14](#) describes the transforms provided by the `METADATA_TRANSFORM` procedure.

Table 25–14 *Transforms Provided by the METADATA_TRANSFORM Procedure*

Name	Datatype	Object Type	Meaning
SEGMENT_ATTRIBUTES	NUMBER	TABLE, INDEX	If nonzero (TRUE), emit storage segment parameters. Defaults to 1.

Table 25–14 (Cont.) Transforms Provided by the METADATA_TRANSFORM Procedure

Name	Datatype	Object Type	Meaning
STORAGE	NUMBER	TABLE	If nonzero (TRUE), emit storage clause. (Ignored if SEGMENT_ATTRIBUTES is zero.) Defaults to nonzero (TRUE).

Exceptions

- **INVALID_HANDLE.** The specified handle is not attached to a Data Pump job.
- **INVALID_ARGVAL.** This message can indicate any of the following:
 - The mode is transportable, which doesn't support transforms.
 - The job's mode does not include the specified `object_type`.
 - The transform has already been specified for the specified `value` and `object_type`.
- **INVALID_OPERATION.** Transforms are only supported for SQL_FILE and Import operations. The job's operation was Export which does not support the use of metadata transforms.
- **INVALID_STATE.** The user called METADATA_TRANSFORM after the job had started (that is, the job was not in the defining state).
- **INCONSISTENT_ARGS.** There was no `value` supplied or it was of the wrong datatype for the transform.
- **SUCCESS_WITH_INFO.** The procedure succeeded, but further information is available through the GET_STATUS procedure.
- **NO_SUCH_JOB.** The specified job does not exist.

Usage Notes

- The METADATA_TRANSFORM procedure is only supported for Import and SQL_FILE operations. It enables you to apply commonly desired, predefined transformations to the definition of objects as part of the transfer. If you need transforms that are not supported within this procedure, you should do a preliminary SQL_FILE operation to produce a SQL script corresponding to the dump file set. By editing the DDL directly and then executing it, you can produce any transformations that you need.
- Transforms for the DataPump API are a subset of the transforms implemented by the DBMS_METADATA.SET_TRANSFORM_PARAMETER API. Multiple

transforms can be defined for a single job. However, each transform defined must be unique according its parameters. That is, two transforms cannot specify conflicting or redundant transformations.

OPEN Function

This function is used to declare a new job using the Data Pump API. The handle that is returned is used as a parameter for calls to all other procedures except ATTACH.

Syntax

```
DBMS_DATAPUMP.OPEN (  
    operation    IN VARCHAR2,  
    mode         IN VARCHAR2,  
    remote_link  IN VARCHAR2 DEFAULT NULL,  
    job_name     IN VARCHAR2 DEFAULT NULL,  
    version      IN VARCHAR2 DEFAULT 'COMPATIBLE')  
RETURN NUMBER;
```

Parameters

Table 25–15 OPEN Function Parameters

Parameter	Meaning
operation	The type of operation to be performed. Table 25–16 contains descriptions of valid operation types.
mode	The scope of the operation to be performed. Table 25–17 contains descriptions of valid modes. Specifying NULL generates an error.
remote_link	If the value of this parameter is non-null, it provides the name of a database link to the remote database that will be the source of data and metadata for the current job.

Table 25–15 (Cont.) OPEN Function Parameters

Parameter	Meaning
job_name	<p>The name of the job. The name is limited to 30 characters; it will be truncated if more than 30 characters are used. It may consist of printable characters and spaces. It is implicitly qualified by the schema of the user executing the OPEN procedure and must be unique to that schema (that is, there cannot be other Data Pump jobs using the same name).</p> <p>The name is used to identify the job both within the API and with other database components such as identifying the job in the DBA_RESUMABLE view if the job becomes suspended through lack of resources. If no name is supplied, a system generated name will be provided for the job in the following format: "SYS_<OPERATION>_<MODE>_%N".</p> <p>The default job name is formed where %N expands to a two-digit incrementing integer starting at '01' (for example, "SYS_IMPORT_FULL_03"). The name supplied for the job will also be used to name the master table and other resources associated with the job.</p>
version	<p>The version of database objects to be extracted. This option is only valid for Export, network Import, and SQL_FILE operations. Database objects or attributes that are incompatible with the version will not be extracted. Legal values for this parameter are as follows:</p> <ul style="list-style-type: none"> ▪ COMPATIBLE - (default) the version of the metadata corresponds to the database compatibility level and the compatibility release level for feature (as given in the V\$COMPATIBILITY view). Database compatibility must be set to 9.2 or higher. ▪ LATEST - the version of the metadata corresponds to the database version. ▪ A specific database version, for example, '10.0.0'. In Oracle Database10g, this value cannot be lower than 10.0.0.

[Table 25–16](#) describes the valid operation types for the OPEN procedure.

Table 25–16 Valid Operation Types for the OPEN Procedure

Operation	Description
EXPORT	Saves data and metadata to a dump file set or obtains an estimate of the size of the data for an operation.
IMPORT	Restores data and metadata from a dump file set or across a database link.

Table 25–16 (Cont.) Valid Operation Types for the OPEN Procedure

Operation	Description
SQL_FILE	Displays the metadata within a dump file set, or from across a network link, as a SQL script. The location of the SQL script is specified through the ADD_FILE procedure.

Table 25–17 describes the valid modes for the OPEN procedure.

Table 25–17 Valid Modes for the OPEN Procedure

Mode	Description
FULL	Operates on the full database or full dump file set except for the SYS, XDB, ORDSYS, MDSYS, CTXSYS, ORDPLUGINS, and LBACSYS schemas.
SCHEMA	Operates on a set of selected schemas. Defaults to the schema of the current user. All objects in the selected schemas are processed. Users cannot specify SYS, XDB, ORDSYS, MDSYS, CTXSYS, ORDPLUGINS, or LBACSYS schemas for this mode.
TABLE	Operates on a set of selected tables. Defaults to all of the tables in the current user's schema. Only tables and their dependent objects are processed.
TABLESPACE	Operates on a set of selected tablespaces. No defaulting is performed. Tables that have storage in the specified tablespaces are processed in the same manner as in Table mode.
TRANSPORTABLE	Operates on metadata for tables (and their dependent objects) within a set of selected tablespaces to perform a transportable tablespace export/import.

Return Values

- An opaque handle for the job. This handle is used as input to the following procedures: SET_PARALLEL, ADD_FILE, DETACH, STOP_JOB, GET_STATUS, LOG_ENTRY, METADATA_FILTER, DATA_FILTER, METADATA_TRANSFORM, METADATA_REMAP, SET_PARAMETER, and START_JOB.

Exceptions

- INVALID_ARGVAL. An invalid operation or mode was specified. A NULL or invalid value was supplied for an input parameter. The error message text identifies the parameter.

- `JOB_EXISTS`. A table already exists with the specified job name.
- `PRIVILEGE_ERROR`. The user does not have the necessary privileges or roles to use the specified mode.
- `INTERNAL_ERROR`. The job was created under the wrong schema or the master table was of the wrong format.
- `SUCCESS_WITH_INFO`. The procedure succeeded, but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- When the job is created, a master table is created for the job under the caller's schema within the caller's default tablespace. A handle referencing the job is returned that attaches the current session to the job. Once attached, the handle remains valid until either an explicit or implicit detach occurs. The handle is only valid in the caller's session. Other handles can be attached to the same job from a different session by using the `ATTACH` procedure.
- If the `OPEN` fails, call `GET_STATUS` with a null handle to retrieve additional information about the failure.

SET_PARALLEL Procedure

This procedure adjusts the degree of parallelism within a job.

Syntax

```
DBMS_DATAPUMP.SET_PARALLEL(  
    handle      IN NUMBER,  
    degree      IN NUMBER);
```

Parameters

Table 25–18 *SET_PARALLEL Procedure Parameters*

Parameter	Description
handle	The handle of a job. The current session must have previously attached to the handle through an OPEN or ATTACH call.
degree	The maximum number of worker processes that can be used for the job. You use this parameter to adjust the amount of resources used for a job.

Exceptions

- **INVALID_HANDLE.** The specified handle is not attached to a Data Pump job.
- **INVALID_OPERATION.** The SET_PARALLEL procedure is only valid for export and import operations.
- **INVALID_ARGVAL.** An invalid value was supplied for an input parameter.
- **SUCCESS_WITH_INFO.** The procedure succeeded, but further information is available through the GET_STATUS procedure.
- **NO_SUCH_JOB.** The specified job does not exist.

Usage Notes

- The SET_PARALLEL procedure is only available in the Enterprise Edition of the Oracle database.
- The SET_PARALLEL procedure can be executed by any session attached to a job. The job must be in one of the following states: Defining, Idling, or Executing.

- The effect of decreasing the degree of parallelism may be delayed because ongoing work needs to find an orderly completion point before `SET_PARALLEL` can take effect.
- Decreasing the parallelism will not result in fewer worker processes associated with the job. It will only decrease the number of worker processes that will be executing at any given time.
- Increasing the parallelism will take effect immediately if there is work that can be performed in parallel.
- The degree of parallelism requested by a user may be decreased based upon settings in the resource manager or through limitations introduced by the `PROCESSES` or `SESSIONS` initialization parameters in the `init.ora` file.
- To parallelize an Export job to a degree of n , the user should supply n files in the dump file set or specify a substitution variable in a file specification. Otherwise, some of the worker processes will be idle while waiting for files.
- `SQL_FILE` operations always operate with a degree of 1. Jobs running in the Transportable mode always operate with a degree of 1.

SET_PARAMETER Procedures

This procedure is used to specify job-processing options.

Syntax

```
DBMS_DATAPUMP.SET_PARAMETER(  
    handle      IN NUMBER,  
    name        IN VARCHAR2,  
    value       IN VARCHAR2);
```

```
DBMS_DATAPUMP.SET_PARAMETER (  
    handle      IN NUMBER,  
    name        IN VARCHAR2,  
    value       IN NUMBER);
```

Parameters

Table 25–19 SET_PARAMETER Procedure Parameters

Parameter	Description
handle	The handle of a job. The current session must have previously attached to the handle through an OPEN call.
name	The name of the parameter. Table 25–20 describes the valid parameter names.
value	The value for the specified parameter.

[Table 25–20](#) describes the valid options for the name parameter of the SET_PARAMETER procedure.

Table 25–20 Valid Options for the name Parameter in the SET_PARAMETER Procedure

Parameter Name	Datatype	Supported Operations	Meaning
CLIENT_COMMAND	Text	All	An opaque string used to describe the current operation from the client's perspective. The command-line procedures will use this string to store the original command used to invoke the job.
ESTIMATE	Text	Export and Import	<p>Specifies that the estimate method for the size of the tables should be performed before starting the job.</p> <p>If <code>BLOCKS</code>, a size estimate for the user tables is calculated using the count of blocks allocated to the user tables.</p> <p>If <code>STATISTICS</code>, a size estimate for the user tables is calculated using the statistics associated with each table. If no statistics are available for a table, the size of the table is estimated using <code>BLOCKS</code>.</p> <p>The <code>ESTIMATE</code> parameter cannot be used in Transportable Tablespace mode.</p> <p>Default=<code>BLOCKS</code>.</p>
ESTIMATE_ONLY	Number	Export	Specifies that only the estimation portion of an export job should be performed. This option is useful for estimating the size of dump files when the size of the export is unknown.
FLASHBACK_SCN	NUMBER	Export and network Import	System change number (SCN) to serve as transactionally consistent point for reading user data. If neither <code>FLASHBACK_SCN</code> nor <code>FLASHBACK_TIME</code> is specified, there will be no transactional consistency between partitions, except for logical standby databases and Streams targets. <code>FLASHBACK_SCN</code> is not supported in Transportable mode.
FLASHBACK_TIME	Text	Export and network Import	<p>Either the date and time used to determine a consistent point for reading user data or a string of the form <code>TO_TIMESTAMP (. . .)</code>.</p> <p>If neither <code>FLASHBACK_SCN</code> nor <code>FLASHBACK_TIME</code> is specified, there will be no transactional consistency between partitions.</p> <p><code>FLASHBACK_SCN</code> and <code>FLASHBACK_TIME</code> cannot both be specified for the same job. <code>FLASHBACK_TIME</code> is not supported in Transportable mode.</p>

Table 25–20 (Cont.) Valid Options for the name Parameter in the SET_PARAMETER Procedure

Parameter Name	Datatype	Supported Operations	Meaning
INCLUDE_ METADATA	NUMBER	Export and Import	<p>If nonzero, metadata for objects will be moved in addition to user table data.</p> <p>If zero, metadata for objects will not be moved. This parameter converts an Export operation into an unload of user data and an Import operation into a load of user data.</p> <p>INCLUDE_METADATA is not supported in Transportable mode.</p> <p>Default=1.</p>
REUSE_ DATAFILES	NUMBER	Import	<p>If nonzero, tablespace data files can be created using preexisting data files for tablespace creations. REUSE_DATAFILES is only supported in Full mode.</p> <p>Default=0</p>
SKIP_ UNUSABLE_ INDEXES	NUMBER	Import	<p>If nonzero, rows will be inserted into tables having unusable indexes. SKIP_UNUSABLE_INDEXES is not supported in Transportable mode.</p> <p>Default=1</p>
TABLE_EXISTS_ ACTION	Text	Import	<p>Specifies the action to be performed when data is loaded into a preexisting table. The possible actions are: TRUNCATE, REPLACE, APPEND, and SKIP.</p> <p>If INCLUDE_METADATA=0, only TRUNCATE and APPEND are supported.</p> <p>If TRUNCATE, rows are removed from a preexisting table before inserting rows from the Import.</p> <p>Note that if TRUNCATE is specified on tables referenced by foreign key constraints, the TRUNCATE will be modified into a REPLACE.</p> <p>If REPLACE, preexisting tables are replaced with new definitions. Before creating the new table, the old table is dropped.</p> <p>If APPEND, new rows are added to the existing rows in the table.</p> <p>If SKIP, the preexisting table is left unchanged.</p> <p>TABLE_EXISTS_ACTION is not supported in Transportable mode.</p> <p>The default is SKIP if metadata is included in the import. The default is APPEND if INCLUDE_METADATA is set to 0.</p>

Table 25–20 (Cont.) Valid Options for the name Parameter in the SET_PARAMETER Procedure

Parameter Name	Datatype	Supported Operations	Meaning
TABLESPACE_ DATAFILE	Text	Import	Specifies the full file specification for a datafile in the transportable tablespace set. TABLESPACE_DATAFILE is only valid for transportable mode imports. TABLESPACE_DATAFILE can be specified multiple times, but the value specified for each occurrence must be different.
TTS_FULL_ CHECK	NUMBER	Export	If nonzero, verifies that a transportable tablespace set has no dependencies (specifically, IN pointers) on objects outside the set, and vice versa. Only valid for Transportable mode Exports. Default=0.
USER_METADATA	NUMBER	Export and network Import	For schema-mode operations, specifies that the metadata to re-create the users' schemas (for example, privilege grants to the exported schemas) should also be part of the operation if set to nonzero. Users must be privileged to explicitly set this parameter. The USER_METADATA parameter cannot be used in Table, Tablespace, or Transportable Tablespace mode. Default=1 if user has EXP_FULL_DATABASE role; 0 otherwise.

Exceptions

- INVALID_HANDLE. The specified handle is not attached to a Data Pump job.
- INVALID_ARGVAL. This exception could be due to any of the following causes:
 - An invalid name was supplied for an input parameter
 - The wrong datatype was used for value
 - A value was not supplied
 - The supplied value was not allowed for the specified parameter name
 - A flashback parameter had been established after a different flashback parameter had already been established
 - A parameter was specified that did not support duplicate definitions
- INVALID_OPERATION. The operation specified is invalid in this context.

- `INVALID_STATE`. The specified job is not in the Defining state.
- `INCONSISTENT_ARGS`. Either the specified parameter is not supported for the current operation type or it is not supported for the current mode.
- `PRIVILEGE_ERROR`. The user does not have the `EXP_FULL_DATABASE` or `IMP_FULL_DATABASE` role required for the specified parameter.
- `SUCCESS_WITH_INFO`. The procedure succeeded, but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- The `SET_PARAMETER` procedure is used to specify optional features for the current job. See [Table 25-20](#) for a list of supported options.

START_JOB Procedure

This procedure begins or resumes execution of a job.

Syntax

```
DBMS_DATAPUMP.START_JOB (
    handle          IN NUMBER,
    skip_current    IN NUMBER DEFAULT 0);
```

Parameters

Table 25–21 *START_JOB Procedure Parameters*

Parameter	Description
handle	The handle of a job. The current session must have previously attached to the handle through either the <code>OPEN</code> or <code>ATTACH</code> procedure.
skip_current	<p>If nonzero, causes actions that were 'in progress' on a previous execution of the job to be skipped when the job restarts. The skip will only be honored for Import jobs. This mechanism allows the user to skip actions that trigger fatal bugs and cause the premature termination of a job. Multiple actions can be skipped on a restart. The log file will identify which actions are skipped. If a domain index was being processed, all pieces of the domain index are skipped even if the error occurred in only a subcomponent of the domain index.</p> <p>A description of the actions skipped is entered into the log file. <code>skip_current</code> is ignored for the initial <code>START_JOB</code> in a job.</p> <p>If zero, no data or metadata is lost upon a restart.</p>

Exceptions

- `INVALID_HANDLE`. The specified handle is not attached to a Data Pump job.
- `INVALID_STATE`. The causes of this exception can be any of the following:
 - No files have been defined for an Export, non-network Import, or `SQL_FILE` job
 - An `ADD_FILE` procedure has not been called to define the output for a `SQL_FILE` job
 - A `TABLESPACE_DATAFILE` parameter has not been defined for a Transportable Import job

- A `TABLESPACE_EXPR` metadata filter has not been defined for a Transportable or Tablespace mode Export or Network job
- The dump file set on an Import of `SQL_FILE` job was either incomplete or missing a master table specification
- `INVALID_OPERATION`. Unable to restore master table from a dump file set.
- `INTERNAL_ERROR`. An inconsistency was detected when the job was started. Additional information may be available through the `GET_STATUS` procedure.
- `SUCCESS_WITH_INFO`. The procedure succeeded, but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- When this procedure is called to request that the corresponding job be started or restarted, the state of the job is changed from either the Defining or Idling state to the Executing state.
- If the `SET_PARALLEL` procedure was not called prior to the `START_JOB` procedure, the initial level of parallelism used in the job will be 1. If `SET_PARALLEL` was called prior to the job starting, the `degree` specified by the last `SET_PARALLEL` call determines the parallelism for the job. On restarts, the parallelism is determined by the previous parallel setting for the job, unless it is overridden by another `SET_PARALLEL` call.
- To restart a stopped job, an `ATTACH` must be performed prior to executing the `START_JOB` procedure.

STOP_JOB Procedure

This procedure terminates a job, but optionally, preserves the state of the job.

Syntax

```
DBMS_DATAPUMP.STOP_JOB (
    handle      IN NUMBER,
    immediate   IN NUMBER DEFAULT 0,
    keep_master IN NUMBER DEFAULT NULL,
    delay       IN NUMBER DEFAULT 0);
```

Parameters

Table 25–22 *STOP_JOB Procedure Parameters*

Parameter	Description
handle	The handle of a job. The current session must have previously attached to the handle through an OPEN or ATTACH call. At the end of the procedure, the user is detached from the handle.
immediate	If nonzero, the worker processes are aborted immediately. If zero, the worker processes are allowed to complete their current work item (either metadata or table data) before they are terminated. Performing an immediate shutdown halts the job more quickly, but parts of the job will have to be rerun if the job is ever restarted.
keep_master	If nonzero, the master table is retained when the job is stopped. If zero, the master table is dropped when the job is stopped. If the master table is dropped, the job will not be restartable. If the master table is dropped during an export job, the created dump files are deleted.
delay	The number of seconds to wait until other attached sessions are forcibly detached. The delay allows other sessions attached to the job to be notified that a stop has been performed. The job keeps running until either all clients have detached or the delay has been satisfied. If no delay is specified, then the default delay is 60 seconds. If a shorter delay is used, clients might not be able to retrieve the final messages for the job through the GET_STATUS procedure.

Exceptions

- **INVALID_HANDLE.** The specified handle is not attached to a Data Pump job.

- `INVALID STATE`. The job is already in the process of being stopped or completed.
- `SUCCESS_WITH_INFO`. The procedure succeeded, but further information is available through the `GET_STATUS` procedure.
- `NO_SUCH_JOB`. The specified job does not exist.

Usage Notes

- This procedure is used to request that the corresponding job stop executing.
- The termination of a job that is in an Executing state may take several minutes to complete in an orderly fashion.
- For jobs in the Defining, Idling, or Completing states, this procedure is functionally equivalent to the `DETACH` procedure.
- Once a job is stopped, it can be restarted using the `ATTACH` and `START_JOB` procedures, provided the master table and the dump file set are left intact.
- If the `KEEP_MASTER` parameter is not specified, and the job is in the Defining state or has a mode of Transportable, the master table is dropped. Otherwise, the master table is retained.

This package provides access to some SQL data definition language (DDL) statements from stored procedures. It also provides special administration operations that are not available as DDLs.

This chapter contains the following topics:

- [Using DBMS_DDL](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_DDL Subprograms](#)

Using DBMS_DDL

- [Security Model](#)
- [Operational Notes](#)

Security Model

This package runs with the privileges of the calling user, rather than the package owner SYS.

Operational Notes

The `ALTER_COMPILE` procedure commits the current transaction, performs the operation, and then commits again.

Summary of DBMS_DDL Subprograms

Table 26–1 DBMS_DDL Package Subprograms

Subprogram	Description
ALTER_COMPILE Procedure on page 26-4	Compiles the PL/SQL object
ALTER_TABLE_NOT_REFERENCEABLE Procedure on page 26-5	Reorganizes object tables and swizzles references
ALTER_TABLE_REFERENCEABLE Procedure on page 26-5	Reorganizes object tables and swizzles references
IS_TRIGGER_FIRE_ONCE Function on page 26-8	Returns <code>TRUE</code> if the specified DML or DDL trigger is set to fire once. Otherwise, returns <code>FALSE</code>
SET_TRIGGER FIRING_PROPERTY Procedure on page 26-9	Sets the specified DML or DDL trigger's firing property

ALTER_COMPILE Procedure

This procedure is equivalent to the following SQL statement:

```
ALTER PROCEDURE | FUNCTION | PACKAGE [<schema>.] <name> COMPILE [BODY]
```

Syntax

```
DBMS_DDL.ALTER_COMPILE (
    type      VARCHAR2,
    schema    VARCHAR2,
    name      VARCHAR2);
```

Parameters

Table 26–2 ALTER_COMPILE Procedure Parameters

Parameter	Description
type	Must be either PROCEDURE, FUNCTION, PACKAGE, PACKAGE BODY or TRIGGER.
schema	Schema name. If NULL, then use current schema (case-sensitive).
name	Name of the object (case-sensitive).

Exceptions

Table 26–3 ALTER_COMPILE Procedure Exceptions

Exception	Description
ORA-20000:	Insufficient privileges or object does not exist.
ORA-20001:	Remote object, cannot compile.
ORA-20002:	Bad value for object type Should be either PACKAGE, PACKAGE BODY, PROCEDURE, FUNCTION, or TRIGGER.

ALTER_TABLE_NOT_REFERENCEABLE Procedure

This procedure alters the given object table `table_schema.table_name` so it becomes not the default referenceable table for the schema `affected_schema`. This is equivalent to SQL

```
ALTER TABLE [<table_schema>.<table_name>] NOT REFERENCEABLE FOR <affected_
schema>
```

which is currently not supported or available as a DDL statement.

Syntax

```
DBMS_DDL.ALTER_TABLE_NOT_REFERENCEABLE (
    table_name          IN          VARCHAR2,
    table_schema        IN  DEFAULT NULL,
    affected_schema     IN  DEFAULT NULL);
```

Parameters

Table 26–4 ALTER_TABLE_NOT_REFERENCEABLE Procedure Parameters

Parameter	Description
<code>table_name</code>	The name of the table to be altered. Cannot be a synonym. Must not be NULL. Case sensitive.
<code>table_schema</code>	The name of the schema owning the table to be altered. If NULL then the current schema is used. Case sensitive.
<code>affected_schema</code>	The name of the schema affected by this alteration. If NULL then the current schema is used. Case sensitive.

Usage Notes

This procedure simply reverts for the affected schema to the default table referenceable for PUBLIC; that is., it simply undoes the previous ALTER_TABLE_REFERENCEABLE call for this specific schema. The affected schema must a particular schema (cannot be PUBLIC).

The user that executes this procedure must own the table (that is, the schema is the same as the user), and the affected schema must be the same as the user.

If the user executing this procedure has `ALTER ANY TABLE` and `SELECT ANY TABLE` and `DROP ANY TABLE` privileges, the user doesn't have to own the table and the affected schema can be any valid schema.

ALTER_TABLE_REFERENCEABLE Procedure

This procedure alters the given object table `table_schema.table_name` so it becomes the referenceable table for the given schema `affected_schema`. This is equivalent to SQL

```
ALTER TABLE [<table_schema>.<table_name>] REFERENCEABLE FOR <affected_schema>
```

which is currently not supported or available as a DDL statement.

Syntax

```
DBMS_DDL.ALTER_TABLE_REFERENCEABLE
  table_name      IN  VARCHAR2,
  table_schema    IN  DEFAULT NULL,
  affected_schema IN  DEFAULT NULL);
```

Parameters

Table 26-5 ALTER_TABLE_REFERENCEABLE Procedure Parameters

Parameter	Description
<code>table_name</code>	The name of the table to be altered. Cannot be a synonym. Must not be NULL. Case sensitive.
<code>table_schema</code>	The name of the schema owning the table to be altered. If NULL then the current schema is used. Case sensitive.
<code>affected_schema</code>	The name of the schema affected by this alteration. If NULL then the current schema is used. Case sensitive.

Usage Notes

When you create an object table, it automatically becomes referenceable, unless you use the `OID AS` clause when creating the table. The `OID AS` clause makes it possible for you to create an object table and to assign to the new table the same EOID as another object table of the same type. After you create a new table using the `OID AS` clause, you end up with two object table with the same EOID; the new table is not referenceable, the original one is. All references that used to point to the objects in the original table still reference the same objects in the same original table.

If you execute this procedure on the new table, it will make the new table the referenceable table replacing the original one; thus, those references now point to the objects in the new table instead of the original table.

IS_TRIGGER_FIRE_ONCE Function

This function returns `TRUE` if the specified DML or DDL trigger is set to fire once. Otherwise, it returns `FALSE`.

A fire once trigger fires in a user session but does not fire in the following cases:

- For changes made by a Streams apply process
- For changes made by executing one or more Streams apply errors using the `EXECUTE_ERROR` or `EXECUTE_ALL_ERRORS` procedure in the `DBMS_APPLY_ADM` package

Note: Only DML and DDL triggers can be fire once. All other types of triggers always fire.

See Also: ["SET_TRIGGER_FIRING_PROPERTY Procedure"](#) on page 26-9

Syntax

```
DBMS_DDL.IS_TRIGGER_FIRE_ONCE
  trig_owner      IN VARCHAR2,
  trig_name       IN VARCHAR2)
RETURN BOOLEAN;
```

Parameters

Table 26–6 *IS_TRIGGER_FIRE_ONCE Function Parameters*

Parameter	Description
<code>trig_owner</code>	Schema of trigger
<code>trig_name</code>	Name of trigger

SET_TRIGGER_FIRING_PROPERTY Procedure

This procedure sets the specified DML or DDL trigger's firing property. Use this procedure to control a DML or DDL trigger's firing property for changes:

- Applied by a Streams apply process
- Made by executing one or more Streams apply errors using the EXECUTE_ERROR or EXECUTE_ALL_ERRORS procedure in the DBMS_APPLY_ADM package.

Syntax

```
DBMS_DDL.SET_TRIGGER_FIRING_PROPERTY
  trig_owner      IN  VARCHAR2,
  trig_name       IN  VARCHAR2,
  fire_once       IN  BOOLEAN);
```

Parameters

Table 26–7 SET_TRIGGER_FIRING_PROPERTY Procedure Parameters

Parameter	Description
trig_owner	Schema of the trigger to set
trig_name	Name of the trigger to set
fire_once	If TRUE, then the trigger is set to fire once. By default, the fire_once parameter is set to TRUE for DML and DDL triggers. If FALSE, then the trigger is set to always fire.

Usage Notes

You can specify one of the following settings for a trigger's firing property:

- If the fire_once parameter is set to TRUE for a trigger, then the trigger does not fire for these types of changes.
- If the fire_once parameter is set to FALSE for a trigger, then the trigger fires for these types of changes.

Regardless of the firing property set by this procedure, a trigger continues to fire when changes are made by means other than the apply process or apply error execution. For example, if a user session or an application makes a change, then the trigger continues to fire, regardless of the firing property.

Note:

- If you dequeue an error transaction from the error queue and execute it without using the `DBMS_APPLY_ADM` package, then relevant changes resulting from this execution cause a trigger to fire, regardless of the trigger firing property.
 - Only DML and DDL triggers can be fire once. All other types of triggers always fire.
-
-

See Also: *Oracle Streams Concepts and Administration* for more information about the apply process and controlling a trigger's firing property

DBMS_DEBUG

DBMS_DEBUG is a PL/SQL interface to the PL/SQL debugger layer, Probe, in the Oracle server.

This API is primarily intended to implement server-side debuggers and it provides a way to debug server-side PL/SQL program units.

Note: The term *program unit* refers to a PL/SQL program of any type (procedure, function, package, package body, trigger, anonymous block, object type, or object type body).

This chapter contains the following topics:

- [Using DBMS_DEBUG](#)
 - [Overview](#)
 - [Constants](#)
 - [Variables](#)
 - [Types](#)
 - [Exceptions](#)
 - [Operational Notes](#)
- [Summary of DBMS_DEBUG Subprograms](#)

Using DBMS_DEBUG

- [Overview](#)
- [Constants](#)
- [Variables](#)
- [Types](#)
- [Exceptions](#)
- [Operational Notes](#)

Overview

To debug server-side code, you must have two database sessions: one session to run the code in debug mode (the target session), and a second session to supervise the target session (the debug session).

The target session becomes available for debugging by making initializing calls with `DBMS_DEBUG`. This marks the session so that the PL/SQL interpreter runs in debug mode and generates debug events. As debug events are generated, they are posted from the session. In most cases, debug events require return notification: the interpreter pauses awaiting a reply.

Meanwhile, the debug session must also initialize itself using `DBMS_DEBUG`: This tells it which target session to supervise. The debug session may then call entry points in `DBMS_DEBUG` to read events that were posted from the target session and to communicate with the target session.

The following subprograms are run in the target session (the session that is to be debugged):

- [SYNCHRONIZE Function](#)
- [DEBUG_ON Procedure](#)
- [DEBUG_OFF Procedure](#)

`DBMS_DEBUG` does not provide an interface to the PL/SQL compiler, but it does depend on debug information optionally generated by the compiler. Without debug information, it is not possible to examine or modify the values of parameters or variables.

Constants

A breakpoint status may have the following value:

- `breakpoint_status_unused`—breakpoint is not in use

Otherwise, the status is a mask of the following values:

- `breakpoint_status_active`—a line breakpoint
- `breakpoint_status_disabled`—breakpoint is currently disabled
- `breakpoint_status_remote`—a shadow breakpoint (a local representation of a remote breakpoint)

Variables

Variable	Description
<code>default_timeout</code>	The timeout value (used by both sessions). The smallest possible timeout is 1 second. If this value is set to 0, then a large value (3600) is used.

Types

- [BACKTRACE_TABLE](#) Type
- [BREAKPOINT_INFO](#) Type
- [BREAKPOINT_TABLE](#) Type
- [INDEX_TABLE](#) Type
- [PROGRAM_INFO](#) Types
- [RUNTIME_INFO](#) Type
- [VC2_TABLE](#) Type

BACKTRACE_TABLE Type

This type is used by `PRINT_BACKTRACE`.

```
TYPE backtrace_table IS TABLE OF program_info INDEX BY BINARY_INTEGER;
```

BREAKPOINT_INFO Type

This type gives information about a breakpoint, such as its current status and the program unit in which it was placed.

```
TYPE breakpoint_info IS RECORD
(
  -- These fields are duplicates of 'program_info':
  Name          VARCHAR2(30),
  Owner         VARCHAR2(30),
  DbLink        VARCHAR2(30),
  Line#         BINARY_INTEGER,
  LibunitType   BINARY_INTEGER,
  Status        BINARY_INTEGER  -- see breakpoint_status_* in following sections
);
```

BREAKPOINT_TABLE Type

This type is used by SHOW_BREAKPOINTS.

```
TYPE breakpoint_table IS TABLE OF breakpoint_info INDEX BY BINARY_INTEGER;
```

INDEX_TABLE Type

This type is used by GET_INDEXES to return the available indexes for an indexed table.

```
TYPE index_table IS table of BINARY_INTEGER INDEX BY BINARY_INTEGER;
```

PROGRAM_INFO Types

This type specifies a program location. It is a line number in a program unit. This is used for stack backtraces and for setting and examining breakpoints. The read-only fields are currently ignored by Probe for breakpoint operations. They are set by Probe only for stack backtraces.

Type	Description
EntrypointName	Null, unless this is a nested procedure or function.
LibunitType	Disambiguate among objects that share the same namespace (for example, procedure and package specifications). See the Libunit Types on page 27-13 for more information.

```

TYPE program_info IS RECORD
(
  -- The following fields are used when setting a breakpoint
  Namespace      BINARY_INTEGER, -- See 'NAMESPACES' in following sections
  Name           VARCHAR2(30),    -- name of the program unit
  Owner          VARCHAR2(30),    -- owner of the program unit
  Dblink         VARCHAR2(30),    -- database link, if remote
  Line#          BINARY_INTEGER,
  -- Read-only fields (set by Probe when doing a stack backtrace)
  LibunitType    BINARY_INTEGER,
  EntrypointName VARCHAR2(30)
);

```

RUNTIME_INFO Type

This type gives context information about the running program.

```

TYPE runtime_info IS RECORD
(
  Line#           BINARY_INTEGER, -- (duplicate of program.line#)
  Terminated    BINARY_INTEGER, -- has the program terminated?
  Breakpoint     BINARY_INTEGER, -- breakpoint number
  StackDepth     BINARY_INTEGER, -- number of frames on the stack
  InterpreterDepth BINARY_INTEGER, -- <reserved field>
  Reason         BINARY_INTEGER, -- reason for suspension
  Program        program_info     -- source location
);

```

VC2_TABLE Type

This type is used by SHOW_SOURCE.

```

TYPE vc2_table IS TABLE OF VARCHAR2(90) INDEX BY BINARY_INTEGER;

```

Exceptions

These values are returned by the various functions called in the debug session (SYNCHRONIZE, CONTINUE, SET_BREAKPOINT, and so on). If PL/SQL exceptions worked across client/server and server/server boundaries, then these would all be exceptions rather than error codes.

Value	Description
success	Normal termination.

Statuses returned by `GET_VALUE` and `SET_VALUE`:

Status	Description
<code>error_bogus_frame</code>	No such entrypoint on the stack.
<code>error_no_debug_info</code>	Program was compiled without debug symbols.
<code>error_no_such_object</code>	No such variable or parameter.
<code>error_unknown_type</code>	Debug information is unreadable.
<code>error_indexed_table</code>	Returned by <code>GET_VALUE</code> if the object is a table, but no index was provided.
<code>error_illegal_index</code>	No such element exists in the collection.
<code>error_nullcollection</code>	Table is atomically null.
<code>error_nullvalue</code>	Value is null.

Statuses returned by `SET_VALUE`:

Status	Description
<code>error_illegal_value</code>	Constraint violation.
<code>error_illegal_null</code>	Constraint violation.
<code>error_value_malformed</code>	Unable to decipher the given value.
<code>error_other</code>	Some other error.
<code>error_name_incomplete</code>	Name did not resolve to a scalar.

Statuses returned by the breakpoint functions:

Status	Description
<code>error_no_such_breakpt</code>	No such breakpoint.
<code>error_idle_breakpt</code>	Cannot enable or disable an unused breakpoint.
<code>error_bad_handle</code>	Unable to set breakpoint in given program (nonexistent or security violation).

General error codes (returned by many of the `DBMS_DEBUG` subprograms):

Status	Description
error_unimplemented	Functionality is not yet implemented.
error_deferred	No program running; operation deferred.
error_exception	An exception was raised in the DBMS_DEBUG or Probe packages on the server.
error_communication	Some error other than a timeout occurred.
error_timeout	Timeout occurred.

Exception	Description
illegal_init	DEBUG_ON was called prior to INITIALIZE.

The following exceptions are raised by procedure SELF_CHECK:

Exception	Description
pipe_creation_failure	Could not create a pipe.
pipe_send_failure	Could not write data to the pipe.
pipe_receive_failure	Could not read data from the pipe.
pipe_datatype_mismatch	Datatype in the pipe was wrong.
pipe_data_error	Data got garbled in the pipe.

Operational Notes

There are two ways to ensure that debug information is generated: through a session switch, or through individual recompilation.

To set the session switch, enter the following statement:

```
ALTER SESSION SET PLSQL_DEBUG = true;
```

This instructs the compiler to generate debug information for the remainder of the session. It does not recompile any existing PL/SQL.

To generate debug information for existing PL/SQL code, use one of the following statements (the second recompiles a package or type body):

```
ALTER [PROCEDURE | FUNCTION | PACKAGE | TRIGGER | TYPE] <name> COMPILE DEBUG;
```

```
ALTER [PACKAGE | TYPE] <name> COMPILE DEBUG BODY;
```

Figure 27-1 and **Figure 27-2** illustrate the flow of operations in the session to be debugged and in the debugging session.

Figure 27-1 Target Session






Figure 27-2 Debug Session

Figure 27-3 Debug Session (Cont.)



Control of the Interpreter

The interpreter pauses execution at the following times:

1. At startup of the interpreter so any deferred breakpoints may be installed prior to execution.
2. At any line containing an enabled breakpoint.
3. At any line where an *interesting* event occurs. The set of interesting events is specified by the flags passed to `DBMS_DEBUG.CONTINUE` in the `breakflags` parameter.

Session Termination

There is no event for session termination. Therefore, it is the responsibility of the debug session to check and make sure that the target session has not ended. A call to `DBMS_DEBUG.SYNCHRONIZE` after the target session has ended causes the debug session to hang until it times out.

Deferred Operations

The diagram suggests that it is possible to set breakpoints prior to having a target session. This is true. In this case, Probe caches the breakpoint request and transmits it to the target session at first synchronization. However, if a breakpoint request is deferred in this fashion, then:

- `SET_BREAKPOINT` does not set the breakpoint number (it can be obtained later from `SHOW_BREAKPOINTS` if necessary).
- `SET_BREAKPOINT` does not validate the breakpoint request. If the requested source line does not exist, then an error silently occurs at synchronization, and no breakpoint is set.

Diagnostic Output

To debug Probe, there are *diagnostics* parameters to some of the calls in `DBMS_DEBUG`. These parameters specify whether to place diagnostic output in the RDBMS tracefile. If output to the RDBMS tracefile is disabled, these parameters have no effect.

Common and Debug Session Sections

Common Section

The following subprograms may be called in either the target or the debug session:

- `PROBE_VERSION` Procedure
- `SELF_CHECK` Procedure
- `SET_TIMEOUT` Function

Target Session

The following subprograms may be called only in the target session:

- `INITIALIZE` Function
- `DEBUG_ON` Procedure
- `DEBUG_OFF` Procedure
- `SET_TIMEOUT_BEHAVIOUR` Procedure
- `GET_TIMEOUT_BEHAVIOUR` Function

Debug Session Section

The following subprograms should be run in the debug session only:

- `ATTACH_SESSION` Procedure
- `SYNCHRONIZE` Function
- `SHOW_FRAME_SOURCE` Procedure
- `SHOW_SOURCE` Procedures

- [GET_MORE_SOURCE Procedure](#)
- [PRINT_BACKTRACE Procedure](#)
- [CONTINUE Function](#)
- [SET_BREAKPOINT Function](#)
- [DELETE_BREAKPOINT Function](#)
- [SET_OER_BREAKPOINT Function](#)
- [DELETE_OER_BREAKPOINT Function](#)
- [ENABLE_BREAKPOINT Function](#)
- [DISABLE_BREAKPOINT Function](#)
- [SHOW_BREAKPOINTS Procedures](#)
- [SET_VALUE Functionn](#)
- [GET_VALUE Function](#)
- [TARGET_PROGRAM_RUNNING Procedure](#)
- [DETACH_SESSION Procedure](#)
- [GET_RUNTIME_INFO Function](#)
- [PRINT_INSTANTIATIONS Procedure](#)
- [PING Procedure](#)
- [GET_LINE_MAP Function](#)
- [GET_RUNTIME_INFO Function](#)
- [GET_INDEXES Function](#)
- [EXECUTE Procedure](#)

OER Breakpoints

Exceptions that are declared in PL/SQL programs are known as user-defined exceptions. In addition, there are Oracle Errors (OERs) that are returned from the Oracle kernel. To tie the two mechanisms together, PL/SQL provides the `exception_init` pragma that turns a user-defined exception into an OER, so that a PL/SQL handler may be used for it, and so that the PL/SQL engine can return OERs to the Oracle kernel. As of the current release, the only information available about an OER is its number. If two user-defined exceptions are `exception_init`'d to the same OER, they are indistinguishable.

Namespaces

Program units on the server reside in different namespaces. When setting a breakpoint, specify the desired namespace.

1. `Namespace_cursor` contains cursors (anonymous blocks).
2. `Namespace_pgkspec_or_toplevel` contains:
 - Package specifications.
 - Procedures and functions that are not nested inside other packages, procedures, or functions.
 - Object types.
3. `Namespace_pkg_body` contains package bodies and type bodies.
4. `Namespace_trigger` contains triggers.

Libunit Types

These values are used to disambiguate among objects in a given namespace. These constants are used in `PROGRAM_INFO` when Probe is giving a stack backtrace.

- `LibunitType_cursor`
- `LibunitType_procedure`
- `LibunitType_function`
- `LibunitType_package`
- `LibunitType_package_body`
- `LibunitType_trigger`
- `LibunitType_Unknown`

Breakflags

These are values to use for the `breakflags` parameter to `CONTINUE`, in order to tell Probe what events are of interest to the client. These flags may be combined.

Value	Description
<code>break_next_line</code>	Break at next source line (step over calls).
<code>break_any_call</code>	Break at next source line (step into calls).

Value	Description
<code>break_any_return</code>	Break after returning from current entrypoint (skip over any entrypoints called from the current routine).
<code>break_return</code>	Break the next time an entrypoint gets ready to return. (This includes entrypoints called from the current one. If interpreter is running <code>Proc1</code> , which calls <code>Proc2</code> , then <code>break_return</code> stops at the end of <code>Proc2</code> .)
<code>break_exception</code>	Break when an exception is raised.
<code>break_handler</code>	Break when an exception handler is executed.
<code>abort_execution</code>	Stop execution and force an 'exit' event as soon as <code>DBMS_DEBUG.CONTINUE</code> is called.

Information Flags

These are flags which may be passed as the `info_requested` parameter to `SYNCHRONIZE`, `CONTINUE`, and `GET_RUNTIME_INFO`.

Flag	Description
<code>info_getStackDepth</code>	Get the current depth of the stack.
<code>info_getBreakpoint</code>	Get the breakpoint number.
<code>info_getLineinfo</code>	Get program unit information.

Reasons for Suspension

After `CONTINUE` is run, the program either runs to completion or breaks on some line.

Reason	Description
<code>reason_none</code>	-
<code>reason_interpreter_starting</code>	Interpreter is starting.
<code>reason_breakpoint</code>	Hit a breakpoint.
<code>reason_enter</code>	Procedure entry.
<code>reason_return</code>	Procedure is about to return.

Reason	Description
<code>reason_finish</code>	Procedure is finished.
<code>reason_line</code>	Reached a new line.
<code>reason_interrupt</code>	An interrupt occurred.
<code>reason_exception</code>	An exception was raised.
<code>reason_exit</code>	Interpreter is exiting (old form).
<code>reason_knl_exit</code>	Kernel is exiting.
<code>reason_handler</code>	Start exception-handler.
<code>reason_timeout</code>	A timeout occurred.
<code>reason_instantiate</code>	Instantiation block.
<code>reason_abort</code>	Interpreter is aborting.

Summary of DBMS_DEBUG Subprograms

Table 27–1 DBMS_DEBUG Package Subprograms

Subprogram	Description
ATTACH_SESSION Procedure on page 27-19	Notifies the debug session about the target debugID
CONTINUE Function on page 27-20	Continues execution of the target program
DEBUG_OFF Procedure on page 21	Turns debug-mode off
DEBUG_ON Procedure on page 27-22	Turns debug-mode on
DELETE_BREAKPOINT Function on page 27-23	Deletes a breakpoint
DELETE_OER_BREAKPOINT Function on page 27-24	Deletes an OER breakpoint
DETACH_SESSION Procedure on page 27-25	Stops debugging the target program
DISABLE_BREAKPOINT Function on page 27-26	Disables a breakpoint
ENABLE_BREAKPOINT Function on page 27-27	Activates an existing breakpoint
EXECUTE Procedure on page 27-28	Executes SQL or PL/SQL in the target session
GET_INDEXES Function on page 27-31	Returns the set of indexes for an indexed table
GET_MORE_SOURCE Procedure on page 27-32	Provides additional source in the event of buffer overflow when using SHOW_SOURCE
GET_LINE_MAP Function on page 27-33	Returns information about line numbers in a program unit
GET_RUNTIME_INFO Function on page 27-34	Returns information about the current program

Table 27–1 (Cont.) DBMS_DEBUG Package Subprograms

Subprogram	Description
GET_TIMEOUT_BEHAVIOUR Function on page 27-35	Returns the current timeout behavior
GET_VALUE Function on page 27-36	Gets a value from the currently-running program
INITIALIZE Function on page 27-39	Sets debugID in target session
PING Procedure on page 27-41	Pings the target session to prevent it from timing out
PRINT_BACKTRACE Procedure on page 27-42	Prints a stack backtrace
PRINT_INSTANTIATIONS Procedure on page 27-43	Prints a stack backtrace
PROBE_VERSION Procedure on page 27-44	Returns the version number of DBMS_DEBUG on the server
SELF_CHECK Procedure on page 27-45	Performs an internal consistency check
SET_BREAKPOINT Function on page 27-46	Sets a breakpoint in a program unit
SET_OER_BREAKPOINT Function on page 27-48	Sets an OER breakpoint
SET_TIMEOUT Function on page 27-49	Sets the timeout value
SET_TIMEOUT_BEHAVIOUR Procedure on page 27-50	Tells Probe what to do with the target session when a timeout occurs
SET_VALUE Function on page 27-51	Sets a value in the currently-running program
SHOW_BREAKPOINTS Procedures on page 27-53	Returns a listing of the current breakpoints
SHOW_FRAME_SOURCE Procedure on page 27-54	Fetches the frame source
SHOW_SOURCE Procedures on page 27-55	Fetches program source

Table 27–1 (Cont.) DBMS_DEBUG Package Subprograms

Subprogram	Description
SYNCHRONIZE Function on page 27-57	Waits for program to start running
TARGET_PROGRAM_RUNNING Procedure on page 27-58	Returns <code>TRUE</code> if the target session is currently executing a stored procedure, or <code>FALSE</code> if it is not

ATTACH_SESSION Procedure

This procedure notifies the debug session about the target program.

Syntax

```
DBMS_DEBUG.ATTACH_SESSION (  
    debug_session_id IN VARCHAR2,  
    diagnostics      IN BINARY_INTEGER := 0);
```

Parameters

Table 27–2 *ATTACH_SESSION Procedure Parameters*

Parameter	Description
debug_session_id	Debug ID from a call to INITIALIZE in target session.
diagnostics	Generate diagnostic output if nonzero.

CONTINUE Function

This function passes the given breakflags (a mask of the events that are of interest) to Probe in the target process. It tells Probe to continue execution of the target process, and it waits until the target process runs to completion or signals an event.

If `info_requested` is not NULL, then calls `GET_RUNTIME_INFO`.

Syntax

```
DBMS_DEBUG.CONTINUE (  
    run_info          IN OUT runtime_info,  
    breakflags       IN      BINARY_INTEGER,  
    info_requested    IN      BINARY_INTEGER := NULL)  
RETURN BINARY_INTEGER;
```

Parameters

Table 27–3 CONTINUE Function Parameters

Parameter	Description
<code>run_info</code>	Information about the state of the program.
<code>breakflags</code>	Mask of events that are of interest. See " Breakflags " on page 27-13.
<code>info_requested</code>	Which information should be returned in <code>run_info</code> when the program stops. See " Information Flags " on page 27-14.

Return Values

Table 27–4 CONTINUE Function Return Values

Return	Description
<code>success</code>	
<code>error_timeout</code>	Timed out before the program started running.
<code>error_communication</code>	Other communication error.

DEBUG_OFF Procedure

Caution: There must be a debug session waiting if immediate is TRUE.

This procedure notifies the target session that debugging should no longer take place in that session. It is not necessary to call this function before ending the session.

Syntax

```
DBMS_DEBUG.DEBUG_OFF;
```

Usage Notes

The server does not handle this entrypoint specially. Therefore, it attempts to debug this entrypoint.

DEBUG_ON Procedure

This procedure marks the target session so that all PL/SQL is run in debug mode. This must be done before any debugging can take place.

Syntax

```
DBMS_DEBUG.DEBUG_ON (  
    no_client_side_plsql_engine BOOLEAN := TRUE,  
    immediate                   BOOLEAN := FALSE);
```

Parameters

Table 27–5 *DEBUG_ON Procedure Parameters*

Parameter	Description
<code>no_client_side_plsql_engine</code>	Should be left to its default value unless the debugging session is taking place from a client-side PL/SQL engine.
<code>immediate</code>	If this is <code>TRUE</code> , then the interpreter immediately switches itself into debug-mode, instead of continuing in regular mode for the duration of the call.

DELETE_BREAKPOINT Function

This function deletes a breakpoint.

Syntax

```
DBMS_DEBUG.DELETE_BREAKPOINT (
    breakpoint IN BINARY_INTEGER)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–6 *DELETE_BREAKPOINT Function Parameters*

Parameter	Description
breakpoint	Breakpoint number from a previous call to SET_BREAKPOINT.

Return Values

Table 27–7 *DELETE_BREAKPOINT Function Return Values*

Return	Description
success	
error_no_such_breakpt	No such breakpoint exists.
error_idle_breakpt	Cannot delete an unused breakpoint.
error_stale_breakpt	The program unit was redefined since the breakpoint was set.

DELETE_OER_BREAKPOINT Function

This function deletes an OER breakpoint.

Syntax

```
DBMS_DEBUG.DELETE_OER_BREAKPOINT (  
    oer IN PLS_INTEGER)  
RETURN PLS_INTEGER;
```

Parameters

Table 27–8 *DELETE_OER_BREAKPOINT Function Parameters*

Parameter	Description
oer	The OER (positive 4-byte number) to delete.

DETACH_SESSION Procedure

This procedure stops debugging the target program. This procedure may be called at any time, but it does not notify the target session that the debug session is detaching itself, and it does not terminate execution of the target session. Therefore, care should be taken to ensure that the target session does not hang itself.

Syntax

```
DBMS_DEBUG.DETACH_SESSION;
```

DISABLE_BREAKPOINT Function

This function makes an existing breakpoint inactive but leaves it in place.

Syntax

```
DBMS_DEBUG.DISABLE_BREAKPOINT (  
    breakpoint IN BINARY_INTEGER)  
RETURN BINARY_INTEGER;
```

Parameters

Table 27–9 *DISABLE_BREAKPOINT Function Parameters*

Parameter	Description
breakpoint	Breakpoint number from a previous call to SET_BREAKPOINT.

Return Values

Table 27–10 *DISABLE_BREAKPOINT Function Return Values*

Returns	Description
success	
error_no_such_breakpt	No such breakpoint exists.
error_idle_breakpt	Cannot disable an unused breakpoint.

ENABLE_BREAKPOINT Function

This function is the reverse of disabling. This enables a previously disabled breakpoint.

Syntax

```
DBMS_DEBUG.ENABLE_BREAKPOINT (
    breakpoint IN BINARY_INTEGER)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–11 *ENABLE_BREAKPOINT Function Parameters*

Parameter	Description
breakpoint	Breakpoint number from a previous call to SET_BREAKPOINT.

Return Values

Table 27–12 *ENABLE_BREAKPOINT Function Return Values*

Return	Description
success	Success.
error_no_such_breakpt	No such breakpoint exists.
error_idle_breakpt	Cannot enable an unused breakpoint.

EXECUTE Procedure

This procedure executes SQL or PL/SQL code in the target session. The target session is assumed to be waiting at a breakpoint (or other event). The call to `DBMS_DEBUG.EXECUTE` occurs in the debug session, which then asks the target session to execute the code.

Syntax

```
DBMS_DEBUG.EXECUTE (
  what          IN VARCHAR2,
  frame#        IN BINARY_INTEGER,
  bind_results  IN BINARY_INTEGER,
  results       IN OUT NOCOPY dbms_debug_vc2coll,
  errm          IN OUT NOCOPY VARCHAR2);
```

Parameters

Table 27–13 EXECUTE Procedure Parameters

Parameter	Description
<code>what</code>	SQL or PL/SQL source to execute.
<code>frame#</code>	The context in which to execute the code. Only -1 (global context) is supported at this time.
<code>bind_results</code>	Whether the source wants to bind to <code>results</code> in order to return values from the target session. 0 = No 1 = Yes
<code>results</code>	Collection in which to place results, if <code>bind_results</code> is not 0.
<code>errm</code>	Error message, if an error occurred; otherwise, NULL.

Examples

Example 1

This example executes a SQL statement. It returns no results.

```
DECLARE
  coll sys.dbms_debug_vc2coll; -- results (unused)
  errm VARCHAR2(100);
```

```

BEGIN
  dbms_debug.execute('insert into emp(ename,empno,deptno) ' ||
                    'values(''LJE'', 1, 1)',
                    -1, 0, coll, errm);
END;

```

Example 2

This example executes a PL/SQL block, and it returns no results. The block is an autonomous transaction, which means that the value inserted into the table becomes visible in the debug session.

```

DECLARE
  coll sys.dbms_debug_vc2coll;
  errm VARCHAR2(100);
BEGIN
  dbms_debug.execute(
    'DECLARE PRAGMA autonomous_transaction; ' ||
    'BEGIN ' ||
    '  insert into emp(ename, empno, deptno) ' ||
    '  values(''LJE'', 1, 1); ' ||
    ' COMMIT; ' ||
    'END;',
    -1, 0, coll, errm);
END;

```

Example 3

This example executes a PL/SQL block, and it returns some results.

```

DECLARE
  coll sys.dbms_debug_vc2coll;
  errm VARCHAR2(100);
BEGIN
  dbms_debug.execute(
    'DECLARE ' ||
    '  pp SYS.dbms_debug_vc2coll := SYS.dbms_debug_vc2coll(); ' ||
    '  x PLS_INTEGER; ' ||
    '  i PLS_INTEGER := 1; ' ||
    'BEGIN ' ||
    '  SELECT COUNT(*) INTO x FROM emp; ' ||
    '  pp.EXTEND(x * 6); ' ||
    '  FOR c IN (SELECT * FROM emp) LOOP ' ||
    '    pp(i) := ''Ename: '' || c.ename; i := i+1; ' ||
    '    pp(i) := ''Empno: '' || c.empno; i := i+1; ' ||
    '    pp(i) := ''Job:   '' || c.job;   i := i+1; ' ||

```

EXECUTE Procedure

```
        pp(i) := 'Mgr:  ' || c.mgr;  i := i+1; ' ||
        pp(i) := 'Sal:  ' || c.sal;  i := i+1; ' ||
        pp(i) := null;              i := i+1; ' ||
    END LOOP; ' ||
    :1 := pp; ' ||
'END;',
    -1, 1, coll, errm);
each := coll.FIRST;
WHILE (each IS NOT NULL) LOOP
    dosomething(coll(each));
    each := coll.NEXT(each);
END LOOP;
END;
```

GET_INDEXES Function

Given a name of a variable or parameter, this function returns the set of its indexes, if it is an indexed table. An error is returned if it is not an indexed table.

Syntax

```
DBMS_DEBUG.GET_INDEXES (
    varname   IN  VARCHAR2,
    frame#    IN  BINARY_INTEGER,
    handle     IN  program_info,
    entries    OUT index_table)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–14 *GET_INDEXES Function Parameters*

Parameter	Description
varname	Name of the variable to get index information about.
frame#	Number of frame in which the variable or parameter resides; NULL for a package variable.
handle	Package description, if object is a package variable.
entries	1-based table of the indexes. If non-NULL, then <code>entries(1)</code> contains the first index of the table, <code>entries(2)</code> contains the second index, and so on.

Return Values

Table 27–15 *GET_INDEXES Function Return Values*

Return	Description
error_no_such_object	Either: <ul style="list-style-type: none"> - The package does not exist. - The package is not instantiated. - The user does not have privileges to debug the package. - The object does not exist in the package.

GET_MORE_SOURCE Procedure

When source does not fit in the buffer provided by that version of the [SHOW_SOURCE Procedures](#) which produce a formatted buffer, this procedure provides additional source.

Syntax

```
DBMS_DEBUG.GET_MORE_SOURCE (  
    buffer          IN OUT VARCHAR2,  
    buflen         IN BINARY_INTEGER,  
    piece#         IN BINARY_INTEGER);
```

Parameters

Table 27–16 GET_MORE_SOURCE Procedure Parameters

Parameter	Description
buffer	The buffer.
buflen	The length of the buffer.
piece#	A value between 2 and the value returned in the parameter pieces from the call to the relevant version of the SHOW_SOURCE Procedures .

Usage Notes

This procedure should be called only after the version of SHOW_SOURCE that returns a formatted buffer.

GET_LINE_MAP Function

This function finds line and entrypoint information about a program so that a debugger can determine the source lines at which it is possible to place breakpoints.

Syntax

```
DBMS_DEBUG.GET_LINE_MAP (
  program           IN  program_info,
  maxline           OUT BINARY_INTEGER,
  number_of_entry_points OUT BINARY_INTEGER,
  linemap           OUT  RAW)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–17 GET_LINE_MAP Function Parameters

Parameter	Description
program	A top-level program unit (procedure / package / function / package body, and so on). Its Namespace, Name, and Owner fields must be initialized, the remaining fields are ignored.
maxline	The largest source code line number in 'program'.
number_of_entry_points	The number of subprograms in 'program'
linemap	A bitmap representing the executable lines of 'program'. If line number N is executable, bit number N MOD 8 will be set to 1 at linemap position N / 8. The length of returned linemap is either maxline divided by 8 (plus one if maxline MOD 8 is not zero) or 32767 in the unlikely case of maxline being larger than 32767 * 8.

Return Values

Table 27–18 GET_LINE_MAP Function Return Values

Return	Description
success	A successful completion.
error_no_debug_info	The program unit exists, but has no debug info.
error_bad_handle	No such program unit exists.

GET_RUNTIME_INFO Function

This function returns information about the current program. It is only needed if the `info_requested` parameter to `SYNCHRONIZE` or `CONTINUE` was set to 0.

Note: This is currently only used by client-side PL/SQL.

Syntax

```
DBMS_DEBUG.GET_RUNTIME_INFO (  
    info_requested IN BINARY_INTEGER,  
    run_info      OUT runtime_info)  
RETURN BINARY_INTEGER;
```

Parameters

Table 27–19 *GET_RUNTIME_INFO Function Parameters*

Parameter	Description
<code>info_requested</code>	Which information should be returned in <code>run_info</code> when the program stops. See " Information Flags " on page 27-14.
<code>run_info</code>	Information about the state of the program.

GET_TIMEOUT_BEHAVIOUR Function

This procedure returns the current timeout behavior. This call is made in the target session.

Syntax

```
DBMS_DEBUG.GET_TIMEOUT_BEHAVIOUR
RETURN BINARY_INTEGER;
```

Parameters

Table 27–20 *GET_TIMEOUT_BEHAVIOUR Function Parameters*

Parameter	Description
oer	The OER (a 4-byte positive number).

Return Values

Table 27–21 *GET_TIMEOUT_BEHAVIOUR Function Return Values*

Return	Description
success	A successful completion.

Information Flags

```
info_getOerInfo CONSTANT PLS_INTEGER:= 32;
```

Usage Notes

Less functionality is supported on OER breakpoints than on code breakpoints. In particular, note that:

- No "breakpoint number" is returned - the number of the OER is used instead. Thus it is impossible to set duplicate breakpoints on a given OER (it is a no-op).
- It is not possible to disable an OER breakpoint (although clients are free to simulate this by deleting it).
- OER breakpoints are deleted using `delete_oer_breakpoint`.

GET_VALUE Function

This function gets a value from the currently-running program. There are two overloaded GET_VALUE functions.

Syntax

```
DBMS_DEBUG.GET_VALUE (  
    variable_name IN VARCHAR2,  
    frame#        IN BINARY_INTEGER,  
    scalar_value  OUT VARCHAR2,  
    format        IN VARCHAR2 := NULL)  
RETURN BINARY_INTEGER;
```

Parameters

Table 27-22 GET_VALUE Function Parameters

Parameter	Description
variable_name	Name of the variable or parameter.
frame#	Frame in which it lives; 0 means the current procedure.
scalar_value	Value.
format	Optional date format to use, if meaningful.

Return Values

Table 27-23 GET_VALUE Function Return Values

Return	Description
success	A successful completion.
error_bogus_frame	Frame does not exist.
error_no_debug_info	Entrypoint has no debug information.
error_no_such_object	variable_name does not exist in frame#.
error_unknown_type	The type information in the debug information is illegible.
error_nullvalue	Value is NULL.
error_indexed_table	The object is a table, but no index was provided.

This form of `GET_VALUE` is for fetching package variables. Instead of a frame#, it takes a handle, which describes the package containing the variable.

Syntax

```
DBMS_DEBUG.GET_VALUE (
    variable_name IN VARCHAR2,
    handle        IN program_info,
    scalar_value  OUT VARCHAR2,
    format        IN VARCHAR2 := NULL)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–24 *GET_VALUE Function Parameters*

Parameter	Description
<code>variable_name</code>	Name of the variable or parameter.
<code>handle</code>	Description of the package containing the variable.
<code>scalar_value</code>	Value.
<code>format</code>	Optional date format to use, if meaningful.

Return Values

Table 27–25 *GET_VALUE Function Return Values*

Return	Description
<code>error_no_such_object</code>	Either: <ul style="list-style-type: none"> - Package does not exist. - Package is not instantiated. - User does not have privileges to debug the package. - Object does not exist in the package.
<code>error_indexed_table</code>	The object is a table, but no index was provided.

Examples

This example illustrates how to get the value with a given package `PACK` in schema `SCOTT`, containing variable `VAR`:

```
DECLARE
```

GET_VALUE Function

```
        handle      dbms_debug.program_info;
        resultbuf   VARCHAR2(500);
        retval      BINARY_INTEGER;
BEGIN
    handle.Owner      := 'SCOTT';
    handle.Name       := 'PACK';
    handle.namespace := dbms_debug.namespace_pkgspec_or_toplevel;
    retval            := dbms_debug.get_value('VAR', handle, resultbuf, NULL);
END;
```

INITIALIZE Function

This function initializes the target session for debugging.

Syntax

```
DBMS_DEBUG.INITIALIZE (
    debug_session_id IN VARCHAR2      := NULL,
    diagnostics      IN BINARY_INTEGER := 0)
RETURN VARCHAR2;
```

Parameters

Table 27–26 INITIALIZE Function Parameters

Parameter	Description
debug_session_id	Name of session ID. If NULL, then a unique ID is generated.
diagnostics	Indicates whether to dump diagnostic output to the tracefile. 0 = (default) no diagnostics 1 = print diagnostics

Return Values

The newly-registered debug session ID (debugID)

Usage Notes

You cannot use `DBMS_DEBUG` and the JDWP-based debugging interface simultaneously. This call will either fail with an ORA-30677 error if the session is currently being debugged with the JDWP-based debugging interface or, if the call succeeds, any further use of the JDWP-based interface to debug this session will be disallowed.

Calls to `DBMS_DEBUG` will succeed only if either the caller or the specified debug role carries the `DEBUG CONNECT SESSION` privilege. Failing that, an ORA-1031 error will be raised. Other exceptions are also possible if a debug role is specified but the password does not match, or if the calling user has not been granted the role, or the role is application-enabled and this call does not originate from within the role-enabling package.

The `CREATE ANY PROCEDURE` privilege does not affect the visibility of routines through the debugger. A privilege `DEBUG` for each object has been introduced with a corresponding `DEBUG ANY PROCEDURE` variant. These are required in order to see routines owned by users other than the session's login user.

Authentication of the debug role and the check for `DEBUG CONNECT SESSION` privilege will be done in the context of the caller to this routine. If the caller is a definer's rights routine or has been called from one, only privileges granted to the definer user, the debug role, or `PUBLIC` will be used to check for `DEBUG CONNECT SESSION`. If this call is from within a definer's rights routine, the debug role, if specified, must be one that has been granted to that definer, but it need not also have been granted to the session login user or be enabled in the calling session at the time the call is made.

The checks made by the debugger after this call is made looking for the `DEBUG` privilege on individual procedures will be done in the context of the session's login user, the roles that were enabled at session level at the moment this call was made (even if those roles were not available within a definer's rights environment of the call), and the debug role.

PING Procedure

This procedure pings the target session to prevent it from timing out. Use this procedure when execution is suspended in the target session, for example at a breakpoint.

If the `timeout_behaviour` is set to `retry_on_timeout` then this procedure is not necessary.

Syntax

```
DBMS_DEBUG.PING;
```

Exceptions

Oracle will display the `no_target_program` exception if there is no target program or if the target session is not currently waiting for input from the debug session.

Usage Notes

Timeout options for the target session are registered with the target session by calling `set_timeout_behaviour`.

- `retry_on_timeout` - **Retry.** Timeout has no effect. This is like setting the timeout to an infinitely large value.
- `continue_on_timeout` - Continue execution, using same event flags.
- `nodebug_on_timeout` - Turn debug-mode OFF (in other words, call `debug_off`) and then continue execution. No more events will be generated by this target session unless it is re-initialized by calling `debug_on`.
- `abort_on_timeout` - Continue execution, using the `abort_execution` flag, which should cause the program to terminate immediately. The session remains in debug-mode.

```
retry_on_timeout CONSTANT BINARY_INTEGER:= 0;
```

```
continue_on_timeout CONSTANT BINARY_INTEGER:= 1;
```

```
nodebug_on_timeout CONSTANT BINARY_INTEGER:= 2;
```

```
abort_on_timeout CONSTANT BINARY_INTEGER:= 3;
```

PRINT_BACKTRACE Procedure

This procedure prints a backtrace listing of the current execution stack. This should only be called if a program is currently running.

There are two overloaded `PRINT_BACKTRACE` procedures.

Syntax

```
DBMS_DEBUG.PRINT_BACKTRACE (  
    listing IN OUT VARCHAR2);
```

```
DBMS_DEBUG.PRINT_BACKTRACE (  
    backtrace OUT backtrace_table);
```

Table 27–27 *PRINT_BACKTRACE Procedure Parameters*

Parameter	Description
<code>listing</code>	A formatted character buffer with embedded newlines.
<code>backtrace</code>	1-based indexed table of backtrace entries. The currently-running procedure is the last entry in the table (that is, the frame numbering is the same as that used by <code>GET_VALUE</code>). Entry 1 is the oldest procedure on the stack.

PRINT_INSTANTIATIONS Procedure

This procedure returns a list of the packages that have been instantiated in the current session.

Syntax

```
DBMS_DEBUG.PRINT_INSTANTIATIONS (
    pkgs   IN OUT NOCOPY backtrace_table,
    flags  IN BINARY_INTEGER);
```

Parameters

Table 27–28 PRINT_INSTANTIATIONS Procedure Parameters

Parameter	Description
pkgs (OUT)	The instantiated packages
flags	Bitmask of options: <ul style="list-style-type: none"> ■ 1 - show specs ■ 2 - show bodies ■ 4 - show local instantiations ■ 8 - show remote instantiations (NYI) ■ 16 - do a fast job. The routine does not test whether debug information exists or whether the libunit is shrink-wrapped.

Exceptions

`no_target_program` - target session is not currently executing

Usage Notes

On return, `pkgs` contains a `program_info` for each instantiation. The valid fields are: `Namespace`, `Name`, `Owner`, and `LibunitType`.

In addition, `Line#` contains a bitmask of:

- 1 - the libunit contains debug info
- 2 - the libunit is shrink-wrapped

PROBE_VERSION Procedure

This procedure returns the version number of DBMS_DEBUG on the server.

Syntax

```
DBMS_DEBUG.PROBE_VERSION (
    major out BINARY_INTEGER,
    minor out BINARY_INTEGER);
```

Parameters

Table 27–29 *PROBE_VERSION Procedure Parameters*

Parameter	Description
major	Major version number.
minor	Minor version number: increments as functionality is added.

SELF_CHECK Procedure

This procedure performs an internal consistency check. `SELF_CHECK` also runs a communications test to ensure that the Probe processes are able to communicate.

If `SELF_CHECK` does not return successfully, then an incorrect version of `DBMS_DEBUG` was probably installed on this server. The solution is to install the correct version (`pbload.sql` loads `DBMS_DEBUG` and the other relevant packages).

Syntax

```
DBMS_DEBUG.SELF_CHECK (
    timeout IN binary_integer := 60);
```

Parameters

Table 27–30 *SELF_CHECK Procedure Parameters*

Parameter	Description
timeout	The timeout to use for the communication test. Default is 60 seconds.

Exceptions

Table 27–31 *SELF_CHECK Procedure Exceptions*

Exception	Description
OER-6516	Probe version is inconsistent.
pipe_creation_failure	Could not create a pipe.
pipe_send_failure	Could not write data to the pipe.
pipe_receive_failure	Could not read data from the pipe.
pipe_datatype_mismatch	Datatype in the pipe was wrong.
pipe_data_error	Data got garbled in the pipe.

All of these exceptions are fatal. They indicate a serious problem with Probe that prevents it from working correctly.

SET_BREAKPOINT Function

This function sets a breakpoint in a program unit, which persists for the current session. Execution pauses if the target program reaches the breakpoint.

Syntax

```
DBMS_DEBUG.SET_BREAKPOINT (
    program      IN program_info,
    line#        IN BINARY_INTEGER,
    breakpoint#  OUT BINARY_INTEGER,
    fuzzy        IN BINARY_INTEGER := 0,
    iterations   IN BINARY_INTEGER := 0)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–32 SET_BREAKPOINT Function Parameters

Parameter	Description
program	Information about the program unit in which the breakpoint is to be set. (In version 2.1 and later, the namespace, name, owner, and dblink may be set to NULL, in which case the breakpoint is placed in the currently-running program unit.)
line#	Line at which the breakpoint is to be set.
breakpoint#	On successful completion, contains the unique breakpoint number by which to refer to the breakpoint.
fuzzy	Only applicable if there is no executable code at the specified line: 0 means return <code>error_illegal_line</code> . 1 means search forward for an adjacent line at which to place the breakpoint. -1 means search backward for an adjacent line at which to place the breakpoint.
iterations	Number of times to wait before signalling this breakpoint.

Return Values

Note: The `fuzzy` and `iterations` parameters are not yet implemented.

Table 27–33 *SET_BREAKPOINT Function Return Values*

Return	Description
<code>success</code>	A successful completion.
<code>error_illegal_line</code>	Cannot set a breakpoint at that line.
<code>error_bad_handle</code>	No such program unit exists.

SET_OER_BREAKPOINT Function

This function sets an OER breakpoint.

Syntax

```
DBMS_DEBUG.SET_OER_BREAKPOINT (  
    oer IN PLS_INTEGER)  
RETURN PLS_INTEGER;
```

Parameters

Table 27–34 SET_OER_BREAKPOINT Function Parameters

Parameter	Description
oer	The OER (positive 4-byte number) to delete.

Return Values

Table 27–35 SET_OER_BREAKPOINT Function Return Values

Return	Description
success	A successful completion.
error_no_such_ breakpt	No such OER breakpoint exists.

SET_TIMEOUT Function

This function sets the timeout value and returns the new timeout value.

Syntax

```
DBMS_DEBUG.SET_TIMEOUT (  
    timeout BINARY_INTEGER)  
RETURN BINARY_INTEGER;
```

Parameters

Table 27–36 *SET_TIMEOUT Function Parameters*

Parameter	Description
timeout	The timeout to use for communication between the target and debug sessions.

SET_TIMEOUT_BEHAVIOUR Procedure

This procedure tells Probe what to do with the target session when a timeout occurs. This call is made in the target session.

Syntax

```
DBMS_DEBUG.SET_TIMEOUT_BEHAVIOUR (  
    behaviour IN PLS_INTEGER);
```

Parameters

Table 27-37 SET_TIMEOUT_BEHAVIOUR Procedure Parameters

Parameter	Description
behaviour	One of the following:
retry_on_timeout	Retry. Timeout has no effect. This is like setting the timeout to an infinitely large value.
continue_on_timeout	Continue execution, using same event flags.
nodebug_on_timeout	Turn debug-mode OFF (in other words, call <code>debug_off</code>) and continue execution. No more events will be generated by this target session unless it is re-initialized by calling <code>debug_on</code> .
abort_on_timeout	Continue execution, using the <code>abort_execution</code> flag, which should cause the program to terminate immediately. The session remains in debug-mode.

Exceptions

unimplemented - the requested behavior is not recognized

Usage Notes

The default behavior (if this procedure is not called) is `continue_on_timeout`, since it allows a debugger client to reestablish control (at the next event) but does not cause the target session to hang indefinitely.

SET_VALUE Function

This function sets a value in the currently-running program. There are two overloaded SET_VALUE functions.

Syntax

```
DBMS_DEBUG.SET_VALUE (
    frame#           IN binary_integer,
    assignment_statement IN varchar2)
RETURN BINARY_INTEGER;
```

```
DBMS_DEBUG.SET_VALUE (
    handle           IN program_info,
    assignment_statement IN VARCHAR2)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–38 SET_VALUE Function Parameters

Parameter	Description
frame#	Frame in which the value is to be set; 0 means the currently executing frame.
handle	Description of the package containing the variable.
assignment_statement	An assignment statement (which must be legal PL/SQL) to run in order to set the value. For example, 'x := 3;'. Only scalar values are supported in this release. The right side of the assignment statement must be a scalar.

Return Values

Table 27–39 SET_VALUE Function Return Values

Return	Description
success	-
error_illegal_value	Not possible to set it to that value.
error_illegal_null	Cannot set to NULL because object type specifies it as 'not null'.

Table 27–39 SET_VALUE Function Return Values

Return	Description
error_value_malformed	Value is not a scalar.
error_name_incomplete	The assignment statement does not resolve to a scalar. For example, 'x := 3;', if x is a record.
error_no_such_object	Either: <ul style="list-style-type: none">- Package does not exist.- Package is not instantiated.- User does not have privileges to debug the package.- Object does not exist in the package.

Usage Notes

In some cases, the PL/SQL compiler uses temporaries to access package variables, and does not guarantee to update such temporaries. It is possible, although unlikely, that modification to a package variable using SET_VALUE might not take effect for a line or two.

Examples

To set the value of SCOTT.PACK.var to 6:

```
DECLARE
    handle dbms_debug.program_info;
    retval BINARY_INTEGER;
BEGIN
    handle.Owner      := 'SCOTT';
    handle.Name       := 'PACK';
    handle.namespace := dbms_debug.namespace_pkgspec_or_toplevel;
    retval            := dbms_debug.set_value(handle, 'var := 6;');
END;
```

SHOW_BREAKPOINTS Procedures

There are two overloaded procedures that return a listing of the current breakpoints. There are three overloaded SHOW_BREAKPOINTS procedures.

Syntax

```
DBMS_DEBUG.SHOW_BREAKPOINTS (
    listing    IN OUT VARCHAR2);

DBMS_DEBUG.SHOW_BREAKPOINTS (
    listing    OUT breakpoint_table);

DBMS_DEBUG.SHOW_BREAKPOINTS (
    code_breakpoints OUT breakpoint_table,
    oer_breakpoints  OUT oer_table);
```

Parameters

Table 27–40 *SHOW_BREAKPOINTS Procedure Parameters*

Parameter	Description
listing	A formatted buffer (including newlines) of the breakpoints. Indexed table of breakpoint entries. The breakpoint number is indicated by the index into the table. Breakpoint numbers start at 1 and are reused when deleted.
code_breakpoints	The indexed table of breakpoint entries, indexed by breakpoint number.
oer_breakpoints	The indexed table of OER breakpoints, indexed by OER.

SHOW_FRAME_SOURCE Procedure

The procedure gets the source code. There are two overloaded SHOW_SOURCE procedures.

Syntax

```
DBMS_DEBUG.SHOW_FRAME_SOURCE (
    first_line IN          BINARY_INTEGER,
    last_line  IN          BINARY_INTEGER,
    source     IN OUT NOCOPY vc2_table,
    frame_num  IN          BINARY_INTEGER);
```

Parameters

Table 27-41 SHOW_FRAME_SOURCE Procedure Parameters

Parameter	Description
first_line	Line number of first line to fetch. (PL/SQL programs always start at line 1 and have no holes.)
last_line	Line number of last line to fetch. No lines are fetched past the end of the program.
source	The resulting table, which may be indexed by line#.
frame_num	1-based frame number.

Usage Notes

- You use this function only when backtrace shows an anonymous unit is executing at a given frame position and you need to view the source in order to set a breakpoint.
- If frame number is top of the stack and it's an anonymous block then SHOW_SOURCE can also be used.
- If it's a stored PLSQL package/function/procedure then use SQL as described in the [Usage Notes](#) to [SHOW_SOURCE Procedures](#).

SHOW_SOURCE Procedures

The procedure gets the source code. There are two overloaded `SHOW_SOURCE` procedures.

Syntax

```
DBMS_DEBUG.SHOW_SOURCE (
    first_line IN BINARY_INTEGER,
    last_line  IN BINARY_INTEGER,
    source     OUT vc2_table);

DBMS_DEBUG.SHOW_SOURCE (
    first_line IN BINARY_INTEGER,
    last_line  IN BINARY_INTEGER,
    window     IN BINARY_INTEGER,
    print_arrow IN BINARY_INTEGER,
    buffer     IN OUT VARCHAR2,
    buflen     IN BINARY_INTEGER,
    pieces     OUT BINARY_INTEGER);
```

Parameters

Table 27–42 *SHOW_SOURCE Procedure Parameters*

Parameter	Description
<code>first_line</code>	Line number of first line to fetch. (PL/SQL programs always start at line 1 and have no holes.)
<code>last_line</code>	Line number of last line to fetch. No lines are fetched past the end of the program.
<code>source</code>	The resulting table, which may be indexed by line#.
<code>window</code>	'Window' of lines (the number of lines around the current source line).
<code>print_arrow</code>	Nonzero means to print an arrow before the current line.
<code>buffer</code>	Buffer in which to place the source listing.
<code>buflen</code>	Length of buffer.
<code>pieces</code>	Set to nonzero if not all the source could be placed into the given buffer.

Return Values

An indexed table of source-lines. The source lines are stored starting at `first_line`. If any error occurs, then the table is empty.

Usage Notes

The best way to get the source code (for a program that is being run) is to use SQL. For example:

```
DECLARE
    info DBMS_DEBUG.runtime_info;
BEGIN
    -- call DBMS_DEBUG.SYNCHRONIZE, CONTINUE,
    -- or GET_RUNTIME_INFO to fill in 'info'
    SELECT text INTO <buffer> FROM all_source
    WHERE owner = info.Program.Owner
        AND name = info.Program.Name
        AND line = info.Line#;
END;
```

However, this does not work for nonpersistent programs (for example, anonymous blocks and trigger invocation blocks). For nonpersistent programs, call `SHOW_SOURCE`. There are two flavors: one returns an indexed table of source lines, and the other returns a packed (and formatted) buffer.

The second overloading of `SHOW_SOURCE` returns the source in a formatted buffer, complete with line-numbers. It is faster than the indexed table version, but it does not guarantee to fetch all the source.

If the source does not fit in `bufferlength` (`buflen`), then additional pieces can be retrieved using the `GET_MORE_SOURCE` procedure (`pieces` returns the number of additional pieces that need to be retrieved).

SYNCHRONIZE Function

This function waits until the target program signals an event. If `info_requested` is not `NULL`, then it calls `GET_RUNTIME_INFO`.

Syntax

```
DBMS_DEBUG.SYNCHRONIZE (
    run_info          OUT  runtime_info,
    info_requested IN   BINARY_INTEGER := NULL)
RETURN BINARY_INTEGER;
```

Parameters

Table 27–43 SYNCHRONIZE Function Parameters

Parameter	Description
<code>run_info</code>	Structure in which to write information about the program. By default, this includes information about what program is running and at which line execution has paused.
<code>info_requested</code>	Optional bit-field in which to request information other than the default (which is <code>info_getStackDepth + info_getLineInfo</code>). 0 means that no information is requested at all. See " Information Flags " on page 27-14.

Return Values

Table 27–44 SYNCHRONIZE Function Return Values

Return	Description
<code>success</code>	A successful completion.
<code>error_timeout</code>	Timed out before the program started execution.
<code>error_communication</code>	Other communication error.

TARGET_PROGRAM_RUNNING Procedure

This procedure returns `TRUE` if the target session is currently executing a stored procedure, or `FALSE` if it is not.

Syntax

```
DBMS_DEBUG.TARGET_PROGRAM_RUNNING  
RETURN BOOLEAN;
```

DBMS_DEFER

DBMS_DEFER is the user interface to a replicated transactional deferred remote procedure call facility. Replicated applications use the calls in this interface to queue procedure calls for later transactional execution at remote nodes.

These procedures are typically called from either after row triggers or application specified update procedures.

- [Documentation of DBMS_DEFER](#)

Documentation of DBMS_DEFER

For a complete description of this package within the context of Replication, see DBMS_DEFER in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_DEFER_QUERY

DBMS_DEFER_QUERY enables you to query the deferred transactions queue data that is not exposed through views.

- [Documentation of DBMS_DEFER_QUERY](#)

Documentation of DBMS_DEFER_QUERY

For a complete description of this package within the context of Replication, see DBMS_DEFER_QUERY in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_DEFER_SYS

DBMS_DEFER_SYS subprograms manage default replication node lists. This package is the system administrator interface to a replicated transactional deferred remote procedure call facility. Administrators and replication daemons can execute transactions queued for remote nodes using this facility, and administrators can control the nodes to which remote calls are destined.

- [Documentation of DBMS_DEFER_SYS](#)

Documentation of DBMS_DEFER_SYS

For a complete description of this package within the context of Replication, see `DBMS_DEFER_SYS` in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_DESCRIBE

You can use the `DBMS_DESCRIBE` package to get information about a PL/SQL object. When you specify an object name, `DBMS_DESCRIBE` returns a set of indexed tables with the results. Full name translation is performed and security checking is also checked on the final object.

This chapter contains the following topics:

- [Using DBMS_DESCRIBE](#)
 - [Overview](#)
 - [Security Model](#)
 - [Types](#)
 - [Exceptions](#)
 - [Operational Notes](#)
 - [Examples](#)
- [Summary of DBMS_DESCRIBE Subprograms](#)

Using DBMS_DESCRIBE

- [Overview](#)
- [Security Model](#)
- [Types](#)
- [Exceptions](#)
- [Operational Notes](#)
- [Examples](#)

Overview

This package provides the same functionality as the Oracle Call Interface `OCIDescribeAny` call.

See Also: *Oracle Call Interface Programmer's Guide*

Security Model

This package is available to `PUBLIC` and performs its own security checking based on the schema object being described.

Types

The `DBMS_DESCRIBE` package declares two PL/SQL table types, which are used to hold data returned by `DESCRIBE_PROCEDURE` in its `OUT` parameters. The types are:

```
TYPE VARCHAR2_TABLE IS TABLE OF VARCHAR2(30)
    INDEX BY BINARY_INTEGER;
```

```
TYPE NUMBER_TABLE IS TABLE OF NUMBER
    INDEX BY BINARY_INTEGER;
```

Exceptions

`DBMS_DESCRIBE` can raise application errors in the range `-20000` to `-20004`.

Table 31-1 DBMS_DESCRIBE Errors

Error	Description
ORA-20000	ORU 10035: cannot describe a package ('X') only a procedure within a package.
ORA-20001	ORU-10032: procedure 'X' within package 'Y' does not exist.
ORA-20002	ORU-10033: object 'X' is remote, cannot describe; expanded name 'Y'.
ORA-20003	ORU-10036: object 'X' is invalid and cannot be described.
ORA-20004	Syntax error attempting to parse 'X'.

Operational Notes

From a third generation language, we cannot directly bind to an argument of record or boolean type. For a Boolean, the following workaround is available:

Assume function F returns a Boolean. G is a procedure with one IN Boolean argument, and H is a procedure with one OUT Boolean argument. You can execute these functions, binding in DTYINTS (native integer) as follows, where 0=>FALSE and 1=>TRUE:

```

DECLARE b BOOLEAN;
BEGIN h(b);
  IF b
    THEN :dtyint_bind_var := 1;
    ELSE :dtyint_bind_var := 0;
  END IF;
END;
```

Access to procedures with arguments of the record type require writing a wrapper similar to that in the preceding example.

Examples

One use of the DESCRIBE_PROCEDURE procedure is as an external service interface.

For example, consider a client that provides an OBJECT_NAME of SCOTT.ACCOUNT_UPDATE, where ACCOUNT_UPDATE is an overloaded function with specification:

```

TABLE account (account_no NUMBER, person_id NUMBER,
               balance NUMBER(7,2))
TABLE person (person_id number(4), person_nm varchar2(10))
```

```

FUNCTION ACCOUNT_UPDATE (account_no NUMBER,
                        person      person%rowtype,
                        amounts     DBMS_DESCRIBE.NUMBER_TABLE,
                        trans_date  DATE)
return account.balance%type;

```

```

FUNCTION ACCOUNT_UPDATE (account_no NUMBER,
                        person      person%rowtype,
                        amounts     DBMS_DESCRIBE.NUMBER_TABLE,
                        trans_no    NUMBER)
return account.balance%type;

```

This procedure might look similar to the following output:

overload	position	argument	level	datatype	length	prec	scale	rad
1	0		0	2	22	7	2	10
1	1	ACCOUNT	0	2	0	0	0	0
1	2	PERSON	0	250	0	0	0	0
1	1	PERSON_ID	1	2	22	4	0	10
1	2	PERSON_NM	1	1	10	0	0	0
1	3	AMOUNTS	0	251	0	0	0	0
1	1		1	2	22	0	0	0
1	4	TRANS_DATE	0	12	0	0	0	0
2	0		0	2	22	7	2	10
2	1	ACCOUNT_NO	0	2	22	0	0	0
2	2	PERSON	0	2	22	4	0	10
2	3	AMOUNTS	0	251	22	4	0	10
2	1		1	2	0	0	0	0
2	4	TRANS_NO	0	2	0	0	0	0

The following PL/SQL procedure has as its parameters all of the PL/SQL datatypes:

```

CREATE OR REPLACE PROCEDURE p1 (
    pvc2   IN   VARCHAR2,
    pvc    OUT  VARCHAR,
    pstr   IN OUT STRING,
    plong  IN   LONG,
    prowid IN   ROWID,
    pchara IN   CHARACTER,
    pchar  IN   CHAR,
    praw  IN   RAW,
    plraw  IN   LONG RAW,
    pbinint IN  BINARY_INTEGER,

```

```

pplsint IN      PLS_INTEGER,
pbool  IN      BOOLEAN,
pnat   IN      NATURAL,
ppos   IN      POSITIVE,
pposn  IN      POSITIVEN,
pnatn  IN      NATURALN,
pnum   IN      NUMBER,
pintgr IN      INTEGER,
pint   IN      INT,
psmall IN      SMALLINT,
pdec   IN      DECIMAL,
preal  IN      REAL,
pfloat IN      FLOAT,
pnumer IN      NUMERIC,
pdp    IN      DOUBLE PRECISION,
pdate  IN      DATE,
pmls   IN      MLSLABEL) AS

```

```

BEGIN
  NULL;
END;

```

If you describe this procedure using the following:

```
CREATE OR REPLACE PACKAGE describe_it AS
```

```

  PROCEDURE desc_proc (name VARCHAR2);

```

```
END describe_it;
```

```
CREATE OR REPLACE PACKAGE BODY describe_it AS
```

```

PROCEDURE prt_value(val VARCHAR2, isize INTEGER) IS
  n INTEGER;
BEGIN
  n := isize - LENGTHB(val);
  IF n < 0 THEN
    n := 0;
  END IF;
  DBMS_OUTPUT.PUT(val);
  FOR i in 1..n LOOP
    DBMS_OUTPUT.PUT(' ');
  END LOOP;
END prt_value;

```

```
PROCEDURE desc_proc (name VARCHAR2) IS

    overload      DBMS_DESCRIBE.NUMBER_TABLE;
    position      DBMS_DESCRIBE.NUMBER_TABLE;
    c_level       DBMS_DESCRIBE.NUMBER_TABLE;
    arg_name      DBMS_DESCRIBE.VARCHAR2_TABLE;
    dtypes        DBMS_DESCRIBE.NUMBER_TABLE;
    def_val       DBMS_DESCRIBE.NUMBER_TABLE;
    p_mode        DBMS_DESCRIBE.NUMBER_TABLE;
    length        DBMS_DESCRIBE.NUMBER_TABLE;
    precision     DBMS_DESCRIBE.NUMBER_TABLE;
    scale         DBMS_DESCRIBE.NUMBER_TABLE;
    radix         DBMS_DESCRIBE.NUMBER_TABLE;
    spare         DBMS_DESCRIBE.NUMBER_TABLE;
    idx           INTEGER := 0;

BEGIN
    DBMS_DESCRIBE.DESCRIBE_PROCEDURE(
        name,
        null,
        null,
        overload,
        position,
        c_level,
        arg_name,
        dtypes,
        def_val,
        p_mode,
        length,
        precision,
        scale,
        radix,
        spare);

    DBMS_OUTPUT.PUT_LINE('Position      Name          DTY  Mode');
    LOOP
        idx := idx + 1;
        prt_value(TO_CHAR(position(idx)), 12);
        prt_value(arg_name(idx), 12);
        prt_value(TO_CHAR(dtypes(idx)), 5);
        prt_value(TO_CHAR(p_mode(idx)), 5);
        DBMS_OUTPUT.NEW_LINE;
    END LOOP;
EXCEPTION
    WHEN NO_DATA_FOUND THEN
```

```
DBMS_OUTPUT.NEW_LINE;  
DBMS_OUTPUT.NEW_LINE;  
  
END desc_proc;  
END describe_it;
```

Then the results list all the numeric codes for the PL/SQL datatypes:

Position	Name	Datatype_Code	Mode
1	PVC2	1	0
2	PVC	1	1
3	PSTR	1	2
4	PLONG	8	0
5	PROWID	11	0
6	PCHARA	96	0
7	PCHAR	96	0
8	PRAW	23	0
9	PLRAW	24	0
10	PBININT	3	0
11	PPLSINT	3	0
12	PBOOL	252	0
13	PNAT	3	0
14	PPOS	3	0
15	PPOSN	3	0
16	PNATN	3	0
17	PNUM	2	0
18	PINTGR	2	0
19	PINT	2	0
20	PSMALL	2	0
21	PDEC	2	0
22	PREAL	2	0
23	PFLOAT	2	0
24	PNUMER	2	0
25	PDP	2	0
26	PDATE	12	0
27	PMLS	106	0

Summary of DBMS_DESCRIBE Subprograms

Table 31–2 *DBMS_DESCRIBE Package Subprograms*

Subprogram	Description
DESCRIBE_PROCEDURE Procedure on page 31-9	Provides a brief description of a PL/SQL stored procedure

DESCRIBE_PROCEDURE Procedure

The procedure `DESCRIBE_PROCEDURE` provides a brief description of a PL/SQL stored procedure. It takes the name of a stored procedure and returns information about each parameter of that procedure.

Syntax

```
DBMS_DESCRIBE.DESCRIBE_PROCEDURE(  
    object_name          IN  VARCHAR2,  
    reserved1           IN  VARCHAR2,  
    reserved2           IN  VARCHAR2,  
    overload            OUT NUMBER_TABLE,  
    position            OUT NUMBER_TABLE,  
    level               OUT NUMBER_TABLE,  
    argument_name       OUT VARCHAR2_TABLE,  
    datatype            OUT NUMBER_TABLE,  
    default_value       OUT NUMBER_TABLE,  
    in_out              OUT NUMBER_TABLE,  
    length              OUT NUMBER_TABLE,  
    precision           OUT NUMBER_TABLE,  
    scale               OUT NUMBER_TABLE,  
    radix               OUT NUMBER_TABLE,  
    spare               OUT NUMBER_TABLE,  
    include_string_constraints OUT BOOLEAN DEFAULT FALSE);
```

Parameters

Table 31–3 DBMS_DESCRIBE.DESCRIBE_PROCEDURE Parameters

Parameter	Description
object_name	<p>Name of the procedure being described.</p> <p>The syntax for this parameter follows the rules used for identifiers in SQL. The name can be a synonym. This parameter is required and may not be null. The total length of the name cannot exceed 197 bytes. An incorrectly specified OBJECT_NAME can result in one of the following exceptions:</p> <p>ORA-20000 - A package was specified. You can only specify a stored procedure, stored function, packaged procedure, or packaged function.</p> <p>ORA-20001 - The procedure or function that you specified does not exist within the given package.</p> <p>ORA-20002 - The object that you specified is a remote object. This procedure cannot currently describe remote objects.</p> <p>ORA-20003 - The object that you specified is invalid and cannot be described.</p> <p>ORA-20004 - The object was specified with a syntax error.</p>
reserved1	Reserved for future use -- must be set to NULL or the empty string.
reserved2	
overload	<p>A unique number assigned to the procedure's signature.</p> <p>If a procedure is overloaded, then this field holds a different value for each version of the procedure.</p>
position	<p>Position of the argument in the parameter list.</p> <p>Position 0 returns the values for the return type of a function.</p>
level	If the argument is a composite type, such as record, then this parameter returns the level of the datatype. See the <i>Oracle Call Interface Programmer's Guide</i> for a description of the ODESSP call for an example.
argument_name	Name of the argument associated with the procedure that you are describing.

Table 31–3 (Cont.) DBMS_DESCRIBE.DESCRIBE_PROCEDURE Parameters

Parameter	Description
datatype	<p>Oracle datatype of the argument being described. The datatypes and their numeric type codes are:</p> <ul style="list-style-type: none"> 0 placeholder for procedures with no arguments 1 VARCHAR, VARCHAR2, STRING 2 NUMBER, INTEGER, SMALLINT, REAL, FLOAT, DECIMAL 3 BINARY_INTEGER, PLS_INTEGER, POSITIVE, NATURAL 8 LONG 11 ROWID 12 DATE 23 RAW 24 LONG RAW 58 OPAQUE TYPE 96 CHAR (ANSI FIXED CHAR), CHARACTER 106 MLSLABEL 121 OBJECT 122 NESTED TABLE 123 VARRAY 178 TIME 179 TIME WITH TIME ZONE 180 TIMESTAMP 181 TIMESTAMP WITH TIME ZONE 231 TIMESTAMP WITH LOCAL TIME ZONE 250 PL/SQL RECORD 251 PL/SQL TABLE 252 PL/SQL BOOLEAN
default_value	1 if the argument being described has a default value; otherwise, the value is 0.
in_out	<p>Describes the mode of the parameter:</p> <ul style="list-style-type: none"> 0 IN 1 OUT 2 IN OUT
length	For %rowtype formal arguments, the length constraint is returned, otherwise 0 is returned. If the include_string_constraints parameter is set to TRUE, the argument's formal length constraint is passed back if it is of the appropriate type. Those are the string types: 1;8;23;24;96
precision	If the argument being described is of datatype 2 (NUMBER), then this parameter is the precision of that number.

Table 31–3 (Cont.) DBMS_DESCRIBE.DESCRIBE_PROCEDURE Parameters

Parameter	Description
scale	If the argument being described is of datatype 2 (NUMBER), then this parameter is the scale of that number.
radix	If the argument being described is of datatype 2 (NUMBER), then this parameter is the radix of that number.
spare	Reserved for future functionality.
include_string_constraints	The default is FALSE. If the parameter is set to TRUE, the arguments' formal type constraints is passed back if it is of the appropriate type. Those are the string types: 1;8;23;24;96

Return Values

All values from DESCRIBE_PROCEDURE are returned in its OUT parameters. The datatypes for these are PL/SQL tables, to accommodate a variable number of parameters.

DBMS_DIMENSION

DBMS_DIMENSION enables you to verify dimension relationships and provides an alternative to the Enterprise Manager Dimension Wizard for displaying a dimension definition.

See Also: *Oracle Data Warehousing Guide* for detailed conceptual and usage information about the DBMS_DIMENSION package

This chapter contains the following topics:

- [Using DBMS_DIMENSION](#)
 - [Security Model](#)
- [Summary of DBMS_DIMENSION Subprograms](#)

Using DBMS_DIMENSION

- [Security Model](#)

Security Model

Security on this package can be controlled by granting `EXECUTE` to selected users or roles.

A user can validate or describe all the dimensions in his own schema. To validate or describe a dimension in another schema, you must have either an object privilege on the dimension or one of the following system privileges: `CREATE ANY DIMENSION`, `ALTER ANY DIMENSION`, and `DROP ANY DIMENSION`.

Summary of DBMS_DIMENSION Subprograms

Table 32-1 DBMS_DIMENSION Package Subprograms

Subprogram	Description
DESCRIBE_DIMENSION Procedure on page 32-4	Prints out the definition of the input dimension, including dimension owner and name, levels, hierarchies, and attributes
VALIDATE_DIMENSION Procedure on page 32-5	Verifies that the relationships specified in a dimension are correct

DESCRIBE_DIMENSION Procedure

This procedure displays the definition of the dimension, including dimension name, levels, hierarchies, and attributes. It displays the output using the `DBMS_OUTPUT` package.

Syntax

```
DBMS_DIMENSION.DESCRIBE_DIMENSION (  
    dimension IN VARCHAR2);
```

Parameters

Table 32–2 *DESCRIBE_DIMENSION Procedure Parameter*

Parameter	Description
<code>dimension</code>	The owner and name of the dimension in the format of <i>owner.name</i> .

VALIDATE_DIMENSION Procedure

This procedure verifies that the relationships specified in a dimension are valid. The rowid for any row that is found to be invalid will be stored in the table `DIMENSION_EXCEPTIONS` in the user's schema.

Syntax

```
DBMS_DIMENSION.VALIDATE_DIMENSION (
    dimension          IN VARCHAR2,
    incremental        IN BOOLEAN := TRUE,
    check_nulls       IN BOOLEAN := FALSE,
    statement_id       IN VARCHAR2 := NULL );
```

Parameters

Table 32–3 *VALIDATE_DIMENSION Procedure Parameters*

Parameter	Description
<code>dimension</code>	The owner and name of the dimension in the format of <code>owner.name</code> .
<code>incremental</code>	If <code>TRUE</code> , check only the new rows for tables of this dimension. If <code>FALSE</code> , check all the rows.
<code>check_nulls</code>	If <code>TRUE</code> , then all level columns are verified to be non-null. If <code>FALSE</code> , this check is omitted. Specify <code>FALSE</code> when non-nullness is guaranteed by other means, such as <code>NOT NULL</code> constraints.
<code>statement_id</code>	A client-supplied unique identifier to associate output rows with specific invocations of the procedure.

DBMS_DISTRIBUTED_TRUST_ADMIN

DBMS_DISTRIBUTED_TRUST_ADMIN procedures maintain the Trusted Servers List. Use these procedures to define whether a server is trusted. If a database is not trusted, Oracle refuses current user database links from the database.

This chapter contains the following topics:

- [Using DBMS_DISTRIBUTED_TRUST_ADMIN](#)
 - [Overview](#)
 - [Security Model](#)
 - [Examples](#)
- [Summary of DBMS_DISTRIBUTED_TRUST_ADMIN Subprograms](#)

Using DBMS_DISTRIBUTED_TRUST_ADMIN

- [Overview](#)
- [Security Model](#)
- [Examples](#)

Overview

Oracle uses local Trusted Servers Lists, along with enterprise domain membership lists stored in the enterprise LDAP directory service, to determine if another database is trusted. The LDAP directory service entries are managed with the Enterprise Security Manager Tool in Oracle Enterprise Manager.

Oracle considers another database to be "trusted" if it meets the following criteria:

1. It is in the same enterprise domain in the directory service as the local database.
2. The enterprise domain is marked as trusted in the directory service.
3. It is not listed as untrusted in the local Trusted Servers List. Current user database links will only be accepted from another database if both databases involved trust each other.

You can list a database server locally in the Trusted Servers List regardless of what is listed in the directory service. However, if you list a database that is not in the same domain as the local database, or if that domain is untrusted, the entry will have no effect.

This functionality is part of the Enterprise User Security feature of the Oracle Advanced Security Option.

Security Model

To execute `DBMS_DISTRIBUTED_TRUST_ADMIN`, the `EXECUTE_CATALOG_ROLE` role must be granted to the DBA. To select from the view `TRUSTED_SERVERS`, the `SELECT_CATALOG_ROLE` role must be granted to the DBA.

It is important to know whether all servers are trusted or not trusted. Trusting a particular server with the `ALLOW_SERVER` procedure does not have any effect if the database already trusts all databases, or if that database is already trusted. Similarly,

denying a particular server with the `DENY_SERVER` procedure does not have any effect if the database already does not trust any database or if that database is already untrusted.

The procedures `DENY_ALL` and `ALLOW_ALL` delete all entries (in other words, server names) that are explicitly allowed or denied using the `ALLOW_SERVER` procedure or `DENY_SERVER` procedure respectively.

Examples

If you have not yet used the package `DBMS_DISTRIBUTED_TRUST_ADMIN` to change the trust listing, by default you trust all databases in the same enterprise domain if that domain is listed as trusted in the directory service:

```
SELECT * FROM TRUSTED_SERVERS;
TRUST      NAME
-----
Trusted    All
```

Because all servers are currently trusted, you can execute the [DENY_SERVER Procedure](#) and specify that a particular server is not trusted:

```
EXECUTE DBMS_DISTRIBUTED_TRUST_ADMIN.DENY_SERVER
        ('SALES.US.AMERICAS.ACME_AUTO.COM');
PL/SQL procedure successfully completed.
```

```
SELECT * FROM TRUSTED_SERVERS;
TRUST      NAME
-----
Untrusted  SALES.US.AMERICAS.ACME_AUTO.COM
```

By executing the [DENY_ALL Procedure](#), you can choose to not trust any database server:

```
EXECUTE DBMS_DISTRIBUTED_TRUST_ADMIN.DENY_ALL;

PL/SQL procedure successfully completed.
```

```
SELECT * FROM TRUSTED_SERVERS;

TRUST      NAME
-----
Untrusted  All
```

The **ALLOW_SERVER Procedure** can be used to specify that one particular database is to be trusted:

```
EXECUTE DBMS_DISTRIBUTED_TRUST_ADMIN.ALLOW_SERVER  
      ('SALES.US.AMERICAS.ACME_AUTO.COM');
```

PL/SQL procedure successfully completed.

```
SELECT * FROM TRUSTED_SERVERS;
```

```
TRUST      NAME
```

```
-----
```

```
Trusted    SALES.US.AMERICAS.ACME_AUTO.COM
```

Summary of DBMS_DISTRIBUTED_TRUST_ADMIN Subprograms

Table 33–1 DBMS_DISTRIBUTED_TRUST_ADMIN Package Subprograms

Subprogram	Description
ALLOW_ALL Procedure on page 33-6	Empties the list and inserts a row indicating that all servers should be trusted
ALLOW_SERVER Procedure on page 33-7	Enables a specific server to be allowed access even though deny all is indicated in the list
DENY_ALL Procedure on page 33-8	Empties the list and inserts a row indicating that all servers should be untrusted
DENY_SERVER Procedure on page 33-9	Enables a specific server to be denied access even though allow all is indicated in the list

ALLOW_ALL Procedure

This procedure empties the Trusted Servers List and specifies that all servers that are members of a trusted domain in an enterprise directory service and that are in the same domain are allowed access.

The view `TRUSTED_SERVERS` will show "TRUSTED ALL" indicating that the database trusts all servers that are currently trusted by the enterprise directory service.

Syntax

```
DBMS_DISTRIBUTED_TRUST_ADMIN.ALLOW_ALL;
```

Usage Notes

`ALLOW_ALL` only applies to servers listed as trusted in the enterprise directory service and in the same enterprise domain.

ALLOW_SERVER Procedure

This procedure ensures that the specified server is considered trusted (even if you have previously specified "deny all").

Syntax

```
DBMS_DISTRIBUTED_TRUST_ADMIN.ALLOW_SERVER (  
    server IN VARCHAR2);
```

Parameters

Table 33–2 *ALLOW_SERVER Procedure Parameters*

Parameter	Description
server	Unique, fully-qualified name of the server to be trusted.

Usage Notes

If the Trusted Servers List contains the entry "deny all", then this procedure adds a specification indicating that a specific database (for example, DBx) is to be trusted.

If the Trusted Servers List contains the entry "allow all", and if there is no "deny DBx" entry in the list, then executing this procedure causes no change.

If the Trusted Servers List contains the entry "allow all", and if there is a "deny DBx" entry in the list, then that entry is deleted.

DENY_ALL Procedure

This procedure empties the Trusted Servers List and specifies that all servers are denied access.

The view `TRUSTED_SERVERS` will show "UNTRUSTED ALL" indicating that no servers are currently trusted.

Syntax

```
DBMS_DISTRIBUTED_TRUST_ADMIN.DENY_ALL;
```


DENY_SERVER Procedure

This procedure ensures that the specified server is considered untrusted (even if you have previously specified `allow all`).

Syntax

```
DBMS_DISTRIBUTED_TRUST_ADMIN.DENY_SERVER (  
    server IN VARCHAR2);
```

Parameters

Table 33–3 *DENY_SERVER Procedure Parameters*

Parameter	Description
<code>server</code>	Unique, fully-qualified name of the server to be untrusted.

Usage Notes

If the Trusted Servers List contains the entry `allow all`, then this procedure adds an entry indicating that the specified database (for example, `DBx`) is not to be trusted.

If the Trusted Servers List contains the entry `"deny all"`, and if there is no `"allow DBx"` entry in the list, then this procedure causes no change.

If the Trusted Servers List contains the entry `"deny all"`, and if there is an `"allow DBx"` entry, then this procedure causes that entry to be deleted.

The `DBMS_FGA` package provides fine-grained security functions.

See Also: *Oracle Database Application Developer's Guide - Fundamentals* for a fuller discussion and more usage information on `DBMS_FGA`.

This chapter contains the following topics:

- [Using DBMS_FGA](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_FGA Subprograms](#)

Using DBMS_FGA

- [Security Model](#)
- [Operational Notes](#)

Security Model

Execute privilege on DBMS_FGA is needed for administering audit policies. Because the audit function can potentially capture all user environment and application context values, policy administration should be executable by privileged users only.

Operational Notes

This package is available for only cost-based optimization. The rule-based optimizer may generate unnecessary audit records since audit monitoring can occur before row filtering. For both the rule-based optimizer and the cost-based optimizer, you can refer to DBA_FGA_AUDIT_TRAIL to analyze the SQL text and corresponding bind variables that are issued.

Summary of DBMS_FGA Subprograms

Table 34–1 DBMS_FGA Package Subprograms

Subprogram	Description
ADD_POLICY Procedure on page 34-4	Creates an audit policy using the supplied predicate as the audit condition
DISABLE_POLICY Procedure on page 34-8	Disables an audit policy
DROP_POLICY Procedure on page 34-9	Drops an audit policy
ENABLE_POLICY Procedure on page 34-10	Enables an audit policy

ADD_POLICY Procedure

This procedure creates an audit policy using the supplied predicate as the audit condition. The maximum number of FGA policies on any table or view object is 256.

Syntax

```
DBMS_FGA.ADD_POLICY(
    object_schema  VARCHAR2,
    object_name    VARCHAR2,
    policy_name    VARCHAR2,
    audit_condition VARCHAR2,
    audit_column   VARCHAR2,
    handler_schema VARCHAR2,
    handler_module VARCHAR2,
    enable         BOOLEAN,
    statement_types VARCHAR2,
    audit_trail    BINARY_INTEGER IN DEFAULT,
    audit_column_opts BINARY_INTEGER IN DEFAULT);
```

Parameters

Table 34–2 ADD_POLICY Procedure Parameters

Parameter	Description
object_schema	The schema of the object to be audited. Default value: NULL. (If NULL, the current effective user schema is assumed.)
object_name	The name of the object to be audited.
policy_name	The unique name of the policy.
audit_condition	A condition in a row that indicates a monitoring condition. NULL is allowed and acts as TRUE. Default value: NULL
audit_column	The columns to be checked for access. These can include hidden columns. The default, NULL, causes audit if any column is accessed or affected. Default value: NULL

Table 34–2 ADD_POLICY Procedure Parameters

Parameter	Description
handler_schema	The schema that contains the event handler. The default, NULL, causes the current schema to be used. Default value: NULL
handler_module	The function name of the event handler; includes the package name if necessary. This function is invoked only after the first row that matches the audit condition is processed in the query. If the procedure fails with exception, the user SQL statement will fail as well. Default value: NULL
enable	Enables the policy if TRUE, which is the default. Default value: TRUE
statement_types	The SQL statement types to which this policy is applicable: insert, update, delete, or select only. Default value: SELECT
audit_trail	Whether to populate LSQLTEXT and LSQLBIND in fga_log\$. Default value: DB_EXTENDED
audit_column_opts	Establishes whether a statement is audited when the query references <i>any</i> column specified in the audit_column parameter or only when <i>all</i> such columns are referenced. Default value: ANY_COLUMNS

Usage Notes

- **Example:** `DBMS_FGA.ADD_POLICY(object_schema => 'scott', object_name=>'emp', policy_name => 'mypolicy1', audit_condition => 'sal < 100', audit_column =>'comm, credit_card, expirn_date', handler_schema => NULL, handler_module => NULL, enable => TRUE, statement_types=> 'INSERT, UPDATE');`
- An FGA policy should not be applied to out-of-line columns such as LOB columns.
- If `object_schema` is NULL, the current effective user schema is assumed.
- The audit function (`handler_module`) is an alerting mechanism for the administrator; it must have the following interface:

```
PROCEDURE <fname> ( object_schema VARCHAR2, object_name VARCHAR2, policy_
name VARCHAR2 ) AS ...
```

where `fname` is the name of the procedure, `object_schema` is the name of the schema of the table audited, `object_name` is the name of the table to be audited, and `policy_name` is the name of the policy being enforced.

- Each audit policy is applied to the query individually. However, at most one audit record may be generated for each policy, no matter how many rows being returned satisfy that policy's audit_condition. In other words, whenever any number of rows being returned satisfy an audit condition defined on the table, a single audit record will be generated for each such policy.
- If a table with an FGA policy defined on it receives a Fast Path insert or a vectored update, the hint is automatically disabled before any such operations. Disabling the hint allows auditing to occur according to the policy's terms. (One example of a Fast Path insert is the statement `INSERT-WITH-APPEND-hint`.)
- The `audit_condition` must be a boolean expression that can be evaluated using the values in the row being inserted, updated, or deleted. This condition can be `NULL` (or omitted), which is interpreted as `TRUE`, but it cannot contain the following elements:
 - Subqueries or sequences
 - Any direct use of `SYSDATE`, `UID`, `USER` or `USERENV` functions. However, a user-defined function and other SQL functions can use these functions to return the desired information.
 - Any use of the pseudocolumns `LEVEL`, `PRIOR`, or `ROWNUM`.

Specifying an audit condition of `"1=1"` to force auditing of all specified statements ("`statement_types`") affecting the specified column ("`audit_column`") is no longer needed to achieve this purpose. `NULL` will cause audit even if no rows were processed, so that all actions on a table with this policy are audited.

- The `audit_trail` parameter specifies whether to record the query's SQL Text and SQL Bind variable information in the FGA audit trail (`fga_log$`) columns named `LSQLTEXT` and `LSQLBIND`:
 - To populate, set to `DBMS_FGA.DB_EXTENDED` (the default);
 - To leave unpopulated, set to `DBMS_FGA.DB`.

The `audit_trail` parameter appears in the `ALL_AUDIT_POLICIES` view.

- The `audit_column_opts` parameter establishes whether a statement is audited

- when the query references any column specified in the `audit_column` parameter (`audit_column_opts = DBMS_FGA.ANY_COLUMNS`), or
- only when all such columns are referenced (`audit_column_opts = DBMS_FGA.ALL_COLUMNS`).

The default is `DBMS_FGA.ANY_COLUMNS`.

The `ALL_AUDIT_POLICIES` view also shows `audit_column_opts`.

Examples

```
DBMS_FGA.ADD_POLICY (object_schema => 'scott', object_name=>'emp', policy_name
=> 'mypolicy1', audit_condition => 'sal < 100', audit_column =>'comm, credit_
card, expirn_date', handler_schema => NULL, handler_module => NULL, enable =>
TRUE, statement_types=> 'INSERT, UPDATE');
```

DISABLE_POLICY Procedure

This procedure disables an audit policy.

Syntax

```
DBMS_FGA.DISABLE_POLICY(  
    object_schema  VARCHAR2,  
    object_name    VARCHAR2,  
    policy_name    VARCHAR2 );
```

Parameters

Table 34–3 *DISABLE_POLICY Procedure Parameters*

Parameter	Description
<code>object_schema</code>	The schema of the object to be audited. (If NULL, the current effective user schema is assumed.)
<code>object_name</code>	The name of the object to be audited.
<code>policy_name</code>	The unique name of the policy.

The default value for `object_schema` is NULL. (If NULL, the current effective user schema is assumed.)

DROP_POLICY Procedure

This procedure drops an audit policy.

Syntax

```
DBMS_FGA.DROP_POLICY(  
    object_schema  VARCHAR2,  
    object_name    VARCHAR2,  
    policy_name    VARCHAR2 );
```

Parameters

Table 34–4 DROP_POLICY Procedure Parameters

Parameter	Description
object_schema	The schema of the object to be audited. (If NULL, the current effective user schema is assumed.)
object_name	The name of the object to be audited.
policy_name	The unique name of the policy.

Usage Notes

The DBMS_FGA procedures cause current DML transactions, if any, to commit before the operation. However, the procedures do not cause a commit first if they are inside a DDL event trigger. With DDL transactions, the DBMS_FGA procedures are part of the DDL transaction. The default value for object_schema is NULL. (If NULL, the current effective user schema is assumed.)

ENABLE_POLICY Procedure

This procedure enables an audit policy.

Syntax

```
DBMS_FGA.ENABLE_POLICY(  
    object_schema  VARCHAR2,  
    object_name    VARCHAR2,  
    policy_name    VARCHAR2,  
    enable         BOOLEAN);
```

Parameters

Table 34–5 *ENABLE_POLICY Procedure Parameters*

Parameter	Description
object_schema	The schema of the object to be audited. (If NULL, the current effective user schema is assumed.)
object_name	The name of the object to be audited.
policy_name	The unique name of the policy.
enable	Defaults to TRUE to enable the policy.

DBMS_FILE_TRANSFER

The `DBMS_FILE_TRANSFER` package provides procedures to copy a binary file within a database or to transfer a binary file between databases.

See Also:

- *Oracle Database Concepts* for conceptual information about file transfer
- *Oracle Database Administrator's Guide* for instructions about using file transfer
- *Oracle Streams Concepts and Administration for applications of file transfer.*

This chapter contains the following topic:

- [Summary of DBMS_FILE_TRANSFER Subprograms](#)

Summary of DBMS_FILE_TRANSFER Subprograms

Table 35–1 *DBMS_FILE_TRANSFER Package Subprograms*

Subprogram	Description
COPY_FILE Procedure on page 35-3	Reads a local file and creates a copy of it in the local file system
GET_FILE Procedure on page 35-5	Contacts a remote database to read a remote file and then creates a copy of the file in the local file system
PUT_FILE Procedure on page 35-7	Reads a local file and contacts a remote database to create a copy of the file in the remote file system

COPY_FILE Procedure

This procedure reads a local file and creates a copy of it in the local file system. The file that is copied is the source file, and new file that results from the copy is the destination file. The destination file is not closed until the procedure completes successfully.

Syntax

```
DBMS_FILE_TRANSFER.COPY_FILE(
    source_directory_object    IN  VARCHAR2,
    source_file_name          IN  VARCHAR2,
    destination_directory_object IN  VARCHAR2,
    destination_file_name     IN  VARCHAR2);
```

Parameters

Table 35–2 COPY_FILE Procedure Parameters

Parameter	Description
source_directory_object	The directory object from which the file is copied in the local file system. This directory object must exist.
source_file_name	The name of the file that is copied in the local file system. This file must exist in the local file system in the directory associated with the source directory object.
destination_directory_object	The directory object into which the file is placed in the local file system. This directory object must exist in the local file system.
destination_file_name	The name of the file copied to the destination directory object in the local file system. A file with the same name must not exist in the destination directory in the local file system.

Usage Notes

To run this procedure successfully, the current user must have the following privileges:

- Read privilege on the directory object specified in the `source_directory_object` parameter

- Write privilege on directory object specified in the `destination_directory_object` parameter

This procedure converts directory object parameters to uppercase unless they are surrounded by double quotation marks, but this procedure does not convert file names to uppercase.

Also, the copied file must meet the following requirements:

- The size of the copied file must be a multiple of 512 bytes.
- The size of the copied file must be less than or equal to two terabytes.

Transferring the file is not transactional. The copied file is treated as a binary file, and no character set conversion is performed. To monitor the progress of a long file copy, query the `V$SESSION_LONGOPS` dynamic performance view.

GET_FILE Procedure

This procedure contacts a remote database to read a remote file and then creates a copy of the file in the local file system. The file that is copied is the source file, and the new file that results from the copy is the destination file. The destination file is not closed until the procedure completes successfully.

Syntax

```
DBMS_FILE_TRANSFER.GET_FILE
    source_directory_object    IN  VARCHAR2,
    source_file_name          IN  VARCHAR2,
    source_database           IN  VARCHAR2,
    destination_directory_object IN VARCHAR2,
    destination_file_name     IN  VARCHAR2);
```

Parameters

Table 35-3 *GET_FILE Procedure Parameters*

Parameter	Description
source_directory_object	The directory object from which the file is copied at the source site. This directory object must exist at the source site.
source_file_name	The name of the file that is copied in the remote file system. This file must exist in the remote file system in the directory associated with the source directory object.
source_database	The name of a database link to the remote database where the file is located.
destination_directory_object	The directory object into which the file is placed at the destination site. This directory object must exist in the local file system.
destination_file_name	The name of the file copied to the local file system. A file with the same name must not exist in the destination directory in the local file system.

Usage Notes

To run this procedure successfully, the following users must have the following privileges:

- The connected user at the source database must have read privilege on the directory object specified in the `source_directory_object` parameter.
- The current user at the local database must have write privilege on the directory object specified in the `destination_directory_object` parameter.

This procedure converts directory object parameters to uppercase unless they are surrounded by double quotation marks, but this procedure does not convert file names to uppercase.

Also, the copied file must meet the following requirements:

- The size of the copied file must be a multiple of 512 bytes.
- The size of the copied file must be less than or equal to two terabytes.

Transferring the file is not transactional. The copied file is treated as a binary file, and no character set conversion is performed. To monitor the progress of a long file transfer, query the `V$SESSION_LONGOPS` dynamic performance view.

PUT_FILE Procedure

This procedure reads a local file and contacts a remote database to create a copy of the file in the remote file system. The file that is copied is the source file, and the new file that results from the copy is the destination file. The destination file is not closed until the procedure completes successfully.

Syntax

```
DBMS_FILE_TRANSFER.PUT_FILE(
    source_directory_object    IN  VARCHAR2,
    source_file_name          IN  VARCHAR2,
    destination_directory_object IN  VARCHAR2,
    destination_file_name     IN  VARCHAR2,
    destination_database      IN  VARCHAR2);
```

Parameters

Table 35–4 *PUT_FILE Procedure Parameters*

Parameter	Description
source_directory_object	The directory object from which the file is copied at the local source site. This directory object must exist at the source site.
source_file_name	The name of the file that is copied from the local file system. This file must exist in the local file system in the directory associated with the source directory object.
destination_directory_object	The directory object into which the file is placed at the destination site. This directory object must exist in the remote file system.
destination_file_name	The name of the file placed in the remote file system. A file with the same name must not exist in the destination directory in the remote file system.
destination_database	The name of a database link to the remote database to which the file is copied.

Usage Notes

To run this procedure successfully, the following users must have the following privileges:

- The current user at the local database must have read privilege on the directory object specified in the `source_directory_object` parameter.
- The connected user at the destination database must have write privilege to the directory object specified in the `destination_directory_object` parameter.

This procedure converts directory object parameters to uppercase unless they are surrounded by double quotation marks, but this procedure does not convert file names to uppercase.

Also, the copied file must meet the following requirements:

- The size of the copied file must be a multiple of 512 bytes.
- The size of the copied file must be less than or equal to two terabytes.

Transferring the file is not transactional. The copied file is treated as a binary file, and no character set conversion is performed. To monitor the progress of a long file transfer, query the `V$SESSION_LONGOPS` dynamic performance view.

DBMS_FLASHBACK

Using `DBMS_FLASHBACK`, you can flash back to a version of the database at a specified wall-clock time or a specified system change number (SCN)

See Also: *Oracle Database Application Developer's Guide - Fundamentals* and *Oracle Database SQL Reference* for detailed information about `DBMS_FLASHBACK`.

This chapter contains the following topics:

- [Using DBMS_FLASHBACK](#)
 - [Overview](#)
 - [Security Model](#)
 - [Exceptions](#)
 - [Operational Notes](#)
 - [Examples](#)
- [Summary of DBMS_FLASHBACK Subprograms](#)

Using DBMS_FLASHBACK

- [Overview](#)
- [Security Model](#)
- [Exceptions](#)
- [Operational Notes](#)
- [Examples](#)

Overview

When `DBMS_FLASHBACK` is enabled, the user session uses the Flashback version of the database, and applications can execute against the Flashback version of the database.

You may want to use `DBMS_FLASHBACK` for the following reasons:

- **Self-service repair:** If you accidentally delete rows from a table, you can recover the deleted rows.
- **Packaged applications such as e-mail and voicemail:** You can use Flashback to restore deleted e-mail by re-inserting the deleted message into the current message box.
- **Decision support system (DSS) and online analytical processing (OLAP) applications:** You can perform data analysis or data modeling to track seasonal demand.

Security Model

To use this package, a database administrator must grant `EXECUTE` privileges for `DBMS_FLASHBACK`.

Exceptions

Table 36–1 DBMS_FLASHBACK Error Messages

Error	Description
ORA-08180	Time specified is too old.
ORA-08181	Invalid system change number specified.
ORA-08182	User cannot begin read-only or serializable transactions in Flashback mode.
ORA-08183	User cannot enable Flashback within an uncommitted transaction.
ORA-08184	User cannot enable Flashback within another Flashback session.
ORA-08185	SYS cannot enable Flashback mode.

Operational Notes

DBMS_FLASHBACK is automatically turned off when the session ends, either by disconnection or by starting another connection.

PL/SQL cursors opened in Flashback mode return rows as of the flashback time or SCN. Different concurrent sessions (connections) in the database can perform Flashback to different wall-clock times or SCNs. DML and DDL operations and distributed operations are not allowed while a session is running in Flashback mode. You can use PL/SQL cursors opened before disabling Flashback to perform DML.

Under Automatic Undo Management (AUM) mode, you can use retention control to control how far back in time to go for the version of the database you need. If you need to perform a Flashback over a 24-hour period, the DBA should set the `undo_retention` parameter to 24 hours. This way, the system retains enough undo information to regenerate the older versions of the data.

You can set the `RETENTION GUARANTEE` clause for the undo tablespace to ensure that unexpired undo is not discarded. `UNDO_RETENTION` is not in itself a complete guarantee because, if the system is under space pressure, unexpired undo may be overwritten with freshly generated undo. In such cases, `RETENTION GUARANTEE` prevents this. For more information, see the *Oracle Database Administrator's Guide*

In a Flashback-enabled session, `SYSDATE` will not be affected; it will continue to provide the current time.

DBMS_FLASHBACK can be used within logon triggers to enable Flashback without changing the application code.

Examples

The following example illustrates how Flashback can be used when the deletion of a senior employee triggers the deletion of all the personnel reporting to him. Using the Flashback feature, you can recover and re-insert the missing employees.

```
DROP TABLE employee;
DROP TABLE keep_scn;
```

REM keep_scn is a temporary table to store scns that we are interested in

```
CREATE TABLE keep_scn (scn number);
SET ECHO ON
CREATE TABLE employee (
    employee_no    number(5) PRIMARY KEY,
    employee_name  varchar2(20),
    employee_mgr   number(5)
        CONSTRAINT mgr_fkey REFERENCES EMPLOYEE ON DELETE CASCADE,
    salary         number,
    hiredate      date
);
```

REM Populate the company with employees

```
INSERT INTO employee VALUES (1, 'John Doe', null, 1000000, '5-jul-81');
INSERT INTO employee VALUES (10, 'Joe Johnson', 1, 500000, '12-aug-84');
INSERT INTO employee VALUES (20, 'Susie Tiger', 10, 250000, '13-dec-90');
INSERT INTO employee VALUES (100, 'Scott Tiger', 20, 200000, '3-feb-86');
INSERT INTO employee VALUES (200, 'Charles Smith', 100, 150000, '22-mar-88');
INSERT INTO employee VALUES (210, 'Jane Johnson', 100, 100000, '11-apr-87');
INSERT INTO employee VALUES (220, 'Nancy Doe', 100, 100000, '18-sep-93');
INSERT INTO employee VALUES (300, 'Gary Smith', 210, 75000, '4-nov-96');
INSERT INTO employee VALUES (310, 'Bob Smith', 210, 65000, '3-may-95');
COMMIT;
```

REM Show the entire org

```
SELECT lpad(' ', 2*(level-1)) || employee_name Name
FROM employee
CONNECT BY PRIOR employee_no = employee_mgr
START WITH employee_no = 1
ORDER BY LEVEL;
```

*REM Sleep for a short time (approximately 10 to 20 seconds) to avoid querying
REM close to table creation*

```
EXECUTE DBMS_LOCK.SLEEP(10);
```

REM Store this snapshot for later access through Flashback

```
DECLARE
I NUMBER;
BEGIN
I := DBMS_FLASHBACK.GET_SYSTEM_CHANGE_NUMBER;
INSERT INTO keep_scn VALUES (I);
COMMIT;
END;
/
```

REM Scott decides to retire but the transaction is done incorrectly

```
DELETE FROM EMPLOYEE WHERE employee_name = 'Scott Tiger';
COMMIT;
```

REM notice that all of scott's employees are gone

```
SELECT lpad(' ', 2*(level-1)) || employee_name Name
FROM EMPLOYEE
CONNECT BY PRIOR employee_no = employee_mgr
START WITH employee_no = 1
ORDER BY LEVEL;
```

REM Flashback to see Scott's organization

```
DECLARE
    restore_scn number;
BEGIN
    SELECT scn INTO restore_scn FROM keep_scn;
    DBMS_FLASHBACK.ENABLE_AT_SYSTEM_CHANGE_NUMBER (restore_scn);
END;
/
```

REM Show Scott's org.

```
SELECT lpad(' ', 2*(level-1)) || employee_name Name
FROM employee
CONNECT BY PRIOR employee_no = employee_mgr
START WITH employee_no =
    (SELECT employee_no FROM employee WHERE employee_name = 'Scott Tiger')
ORDER BY LEVEL;
```

REM Restore scott's organization.

```
DECLARE
    scotts_emp NUMBER;
    scotts_mgr NUMBER;
    CURSOR c1 IS
        SELECT employee_no, employee_name, employee_mgr, salary, hiredate
        FROM employee
        CONNECT BY PRIOR employee_no = employee_mgr
        START WITH employee_no =
            (SELECT employee_no FROM employee WHERE employee_name = 'Scott Tiger');
    c1_rec c1 % ROWTYPE;
BEGIN
    SELECT employee_no, employee_mgr INTO scotts_emp, scotts_mgr FROM employee
    WHERE employee_name = 'Scott Tiger';
    /* Open c1 in flashback mode */
    OPEN c1;
    /* Disable Flashback */
    DBMS_FLASHBACK.DISABLE;
LOOP
    FETCH c1 INTO c1_rec;
    EXIT WHEN c1%NOTFOUND;
    /*
        Note that all the DML operations inside the loop are performed
        with Flashback disabled
    */
    IF (c1_rec.employee_mgr = scotts_emp) then
        INSERT INTO employee VALUES (c1_rec.employee_no,
            c1_rec.employee_name,
            scotts_mgr,
            c1_rec.salary,
            c1_rec.hiredate);
    ELSE
        IF (c1_rec.employee_no != scotts_emp) THEN
            INSERT INTO employee VALUES (c1_rec.employee_no,
                c1_rec.employee_name,
                c1_rec.employee_mgr,
                c1_rec.salary,
                c1_rec.hiredate);
        END IF;
    END IF;
END LOOP;
END;
/

REM Show the restored organization.
select lpad(' ', 2*(level-1)) || employee_name Name
```

```
FROM employee
CONNECT BY PRIOR employee_no = employee_mgr
START WITH employee_no = 1
ORDER BY LEVEL;
```

Summary of DBMS_FLASHBACK Subprograms

Table 36–2 DBMS_FLASHBACK Package Subprograms

Subprogram	Description
DISABLE Procedure on page 36-9	Disables the Flashback mode for the entire session
ENABLE_AT_SYSTEM_CHANGE_NUMBER Procedure on page 36-10	Enables Flashback for the entire session. Takes an SCN as an Oracle number and sets the session snapshot to the specified number. Inside the Flashback mode, all queries will return data consistent as of the specified wall-clock time or SCN
ENABLE_AT_TIME Procedure on page 36-11	Enables Flashback for the entire session. The snapshot time is set to the SCN that most closely matches the time specified in <code>query_time</code>
GET_SYSTEM_CHANGE_NUMBER Function on page 36-12	Returns the current SCN as an Oracle number. You can use the SCN to store specific snapshots
SCN_TO_TIMESTAMP Function on page 36-13	Takes the current SCN as an Oracle number datatype and returns a <code>TIMESTAMP</code> .
TIMESTAMP_TO_SCN Function on page 36-14	Takes a <code>TIMESTAMP</code> as input and returns the current SCN as an Oracle number datatype

DISABLE Procedure

This procedure disables the Flashback mode for the entire session.

Syntax

```
DBMS_FLASHBACK.DISABLE;
```

Examples

The following example queries the salary of an employee, Joe, on August 30, 2000:

```
EXECUTE dbms_flashback.enable_at_time('30-AUG-2000');  
SELECT salary FROM emp where name = 'Joe'  
EXECUTE dbms_flashback.disable;
```

ENABLE_AT_SYSTEM_CHANGE_NUMBER Procedure

This procedure takes an SCN as an input parameter and sets the session snapshot to the specified number. In the Flashback mode, all queries return data consistent as of the specified wall-clock time or SCN. It enables Flashback for the entire session.

Syntax

```
DBMS_FLASHBACK.ENABLE_AT_SYSTEM_CHANGE_NUMBER (  
    query_scn IN NUMBER);
```

Parameters

Table 36–3 *ENABLE_AT_SYSTEM_CHANGE_NUMBER Procedure Parameters*

Parameter	Description
query_scn	The system change number (SCN), a version number for the database that is incremented on every transaction commit.

ENABLE_AT_TIME Procedure

This procedure enables Flashback for the entire session. The snapshot time is set to the SCN that most closely matches the time specified in `query_time`. It enables Flashback for the entire session.

Syntax

```
DBMS_FLASHBACK.ENABLE_AT_TIME (
    query_time    IN TIMESTAMP);
```

Parameters

Table 36–4 *ENABLE_AT_TIME Procedure Parameters*

Parameter	Description
<code>query_time</code>	<p>This is an input parameter of type <code>TIMESTAMP</code>. A time stamp can be specified in the following ways:</p> <ul style="list-style-type: none"> ■ Using the <code>TIMESTAMP</code> constructor: Example: <code>execute dbms_flashback.enable_at_time(TIMESTAMP '2001-01-09 12:31:00')</code>. Use the Globalization Support (NLS) format and supply a string. The format depends on the Globalization Support settings. ■ Using the <code>TO_TIMESTAMP</code> function: Example: <code>execute dbms_flashback.enable_at_time(TO_TIMESTAMP('12-02-2001 14:35:00', 'DD-MM-YYYY HH24:MI:SS'))</code>. You provide the format you want to use. This example shows the <code>TO_TIMESTAMP</code> function for February 12, 2001, 2:35 PM. ■ If the time is omitted from query time, it defaults to the beginning of the day, that is, 12:00 A.M. ■ Note that if the query time contains a time zone, the time zone information is truncated.

GET_SYSTEM_CHANGE_NUMBER Function

This function returns the current SCN as an Oracle number datatype. You can obtain the current change number and store it for later use. This helps you retain specific snapshots.

Syntax

```
DBMS_FLASHBACK.GET_SYSTEM_CHANGE_NUMBER  
RETURN NUMBER;
```


SCN_TO_TIMESTAMP Function

This function takes the SCN as an Oracle number datatype and returns the corresponding `TIMESTAMP`.

Syntax

```
DBMS_FLASHBACK.SCN_TO_TIMESTAMP  
  query_scn IN      NUMBER)  
RETURN TIMESTAMP;
```

Parameters

Table 36–5 *SCN_TO_TIMESTAMP Procedure Parameters*

Parameter	Description
<code>query_scn</code>	The system change number (SCN), a version number for the database that is incremented on every transaction commit.

TIMESTAMP_TO_SCN Function

This function takes a `TIMESTAMP` as input and returns the corresponding SCN as an Oracle number datatype.

Syntax

```
DBMS_FLASHBACK.TIMESTAMP_TO_SCN  
  query_time IN      TIMESTAMP  
RETURN NUMBER);
```

Parameters

Table 36–6 *TIMESTAMP_TO_SCN Procedure Parameters*

Parameter	Description
<code>query_time</code>	<p>This is an input parameter of type <code>TIMESTAMP</code>. A time stamp can be specified in the following ways:</p> <ul style="list-style-type: none">■ Using the <code>TIMESTAMP</code> constructor: Example: execute <code>DBMS_FLASHBACK.ENABLE_AT_TIME(TIMESTAMP '2001-01-09 12:31:00')</code>. Use the Globalization Support (NLS) format and supply a string. The format depends on the Globalization Support settings.■ Using the <code>TO_TIMESTAMP</code> function: Example: execute <code>dbms_flashback.enable_at_time(TO_TIMESTAMP('12-02-2001 14:35:00', 'DD-MM-YYYY HH24:MI:SS'))</code>. You provide the format you want to use. This example shows the <code>TO_TIMESTAMP</code> function for February 12, 2001, 2:35 PM.■ If the time is omitted from query time, it defaults to the beginning of the day, that is, 12:00 A.M.■ Note that if the query time contains a time zone, the time zone information is truncated.

DBMS_FREQUENT_ITEMSET

The DBMS_FREQUENT_ITEMSET package enables frequent itemset counting. The two functions are identical except in the input cursor format difference.

This chapter contains the following topics:

- [Summary of DBMS_FREQUENT_ITEMSET Subprograms](#)

Summary of DBMS_FREQUENT_ITEMSET Subprograms

Table 37–1 *DBMS_FREQUENT_ITEMSET Package Subprograms*

Subprogram	Description
FI_TRANSACTIONAL Function on page 37-3	Counts all frequent itemsets given a cursor for input data which is in 'TRANSACTIONAL' row format, support threshold, minimum itemset length, maximum itemset length, items to be included, items to be excluded
FI_HORIZONTAL Function on page 37-8	Counts all frequent itemsets given a cursor for input data which is in 'HORIZONTAL' row format, support threshold, minimum itemset length, maximum itemset length, items to be included, items to be excluded

FI_TRANSACTIONAL Function

This procedure counts all frequent itemsets given a cursor for input data which is in 'TRANSACTIONAL' row format, support threshold, minimum itemset length, maximum itemset length, items to be included, items to be excluded. The result will be a table of rows in form of itemset, support, length, total number of transactions.

In 'TRANSACTIONAL' row format, each transaction is spread across multiple rows. All the rows of a given transaction have the same transaction id, and each row has a different item id. Combining all of the item ids which share a given transaction id results in a single transaction.

Syntax

```
DBMS_FREQUENT_ITEMSET.FI_TRANSACTIONAL (
  tranx_cursor      IN   SYSREFCURSOR,
  support_threshold IN   NUMBER,
  itemset_length_min IN  NUMBER,
  itemset_length_max IN  NUMBER,
  including_items   IN   SYS_REFCURSOR DEFAULT NULL,
  excluding_items   IN   SYS_REFCURSOR DEFAULT NULL)
RETURN TABLE OF ROW (
  itemset [Nested Table of Item Type DERIVED FROM tranx_cursor],
  support      NUMBER,
  length       NUMBER,
  total_tranx  NUMBER);
```

Parameters

Table 37-2 *FI_TRANSACTIONAL Procedure Parameters*

Parameter	Description
tranx_cursor	The cursor parameter that the user will supply when calling the function. It should return two columns in its returning row, the first column being the transaction id, the second column being the item id. The item id must be number or character type (for example, VARCHAR2(n)).
support_threshold	A fraction number of total transaction count. An itemset is termed "frequent" if [the number of transactions it occurs in] divided by [the total number of transactions] exceed the fraction. The parameter must be a NUMBER.

Table 37–2 (Cont.) FI_TRANSACTIONAL Procedure Parameters

Parameter	Description
<code>itemset_length_min</code>	The minimum length for interested frequent itemset. The parameter must be a <code>NUMBER</code> between 1 and 20, inclusive.
<code>itemset_length_max</code>	The maximum length for interested frequent itemset. This parameter must be a <code>NUMBER</code> between 1 and 20, inclusive, and must not be less than <code>itemset_length_min</code> .
<code>including_items</code>	A cursor from which a list of items can be fetched. At least one item from the list must appear in frequent itemsets that will be returned. The default is <code>NULL</code> .
<code>excluding_items</code>	A cursor from which a list of items can be fetched. No item from the list can appear in frequent itemsets that will returned. The default is <code>NULL</code> .

Return Values

Table 37–3 FI_TRANSACTIONAL Procedure Parameters

Parameter	Description
<code>support</code>	The number of transactions in which a frequent itemset occurs. This will be returned as a <code>NUMBER</code> .
<code>itemset</code>	A collection of items which is computed as frequent itemset. This will be returned as a nested table of item type which is the item column type of the input cursor.
<code>length</code>	Number of items in a frequent itemset. This will be returned as a <code>NUMBER</code> .
<code>total_tranx</code>	The total transaction count. This will be returned as a <code>NUMBER</code> , and will be the same for all returned rows, similar to a reporting aggregate.

Usage Notes

Applications must predefine a nested table type of the input item type and cast the output itemset into this predefined nested table type before further processing, such as loading into a table.

Examples

Suppose that the input table `tranx_table_in` looks as follows:

```
(1, 'apple')
```

```
(1, 'banana')
(2, 'apple')
(2, 'milk')
(2, 'banana')
(3, 'orange')
```

and the user is trying to find itemsets that satisfy a support-threshold of 60% and have the itemset-length greater than 1 (namely, (apple, banana)).

The output of this function would contain the following output row:

```
itemset=('apple','banana'), support=2, length=2, total_tranx=3
```

You need to create a nested table of item type before you submit a query to perform the frequent itemset counting. In this example, since item is of VARCHAR2(30), you must create a nested table of VARCHAR2(30):

```
CREATE TYPE fi_varchar_nt AS TABLE OF VARCHAR2(30);
SELECT CAST(itemset as FI_VARCHAR_NT) itemset, support, length, total_tranx
FROM table(DBMS_FREQUENT_ITEMSET.FI_TRANSACTIONAL(
    cursor(SELECT tid, iid FROM tranx_table_in),
    0.6,
    2,
    5,
    NULL,
    NULL));
```

Here is another example to illustrate how to include certain items and exclude certain items in the counting.

```
SELECT CAST(itemset as FI_VARCHAR_NT) itemset, support, length, total_tranx
FROM table(DBMS_FREQUENT_ITEMSET.FI_TRANSACTIONAL(
    CURSOR(SELECT tid, iid FROM tranx_table_in),
    0.6,
    2,
    5,
    CURSOR(SELECT * FROM table(FI_VARCHAR_NT
        ('apple','banana','orange'))),
    CURSOR(SELECT * FROM table(FI_VARCHAR_NT('milk'))));
```

Using the including/excluding items parameter, you are able to further optimize the execution by ignoring itemsets that are not expected by application.

You can also use transactional output through collection unnesting:

```
SELECT
    bt.setid, nt.*
```

```

FROM
(SELECT cast(Itemset as FI_VARCHAR_NT) itemset, rownum setid
 FROM table(
   DBMS_FREQUENT_ITEMSET.FI_TRANSACTIONAL(
     CURSOR(SELECT tid, iid FROM tranx_table_in), 0.6, 2, 5,
     NULL, NULL)) bt,
 table(bt.itemset) nt;

```

If you want to use an insert statement to load frequent itemsets into a nested table, it is better to use the NESTED_TABLE_FAST_INSERT hint for performance:

```

CREATE TABLE fq_nt (coll FI_VARCHAR_NT) NESTED TABLE coll STORE AS
  coll_nest;
INSERT /*+ NESTED_TABLE_FAST_INSERT */ INTO fq_nt
  SELECT cast(itemset as FI_VARCHAR_NT)
  FROM table(DBMS_FREQUENT_ITEMSET.FI_TRANSACTIONAL(
    cursor(SELECT tid, iid FROM tranx_table_in), 0.6, 2, 5,
    NULL, NULL));

```

Note that if you want to use the package inside a PL/SQL cursor, you must cast the return type of the table function:

```

CREATE TYPE fi_res AS OBJECT (
  itemset      FI_VARCHAR_NT,
  support      NUMBER,
  length       NUMBER,
  total_tranx  NUMBER
);
/
CREATE TYPE fi_coll AS TABLE OF fi_res;
/

DECLARE
  cursor freqC is
    SELECT Itemset
    FROM table(
      CAST(DBMS_FREQUENT_ITEMSET.FI_TRANSACTIONAL(
        cursor(SELECT tid, iid FROM tranx_table_in), 0.6, 2, 5,
        NULL, NULL) AS fi_coll));
  coll_nt  FI_VARCHAR_NT;
  num_rows int;
  num_itms int;
BEGIN
  num_rows := 0;
  num_itms := 0;
  OPEN freqC;

```



```
LOOP
  FETCH freqC INTO coll_nt;
  EXIT WHEN freqC%NOTFOUND;
  num_rows := num_rows + 1;
  num_itms := num_itms + coll_nt.count;
END LOOP;
CLOSE freqC;
DBMS_OUTPUT.PUT_LINE('Totally ' || num_rows || ' rows ' || num_itms || '
items were produced.');
```

```
END;
/
```

FI_HORIZONTAL Function

The purpose of this table function is to count all frequent itemsets given a cursor for input data which is in 'HORIZONTAL' row format, support threshold, minimum itemset length, maximum itemset length, items to be included, items to be excluded. The result will be a table of rows in form of itemset, support, length, total transactions counted.

In 'HORIZONTAL' row format, each row contains all of the item ids for a single transaction. Since all of the items come together, no transaction id is necessary.

The benefit of this table function is that if an application already has data in horizontal format, the database can skip the step of transforming rows that are in transactional format into horizontal format.

Syntax

```
DBMS_FREQUENT_ITEMSET.FI_HORIZONTAL(
    tranx_cursor      IN      SYSREFCURSOR,
    support_threshold IN      NUMBER,
    itemset_length_min IN    NUMBER,
    itemset_length_max IN    NUMBER,
    including_items   IN      SYS_REFCURSOR DEFAULT NULL,
    excluding_items   IN      SYS_REFCURSOR DEFAULT NULL)
RETURN TABLE OF ROW (
    itemset [Nested Table of Item Type DERIVED FROM tranx_cursor],
    support      NUMBER,
    length       NUMBER,
    total_tranx  NUMBER);
```

Parameters

Table 37–4 *FI_HORIZONTAL Procedure Parameters*

Parameter	Description
tranx_cursor	The cursor parameter that the user will supply when calling the function. There is no limits on the number of returning columns. Each column of cursor represents an item. All columns of the cursor must be of the same data type. The item id must be number or character type (for example, VARCHAR2(n)).

Table 37–4 (Cont.) FI_HORIZONTAL Procedure Parameters

Parameter	Description
support_threshold	A fraction number of total transaction count. An itemset is termed "frequent" if [the number of transactions it occurs in] divided by [the total number of transactions] exceed the fraction. The parameter must be a NUMBER.
itemset_length_min	The minimum length for interested frequent itemset. The parameter must be a NUMBER between 1 and 20, inclusive.
itemset_length_max	The maximum length for interested frequent itemset. This parameter must be a NUMBER between 1 and 20, inclusive, and must not be less than itemset_length_min.
including_items	A cursor from which a list of items can be fetched. At least one item from the list must appear in frequent itemsets that are returned. The default is NULL.
excluding_items	A cursor from which a list of items can be fetched. No item from the list can appear in frequent itemsets that are returned. The default is NULL.

Return Values

Table 37–5 FI_HORIZONTAL Procedure Parameters

Parameter	Description
support	The number of transactions in which a frequent itemset occurs. This will be returned as a NUMBER.
itemset	A collection of items which is computed as frequent itemset. This will be returned as a nested table of item type which is the item column type of the input cursor.
length	Number of items in a frequent itemset. This will be returned as a NUMBER.
total_tranx	The total transaction count. This will be returned as a NUMBER.

Example

Suppose you have a table `horiz_table_in`.

```
horiz_table_in(iid1 VARCHAR2(30), iid2 VARCHAR2(30), iid3 VARCHAR2(30), iid4
VARCHAR2(30), iid5 VARCHAR2(30));
```

and the data in `horiz_table_in` looks as follows:

```

('apple', 'banana', NULL, NULL, NULL)
('apple', 'milk', 'banana', NULL, NULL)
('orange', NULL, NULL, NULL, NULL)

```

Suppose you want to find out what combinations of items is frequent with a given support threshold of 30%, requiring itemset containing at least one of ('apple','banana','orange'), but excluding any of ('milk') in any itemset. You use the following query:

```

CREATE TYPE fi_varchar_nt AS TABLE OF VARCHAR2(30);
SELECT CAST(itemset as FI_VARCHAR_NT)itemset, support, length, total_tranx
  FROM table(DBMS_FREQUENT_ITEMSET.FI_HORIZONTAL(
            CURSOR(SELECT iid1, iid2, iid3, iid4, iid5
                    FROM horiz_table_in),
            0.3,
            2,
            5,
            CURSOR(SELECT * FROM table(FI_VARCHAR_NT
                                     ('apple','banana','orange'))),
            CURSOR(SELECT * FROM table(FI_VARCHAR_NT('milk'))));

```

DBMS_HS_PASSTHROUGH

The pass-through SQL feature allows an application developer to send a statement directly to a non-Oracle system without being interpreted by the Oracle server. This can be useful if the non-Oracle system allows for operations in statements for which there is no equivalent in Oracle.

You can run these statements directly at the non-Oracle system using the PL/SQL package `DBMS_HS_PASSTHROUGH`. Any statement executed with this package is run in the same transaction as regular "transparent" SQL statements.

This chapter discusses the following topic:

- [Summary of DBMS_HS_PASSTHROUGH Subprograms](#)

See Also: *Oracle Database Heterogeneous Connectivity Administrator's Guide*

Summary of DBMS_HS_PASSTHROUGH Subprograms

Table 38–1 DBMS_HS_PASSTHROUGH Package Subprograms

Subprogram	Description
BIND_VARIABLE Procedure on page 38-3	Binds an IN variable positionally with a PL/SQL program variable
BIND_VARIABLE_RAW Procedure on page 38-5	Binds IN variables of type RAW
BIND_OUT_VARIABLE Procedure on page 38-7	Binds an OUT variable with a PL/SQL program variable
BIND_OUT_VARIABLE_RAW Procedure on page 38-9	Binds an OUT variable of datatype RAW with a PL/SQL program variable
BIND_INOUT_VARIABLE Procedure on page 38-11	Binds IN OUT bind variables
BIND_INOUT_VARIABLE_RAW Procedure on page 38-13	Binds IN OUT bind variables of datatype RAW
CLOSE_CURSOR Procedure on page 38-15	Closes the cursor and releases associated memory after the SQL statement has been run at the non-Oracle system
EXECUTE_IMMEDIATE Procedure on page 38-16	Runs a (non-SELECT) SQL statement immediately, without bind variables
EXECUTE_NON_QUERY Function on page 38-17	Runs a (non-SELECT) SQL statement
FETCH_ROW Function on page 38-18	Fetches rows from a query
GET_VALUE Procedure on page 38-20	Retrieves column value from SELECT statement, or retrieves OUT bind parameters
GET_VALUE_RAW Procedure on page 38-22	Similar to GET_VALUE, but for datatype RAW
OPEN_CURSOR Function on page 38-24	Opens a cursor for running a passthrough SQL statement at the non-Oracle system
PARSE Procedure on page 38-25	Parses SQL statement at non-Oracle system

BIND_VARIABLE Procedure

This procedure binds an IN variable positionally with a PL/SQL program variable.

Syntax

```
DBMS_HS_PASSTHROUGH.BIND_VARIABLE (
  c      IN BINARY_INTEGER NOT NULL,
  p      IN BINARY_INTEGER NOT NULL,
  v      IN <dt>,
  n      IN VARCHAR2);
```

<dt> is either DATE, NUMBER, or VARCHAR2.

See Also: To bind RAW variables use [BIND_VARIABLE_RAW Procedure](#) on page 38-5.

Parameters

Table 38–2 BIND_VARIABLE Procedure Parameters

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed using the routines OPEN_CURSOR and PARSE respectively.
p	Position of the bind variable in the SQL statement: Starts at 1.
v	Value that must be passed to the bind variable name.
n	(Optional) Name of the bind variable. For example, in <code>SELECT * FROM emp WHERE ename = :ename</code> , the position of the bind variable :ename is 1, the name is :ename. This parameter can be used if the non-Oracle system supports "named binds" instead of positional binds. Passing the position is still required.

Exceptions

Table 38–3 BIND_VARIABLE Procedure Exceptions

Exception	Description
ORA-28550	The cursor passed is invalid.

Table 38–3 *BIND_VARIABLE Procedure Exceptions*

Exception	Description
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined: WNDS, RNDS

BIND_VARIABLE_RAW Procedure

This procedure binds IN variables of type RAW.

Syntax

```
DBMS_HS_PASSTHROUGH.BIND_VARIABLE_RAW (
  c    IN BINARY_INTEGER NOT NULL,
  p    IN BINARY_INTEGER NOT NULL,
  v    IN RAW,
  n    IN VARCHAR2);
```

Parameters

Table 38–4 BIND_VARIABLE_RAW Procedure Parameters

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines OPEN_CURSOR and PARSE respectively.
p	Position of the bind variable in the SQL statement: Starts at 1.
v	Value that must be passed to the bind variable.
n	(Optional) Name of the bind variable. For example, in SELECT * FROM emp WHERE ename= :ename, the position of the bind variable :ename is 1, the name is :ename. This parameter can be used if the non-Oracle system supports "named binds" instead of positional binds. Passing the position is still required.

Exceptions

Table 38–5 BIND_VARIABLE_RAW Procedure Exceptions

Exception	Description
ORA-28550	The cursor passed is invalid.
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS, RNDS

BIND_OUT_VARIABLE Procedure

This procedure binds an OUT variable with a PL/SQL program variable.

Syntax

```
DBMS_HS_PASSTHROUGH.BIND_OUT_VARIABLE (
  c      IN  BINARY_INTEGER NOT NULL,
  p      IN  BINARY_INTEGER NULL,
  v      OUT <dt>,
  n      IN  VARCHAR2);
```

<dt> is either DATE, NUMBER, or VARCHAR2.

See Also: For binding OUT variables of datatype RAW, see [BIND_OUT_VARIABLE_RAW Procedure](#) on page 38-9.

Parameters

Table 38–6 BIND_OUT_VARIABLE Procedure Parameters

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines OPEN_CURSOR and PARSE respectively.
p	Position of the bind variable in the SQL statement: Starts at 1.
v	Variable in which the OUT bind variable stores its value. The package remembers only the "size" of the variable. After the SQL statement is run, you can use GET_VALUE to retrieve the value of the OUT parameter. The size of the retrieved value should not exceed the size of the parameter that was passed using BIND_OUT_VARIABLE.
n	(Optional) Name of the bind variable. For example, in <code>SELECT * FROM emp WHERE ename= :ename</code> , the position of the bind variable :ename is 1, the name is :ename. This parameter can be used if the non-Oracle system supports "named binds" instead of positional binds. Passing the position is still required.

Exceptions

Table 38–7 *BIND_OUT_VARIABLE Procedure Exceptions*

Exception	Description
ORA-28550	The cursor passed is invalid.
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS, RNDS

BIND_OUT_VARIABLE_RAW Procedure

This procedure binds an `OUT` variable of datatype `RAW` with a PL/SQL program variable.

Syntax

```
DBMS_HS_PASSTHROUGH.BIND_OUT_VARIABLE_RAW (
  c      IN  BINARY_INTEGER NOT NULL,
  p      IN  BINARY_INTEGER NOT NULL,
  v      OUT RAW,
  n      IN  VARCHAR2);
```

Parameters

Table 38–8 *BIND_OUT_VARIABLE_RAW Procedure Parameters*

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines <code>OPEN_CURSOR</code> and <code>PARSE</code> respectively.
p	Position of the bind variable in the SQL statement: Starts at 1.
v	Variable in which the <code>OUT</code> bind variable stores its value. The package remembers only the "size" of the variable. After the SQL statement is run, you can use <code>GET_VALUE</code> to retrieve the value of the <code>OUT</code> parameter. The size of the retrieved value should not exceed the size of the parameter that was passed using <code>BIND_OUT_VARIABLE_RAW</code> .
n	(Optional) Name of the bind variable. For example, in <code>SELECT * FROM emp WHERE ename = :ename</code> , the position of the bind variable <code>:ename</code> is 1, the name is <code>:ename</code> . This parameter can be used if the non-Oracle system supports "named binds" instead of positional binds. Passing the position is still required.

Exceptions

Table 38–9 *BIND_OUT_VARIABLE_RAW Procedure Exceptions*

Exception	Description
ORA-28550	The cursor passed is invalid.

Table 38–9 *BIND_OUT_VARIABLE_RAW Procedure Exceptions*

Exception	Description
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS, RNDS

BIND_INOUT_VARIABLE Procedure

This procedure binds IN OUT bind variables.

Syntax

```
DBMS_HS_PASSTHROUGH.BIND_INOUT_VARIABLE (
  c      IN      BINARY_INTEGER NOT NULL,
  p      IN      BINARY_INTEGER NOT NULL,
  v      IN OUT  <dt>,
  n      IN      VARCHAR2);
```

<dt> is either DATE, NUMBER, or VARCHAR2.

See Also: For binding IN OUT variables of datatype RAW see [BIND_INOUT_VARIABLE_RAW Procedure](#) on page 38-13.

Parameters

Table 38–10 *BIND_INOUT_VARIABLE Procedure Parameters*

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines OPEN_CURSOR and PARSE respectively.
p	Position of the bind variable in the SQL statement: Starts at 1.
v	This value is used for two purposes: - To provide the IN value before the SQL statement is run. - To determine the size of the out value.
n	(Optional) Name of the bind variable. For example, in <code>SELECT * FROM emp WHERE ename= :ename</code> , the position of the bind variable <code>:ename</code> is 1, the name is <code>:ename</code> . This parameter can be used if the non-Oracle system supports "named binds" instead of positional binds. Passing the position is still required.

Exceptions

Table 38–11 *BIND_INOUT_VARIABLE Procedure Exceptions*

Exception	Description
ORA-28550	The cursor passed is invalid.
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS, RNDS

BIND_INOUT_VARIABLE_RAW Procedure

This procedure binds IN OUT bind variables of datatype RAW.

Syntax

```
DBMS_HS_PASSTHROUGH.BIND_INOUT_VARIABLE_RAW (
  c      IN      BINARY_INTEGER NOT NULL,
  p      IN      BINARY_INTEGER NOT NULL,
  v      IN OUT  RAW,
  n      IN      VARCHAR2);
```

Parameters

Table 38–12 BIND_INOUT_VARIABLE_RAW Procedure Parameters

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed using the routines OPEN_CURSOR and PARSE respectively.
p	Position of the bind variable in the SQL statement: Starts at 1.
v	This value is used for two purposes: - To provide the IN value before the SQL statement is run. - To determine the size of the out value.
n	(Optional) Name the bind variable. For example, in SELECT * FROM emp WHERE ename = :ename, the position of the bind variable :ename is 1, the name is :ename. This parameter can be used if the non-Oracle system supports "named binds" instead of positional binds. Passing the position is still required.

Exceptions

Table 38–13 BIND_INOUT_VARIABLE_RAW Procedure Exceptions

Exception	Description
ORA-28550	The cursor passed is invalid.
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)

Table 38–13 *BIND_INOUT_VARIABLE_RAW Procedure Exceptions*

Exception	Description
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS, RNDS

CLOSE_CURSOR Procedure

This function closes the cursor and releases associated memory after the SQL statement has been run at the non-Oracle system. If the cursor was not open, then the operation is a "no operation".

Syntax

```
DBMS_HS_PASSTHROUGH.CLOSE_CURSOR (
  c IN BINARY_INTEGER NOT NULL);
```

Parameters

Table 38–14 *CLOSE_CURSOR Procedure Parameters*

Parameter	Description
c	Cursor to be released.

Exceptions

Table 38–15 *CLOSE_CURSOR Procedure Exceptions*

Exception	Description
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS, RNDS

EXECUTE_IMMEDIATE Procedure

This function runs a SQL statement immediately. Any valid SQL command except `SELECT` can be run immediately. The statement must not contain any bind variables. The statement is passed in as a `VARCHAR2` in the argument. Internally the SQL statement is run using the `PASSTHROUGH SQL` protocol sequence of `OPEN_CURSOR`, `PARSE`, `EXECUTE_NON_QUERY`, `CLOSE_CURSOR`.

Syntax

```
DBMS_HS_PASSTHROUGH.EXECUTE_IMMEDIATE (  
    s IN VARCHAR2 NOT NULL)  
RETURN BINARY_INTEGER;
```

Parameters

Table 38–16 EXECUTE_IMMEDIATE Procedure Parameters

Parameter	Description
<code>s</code>	<code>VARCHAR2</code> variable with the statement to be executed immediately.

Return Values

The number of rows affected by the execution of the SQL statement.

Exceptions

Table 38–17 EXECUTE_IMMEDIATE Procedure Exceptions

Exception	Description
ORA-28551	SQL statement is invalid.
ORA-28544	Max open cursors.
ORA-28555	A <code>NULL</code> value was passed for a <code>NOT NULL</code> parameter.

EXECUTE_NON_QUERY Function

This function runs a SQL statement. The SQL statement cannot be a `SELECT` statement. A cursor has to be open and the SQL statement has to be parsed before the SQL statement can be run.

Syntax

```
DBMS_HS_PASSTHROUGH.EXECUTE_NON_QUERY (
  c IN BINARY_INTEGER NOT NULL)
RETURN BINARY_INTEGER;
```

Parameters

Table 38–18 EXECUTE_NON_QUERY Function Parameters

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines <code>OPEN_CURSOR</code> and <code>PARSE</code> respectively.

Return Values

The number of rows affected by the SQL statement in the non-Oracle system

Exceptions

Table 38–19 EXECUTE_NON_QUERY Procedure Exceptions

Exception	Description
ORA-28550	The cursor passed is invalid.
ORA-28552	<code>BIND_VARIABLE</code> procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28555	A <code>NULL</code> value was passed for a <code>NOT NULL</code> parameter.

FETCH_ROW Function

This function fetches rows from a result set. The result set is defined with a SQL `SELECT` statement. When there are no more rows to be fetched, the exception `NO_DATA_FOUND` is raised. Before the rows can be fetched, a cursor has to be opened, and the SQL statement has to be parsed.

Syntax

```
DBMS_HS_PASSTHROUGH.FETCH_ROW (
    c    IN BINARY_INTEGER NOT NULL,
    f    IN BOOLEAN)
RETURN BINARY_INTEGER;
```

Parameters

Table 38–20 *FETCH_ROW Function Parameters*

Parameter	Description
<code>c</code>	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines <code>OPEN_CURSOR</code> and <code>PARSE</code> respectively.
<code>first</code>	(Optional) Reexecutes <code>SELECT</code> statement. Possible values: <ul style="list-style-type: none"> - <code>TRUE</code>: reexecute <code>SELECT</code> statement. - <code>FALSE</code>: fetch the next row, or if run for the first time, then execute and fetch rows (default).

Return Values

The returns the number of rows fetched. The function returns "0" if the last row was already fetched.

Exceptions

Table 38–21 *FETCH_ROW Procedure Exceptions*

Exception	Description
ORA-28550	The cursor passed is invalid.
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)

Table 38–21 *FETCH_ROW Procedure Exceptions*

Exception	Description
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS

GET_VALUE Procedure

This procedure has two purposes:

- It retrieves the select list items of `SELECT` statements, after a row has been fetched.
- It retrieves the `OUT` bind values, after the SQL statement has been run.

Syntax

```
DBMS_HS_PASSTHROUGH.GET_VALUE (  
  c      IN BINARY_INTEGER NOT NULL,  
  p      IN BINARY_INTEGER NOT NULL,  
  v      OUT <dt>);
```

<dt> is either `DATE`, `NUMBER`, or `VARCHAR2`.

See Also: For retrieving values of datatype `RAW`, see [GET_VALUE_RAW Procedure](#) on page 38-22.

Parameters

Table 38-22 GET_VALUE Procedure Parameters

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines <code>OPEN_CURSOR</code> and <code>PARSE</code> respectively.
p	Position of the bind variable or select list item in the SQL statement: Starts at 1.
v	Variable in which the <code>OUT</code> bind variable or select list item stores its value.

Exceptions

Table 38–23 *GET_VALUE Procedure Exceptions*

Exception	Description
ORA-1403	Returns NO_DATA_FOUND exception when running the GET_VALUE after the last row was fetched (that is, FETCH_ROW returned "0").
ORA-28550	The cursor passed is invalid.
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS

GET_VALUE_RAW Procedure

This procedure is similar to `GET_VALUE`, but for datatype `RAW`.

Syntax

```
DBMS_HS_PASSTHROUGH.GET_VALUE_RAW (  
  c    IN  BINARY_INTEGER NOT NULL,  
  p    IN  BINARY_INTEGER NOT NULL,  
  v    OUT RAW);
```

Parameters

Table 38–24 *GET_VALUE_RAW Procedure Parameters*

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened and parsed, using the routines <code>OPEN_CURSOR</code> and <code>PARSE</code> respectively.
p	Position of the bind variable or select list item in the SQL statement: Starts at 1.
v	Variable in which the <code>OUT</code> bind variable or select list item stores its value.

Exceptions

Table 38–25 *GET_VALUE_RAW Procedure Exceptions*

Exception	Description
ORA-1403	Returns <code>NO_DATA_FOUND</code> exception when running the <code>GET_VALUE</code> after the last row was fetched (that is, <code>FETCH_ROW</code> returned "0").
ORA-28550	The cursor passed is invalid.
ORA-28552	Procedure is not run in right order. (Did you first open the cursor and parse the SQL statement?)
ORA-28553	The position of the bind variable is out of range.
ORA-28555	A <code>NULL</code> value was passed for a <code>NOT NULL</code> parameter.

Pragmas

Purity level defined : WNDS

OPEN_CURSOR Function

This function opens a cursor for running a pass-through SQL statement at the non-Oracle system. This function must be called for any type of SQL statement.

The function returns a cursor, which must be used in subsequent calls. This call allocates memory. To deallocate the associated memory, call the procedure `CLOSE_CURSOR`.

Syntax

```
DBMS_HS_PASSTHROUGH.OPEN_CURSOR  
RETURN BINARY_INTEGER;
```

Return Values

The cursor to be used on subsequent procedure and function calls.

Exceptions

Table 38–26 OPEN_CURSOR Function Exceptions

Exception	Description
ORA-28554	Maximum number of open cursor has been exceeded. Increase Heterogeneous Services' OPEN_CURSORS initialization parameter.

Pragmas

Purity level defined : WNDS, RNDS

PARSE Procedure

This procedure parses SQL statement at non-Oracle system.

Syntax

```
DBMS_HS_PASSTHROUGH.PARSE (
  c          IN  BINARY_INTEGER NOT NULL,
  stmt      IN  VARCHAR2 NOT NULL);
```

Parameters

Table 38–27 *PARSE Procedure Parameters*

Parameter	Description
c	Cursor associated with the pass-through SQL statement. Cursor must be opened using function OPEN_CURSOR.
stmt	Statement to be parsed.

Exceptions

Table 38–28 *PARSE Procedure Exceptions*

Exception	Description
ORA-28550	The cursor passed is invalid.
ORA-28551	SQL statement is illegal.
ORA-28555	A NULL value was passed for a NOT NULL parameter.

Pragmas

Purity level defined : WNDS, RNDS

The `DBMS_IOT` package creates a table into which references to the chained rows for an index-organized table can be placed using the `ANALYZE` command. `DBMS_IOT` can also create an exception table into which references to the rows of an index-organized table that violate a constraint can be placed during the `enable_constraint` operation.

`DBMS_IOT` is not loaded during database installation. To install `DBMS_IOT`, run `dbmsiotc.sql`, available in the `ADMIN` directory.

This chapter contains the following topics:

- [Summary of DBMS_IOT Subprograms](#)

Note: With the introduction of logical-rowids for IOTs with Oracle Database Release 8.1, you no longer need to use the procedures contained in this package which is retained for backward compatibility only. It is however required for servers running with Oracle Database Release 8.0.

Summary of DBMS_IOT Subprograms

Table 39–1 *DBMS_IOT Package Subprograms*

Subprogram	Description
BUILD_CHAIN_ROWS_TABLE Procedure on page 39-3	Creates a table into which references to the chained rows for an index-organized table can be placed using the <code>ANALYZE</code> command
BUILD_EXCEPTIONS_TABLE Procedure on page 39-5	Creates an exception table into which rows of an index-organized table that violate a constraint can be placed

BUILD_CHAIN_ROWS_TABLE Procedure

This procedure creates a table into which references to the chained rows for an index-organized table can be placed using the ANALYZE command.

Syntax

```
DBMS_IOT.BUILD_CHAIN_ROWS_TABLE (
  owner           IN VARCHAR2,
  iot_name        IN VARCHAR2,
  chainrow_table_name IN VARCHAR2 default 'IOT_CHAINED_ROWS');
```

Parameters

Table 39–2 BUILD_CHAIN_ROWS_TABLE Procedure Parameters

Parameter	Description
owner	Owner of the index-organized table.
iot_name	Index-organized table name.
chainrow_table_name	Intended name for the chained-rows table.

Usage Notes

You should create a separate chained-rows table for each index-organized table to accommodate its primary key.

Examples

```
CREATE TABLE l(a char(16),b char(16), c char(16), d char(240),
PRIMARY KEY(a,b,c)) ORGANIZATION INDEX pctthreshold 10 overflow;
EXECUTE DBMS_IOT.BUILD_CHAIN_ROWS_TABLE('SYS','L','LC');
```

A chained-row table is created with the following columns:

Column Name	Null?	Type
OWNER_NAME		VARCHAR2(30)
TABLE_NAME		VARCHAR2(30)
CLUSTER_NAME		VARCHAR2(30)
PARTITION_NAME		VARCHAR2(30)
SUBPARTITION_NAME		VARCHAR2(30)
HEAD_ROWID		ROWID

BUILD_CHAIN_ROWS_TABLE Procedure

TIMESTAMP

A

B

C

DATE

CHAR(16)

CHAR(16)

CHAR(16)

BUILD_EXCEPTIONS_TABLE Procedure

This procedure creates an exception table into which rows of an index-organized table that violate a constraint can be placed during the execution of the following SQL statements:

- ALTER TABLE ... ENABLE CONSTRAINT ... EXCEPTIONS INTO
- ALTER TABLE ... ADD CONSTRAINT ... EXCEPTIONS INTO

Syntax

```
DBMS_IOT.BUILD_EXCEPTIONS_TABLE (
  owner          IN VARCHAR2,
  iot_name       IN VARCHAR2,
  exceptions_table_name IN VARCHAR2 default 'IOT_EXCEPTIONS');
```

Parameters

Table 39–3 *BUILD_EXCEPTIONS_TABLE Procedure Parameters*

Parameter	Description
owner	Owner of the index-organized table.
iot_name	Index-organized table name.
exceptions_table_name	Intended name for exception-table.

Usage Notes

You should create a separate exception table for each index-organized table to accommodate its primary key.

Examples

```
EXECUTE DBMS_IOT.BUILD_EXCEPTIONS_TABLE('SYS', 'L', 'LE');
```

An exception table for the preceding index-organized table with the following columns:

Column Name	Null?	Type
ROW_ID		VARCHAR2(30)
OWNER		VARCHAR2(30)

BUILD_EXCEPTIONS_TABLE Procedure

TABLE_NAME	VARCHAR2(30)
CONSTRAINT	VARCHAR2(30)
A	CHAR(16)
B	CHAR(16)
C	CHAR(16)

The DBMS_JAVA package provides a PL/SQL interface for accessing database functionality from Java.

- [Documentation of DBMS_JAVA](#)

Documentation of DBMS_JAVA

For a complete description of this package within the context of DBMS_JAVA, see DBMS_JAVA in the *Oracle Database Java Developer's Guide*.

The DBMS_JOB package schedules and manages jobs in the job queue.

Note: The DBMS_JOB package has been superseded by the [DBMS_SCHEDULER](#) package. In particular, if you are administering jobs to manage system load, you should consider disabling DBMS_JOB by revoking the package execution privilege for users.

For more information, see "Moving from DBMS_JOB to DBMS_SCHEDULER" in *Oracle Database Administrator's Guide*.

This chapter contains the following topics:

- [Using DBMS_JOB](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_JOB Subprograms](#)

Using DBMS_JOB

- [Security Model](#)
- [Operational Notes](#)

Security Model

No specific system privileges are required to use DBMS_JOB. No system privileges are available to manage DBMS_JOB. Jobs cannot be altered or deleted other than jobs owned by the user. This is true for all users including those users granted DBA privileges.

You can execute procedures that are owned by the user or for which the user is explicitly granted EXECUTE. However, procedures for which the user is granted the execute privilege through roles cannot be executed.

Note that, once a job is started and running, there is no easy way to stop the job.

Operational Notes

- [Working with Real Application Clusters](#)
- [Stopping a Job](#)

Working with Real Application Clusters

DBMS_JOB supports multi-instance execution of jobs. By default jobs can be executed on any instance, but only one single instance will execute the job. In addition, you can force instance binding by binding the job to a particular instance. You implement instance binding by specifying an instance number to the instance affinity parameter. Note, however, that in 10i instance binding is not recommended. Service affinity is preferred. This concept is implemented in the [DBMS_SCHEDULER](#) package.

The following procedures can be used to create, alter or run jobs with instance affinity. Note that not specifying affinity means any instance can run the job.

DBMS_JOB.SUBMIT

To submit a job to the job queue, use the following syntax:

```
DBMS_JOB.SUBMIT(
```



```

JOB      OUT      BINARY_INTEGER,
WHAT     IN       VARCHAR2, NEXT_DATE IN DATE DEFAULTSYSDATE,
INTERVAL IN       VARCHAR2 DEFAULT 'NULL',
NO_PARSE IN      BOOLEAN DEFAULT FALSE,
INSTANCE IN      BINARY_INTEGER DEFAULT ANY_INSTANCE,
FORCE    IN      BOOLEAN DEFAULT FALSE);

```

Use the parameters `INSTANCE` and `FORCE` to control job and instance affinity. The default value of `INSTANCE` is 0 (zero) to indicate that any instance can execute the job. To run the job on a certain instance, specify the `INSTANCE` value. Oracle displays error `ORA-23319` if the `INSTANCE` value is a negative number or `NULL`.

The `FORCE` parameter defaults to `FALSE`. If `force` is `TRUE`, any positive integer is acceptable as the job instance. If `FORCE` is `FALSE`, the specified instance must be running, or Oracle displays error number `ORA-23428`.

DBMS_JOB.INSTANCE

To assign a particular instance to execute a job, use the following syntax:

```

DBMS_JOB.INSTANCE( JOB IN BINARY_INTEGER,
INSTANCE          IN BINARY_INTEGER,
FORCE            IN BOOLEAN DEFAULT FALSE);

```

The `FORCE` parameter in this example defaults to `FALSE`. If the instance value is 0 (zero), job affinity is altered and any available instance can execute the job despite the value of force. If the `INSTANCE` value is positive and the `FORCE` parameter is `FALSE`, job affinity is altered only if the specified instance is running, or Oracle displays error `ORA-23428`.

If the `FORCE` parameter is `TRUE`, any positive integer is acceptable as the job instance and the job affinity is altered. Oracle displays error `ORA-23319` if the `INSTANCE` value is negative or `NULL`.

DBMS_JOB.CHANGE

To alter user-definable parameters associated with a job, use the following syntax:

```

DBMS_JOB.CHANGE( JOB IN BINARY_INTEGER,
WHAT             IN VARCHAR2 DEFAULT NULL,
NEXT_DATE       IN DATE DEFAULT NULL,
INTERVAL        IN VARCHAR2 DEFAULT NULL,
INSTANCE        IN BINARY_INTEGER DEFAULT NULL,
FORCE           IN BOOLEAN DEFAULT FALSE );

```

Two parameters, `INSTANCE` and `FORCE`, appear in this example. The default value of `INSTANCE` is `NULL` indicating that job affinity will not change.

The default value of `FORCE` is `FALSE`. Oracle displays error `ORA-23428` if the specified instance is not running and error `ORA-23319` if the `INSTANCE` number is negative.

DBMS_JOB.RUN

The `FORCE` parameter for `DBMS_JOB.RUN` defaults to `FALSE`. If force is `TRUE`, instance affinity is irrelevant for running jobs in the foreground process. If force is `FALSE`, the job can run in the foreground only in the specified instance. Oracle displays error `ORA-23428` if force is `FALSE` and the connected instance is the incorrect instance.

```
DBMS_JOB.RUN(  
    JOB      IN BINARY_INTEGER,  
    FORCE    IN BOOLEAN DEFAULT FALSE);
```

Stopping a Job

Note that, once a job is started and running, there is no easy way to stop the job.

Summary of DBMS_JOB Subprograms

Table 41-1 DBMS_JOB Package Subprograms

Subprogram	Description
BROKEN Procedure on page 41-6	Disables job execution
CHANGE Procedure on page 41-7	Alters any of the user-definable parameters associated with a job
INSTANCE Procedure on page 41-9	Assigns a job to be run by a instance
INTERVAL Procedure on page 41-10	Alters the interval between executions for a specified job
NEXT_DATE Procedure on page 41-11	Alters the next execution time for a specified job
REMOVE Procedure on page 41-12	Removes specified job from the job queue
RUN Procedure on page 41-13	Forces a specified job to run
SUBMIT Procedure on page 41-14	Submits a new job to the job queue
USER_EXPORT Procedures on page 41-16	Re-creates a given job for export, or re-creates a given job for export with instance affinity
WHAT Procedure on page 41-17	Alters the job description for a specified job

BROKEN Procedure

This procedure sets the broken flag. Broken jobs are never run.

Syntax

```
DBMS_JOB.BROKEN (  
    job          IN  BINARY_INTEGER,  
    broken       IN  BOOLEAN,  
    next_date    IN  DATE DEFAULT SYSDATE);
```

Parameters

Table 41–2 *BROKEN Procedure Parameters*

Parameter	Description
job	Number of the job being run.
broken	Job broken: IN value is FALSE.
next_data	Date of the next refresh.

Note: If you set job as broken while it is running, Oracle resets the job's status to normal after the job completes. Therefore, only execute this procedure for jobs that are not running.

Usage Notes

You must issue a COMMIT statement immediately after the statement.

CHANGE Procedure

This procedure changes any of the fields a user can set in a job.

Syntax

```
DBMS_JOB.CHANGE (
  job      IN  BINARY_INTEGER,
  what     IN  VARCHAR2,
  next_date IN DATE,
  interval IN  VARCHAR2,
  instance IN BINARY_INTEGER DEFAULT NULL,
  force    IN  BOOLEAN DEFAULT FALSE);
```

Parameters

Table 41–3 *CHANGE Procedure Parameters*

Parameter	Description
job	Number of the job being run.
what	PL/SQL procedure to run.
next_date	Date of the next refresh.
interval	Date function; evaluated immediately before the job starts running.
instance	When a job is submitted, specifies which instance can run the job. This defaults to <code>NULL</code> , which indicates that instance affinity is not changed.
force	If this is <code>FALSE</code> , then the specified instance (to which the instance number change) must be running. Otherwise, the routine raises an exception. If this is <code>TRUE</code> , then any positive integer is acceptable as the job instance.

Usage Notes

- You must issue a `COMMIT` statement immediately after the statement.
- The parameters `instance` and `force` are added for job queue affinity. Job queue affinity gives users the ability to indicate whether a particular instance or any instance can run a submitted job.

- If the parameters `what`, `next_date`, or `interval` are `NULL`, then leave that value as it is.

Example

```
BEGIN
  DBMS_JOB.CHANGE(14144, null, null, 'sysdate+3');
COMMIT;
END;
```

INSTANCE Procedure

This procedure changes job instance affinity.

Syntax

```
DBMS_JOB.INSTANCE (  
    job          IN BINARY_INTEGER,  
    instance     IN BINARY_INTEGER,  
    force        IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 41–4 *INSTANCE Procedure Parameters*

Parameter	Description
job	Number of the job being run.
instance	When a job is submitted, a user can specify which instance can run the job.
force	If this is <code>TRUE</code> , then any positive integer is acceptable as the job instance. If this is <code>FALSE</code> (the default), then the specified instance must be running; otherwise the routine raises an exception.

Usage Notes

You must issue a `COMMIT` statement immediately after the statement.

INTERVAL Procedure

This procedure changes how often a job runs.

Syntax

```
DBMS_JOB.INTERVAL (  
    job      IN  BINARY_INTEGER,  
    interval IN  VARCHAR2);
```

Parameters

Table 41–5 *INTERVAL Procedure Parameters*

Parameter	Description
job	Number of the job being run.
interval	Date function, evaluated immediately before the job starts running.

Usage Notes

- If the job completes successfully, then this new date is placed in `next_date`. `interval` is evaluated by plugging it into the statement `select interval into next_date from dual`;
- The `interval` parameter must evaluate to a time in the future. Legal intervals include:

Interval	Description
'sysdate + 7'	Run once a week.
'next_day(sysdate, ''TUESDAY'')'	Run once every Tuesday.
'null'	Run only once.

- If `interval` evaluates to `NULL` and if a job completes successfully, then the job is automatically deleted from the queue.
- You must issue a `COMMIT` statement immediately after the statement.

NEXT_DATE Procedure

This procedure changes when an existing job next runs.

Syntax

```
DBMS_JOB.NEXT_DATE (  
    job          IN BINARY_INTEGER,  
    next_date IN DATE);
```

Parameters

Table 41–6 *NEXT_DATE Procedure Parameters*

Parameter	Description
job	Number of the job being run.
next_date	Date of the next refresh: it is when the job will be automatically run, assuming there are background processes attempting to run it.

Usage Notes

You must issue a COMMIT statement immediately after the statement.

REMOVE Procedure

This procedure removes an existing job from the job queue. This currently does not stop a running job.

Syntax

```
DBMS_JOB.REMOVE (  
    job          IN BINARY_INTEGER );
```

Parameters

Table 41–7 REMOVE Procedure Parameters

Parameter	Description
job	Number of the job being run.

Usage Notes

You must issue a COMMIT statement immediately after the statement.

Example

```
BEGIN  
    DBMS_JOB.REMOVE(14144);  
    COMMIT;  
END;
```

RUN Procedure

This procedure runs job `JOB` now. It runs it even if it is broken.

Running the job recomputes `next_date`. See view `user_jobs`.

Syntax

```
DBMS_JOB.RUN (
    job          IN  BINARY_INTEGER,
    force        IN  BOOLEAN DEFAULT FALSE);
```

Parameters

Table 41–8 *RUN Procedure Parameters*

Parameter	Description
<code>job</code>	Number of the job being run.
<code>force</code>	If this is <code>TRUE</code> , then instance affinity is irrelevant for running jobs in the foreground process. If this is <code>FALSE</code> , then the job can be run in the foreground only in the specified instance.

Example

```
EXECUTE DBMS_JOB.RUN(14144);
```

Caution: This re-initializes the current session's packages.

Exceptions

An exception is raised if `force` is `FALSE`, and if the connected instance is the wrong one.

SUBMIT Procedure

This procedure submits a new job. It chooses the job from the sequence `sys.jobseq`.

Syntax

```
DBMS_JOB.SUBMIT (  
    job          OUT BINARY_INTEGER,  
    what         IN  VARCHAR2,  
    next_date    IN  DATE DEFAULT sysdate,  
    interval     IN  VARCHAR2 DEFAULT 'null',  
    no_parse     IN  BOOLEAN DEFAULT FALSE,  
    instance     IN  BINARY_INTEGER DEFAULT any_instance,  
    force       IN  BOOLEAN DEFAULT FALSE);
```

Parameters

Table 41–9 *SUBMIT Procedure Parameters*

Parameter	Description
<code>job</code>	Number of the job being run.
<code>what</code>	PL/SQL procedure to run.
<code>next_date</code>	Next date when the job will be run.
<code>interval</code>	Date function that calculates the next time to run the job. The default is <code>NULL</code> . This must evaluate to either a future point in time or <code>NULL</code> .
<code>no_parse</code>	A flag. The default is <code>FALSE</code> . If this is set to <code>FALSE</code> , then Oracle parses the procedure associated with the job. If this is set to <code>TRUE</code> , then Oracle parses the procedure associated with the job the first time that the job is run. For example, if you want to submit a job before you have created the tables associated with the job, then set this to <code>TRUE</code> .
<code>instance</code>	When a job is submitted, specifies which instance can run the job.
<code>force</code>	If this is <code>TRUE</code> , then any positive integer is acceptable as the job instance. If this is <code>FALSE</code> (the default), then the specified instance must be running; otherwise the routine raises an exception.

Usage Notes

- You must issue a `COMMIT` statement immediately after the statement.
- The parameters `instance` and `force` are added for job queue affinity. Job queue affinity gives users the ability to indicate whether a particular instance or any instance can run a submitted job.

Example

This submits a new job to the job queue. The job calls the procedure `DBMS_DDL.ANALYZE_OBJECT` to generate optimizer statistics for the table `DQUON.ACCOUNTS`. The statistics are based on a sample of half the rows of the `ACCOUNTS` table. The job is run every 24 hours:

```
VARIABLE jobno number;
BEGIN
  DBMS_JOB.SUBMIT(:jobno,
    'dbms_ddl.analyze_object(''TABLE'',
    ''DQUON'', ''ACCOUNTS'',
    ''ESTIMATE'', NULL, 50);'
    SYSDATE, 'SYSDATE + 1');
  COMMIT;
END;
/
Statement processed.
print jobno
JOBNO
-----
14144
```

USER_EXPORT Procedures

There are two overloaded procedures. The first produces the text of a call to re-create the given job. The second alters instance affinity (8i and after) and preserves the compatibility.

Syntax

```
DBMS_JOB.USER_EXPORT (  
    job      IN      BINARY_INTEGER,  
    mycall  IN OUT  VARCHAR2);
```

```
DBMS_JOB.USER_EXPORT (  
    job      IN      BINARY_INTEGER,  
    mycall  IN OUT  VARCHAR2,  
    myinst  IN OUT  VARCHAR2);
```

Parameters

Table 41–10 *USER_EXPORT Procedure Parameter*

Parameter	Description
job	Number of the job being run.
mycall	Text of a call to re-create the given job.
myinst	Text of a call to alter instance affinity.

WHAT Procedure

This procedure changes what an existing job does, and replaces its environment.

Syntax

```
DBMS_JOB.WHAT (  
    job      IN BINARY_INTEGER,  
    what     IN VARCHAR2);
```

Parameters

Table 41–11 *WHAT Procedure Parameters*

Parameter	Description
job	Number of the job being run.
what	PL/SQL procedure to run.

Usage Notes

- You must issue a `COMMIT` statement immediately after the statement.
- Some legal values of `what` (assuming the routines exist) are:
 - `'myproc(''10-JAN-82'', next_date, broken);'`
 - `'scott.emppackage.give_raise(''JENKINS'', 30000.00);'`
 - `'dbms_job.remove(job);'`

The DBMS_LDAP package lets you access data from LDAP servers.

- [Documentation of DBMS_LDAP](#)

Documentation of DBMS_LDAP

For a complete description of this package within the context of Oracle Internet Directory, see `DBMS_LDAP` in the *Oracle Internet Directory Application Developer's Guide*.

DBMS_LDAP_UTL

The DBMS_LDAP_UTL package contains the Oracle Extension utility functions.

- [Documentation of DBMS_LDAP_UTL](#)

Documentation of DBMS_LDAP_UTL

For a complete description of this package within the context of Oracle Internet Directory, see `DBMS_LDAP_UTL` in the *Oracle Internet Directory Application Developer's Guide*.

DBMS_LIBCACHE

The `DBMS_LIBCACHE` package consists of one subprogram that prepares the library cache on an Oracle instance by extracting SQL and PL/SQL from a remote instance and compiling this SQL locally without execution. The value of compiling the cache of an instance is to prepare the information the application requires to execute in advance of failover or switchover.

This chapter contains the following topics:

- [Using DBMS_LIBCACHE](#)
 - [Overview](#)
 - [Security Model](#)
- [Summary of DBMS_LIBCACHE Subprograms](#)

Using DBMS_LIBCACHE

- [Overview](#)
- [Security Model](#)

Overview

Compiling a shared cursor consists of open, parse, and bind operations, plus the type-checking and execution plan functions performed at the first execution. All of these steps are executed in advance by the package `DBMS_LIBCACHE` for `SELECT` statements. The open and parse functions are executed in advance for `PL/SQL` and `DML`. For `PL/SQL`, executing the parse phase has the effect of loading all library cache heaps other than the `MCODE`.

Security Model

To execute `DBMS_LIBCACHE` you must directly access the same objects as do `SQL` statements. You can best accomplish this by utilizing the same user id as the original system on the remote system.

When there are multiple schema users, `DBMS_LIBCACHE` should be called for each.

Alternatively, `DBMS_LIBCACHE` may be called with the generic user `PARSER`. However, this user cannot parse the `SQL` that uses objects with access granted through roles. This is a standard `PL/SQL` security limitation.

Summary of DBMS_LIBCACHE Subprograms

Table 44–1 DBMS_LIBCACHE Package Subprograms

Subprogram	Description
COMPILE_FROM_REMOTE Procedure on page 44-4	Extracts SQL in batch from the source instance and compiles the SQL at the target instance

COMPILE_FROM_REMOTE Procedure

This procedure extracts SQL in batch from the source instance and compiles the SQL at the target instance.

Syntax

```
DBMS_LIBCACHE.COMPILE_FROM_REMOTE (
  p_db_link          IN      dbms_libcache$def.db_link%type,
  p_username         IN      VARCHAR2 default null,
  p_threshold_executions IN  NATURAL default 3,
  p_threshold_sharable_mem IN NATURAL default 1000,
  p_parallel_degree  IN      NATURAL default 1);
```

Parameters

Table 44–2 *COMPILE_FROM_REMOTE Procedure Parameters*

Parameter	Description
p_db_link	The database link to the source name (mandatory).
p_instance_name	The source instance name (reserved for future use).
p_username	The source username (default is all users).
p_threshold_executions	The lower bound on the number of executions.
p_threshold_sharable_mem	The lower bound on shared memory size.
p_parallel_degree	The number of parallel jobs

Usage Notes

- P_DB_LINK

The database link pointing to the instance that will be used for extracting the SQL statements. The user must have the role `SELECT_ON_CATALOG` at the source instance. For improved security, the connection may use a password file or LDAP authentication. The database link is mandatory only for releases with `dbms_libcache$def.ACCESS_METHOD = DB_LINK_METHOD`

- `P_INSTANCE_NAME` (reserved for future use)

The name of the instance that will be used for extracting the SQL statements. The instance name must be unique for all instances excluding the local instance. The name is not case sensitive.
- `P_USERNAME`

The name of the username that will be used for extracting the SQL statements. The username is an optional parameter that is used to ensure the parsing user id is the same as that on the source instance. For an application where users connect as a single `user_id`, for example `APPS`, `APPS` is the parsing `user_id` that is recorded in the shared pool. To select only SQL statements parsed by `APPS`, enter the string 'APPS' in this field. To also select statements executed by batch, repeat the executing the procedure with the schema owner, for example `GL`. If the username is supplied, it must be valid. The name is not case sensitive.
- `P_THRESHOLD_EXECUTIONS`

The lower bound for the number of executions, below which a SQL statement will not be selected for parsing. This parameter is optional. It allows the application to extract and compile statements with executions, for example, greater than 3. The default value is 1. This means SQL statements that have never executed, including invalid SQL statements, will not be extracted.
- `P_THRESHOLD_SHARABLE_MEM`

The lower bound for the size of the shared memory consumed by the cursors on the source instance. Below this value a SQL statement will not be selected for parsing. This parameter is optional. It allows the application to extract and compile statements with shared memory for example, greater than 10000 bytes.
- `P_PARALLEL_DEGREE`

The number of parallel jobs that execute to complete the parse operation. These tasks are spawned as parallel jobs against a sub-range of the SQL statements selected for parsing. This parameter is reserved for parallel compile jobs which are currently not implemented.

The `DBMS_LOB` package provides subprograms to operate on `BLOBs`, `CLOBs`, `NCLOBs`, `BFILEs`, and temporary `LOBs`. You can use `DBMS_LOB` to access and manipulation specific parts of a `LOB` or complete `LOBs`.

See Also: *Oracle Database Application Developer's Guide - Large Objects*

This chapter contains the following topics:

- [Using DBMS_LOB](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Types](#)
 - [Rules and Limits](#)
 - [Operational Notes](#)
- [Summary of DBMS_LOB Subprograms](#)

Using DBMS_LOB

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Types](#)
- [Rules and Limits](#)
- [Operational Notes](#)

Overview

DBMS_LOB can read and modify BLOBs, CLOBs, and NCLOBs; it provides read-only operations for BFILEs. The bulk of the LOB operations are provided by this package.

Security Model

This package must be created under SYS. Operations provided by this package are performed under the current calling user, not under the package owner SYS.

Any DBMS_LOB subprogram called from an anonymous PL/SQL block is executed using the privileges of the current user. Any DBMS_LOB subprogram called from a stored procedure is executed using the privileges of the owner of the stored procedure.

When creating the procedure, users can set the AUTHID to indicate whether they want definer's rights or invoker's rights. For example:

```
CREATE PROCEDURE procl authid definer ...
```

or

```
CREATE PROCEDURE procl authid current_user ...
```

See Also: For more information on AUTHID and privileges, see *PL/SQL User's Guide and Reference*

You can provide secure access to `BFILES` using the `DIRECTORY` feature discussed in `BFILENAME` function in the *Oracle Database Application Developer's Guide - Large Objects* and the *Oracle Database SQL Reference*.

For information about the security model pertaining to temporary LOBs, see [Operational Notes](#).

Constants

DBMS_LOB defines the following constants:

```
file_readonly CONSTANT BINARY_INTEGER := 0;
lob_readonly  CONSTANT BINARY_INTEGER := 0;
lob_readwrite CONSTANT BINARY_INTEGER := 1;
lobmaxsize   CONSTANT INTEGER        := 18446744073709551615;
call         CONSTANT PLS_INTEGER    := 12;
session      CONSTANT PLS_INTEGER    := 10;
```

Types

Parameters for the DBMS_LOB subprograms use these datatypes:

Table 45–1 DBMS_LOB Datatypes

Type	Description
BLOB	A source or destination binary LOB.
RAW	A source or destination RAW buffer (used with BLOB).
CLOB	A source or destination character LOB (including NCLOB).
VARCHAR2	A source or destination character buffer (used with CLOB and NCLOB).
INTEGER	Specifies the size of a buffer or LOB, the offset into a LOB, or the amount to access.
BFILE	A large, binary object stored outside the database.

The DBMS_LOB package defines no special types. An NCLOB is a CLOB for holding fixed-width and varying-width, multibyte national character sets. The clause `ANY_CS` in the specification of DBMS_LOB subprograms for CLOBs enables the CLOB type to accept a CLOB or NCLOB locator variable as input.

Rules and Limits

- [General Rules and Limits](#)
- [Rules and Limits Specific to External Files \(BFILES\)](#)
- [Maximum LOB Size](#)
- [Maximum Buffer Size](#)

General Rules and Limits

- The following rules apply in the specification of subprograms in this package:
 - `length`, `offset`, and `amount` parameters for subprograms operating on BLOBs and BFILES must be specified in terms of *bytes*.
 - `length`, `offset`, and `amount` parameters for subprograms operating on CLOBs must be specified in terms of *characters*.
- A subprogram raises an `INVALID_ARGVAL` exception if the following restrictions are not followed in specifying values for parameters (unless otherwise specified):
 1. Only positive, absolute offsets from the beginning of LOB data are permitted: Negative offsets from the tail of the LOB are not permitted.
 2. Only positive, nonzero values are permitted for the parameters that represent size and positional quantities, such as `amount`, `offset`, `newlen`, `nth`, and so on. Negative offsets and ranges observed in SQL string functions and operators are not permitted.
 3. The value of `offset`, `amount`, `newlen`, `nth` must not exceed the value `lobmaxsize` (4GB-1) in any `DBMS_LOB` subprogram.
 4. For CLOBs consisting of fixed-width multibyte characters, the maximum value for these parameters must not exceed $(lobmaxsize/character_width_in_bytes)$ characters.

For example, if the CLOB consists of 2-byte characters, such as:

```
JA16SJISFIXED
```

Then, the maximum `amount` value should not exceed:

```
4294967295/2 = 2147483647 characters.
```

- PL/SQL language specifications stipulate an upper limit of 32767 bytes (not characters) for RAW and VARCHAR2 parameters used in DBMS_LOB subprograms. For example, if you declare a variable to be:

```
charbuf VARCHAR2(3000)
```

Then, `charbuf` can hold 3000 single byte characters or 1500 2-byte fixed width characters. This has an important consequence for DBMS_LOB subprograms for CLOBs and NCLOBs.

- The `%CHARSET` clause indicates that the form of the parameter with `%CHARSET` must match the form of the `ANY_CS` parameter to which it refers.

For example, in DBMS_LOB subprograms that take a VARCHAR2 buffer parameter, the form of the VARCHAR2 buffer must match the form of the CLOB parameter. If the input LOB parameter is of type NCLOB, then the buffer must contain NCHAR data. Conversely, if the input LOB parameter is of type CLOB, then the buffer must contain CHAR data.

For DBMS_LOB subprograms that take two CLOB parameters, both CLOB parameters must have the same form; that is, they must both be NCLOBs, or they must both be CLOBs.

- If the value of `amount` plus the `offset` exceeds the maximum LOB size allowed by the database, then access exceptions are raised.

Under these input conditions, read subprograms, such as `READ`, `COMPARE`, `INSTR`, and `SUBSTR`, read until `End of Lob/File` is reached. For example, for a `READ` operation on a BLOB or BFILE, if the user specifies `offset` value of 3 GB and an `amount` value of 2 GB, then `READ` reads only $((4\text{GB}-1) - 3\text{GB})$ bytes.

- Functions with NULL or invalid input values for parameters return a NULL. Procedures with NULL values for destination LOB parameters raise exceptions.
- Operations involving patterns as parameters, such as `COMPARE`, `INSTR`, and `SUBSTR` do not support regular expressions or special matching characters (such as `%` in the `LIKE` operator in SQL) in the `pattern` parameter or substrings.
- The `End of LOB` condition is indicated by the `READ` procedure using a `NO_DATA_FOUND` exception. This exception is raised only upon an attempt by the user to read beyond the end of the LOB. The `READ` buffer for the last read contains 0 bytes.

- For consistent LOB updates, you must lock the row containing the destination LOB before making a call to any of the procedures (mutators) that modify LOB data.
- Unless otherwise stated, the default value for an `offset` parameter is 1, which indicates the first byte in the BLOB or BFILE data, and the first character in the CLOB or NCLOB value. No default values are specified for the `amount` parameter — you must input the values explicitly.
- You must lock the row containing the destination internal LOB before calling any subprograms that modify the LOB, such as APPEND, COPY, ERASE, TRIM, or WRITE. These subprograms do not implicitly lock the row containing the LOB.

Rules and Limits Specific to External Files (BFILES)

- The subprograms COMPARE, INSTR, READ, SUBSTR, FILECLOSE, FILECLOSEALL and LOADFROMFILE operate only on an *opened* BFILE locator; that is, a successful FILEOPEN call must precede a call to any of these subprograms.
- For the functions FILEEXISTS, FILEGETNAME and GETLENGTH, a file's open/close status is unimportant; however, the file must exist physically, and you must have adequate privileges on the DIRECTORY object and the file.
- DBMS_LOB does not support any concurrency control mechanism for BFILE operations.
- In the event of several open files in the session whose closure has not been handled properly, you can use the FILECLOSEALL subprogram to close all files opened in the session and resume file operations from the beginning.
- If you are the creator of a DIRECTORY, or if you have system privileges, then use the CREATE OR REPLACE, DROP, and REVOKE statements in SQL with extreme caution.

If you, or other grantees of a particular directory object, have several open files in a session, then any of the preceding commands can adversely affect file operations. In the event of such abnormal termination, your only choice is to invoke a program or anonymous block that calls FILECLOSEALL, reopen your files, and restart your file operations.

- All files opened during a user session are implicitly closed at the end of the session. However, Oracle strongly recommends that you close the files after *both* normal and abnormal termination of operations on the BFILE .

In the event of normal program termination, proper file closure ensures that the number of files that are open simultaneously in the session remains less than `SESSION_MAX_OPEN_FILES`.

In the event of abnormal program termination from a PL/SQL program, it is imperative that you provide an exception handler that ensures closure of all files opened in that PL/SQL program. This is necessary because after an exception occurs, only the exception handler has access to the `BFILE` variable in its most current state.

After the exception transfers program control outside the PL/SQL program block, all references to the open `BFILES` are lost. The result is a larger open file count which may or may not exceed the `SESSION_MAX_OPEN_FILES` value.

For example, consider a `READ` operation past the end of the `BFILE` value, which generates a `NO_DATA_FOUND` exception:

```
DECLARE
    fil BFILE;
    pos INTEGER;
    amt BINARY_INTEGER;
    buf RAW(40);
BEGIN
    SELECT ad_graphic INTO fil FROM print_media WHERE product_id = 3106;
    dbms_lob.open(fil, dbms_lob.lob_readonly);
    amt := 40; pos := 1 + dbms_lob.getlength(fil); buf := '';
    dbms_lob.read(fil, amt, pos, buf);
    dbms_output.put_line('Read F1 past EOF: ' ||
        utl_raw.cast_to_varchar2(buf));
    dbms_lob.close(fil);
END;
```

```
ORA-01403: no data found
ORA-06512: at "SYS.DBMS_LOB", line 373
ORA-06512: at line 10
```

After the exception has occurred, the `BFILE` locator variable `file` goes out of scope, and no further operations on the file can be done using that variable. Therefore, the solution is to use an exception handler:

```
DECLARE
    fil BFILE;
    pos INTEGER;
    amt BINARY_INTEGER;
    buf RAW(40);
BEGIN
```

```
SELECT ad_graphic INTO fil FROM print_media WHERE product_id = 3106;
dbms_lob.open(fil, dbms_lob.lob_readonly);
amt := 40; pos := 1 + dbms_lob.getlength(fil); buf := '';
dbms_lob.read(fil, amt, pos, buf);
dbms_output.put_line('Read F1 past EOF: ' ||
    utl_raw.cast_to_varchar2(buf));
dbms_lob.close(fil);
exception
WHEN no_data_found
THEN
    BEGIN
        dbms_output.put_line('End of File reached. Closing file');
        dbms_lob.fileclose(fil);
        -- or dbms_lob.filecloseall if appropriate
    END;
END;
```

```
Statement processed.
End of File reached. Closing file
```

In general, you should ensure that files opened in a PL/SQL block using `DBMS_LOB` are closed before normal or abnormal termination of the block.

Maximum LOB Size

The maximum size of a LOB supported by the database is equal to the value of the `db_block_size` initialization parameter times the value 4294967295. This allows for a maximum LOB size ranging from 8 terabytes to 128 terabytes.

Maximum Buffer Size

The maximum buffer size, 32767 bytes, is represented by `maxbufsize`.

Operational Notes

All `DBMS_LOB` subprograms work based on LOB locators. For the successful completion of `DBMS_LOB` subprograms, you must provide an input locator that represents a LOB that already exists in the database tablespaces or external file system. See also Chapter 1 of *Oracle Database Application Developer's Guide - Large Objects*.

To use LOBs in your database, you must first use SQL data definition language (DDL) to define the tables that contain LOB columns.

- [Internal LOBs](#)
- [External LOBs](#)
- [Temporary LOBs](#)

Internal LOBs

To populate your table with internal LOBs after LOB columns are defined in a table, you use the SQL data manipulation language (DML) to initialize or populate the locators in the LOB columns.

External LOBs

For an external LOB (BFILE) to be represented by a LOB locator, you must:

- Ensure that a DIRECTORY object representing a valid, existing physical directory has been defined, and that physical files (the LOBs you plan to add) exist with read permission for the database. If your operating system uses case-sensitive path names, then be sure you specify the directory in the correct format.
- Pass the DIRECTORY object and the filename of the external LOB you are adding to the BFILENAME function to create a LOB locator for your external LOB.

Once you have completed these tasks, you can insert or update a row containing a LOB column using the given LOB locator.

After the LOBs are defined and created, you can then SELECT from a LOB locator into a local PL/SQL LOB variable and use this variable as an input parameter to DBMS_LOB for access to the LOB value.

For details on the different ways to do this, you must refer to the section of the *Oracle Database Application Developer's Guide - Large Objects* that describes *Accessing External LOBs (BFILES)*.

Temporary LOBs

The database supports the definition, creation, deletion, access, and update of temporary LOBs. Your temporary tablespace stores the temporary LOB data. Temporary LOBs are not permanently stored in the database. Their purpose is mainly to perform transformations on LOB data.

For temporary LOBs, you must use the OCI, PL/SQL, or another programmatic interface to create or manipulate them. Temporary LOBs can be either BLOBs, CLOBs, or NCLOBs.

A temporary LOB is empty when it is created. By default, all temporary LOBs are deleted at the end of the session in which they were created. If a process dies unexpectedly or if the database crashes, then temporary LOBs are deleted, and the space for temporary LOBs is freed.

There is also an interface to let you group temporary LOBs together into a logical bucket. The duration represents this logical store for temporary LOBs. Each temporary LOB can have separate storage characteristics, such as `CACHE/ NOCACHE`. There is a default store for every session into which temporary LOBs are placed if you don't specify a specific duration. Additionally, you are able to perform a free operation on durations, which causes all contents in a duration to be freed.

There is no support for consistent read (CR), undo, backup, parallel processing, or transaction management for temporary LOBs. Because CR and rollbacks are not supported for temporary LOBs, you must free the temporary LOB and start over again if you encounter an error.

Because CR, undo, and versions are not generated for temporary LOBs, there is potentially a performance impact if you assign multiple locators to the same temporary LOB. Semantically, each locator should have its own copy of the temporary LOB.

A copy of a temporary LOB is created if the user modifies the temporary LOB while another locator is also pointing to it. The locator on which a modification was performed now points to a new copy of the temporary LOB. Other locators no longer see the same data as the locator through which the modification was made. A deep copy was not incurred by permanent LOBs in these types of situations, because CR snapshots and version pages enable users to see their own versions of the LOB cheaply.

You can gain pseudo-REF semantics by using pointers to locators in OCI and by having multiple pointers to locators point to the same temporary LOB locator, if necessary. In PL/SQL, you must avoid using more than one locator for each temporary LOB. The temporary LOB locator can be passed by reference to other procedures.

Because temporary LOBs are not associated with any table schema, there are no meanings to the terms in-row and out-of-row temporary LOBs. Creation of a temporary LOB instance by a user causes the engine to create and return a locator to the LOB data. The PL/SQL `DBMS_LOB` package, PRO*C, OCI, and other programmatic interfaces operate on temporary LOBs through these locators just as they do for permanent LOBs.

There is no support for client side temporary LOBs. All temporary LOBs reside in the server.

Temporary LOBs do not support the `EMPTY_BLOB` or `EMPTY_CLOB` functions that are supported for permanent LOBs. The `EMPTY_BLOB` function specifies the fact that the LOB is initialized, but not populated with any data.

A temporary LOB instance can only be destroyed by using OCI or the `DBMS_LOB` package by using the appropriate `FREETEMPORARY` or `OCIDurationEnd` statement.

A temporary LOB instance can be accessed and modified using appropriate OCI and `DBMS_LOB` statements, just as for regular permanent internal LOBs. To make a temporary LOB permanent, you must explicitly use the OCI or `DBMS_LOB COPY` command, and copy the temporary LOB into a permanent one.

Security is provided through the LOB locator. Only the user who created the temporary LOB is able to see it. Locators are not expected to be able to pass from one user's session to another. Even if someone did pass a locator from one session to another, they would not access the temporary LOBs from the original session. Temporary LOB lookup is localized to each user's own session. Someone using a locator from somewhere else is only able to access LOBs within his own session that have the same LOB ID. Users should not try to do this, but if they do, they are not able to affect anyone else's data.

The database keeps track of temporary LOBs for each session in a `v$` view called `V$TEMPORARY_LOBS`, which contains information about how many temporary LOBs exist for each session. `v$` views are for DBA use. From the session, the database can determine which user owns the temporary LOBs. By using `V$TEMPORARY_LOBS` in conjunction with `DBA_SEGMENTS`, a DBA can see how much space is being used by a session for temporary LOBs. These tables can be used by DBAs to monitor and guide any emergency cleanup of temporary space used by temporary LOBs.

The following notes are specific to temporary LOBs:

1. All functions in `DBMS_LOB` return `NULL` if any of the input parameters are `NULL`. All procedures in `DBMS_LOB` raise an exception if the LOB locator is input as `NULL`.
2. Operations based on `CLOBs` do not verify if the character set IDs of the parameters (`CLOB` parameters, `VARCHAR2` buffers and patterns, and so on) match. It is the user's responsibility to ensure this.
3. Data storage resources are controlled by the DBA by creating different temporary tablespaces. DBAs can define separate temporary tablespaces for different users, if necessary.

4. Temporary LOBs still adhere to value semantics in order to be consistent with permanent LOBs and to try to conform to the ANSI standard for LOBs. As a result, each time a user does an `OCILOBLocatorAssign`, or the equivalent assignment in PL/SQL, the database makes a copy of the temporary LOB.

Each locator points to its own LOB value. If one locator is used to create a temporary LOB, and then is assigned to another LOB locator using `OCILOBLocatorAssign` in OCI or through an assignment operation in PL/SQL, then the database copies the original temporary LOB and causes the second locator to point to the copy.

In order for users to modify the same LOB, they must go through the same locator. In OCI, this can be accomplished fairly easily by using pointers to locators and assigning the pointers to point to the same locator. In PL/SQL, the same LOB variable must be used to update the LOB to get this effect.

The following example shows a place where a user incurs a copy, or at least an extra round-trip to the server.

```
DECLARE
  a blob;
  b blob;
BEGIN
  dbms_lob.createtemporary(b, TRUE);
  -- the following assignment results in a deep copy
  a := b;
END;
```

The PL/SQL compiler makes temporary copies of actual arguments bound to OUT or IN OUT parameters. If the actual parameter is a temporary LOB, then the temporary copy is a deep (value) copy.

The following PL/SQL block illustrates the case where the user incurs a deep copy by passing a temporary LOB as an IN OUT parameter.

```
DECLARE
  a blob;
  procedure foo(parm IN OUT blob) is
  BEGIN
    ...
  END;
BEGIN
  dbms_lob.createtemporary(a, TRUE);
  -- the following call results in a deep copy of the blob a
  foo(a);
END;
```

To minimize deep copies on PL/SQL parameter passing, use the `NOCOPY` compiler hint where possible.

The duration parameter passed to `dbms_lob.createtemporary()` is a hint. The duration of the new temp LOB is the same as the duration of the locator variable in PL/SQL. For example, in the preceding program block, the program variable `a` has the duration of the residing frame. Therefore at the end of the block, memory of `a` will be freed at the end of the function.

If a PL/SQL package variable is used to create a temp LOB, it will have the duration of the package variable, which has a duration of `SESSION`.

```
BEGIN
  y clob;
END;
/
BEGIN
  dbms_lob.createtemporary(package.y, TRUE);
END;
```

See Also: *PL/SQL User's Guide and Reference* for more information on `NOCOPY` syntax

Exceptions

Table 45–2 *DBMS_LOB Exceptions*

Exception	Code	Description
<code>INVALID_ARGVAL</code>	21560	The argument is expecting a nonNULL, valid value but the argument value passed in is NULL, invalid, or out of range.
<code>ACCESS_ERROR</code>	22925	You are trying to write too much data to the LOB: LOB size is limited to 4 gigabytes.
<code>NOEXIST_DIRECTORY</code>	22285	The directory leading to the file does not exist.
<code>NOPRIV_DIRECTORY</code>	22286	The user does not have the necessary access privileges on the directory or the file for the operation.
<code>INVALID_DIRECTORY</code>	22287	The directory used for the current operation is not valid if being accessed for the first time, or if it has been modified by the DBA since the last access.

Table 45-2 DBMS_LOB Exceptions

Exception	Code	Description
OPERATION_FAILED	22288	The operation attempted on the file failed.
UNOPENED_FILE	22289	The file is not open for the required operation to be performed.
OPEN_TOOMANY	22290	The number of open files has reached the maximum limit.
NO_DATA_FOUND		EndofLob indicator for looping read operations. This is not a hard error.
VALUE_ERROR	6502	PL/SQL error for invalid values to subprogram's parameters.

Summary of DBMS_LOB Subprograms

Table 45–3 DBMS_LOB Package Subprograms

Subprogram	Description
APPEND Procedure on page 45-17	Appends the contents of the source LOB to the destination LOB
CLOSE Procedure on page 45-19	Closes a previously opened internal or external LOB
COMPARE Function on page 45-21	Compares two entire LOBs or parts of two LOBs
CONVERTTOBLOB Procedure on page 45-24	Reads character data from a source CLOB or NCLOB instance, converts the character data to the specified character, writes the converted data to a destination BLOB instance in binary format, and returns the new offsets
CONVERTTOCLOB Procedure on page 45-28	Takes a source BLOB instance, converts the binary data in the source instance to character data using the specified character, writes the character data to a destination CLOB or NCLOB instance, and returns the new offsets
COPY Procedure on page 45-32	Copies all, or part, of the source LOB to the destination LOB
CREATETEMPORARY Procedure on page 45-34	Creates a temporary BLOB or CLOB and its corresponding index in the user's default temporary tablespace
ERASE Procedure on page 45-35	Erases all or part of a LOB
FILECLOSE Procedure on page 45-37	Closes the file
FILECLOSEALL Procedure on page 45-39	Closes all previously opened files
FILEEXISTS Function on page 45-40	Checks if the file exists on the server
FILEGETNAME Procedure on page 45-42	Gets the directory object name and file name
FILEISOPEN Function on page 45-43	Checks if the file was opened using the input BFILE locators

Table 45–3 (Cont.) DBMS_LOB Package Subprograms

Subprogram	Description
FILEOPEN Procedure on page 45-45	Opens a file
FREETEMPORARY Procedure on page 45-47	Frees the temporary BLOB or CLOB in the user's default temporary tablespace
GETCHUNKSIZE Function on page 45-49	Returns the amount of space used in the LOB chunk to store the LOB value
GETLENGTH Function on page 45-51	Gets the length of the LOB value
GET_STORAGE_LIMIT on page 45-48	Returns the storage limit for LOBs in your database configuration
INSTR Function on page 45-53	Returns the matching position of the <i>n</i> th occurrence of the pattern in the LOB
ISOPEN Function on page 45-56	Checks to see if the LOB was already opened using the input locator
ISTEMPORARY Function on page 45-58	Checks if the locator is pointing to a temporary LOB
LOADFROMFILE Procedure on page 45-59	Loads BFILE data into an internal LOB
LOADBLOBFROMFILE Procedure on page 45-62	Loads BFILE data into an internal BLOB
LOADCLOBFROMFILE Procedure on page 45-65	Loads BFILE data into an internal CLOB
OPEN Procedure on page 45-69	Opens a LOB (internal, external, or temporary) in the indicated mode
READ Procedure on page 45-71	Reads data from the LOB starting at the specified offset
SUBSTR Function on page 45-74	Returns part of the LOB value starting at the specified offset
TRIM Procedure on page 45-77	Trims the LOB value to the specified shorter length
WRITE Procedure on page 45-79	Writes data to the LOB from a specified offset
WRITEAPPEND Procedure on page 45-82	Writes a buffer to the end of a LOB

APPEND Procedure

This procedure appends the contents of a source internal LOB to a destination LOB. It appends the complete source LOB.

There are two overloaded APPEND procedures.

Syntax

```
DBMS_LOB.APPEND (
  dest_lob IN OUT NOCOPY BLOB,
  src_lob  IN          BLOB);
```

```
DBMS_LOB.APPEND (
  dest_lob IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
  src_lob  IN          CLOB CHARACTER SET dest_lob%CHARSET);
```

Parameters

Table 45–4 APPEND Procedure Parameters

Parameter	Description
dest_lob	Locator for the internal LOB to which the data is to be appended.
src_lob	Locator for the internal LOB from which the data is to be read.

Exceptions

Table 45–5 APPEND Procedure Exceptions

Exception	Description
VALUE_ERROR	Either the source or the destination LOB is NULL.

Usage Notes

It is not mandatory that you wrap the LOB operation inside the Open/Close APIs. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the `LOB` operation inside the `Open/Close` API, the functional and domain indexes are updated each time you write to the `LOB`. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the `LOB` within the `OPEN` or `CLOSE` statement.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

CLOSE Procedure

This procedure closes a previously opened internal or external LOB.

Syntax

```
DBMS_LOB.CLOSE (
    lob_loc    IN OUT NOCOPY BLOB);

DBMS_LOB.CLOSE (
    lob_loc    IN OUT NOCOPY CLOB CHARACTER SET ANY_CS);

DBMS_LOB.CLOSE (
    file_loc   IN OUT NOCOPY BFILE);
```

Parameters

Table 45–6 *CLOSE Procedure Parameters*

Parameter	Description
lob_loc	LOB locator. For more information, see Operational Notes .

Exceptions

No error is returned if the BFILE exists but is not opened. An error is returned if the LOB is not open.

Usage Notes

CLOSE requires a round-trip to the server for both internal and external LOBs. For internal LOBs, CLOSE triggers other code that relies on the close call, and for external LOBs (BFILES), CLOSE actually closes the server-side operating system file.

It is not mandatory that you wrap all LOB operations inside the Open/Close APIs. However, if you open a LOB, you must close it before you commit or rollback the transaction; an error is produced if you do not. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

It is an error to commit the transaction before closing all opened LOBs that were opened by the transaction. When the error is returned, the openness of the open LOBs is discarded, but the transaction is successfully committed. Hence, all the changes made to the LOB and non-LOB data in the transaction are committed, but

the domain and function-based indexes are not updated. If this happens, you should rebuild the functional and domain indexes on the LOB column.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

COMPARE Function

This function compares two entire LOBs or parts of two LOBs.

Syntax

```
DBMS_LOB.COMPARE (
    lob_1          IN BLOB,
    lob_2          IN BLOB,
    amount         IN INTEGER := 4294967295,
    offset_1       IN INTEGER := 1,
    offset_2       IN INTEGER := 1)
RETURN INTEGER;
```

```
DBMS_LOB.COMPARE (
    lob_1          IN CLOB CHARACTER SET ANY_CS,
    lob_2          IN CLOB CHARACTER SET lob_1%CHARSET,
    amount         IN INTEGER := 4294967295,
    offset_1       IN INTEGER := 1,
    offset_2       IN INTEGER := 1)
RETURN INTEGER;
```

```
DBMS_LOB.COMPARE (
    lob_1          IN BFILE,
    lob_2          IN BFILE,
    amount         IN INTEGER,
    offset_1       IN INTEGER := 1,
    offset_2       IN INTEGER := 1)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(COMPARE, WNDS, WNPS, RNDS, RNPS);
```

Parameters

Table 45-7 COMPARE Function Parameters

Parameter	Description
lob_1	LOB locator of first target for comparison.
lob_2	LOB locator of second target for comparison.
amount	Number of bytes (for BLOBs) or characters (for CLOBs) to compare.

Table 45–7 COMPARE Function Parameters

Parameter	Description
<code>offset_1</code>	Offset in bytes or characters on the first LOB (origin: 1) for the comparison.
<code>offset_2</code>	Offset in bytes or characters on the first LOB (origin: 1) for the comparison.

Return Values

- INTEGER: Zero if the comparison succeeds, nonzero if not.
- NULL, if
 - `amount < 1`
 - `amount > LOBMAXSIZE`
 - `offset_1` or `offset_2 < 1`
 - * `offset_1` or `offset_2 > LOBMAXSIZE`

Usage Notes

You can only compare LOBs of the same datatype (LOBs of BLOB type with other BLOBs, and CLOBs with CLOBs, and BFILEs with BFILEs). For BFILEs, the file must be already opened using a successful FILEOPEN operation for this operation to succeed.

COMPARE returns zero if the data exactly matches over the range specified by the `offset` and `amount` parameters. Otherwise, a nonzero INTEGER is returned.

For fixed-width n -byte CLOBs, if the input `amount` for COMPARE is specified to be greater than $(4294967295/n)$, then COMPARE matches characters in a range of size $(4294967295/n)$, or $\text{Max}(\text{length}(\text{clob1}), \text{length}(\text{clob2}))$, whichever is lesser.

Exceptions

Table 45–8 COMPARE Function Exceptions for BFILE operations

Exception	Description
<code>UNOPENED_FILE</code>	File was not opened using the input locator.
<code>NOEXIST_DIRECTORY</code>	Directory does not exist.

Table 45–8 COMPARE Function Exceptions for BFILE operations

Exception	Description
NOPRIV_DIRECTORY	You do not have privileges for the directory.
INVALID_DIRECTORY	Directory has been invalidated after the file was opened.
INVALID_OPERATION	File does not exist, or you do not have access privileges on the file.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

CONVERTTOBLOB Procedure

This procedure reads character data from a source CLOB or NCLOB instance, converts the character data to the character set you specify, writes the converted data to a destination BLOB instance in binary format, and returns the new offsets. You can use this interface with any combination of persistent or temporary LOB instances as the source or destination.

Syntax

```
DBMS_LOB.CONVERTTOBLOB(
  dest_lob      IN OUT      NOCOPY BLOB,
  src_clob      IN          CLOB CHARACTER SET ANY_CS,
  amount       IN          INTEGER,
  dest_offset   IN OUT      INTEGER,
  src_offset    IN OUT      INTEGER,
  blob_csid    IN          NUMBER,
  lang_context  IN OUT      INTEGER,
  warning      OUT          INTEGER);
```

Parameters

Table 45–9 *CONVERTTOBLOB Procedure Parameters*

Parameter	Description
dest_lob	LOB locator of the destination LOB instance.
src_blob	LOB locator of the source LOB instance.
amount	Number of characters to convert from the source LOB. If you want to copy the entire LOB, pass the constant DBMS_LOB.LOBMAXSIZE. If you pass any other value, it must be less than or equal to the size of the LOB.
dest_offset	(IN) Offset in bytes in the destination LOB for the start of the write. Specify a value of 1 to start at the beginning of the LOB. (OUT) The new offset in bytes after the end of the write.
src_offset	(IN) Offset in characters in the source LOB for the start of the read. (OUT) Offset in characters in the source LOB right after the end of the read.
blob_csid	Desired character set ID of the converted data.

Table 45–9 (Cont.) CONVERTTLOB Procedure Parameters (Cont.)

Parameter	Description
lang_context	<p>(IN) Language context, such as shift status, for the current conversion.</p> <p>(OUT) The language context at the time when the current conversion is done.</p> <p>This information is returned so you can use it for subsequent conversions without losing or misinterpreting any source data. For the very first conversion, or if do not care, use the default value of zero.</p>
warning	<p>(OUT) Warning message. This parameter indicates when something abnormal happened during the conversion. You are responsible for checking the warning message.</p> <p>Currently, the only possible warning is — inconvertible character. This occurs when the character in the source cannot be properly converted to a character in destination. The default replacement character (for example, '?') is used in place of the inconvertible character. The return value of this error message is defined as the constant warn_inconvertible_char in the DBMS_LOB package.</p>

Usage Notes

Preconditions

Before calling the CONVERTTLOB procedure, the following preconditions must be met:

- Both the source and destination LOB instances must exist.
- If the destination LOB is a persistent LOB, the row must be locked. To lock the row, select the LOB using the FOR UPDATE clause of the SELECT statement.

Constants and Defaults

All parameters are required. You must pass a variable for each OUT or IN OUT parameter. You must pass either a variable or a value for each IN parameter.

Table 45–10 gives a summary of typical values for each parameter. The first column lists the parameter, the second column lists the typical value, and the last column describes the result of passing the value. Note that constants are used for some values. These constants are defined in the dbmslob.sql package specification file.

Table 45–10 *DBMS_LOB.CONVERTTOBLOB Typical Values*

Parameter	Value	Description
amount	lobmaxsize (IN)	convert the entire file
dest_offset	1 (IN)	start from the beginning
src_offset	1 (IN)	start from the beginning
csid	default_csid (IN)	default csid, use same csid as source LOB
lang_context	default_lang_ctx (IN)	default language context
warning	no_warning (OUT) warn_inconvertible_char (OUT)	no warning message, success character in source cannot be properly converted

General Notes

You must specify the desired character set for the destination LOB in the `blob_csid` parameter. You can pass a zero value for `blob_csid`. When you do so, the database assumes that the desired character set is the same as the source LOB character set, and performs a binary copy of the data—no character set conversion is performed.

You must specify the offsets for both the source and destination LOBs, and the number of bytes to copy from the source LOB. The `amount` and `src_offset` values are in characters and the `dest_offset` is in bytes. To convert the entire LOB, you can specify `LOBMAXSIZE` for the `amount` parameter.

Exceptions

[Table 45–11](#) gives possible exceptions this procedure can throw. The first column lists the exception string and the second column describes the error conditions that can cause the exception.

Table 45–11 *CONVERTTOBLOB Procedure Exceptions*

Exception	Description
VALUE_ERROR	Any of the input parameters are NULL or INVALID.

Table 45–11 (Cont.) CONVERTTOBLOB Procedure Exceptions

Exception	Description
INVALID_ARGVAL	One or more of the following: <ul style="list-style-type: none">- src_offset or dest_offset < 1.- src_offset or dest_offset > LOBMAXSIZE.- amount < 1.- amount > LOBMAXSIZE.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for more information on using LOBs in application development

CONVERTTOCLOB Procedure

This procedure takes a source BLOB instance, converts the binary data in the source instance to character data using the character set you specify, writes the character data to a destination CLOB or NCLOB instance, and returns the new offsets. You can use this interface with any combination of persistent or temporary LOB instances as the source or destination.

Syntax

```
DBMS_LOB.CONVERTTOCLOB(
    dest_lob      IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
    src_blob      IN              BLOB,
    amount        IN              INTEGER,
    dest_offset   IN OUT         INTEGER,
    src_offset     IN OUT         INTEGER,
    blob_csid     IN              NUMBER,
    lang_context  IN OUT         INTEGER,
    warning       OUT             INTEGER);
```

Parameters

Table 45–12 *CONVERTTOCLOB Procedure Parameters*

Parameter	Description
dest_lob	LOB locator of the destination LOB instance.
src_blob	LOB locator of the source LOB instance.
amount	Number of bytes to convert from the source LOB. If you want to copy the entire BLOB, pass the constant DBMS_LOB.LOBMAXSIZE. If you pass any other value, it must be less than or equal to the size of the BLOB.
dest_offset	(IN) Offset in characters in the destination LOB for the start of the write. Specify a value of 1 to start at the beginning of the LOB. (OUT) The new offset in characters after the end of the write. This offset always points to the beginning of the first complete character after the end of the write.
src_offset	(IN) Offset in bytes in the source LOB for the start of the read. (OUT) Offset in bytes in the source LOB right after the end of the read.

Table 45–12 (Cont.) CONVERTTOCLOB Procedure Parameters (Cont.)

Parameter	Description
blob_csid	Desired character set ID of the converted data.
lang_context	<p>(IN) Language context, such as shift status, for the current conversion.</p> <p>(OUT) The language context at the time when the current conversion is done.</p> <p>This information is returned so you can use it for subsequent conversions without losing or misinterpreting any source data. For the very first conversion, or if do not care, use the default value of zero.</p>
warning	<p>Warning message. This parameter indicates when something abnormal happened during the conversion. You are responsible for checking the warning message.</p> <p>Currently, the only possible warning is — inconvertible character. This occurs when the character in the source cannot be properly converted to a character in destination. The default replacement character (for example, '?') is used in place of the inconvertible character. The return value of this error message is defined as the constant <code>warn_inconvertible_char</code> in the <code>DBMS_LOB</code> package.</p>

Usage Notes

Preconditions

Before calling the `CONVERTTOCLOB` procedure, the following preconditions must be met:

- Both the source and destination LOB instances must exist.
- If the destination LOB is a persistent LOB, the row must be locked before calling the `CONVERTTOCLOB` procedure. To lock the row, select the LOB using the `FOR UPDATE` clause of the `SELECT` statement.

Constants and Defaults

All parameters are required. You must pass a variable for each `OUT` or `IN OUT` parameter. You must pass either a variable or a value for each `IN` parameter.

[Table 45–13](#) gives a summary of typical values for each parameter. The first column lists the parameter, the second column lists the typical value, and the last column describes the result of passing the value. Note that constants are used for some values. These constants are defined in the `dbmslob.sql` package specification file.

Table 45–13 DBMS_LOB.CONVERTTOCLOB Typical Values

Parameter	Value	Description
amount	lobmaxsize (IN)	convert the entire file
dest_offset	1 (IN)	start from the beginning
src_offset	1 (IN)	start from the beginning
csid	default_csid (IN)	default csid, use destination csid
lang_context	default_lang_ctx (IN)	default language context
warning	no_warning (OUT) warn_inconvertible_char (OUT)	no warning message, success character in source cannot be properly converted

General Notes

You must specify the desired character set for the destination LOB in the `blob_csid` parameter. You can pass a zero value for `blob_csid`. When you do so, the database assumes that the BLOB contains character data in the same character set as the destination CLOB, and performs a binary copy of the data to the destination LOB, no character set conversion being performed.

You must specify the offsets for both the source and destination LOBs, and the number of bytes to copy from the source BLOB. The `amount` and `src_offset` values are in bytes and the `dest_offset` is in characters. To convert the entire BLOB, you can specify `LOBMAXSIZE` for the `amount` parameter.

Exceptions

Table 45–14 CONVERTTOCLOB Procedure Exceptions

Exception	Description
VALUE_ERROR	Any of the input parameters are NULL or INVALID.
INVALID_ARGVAL	One or more of the following: <ul style="list-style-type: none"> - <code>src_offset</code> or <code>dest_offset</code> < 1. - <code>src_offset</code> or <code>dest_offset</code> > <code>LOBMAXSIZE</code>. - <code>amount</code> < 1. - <code>amount</code> > <code>LOBMAXSIZE</code>.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for more information on using LOBs in application development

COPY Procedure

This procedure copies all, or a part of, a source internal LOB to a destination internal LOB. You can specify the offsets for both the source and destination LOBs, and the number of bytes or characters to copy.

Syntax

```
DBMS_LOB.COPY (
  dest_lob   IN OUT NOCOPY BLOB,
  src_lob    IN           BLOB,
  amount     IN           INTEGER,
  dest_offset IN           INTEGER := 1,
  src_offset IN           INTEGER := 1);
```

```
DBMS_LOB.COPY (
  dest_lob   IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
  src_lob    IN           CLOB CHARACTER SET dest_lob%CHARSET,
  amount     IN           INTEGER,
  dest_offset IN           INTEGER := 1,
  src_offset IN           INTEGER := 1);
```

Parameters

Table 45–15 COPY Procedure Parameters

Parameter	Description
dest_lob	LOB locator of the copy target.
src_lob	LOB locator of source for the copy.
amount	Number of bytes (for BLOBs) or characters (for CLOBs) to copy.
dest_offset	Offset in bytes or characters in the destination LOB (origin: 1) for the start of the copy.
src_offset	Offset in bytes or characters in the source LOB (origin: 1) for the start of the copy.

Exceptions

Table 45–16 COPY Procedure Exceptions

Exception	Description
VALUE_ERROR	Any of the input parameters are NULL or invalid.
INVALID_ARGVAL	Either: <ul style="list-style-type: none"> - src_offset or dest_offset < 1 - src_offset or dest_offset > LOBMAXSIZE - amount < 1 - amount > LOBMAXSIZE

Usage Notes

If the offset you specify in the destination LOB is beyond the end of the data currently in this LOB, then zero-byte fillers or spaces are inserted in the destination BLOB or CLOB respectively. If the offset is less than the current length of the destination LOB, then existing data is overwritten.

It is not an error to specify an amount that exceeds the length of the data in the source LOB. Thus, you can specify a large amount to copy from the source LOB, which copies data from the `src_offset` to the end of the source LOB.

It is not mandatory that you wrap the LOB operation inside the Open/Close APIs. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the Open/Close API, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the OPEN or CLOSE statement.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

CREATETEMPORARY Procedure

This procedure creates a temporary BLOB or CLOB and its corresponding index in your default temporary tablespace.

Syntax

```
DBMS_LOB.CREATETEMPORARY (
    lob_loc IN OUT NOCOPY BLOB,
    cache   IN           BOOLEAN,
    dur     IN           PLS_INTEGER := 10);

DBMS_LOB.CREATETEMPORARY (
    lob_loc IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
    cache   IN           BOOLEAN,
    dur     IN           PLS_INTEGER := 10);
```

Parameters

Table 45–17 CREATETEMPORARY Procedure Parameters

Parameter	Description
lob_loc	LOB locator. For more information, see Operational Notes .
cache	Specifies if LOB should be read into buffer cache or not.
dur	1 of 2 predefined duration values (SESSION or CALL) which specifies a hint as to whether the temporary LOB is cleaned up at the end of the session or call. If dur is omitted, then the session duration is used.

See Also:

- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure
- *PL/SQL User's Guide and Reference* for more information about NOCOPY and passing temporary lob as parameters

ERASE Procedure

This procedure erases an entire internal LOB or part of an internal LOB.

Syntax

```
DBMS_LOB.ERASE (
  lob_loc          IN OUT NOCOPY BLOB,
  amount          IN OUT NOCOPY INTEGER,
  offset          IN              INTEGER := 1);

DBMS_LOB.ERASE (
  lob_loc          IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
  amount          IN OUT NOCOPY INTEGER,
  offset          IN              INTEGER := 1);
```

Parameters

Table 45–18 ERASE Procedure Parameters

Parameter	Description
lob_loc	Locator for the LOB to be erased. For more information, see Operational Notes .
amount	Number of bytes (for BLOBs or BFILES) or characters (for CLOBs or NCLOBs) to be erased.
offset	Absolute offset (origin: 1) from the beginning of the LOB in bytes (for BLOBs) or characters (CLOBs).

Usage Notes

Note: The length of the LOB is not decreased when a section of the LOB is erased. To decrease the length of the LOB value, see the ["TRIM Procedure"](#) on page 45-77.

When data is erased from the middle of a LOB, zero-byte fillers or spaces are written for BLOBs or CLOBs respectively.

The actual number of bytes or characters erased can differ from the number you specified in the `amount` parameter if the end of the LOB value is reached before

erasing the specified number. The actual number of characters or bytes erased is returned in the `amount` parameter.

Exceptions

Table 45–19 *ERASE Procedure Exceptions*

Exception	Description
VALUE_ERROR	Any input parameter is NULL.
INVALID_ARGVAL	Either: - <code>amount < 1</code> or <code>amount > LOBMAXSIZE</code> - <code>offset < 1</code> or <code>offset > LOBMAXSIZE</code>

Usage Notes

It is not mandatory that you wrap the LOB operation inside the Open/Close APIs. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the Open/Close API, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the OPEN or CLOSE statement.

See Also:

- ["TRIM Procedure"](#) on page 45-77
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

FILECLOSE Procedure

This procedure closes a BFILE that has already been opened through the input locator.

Note: The database has only read-only access to BFILES. This means that BFILES cannot be written through the database.

Syntax

```
DBMS_LOB.FILECLOSE (
    file_loc IN OUT NOCOPY BFILE);
```

Parameters

Table 45–20 FILECLOSE Procedure Parameter

Parameter	Description
file_loc	Locator for the BFILE to be closed.

Exceptions

Table 45–21 FILECLOSE Procedure Exceptions

Exception	Description
VALUE_ERROR	NULL input value for file_loc.
UNOPENED_FILE	File was not opened with the input locator.
NOEXIST_ DIRECTORY	Directory does not exist.
NOPRIV_DIRECTORY	You do not have privileges for the directory.
INVALID_ DIRECTORY	Directory has been invalidated after the file was opened.
INVALID_ OPERATION	File does not exist, or you do not have access privileges on the file.

See Also:

- ["FILEOPEN Procedure"](#) on page 45-45
- ["FILECLOSEALL Procedure"](#) on page 45-39
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

FILECLOSEALL Procedure

This procedure closes all `BFILE`s opened in the session.

Syntax

```
DBMS_LOB.FILECLOSEALL;
```

Exceptions

Table 45–22 *FILECLOSEALL Procedure Exception*

Exception	Description
<code>UNOPENED_FILE</code>	No file has been opened in the session.

See Also:

- ["FILEOPEN Procedure"](#) on page 45-45
- ["FILECLOSE Procedure"](#) on page 45-37
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

FILEEXISTS Function

This function finds out if a given `BFILE` locator points to a file that actually exists on the server's file system.

Syntax

```
DBMS_LOB.FILEEXISTS (  
    file_loc    IN    BFILE)  
    RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(FILEEXISTS, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 45-23 FILEEXISTS Function Parameter

Parameter	Description
<code>file_loc</code>	Locator for the <code>BFILE</code> .

Return Values

Table 45-24 FILEEXISTS Function Return Values

Return	Description
0	Physical file does not exist.
1	Physical file exists.

Exceptions

Table 45-25 FILEEXISTS Function Exceptions

Exception	Description
<code>NOEXIST_DIRECTORY</code>	Directory does not exist.
<code>NOPRIV_DIRECTORY</code>	You do not have privileges for the directory.

Table 45-25 FILEEXISTS Function Exceptions

Exception	Description
INVALID_ DIRECTORY	Directory has been invalidated after the file was opened.

See Also:

- ["FILEISOPEN Function"](#) on page 45-43.
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

FILEGETNAME Procedure

This procedure determines the directory object and filename, given a BFILE locator. This function only indicates the directory object name and filename assigned to the locator, not if the physical file or directory actually exists.

The maximum constraint values for the `dir_alias` buffer is 30, and for the entire path name, it is 2000.

Syntax

```
DBMS_LOB.FILEGETNAME (  
    file_loc   IN   BFILE,  
    dir_alias  OUT  VARCHAR2,  
    filename   OUT  VARCHAR2);
```

Parameters

Table 45–26 FILEGETNAME Procedure Parameters

Parameter	Description
<code>file_loc</code>	Locator for the BFILE
<code>dir_alias</code>	Directory object name
<code>filename</code>	Name of the BFILE

Exceptions

Table 45–27 FILEGETNAME Procedure Exceptions

Exception	Description
<code>VALUE_ERROR</code>	Any of the input parameters are NULL or INVALID.
<code>INVALID_ARGVAL</code>	<code>dir_alias</code> or <code>filename</code> are NULL.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

FILEISOPEN Function

This function finds out whether a BFILE was opened with the given FILE locator.

Syntax

```
DBMS_LOB.FILEISOPEN (
    file_loc IN BFILE)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(FILEISOPEN, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 45–28 FILEISOPEN Function Parameter

Parameter	Description
file_loc	Locator for the BFILE.

Return Values

INTEGER: 0 = file is not open, 1 = file is open

Usage Notes

If the input FILE locator was never passed to the FILEOPEN procedure, then the file is considered not to be opened by this locator. However, a different locator may have this file open. In other words, openness is associated with a specific locator.

Exceptions

Table 45–29 FILEISOPEN Function Exceptions

Exception	Description
NOEXIST_DIRECTORY	Directory does not exist.
NOPRIV_DIRECTORY	You do not have privileges for the directory.
INVALID_DIRECTORY	Directory has been invalidated after the file was opened.

See Also:

- ["FILEEXISTS Function"](#) on page 45-40
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

FILEOPEN Procedure

This procedure opens a BFILE for read-only access. BFILE data may not be written through the database.

Syntax

```
DBMS_LOB.FILEOPEN (
    file_loc  IN OUT NOCOPY BFILE,
    open_mode IN             BINARY_INTEGER := file_readonly);
```

Parameters

Table 45–30 FILEOPEN Procedure Parameters

Parameter	Description
file_loc	Locator for the BFILE.
open_mode	File access is read-only.

Exceptions

Table 45–31 FILEOPEN Procedure Exceptions

Exception	Description
VALUE_ERROR	file_loc or open_mode is NULL.
INVALID_ARGVAL	open_mode is not equal to FILE_READONLY.
OPEN_TOOMANY	Number of open files in the session exceeds session_max_open_files.
NOEXIST_DIRECTORY	Directory associated with file_loc does not exist.
INVALID_DIRECTORY	Directory has been invalidated after the file was opened.
INVALID_OPERATION	File does not exist, or you do not have access privileges on the file.

See Also:

- ["FILECLOSE Procedure"](#) on page 45-37
- ["FILECLOSEALL Procedure"](#) on page 45-39
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

FREETEMPORARY Procedure

This procedure frees the temporary BLOB or CLOB in your default temporary tablespace.

Syntax

```
DBMS_LOB.FREETEMPORARY (
    lob_loc IN OUT NOCOPY BLOB);
```

```
DBMS_LOB.FREETEMPORARY (
    lob_loc IN OUT NOCOPY CLOB CHARACTER SET ANY_CS);
```

Parameters

Table 45–32 *FREETEMPORARY Procedure Parameters*

Parameter	Description
lob_loc	LOB locator. For more information, see Operational Notes .

Usage Notes

After the call to FREETEMPORARY, the LOB locator that was freed is marked as invalid.

If an invalid LOB locator is assigned to another LOB locator using OCILobLocatorAssign in OCI or through an assignment operation in PL/SQL, then the target of the assignment is also freed and marked as invalid.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

GET_STORAGE_LIMIT

The `DBMS_LOB.GET_STORAGE_LIMIT` function returns the LOB storage limit for your database configuration. The `DBMS_LOB` package supports LOB instances up to this storage limit in size.

Syntax

```
DBMS_LOB.GET_STORAGE_LIMIT  
    RETURN INTEGER;
```

Return Value

The value returned from this function is the maximum allowable size for LOB instances for your database configuration. The return value depends on your `DB_BLOCK_SIZE` initialization parameter setting and is calculated as (4 gigabytes minus 1) times the value of the `DB_BLOCK_SIZE` initialization parameter.

Usage

Note that BLOB instances are sized in bytes while CLOB and NCLOB instances are sized in characters.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for details on LOB storage limits

GETCHUNKSIZE Function

When creating the table, you can specify the chunking factor, which can be a multiple of database blocks. This corresponds to the chunk size used by the LOB data layer when accessing or modifying the LOB value. Part of the chunk is used to store system-related information, and the rest stores the LOB value.

This function returns the amount of space used in the LOB chunk to store the LOB value.

Syntax

```
DBMS_LOB.GETCHUNKSIZE (
    lob_loc IN BLOB)
RETURN INTEGER;
```

```
DBMS_LOB.GETCHUNKSIZE (
    lob_loc IN CLOB CHARACTER SET ANY_CS)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(GETCHUNKSIZE, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 45–33 *GETCHUNKSIZE Function Parameters*

Parameter	Description
lob_loc	LOB locator. For more information, see Operational Notes .

Return Values

The value returned for BLOBs is in terms of bytes. The value returned for CLOBs is in terms of characters.

Usage Notes

Performance is improved if you enter read/write requests using a multiple of this chunk size. For writes, there is an added benefit, because LOB chunks are versioned, and if all writes are done on a chunk basis, then no extra or excess versioning is done or duplicated. You could batch up the WRITE until you have enough for a chunk, instead of issuing several WRITE calls for the same chunk.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

GETLENGTH Function

This function gets the length of the specified LOB. The length in bytes or characters is returned.

The length returned for a BFILE includes the EOF, if it exists. Any 0-byte or space filler in the LOB caused by previous ERASE or WRITE operations is also included in the length count. The length of an empty internal LOB is 0.

Syntax

```
DBMS_LOB.GETLENGTH (
    lob_loc    IN BLOB)
    RETURN INTEGER;

DBMS_LOB.GETLENGTH (
    lob_loc    IN CLOB    CHARACTER SET ANY_CS)
    RETURN INTEGER;

DBMS_LOB.GETLENGTH (
    file_loc   IN BFILE)
    RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(GETLENGTH, WNDS, WNPS, RNDS, RNPS);
```

Parameters

Table 45–34 GETLENGTH Function Parameter

Parameter	Description
file_loc	The file locator for the LOB whose length is to be returned.

Return Values

The length of the LOB in bytes or characters as an INTEGER. NULL is returned if the input LOB is NULL or if the input lob_loc is NULL. An error is returned in the following cases for BFILES:

- lob_loc does not have the necessary directory and operating system privileges
- lob_loc cannot be read because of an operating system read error

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

INSTR Function

This function returns the matching position of the *n*th occurrence of the pattern in the LOB, starting from the offset you specify.

Syntax

```
DBMS_LOB.INSTR (
  lob_loc    IN   BLOB,
  pattern    IN   RAW,
  offset     IN   INTEGER := 1,
  nth        IN   INTEGER := 1)
RETURN INTEGER;
```

```
DBMS_LOB.INSTR (
  lob_loc    IN   CLOB          CHARACTER SET ANY_CS,
  pattern    IN   VARCHAR2     CHARACTER SET lob_loc%CHARSET,
  offset     IN   INTEGER := 1,
  nth        IN   INTEGER := 1)
RETURN INTEGER;
```

```
DBMS_LOB.INSTR (
  file_loc   IN   BFILE,
  pattern    IN   RAW,
  offset     IN   INTEGER := 1,
  nth        IN   INTEGER := 1)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(INSTR, WNDS, WNPS, RNDS, RNPS);
```

Parameters

Table 45–35 INSTR Function Parameters

Parameter	Description
lob_loc	Locator for the LOB to be examined. For more information, see Operational Notes .
file_loc	The file locator for the LOB to be examined.

Table 45–35 INSTR Function Parameters

Parameter	Description
<code>pattern</code>	Pattern to be tested for. The pattern is a group of RAW bytes for BLOBs, and a character string (VARCHAR2) for CLOBs. The maximum size of the pattern is 16383 bytes.
<code>offset</code>	Absolute offset in bytes (BLOBs) or characters (CLOBs) at which the pattern matching is to start. (origin: 1)
<code>nth</code>	Occurrence number, starting at 1.

Return Values

Table 45–36 INSTR Function Return Values

Return	Description
INTEGER	Offset of the start of the matched pattern, in bytes or characters. It returns 0 if the pattern is not found.
NULL	Either: -any one or more of the IN parameters was NULL or INVALID. -offset < 1 or offset > LOBMAXSIZE. -nth < 1. -nth > LOBMAXSIZE.

Usage Notes

The form of the VARCHAR2 buffer (the `pattern` parameter) must match the form of the CLOB parameter. In other words, if the input LOB parameter is of type NCLOB, then the buffer must contain NCHAR data. Conversely, if the input LOB parameter is of type CLOB, then the buffer must contain CHAR data.

For BFILEs, the file must be already opened using a successful FILEOPEN operation for this operation to succeed.

Operations that accept RAW or VARCHAR2 parameters for pattern matching, such as INSTR, do not support regular expressions or special matching characters (as in the case of SQL LIKE) in the pattern parameter or substrings.

Exceptions

Table 45–37 *INSTR Function Exceptions for BFILES*

Exception	Description
UNOPENED_FILE	File was not opened using the input locator.
NOEXIST_DIRECTORY	Directory does not exist.
NOPRIV_DIRECTORY	You do not have privileges for the directory.
INVALID_DIRECTORY	Directory has been invalidated after the file was opened.
INVALID_OPERATION	File does not exist, or you do not have access privileges on the file.

See Also:

- ["SUBSTR Function"](#) on page 45-74
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

ISOPEN Function

This function checks to see if the `LOB` was already opened using the input locator. This subprogram is for internal and external `LOBs`.

Syntax

```
DBMS_LOB.ISOPEN (  
    lob_loc IN BLOB)  
    RETURN INTEGER;  
  
DBMS_LOB.ISOPEN (  
    lob_loc IN CLOB CHARACTER SET ANY_CS)  
    RETURN INTEGER;  
  
DBMS_LOB.ISOPEN (  
    file_loc IN BFILE)  
    RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(ISOPEN, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 45–38 ISOPEN Function Parameters

Parameter	Description
<code>lob_loc</code>	<code>LOB</code> locator. For more information, see Operational Notes .
<code>file_loc</code>	File locator.

Usage Notes

For `BFILES`, openness is associated with the locator. If the input locator was never passed to `OPEN`, the `BFILE` is not considered to be opened by this locator. However, a different locator may have opened the `BFILE`. More than one `OPEN` can be performed on the same `BFILE` using different locators.

For internal `LOBs`, openness is associated with the `LOB`, not with the locator. If `locator1` opened the `LOB`, then `locator2` also sees the `LOB` as open. For internal `LOBs`, `ISOPEN` requires a round-trip, because it checks the state on the server to see if the `LOB` is indeed open.

For external LOBs (`BFILES`), `ISOPEN` also requires a round-trip, because that's where the state is kept.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

ISTEMPORARY Function

This function determines whether a LOB instance is temporary.

Syntax

```
DBMS_LOB.ISTEMPORARY (
    lob_loc IN BLOB)
RETURN INTEGER;

DBMS_LOB.ISTEMPORARY (
    lob_loc IN CLOB CHARACTER SET ANY_CS)
RETURN INTEGER;
```

Pragmas

```
PRAGMA RESTRICT_REFERENCES(istemporary, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 45–39 *ISTEMPORARY Procedure Parameters*

Parameter	Description
lob_loc	LOB locator. For more information, see Operational Notes .

Return Values

This function returns TRUE in temporary if the locator is pointing to a temporary LOB. It returns FALSE otherwise.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

LOADFROMFILE Procedure

This procedure copies all, or a part of, a source external LOB (BFILE) to a destination internal LOB.

Syntax

```
DBMS_LOB.LOADFROMFILE (
  dest_lob   IN OUT NOCOPY BLOB,
  src_file   IN           BFILE,
  amount     IN           INTEGER,
  dest_offset IN           INTEGER := 1,
  src_offset IN           INTEGER := 1);
```

Parameters

Table 45–40 *LOADFROMFILE Procedure Parameters*

Parameter	Description
<code>dest_lob</code>	LOB locator of the target for the load.
<code>src_file</code>	BFILE locator of the source for the load.
<code>amount</code>	Number of bytes to load from the BFILE.
<code>dest_offset</code>	Offset in bytes or characters in the destination LOB (origin: 1) for the start of the load.
<code>src_offset</code>	Offset in bytes in the source BFILE (origin: 1) for the start of the load.

Usage Notes

You can specify the offsets for both the source and destination LOBs, and the number of bytes to copy from the source BFILE. The `amount` and `src_offset`, because they refer to the BFILE, are in terms of bytes, and the `dest_offset` is either in bytes or characters for BLOBs and CLOBs respectively.

Note: The input BFILE must have been opened prior to using this procedure. No character set conversions are performed implicitly when binary BFILE data is loaded into a CLOB. The BFILE data must already be in the same character set as the CLOB in the database. No error checking is performed to verify this.

If the offset you specify in the destination LOB is beyond the end of the data currently in this LOB, then zero-byte fillers or spaces are inserted in the destination BLOB or CLOB respectively. If the offset is less than the current length of the destination LOB, then existing data is overwritten.

There is an error if the input amount plus offset exceeds the length of the data in the BFILE.

Note: If the character set is varying width, UTF-8 for example, the LOB value is stored in the fixed-width UCS2 format. Therefore, if you are using `DBMS_LOB.LOADFROMFILE`, the data in the BFILE should be in the UCS2 character set instead of the UTF-8 character set. However, you should use `sql*loader` instead of `LOADFROMFILE` to load data into a CLOB or NCLOB because `sql*loader` will provide the necessary character set conversions.

It is not mandatory that you wrap the LOB operation inside the Open/Close APIs. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the Open/Close API, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the OPEN or CLOSE statement.

Exceptions

Table 45–41 *LOADFROMFILE Procedure Exceptions*

Exception	Description
VALUE_ERROR	Any of the input parameters are NULL or INVALID.
INVALID_ARGVAL	Either: <ul style="list-style-type: none"> - <code>src_offset</code> or <code>dest_offset</code> < 1. - <code>src_offset</code> or <code>dest_offset</code> > LOBMAXSIZE. - <code>amount</code> < 1. - <code>amount</code> > LOBMAXSIZE.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

LOADBLOBFROMFILE Procedure

This procedure loads data from BFILE to internal BLOB. This achieves the same outcome as LOADFROMFILE, and returns the new offsets.

Syntax

```
DBMS_LOB.LOADBLOBFROMFILE (
  dest_lob    IN OUT NOCOPY BLOB,
  src_bfile   IN           BFILE,
  amount      IN           INTEGER,
  dest_offset IN OUT      INTEGER,
  src_offset  IN OUT      INTEGER);
```

Parameters

Table 45–42 *LOADBLOBFROMFILE Procedure Parameters*

Parameter	Description
dest_lob	BLOB locator of the target for the load.
src_bfile	BFILE locator of the source for the load.
amount	Number of bytes to load from the BFILE. You can also use DBMS_LOB.LOEMAXSIZE to load until the end of the BFILE.
dest_offset	(IN) Offset in bytes in the destination BLOB (origin: 1) for the start of the write. (OUT) New offset in bytes in the destination BLOB right after the end of this write, which is also where the next write should begin.
src_offset	(IN) Offset in bytes in the source BFILE (origin: 1) for the start of the read. (OUT) Offset in bytes in the source BFILE right after the end of this read, which is also where the next read should begin.

Usage Notes

You can specify the offsets for both the source and destination LOBs, and the number of bytes to copy from the source BFILE. The amount and src_offset, because they refer to the BFILE, are in terms of bytes, and the dest_offset is in bytes for BLOBs.

If the offset you specify in the destination LOB is beyond the end of the data currently in this LOB, then zero-byte fillers or spaces are inserted in the destination

BLOB. If the offset is less than the current length of the destination LOB, then existing data is overwritten.

There is an error if the input amount plus offset exceeds the length of the data in the BFILE (unless the amount specified is LOBMAXSIZE which you can specify to continue loading until the end of the BFILE is reached).

It is not mandatory that you wrap the LOB operation inside the OPEN/CLOSE operations. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the OPEN/CLOSE, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the OPEN or CLOSE statement.

Constants and Defaults

There is no easy way to omit parameters. You must either declare a variable for IN/OUT parameter or provide a default value for the IN parameter. Here is a summary of the constants and the defaults that can be used.

Table 45–43 Suggested Values of the Parameter

Parameter	Default Value	Description
amount	DBMSLOB.LOBMAXSIZE (IN)	Load the entire file
dest_offset	1 (IN)	start from the beginning
src_offset	1 (IN)	start from the beginning

Constants defined in DBMSLOB.SQL

lobmaxsize	CONSTANT INTEGER	:= 4294967295;
------------	------------------	----------------

Exceptions

Table 45–44 *LOADBLOBFROMFILE Procedure Exceptions*

Exception	Description
VALUE_ERROR	Any of the input parameters are NULL or INVALID.
INVALID_ARGVAL	Either: <ul style="list-style-type: none">- src_offset or dest_offset < 1.- src_offset or dest_offset > LOBMAXSIZE.- amount < 1.- amount > LOBMAXSIZE.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

LOADCLOBFROMFILE Procedure

This procedure loads data from a BFILE to an internal CLOB/NCLOB with necessary character set conversion and returns the new offsets.

Syntax

```
DBMS_LOB.LOADCLOBFROMFILE (
  dest_lob      IN OUT NOCOPY  BLOB,
  src_bfile     IN              BFILE,
  amount        IN              INTEGER,
  dest_offset   IN OUT         INTEGER,
  src_offset    IN OUT         INTEGER,
  src_csid      IN              NUMBER,
  lang_context  IN OUT         INTEGER,
  warning       OUT             INTEGER);
```

Parameters

Table 45–45 *LOADCLOBFROMFILE Procedure Parameters*

Parameter	Description
dest_lob	CLOB/NCLOB locator of the target for the load.
src_bfile	BFILE locator of the source for the load.
amount	Number of bytes to load from the BFILE. Use DBMS_LOB.LOBMAXSIZE to load until the end of the BFILE.
dest_offset	(IN) Offset in characters in the destination CLOB (origin: 1) for the start of the write. (OUT) The new offset in characters right after the end of this load, which is also where the next load should start. It always points to the beginning of the first complete character after the end of load. If the last character is not complete, offset goes back to the beginning of the partial character.
src_offset	(IN) Offset in bytes in the source BFILE (origin: 1) for the start of the read. (OUT) Offset in bytes in the source BFILE right after the end of this read, which is also where the next read should begin.
src_csid	Character set id of the source (BFILE) file.

Table 45–45 *LOADCLOBFROMFILE Procedure Parameters*

Parameter	Description
lang_context	(IN) Language context, such as shift status, for the current load. (OUT) The language context at the time when the current load stopped, and what the next load should be using if continuing loading from the same source. This information is returned to the user so that they can use it for the continuous load without losing or misinterpreting any source data. For the very first load or if do not care, simply use the default 0. The details of this language context is hidden from the user. One does not need to know what it is or what's in it in order to make the call
warning	(OUT) Warning message. This indicates something abnormal happened during the loading. It may or may not be caused by the user's mistake. The loading is completed as required, and it's up to the user to check the warning message. Currently, the only possible warning is the inconvertible character. This happens when the character in the source cannot be properly converted to a character in destination, and the default replacement character (for example, '?') is used in place. The message is defined as warn_inconvertible_char in DBMSLOB.

Usage Notes

You can specify the offsets for both the source and destination LOBs, and the number of bytes to copy from the source `BFILE`. The `amount` and `src_offset`, because they refer to the `BFILE`, are in terms of bytes, and the `dest_offset` is in characters for `CLOBs`.

If the offset you specify in the destination LOB is beyond the end of the data currently in this LOB, then zero-byte fillers or spaces are inserted in the destination CLOB. If the offset is less than the current length of the destination LOB, then existing data is overwritten.

There is an error if the input amount plus offset exceeds the length of the data in the `BFILE` (unless the amount specified is `LOBMAXSIZE` which you can specify to continue loading until the end of the `BFILE` is reached).

Note the following requirements:

- The destination character set is always the same as the database character set in the case of `CLOB` and national character set in the case of `NCLOB`.

- `csid=0` indicates the default behavior that uses database `csid` for CLOB and national `csid` for NCLOB in the place of source `csid`. Conversion is still necessary if it is of varying width
- It is not mandatory that you wrap the LOB operation inside the OPEN/CLOSE operations. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the OPEN/CLOSE, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the OPEN or CLOSE statement.

Constants and Defaults

There is no easy way to omit parameters. You must either declare a variable for IN/OUT parameter or give a default value for the IN parameter. Here is a summary of the constants and the defaults that can be used.

Table 45–46 Suggested Values of the Parameter

Parameter	Default Value	Description
<code>amount</code>	<code>DBMSLOB.LOBBMAX SIZE (IN)</code>	Load the entire file
<code>dest_offset</code>	<code>1 (IN)</code>	start from the beginning
<code>src_offset</code>	<code>1 (IN)</code>	start from the beginning
<code>csid</code>	<code>0 (IN)</code>	default <code>csid</code> , use destination <code>csid</code>
<code>lang_context</code>	<code>0 (IN)</code>	default language context
<code>warning</code>	<code>0 (OUT)</code>	no warning message, everything is ok

Constants defined in `DBMSLOB.SQL`

<code>lobmaxsize</code>	<code>CONSTANT INTEGER</code>	<code>:= 4294967295;</code>
<code>warn_inconvertible_char</code>	<code>CONSTANT INTEGER</code>	<code>:= 1;</code>
<code>default_csid</code>	<code>CONSTANT INTEGER</code>	<code>:= 0;</code>
<code>default_lang_ctx</code>	<code>CONSTANT INTEGER</code>	<code>:= 0;</code>
<code>no_warning</code>	<code>CONSTANT INTEGER</code>	<code>:= 0;</code>

Exceptions

Table 45–47 *LOADCLOBFROMFILE Procedure Exceptions*

Exception	Description
VALUE_ERROR	Any of the input parameters are NULL or INVALID.
INVALID_ARGVAL	Either: <ul style="list-style-type: none">- src_offset or dest_offset < 1.- src_offset or dest_offset > LOBMAXSIZE.- amount < 1.- amount > LOBMAXSIZE.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

OPEN Procedure

This procedure opens a LOB, internal or external, in the indicated mode. Valid modes include read-only, and read/write.

Syntax

```
DBMS_LOB.OPEN (
  lob_loc  IN OUT NOCOPY BLOB,
  open_mode IN          BINARY_INTEGER);

DBMS_LOB.OPEN (
  lob_loc  IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
  open_mode IN          BINARY_INTEGER);

DBMS_LOB.OPEN (
  file_loc IN OUT NOCOPY BFILE,
  open_mode IN          BINARY_INTEGER := file_readonly);
```

Parameters

Table 45–48 OPEN Procedure Parameters

Parameter	Description
lob_loc	LOB locator. For more information, see Operational Notes .
open_mode	Mode in which to open. For BLOB and CLOB types, the mode can be either: <code>lob_readonly</code> or <code>lob_readwrite</code> . For BFILE types, the mode must be <code>file_readonly</code> .

Usage Notes

Note: If the LOB was opened in read-only mode, and if you try to write to the LOB, then an error is returned. BFILE can only be opened with read-only mode.

OPEN requires a round-trip to the server for both internal and external LOBs. For internal LOBs, OPEN triggers other code that relies on the OPEN call. For external

LOBs (BFILEs), OPEN requires a round-trip because the actual operating system file on the server side is being opened.

It is not mandatory that you wrap all LOB operations inside the Open/Close APIs. However, if you open a LOB, you must close it before you commit or rollback the transaction; an error is produced if you do not. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

It is an error to commit the transaction before closing all opened LOBs that were opened by the transaction. When the error is returned, the openness of the open LOBs is discarded, but the transaction is successfully committed. Hence, all the changes made to the LOB and nonLOB data in the transaction are committed, but the domain and function-based indexes are not updated. If this happens, you should rebuild the functional and domain indexes on the LOB column.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

READ Procedure

This procedure reads a piece of a LOB, and returns the specified amount into the `buffer` parameter, starting from an absolute offset from the beginning of the LOB.

The number of bytes or characters actually read is returned in the `amount` parameter. If the input `offset` points past the End of LOB, then `amount` is set to 0, and a `NO_DATA_FOUND` exception is raised.

Syntax

```
DBMS_LOB.READ (
  lob_loc   IN           BLOB,
  amount    IN OUT NOCOPY BINARY_INTEGER,
  offset     IN           INTEGER,
  buffer     OUT          RAW);

DBMS_LOB.READ (
  lob_loc   IN           CLOB CHARACTER SET ANY_CS,
  amount    IN OUT NOCOPY BINARY_INTEGER,
  offset     IN           INTEGER,
  buffer     OUT          VARCHAR2 CHARACTER SET lob_loc%CHARSET);

DBMS_LOB.READ (
  file_loc  IN           BFILE,
  amount    IN OUT NOCOPY BINARY_INTEGER,
  offset     IN           INTEGER,
  buffer     OUT          RAW);
```

Parameters

Table 45–49 READ Procedure Parameters

Parameter	Description
<code>lob_loc</code>	Locator for the LOB to be read. For more information, see Operational Notes .
<code>file_loc</code>	The file locator for the LOB to be examined.
<code>amount</code>	Number of bytes (for BLOBs) or characters (for CLOBs) to read, or number that were read.
<code>offset</code>	Offset in bytes (for BLOBs) or characters (for CLOBs) from the start of the LOB (origin: 1).

Table 45–49 READ Procedure Parameters

Parameter	Description
<code>buffer</code>	Output buffer for the read operation.

Exceptions

[Table 45–50](#) lists exceptions that apply to any LOB instance. [Table 45–51](#) lists exceptions that apply only to BFILEs.

Table 45–50 READ Procedure Exceptions

Exception	Description
<code>VALUE_ERROR</code>	Any of <code>lob_loc</code> , <code>amount</code> , or <code>offset</code> parameters are NULL.
<code>INVALID_ARGVAL</code>	Either: <ul style="list-style-type: none"> - <code>amount < 1</code> - <code>amount > MAXBUFSIZE</code> - <code>offset < 1</code> - <code>offset > LOBMAXSIZE</code> - <code>amount</code> is greater, in bytes or characters, than the capacity of <code>buffer</code>.
<code>NO_DATA_FOUND</code>	End of the LOB is reached, and there are no more bytes or characters to read from the LOB: <code>amount</code> has a value of 0.

Table 45–51 READ Procedure Exceptions for BFILEs

Exception	Description
<code>UNOPENED_FILE</code>	File is not opened using the input locator.
<code>NOEXIST_DIRECTORY</code>	Directory does not exist.
<code>NOPRIV_DIRECTORY</code>	You do not have privileges for the directory.
<code>INVALID_DIRECTORY</code>	Directory has been invalidated after the file was opened.
<code>INVALID_OPERATION</code>	File does not exist, or you do not have access privileges on the file.

Usage Notes

The form of the `VARCHAR2` buffer must match the form of the `CLOB` parameter. In other words, if the input `LOB` parameter is of type `NCLOB`, then the buffer must contain `NCHAR` data. Conversely, if the input `LOB` parameter is of type `CLOB`, then the buffer must contain `CHAR` data.

When calling `DBMS_LOB.READ` from the client (for example, in a `BEGIN/END` block from within `SQL*Plus`), the returned buffer contains data in the client's character set. The database converts the `LOB` value from the server's character set to the client's character set before it returns the buffer to the user.

See Also: *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

SUBSTR Function

This function returns `amount` bytes or characters of a LOB, starting from an absolute `offset` from the beginning of the LOB.

For fixed-width `n`-byte CLOBs, if the input `amount` for SUBSTR is greater than $(32767/n)$, then SUBSTR returns a character buffer of length $(32767/n)$, or the length of the CLOB, whichever is lesser. For CLOBs in a varying-width character set, `n` is the maximum byte-width used for characters in the CLOB.

Syntax

```
DBMS_LOB.SUBSTR (  
  lob_loc      IN      BLOB,  
  amount       IN      INTEGER := 32767,  
  offset       IN      INTEGER := 1)  
RETURN RAW;  
  
DBMS_LOB.SUBSTR (  
  lob_loc      IN      CLOB CHARACTER SET ANY_CS,  
  amount       IN      INTEGER := 32767,  
  offset       IN      INTEGER := 1)  
RETURN VARCHAR2 CHARACTER SET lob_loc%CHARSET;  
  
DBMS_LOB.SUBSTR (  
  file_loc     IN      BFILE,  
  amount       IN      INTEGER := 32767,  
  offset       IN      INTEGER := 1)  
RETURN RAW;
```

Pragmas

```
pragma restrict_references(SUBSTR, WNDS, WNPS, RNDS, RNPS);
```

Parameters

Table 45–52 SUBSTR Function Parameters

Parameter	Description
<code>lob_loc</code>	Locator for the LOB to be read. For more information, see Operational Notes .
<code>file_loc</code>	The file locator for the LOB to be examined.

Table 45–52 SUBSTR Function Parameters

Parameter	Description
amount	Number of bytes (for BLOBs) or characters (for CLOBs) to be read.
offset	Offset in bytes (for BLOBs) or characters (for CLOBs) from the start of the LOB (origin: 1).

Return Values

Table 45–53 SUBSTR Function Return Values

Return	Description
RAW	Function overloading that has a BLOB or BFILE in parameter.
VARCHAR2	CLOB version.
NULL	Either: <ul style="list-style-type: none"> - any input parameter is NULL - amount < 1 - amount > 32767 - offset < 1 - offset > LOBMAXSIZE

Exceptions

Table 45–54 SUBSTR Function Exceptions for BFILE operations

Exception	Description
UNOPENED_FILE	File is not opened using the input locator.
NOEXIST_DIRECTORY	Directory does not exist.
NOPRIV_DIRECTORY	You do not have privileges for the directory.
INVALID_DIRECTORY	Directory has been invalidated after the file was opened.
INVALID_OPERATION	File does not exist, or you do not have access privileges on the file.

Usage Notes

The form of the `VARCHAR2` buffer must match the form of the `CLOB` parameter. In other words, if the input `LOB` parameter is of type `NCLOB`, then the buffer must contain `NCHAR` data. Conversely, if the input `LOB` parameter is of type `CLOB`, then the buffer must contain `CHAR` data.

When calling `DBMS_LOB.SUBSTR` from the client (for example, in a `BEGIN/END` block from within `SQL*Plus`), the returned buffer contains data in the client's character set. The database converts the `LOB` value from the server's character set to the client's character set before it returns the buffer to the user.

See Also:

- ["INSTR Function"](#) on page 45-53
- ["READ Procedure"](#) on page 45-71
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

TRIM Procedure

This procedure trims the value of the internal LOB to the length you specify in the `newlen` parameter. Specify the length in bytes for BLOBs, and specify the length in characters for CLOBs.

Note: The TRIM procedure decreases the length of the LOB to the value specified in the `newlen` parameter.

If you attempt to TRIM an empty LOB, then nothing occurs, and TRIM returns no error. If the new length that you specify in `newlen` is greater than the size of the LOB, then an exception is raised.

Syntax

```
DBMS_LOB.TRIM (
  lob_loc      IN OUT NOCOPY BLOB,
  newlen       IN          INTEGER);

DBMS_LOB.TRIM (
  lob_loc      IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
  newlen       IN          INTEGER);
```

Parameters

Table 45–55 TRIM Procedure Parameters

Parameter	Description
<code>lob_loc</code>	Locator for the internal LOB whose length is to be trimmed. For more information, see Operational Notes .
<code>newlen</code>	New, trimmed length of the LOB value in bytes for BLOBs or characters for CLOBs.

Exceptions

Table 45–56 *TRIM Procedure Exceptions*

Exception	Description
VALUE_ERROR	lob_loc is NULL.
INVALID_ARGVAL	Either: - new_len < 0 - new_len > LOBMAXSIZE

Usage Notes

It is not mandatory that you wrap the LOB operation inside the Open/Close APIs. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the Open/Close API, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the OPEN or CLOSE statement.

See Also:

- ["ERASE Procedure"](#) on page 45-35
- ["WRITEAPPEND Procedure"](#) on page 45-82
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

WRITE Procedure

This procedure writes a specified amount of data into an internal LOB, starting from an absolute offset from the beginning of the LOB. The data is written from the `buffer` parameter.

WRITE replaces (overwrites) any data that already exists in the LOB at the offset, for the length you specify.

Syntax

```
DBMS_LOB.WRITE (
  lob_loc  IN OUT NOCOPY BLOB,
  amount   IN              BINARY_INTEGER,
  offset   IN              INTEGER,
  buffer   IN              RAW);

DBMS_LOB.WRITE (
  lob_loc  IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
  amount   IN              BINARY_INTEGER,
  offset   IN              INTEGER,
  buffer   IN              VARCHAR2 CHARACTER SET lob_loc%CHARSET);
```

Parameters

Table 45-57 *WRITE Procedure Parameters*

Parameter	Description
<code>lob_loc</code>	Locator for the internal LOB to be written to. For more information, see Operational Notes .
<code>amount</code>	Number of bytes (for BLOBs) or characters (for CLOBs) to write, or number that were written.
<code>offset</code>	Offset in bytes (for BLOBs) or characters (for CLOBs) from the start of the LOB (origin: 1) for the write operation.
<code>buffer</code>	Input buffer for the write.

Exceptions

Table 45–58 *WRITE Procedure Exceptions*

Exception	Description
VALUE_ERROR	Any of <code>lob_loc</code> , <code>amount</code> , or <code>offset</code> parameters are <code>NULL</code> , out of range, or <code>INVALID</code> .
INVALID_ARGVAL	Either: <ul style="list-style-type: none"> - <code>amount < 1</code> - <code>amount > MAXBUFSIZE</code> - <code>offset < 1</code> - <code>offset > LOBMAXSIZE</code>

Usage Notes

There is an error if the input amount is more than the data in the buffer. If the input amount is less than the data in the buffer, then only amount bytes or characters from the buffer is written to the LOB. If the offset you specify is beyond the end of the data currently in the LOB, then zero-byte fillers or spaces are inserted in the BLOB or CLOB respectively.

The form of the `VARCHAR2` buffer must match the form of the `CLOB` parameter. In other words, if the input LOB parameter is of type `NCLOB`, then the buffer must contain `NCHAR` data. Conversely, if the input LOB parameter is of type `CLOB`, then the buffer must contain `CHAR` data.

When calling `DBMS_LOB.WRITE` from the client (for example, in a `BEGIN/END` block from within `SQL*Plus`), the buffer must contain data in the client's character set. The database converts the client-side buffer to the server's character set before it writes the buffer data to the LOB.

It is not mandatory that you wrap the LOB operation inside the `Open/Close` APIs. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the `Open/Close` API, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the `OPEN` or `CLOSE` statement.

See Also:

- ["APPEND Procedure"](#) on page 45-17
- ["COPY Procedure"](#) on page 45-32
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

WRITEAPPEND Procedure

This procedure writes a specified amount of data to the end of an internal LOB. The data is written from the `buffer` parameter.

Syntax

```
DBMS_LOB.WRITEAPPEND (
    lob_loc IN OUT NOCOPY BLOB,
    amount IN          BINARY_INTEGER,
    buffer IN          RAW);

DBMS_LOB.WRITEAPPEND (
    lob_loc IN OUT NOCOPY CLOB CHARACTER SET ANY_CS,
    amount IN          BINARY_INTEGER,
    buffer IN          VARCHAR2 CHARACTER SET lob_loc%CHARSET);
```

Parameters

Table 45–59 *WRITEAPPEND Procedure Parameters*

Parameter	Description
<code>lob_loc</code>	Locator for the internal LOB to be written to. For more information, see Operational Notes .
<code>amount</code>	Number of bytes (for BLOBs) or characters (for CLOBs) to write, or number that were written.
<code>buffer</code>	Input buffer for the write.

Usage Notes

There is an error if the input amount is more than the data in the buffer. If the input amount is less than the data in the buffer, then only amount bytes or characters from the buffer are written to the end of the LOB.

Exceptions

Table 45–60 *WRITEAPPEND Procedure Exceptions*

Exception	Description
<code>VALUE_ERROR</code>	Any of <code>lob_loc</code> , <code>amount</code> , or <code>offset</code> parameters are <code>NULL</code> , out of range, or <code>INVALID</code> .

Table 45–60 *WRITEAPPEND Procedure Exceptions*

Exception	Description
INVALID_ARGVAL	Either: - amount < 1 - amount > MAXBUFSIZE

Usage Notes

The form of the VARCHAR2 buffer must match the form of the CLOB parameter. In other words, if the input LOB parameter is of type NCLOB, then the buffer must contain NCHAR data. Conversely, if the input LOB parameter is of type CLOB, then the buffer must contain CHAR data.

When calling DBMS_LOB.WRITEAPPEND from the client (for example, in a BEGIN/END block from within SQL*Plus), the buffer must contain data in the client's character set. The database converts the client-side buffer to the server's character set before it writes the buffer data to the LOB.

It is not mandatory that you wrap the LOB operation inside the Open/Close APIs. If you did not open the LOB before performing the operation, the functional and domain indexes on the LOB column are updated during the call. However, if you opened the LOB before performing the operation, you must close it before you commit or rollback the transaction. When an internal LOB is closed, it updates the functional and domain indexes on the LOB column.

If you do not wrap the LOB operation inside the Open/Close API, the functional and domain indexes are updated each time you write to the LOB. This can adversely affect performance. Therefore, it is recommended that you enclose write operations to the LOB within the OPEN or CLOSE statement.

See Also:

- ["APPEND Procedure"](#) on page 45-17
- ["COPY Procedure"](#) on page 45-32
- ["WRITE Procedure"](#) on page 45-79
- *Oracle Database Application Developer's Guide - Large Objects* for additional details on usage of this procedure

The `DBMS_LOCK` package provides an interface to Oracle Lock Management services. You can request a lock of a specific mode, give it a unique name recognizable in another procedure in the same or another instance, change the lock mode, and release it.

See Also: For more information, and an example of how to use the `DBMS_LOCK` package, see *About User Locks in Oracle Database Application Developer's Guide - Fundamentals*

This chapter contains the following topics:

- [Using DBMS_LOCK](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Rules and Limits](#)
 - [Operational Notes](#)
- [Summary of DBMS_LOCK Subprograms](#)

Using DBMS_LOCK

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Rules and Limits](#)
- [Operational Notes](#)

Overview

Some uses of user locks:

- Providing exclusive access to a device, such as a terminal
- Providing application-level enforcement of read locks
- Detecting when a lock is released and cleanup after the application
- Synchronizing applications and enforcing sequential processing

Security Model

There might be operating system-specific limits on the maximum number of total locks available. This *must* be considered when using locks or making this package available to other users. Consider granting the `EXECUTE` privilege only to specific users or roles.

A better alternative would be to create a cover package limiting the number of locks used and grant `EXECUTE` privilege to specific users. An example of a cover package is documented in the `DBMS_LOCK.SQL` package specification file. The abbreviations for these locks as they appear in Enterprise Manager monitors are in parentheses.

Constants

Table 46–1 Constants - Names and Oracle Enterprise Manager Abbreviations

Constant	Name	Alternate Name(s)	Oracle Enterprise Manager Abbreviation
nl_mode (1)	Null		
ss_mode (2)	Sub Shared		ULRS
sx_mode (3)	Sub eXclusive	Row Exclusive Mode,	ULRX
s_mode (4)	Sub eXclusive	Row Exclusive Mode, Intended Exclusive	ULRSX
ssx_mode (5)	Shared	Share Row Exclusive Mode	
x_mode (6)	eXclusive		ULX

These are the various lock modes (nl -> "Null", ss -> "Sub Shared", sx -> "Sub eXclusive", s -> "Shared", ssx -> "Shared Sub eXclusive", x -> "eXclusive").

A sub-share lock can be used on an aggregate object to indicate that share locks are being acquired on subparts of the object. Similarly, a sub-exclusive lock can be used on an aggregate object to indicate that exclusive locks are being acquired on sub-parts of the object. A share-sub-exclusive lock indicates that the entire aggregate object has a share lock, but some of the sub-parts may additionally have exclusive locks.

Rules and Limits

When another process holds "held", an attempt to get "get" does the following:

Table 46–2 Lock Compatibility

HELD MODE	GET NL	GET SS	GET SX	GET S	GET SSX	GET X
NL	Success	Success	Success	Success	Success	Success
SS	Success	Success	Success	Success	Success	Fail

Table 46–2 Lock Compatibility

HELD MODE	GET NL	GET SS	GET SX	GET S	GET SSX	GET X
SX	Success	Success	Success	Fail	Fail	Fail
S	Success	Success	Fail	Success	Fail	Fail
SSX	Success	Success	Fail	Fail	Fail	Fail
X	Success	Fail	Fail	Fail	Fail	Fail

```
maxwait constant integer := 32767;
```

The constant `maxwait` waits forever.

Operational Notes

User locks never conflict with Oracle locks because they are identified with the prefix "UL". You can view these locks using the Enterprise Manager lock monitor screen or the appropriate fixed views. User locks are automatically released when a session terminates. The lock identifier is a number in the range of 0 to 1073741823.

Because a reserved user lock is the same as an Oracle lock, it has all the functionality of an Oracle lock, such as deadlock detection. Be certain that any user locks used in distributed transactions are released upon `COMMIT`, or an undetected deadlock may occur.

`DBMS_LOCK` is most efficient with a limit of a few hundred locks for each session. Oracle strongly recommends that you develop a standard convention for using these locks in order to avoid conflicts among procedures trying to use the same locks. For example, include your company name as part of your lock names.

Summary of DBMS_LOCK Subprograms

Table 46–3 DBMS_LOCK Package Subprograms

Subprogram	Description
ALLOCATE_UNIQUE Procedure on page 46-6	Allocates a unique lock ID to a named lock.
CONVERT Function on page 46-8	Converts a lock from one mode to another.
RELEASE Function on page 46-10	Releases a lock.
REQUEST Function on page 46-11	Requests a lock of a specific mode.
SLEEP Procedure on page 46-13	Puts a procedure to sleep for a specific time.

ALLOCATE_UNIQUE Procedure

This procedure allocates a unique lock identifier (in the range of 1073741824 to 1999999999) given a lock name. Lock identifiers are used to enable applications to coordinate their use of locks. This is provided because it may be easier for applications to coordinate their use of locks based on lock names rather than lock numbers.

Syntax

```
DBMS_LOCK.ALLOCATE_UNIQUE (
    lockname          IN VARCHAR2,
    lockhandle        OUT VARCHAR2,
    expiration_secs  IN  INTEGER  DEFAULT 864000);
```

Parameters

Table 46–4 *ALLOCATE_UNIQUE Procedure Parameters*

Parameter	Description
lockname	Name of the lock for which you want to generate a unique ID. Do not use lock names beginning with ORA\$; these are reserved for products supplied by Oracle.
lockhandle	Returns the handle to the lock ID generated by ALLOCATE_UNIQUE. You can use this handle in subsequent calls to REQUEST, CONVERT, and RELEASE. A handle is returned instead of the actual lock ID to reduce the chance that a programming error accidentally creates an incorrect, but valid, lock ID. This provides better isolation between different applications that are using this package. LOCKHANDLE can be up to VARCHAR2 (128). All sessions using a lock handle returned by ALLOCATE_UNIQUE with the same lock name are referring to the same lock. Therefore, do not pass lock handles from one session to another.

Table 46–4 *ALLOCATE_UNIQUE Procedure Parameters*

Parameter	Description
<code>expiration_secs</code>	<p>Number of seconds to wait after the last <code>ALLOCATE_UNIQUE</code> has been performed on a given lock, before permitting that lock to be deleted from the <code>DBMS_LOCK_ALLOCATED</code> table.</p> <p>The default waiting period is 10 days. You should not delete locks from this table. Subsequent calls to <code>ALLOCATE_UNIQUE</code> may delete expired locks to recover space.</p>

Usage Notes

If you choose to identify locks by name, you can use `ALLOCATE_UNIQUE` to generate a unique lock identification number for these named locks.

The first session to call `ALLOCATE_UNIQUE` with a new lock name causes a unique lock ID to be generated and stored in the `dbms_lock_allocated` table. Subsequent calls (usually by other sessions) return the lock ID previously generated.

A lock name is associated with the returned lock ID for at least `expiration_secs` (defaults to 10 days) past the last call to `ALLOCATE_UNIQUE` with the given lock name. After this time, the row in the `dbms_lock_allocated` table for this lock name may be deleted in order to recover space. `ALLOCATE_UNIQUE` performs a commit.

Note: Named user locks may be less efficient, because Oracle uses SQL to determine the lock associated with a given name.

Exceptions

ORA-20000, ORU-10003: Unable to find or insert lock <lockname> into catalog `dbms_lock_allocated`.

CONVERT Function

This function converts a lock from one mode to another. `CONVERT` is an overloaded function that accepts either a user-defined lock identifier, or the lock handle returned by the `ALLOCATE_UNIQUE` procedure.

Syntax

```
DBMS_LOCK.CONVERT(
    id          IN INTEGER ||
    lockhandle  IN VARCHAR2,
    lockmode   IN INTEGER,
    timeout     IN NUMBER DEFAULT MAXWAIT)
RETURN INTEGER;
```

Parameters

Table 46–5 *CONVERT Function Parameters*

Parameter	Description
<code>id</code> or <code>lockhandle</code>	User assigned lock identifier, from 0 to 1073741823, or the lock handle, returned by <code>ALLOCATE_UNIQUE</code> , of the lock mode you want to change.
<code>lockmode</code>	New mode that you want to assign to the given lock. For the available modes and their associated integer identifiers, see Constants on page 46-3.
<code>timeout</code>	Number of seconds to continue trying to change the lock mode. If the lock cannot be converted within this time period, then the call returns a value of 1 (timeout).

Return Values

Table 46–6 *CONVERT Function Return Values*

Return Value	Description
0	Success
1	Timeout
2	Deadlock

Table 46-6 *CONVERT Function Return Values*

Return Value	Description
3	Parameter error
4	Don't own lock specified by <code>id</code> or <code>lockhandle</code>
5	Illegal lock handle

RELEASE Function

This function explicitly releases a lock previously acquired using the `REQUEST` function. Locks are automatically released at the end of a session. `RELEASE` is an overloaded function that accepts either a user-defined lock identifier, or the lock handle returned by the `ALLOCATE_UNIQUE` procedure.

Syntax

```
DBMS_LOCK.RELEASE (  
    id          IN INTEGER)  
RETURN INTEGER;
```

```
DBMS_LOCK.RELEASE (  
    lockhandle IN VARCHAR2)  
RETURN INTEGER;
```

Parameters

Table 46–7 *RELEASE Function Parameter*

Parameter	Description
<code>id</code> or <code>lockhandle</code>	User assigned lock identifier, from 0 to 1073741823, or the lock handle, returned by <code>ALLOCATE_UNIQUE</code> , of the lock mode you want to change.

Return Values

Table 46–8 *RELEASE Function Return Values*

Return Value	Description
0	Success
3	Parameter error
4	Do not own lock specified by <code>id</code> or <code>lockhandle</code>
5	Illegal lock handle

REQUEST Function

This function requests a lock with a given mode. `REQUEST` is an overloaded function that accepts either a user-defined lock identifier, or the lock handle returned by the `ALLOCATE_UNIQUE` procedure.

Syntax

```
DBMS_LOCK.REQUEST(
  id                IN  INTEGER ||
  lockhandle        IN  VARCHAR2,
  lockmode          IN  INTEGER DEFAULT X_MODE,
  timeout           IN  INTEGER DEFAULT MAXWAIT,
  release_on_commit IN  BOOLEAN DEFAULT FALSE)
RETURN INTEGER;
```

The current default values, such as `X_MODE` and `MAXWAIT`, are defined in the `DBMS_LOCK` package specification.

Parameters

Table 46–9 *REQUEST Function Parameters*

Parameter	Description
id or lockhandle	User assigned lock identifier, from 0 to 1073741823, or the lock handle, returned by <code>ALLOCATE_UNIQUE</code> , of the lock mode you want to change.
lockmode	Mode that you are requesting for the lock. For the available modes and their associated integer identifiers, see Constants on page 46-3.
timeout	Number of seconds to continue trying to grant the lock. If the lock cannot be granted within this time period, then the call returns a value of 1 (timeout).
release_on_commit	Set this parameter to <code>TRUE</code> to release the lock on commit or roll-back. Otherwise, the lock is held until it is explicitly released or until the end of the session.

Return Values

Table 46–10 *REQUEST Function Return Values*

Return Value	Description
0	Success
1	Timeout
2	Deadlock
3	Parameter error
4	Already own lock specified by <code>id</code> or <code>lockhandle</code>
5	Illegal lock handle

SLEEP Procedure

This procedure suspends the session for a given period of time.

Syntax

```
DBMS_LOCK.SLEEP (  
    seconds IN NUMBER);
```

Parameters

Table 46–11 *SLEEP Procedure Parameters*

Parameter	Description
seconds	Amount of time, in seconds, to suspend the session. The smallest increment can be entered in hundredths of a second; for example, 1.95 is a legal time value.

DBMS_LOGMNR

The `DBMS_LOGMNR` package contains procedures used to initialize the LogMiner tool and to begin and end a LogMiner session.

See Also: *Oracle Database Utilities* for information about using LogMiner and [DBMS_LOGMNR_D](#) for information on the package subprograms that extract a LogMiner dictionary and re-create LogMiner tables in alternate tablespaces

This chapter contains the following topics:

- [Using DBMS_LOGMNR](#)
 - [Security Model](#)
 - [Constants](#)
 - [Operational Notes](#)
- [Summary of DBMS_LOGMNR Subprograms](#)

Using DBMS_LOGMNR

- [Security Model](#)
- [Constants](#)
- [Operational Notes](#)

Security Model

You must have the role, EXECUTE_CATALOG_ROLE to use the DBMS_LOGMNR package.

Constants

[Table 47-1](#) describes the constants for the ADD_LOGFILE options flag in the DBMS_LOGMNR package.

Table 47-1 Constants for ADD_LOGFILE Options Flag

Constant	Description
NEW	Implicitly calls the DBMS_LOGMNR.END_LOGMNR procedure to end the current LogMiner session and then creates a new session. The new session starts a new list of redo log files to be analyzed, beginning with the redo log file you specify.
ADDFILE	Adds the specified redo log file to the list of redo log files to be analyzed. Any attempt to add a duplicate file raises an exception (ORA-01289). This is the default if no options flag is specified.

Table 47-2 describes the constants for the `START_LOGMNR` options flag in the `DBMS_LOGMNR` package.

Table 47-2 Constants for `START_LOGMNR` Options Flag

Constant	Description
<code>COMMITTED_DATA_ONLY</code>	<p>If set, DML statements corresponding to committed transactions are returned. DML statements corresponding to a committed transaction are grouped together. Transactions are returned in their commit order. Transactions that are rolled back or in-progress are filtered out, as are internal redo records (those related to index operations, management, and so on).</p> <p>If this option is not set, all rows for all transactions (committed, rolled back, and in-progress) are returned in the order in which they are found in the redo logs (in order of SCN values).</p>
<code>SKIP_CORRUPTION</code>	<p>Directs a select operation on the <code>V\$logmnr_contents</code> view to skip any corruptions in the redo log file being analyzed and continue processing. This option works only when a block in the redo log file (and not the header of the redo log file) is corrupt. You should check the <code>INFO</code> column in the <code>V\$logmnr_contents</code> view to determine the corrupt blocks skipped by LogMiner. When a corruption in the redo log file is skipped, the <code>OPERATION</code> column contains the value <code>CORRUPTED_BLOCKS</code>, and the <code>STATUS</code> column contains the value <code>1343</code>.</p>
<code>DDL_DICT_TRACKING</code>	<p>If the LogMiner dictionary in use is a flat file or in the redo log files, LogMiner updates its internal dictionary if a DDL event occurs. This ensures that correct <code>SQL_REDO</code> and <code>SQL_UNDO</code> information is maintained for objects that are modified after the LogMiner internal dictionary is built. The database to which LogMiner is connected must be open.</p> <p>This option cannot be used in conjunction with the <code>DICTIONARY_FROM_ONLINE_CATALOG</code> option and cannot be used when the LogMiner dictionary being used is one that was extracted to a flat file prior to Oracle9i.</p>

Table 47-2 (Cont.) Constants for START_LOGMNR Options Flag

Constant	Description
DICT_FROM_ONLINE_CATALOG	<p>Directs LogMiner to use the current online database dictionary rather than a LogMiner dictionary contained in a flat file or in the redo log files being analyzed.</p> <p>This option cannot be used in conjunction with the DDL_DICT_TRACKING option. The database to which LogMiner is connected must be the same one that generated the redo log files.</p> <p>Expect to see a value of 2 in the STATUS column of the V\$LOGMNR_CONTENTS view if the table definition in the database does not match the table definition in the redo log file.</p>
DICT_FROM_REDO_LOGS	<p>If set, LogMiner expects to find a LogMiner dictionary in the redo log files that were specified. The redo log files are specified with the DBMS_LOGMNR.ADD_LOGFILE procedure or with the DBMS_LOGMNR.START_LOGMNR procedure with the CONTINUOUS_MINE option.</p>
NO_SQL_DELIMITER	<p>If set, the SQL delimiter (a semicolon) is not placed at the end of reconstructed SQL statements. This is helpful for applications that open a cursor and then execute the reconstructed statements.</p>
NO_ROWID_IN_STMT	<p>If set, the ROWID clause is not included in the reconstructed SQL statements. The redo log file may already contain logically unique identifiers for modified rows if supplemental logging is enabled.</p> <p>When using this option, you must be sure that supplemental logging was enabled in the source database at the appropriate level and that no duplicate rows exist in the tables of interest. LogMiner does not make any guarantee regarding the uniqueness of logical row identifiers.</p>
PRINT_PRETTY_SQL	<p>If set, LogMiner formats the reconstructed SQL statements for ease of reading. These reconstructed SQL statements are not executable.</p>
CONTINUOUS_MINE	<p>Directs LogMiner to automatically add redo log files, as needed, to find the data of interest. You only need to specify the first log to start mining, or just the starting SCN or date to indicate to LogMiner where to begin mining logs. You are not required to specify any redo log files explicitly. LogMiner automatically adds and mines the (archived and online) redo log files for the data of interest. This option requires that LogMiner is connected to the same database instance that is generating the redo log files.</p>

Operational Notes

A **LogMiner session** begins with a call to `DBMS_LOGMNR.ADD_LOGFILE` or `DBMS_LOGMNR.START_LOGMNR` (the former if you plan to specify log files explicitly; the latter if you plan to use continuous mining). The session ends with a call to `DBMS_LOGMNR.END_LOGMNR`. Within a LogMiner session, you can specify the redo log files to be analyzed and the SCN or time range of interest; then you can issue SQL `SELECT` statements against the `V$LOGMNR_CONTENTS` view to retrieve the data of interest.

Summary of DBMS_LOGMNR Subprograms

Table 47-3 DBMS_LOGMNR Package Subprograms

Subprogram	Description
ADD_LOGFILE Procedure on page 47-7	Adds a redo log file to the existing or newly created list of redo log files for LogMiner to process, so that if a new list is created, this marks the beginning of a LogMiner session
COLUMN_PRESENT Function on page 47-9	You can call this function for any row returned from the V\$logmnr_contents view to determine if undo or redo column values exist for the column specified by the column_name input parameter to this function
END_LOGMNR Procedure on page 47-11	Finishes a LogMiner session
MINE_VALUE Function on page 47-12	You can call this function for any row returned from the V\$logmnr_contents view to retrieve the undo or redo column value of the column specified by the column_name input parameter to this function
REMOVE_LOGFILE Procedure on page 47-14	Removes a redo log file from the list of redo log files for LogMiner to process
START_LOGMNR Procedure on page 47-16	Initializes the LogMiner utility and starts LogMiner (unless the session was already started with a call to DBMS_LOGMNR.ADD_LOGFILE)

ADD_LOGFILE Procedure

This procedure adds a file to an existing or newly created list of log files for LogMiner to process.

Syntax

```
DBMS_LOGMNR.ADD_LOGFILE(
  LogFileName      IN VARCHAR2,
  options          IN BINARY_INTEGER default ADDFILE );
```

Parameters

Table 47–4 ADD_LOGFILE Procedure Parameters

Parameter	Description
LogFileName	Specifies the name of the redo log file to add to the list of redo log files to be analyzed during this session.
options	Does one of the following: <ul style="list-style-type: none"> ■ Starts a new LogMiner session and a new list of redo log files for analysis (DBMS_LOGMNR.NEW) ■ Adds a file to an existing list of redo log files for analysis (DBMS_LOGMNR.ADDFILE) See Table 47–1, "Constants for ADD_LOGFILE Options Flag" .

Usage Notes

- Before querying the V\$LOGMNR_CONTENTS view, you must make a successful call to the DBMS_LOGMNR.START_LOGMNR procedure (within the current LogMiner session).
- Unless you specify the CONTINUOUS_MINE option, the LogMiner session must be set up with a list of redo log files to be analyzed. Use the ADD_LOGFILE procedure to specify the list of redo log files to analyze.
- If you are not using the CONTINUOUS_MINE option and you want to analyze more than one redo log file, you must call the ADD_LOGFILE procedure separately for each redo log file. The redo log files do not need to be registered in any particular order.
- Both archived and online redo log files can be mined.

- After you have added the first redo log file to the list, each additional redo log file that you add to the list must be associated with the same database and database `RESETLOGS SCN` as the first redo log file. (The database `RESETLOGS SCN` uniquely identifies each execution of an `ALTER DATABASE OPEN RESETLOGS` statement. When the online redo logs are reset, Oracle creates a new and unique incarnation of the database.)
- To analyze the redo log files from a different database (or a database incarnation with a different database `RESETLOGS SCN`) than that with which the current list of redo log files is associated, use the `END_LOGMNR` procedure to end the current LogMiner session, and then build a new list using the `ADD_LOGFILE` procedure.
- LogMiner matches redo log files by the log sequence number. Thus, two redo log files with different names but with the same log sequence number will return the `ORA-01289` exception. For instance, the online counterpart of an archived redo log file has a different name from the archived redo log file, but attempting to register it with LogMiner after registering the archived counterpart will result in the `ORA-01289` exception being returned.

Exceptions

- `ORA-01284`: file <filename> cannot be opened.
- `ORA-01287`: file <filename> is from a different database incarnation.
- `ORA-01289`: cannot add duplicate log file <filename>.
- `ORA-01290`: cannot remove unlisted log file <filename>.
- `ORA-01324`: cannot add file <filename> due to `DB_ID` mismatch.

COLUMN_PRESENT Function

This function is designed to be used in conjunction with the `MINE_VALUE` function.

If the `MINE_VALUE` function returns a `NULL` value, it can mean either:

- The specified column is not present in the redo or undo portion of the data.
- The specified column is present and has a `NULL` value.

To distinguish between these two cases, use the `COLUMN_PRESENT` function, which returns a 1 if the column is present in the redo or undo portion of the data. Otherwise, it returns a 0.

Syntax

```
DBMS_LOGMNR.COLUMN_PRESENT(
    sql_redo_undo      IN RAW,
    column_name        IN VARCHAR2 default '') RETURN NUMBER;
```

Parameters

Table 47–5 *COLUMN_PRESENT Function Parameters*

Parameter	Description
<code>sql_redo_undo</code>	Specifies either the <code>REDO_VALUE</code> or the <code>UNDO_VALUE</code> column in the <code>V\$LOGMNR_CONTENTS</code> view from which to extract data values. See the Usage Notes for more information.
<code>column_name</code>	Specifies the fully qualified name (<code>schema.table.column</code>) of the column for which this function will return information.

Return Values

[Table 47–6](#) describes the return values for the `COLUMN_PRESENT` function. The `COLUMN_PRESENT` function returns 1 if the self-describing record (the first parameter) contains the column specified in the second parameter. This can be used to determine the meaning of `NULL` values returned by the `DBMS_LOGMNR.MINE_VALUE` function.

Table 47–6 *Return Values for COLUMN_PRESENT Function*

Return	Description
0	Specified column is not present in this row of <code>V\$LOGMNR_CONTENTS</code> .

Table 47–6 (Cont.) Return Values for COLUMN_PRESENT Function

Return	Description
1	Column is present in this row of V\$LOGMNR_CONTENTS.

Usage Notes

- To use the COLUMN_PRESENT function, you must have successfully started LogMiner.
- The COLUMN_PRESENT function must be invoked in the context of a select operation on the V\$LOGMNR_CONTENTS view.
- The COLUMN_PRESENT function does not support LONG, LOB, ADT, or COLLECTION datatypes.
- The value for the sql_redo_undo parameter depends on the operation performed and the data of interest:
 - If an update operation was performed and you want to know what the value was prior to the update operation, specify UNDO_VALUE.
 - If an update operation was performed and you want to know what the value is after the update operation, specify REDO_VALUE.
 - If an insert operation was performed, typically you would specify REDO_VALUE (because the value of a column prior to an insert operation will always be null).
 - If a delete operation was performed, typically you would specify UNDO_VALUE (because the value of a column after a delete operation will always be null).

Exceptions

- ORA-01323: invalid state.
Currently, a LogMiner dictionary is not associated with the LogMiner session. You must specify a LogMiner dictionary for the LogMiner session.
- ORA-00904: invalid identifier.
The value specified for the column_name parameter was not a fully qualified column name.

END_LOGMNR Procedure

This procedure finishes a LogMiner session. Because this procedure performs cleanup operations that may not otherwise be done, you must use it to properly end a LogMiner session. This procedure is called automatically when you log out of a database session or when you call `DBMS_LOGMNR.ADD_LOGFILE` and specify the `NEW` option.

Syntax

```
DBMS_LOGMNR.END_LOGMNR;
```

Exceptions

- **ORA-01307: No LogMiner session is currently active.**
The `END_LOGMNR` procedure was called without adding any log files or before the `START_LOGMNR` procedure was called.

MINE_VALUE Function

This function facilitates queries based on a column's data value. This function takes two arguments. The first one specifies whether to mine the redo (REDO_VALUE) or undo (UNDO_VALUE) portion of the data. The second argument is a string that specifies the fully qualified name of the column to be mined. The MINE_VALUE function always returns a string that can be converted back to the original datatype.

Syntax

```
DBMS_LOGMNR.MINE_VALUE(  
    sql_redo_undo      IN RAW,  
    column_name        IN VARCHAR2 default '' ) RETURN VARCHAR2;
```

Parameters

Table 47-7 MINE_VALUE Function Parameters

Parameter	Description
sql_redo_undo	Specifies either the REDO_VALUE or the UNDO_VALUE column in the V\$LOGMNR_CONTENTS view from which to extract data values. See the Usage Notes for more information.
column_name	Specifies the fully qualified name (schema.table.column) of the column for which this function will return information.

Return Values

Table 47-8 Return Values for MINE_VALUE Function

Return	Description
NULL	The column is not contained within the self-describing record, or the column value is NULL. To distinguish between the two different null possibilities, use the DBMS_LOGMNR.COLUMN_PRESENT function.
NON-NULL	The column is contained within the self-describing record; the value is returned in string format.

Usage Notes

- To use the MINE_VALUE function, you must have successfully started LogMiner.

- The `MINE_VALUE` function must be invoked in the context of a select operation from the `V$logmnr_contents` view.
- The `MINE_VALUE` function does not support `LONG`, `LOB`, `ADT`, or `COLLECTION` datatypes.
- The value for the `sql_redo_undo` parameter depends on the operation performed and the data of interest:
 - If an update operation was performed and you want to know what the value was prior to the update operation, specify `UNDO_VALUE`.
 - If an update operation was performed and you want to know what the value is after the update operation, specify `REDO_VALUE`.
 - If an insert operation was performed, typically you would specify `REDO_VALUE` (because the value of a column prior to an insert operation will always be null).
 - If a delete operation was performed, typically you would specify `UNDO_VALUE` (because the value of a column after a delete operation will always be null).

Exceptions

- **ORA-01323: invalid state.**
Currently, a LogMiner dictionary is not associated with the LogMiner session. You must specify a LogMiner dictionary for the LogMiner session.
- **ORA-00904: invalid identifier.**
The value specified for the `column_name` parameter was not a fully qualified column name.

REMOVE_LOGFILE Procedure

This procedure removes a redo log file from an existing list of redo log files for LogMiner to process.

Note: This procedure replaces the `REMOVEFILE` constant that was an option on the `ADD_LOGFILE` procedure prior to Oracle Database 10g.

Syntax

```
DBMS_LOGMNR.REMOVE_LOGFILE(
    LogFileName    IN VARCHAR2);
```

Parameters

Table 47–9 REMOVE_LOGFILE Procedure Parameters

Parameter	Description
LogFileName	Specifies the name of the redo log file to be removed from the list of redo log files to be analyzed during this session.

Usage Notes

- Before querying the `V$LOGMNR_CONTENTS` view, you must make a successful call to the `DBMS_LOGMNR.START_LOGMNR` procedure (within the current LogMiner session).
- You can use this procedure to remove a redo log file from the list of redo log files for LogMiner to process if you know that redo log file does not contain any data of interest.
- Multiple redo log files can be removed by calling this procedure repeatedly.
- The redo log files do not need to be removed in any particular order.
- To start a new list of redo log files for analysis, use the `END_LOGMNR` procedure to end the current LogMiner session, and then build a new list using the `ADD_LOGFILE` procedure.
- Even if you remove all redo log files from the list, any subsequent calls you make to the `ADD_LOGFILE` procedure must match the database ID and `RESETLOGS SCN` of the removed redo log files. Therefore, to analyze the redo

log files from a different database (or a database incarnation with a different database `RESETLOGS SCN`) than that with which the current list of redo log files is associated, use the `END_LOGMNR` procedure to end the current LogMiner session, and then build a new list using the `ADD_LOGFILE` procedure.

Exceptions

- `ORA-01290`: cannot remove unlisted log file <filename>.

START_LOGMNR Procedure

This procedure starts LogMiner by loading the dictionary that LogMiner will use to translate internal schema object identifiers to names.

Syntax

```
DBMS_LOGMNR.START_LOGMNR(
  startScn          IN NUMBER default 0,
  endScn            IN NUMBER default 0,
  startTime         IN DATE default '01-jan-1988',
  endTime          IN DATE default '31-dec-2110',
  DictFileName     IN VARCHAR2 default '',
  Options          IN BINARY_INTEGER default 0 );
```

Parameters

Table 47–10 START_LOGMNR Procedure Parameters

Parameter	Description
startScn	Directs LogMiner to return only redo records with an SCN greater than or equal to the <code>startScn</code> specified. This fails if there is no redo log file containing the specified <code>startScn</code> value. (You can query the <code>FILENAME</code> , <code>LOW_SCN</code> , and <code>NEXT_SCN</code> columns in the <code>V\$LOGMNR_LOGS</code> view for each redo log file to determine the range of SCN values contained in each redo log file.)
endScn	Directs LogMiner to return only redo records with an SCN less than or equal to the <code>endScn</code> specified. If you specify an <code>endScn</code> value that is beyond the value in any redo log file, then LogMiner will use the greatest <code>endScn</code> value in the redo log file that contains the most recent changes. (You can query the <code>FILENAME</code> , <code>LOW_SCN</code> , and <code>NEXT_SCN</code> columns in the <code>V\$LOGMNR_LOGS</code> view for each redo log file to determine the range of SCN values contained in each redo log file.)
startTime	Directs LogMiner to return only redo records with a timestamp greater than or equal to the <code>startTime</code> specified. This fails if there is no redo log file containing the specified <code>startTime</code> value. (You can query the <code>FILENAME</code> , <code>LOW_TIME</code> , and <code>HIGH_TIME</code> columns in the <code>V\$LOGMNR_LOGS</code> view for each redo log file to determine the range of time covered in each redo log file.) This parameter is ignored if <code>startScn</code> is specified. See the Usage Notes for additional information.

Table 47–10 (Cont.) START_LOGMNR Procedure Parameters

Parameter	Description
endTime	<p>Directs LogMiner to return only redo records with a timestamp less than or equal to the <code>endTime</code> specified. If you specify an <code>endTime</code> value that is beyond the value in any redo log file, then LogMiner will use the greatest <code>endTime</code> in the redo log file that contains the most recent changes. You can query the <code>FILENAME</code>, <code>LOW_TIME</code>, and <code>HIGH_TIME</code> columns in the <code>V\$LOGMNR_LOGS</code> view for each redo log file to determine the range of time covered in each redo log file.)</p> <p>This parameter is ignored if <code>endScn</code> is specified. See the Usage Notes for additional information.</p>
DictFileName	<p>Specifies the flat file that contains the LogMiner dictionary. It is used to reconstruct <code>SQL_REDO</code> and <code>SQL_UNDO</code> columns in <code>V\$LOGMNR_CONTENTS</code>, as well as to fully translate <code>SEG_NAME</code>, <code>SEG_OWNER</code>, <code>SEG_TYPE_NAME</code>, <code>TABLE_NAME</code>, and <code>TABLE_SPACE</code> columns. The fully qualified path name for the LogMiner dictionary file must be specified. (This file must have been created previously through the <code>DBMS_LOGMNR_D.BUILD</code> procedure.)</p> <p>You need to specify this parameter only if neither <code>DICT_FROM_REDO_LOGS</code> nor <code>DICT_FROM_ONLINE_CATALOG</code> is specified.</p>
options	See Table 47-2, "Constants for START_LOGMNR Options Flag" .

Usage Notes

- LogMiner can use a dictionary that you previously extracted to the redo log files or to a flat file, or you can specify that LogMiner use the online catalog if LogMiner is mining data from the source system. See *Oracle Database Utilities* and [Chapter 48](#) in this manual for more information about the LogMiner dictionary.
- After executing the `START_LOGMNR` procedure, you can query the following views:
 - `V$LOGMNR_CONTENTS` - contains history of information in redo log files
 - `V$LOGMNR_DICTIONARY` - contains current information about the LogMiner dictionary file extracted to a flat file
 - `V$LOGMNR_PARAMETERS` - contains information about the LogMiner session

(You can query the `V$LOGMNR_LOGS` view after a redo log file list has been added to the list of files that LogMiner is to mine.)

- Parameters and options are not persistent across calls to `DBMS_LOGMNR.START_LOGMNR`. You must specify all desired parameters and options (including SCN and time ranges) each time you call `DBMS_LOGMNR.START_LOGMNR`.
- Be aware that specifying redo log files using a timestamp is not precise.
- The `CONTINUOUS_MINE` option directs LogMiner to automatically add redo log files, as needed, to find the data of interest. You need to specify only the first log to start mining, or just the starting SCN or date to indicate to LogMiner where to begin mining logs. Keep the following in mind when using the `CONTINUOUS_MINE` option:
 - The database control file will hold information about a limited number of archived redo log files, although the number of entries can be quite large. Query the `V$ARCHIVED_LOGS` view to determine which redo log file entries will be found by LogMiner.

Even if an entry is listed in the database control file (and the `V$ARCHIVED_LOGS` view), the archived redo log file may not be accessible by LogMiner for various reasons. For example, the archived redo log file may have been deleted or moved from its location (maybe because of a backup operation to tape), or the directory where it resides may not be available.
 - If you specify the `CONTINUOUS_MINE` option and an ending time or SCN that will occur in the future (or you do not specify an end time or SCN), a query of the `V$LOGMNR_CONTENTS` view will not finish until the database has generated redo log files beyond the specified time or SCN. In this scenario, LogMiner will automatically add archived redo log files to the LogMiner redo log file list as they are generated. In addition, in this scenario only, LogMiner may automatically remove redo log files from the list to keep it at 50 processed redo files. This is to save PGA memory as LogMiner automatically adds redo log files to the list. If LogMiner did not perform automated removal, memory could eventually be exhausted.
 - LogMiner can mine online redo logs. However, if the `CONTINUOUS_MINE` option is not specified, it is possible that the database is writing to the online redo log file at the same time that LogMiner is reading the online redo log file. If a log switch occurs while LogMiner is reading an online redo log file, the database will overwrite what LogMiner is attempting to read. The data that LogMiner returns if the file it is trying to read gets overwritten by the database is unpredictable.
- Keep the following in mind regarding starting and ending times or SCN ranges:

- If you specify neither a `startTime` nor a `startScn` parameter, LogMiner will set the `startScn` parameter to use the lowest SCN value from the redo log file that contains the oldest changes.
- If you specify both time and SCN values, LogMiner uses the SCN value or values and ignores the time values.
- If you specify starting and ending time or SCN values and they are found in the LogMiner redo log file list, then LogMiner mines the logs indicated by those values.
- If you specify starting and ending times or SCN values that are not in the LogMiner redo log file list, and you specify `DBMS_LOGMNR.START_LOGMNR` without the `CONTINUOUS_MINE` option, and you specify:
 - * 0 for the `startTime` or `startScn` value, then the lowest SCN in the LogMiner redo log file list will be used as the `startScn`
 - * A nonzero number for the `startTime` or `startScn` value, then an error is returned
 - * 0 or a nonzero number for the `endTime` or `endScn` value, then the highest SCN in the LogMiner redo log file list will be used as the `endScn`
- If you specify starting and ending times or SCN values and they are not found in the LogMiner redo log file list, and you specify `DBMS_LOGMNR.START_LOGMNR` with the `CONTINUOUS_MINE` option, and you specify:
 - * 0 for the `startTime` or `startScn` value, then an error is returned.
 - * A `startTime` or `startScn` value that is greater than any value in the database's archived redo log files, then LogMiner starts mining in the online redo log file. LogMiner will continue to process the online redo log file until it finds a change at, or beyond, the requested starting point before it returns rows from the `V$LOGMNR_CONTENTS` view.
 - * An `endTime` or `endScn` parameter value that indicates a time or SCN in the future, then LogMiner includes the online redo log files when it mines. When you query the `V$LOGMNR_CONTENTS` view, rows will be returned from this view as changes are made to the database, and will not stop until LogMiner sees a change beyond the requested ending point.
 - * 0 for the `endTime` or `endScn` parameter value, then LogMiner includes the online redo log files when it mines. When you query the

V\$LOGMNR_CONTENTS view, rows will be returned from this view as changes are made to the database, and will not stop until you enter CTL+C or you terminate the PL/SQL cursor.

Exceptions

- ORA-01280: fatal LogMiner error.
The procedure fails with this exception if LogMiner encounters an internal error.
- ORA-01281: SCN range specified is invalid.
The `startScn` or `endScn` parameter value is not a valid SCN, or `endScn` is less than `startScn`.
- ORA-01282: date range specified is invalid.
The value for the `startTime` parameter was greater than the value specified for the `endTime` parameter, or there was no redo log file that was compatible with the date range specified with the `startTime` and `endTime` parameters.
- ORA-01283: options parameter specified is invalid.
- ORA-01284: file <filename> cannot be opened.
The LogMiner dictionary file specified in the `DictFileName` parameter has a full path length greater than 256 characters, or the file cannot be opened.
- ORA-01285: error reading file <filename>.
- ORA-01291: missing log file.
Redo log files that are needed to satisfy the user's requested SCN or time range are missing.
- ORA-01292: no log file has been specified for the current LogMiner session.
- ORA-01293: mounted database required for specified LogMiner options.
- ORA-01294: error occurred while processing information in dictionary file <filename>, possible corruption.
- ORA-01295: DB_ID mismatch between dictionary <filename> and log files.
The specified LogMiner dictionary does not correspond to the database that produced the log files being analyzed.
- ORA-01296: character set mismatch between dictionary <filename> and log files.

- **ORA-01297: redo version mismatch between dictionary <filename> and log files.**
- **ORA-01299: dictionary <filename> corresponds to a different database incarnation.**
- **ORA-01300: writable database required for specified LogMiner options.**

DBMS_LOGMNR_D

The DBMS_LOGMNR_D package contains two procedures:

- The BUILD procedure extracts the LogMiner data dictionary to either the redo log files or to a flat file. This information is saved in preparation for future analysis of redo log files using the LogMiner tool.
- The SET_TABLESPACE procedure re-creates all LogMiner tables in an alternate tablespace.

See Also: *Oracle Database Utilities* for information about using LogMiner and [DBMS_LOGMNR](#) for information on the package subprograms used in running a LogMiner session.

This chapter contains the following topic:

- [Using DBMS_LOGMNR_D](#)
 - [Overview](#)
 - [Security Model](#)
- [Summary of DBMS_LOGMNR_D Subprograms](#)

Using DBMS_LOGMNR_D

- [Overview](#)
- [Security Model](#)

Overview

Note: The **LogMiner data dictionary** consists of the memory data structures and the database tables that are used to store and retrieve information about objects and their versions. It is referred to as the **LogMiner dictionary** throughout the LogMiner documentation.

Security Model

You must have the role, EXECUTE_CATALOG_ROLE to use the DBMS_LOGMNR_D package.

Summary of DBMS_LOGMNR_D Subprograms

Table 48-1 DBMS_LOGMNR_D Package Subprograms

Procedure	Description
BUILD Procedure on page 48-4	Extracts the LogMiner dictionary to either a flat file or one or more redo log files
SET_TABLESPACE Procedure on page 48-8	Re-creates all LogMiner tables in an alternate tablespace

BUILD Procedure

This procedure extracts the LogMiner data dictionary to either the redo log files or to a flat file.

Syntax

```
DBMS_LOGMNR_D.BUILD (
    dictionary_filename IN VARCHAR2,
    dictionary_location IN VARCHAR2,
    options IN NUMBER);
```

Parameters

[Table 48–2](#) describes the parameters for the `BUILD` procedure.

Table 48–2 *BUILD Procedure Parameters*

Parameter	Description
<code>dictionary_filename</code>	Specifies the name of the LogMiner dictionary file.
<code>dictionary_location</code>	Specifies the path to the LogMiner dictionary file directory.
<code>options</code>	Specifies that the LogMiner dictionary is written to either a flat file (<code>STORE_IN_FLAT_FILE</code>) or the redo log files (<code>STORE_IN_REDO_LOGS</code>).

To extract the LogMiner dictionary to a flat file, you must supply a filename and location.

To extract the LogMiner dictionary to the redo log files, specify only the `STORE_IN_REDO_LOGS` option. The size of the LogMiner dictionary may cause it to be contained in multiple redo log files.

The combinations of parameters used result in the following behavior:

- If you do not specify any parameters, an error is returned.
- If you specify a filename and location, without any options, the LogMiner dictionary is extracted to a flat file with that name.
- If you specify a filename and location, as well as the `STORE_IN_FLAT_FILE` option, the LogMiner dictionary is extracted to a flat file with the specified name.

- If you do not specify a filename and location, but do specify the `STORE_IN_REDO_LOGS` option, the LogMiner dictionary is extracted to the redo log files.
- If you specify a filename and location, as well as the `STORE_IN_REDO_LOGS` option, an error is returned.
- If you do not specify a filename and location, but do specify the `STORE_IN_FLAT_FILE` option, an error is returned.

Exceptions

- **ORA-01302: dictionary build options missing or incorrect.**

This error is returned under the following conditions:

- If the value of the `OPTIONS` parameter is not one of the supported values (`STORE_IN_REDO_LOGS`, `STORE_IN_FLAT_FILE`) or is not specified
- If the `STORE_IN_REDO_LOGS` option is not specified and neither the `dictionary_filename` nor the `dictionary_location` parameter is specified
- If the `STORE_IN_REDO_LOGS` option is specified and either the `dictionary_filename` or the `dictionary_location` parameter is specified

- **ORA-01308: initialization parameter `UTL_FILE_DIR` is not set.**
- **ORA-01336: specified dictionary file cannot be opened.**

This error is returned under the following conditions:

- The specified value for the `dictionary_location` does not exist.
- The `UTL_FILE_DIR` initialization parameter is not set to have access to the `dictionary_location`.
- The dictionary file is read-only.

Usage Notes

- Ideally, the LogMiner dictionary file will be created after all database dictionary changes have been made and prior to the creation of any redo log files that are to be analyzed. As of Oracle9i release 1 (9.0.1), you can use LogMiner to dump the LogMiner dictionary to the redo log files or a flat file, perform DDL operations, and dynamically apply the DDL changes to the LogMiner dictionary.

- Do not run the `DBMS_LOGMNR_D.BUILD` procedure if there are any ongoing DDL operations.
- The database must be open when you run the `DBMS_LOGMNR_D.BUILD` procedure.
- When extracting a LogMiner dictionary to a flat file, the procedure queries the dictionary tables of the current database and creates a text-based file containing the contents of the tables. To extract a LogMiner dictionary to a flat file, the following conditions must be met:
 - You must specify a directory for use by the PL/SQL procedure. To do so, set the initialization parameter `UTL_FILE_DIR` in the initialization parameter file. For example:

```
UTL_FILE_DIR = /oracle/dictionary
```

After setting the parameter, you must shut down and restart the database for this parameter to take effect. If you do not set this parameter, the procedure will fail.

- You must ensure that no DDL operations occur while the LogMiner dictionary build is running. Otherwise, the LogMiner dictionary file may not contain a consistent snapshot of the database dictionary.

Be aware that the `DDL_DICT_TRACKING` option to the `DBMS_LOGMNR.START_LOGMNR` procedure is not supported for flat file dictionaries created prior to Oracle9i. If you attempt to use the `DDL_DICT_TRACKING` option with a LogMiner database extracted to a flat file prior to Oracle9i, the ORA-01330 error (problem loading a required build table) is returned.

- To extract a LogMiner dictionary file to the redo log files, the following conditions must be met:
 - The `DBMS_LOGMNR_D.BUILD` procedure must be run on a system that is running Oracle9i or later.
 - Archive log mode must be enabled in order to generate usable redo log files.
 - The `COMPATIBLE` parameter in the initialization parameter file must be set to 9.2.0 or higher.
 - The database to which LogMiner is attached must be Oracle9i or later.

In addition, supplemental logging (at least the minimum level) should be enabled to ensure that you can take advantage of all the features that LogMiner

offers. See *Oracle Database Utilities* for information about using supplemental logging with LogMiner.

Examples

Example 1: Extracting the LogMiner Dictionary to a Flat File

The following example extracts the LogMiner dictionary file to a flat file named `dictionary.ora` in a specified path (`/oracle/database`).

```
SQL> EXECUTE dbms_logmnr_d.build('dictionary.ora', -  
    '/oracle/database/', -  
    options => dbms_logmnr_d.store_in_flat_file);
```

Example 2: Extracting the LogMiner Dictionary to the Redo Log Files

The following example extracts the LogMiner dictionary to the redo log files.

```
SQL> EXECUTE dbms_logmnr_d.build( -  
    options => dbms_logmnr_d.store_in_redo_logs);
```

SET_TABLESPACE Procedure

By default, all LogMiner tables are created to use the `SYSAUX` tablespace. However, it may be desirable to have LogMiner tables use an alternate tablespace. Use this procedure to move LogMiner tables to an alternate tablespace.

Syntax

```
DBMS_LOGMNR_D.SET_TABLESPACE(
    new_tablespace      IN VARCHAR2);
```

Parameters

Table 48–3 SET_TABLESPACE Parameter

Parameter	Description
<code>new_tablespace</code>	A string naming a preexisting tablespace. To move all LogMiner tables to employ this tablespace, supply this parameter.

Usage Notes

- Users upgrading from earlier versions of Oracle Database may find LogMiner tables in the `SYSTEM` tablespace. Oracle encourages such users to consider using the `SET_TABLESPACE` procedure to move the tables to the `SYSAUX` tablespace once they are confident that they will not be downgrading to an earlier version of Oracle Database.
- Users of this routine must supply an existing tablespace.

See Also: *Oracle Database Concepts* and *Oracle Database SQL Reference* for information about tablespaces and how to create them

Example: Using the DBMS_LOGMNR_D.SET_TABLESPACE Procedure

The following example shows the creation of an alternate tablespace and execution of the `DBMS_LOGMNR_D.SET_TABLESPACE` procedure.

```
SQL> CREATE TABLESPACE logmnrts$ datafile '/usr/oracle/dbs/logmnrts.f'
      SIZE 25 M REUSE AUTOEXTEND ON MAXSIZE UNLIMITED;
```

```
SQL> EXECUTE dbms_logmnr_d.set_tablespace('logmnrts$');
```

DBMS_LOGSTDBY

The DBMS_LOGSTDBY package provides procedures for configuring and managing the logical standby database environment.

See Also: *Oracle Data Guard Concepts and Administration* for more information about logical standby databases

This chapter contains the following topics:

- [Using DBMS_LOGSTBY](#)
 - [Overview](#)
 - [Operational Notes](#)
- [Summary of DBMS_LOGSTDBY Subprograms](#)

Using DBMS_LOGSTBY

- [Overview](#)
- [Operational Notes](#)

Overview

The DBMS_LOGSTDBY package helps you manage the SQL Apply (logical standby database) environment. The procedures in the DBMS_LOGSTDBY package help you to accomplish the following main objectives:

- Allow controlled access to tables in the standby database that may require maintenance
- Control how transactions are applied to the logical standby database
- Provide a way to skip applying archived redo log files to selected tables or entire schemas in the standby database, and describe how exceptions should be handled
- Manage initialization parameters used by log apply services
- Ensure supplemental logging is enabled properly and build the LogMiner dictionary

Operational Notes

Ensure you use the correct case when supplying schema and table names to the DBMS_LOGSTDBY package. For example, the following statements show incorrect and correct syntax for a SKIP procedure that skips changes to OE.TEST.

Incorrect statement:

```
EXECUTE DBMS_LOGSTDBY.SKIP ('DML', 'oe', 'test', null);
```

Because the names are specified with lowercase characters, the transactions that update these columns will still be applied to the logical standby database.

Correct statement:

```
EXECUTE DBMS_LOGSTDBY.SKIP ('DML', 'OE', 'TEST', null);
```

Summary of DBMS_LOGSTDBY Subprograms

Table 49–1 DBMS_LOGSTDBY Package Subprograms

Subprogram	Description
APPLY_SET Procedure on page 49-4	Sets the values of specific initialization parameters that configure and maintain log apply services
APPLY_UNSET Procedure on page 49-8	Resets the value of specific initialization parameters to the system default values
BUILD Procedure on page 49-12	Ensures supplemental logging is enabled properly and builds the LogMiner dictionary
INSTANTIATE_TABLE Procedure on page 49-13	Creates and populates a table in the standby database from a corresponding table in the primary database
SKIP Procedure on page 49-15	Specifies which database operations that are performed on the primary database should <i>not</i> be applied to the logical standby database
SKIP_ERROR Procedure on page 49-22	Specifies criteria to follow if an error is encountered, with the result that you can choose to stop log apply services or ignore the error
SKIP_TRANSACTION Procedure on page 49-25	Specifies transaction identification information to skip (ignore) applying specific transactions to the logical standby database
UNSKIP Procedure on page 49-27	Modifies the options set in the <code>SKIP</code> procedure
UNSKIP_ERROR Procedure on page 49-30	Modifies the options set in the <code>SKIP_ERROR</code> procedure
UNSKIP_TRANSACTION Procedure on page 49-31	Modifies the options set in the <code>SKIP_TRANSACTION</code> procedure

APPLY_SET Procedure

Use this procedure to set and modify the values of initialization parameters that configure and manage log apply services in a logical standby database environment. SQL apply cannot be running when you use this procedure.

Syntax

```
DBMS_LOGSTDBY.APPLY_SET (
    parameter      IN VARCHAR,
    value          IN VARCHAR);
```

Parameters

Table 49–2 *APPLY_SET Procedure Parameters*

Parameter	Description
MAX_SGA	<p>Number of megabytes for the system global area (SGA) that SQL Apply will use to cache change records. The default value is 30 megabytes or less if the <code>SHARED_POOL_SIZE</code> initialization parameter is set to a small value. In most cases 30 megabytes is sufficient.</p> <p>Note: In Oracle9i, the parameter default was one quarter of the value set for the <code>SHARED_POOL_SIZE</code> initialization parameter.</p>
MAX_SERVERS	<p>Number of parallel query servers that SQL Apply uses to read and apply redo. It defaults to the value of the <code>PARALLEL_MAX_SERVERS</code> initialization parameter or 9, whichever is lower. Because the correct value for this parameter is really a function of the workload, it is best to explicitly set the parameter, using a reasonable value that will work in most cases.</p> <p>Note: In Oracle9i, the <code>MAX_SERVERS</code> parameter defaulted to the value of the <code>PARALLEL_MAX_SERVERS</code> initialization parameter.</p>
MAX_EVENTS_RECORDED	<p>Number of events that will be stored in the <code>DBA_LOGSTDBY_EVENTS</code> table, which stores logical standby event information.</p>

Table 49–2 (Cont.) APPLY_SET Procedure Parameters

Parameter	Description
TRANSACTION_CONSISTENCY	<p>Level of transaction consistency maintained between the primary and standby databases. Specify one of the following values:</p> <p>FULL: Transactions are applied to the logical standby database in the exact order in which they were committed on the primary database. (Transactions are applied in commit SCN order.) This is the default parameter setting.</p> <p>READ_ONLY: Transactions are committed out of order (which provides better performance), but SQL <code>SELECT</code> statements executed on the standby database always return consistent results based on the last consistent SCN known to SQL apply.</p> <p>NONE: Transactions are applied out of order from how they were committed on the primary database, and no attempt is made to provide read-consistent results.</p> <p>Regardless of the level chosen, modifications done to the same row are always applied in the same order as they happened in the primary database. See the Usage Notes for details and recommendations.</p>
RECORD_SKIP_ERRORS	<p>Controls whether skipped errors (as described by the <code>SKIP_ERROR</code> procedure) are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. Specify one of the following values:</p> <p>TRUE: Skipped errors are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. This is the default parameter setting.</p> <p>FALSE: Skipped errors are not recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table.</p>
RECORD_SKIP_DDL	<p>Controls whether skipped DDL statements are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. Specify one of the following values:</p> <p>TRUE: Skipped DDL statements are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. This is the default parameter setting.</p> <p>FALSE: Skipped DDL statements are not recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table.</p>

Table 49–2 (Cont.) APPLY_SET Procedure Parameters

Parameter	Description
RECORD_APPLIED_DDL	<p>Controls whether DDL statements that have been applied to the logical standby database are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. Specify one of the following values:</p> <p>TRUE: Indicates that DDL statements applied to the logical standby database are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. This is the default parameter setting.</p> <p>FALSE: Indicates that applied DDL statements are not recorded.</p>
APPLY_SERVERS	Controls the number of parallel execution servers used to apply changes. See <i>Oracle Data Guard Concepts and Administration</i> for an explanation of the logical standby processes.
PREPARE_SERVERS	Controls the number of parallel execution servers used to prepare changes. See <i>Oracle Data Guard Concepts and Administration</i> for an explanation of the logical standby processes.

Usage Notes

- Although the default values provided by the system for initialization parameters are adequate for most applications, you might want to use the `APPLY_SET` procedure when you need to perform tuning and maintenance tasks. For example, use the `APPLY_SET` procedure when you want to override default initialization parameter values to tune log apply services.
- Log apply services must not be applying archived redo log data to the standby database when you modify initialization parameters with the `APPLY_SET` procedure. The initialization parameter values that you set using this procedure do not become active until you start log apply services.
- Use the [APPLY_UNSET Procedure](#) to reverse (undo) the actions of the `APPLY_SET` procedure.
- For the `TRANSACTION_CONSISTENCY` parameter:
 - The `FULL` option (the default) is recommended when the logical standby database is used for generic reporting applications. This option results in the lowest performance.
 - The `READ_ONLY` option is recommended when the logical standby database is used for read-only reporting.

SQL Apply periodically refreshes an SCN maintained in SGA that represents a consistent state. Queries executed on the standby database, automatically use Oracle Flashback to the maintained SCN. This is beneficial when the logical standby database is being used to generate reports. Any Oracle Flashback restrictions apply to this option.

- The `NONE` option works well as long as applications that are reading the logical standby database make no assumptions about transaction order. The `NONE` option is also useful when the logical standby database is in catch-up mode.

The `NONE` option results in the best performance of the three options for the `TRANSACTION_CONSISTENCY` parameter. However, this setting might give you inconsistent results on the standby database. If applications that are reading the logical standby database make no assumptions about transaction order, this option works well. For example:

- * On the primary database, one transaction added a new customer and a second transaction added a new order for that customer.
- * On the standby database, those transactions may be reversed. The order for the new customer might be added first. If you then run a reporting application on the standby database that expects to find a customer for the new order, the reporting application might fail because constraints are not checked and triggers are not fired.

Examples

If parallel queries are routinely being performed by applications, a certain number of parallel query servers should be reserved for those queries. To allocate 30 parallel query servers for logical standby log apply services, enter the following statement:

```
SQL> EXECUTE DBMS_LOGSTDBY.APPLY_SET('MAX_SERVERS', 30);
```

Thus, if the `PARALLEL_MAX_SERVERS` parameter is set to 50, 30 servers will be available for logical standby processing and 20 parallel query servers will be allocated for parallel query processing.

Note: If log apply services cannot allocate the parallel query server it requires because parallel queries are currently being processed, log apply services may stop. If this happens, start log apply services again.

APPLY_UNSET Procedure

Use the `APPLY_UNSET` procedure to reverse or undo the settings that you made with the `APPLY_SET` procedure. The `APPLY_UNSET` procedure resets the specified initialization parameter value to the system default value. The initialization parameter default value does not become active until log apply services are started.

Syntax

```
DBMS_LOGSTDBY.APPLY_UNSET (  
    parameter          IN VARCHAR);
```

Parameters

Table 49–3 *APPLY_UNSET Procedure Parameters*

Parameter	Description
<code>MAX_SGA</code>	Number of megabytes for the system global area (SGA) allocation for log apply services cache. The default value is one quarter of the value set for the <code>SHARED_POOL_SIZE</code> initialization parameter.
<code>MAX_SERVERS</code>	Number of parallel query servers specifically reserved for log apply services. By default, log apply services use all available parallel query servers to read the log files and apply changes. See <i>Oracle Database Reference</i> for more information about parallel query servers.
<code>MAX_EVENTS_RECORDED</code>	Number of events that will be stored in the <code>DBA_LOGSTDBY_EVENTS</code> table, which stores logical standby event information.

Table 49–3 (Cont.) APPLY_UNSET Procedure Parameters

Parameter	Description
TRANSACTION_CONSISTENCY	<p>Level of transaction consistency maintained between the primary and standby databases. Specify one of the following values:</p> <p>FULL: Transactions are applied to the logical standby database in the exact order in which they were committed on the primary database. (Transactions are applied in commit SCN order.) This is the default parameter setting.</p> <p>READ_ONLY: Transactions are committed out of order (which provides better performance), but SQL <code>SELECT</code> statements executed on the standby database always return consistent results based on the last consistent SCN known to SQL apply.</p> <p>NONE: Transactions are applied out of order from how they were committed on the primary database, and no attempt is made to provide read-consistent results.</p> <p>Regardless of the level chosen, modifications done to the same row are always applied in the same order as they happened in the primary database. See the Usage Notes for details and recommendations.</p>
RECORD_SKIP_ERRORS	<p>Controls whether skipped errors (as described by the <code>SKIP_ERROR</code> procedure) are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. Specify one of the following values:</p> <p>TRUE: Skipped errors are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. This is the default parameter setting.</p> <p>FALSE: Skipped errors are not recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table.</p>
RECORD_SKIP_DDL	<p>Controls whether skipped DDL statements are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. Specify one of the following values:</p> <p>TRUE: Skipped DDL statements are recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table. This is the default parameter setting.</p> <p>FALSE: Skipped DDL statements are not recorded in the <code>DBA_LOGSTDBY_EVENTS</code> table.</p>

Table 49–3 (Cont.) APPLY_UNSET Procedure Parameters

Parameter	Description
RECORD_APPLIED_DDL	<p>Controls whether DDL statements that have been applied to the logical standby database are recorded in the DBA_LOGSTDBY_EVENTS table. Specify one of the following values:</p> <p>TRUE: Indicates that DDL statements applied to the logical standby database are recorded in the DBA_LOGSTDBY_EVENTS table. This is the default parameter setting.</p> <p>FALSE: Indicates that applied DDL statements are not recorded.</p>
APPLY_SERVERS	Controls the number of parallel execution servers used to apply changes. See <i>Oracle Data Guard Concepts and Administration</i> for an explanation of the logical standby processes.
PREPARE_SERVERS	Controls the number of parallel execution servers used to prepare changes. See <i>Oracle Data Guard Concepts and Administration</i> for an explanation of the logical standby processes.

Usage Notes

- Log apply services must not be applying archived redo log data to the standby database when you modify initialization parameters with the APPLY_UNSET procedure.
- Use the APPLY_SET procedure to set the values of initialization parameters.

Examples

To unset the number of parallel query servers for log apply services, enter the following statement:

```
SQL> EXECUTE DBMS_LOGSTDBY.APPLY_UNSET('MAX_SERVERS');
```

Assuming that the PARALLEL_MAX_SERVERS initialization parameter is set to 50, this statement will result in 50 parallel query servers being available for parallel query processing. This is because, by default, log apply services use all available parallel query servers to read the log files and apply changes.

Note: If log apply services cannot allocate the parallel query server it requires because parallel queries are currently being processed, log apply services may stop. If this happens, start log apply services again.

BUILD Procedure

Use this procedure on the primary database to preserve important metadata (LogMiner dictionary) information in the redo logs. If supplemental logging has not been set correctly, this procedure sets it up and enables it automatically.

Syntax

```
DBMS_LOGSTDBY.BUILD;
```

Usage Notes

- Supplemental log information includes extra information in the archived redo logs that helps log apply services to uniquely identify and correctly maintain tables in a logical standby database.
- LogMiner dictionary information allows log apply services to interpret data in the redo logs.
- The `ALTER DATABASE CREATE LOGICAL STANDBY CONTROLFILE` statement also performs this functionality.

INSTANTIATE_TABLE Procedure

This procedure creates and populates a table in the standby database from a corresponding table in the primary database. The table requires the name of the database link (`dblink`) as an input parameter.

Use the `INSTANTIATE_TABLE` procedure to:

- Add a table to a standby database
- Re-create a table in a standby database

Syntax

```
DBMS_LOGSTDBY.INSTANTIATE_TABLE (
    schema_name      IN VARCHAR2,
    table_name       IN VARCHAR2,
    dblink           IN VARCHAR2);
```

Parameters

Table 49–4 *INSTANTIATE_TABLE Procedure Parameters*

Parameter	Description
<code>schema_name</code>	Name of the schema.
<code>table_name</code>	Name of the table to be created or re-created in the standby database.
<code>dblink</code>	Name of the database link account that has privileges to read and lock the table in the primary database.

Usage Notes

- Use this procedure to create and populate a table in a way that keeps the data on the standby database transactionally consistent with the primary database.
- This procedure assumes that the metadata has been maintained correctly.
- This table is not safe until the redo log that was current on the primary database at the time of execution is applied to the standby database.

Examples

Enter this statement to create and populate a new table on the standby database.

INSTANTIATE_TABLE Procedure

```
SQL> EXECUTE DBMS_LOGSTDBY.INSTANTIATE_TABLE (  
    'myschema', 'mytable', 'mydblink');
```


SKIP Procedure

Use the `SKIP` procedure to define filters that prevent the application of SQL statements on the logical standby database.

By default, all SQL statements executed on a primary database are applied to a logical standby database. If only a subset of activity on a primary database is of interest for application to the standby database, you can use the `SKIP` procedure to define filters that prevent the application of SQL statements on the logical standby database. While skipping (ignoring) SQL statements is the primary goal of filters, it is also possible to associate a stored procedure with a DDL filter so that runtime determinations can be made whether to skip the statement, execute this statement, or execute a replacement statement.

Syntax

```
DBMS_LOGSTDBY.SKIP (
    stmt                IN VARCHAR2,
    schema_name        IN VARCHAR2,
    object_name        IN VARCHAR2,
    proc_name          IN VARCHAR2,
    use_like            IN BOOLEAN,
    esc                 IN CHAR1);
```

Parameters

Table 49–5 SKIP Procedure Parameters

Parameter	Description
<code>stmt</code>	Either a keyword that identifies a set of SQL statements or a specific SQL statement. The use of keywords simplifies configuration since keywords, generally defined by the database object, identify all SQL statements that operate on the specified object. Table 49–6 shows a list of keywords and the equivalent SQL statements, either of which is a valid value for this parameter.
<code>schema_name</code>	The name of one or more schemas (wildcards are permitted) associated with the SQL statements identified by the <code>stmt</code> parameter. If not applicable, this value must be set to <code>NULL</code> .
<code>object_name</code>	The name of one or more objects (wildcards are permitted) associated with the SQL statements identified by the <code>stmt</code> . If not applicable, this value must be set to <code>NULL</code> .

Table 49–5 (Cont.) SKIP Procedure Parameters

Parameter	Description
proc_name	<p data-bbox="568 296 1282 401">Name of a stored procedure to call when log apply services determines that a particular statement matches the filter defined by the <code>stmt</code>, <code>schema_name</code>, and <code>object_name</code> parameters. Specify the procedure in the following format:</p> <pre data-bbox="568 418 1022 444">' "schema" ."package" ."procedure" '</pre> <p data-bbox="568 461 1282 531">This procedure returns a value that directs log apply services to perform one of the following: execute the statement, skip the statement, or execute a replacement statement.</p> <p data-bbox="568 548 1282 600">Log apply services calls the stored procedure with the following call signature:</p> <ul data-bbox="568 618 1282 1326" style="list-style-type: none"> <li data-bbox="568 618 1282 670">■ <code>IN STATEMENT VARCHAR2</code> -- The SQL statement that matches the filter <li data-bbox="568 687 1282 713">■ <code>IN STATEMENT_TYPE VARCHAR2</code> -- The <code>stmt</code> of the filter <li data-bbox="568 730 1282 782">■ <code>IN SCHEMA VARCHAR2</code> -- The <code>schema_name</code> of the filter, if applicable <li data-bbox="568 800 1282 852">■ <code>IN NAME VARCHAR2</code> -- The <code>object_name</code> of the filter, if applicable <li data-bbox="568 869 1282 895">■ <code>IN XIDUSN NUMBER</code> -- Transaction ID part 1 <li data-bbox="568 913 1282 939">■ <code>IN XIDSLT NUMBER</code> -- Transaction ID part 2 <li data-bbox="568 956 1282 982">■ <code>IN XIDSQN NUMBER</code> -- Transaction ID part 3 <li data-bbox="568 999 1282 1069">■ <code>OUT SKIP_ACTION NUMBER</code> -- Action to be taken by log apply services upon completion of this routine. Valid values are: <ul style="list-style-type: none"> <li data-bbox="615 1086 1282 1112"><code>SKIP_ACTION_APPLY</code> -- Execute the statement <li data-bbox="615 1130 1282 1156"><code>SKIP_ACTION_SKIP</code> -- Skip the statement <li data-bbox="615 1173 1282 1225"><code>SKIP_ACTION_REPLACE</code> -- Execute the replacement statement supplied in the <code>NEW_STATEMENT</code> output parameter <li data-bbox="568 1242 1282 1326">■ <code>OUT NEW_STATEMENT VARCHAR2</code> -- The statement to execute in place of the original statement. Use of this option requires that <code>SKIP_ACTION</code> be set to <code>SKIP_ACTION_REPLACE</code>. Otherwise, set this option to <code>NULL</code>.

Table 49–5 (Cont.) SKIP Procedure Parameters

Parameter	Description
<code>use_like</code>	Allows pattern matching to isolate the tables that you want to skip on the logical standby database. The <code>use_like</code> parameter matches a portion of one character value to another by searching the first value for the pattern specified by the second, and calculates strings using characters as defined by the input character set. This parameter follows the same rules for pattern matching described in the <i>Oracle Database SQL Reference</i> .
<code>esc</code>	Identifies an escape character (such as the character <code>"/</code>) that you can use for pattern matching. If the escape character appears in the pattern before the character <code>"%"</code> or <code>"_"</code> then Oracle interprets this character literally in the pattern, rather than as a special pattern matching character. See <i>Oracle Database SQL Reference</i> for more information about pattern matching.

Usage Notes

Caution: Atomic execution cannot be guaranteed if hardware or software failures stop log apply services. In a failure situation, a statement maybe executed more than once.

These stored procedures are not supported with `DBMS_LOGSTDBY.SKIP('DML' . . .)`. If multiple wildcards match a given database statement object defined by the `stmt` parameter, only one of the matching stored procedures will be called (alphabetically, by procedure).

- Use the `SKIP` procedure with caution, particularly when skipping DDL statements. If a `CREATE TABLE` statement is skipped, for example, you must also specify other DDL statements that refer to that table in the `SKIP` procedure. Otherwise, the statements will fail and cause an exception. When this happens, log apply services stop running.
- Before calling the `SKIP` procedure, log apply services must be halted. Do this by issuing an `ALTER DATABASE STOP LOGICAL STANDBY APPLY` statement. Once all desired filters have been specified, issue an `ALTER DATABASE START LOGICAL STANDBY APPLY` statement to start log apply services using the new filter settings.

- See the [UNSKIP Procedure](#) for information about reversing (undoing) the settings of the SKIP procedure.

Skip Statement Options

[Table 49–6](#) lists the supported values for the `stmt` parameter of the SKIP procedure. The left column of the table lists the keywords that may be used to identify the set of SQL statements to the right of the keyword. Any of the SQL statements in the right column, however, are also valid values. Note that keywords are generally defined by database object.

Table 49–6 Supported Values for `stmt` Parameter

Keyword	Associated SQL Statements
NON_SCHEMA_DDL	<i>All DDL that does not pertain to a particular schema</i>
SCHEMA_DDL	<i>All DDL that pertains to a particular schema</i>
DML	<i>Sequence operations such as <code>sequence.nextval</code></i>
CLUSTER	CREATE CLUSTER AUDIT CLUSTER DROP CLUSTER TRUNCATE CLUSTER
CONTEXT	CREATE CONTEXT DROP CONTEXT
DATABASE LINK	CREATE DATABASE LINK DROP DATABASE LINK
DIMENSION	CREATE DIMENSION ALTER DIMENSION DROP DIMENSION
DIRECTORY	CREATE DIRECTORY DROP DIRECTORY
INDEX	CREATE INDEX ALTER INDEX DROP INDEX

Table 49–6 (Cont.) Supported Values for stmt Parameter

Keyword	Associated SQL Statements
PROCEDURE ¹	CREATE FUNCTION CREATE LIBRARY CREATE PACKAGE CREATE PACKAGE BODY CREATE PROCEDURE DROP FUNCTION DROP LIBRARY DROP PACKAGE DROP PROCEDURE
PROFILE	CREATE PROFILE ALTER PROFILE DROP PROFILE
PUBLIC DATABASE LINK	CREATE PUBLIC DATABASE LINK DROP PUBLIC DATABASE LINK
PUBLIC SYNONYM	CREATE PUBLIC SYNONYM DROP PUBLIC SYNONYM
ROLE	CREATE ROLE ALTER ROLE DROP ROLE SET ROLE
ROLLBACK STATEMENT	CREATE ROLLBACK SEGMENT ALTER ROLLBACK SEGMENT DROP ROLLBACK SEGMENT
SEQUENCE	CREATE SEQUENCE DROP SEQUENCE
SESSION	Log-ons
SYNONYM	CREATE SYNONYM DROP SYNONYM
SYSTEM AUDIT	AUDIT <i>SQL_statements</i> NOAUDIT <i>SQL_statements</i>
SYSTEM GRANT	GRANT <i>system_privileges_and_roles</i> REVOKE <i>system_privileges_and_roles</i>
TABLE	CREATE TABLE DROP TABLE TRUNCATE TABLE

Table 49–6 (Cont.) Supported Values for stmt Parameter

Keyword	Associated SQL Statements
TABLESPACE	CREATE TABLESPACE DROP TABLESPACE TRUNCATE TABLESPACE
TRIGGER	CREATE TRIGGER ALTER TRIGGER with ENABLE and DISABLE clauses DROP TRIGGER ALTER TABLE with ENABLE ALL TRIGGERS clause ALTER TABLE with DISABLE ALL TRIGGERS clause
TYPE	CREATE TYPE CREATE TYPE BODY ALTER TYPE DROP TYPE DROP TYPE BODY
USER	CREATE USER ALTER USER DROP USER
VIEW	CREATE VIEW DROP VIEW

¹ Java schema objects (sources, classes, and resources) are considered the same as procedure for purposes of skipping (ignoring) SQL statements.

Exceptions

Table 49–7 DBMS_LOGSTDBY.SKIP Procedure Exceptions

Exception	Description
ORA-16203	"Unable to interpret skip procedure return values." Indicates that a SKIP procedure has either generated an exception or has returned ambiguous values. You can identify the offending procedure by examining the DBA_LOGSTDBY_EVENTS view.

Examples

The following example shows how to use the SKIP procedure to skip (ignore) a schema on the logical standby database.

Example 1 Skip a Schema

To skip changes for a given schema, you must prevent log apply services from creating new objects in the schema and from modifying existing objects in the schema. In addition, the tablespace that supports the schema must not change. The following example demonstrates this using the `SKIP` procedure in a situation where schema *smith* has some number of tables defined in tablespace *bones* that we wish to ignore.

```
BEGIN
DBMS_LOGSTDBY.SKIP('SCHEMA_DDL', 'SMITH', '%', null);
DBMS_LOGSTDBY.SKIP('DML', 'SMITH', '%', null);
DBMS_LOGSTDBY.SKIP('TABLESPACE', null, null, 'SMITH.PROTECT_BONES');

END;
```

In the previous example, wildcards were used for the `object_name` parameter to indicate that the filter applies to all objects. In the last call to the `SKIP` procedure, the `PROTECT_BONES` procedure was supplied so that `TABLESPACE` could prevent tablespace operations on `BONES`. The following example is the definition for the `PROTECT_BONES` procedure:

```
CREATE OR REPLACE PROCEDURE PROTECT_BONES (statement      IN  VARCHAR2,
                                           statement_type IN  VARCHAR2,
                                           schema         IN  VARCHAR2,
                                           name           IN  VARCHAR2,
                                           xidusn        IN  NUMBER,
                                           xidslt        IN  NUMBER,
                                           xidsqn        IN  NUMBER,
                                           skip_action    OUT NUMBER,
                                           new_statement  OUT VARCHAR2) AS

BEGIN
  -- Init
  new_statement := NULL;

  -- Guaranteed to be either CREATE, DROP, or TRUNCATE TABLESPACE
  IF statement LIKE '%TABLESPACE BONES%'
  THEN
    -- Skip the statement
    skip_action := DBMS_LOGSTDBY.SKIP_ACTION_SKIP;
  ELSE
    -- Apply the statement
    skip_action := DBMS_LOGSTDBY.SKIP_ACTION_APPLY;
  END IF;
END protect_bones;
```

SKIP_ERROR Procedure

Upon encountering an error, the logical standby feature uses the criteria contained in this procedure to determine if the error should cause log apply services to stop. All errors to be skipped are stored in system tables that describe how exceptions should be handled.

Syntax

```
DBMS_LOGSTDBY.SKIP_ERROR (  
    stmt                IN VARCHAR2,  
    schema_name         IN VARCHAR2,  
    object_name         IN VARCHAR2,  
    proc_name           IN VARCHAR2,  
    use_like            IN BOOLEAN,  
    esc                 IN CHAR1);
```

Parameters

Table 49–8 SKIP_ERROR Procedure Parameters

Parameter	Description
stmt	Either a keyword that identifies a set of SQL statements or a specific SQL statement. The use of keywords simplifies configuration since keywords, generally defined by the database object, identify all SQL statements that operate on the specified object. Table 49–6 shows a list of keywords and the equivalent SQL statements, either of which is a valid value for this parameter.
schema_name	The name of one or more schemas (wildcards are permitted) associated with the SQL statements identified by the <code>stmt</code> parameter. If not applicable, this value must be set to <code>NULL</code> .
object_name	The name of one or more objects (wildcards are permitted) associated with the SQL statements identified by the <code>stmt</code> . If not applicable, this value must be set to <code>NULL</code> .

Table 49–8 (Cont.) SKIP_ERROR Procedure Parameters

Parameter	Description
proc_name	<p>Name of a stored procedure to call when log apply services determines a particular statement matches the filter defined by the <code>stmt</code>, <code>schema_name</code>, and <code>object_name</code> parameters. Specify the procedure in the following format:</p> <pre>' "schema" . "package" . "procedure" '</pre> <p>This procedure returns a value that directs log apply services to perform one of the following: execute the statement, skip the statement, or execute a replacement statement.</p> <p>Log apply services call the stored procedure with the following call signature:</p> <ul style="list-style-type: none"> ■ IN STATEMENT VARCHAR(4000) -- The first 4K of the statement ■ IN STATEMENT_TYPE VARCHAR2 -- The <code>stmt</code> of the filter ■ IN SCHEMA VARCHAR2 -- The <code>schema_name</code> of the filter, if applicable ■ IN NAME VARCHAR2 -- The <code>object_name</code> of the filter, if applicable ■ IN XIDUSN NUMBER -- Transaction ID part 1 ■ IN XIDSLT NUMBER -- Transaction ID part 2 ■ IN XIDSQN NUMBER -- Transaction ID part 3 ■ IN ERROR VARCHAR(4000) -- Text of error to be recorded (optional) ■ OUT NEW_ERROR VARCHAR(4000) -- Null or modified error text
use_like	<p>Allows pattern matching to isolate the tables that you want to skip on the logical standby database. The <code>use_like</code> parameter matches a portion of one character value to another by searching the first value for the pattern specified by the second, and calculates strings using characters as defined by the input character set. This parameter follows the same rules for pattern matching described in the <i>Oracle Database SQL Reference</i>.</p>
esc	<p>Identifies an escape character (such as the characters "%" or "_") that you can use for pattern matching. If the escape character appears in the pattern before the character "%" or "_" then Oracle interprets this character literally in the pattern, rather than as a special pattern matching character. See <i>Oracle Database SQL Reference</i> for more information about pattern matching.</p>

Usage Notes

- A stored procedure provided to the `SKIP_ERROR` procedure is called when log apply services encounter an error that could shut down the application of redo logs to the standby database.

Running this stored procedure affects the error being written in the `STATUS` column of the `DBA_LOGSTDBY_EVENTS` table. The `STATUS_CODE` column remains unchanged. If the stored procedure is to have no effect, that is, apply will be stopped, then the `NEW_ERROR` is written to the events table. To truly have no effect, set `NEW_ERROR` to `ERROR` in the procedure.

If the stored procedure requires that a shutdown be avoided, then you must set `NEW_ERROR` to `NULL`.

Example

```
DBMS_LOGSTDBY.SKIP_ERROR('DDL', 'joe', 'apptemp', null);
```

SKIP_TRANSACTION Procedure

This procedure provides a way to skip (ignore) applying transactions to the logical standby database. You can skip specific transactions by specifying transaction identification information.

You may want to use the `SKIP_TRANSACTION` procedure to:

- Skip a DDL transaction that has already failed and that might otherwise cause log apply services to stop.
- Skip a DDL transaction that may logically corrupt data.

Syntax

```
DBMS_LOGSTDBY.SKIP_TRANSACTION (
    XIDUSN          IN NUMBER,
    XIDSLT NUMBER   IN NUMBER,
    XIDSQN NUMBER   IN NUMBER);
```

Parameters

[Table 49–9](#) describes the parameters for the `SKIP_TRANSACTION` procedure.

Table 49–9 *SKIP_TRANSACTION Procedure Parameters*

Parameter	Description
XIDUSN NUMBER	Transaction ID undo segment number of the transaction being skipped.
XIDSLT NUMBER	Transaction ID slot number of the transaction being skipped.
XIDSQN NUMBER	Transaction ID sequence number of the transaction being skipped.

Usage Notes

If log apply services stop due to a particular transaction (for example, a DDL transaction), you can specify that transaction ID and then continue to apply. You can call this procedure multiple times for as many transactions as you want log apply services to ignore.

CAUTION: To skip a DML failure, use a `SKIP` procedure, such as `SKIP('DML', 'MySchema', 'MyFailed Table')`. Using the `SKIP_TRANSACTION` procedure for DML transactions may skip changes for other tables, thus logically corrupting them.

Note: Do not let the primary and logical standby databases diverge when skipping transactions. If possible, you should manually execute a compensating transaction in place of the skipped transaction.

- View the last statement in `DBA_LOGSTDBY_EVENTS` to determine the reason that log apply services stopped processing transactions to the logical standby database. Examine the statement and error condition provided.
- Use the `DBA_LOGSTDBY_SKIP_TRANSACTION` view to list the transactions that are going to be skipped by log apply services.
- Also, see the `ALTER DATABASE START LOGICAL STANDBY SKIP FAILED TRANSACTION` statement in *Oracle Database SQL Reference*.

UNSKIP Procedure

This procedure reverses the actions of the `SKIP` procedure by finding the record, matching all the parameters, and removing the record from the system table. The match must be exact, and multiple *skip* actions can be undone only by a matching number of *unskip* actions. You cannot undo multiple skip actions using wildcard characters.

Syntax

```
DBMS_LOGSTDBY.UNSKIP (
    stmt                IN VARCHAR2,
    schema_name         IN VARCHAR2,
    object_name         IN VARCHAR2);
```

Parameters

Table 49–10 UNSKIP Procedure Parameters

Parameter	Description
<code>stmt</code>	Either a keyword that identifies a set of SQL statements or a specific SQL statement. The use of keywords simplifies configuration since keywords, generally defined by the database object, identify all SQL statements that operate on the specified object. Table 49–6 shows a list of keywords and the equivalent SQL statements, either of which is a valid value for this parameter.
<code>schema_name</code>	The name of one or more schemas (wildcards are permitted) associated with the SQL statements identified by the <code>stmt</code> parameter. If not applicable, this value must be set to <code>NULL</code> .
<code>object_name</code>	The name of one or more objects (wildcards are permitted) associated with the SQL statements identified by the <code>stmt</code> . If not applicable, this value must be set to <code>NULL</code> .

Table 49–10 (Cont.) UNSKIP Procedure Parameters

Parameter	Description
<code>proc_name</code>	<p>Name of a stored procedure to call when log apply services determines that a particular statement matches the filter defined by the <code>stmt</code>, <code>schema_name</code>, and <code>object_name</code> parameters. Specify the procedure in the following format:</p> <pre>' "schema" . "package" . "procedure" '</pre> <p>This procedure returns a value that directs log apply services to perform one of the following: execute the statement, skip the statement, or execute a replacement statement.</p> <p>Log apply services calls the stored procedure with the following call signature:</p> <ul style="list-style-type: none"> ■ <code>IN STATEMENT VARCHAR2</code> -- The SQL statement that matches the filter ■ <code>IN STATEMENT_TYPE VARCHAR2</code> -- The <code>stmt</code> of the filter ■ <code>IN SCHEMA VARCHAR2</code> -- The <code>schema_name</code> of the filter, if applicable ■ <code>IN NAME VARCHAR2</code> -- The <code>object_name</code> of the filter, if applicable ■ <code>IN XIDUSN NUMBER</code> -- Transaction ID part 1 ■ <code>IN XIDSLT NUMBER</code> -- Transaction ID part 2 ■ <code>IN XIDSQN NUMBER</code> -- Transaction ID part 3 ■ <code>OUT SKIP_ACTION NUMBER</code> -- Action to be taken by log apply services upon completion of this routine. Valid values are: <ul style="list-style-type: none"> <code>SKIP_ACTION_APPLY</code> -- Execute the statement <code>SKIP_ACTION_SKIP</code> -- Skip the statement <code>SKIP_ACTION_REPLACE</code> -- Execute the replacement statement supplied in the <code>NEW_STATEMENT</code> output parameter ■ <code>OUT NEW_STATEMENT VARCHAR2</code> -- The statement to execute in place of the original statement. Use of this option requires that <code>SKIP_ACTION</code> be set to <code>SKIP_ACTION_REPLACE</code>. Otherwise, set this option to <code>NULL</code>.

Table 49–10 (Cont.) UNSKIP Procedure Parameters

Parameter	Description
use_like	Allows pattern matching to isolate the tables that you want to skip on the logical standby database. The <code>use_like</code> parameter matches a portion of one character value to another by searching the first value for the pattern specified by the second, and calculates strings using characters as defined by the input character set. This parameter follows the same rules for pattern matching described in the <i>Oracle Database SQL Reference</i> .
esc	Identifies an escape character (such as the character "/") that you can use for pattern matching. If the escape character appears in the pattern before the character "%" or "_" then Oracle interprets this character literally in the pattern, rather than as a special pattern matching character. See <i>Oracle Database SQL Reference</i> for more information about pattern matching.

Usage Notes

CAUTION: If DML changes for a table have been skipped, you must follow the call to the `UNSKIP` procedure with a call to a procedure that will import the affected table.

UNSKIP_ERROR Procedure

This procedure reverses or undoes the actions of the `SKIP_ERROR` procedure by finding the record, matching all the parameters, and removing the record from the system table. The match must be exact, and multiple *skip* actions can be undone only by a matching number of *unskip* actions. You cannot undo multiple skip actions with just one unskip procedure call.

Syntax

```
DBMS_LOGSTDBY.UNSKIP_ERROR (  
    stmt                IN VARCHAR2,  
    schema_name         IN VARCHAR2,  
    object_name         IN VARCHAR2);
```

Parameters

The parameter information for the `UNSKIP_ERROR` procedure is the same as that described for the `SKIP_ERROR` procedure. See [Table 49-8](#) for complete parameter information.

Example

```
DBMS_LOGSTDBY.UNSKIP_ERROR;
```


UNSKIP_TRANSACTION Procedure

This procedure reverses the actions of the `SKIP_TRANSACTION` procedure. The match must be exact, and multiple *skip transaction* actions can be undone only by a matching number of *unskip transaction* actions. You cannot undo multiple skip transaction actions using wildcard characters.

Syntax

```
DBMS_LOGSTDBY.UNSKIP_TRANSACTION (
    XIDUSN NUMBER          STRING,
    XIDSLT NUMBER         STRING,
    XIDSQN NUMBER         STRING);
```

Parameters

[Table 49-11](#) describes the parameters for the `UNSKIP_TRANSACTION` procedure.

Table 49-11 *DBMS_LOGSTDBY.UNSKIP_TRANSACTION Procedure Parameters*

Parameter	Description
XIDUSN NUMBER	Transaction ID undo segment number of the transaction being skipped.
XIDSLT NUMBER	Transaction ID slot number of the transaction being skipped.
XIDSQN NUMBER	Transaction ID sequence number of the transaction being skipped.

Usage Notes

- Use the `DBA_LOGSTDBY_SKIP_TRANSACTION` view to list the transactions that are going to be skipped by log apply services.

DBMS_METADATA

The `DBMS_METADATA` package provides a way for you to retrieve metadata from the database dictionary as XML or creation DDL and to submit the XML to re-create the object.

See Also: *Oracle Database Utilities* for more information and for examples of using the Metadata API

This chapter contains the following topics:

- [Using DBMS_METADATA](#)
 - [Overview](#)
 - [Security Model](#)
 - [Types](#)
 - [Rules and Limits](#)
 - [Organization of Subprograms](#)
 - [Subprograms for Retrieval of Multiple Objects from the Database](#)
 - [Subprograms for Submission of XML to the Database](#)
- [Summary of DBMS_METADATA Subprograms](#)

Using DBMS_METADATA

- [Overview](#)
- [Security Model](#)
- [Types](#)
- [Rules and Limits](#)
- [Organization of Subprograms](#)

Overview

You can use the DBMS_METADATA package to retrieve metadata and also to submit XML.

- [Retrieving Metadata](#)
- [Submitting XML](#)

Retrieving Metadata

If you are retrieving metadata, you can specify:

- The kind of object to be retrieved. This can be either a particular object type (such as a table, index, or procedure) or a heterogeneous collection of object types that form a logical unit (such as a database export or schema export).
- Optional selection criteria, such as owner or name.
- Parse items (attributes of the returned objects to be parsed and returned separately).
- Optional transformations on the output, implemented by XSLT scripts. By default the output is represented in XML, but you can specify transformations (into SQL DDL, for example), which are implemented by XSLT (Extensible Stylesheet Language Transformation) stylesheets stored in the database or externally.

DBMS_METADATA provides the following retrieval interfaces:

- For programmatic use: OPEN, SET_FILTER, SET_COUNT, GET_QUERY, SET_PARSE_ITEM, ADD_TRANSFORM, SET_TRANSFORM_PARAM, SET_REMAP_PARAM, FETCH_XXX, and CLOSE retrieve multiple objects.

- For use in SQL queries and for browsing: `GET_XML` and `GET_DDL` return metadata for a single named object. The `GET_DEPENDENT_XML`, `GET_DEPENDENT_DDL`, `GET_GRANTED_XML`, and `GET_GRANTED_DDL` interfaces return metadata for one or more dependent or granted objects. These procedures do not support heterogeneous object types.

Submitting XML

If you are submitting XML, you specify:

- The type of object
- Optional transform parameters to modify the object (for example, changing the object's owner)
- Parse items (attributes of the submitted objects to be parsed and submitted separately)
- Whether to execute the operation or simply return the generated DDL

DBMS_METADATA provides a programmatic interfaces for submission of XML. It is comprised of the following procedures: `OPENW`, `ADD_TRANSFORM`, `SET_TRANSFORM_PARAM`, `SET_REMAP_PARAM`, `SET_PARSE_ITEM`, `CONVERT`, `PUT`, and `CLOSE`.

Security Model

The object views of the Oracle metadata model implement security as follows:

- Nonprivileged users can see the metadata of only their own objects.
- `SYS` and users with `SELECT_CATALOG_ROLE` can see all objects.
- Nonprivileged users can also retrieve public synonyms, system privileges granted to them, and object privileges granted to them or by them to others. This also includes privileges granted to `PUBLIC`.
- If callers request objects they are not privileged to retrieve, no exception is raised; the object is simply not retrieved.
- If nonprivileged users are granted some form of access to an object in someone else's schema, they will be able to retrieve the grant specification through the Metadata API, but not the object's actual metadata.
- In stored procedures, functions, and definers-rights packages, roles (such as `SELECT_CATALOG_ROLE`) are disabled. Therefore, such a PL/SQL program can

only fetch metadata for objects in its own schema. If you want to write a PL/SQL program that fetches metadata for objects in a different schema (based on the invoker's possession of `SELECT_CATALOG_ROLE`), you must make the program invokers-rights.

Types

The following types, used by the `DBMS_METADATA` package, are defined in the `SYS` schema.

```
CREATE TYPE sys.ku$_parsed_item AS OBJECT (  
    item          VARCHAR2(30),  
    value         VARCHAR2(4000),  
    object_row    NUMBER )  
/  
  
CREATE PUBLIC SYNONYM ku$_parsed_item FOR sys.ku$_parsed_item;  
  
CREATE TYPE sys.ku$_parsed_items IS TABLE OF sys.ku$_parsed_item  
/  
  
CREATE PUBLIC SYNONYM ku$_parsed_items FOR sys.ku$_parsed_items;  
  
CREATE TYPE sys.ku$_ddl AS OBJECT (  
    ddlText      CLOB,  
    parsedItem   sys.ku$_parsed_items )  
/  
  
CREATE PUBLIC SYNONYM ku$_ddl FOR sys.ku$_ddl;  
  
CREATE TYPE sys.ku$_ddls IS TABLE OF sys.ku$_ddl  
/  
  
CREATE PUBLIC SYNONYM ku$_ddls FOR sys.ku$_ddls;  
  
CREATE TYPE sys.ku$_multi_ddl AS OBJECT (  
    object_row    NUMBER,  
    ddls          sys.ku$_ddls )  
/  
  
CREATE OR REPLACE PUBLIC SYNONYM ku$_multi_ddl FOR sys.ku$_multi_ddl;  
  
CREATE TYPE sys.ku$_multi_ddls IS TABLE OF sys.ku$_multi_ddl;  
/
```

```
CREATE OR REPLACE PUBLIC SYNONYM ku$_multi_ddls FOR
    sys.ku$_multi_ddls;

CREATE TYPE sys.ku$_ErrorLine IS OBJECT (
    errorNumber    NUMBER,
    errorText      VARCHAR2(2000) )
/

CREATE PUBLIC SYNONYM ku$_ErrorLine FOR sys.ku$_ErrorLine;

CREATE TYPE sys.ku$_ErrorLines IS TABLE OF sys.ku$_ErrorLine
/
CREATE PUBLIC SYNONYM ku$_ErrorLines FOR sys.ku$_ErrorLines;

CREATE TYPE sys.ku$_SubmitResult AS OBJECT (
    ddl sys.ku$_ddl,
    errorLines sys.ku$_ErrorLines );
/

CREATE TYPE sys.ku$_SubmitResults IS TABLE OF sys.ku$_SubmitResult
/

CREATE PUBLIC SYNONYM ku$_SubmitResults FOR sys.ku$_SubmitResults;
```

Rules and Limits

In an Oracle Shared Server (OSS) environment, the DBMS_METADATA package must disable session migration and connection pooling. This results in any shared server process that is serving a session running the package to effectively become a default, dedicated server for the life of the session. You should ensure that sufficient shared servers are configured when the package is used and that the number of servers is not artificially limited by too small a value for the MAX_SHARED_SERVERS initialization parameter.

Organization of Subprograms

The `DBMS_METADATA` subprograms are used to retrieve objects from, and submit XML to, a database. Some subprograms are used for both activities, while others are used only for retrieval or only for submission.

- [Table 50-3](#) provides a summary of `DBMS_METADATA` subprograms used to retrieve multiple objects from a database.
- [Table 50-2](#) provides a summary of `DBMS_METADATA` subprograms used to submit XML metadata to a database.

Subprograms for Retrieval of Multiple Objects from the Database

Table 50-1 *DBMS_METADATA Subprograms For Retrieving Multiple Objects*

Subprogram	Description
OPEN Procedure on page 50-26	Specifies the type of object to be retrieved, the version of its metadata, and the object model
SET_FILTER Procedure on page 50-41	Specifies restrictions on the objects to be retrieved, for example, the object name or schema
SET_COUNT Procedure on page 50-39	Specifies the maximum number of objects to be retrieved in a single <code>FETCH_XXX</code> call
GET_QUERY Procedure on page 50-25	Returns the text of the queries that are used by <code>FETCH_XXX</code>
SET_PARSE_ITEM Procedure on page 50-55	Enables output parsing by specifying an object attribute to be parsed and returned
ADD_TRANSFORM Function on page 50-9	Specifies a transform that <code>FETCH_XXX</code> applies to the XML representation of the retrieved objects
SET_TRANSFORM_PARAM and SET_REMAP_PARAM Procedures on page 50-59	Specifies parameters to the XSLT stylesheet identified by <code>transform_handle</code>
FETCH_XXX Functions on page 50-16	Returns metadata for objects meeting the criteria established by <code>OPEN</code> , <code>SET_FILTER</code> , <code>SET_COUNT</code> , <code>ADD_TRANSFORM</code> , and so on
CLOSE Procedure on page 50-13	Invalidates the handle returned by <code>OPEN</code> and cleans up the associated state
The GET_XXX Functions on page 50-20	Fetches the metadata for a specified object as XML or DDL, using only a single call

Subprograms for Submission of XML to the Database

Table 50–2 DBMS_METADATA Subprograms For Submitting XML

Subprogram	Description
OPENW Procedure on page 50-35	Opens a write context
ADD_TRANSFORM Function on page 50-9	Specifies a transform for the XML documents
SET_TRANSFORM_PARAM and SET_REMAP_PARAM Procedures on page 50-59	SET_TRANSFORM_PARAM specifies a parameter to a transform SET_REMAP_PARAM specifies a remapping for a transform
SET_PARSE_ITEM Procedure on page 50-55	Specifies an object attribute to be parsed
CONVERT Function on page 50-14	Converts an XML document to DDL
PUT Function on page 50-37	Submits an XML document to the database
CLOSE Procedure on page 50-13	Closes the context opened with OPENW

Summary of DBMS_METADATA Subprograms

Table 50–3 DBMS_METADATA Package Subprograms

Subprogram	Description
ADD_TRANSFORM Function on page 50-9	Specifies a transform that <code>FETCH_XXX</code> applies to the XML representation of the retrieved objects
CLOSE Procedure on page 50-13	Invalidates the handle returned by <code>OPEN</code> and cleans up the associated state
CONVERT Function on page 50-14	Converts an XML document to DDL.
FETCH_XXX Functions on page 50-16	Returns metadata for objects meeting the criteria established by <code>OPEN</code> , <code>SET_FILTER</code> , <code>SET_COUNT</code> , <code>ADD_TRANSFORM</code> , and so on
The GET_XXX Functions on page 50-20	Fetches the metadata for a specified object as XML or DDL, using only a single call
GET_QUERY Procedure on page 50-25	Returns the text of the queries that are used by <code>FETCH_XXX</code>
OPEN Procedure on page 50-26	Specifies the type of object to be retrieved, the version of its metadata, and the object model
OPENW Procedure on page 50-35	Opens a write context
PUT Function on page 50-37	Submits an XML document to the database
SET_COUNT Procedure on page 50-39	Specifies the maximum number of objects to be retrieved in a single <code>FETCH_XXX</code> call
SET_FILTER Procedure on page 50-41	Specifies restrictions on the objects to be retrieved, for example, the object name or schema
SET_PARSE_ITEM Procedure on page 50-55	Enables output parsing by specifying an object attribute to be parsed and returned
SET_TRANSFORM_PARAM and SET_REMAP_PARAM Procedures on page 50-59	Specifies parameters to the XSLT stylesheet identified by <code>transform_handle</code>

ADD_TRANSFORM Function

This function is used for both retrieval and submission:

- When this procedure is used to retrieve objects, it specifies a transform that `FETCH_xxx` applies to the XML representation of the retrieved objects.
- When used to submit objects, it specifies a transform that `CONVERT` or `PUT` applies to the XML representation of the submitted objects. It is possible to add more than one transform.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)
- [Subprograms for Submission of XML to the Database](#)

Syntax

```
DBMS_METADATA.ADD_TRANSFORM (
    handle      IN NUMBER,
    name       IN VARCHAR2,
    encoding   IN VARCHAR2 DEFAULT NULL,
    object_type IN VARCHAR2 DEFAULT NULL)
RETURN NUMBER;
```

Parameters

Table 50–4 ADD_TRANSFORM Parameters

Parameters	Description
handle	The handle returned from <code>OPEN</code> when this transform is used to retrieve objects. Or the handle returned from <code>OPENW</code> when this transform is used in the submission of XML metadata.

Table 50–4 (Cont.) ADD_TRANSFORM Parameters

Parameters	Description
name	<p>The name of the transform. If name contains a period, colon, or forward slash, it is interpreted as the URL of a user-supplied XSLT script. See <i>Oracle XML DB Developer's Guide</i>.</p> <p>Otherwise, name designates a transform implemented by this project. The following transforms are defined:</p> <ul style="list-style-type: none">■ DDL - the document is transformed to DDL that creates the object. The output of this transform is <i>not</i> an XML document.■ MODIFY - The document is modified as directed by transform and remap parameters. The output of this transform is an XML document. If no transform or remap parameters are specified, the document is unchanged.
encoding	<p>The name of the Globalization Support character set in which the stylesheet pointed to by name is encoded. This is only valid if name is a URL. If left NULL and the URL is external to the database, UTF-8 encoding is assumed. If left NULL and the URL is internal to the database (that is, it begins with /oradb/), then the encoding is assumed to be the database character set.</p>

Table 50–4 (Cont.) ADD_TRANSFORM Parameters

Parameters	Description
object_type	<p>The definition of this parameter depends upon whether you are retrieving objects or submitting XML metadata.</p> <ol style="list-style-type: none"> When you use ADD_TRANSFORM to retrieve objects, the following definition of object_type applies: <p>Designates the object type to which the transform applies. (Note that this is an object type name, not a path name.) By default the transform applies to the object type of the OPEN handle. When the OPEN handle designates a heterogeneous object type, the following behavior can occur:</p> <ul style="list-style-type: none"> if object_type is omitted, the transform applies to all object types within the heterogeneous collection if object_type is specified, the transform only applies to that specific object type within the collection <p>If you omit this parameter you can add the DDL transform to all objects in a heterogeneous collection with a single call. If you supply this parameter, you can add a transform for a specific object type.</p> When you use ADD_TRANSFORM in the submission of XML metadata, this parameter is the object type to which the transform applies. By default, it is the object type of the OPENW handle. Because the OPENW handle cannot designate a heterogeneous object type, this caller should leave this parameter NULL.

Return Values

The opaque handle that is returned is used as input to SET_TRANSFORM_PARAM and SET_REMAP_PARAM. Note that this handle is different from the handle returned by OPEN or OPENW; it refers to the transform, not the set of objects to be retrieved.

Usage Notes

- With no transforms added, objects are returned by default as XML documents. You call ADD_TRANSFORM to specify an XSLT stylesheet to transform the returned documents.
- You can call ADD_TRANSFORM more than once to apply multiple transforms to XML documents. Transforms are applied in the order in which they were

specified, the output of the first transform being used as input to the second, and so on.

- The output of the DDL transform is *not* an XML document. Therefore, no transform should be added after the DDL transform.

Exceptions

- `INVALID_ARGVAL`. A `NULL` or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INVALID_OPERATION`. `ADD_TRANSFORM` was called after the first call to `FETCH_XXX` for the `OPEN` context. After the first call to `FETCH_XXX` is made, no further calls to `ADD_TRANSFORM` for the current `OPEN` context are permitted.
- `INCONSISTENT_ARGS`. The arguments are inconsistent. Possible inconsistencies include the following:
 - `encoding` is specified even though `name` is not a URL
 - `object_type` is not part of the collection designated by `handle`

CLOSE Procedure

This procedure invalidates the handle returned by `OPEN` (or `OPENW`) and cleans up the associated state.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)
- [Subprograms for Submission of XML to the Database](#)

Syntax

```
DBMS_METADATA.CLOSE (
    handle IN NUMBER);
```

Parameters

Table 50–5 *CLOSE Parameters*

Parameter	Description
handle	The handle returned from <code>OPEN</code> (or <code>OPENW</code>).

Usage Notes

Note: The following notes apply only to object retrieval

You can prematurely terminate the stream of objects established by `OPEN` or (`OPENW`).

- If a call to `FETCH_XXX` returns `NULL`, indicating no more objects, a call to `CLOSE` is made transparently. In this case, you can still call `CLOSE` on the handle and not get an exception. (The call to `CLOSE` is not required.)
- If you know that only one specific object will be returned, you should explicitly call `CLOSE` after the single `FETCH_XXX` call to free resources held by the handle.

Exceptions

- `INVALID_ARGVAL`. The value for the `handle` parameter is `NULL` or invalid.

CONVERT Function

This function transforms an input XML document into creation DDL.

See Also: For more information about related subprograms:

- [Subprograms for Submission of XML to the Database](#)

Syntax

```
DBMS_METADATA.CONVERT (
    handle IN NUMBER,
    document IN sys.XMLType)
RETURN sys.ku$_multi_ddls;
```

```
DBMS_METADATA.CONVERT (
    handle IN NUMBER,
    document IN CLOB)
RETURN sys.ku$_multi_ddls;
```

Parameters

Table 50–6 *CONVERT Function Parameters*

Parameter	Description
handle	The handle returned from OPENW.
document	The XML document containing object metadata of the type of the OPENW handle.

Return Values

DDL to create the object(s).

Usage Notes

You can think of CONVERT as the second half of FETCH_XXX. The difference is that FETCH_XXX gets its XML document from the database, but CONVERT gets its XML document from the caller. The transforms specified with ADD_TRANSFORM are applied in turn, and the result is returned to the caller in a sys.ku\$_multi_ddls nested table. The DDL transform must be specified. If parse items were specified, they are returned in the parsedItems column.

The encoding of the XML document is embedded in its CLOB or XMLType representation. The version of the metadata is embedded in the XML. The generated DDL is valid for the current database compatibility level.

Exceptions

- `INVALID_ARGVAL`. A NULL or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INCONSISTENT_OPERATION`. The DDL transform was not specified.
- `INCOMPATIBLE_DOCUMENT`. The version of the XML document is not compatible with this version of the software.

FETCH_xxx Functions

These functions return metadata for objects meeting the criteria established by OPEN, SET_FILTER, SET_COUNT, ADD_TRANSFORM, and so on. See ["Usage Notes"](#) on page 50-17 for the variants.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)

Syntax

```
DBMS_METADATA.FETCH_XML (
    handle IN NUMBER)
RETURN sys.XMLType;
```

See Also: *Oracle XML DB Developer's Guide* for a description of XMLType

```
DBMS_METADATA.FETCH_DDL (
    handle IN NUMBER)
RETURN sys.ku$_ddl;
```

```
DBMS_METADATA.FETCH_CLOB (
    handle IN NUMBER)
RETURN CLOB;
```

The FETCH procedures are as follows:

```
DBMS_METADATA.FETCH_CLOB (
    handle IN NUMBER,
    doc IN OUT NOCOPY CLOB);
```

```
DBMS_METADATA.FETCH_XML_CLOB (
    handle IN NUMBER,
    doc IN OUT NOCOPY CLOB,
    parsed_items OUT sys.ku$_parsed_items,
    object_type_path OUT VARCHAR2);
```

Parameters

Table 50–7 *FETCH_xxx Function Parameters*

Parameters	Description
handle	The handle returned from OPEN.
doc	The metadata for the objects, or NULL if all objects have been returned.
parsed_items	A nested table containing the items specified by SET_PARSE_ITEM. If SET_PARSE_ITEM was not called, a NULL is returned.
object_type_path	For heterogeneous object types, this is the full path name of the object type for the objects returned by the call to FETCH_XXX. If handle designates a homogeneous object type, a NULL is returned.

Return Values

The metadata for the objects or NULL if all objects have been returned.

Usage Notes

These functions and procedures return metadata for objects meeting the criteria established by the call to OPEN that returned the handle, and subsequent calls to SET_FILTER, SET_COUNT, ADD_TRANSFORM, and so on. Each call to FETCH_XXX returns the number of objects specified by SET_COUNT (or less, if fewer objects remain in the underlying cursor) until all objects have been returned. After the last object is returned, subsequent calls to FETCH_XXX return NULL and cause the stream created by OPEN to be transparently closed.

There are several different FETCH_XXX functions and procedures:

- The FETCH_XML function returns the XML metadata for an object as an XMLType. It assumes that if any transform has been specified, that transform will produce an XML document. In particular, it assumes that the DDL transform has not been specified.
- The FETCH_DDL function returns the DDL (to create the object) in a sys.ku\$_ddls nested table. It assumes that the DDL transform has been specified. Each row of the sys.ku\$_ddls nested table contains a single DDL statement in the ddlText column; if requested, parsed items for the DDL statement will be returned in the parsedItems column. Multiple DDL statements may be returned under the following circumstances:

- When you call `SET_COUNT` to specify a count greater than 1
- When an object is transformed into multiple DDL statements. For example, A `TYPE` object that has a DDL transform applied to it can be transformed into both `CREATE TYPE` and `CREATE TYPE BODY` statements. A `TABLE` object can be transformed into a `CREATE TABLE`, and one or more `ALTER TABLE` statements
- The `FETCH_CLOB` function simply returns the object, transformed or not, as a `CLOB`.
- The `FETCH_CLOB` procedure returns the objects by reference in an `IN OUT NOCOPY` parameter. This is faster than the function variant, which returns LOBs by value.
- The `FETCH_XML_CLOB` procedure returns the XML metadata for the objects as a `CLOB` in an `IN OUT NOCOPY` parameter. This helps to avoid LOB copies, which can consume a lot of resources. It also returns a nested table of parse items and the full path name of the object type of the returned objects.
- All LOBs returned by `FETCH_xxx` are temporary LOBs. You must free the LOB. If the LOB is supplied as an `IN OUT NOCOPY` parameter, you must also create the LOB.
- If `SET_PARSE_ITEM` was called, `FETCH_DDL` and `FETCH_XML_CLOB` return attributes of the object's metadata (or the DDL statement) in a `sys.ku$_parsed_items` nested table. For `FETCH_XML_CLOB`, the nested table is an `OUT` parameter. For `FETCH_DDL`, it is a column in the returned `sys.ku$_ddl` nested table. Each row of the nested table corresponds to an item specified by `SET_PARSE_ITEM` and contains the following columns:
 - `item`—the name of the attribute as specified in the `name` parameter to `SET_PARSE_ITEM`.
 - `value`—the attribute value, or `NULL` if the attribute is not present in the DDL statement.
 - `object_row`—a positive integer indicating the object to which the parse item applies. If multiple objects are returned by `FETCH_xxx`, (because `SET_COUNT` specified a count greater than 1) then `object_row=1` for all items for the first object, 2 for the second, and so on.
- The rows of the `sys.ku$_parsed_items` nested table are ordered by ascending `object_row`, but otherwise the row order is undetermined. To find a particular parse item within an object row the caller must search the table for a match on `item`.

- In general there is no guarantee that a requested parse item will be returned. For example, the parse item may not apply to the object type or to the particular line of DDL, or the item's value may be NULL.
- If `SET_PARSE_ITEM` was not called, NULL is returned as the value of the parsed items nested table.
- It is expected that the same variant of `FETCH_XXX` will be called for all objects selected by `OPEN`. That is, programs will not intermix calls to `FETCH_XML`, `FETCH_DDL`, `FETCH_CLOB`, and so on using the same `OPEN` handle. The effect of calling different variants is undefined; it might do what you expect, but there are no guarantees.
- Every object fetched will be internally consistent with respect to on-going DDL (and the subsequent recursive DML) operations against the dictionary. In some cases, multiple queries may be issued, either because the object type is heterogeneous or for performance reasons (for example, one query for heap tables, one for index-organized tables). Consequently the `FETCH_XXX` calls may in fact be fetches from different underlying cursors (meaning that read consistency is not guaranteed).

Exceptions

Most exceptions raised during execution of the query are propagated to the caller. Also, the following exceptions may be raised:

- `INVALID_ARGVAL`. A NULL or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INCONSISTENT_OPERATION`. Either `FETCH_XML` was called when the DDL transform had been specified, or `FETCH_DDL` was called when the DDL transform had *not* been specified.

The GET_xxx Functions

The following GET_xxx functions let you fetch metadata for objects with a single call:

- GET_XML
- GET_DDL
- GET_DEPENDENT_XML
- GET_DEPENDENT_DDL
- GET_GRANTED_XML
- GET_GRANTED_DDL

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)

Syntax

```
DBMS_METADATA.GET_XML (  
object_type      IN VARCHAR2,  
name             IN VARCHAR2 DEFAULT NULL,  
schema          IN VARCHAR2 DEFAULT NULL,  
version         IN VARCHAR2 DEFAULT 'COMPATIBLE',  
model           IN VARCHAR2 DEFAULT 'ORACLE',  
transform       IN VARCHAR2 DEFAULT NULL)  
RETURN CLOB;
```

```
DBMS_METADATA.GET_DDL (  
object_type      IN VARCHAR2,  
name             IN VARCHAR2 DEFAULT NULL,  
schema          IN VARCHAR2 DEFAULT NULL,  
version         IN VARCHAR2 DEFAULT 'COMPATIBLE',  
model           IN VARCHAR2 DEFAULT 'ORACLE',  
transform       IN VARCHAR2 DEFAULT 'DDL')  
RETURN CLOB;
```

```
DBMS_METADATA.GET_DEPENDENT_XML (  
object_type      IN VARCHAR2,  
base_object_name IN VARCHAR2,  
base_object_schema IN VARCHAR2 DEFAULT NULL,
```

```

version          IN VARCHAR2 DEFAULT 'COMPATIBLE',
model            IN VARCHAR2 DEFAULT 'ORACLE',
transform        IN VARCHAR2 DEFAULT NULL,
object_count     IN NUMBER   DEFAULT 10000)
RETURN CLOB;

```

```

DBMS_METADATA.GET_DEPENDENT_DDL (
object_type      IN VARCHAR2,
base_object_name IN VARCHAR2,
base_object_schema IN VARCHAR2 DEFAULT NULL,
version          IN VARCHAR2 DEFAULT 'COMPATIBLE',
model            IN VARCHAR2 DEFAULT 'ORACLE',
transform        IN VARCHAR2 DEFAULT 'DDL',
object_count     IN NUMBER   DEFAULT 10000)
RETURN CLOB;

```

```

DBMS_METADATA.GET_GRANTED_XML (
object_type      IN VARCHAR2,
grantee          IN VARCHAR2 DEFAULT NULL,
version          IN VARCHAR2 DEFAULT 'COMPATIBLE',
model            IN VARCHAR2 DEFAULT 'ORACLE',
transform        IN VARCHAR2 DEFAULT NULL,
object_count     IN NUMBER   DEFAULT 10000)
RETURN CLOB;

```

```

DBMS_METADATA.GET_GRANTED_DDL (
object_type      IN VARCHAR2,
grantee          IN VARCHAR2 DEFAULT NULL,
version          IN VARCHAR2 DEFAULT 'COMPATIBLE',
model            IN VARCHAR2 DEFAULT 'ORACLE',
transform        IN VARCHAR2 DEFAULT 'DDL',
object_count     IN NUMBER   DEFAULT 10000)
RETURN CLOB;

```

Parameters

Table 50–8 *GET_xxx Function Parameters*

Parameter	Description
object_type	The type of object to be retrieved. This parameter takes the same values as the OPEN object_type parameter, except that it cannot be a heterogeneous object type. The attributes of the object type must be appropriate to the function. That is, for GET_xxx it must be a named object.

Table 50–8 (Cont.) GET_XXX Function Parameters

Parameter	Description
name	The object name. It is used internally in a NAME filter. (If the name is longer than 30 characters, it will be used in a LONGNAME filter.) If this parameter is NULL, then no NAME or LONGNAME filter is specified. See Table 50–17 for a list of filters.
schema	The object schema. It is used internally in a SCHEMA filter. The default is the current user.
version	The version of metadata to be extracted. This parameter takes the same values as the OPEN version parameter.
model	The object model to use. This parameter takes the same values as the OPEN model parameter.
transform	The name of a transformation on the output. This parameter takes the same values as the ADD_TRANSFORM name parameter. For GET_XML this must not be DDL.
base_object_name	The base object name. It is used internally in a BASE_OBJECT_NAME filter.
base_object_schema	The base object schema. It is used internally in a BASE_OBJECT_SCHEMA filter. The default is the current user.
grantee	The grantee. It is used internally in a GRANTEE filter. The default is the current user.
object_count	The maximum number of objects to return. See SET_COUNT Procedure on page 50-39.

Return Values

The metadata for the specified object as XML or DDL.

Usage Notes

- These functions allow you to fetch metadata for objects with a single call. They encapsulate calls to OPEN, SET_FILTER, and so on. The function you use depends on the characteristics of the object type and on whether you want XML or DDL.
 - GET_XXX is used to fetch named objects, especially schema objects (tables, views). They can also be used with nameless objects, such as RESOURCE_COST.
 - GET_DEPENDENT_XXX is used to fetch dependent objects (audits, object grants).

- GET_GRANTED_XXX is used to fetch granted objects (system grants, role grants).
- For some object types you can use more than one function. For example, you can use GET_XXX to fetch an index by name, or GET_DEPENDENT_XXX to fetch the same index by specifying the table on which it is defined.
- GET_XXX only returns a single named object.
- For GET_DEPENDENT_XXX and GET_GRANTED_XXX, an arbitrary number of dependent or granted objects can match the input criteria. You can specify an object count when fetching these objects. (The default count of 10000 should be adequate in most cases.)
- If the DDL transform is specified, session-level transform parameters are inherited.
- If you invoke these functions from SQL*Plus, you should set the PAGESIZE to 0 and set LONG to some large number to get complete, uninterrupted output.

Exceptions

- INVALID_ARGVAL. A NULL or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- OBJECT_NOT_FOUND. The specified object was not found in the database.

Examples

Example: Fetch the XML Representation of SCOTT.EMP

To generate complete, uninterrupted output, set the PAGESIZE to 0 and set LONG to some large number, as shown, before executing your query.

```
SET LONG 2000000
SET PAGESIZE 0
SELECT DBMS_METADATA.GET_XML('TABLE', 'EMP', 'SCOTT')
FROM DUAL;
```

Example: Fetch the DDL for all Complete Tables in the Current Schema, Filter Out Nested Tables and Overflow Segments

This example fetches the DDL for all "complete" tables in the current schema, filtering out nested tables and overflow segments. The example uses SET_TRANSFORM_PARAM (with the handle value = DBMS_METADATA.SESSION_TRANSFORM meaning "for the current session") to specify that storage clauses are

not to be returned in the SQL DDL. Afterwards, the example resets the session-level parameters to their defaults.

To generate complete, uninterrupted output, set the PAGESIZE to 0 and set LONG to some large number, as shown, before executing your query.

```
SET LONG 2000000
SET PAGESIZE 0
EXECUTE DBMS_METADATA.SET_TRANSFORM_PARAM(DBMS_METADATA.SESSION_
TRANSFORM, 'STORAGE', false);
SELECT DBMS_METADATA.GET_DDL('TABLE', u.table_name)
       FROM USER_ALL_TABLES u
       WHERE u.nested='NO'
              AND (u.iot_type is null or u.iot_type='IOT');
EXECUTE DBMS_METADATA.SET_TRANSFORM_PARAM(DBMS_METADATA.SESSION_
TRANSFORM, 'DEFAULT');
```

Example: Fetch the DDL For All Object Grants On HR.EMPLOYEES

```
SELECT DBMS_METADATA.GET_DEPENDENT_DDL('OBJECT_GRANT',
'EMPLOYEES', 'HR') FROM DUAL;
```

Example: Fetch the DDL For All System Grants Granted To SCOTT

```
SELECT DBMS_METADATA.GET_GRANTED_DDL('SYSTEM_GRANT', 'SCOTT')
FROM DUAL;
```

GET_QUERY Procedure

This procedure returns the text of the queries that are used by `FETCH_XXX`. This function assists in debugging.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)

Syntax

```
DBMS_METADATA.GET_QUERY (
    handle IN NUMBER)
RETURN VARCHAR2;
```

Parameters

Table 50–9 *GET_QUERY Procedure Parameters*

Parameter	Description
handle	The handle returned from <code>OPEN</code> . It cannot be the handle for a heterogeneous object type.

Return Values

The text of the queries that will be used by `FETCH_XXX`.

Exceptions

- `INVALID_ARGVAL`. A `NULL` or invalid value was supplied for the `handle` parameter.

OPEN Procedure

This procedure specifies the type of object to be retrieved, the version of its metadata, and the object model. The return value is an opaque context handle for the set of objects to be used in subsequent calls.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)

Syntax

```
DBMS_METADATA.OPEN (  
    object_type IN VARCHAR2,  
    version     IN VARCHAR2 DEFAULT 'COMPATIBLE',  
    model       IN VARCHAR2 DEFAULT 'ORACLE',  
    network_link IN VARCHAR2 DEFAULT NULL)  
RETURN NUMBER;
```

Parameters

Table 50–10 Open Procedure Parameters

Parameter	Description
<code>object_type</code>	<p>The type of object to be retrieved. Table 50–11 lists the valid type names and their meanings. These object types will be supported for the ORACLE model of metadata (see model in this table).</p> <p>The Attributes column in Table 50–11 specifies some object type attributes:</p> <ul style="list-style-type: none"> ■ Schema objects, such as tables, belong to schemas. ■ Named objects have unique names (if they are schema objects, the name is unique to the schema). ■ Dependent objects, such as indexes, are defined with reference to a base schema object. ■ Granted objects are granted or assigned to a user or role and therefore have a named grantee. ■ Heterogeneous object types denote a collection of related objects of different types. See Table 50–12 for a listing of object types returned for the heterogeneous object type. <p>These attributes are relevant when choosing object selection criteria. See "SET_FILTER Procedure" on page 50-41 for more information.</p>
<code>version</code>	<p>The version of metadata to be extracted. Database objects or attributes that are incompatible with the version will not be extracted. Legal values for this parameter are as follows:</p> <p>COMPATIBLE (default)—the version of the metadata corresponds to the database compatibility level.</p> <p>LATEST—the version of the metadata corresponds to the database version.</p> <p>A specific database version, for example, 9.2.0. As of Oracle Database 10g, this value cannot be lower than 9.2.0.</p>
<code>model</code>	<p>Specifies which view to use, because the API can support multiple views on the metadata. Only the ORACLE model is supported as of Oracle Database 10g.</p>
<code>network_link</code>	Reserved.

[Table 50–11](#) provides the name, meaning, attributes, and notes for the DBMS_METADATA package object types. In the attributes column, S represents a schema

object, N represents a named object, D represents a dependent object, G represents a granted object, and H represents a heterogeneous object.

Table 50–11 DBMS_METADATA: Object Types

Type Name	Meaning	Attributes	Notes
AQ_QUEUE	queues	SND	Dependent on table
AQ_QUEUE_TABLE	additional metadata for queue tables	ND	Dependent on table
AQ_TRANSFORM	transforms	SN	None
ASSOCIATION	associate statistics	D	None
AUDIT	audits of SQL statements	DG	Modeled as dependent, granted object. The base object name is the statement audit option name (for example, ALTER SYSTEM). There is no base object schema. The grantee is the user or proxy whose statements are audited.
AUDIT_OBJ	audits of schema objects	D	None
CLUSTER	clusters	SN	None
COMMENT	comments	D	None
CONSTRAINT	constraints	SND	Does not include: <ul style="list-style-type: none"> ■ primary key constraint for IOT ■ column NOT NULL constraints ■ certain REF SCOPE and WITH ROWID constraints for tables with REF columns
CONTEXT	application contexts	N	None
DATABASE_EXPORT	all metadata objects in a database	H	Corresponds to a full database export
DB_LINK	database links	SN	Modeled as schema objects because they have owners. For public links, the owner is PUBLIC. For private links, the creator is the owner.
DEFAULT_ROLE	default roles	G	Granted to a user by ALTER USER
DIMENSION	dimensions	SN	None
DIRECTORY	directories	N	None

Table 50–11 (Cont.) DBMS_METADATA: Object Types

Type Name	Meaning	Attributes	Notes
FGA_POLICY	fine-grained audit policies	D	Not modeled as named object because policy names are not unique.
FUNCTION	stored functions	SN	None
INDEX_STATISTICS	precomputed statistics on indexes	D	The base object is the index's table. See information on filters such as <code>BASE_INDEX_NAME</code> .
INDEX	indexes	SND	None
INDEXTYPE	indextypes	SN	None
JAVA_SOURCE	Java sources	SN	None
JOB	jobs	S	None
LIBRARY	external procedure libraries	SN	None
MATERIALIZED_VIEW	materialized views	SN	None
MATERIALIZED_VIEW_LOG	materialized view logs	D	None
OBJECT_GRANT	object grants	DG	None
OPERATOR	operators	SN	None
OUTLINE	stored outlines	N	This type is being deprecated.
PACKAGE	stored packages	SN	By default, both package specification and package body are retrieved. See " SET_FILTER Procedure " on page 50-41.
PACKAGE_SPEC	package specifications	SN	None
PACKAGE_BODY	package bodies	SN	None
PROCEDURE	stored procedures	SN	None
PROFILE	profiles	N	None
PROXY	proxy authentications	G	Granted to a user by <code>ALTER USER</code>
REF_CONSTRAINT	referential constraint	SND	None
REFRESH_GROUP	refresh groups	SN	None
RESOURCE_COST	resource cost info		None

Table 50–11 (Cont.) DBMS_METADATA: Object Types

Type Name	Meaning	Attributes	Notes
RLS_CONTEXT	driving contexts for enforcement of fine-grained access-control policies	D	Corresponds to the DBMS_RLS.ADD_POLICY_CONTENT procedure
RLS_GROUP	fine-grained access-control policy groups	D	Corresponds to the DBMS_RLS.CREATE_GROUP procedure
RLS_POLICY	fine-grained access-control policies	D	Corresponds to DBMS_RLS.ADD_GROUPED_POLICY. Not modeled as named objects because policy names are not unique.
RMGR_CONSUMER_GROUP	resource consumer groups	SN	Data Pump does not use these object types. Instead, it exports resource manager objects as procedural objects (PROCOBJ, for example).
RMGR_INITIAL_CONSUMER_GROUP	assign initial consumer groups to users	G	None
RMGR_PLAN	resource plans	SN	None
RMGR_PLAN_DIRECTIVE	resource plan directives	D	Dependent on resource plan
ROLE	roles	N	None
ROLE_GRANT	role grants	G	None
ROLLBACK_SEGMENT	rollback segments	N	None
SCHEMA_EXPORT	all metadata objects in a schema	H	Corresponds to user-mode export.
SEQUENCE	sequences	SN	None
SYNONYM	synonyms	See notes.	Private synonyms are schema objects. Public synonyms are not, but for the purposes of this API, their schema name is PUBLIC. The name of a synonym is considered to be the synonym itself. For example, in CREATE PUBLIC SYNONYM FOO FOR BAR, the resultant object is considered to have name FOO and schema PUBLIC.
SYSTEM_GRANT	system privilege grants	G	None
TABLE	tables	SN	None

Table 50–11 (Cont.) DBMS_METADATA: Object Types

Type Name	Meaning	Attributes	Notes
TABLE_DATA	metadata describing row data for a table, nested table, or partition	SND	For partitions, the object name is the partition name. For nested tables, the object name is the storage table name. The base object is the top-level table to which the table data belongs. For nested tables and partitioning, this is the top-level table (<i>not</i> the parent table or partition). For nonpartitioned tables and non-nested tables this is the table itself.
TABLE_EXPORT	metadata for a table and its associated objects	H	Corresponds to table-mode export
TABLE_STATISTICS	precomputed statistics on tables	D	None
TABLESPACE	tablespaces	N	None
TABLESPACE_QUOTA	tablespace quotas	G	Granted with ALTER USER
TRANSPORTABLE_EXPORT	metadata for objects in a transportable tablespace set	H	Corresponds to transportable tablespace export
TRIGGER	triggers	SND	None
TRUSTED_DB_LINK	trusted links	N	None
TYPE	user-defined types	SN	By default, both type and type body are retrieved. See " SET_FILTER Procedure " on page 50-41.
TYPE_SPEC	type specifications	SN	None
TYPE_BODY	type bodies	SN	None
USER	users	N	None
VIEW	views	SN	None
XMLSCHEMA	XML schema	SN	The object's name is its URL (which may be longer than 30 characters). Its schema is the user who registered it.

[Table 50–12](#) lists the types of objects returned for the major heterogeneous object types. For SCHEMA_EXPORT, certain object types are only returned if the INCLUDE_

USER filter is specified at TRUE. In the table, such object types are marked INCLUDE_USER.

Table 50–12 Object Types Returned for the Heterogeneous Object Type

Object Type	DATABASE_EXPORT	SCHEMA_EXPORT	TABLE_EXPORT	TRANSPORTABLE_EXPORT
ASSOCIATION	Yes	No	No	No
AUDIT	Yes	No	No	No
AUDIT_OBJ	Yes	Yes	Yes	Yes
CLUSTER	Yes	Yes	No	Yes
COMMENT	Yes	Yes	Yes	Yes
CONSTRAINT	Yes	Yes	Yes	Yes
CONTEXT	Yes	No	No	No
DB_LINK	Yes	Yes	No	No
DEFAULT_ROLE	Yes	INCLUDE_USER	No	No
DIMENSION	Yes	Yes	No	No
DIRECTORY	Yes	No	No	No
FGA_POLICY	Yes	No	No	Yes
FUNCTION	Yes	Yes	No	No
INDEX_STATISTICS	Yes	Yes	Yes	Yes
INDEX	Yes	Yes	Yes	Yes
INDEXTYPE	Yes	Yes	No	No
JAVA_SOURCE	Yes	Yes	No	No
JOB	Yes	Yes	No	No
LIBRARY	Yes	Yes	No	No
MATERIALIZED_VIEW	Yes	Yes	No	No
MATERIALIZED_VIEW_LOG	Yes	Yes	No	No
OBJECT_GRANT	Yes	Yes	Yes	Yes
OPERATOR	Yes	Yes	No	No

Table 50–12 (Cont.) Object Types Returned for the Heterogeneous Object Type

Object Type	DATABASE_ EXPORT	SCHEMA_ EXPORT	TABLE_ EXPORT	TRANSPORTABLE_ EXPORT
OUTLINE	If OUTLN user's objects are returned	if user is OUTLN	No	No
PACKAGE	Yes	Yes	No	No
PACKAGE_SPEC	Yes	Yes	No	No
PACKAGE_BODY	Yes	Yes	No	No
PASSWORD_HISTORY	Yes	INCLUDE_USER	No	No
PASSWORD_VERIFY_FUNCTION	Yes	No	No	No
PROCEDURE	Yes	Yes	No	No
PROFILE	Yes	No	No	No
PROXY	Yes	No	No	No
REF_CONSTRAINT	Yes	Yes	Yes	Yes
REFRESH_GROUP	Yes	Yes	No	No
RESOURCE_COST	Yes	No	No	No
RLS_CONTEXT	Yes	No	No	Yes
RLS_GROUP	Yes	No	No	Yes
RLS_POLICY	Yes	Table data is retrieved according to policy	Table data is retrieved according to policy	Yes
ROLE	Yes	No	No	No
ROLE_GRANT	Yes	No	No	No
ROLLBACK_SEGMENT	Yes	No	No	No
SEQUENCE	Yes	Yes	No	No
SYNONYM	Yes	Yes	No	No
SYSTEM_GRANT	Yes	INCLUDE_USER	No	No
TABLE	Yes	Yes	Yes	Yes
TABLE_DATA	Yes	Yes	Yes	Yes

Table 50–12 (Cont.) Object Types Returned for the Heterogeneous Object Type

Object Type	DATABASE_ EXPORT	SCHEMA_ EXPORT	TABLE_ EXPORT	TRANSPORTABLE_ EXPORT
TABLE_STATISTICS	Yes	Yes	Yes	Yes
TABLESPACE	Yes	No	No	No
TABLESPACE_QUOTA	Yes	INCLUDE_USER	No	No
TRIGGER	Yes	Yes	Yes	Yes
TRUSTED_DB_LINK	Yes	No	No	No
TYPE	Yes	Yes	No	Yes, if the types are used by tables in the transportable set
TYPE_SPEC	Yes	Yes	No	Yes, if the types are used by tables in the transportable set
TYPE_BODY	Yes	Yes	No	Yes, if the types are used by tables in the transportable set
USER	Yes	INCLUDE_USER	No	No
VIEW	Yes	Yes	No	No
XMLSCHEMA	Yes	Yes	No	No

Return Values

An opaque handle to the class of objects. This handle is used as input to `SET_FILTER`, `SET_COUNT`, `ADD_TRANSFORM`, `GET_QUERY`, `SET_PARSE_ITEM`, `FETCH_xxx`, and `CLOSE`.

Exceptions

- `INVALID_ARGVAL`. A `NULL` or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INVALID_OBJECT_PARAM`. The `version` or `model` parameter was not valid for the `object_type`.

OPENW Procedure

This procedure specifies the type of object to be submitted and the object model. The return value is an opaque context handle.

See Also: For more information about related subprograms:

- [Subprograms for Submission of XML to the Database](#)

Syntax

```
DBMS_METADATA.OPENW
  (object_type  IN VARCHAR2,
   version      IN VARCHAR2 DEFAULT 'COMPATIBLE',
   model        IN VARCHAR2 DEFAULT 'ORACLE')
RETURN NUMBER;
```

Parameters

Table 50–13 OPENW Function Parameters

Parameter	Description
object_type	The type of object to be submitted. Valid types names and their meanings are listed in Table 50–11 . The type cannot be a heterogeneous object type.
version	The version of DDL to be generated by the CONVERT function. DDL clauses that are incompatible with the version will not be generated. The legal values for this parameter are as follows: <ul style="list-style-type: none"> ▪ COMPATIBLE - This is the default. The version of the DDL corresponds to the database compatibility level. Database compatibility must be set to 9.2.0 or higher. ▪ LATEST - The version of the DDL corresponds to the database version. ▪ A specific database version. As of Oracle Database 10g, this value cannot be lower than 9.2.0.
model	Specifies which view to use. Only the Oracle proprietary (ORACLE) view is supported by DBMS_METADATA.

Return Values

An opaque handle to write context. This handle is used as input to the ADD_TRANSFORM, CONVERT, PUT, and CLOSE procedures.

Exceptions

- `INVALID_ARGVAL`. A `NULL` or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INVALID_OBJECT_PARAM`. The `model` parameter was not valid for the `object_type`.

PUT Function

This function submits an XML document containing object metadata to the database to create the objects.

See Also: For more information about related subprograms:

- [Subprograms for Submission of XML to the Database](#)

Syntax

```
DBMS_METADATA.PUT (
    handle IN NUMBER,
    document IN sys.XMLType,
    flags IN NUMBER,
    results IN OUT NOCOPY sys.ku$_SubmitResults)
RETURN BOOLEAN;
```

```
DBMS_METADATA.PUT (
    handle IN NUMBER,
    document IN CLOB,
    flags IN NUMBER,
    results IN OUT NOCOPY sys.ku$_SubmitResults)
RETURN BOOLEAN;
```

Parameters

Table 50–14 PUT Function Parameters

Parameter	Description
handle	The handle returned from OPENW.
document	The XML document containing object metadata for the type of the OPENW handle.
flags	Reserved for future use
results	Detailed results of the operation.

Return Values

TRUE if all SQL operations succeeded; FALSE if there were any errors.

Usage Notes

The `PUT` function converts the XML document to DDL just as `CONVERT` does (applying the specified transforms in turn) and then submits each resultant DDL statement to the database. As with `CONVERT`, the DDL transform must be specified. The DDL statements and associated parse items are returned in the `sys.ku$_SubmitResults` nested table. With each DDL statement is a nested table of error lines containing any errors or exceptions raised by the statement.

The encoding of the XML document is embedded in its CLOB or XMLType representation. The version of the metadata is embedded in the XML. The generated DDL is valid for the current database compatibility level.

Exceptions

- `INVALID_ARGVAL`. A NULL or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INCONSISTENT_OPERATION`. The DDL transform was not specified.
- `INCOMPATIBLE_DOCUMENT`. The version of the XML document is not compatible with this version of the software.

SET_COUNT Procedure

This procedure specifies the maximum number of objects to be retrieved in a single `FETCH_XXX` call. By default, each call to `FETCH_XXX` returns one object. You can use the `SET_COUNT` procedure to override this default. If `FETCH_XXX` is called from a client, specifying a count value greater than 1 can result in fewer server round trips and, therefore, improved performance.

For heterogeneous object types, a single `FETCH_XXX` operation only returns objects of a single object type.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)

Syntax

```
DBMS_METADATA.SET_COUNT (
    handle          IN NUMBER,
    value           IN NUMBER,
    object_type_path IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 50–15 *SET_COUNT Procedure Parameters*

Parameter	Description
handle	The handle returned from <code>OPEN</code> .
value	The maximum number of objects to retrieve.
object_type_path	<p>A path name designating the object types to which the count value applies. By default, the count value applies to the object type of the <code>OPEN</code> handle. When the <code>OPEN</code> handle designates a heterogeneous object type, behavior can be either of the following:</p> <ul style="list-style-type: none"> ▪ if <code>object_type_path</code> is omitted, the count applies to all object types within the heterogeneous collection ▪ if <code>object_type_path</code> is specified, the count only applies to the specific node (or set of nodes) within the tree of object types forming the heterogeneous collection

Exceptions

- **INVALID_ARGVAL.** A NULL or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- **INVALID_OPERATION.** SET_COUNT was called after the first call to FETCH_xxx for the OPEN context. After the first call to FETCH_xxx is made, no further calls to SET_COUNT for the current OPEN context are permitted.
- **INCONSISTENT_ARGS.** object_type parameter is not consistent with handle.

SET_FILTER Procedure

This procedure specifies restrictions on the objects to be retrieved, for example, the object name or schema.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)

Syntax

```
DBMS_METADATA.SET_FILTER (
  handle          IN NUMBER,
  name            IN VARCHAR2,
  value          IN VARCHAR2,
  object_type_path IN VARCHAR2 DEFAULT NULL);
```

```
DBMS_METADATA.SET_FILTER (
  handle          IN NUMBER,
  name            IN VARCHAR2,
  value          IN BOOLEAN DEFAULT TRUE,
  object_type_path IN VARCHAR2 DEFAULT NULL);
```

```
DBMS_METADATA.SET_FILTER (
  handle          IN NUMBER,
  name            IN VARCHAR2,
  value          IN NUMBER,
  object_type_path IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 50–16 *SET_FILTER Procedure Parameters*

Parameter	Description
handle	The handle returned from OPEN.

Table 50–16 (Cont.) SET_FILTER Procedure Parameters

Parameter	Description
name	<p>The name of the filter. For each filter, Table 50–17 lists the <code>object_type</code> it applies to, its name, its datatype (text or Boolean) and its meaning or effect (including its default value, if any).</p> <p>The Datatype column of Table 50–17 also indicates whether a text filter is an expression filter. An expression filter is the right-hand side of a SQL comparison (that is, a SQL comparison operator (=, !=, and so on.)) and the value compared against. The value must contain parentheses and quotation marks where appropriate. Note that in PL/SQL and SQL*Plus, two single quotes (<i>not</i> a double quote) are needed to represent an apostrophe. For example, an example of a <code>NAME_EXPR</code> filter in PL/SQL is as follows:</p> <pre>' IN ('DEPT' , 'EMP')'</pre> <p>The filter value is combined with a particular object attribute to produce a <code>WHERE</code> condition in the query that fetches the objects. In the preceding example, the filter is combined with the attribute corresponding to an object name; objects named <code>'DEPT'</code> and <code>'EMP'</code> are selected.</p>
value	The value of the filter. Text, Boolean, and Numeric filters are supported.
object_type_path	A path name designating the object types to which the filter applies. By default, the filter applies to the object type of the <code>OPEN</code> handle. When the <code>OPEN</code> handle designates a heterogeneous object type, you can use this parameter to specify a filter for a specific node or set of nodes within the tree of object types that form the heterogeneous collection. See Table 50–18 for a listing of some of the values for this parameter.

Table 50-17 describes the object type, name, datatype, and meaning of the filters available with the `SET_FILTER` procedure.

Table 50-17 *SET_FILTER: Filters*

Object Type	Name	Datatype	Meaning
Named objects	NAME	text	Objects with this exact name are selected.
Named objects	NAME_EXPR	text expression	The filter value is combined with the object attribute corresponding to the object name to produce a <code>WHERE</code> condition in the query that fetches the objects. In the preceding example, objects named <code>DEPT</code> and <code>EMP</code> are retrieved. By default, all named objects of <code>object_type</code> are selected.
Named objects	EXCLUDE_NAME_EXPR	text expression	The filter value is combined with the attribute corresponding to the object name to specify objects that are to be excluded from the set of objects fetched. By default, all named objects of the object type are selected.
Schema objects	SCHEMA	text	Objects in this schema are selected. If the object type is <code>SYNONYM</code> , specify <code>PUBLIC</code> to select public synonyms.
Schema objects	SCHEMA_EXPR	text expression	The filter value is combined with the attribute corresponding to the object's schema. The default is determined as follows: - if <code>BASE_OBJECT_SCHEMA</code> is specified, then objects in that schema are selected; - otherwise, objects in the current schema are selected.
PACKAGE, TYPE	SPECIFICATION	Boolean	If <code>TRUE</code> , retrieve the package or type specification. Defaults to <code>TRUE</code> .
PACKAGE, TYPE	BODY	Boolean	If <code>TRUE</code> , retrieve the package or type body. Defaults to <code>TRUE</code> .

Table 50–17 (Cont.) SET_FILTER: Filters

Object Type	Name	Datatype	Meaning
TABLE, CLUSTER, INDEX, TABLE_DATA, TABLE_EXPORT, TRANSPORTABLE_EXPORT	TABLESPACE	text	Objects in this tablespace (or having a partition in this tablespace) are selected.
TABLE, CLUSTER, INDEX, TABLE_DATA, TABLE_EXPORT, TRANSPORTABLE_EXPORT	TABLESPACE_EXPR	text expression	The filter value is combined with the attribute corresponding to the object's tablespace (or in the case of a partitioned table or index, the partition's tablespaces). By default, objects in all tablespaces are selected.
TABLE, objects dependent on tables	PRIMARY	Boolean	If TRUE, retrieve primary tables (that is, tables for which the secondary object bit in <code>obj\$</code> is clear. Defaults to TRUE.
TABLE, objects dependent on tables	SECONDARY	Boolean	If TRUE, retrieve secondary tables (that is, tables for which the secondary object bit in <code>obj\$</code> is set). Defaults to TRUE.
Dependent Objects	BASE_OBJECT_NAME	text	Objects are selected that are defined or granted on objects with this name. Specify SCHEMA for triggers on schemas. Specify DATABASE for database triggers. Column-level comments cannot be selected by column name; the base object name must be the name of the table, view, or materialized view containing the column.
Dependent Objects	BASE_OBJECT_SCHEMA	text	Objects are selected that are defined or granted on objects in this schema. If BASE_OBJECT_NAME is specified with a value other than SCHEMA or DATABASE, this defaults to the current schema.
Dependent Objects	BASE_OBJECT_NAME_EXPR	text expression	The filter value is combined with the attribute corresponding to the name of the base object. Not valid for schema and database triggers.
Dependent Objects	EXCLUDE_BASE_OBJECT_NAME_EXPR	text expression	The filter value is combined with the attribute corresponding to the name of the base object to specify objects that are to be excluded from the set of objects fetched. Not valid for schema and database triggers.
Dependent Objects	BASE_OBJECT_SCHEMA_EXPR	text expression	The filter value is combined with the attribute corresponding to the schema of the base object.

Table 50–17 (Cont.) SET_FILTER: Filters

Object Type	Name	Datatype	Meaning
Dependent Objects	BASE_OBJECT_ TYPE	text	The object type of the base object.
Dependent Objects	BASE_OBJECT_ TYPE_EXPR	text expression	The filter value is combined with the attribute corresponding to the object type of the base object. By default no filtering is done on object type.
Dependent Objects	BASE_OBJECT_ TABLESPACE	text	The tablespace of the base object.
Dependent Objects	BASE_OBJECT_ TABLESPACE_ EXPR	text expression	The filter value is combined with the attribute corresponding to the tablespaces of the base object. By default, no filtering is done on the tablespace.
INDEX, TRIGGER	SYSTEM_ GENERATED	Boolean	If TRUE, select indexes or triggers even if they are system-generated. If FALSE, omit system-generated indexes or triggers. Defaults to TRUE.
Granted Objects	GRANTEE	text	Objects are selected that are granted to this user or role. Specify PUBLIC for grants to PUBLIC.
Granted Objects	PRIVNAME	text	The name of the privilege or role to be granted. For TABLESPACE_QUOTA, only UNLIMITED can be specified.
Granted Objects	PRIVNAME_EXPR	text expression	The filter value is combined with the attribute corresponding to the privilege or role name. By default, all privileges/roles are returned.
Granted Objects	GRANTEE_EXPR	text expression	The filter value is combined with the attribute corresponding to the grantee name.
Granted Objects	EXCLUDE_ GRANTEE_EXPR	text expression	The filter value is combined with the attribute corresponding to the grantee name to specify objects that are to be excluded from the set of objects fetched.
OBJECT_GRANT	GRANTOR	text	Object grants are selected that are granted by this user.
SYNONYM, JAVA_ SOURCE, XMLSCHEMA	LONGNAME	text	A name longer than 30 characters. Objects with this exact name are selected. If the object name is 30 characters or less, the NAME filter must be used.
SYNONYM, JAVA_ SOURCE, XMLSCHEMA	LONGNAME_EXPR	text	The filter value is combined with the attribute corresponding to the object's long name. By default, no filtering is done on the long name of an object.

Table 50–17 (Cont.) SET_FILTER: Filters

Object Type	Name	Datatype	Meaning
All objects	CUSTOM_FILTER	text	<p>The text of a <code>WHERE</code> condition. The condition is appended to the query that fetches the objects. By default, no custom filter is used.</p> <p>The other filters are intended to meet the needs of the majority of users. Use <code>CUSTOM_FILTER</code> when no defined filters exists for your purpose. Of necessity such a filter depends on the detailed structure of the UDTs and views used in the query. Because filters may change from version to version, upward compatibility is not guaranteed.</p>
SCHEMA_EXPORT	SCHEMA	text	The schema whose objects are selected.
SCHEMA_EXPORT	SCHEMA_EXPR	text expression	<p>The filter value is either:</p> <ul style="list-style-type: none"> ■ combined with the attribute corresponding to a schema name to produce a <code>WHERE</code> condition in the query that fetches schema objects, ■ combined with the attribute corresponding to a base schema name to produce a <code>WHERE</code> condition in the query that fetches dependent objects. <p>By default the current user's objects are selected.</p>
SCHEMA_EXPORT	INCLUDE_USER	Boolean	<p>If <code>TRUE</code>, retrieve objects containing privileged information about the user. For example, <code>USER</code>, <code>PASSWORD_HISTORY</code>, <code>TABLESPACE_QUOTA</code>.</p> <p>Defaults to <code>FALSE</code>.</p>
TABLE_EXPORT	SCHEMA	text	Objects (tables and their dependent objects) in this schema are selected.
TABLE_EXPORT	SCHEMA_EXPR	text expression	<p>The filter value is either:</p> <ul style="list-style-type: none"> ■ combined with the attribute corresponding to a schema name to produce a <code>WHERE</code> condition in the query that fetches the tables, ■ combined with the attribute corresponding to a base schema name to produce a <code>WHERE</code> condition in the query that fetches the tables' dependent objects. <p>By default the current user's objects are selected.</p>
TABLE_EXPORT	NAME	text	The table with this exact name is selected along with its dependent objects.

Table 50–17 (Cont.) SET_FILTER: Filters

Object Type	Name	Datatype	Meaning
TABLE_EXPORT	NAME_EXPR	text expression	The filter value is combined with the attribute corresponding to a table name in the queries that fetch tables and their dependent objects. By default all tables in the selected schemas are selected, along with their dependent objects.
Heterogeneous objects	BEGIN_WITH	text	The fully qualified path name of the first object type in the heterogeneous collection to be retrieved. Objects normally fetched prior to this object type will not be retrieved.
Heterogeneous objects	BEGIN_AFTER	text	The fully qualified path name of an object type after which the heterogeneous retrieval should begin. Objects of this type will not be retrieved, nor will objects normally fetched prior to this object type.
Heterogeneous objects	END_BEFORE	text	The fully qualified path name of an object type where the heterogeneous retrieval should end. Objects of this type will not be retrieved, nor will objects normally fetched after this object type.
Heterogeneous objects	END_WITH	text	The fully qualified path name of the last object type in the heterogeneous collection to be retrieved. Objects normally fetched after this object type will not be retrieved.
Heterogeneous objects	INCLUDE_PATH_EXPR, EXCLUDE_PATH_EXPR	text expression	For these two filters, the filter value is combined with the attribute corresponding to an object type path name to produce a WHERE condition in the query that fetches the object types belonging to the heterogeneous collection. Objects of types satisfying this condition are included (INCLUDE_PATH_EXPR) or excluded (EXCLUDE_PATH_EXPR) from the set of object types fetched. Path names in the filter value do not have to be fully qualified. See Table 50–18 for valid path names that can be used with these filters. BEGIN_WITH, BEGIN_AFTER, END_BEFORE, END_WITH, INCLUDE_PATH_EXPR, and EXCLUDE_PATH_EXPR all restrict the set of object types in the heterogeneous collection. By default, objects of all object types in the heterogeneous collection are retrieved.

Usage Notes

- Each call to `SET_FILTER` causes a `WHERE` condition to be added to the underlying query that fetches the set of objects. The `WHERE` conditions are ANDed together, so you can use multiple `SET_FILTER` calls to refine the set of objects to be returned. For example to specify that you want the object named `EMP` in schema `SCOTT`, do the following:

```
SET_FILTER(handle, 'SCHEMA', 'SCOTT');  
SET_FILTER(handle, 'NAME', 'EMP');
```

- You can use the same text expression filter multiple times with different values. All the filter conditions will be applied to the query. For example, to get objects with names between `Felix` and `Oscar`, do the following:

```
SET_FILTER(handle, 'NAME_EXPR', '>= ' 'FELIX' ');  
SET_FILTER(handle, 'NAME_EXPR', '<= ' 'OSCAR' ');
```

- With `SET_FILTER`, you can specify the schema of objects to be retrieved, but security considerations may override this specification. If the caller is `SYS` or has `SELECT_CATALOG_ROLE`, then any object can be retrieved; otherwise, only the following can be retrieved:
 - Schema objects owned by the current user
 - Public synonyms
 - System privileges granted to the current user or to `PUBLIC`
 - Grants on objects for which the current user is owner, grantor, or grantee (either explicitly or as `PUBLIC`).
 - `SCHEMA_EXPORT` where the name is the current user
 - `TABLE_EXPORT` where `SCHEMA` is the current user

If you request objects that you are not privileged to retrieve, no exception is raised; the object is not retrieved, as if it did not exist.

In stored procedures, functions, and definers-rights packages, roles (such as `SELECT_CATALOG_ROLE`) are disabled. Therefore, such a PL/SQL program can only fetch metadata for objects in its own schema. If you want to write a PL/SQL program that fetches metadata for objects in a different schema (based on the invoker's possession of `SELECT_CATALOG_ROLE`), you must make the program invokers-rights.

- For heterogeneous object types, the `BEGIN_WITH` and `BEGIN_AFTER` filters allow restart on an object type boundary. Appropriate filter values are returned by the `FETCH_XML_CLOB` procedure.

Filters on heterogeneous objects provide default values for filters on object types within the collection. You can override this default for a particular object type by specifying the appropriate filter for the specific object type path. For example, for `SCHEMA_EXPORT` the `NAME` filter specifies the schema to be fetched including all the tables in the schema, but you can further restrict this set of tables by supplying a `NAME_EXPR` filter explicitly for the `TABLE` object type path. [Table 50–18](#) lists valid object type path names for the major heterogeneous object types along with an explanation of the scope of each path name. (See [Table 50–17](#) for filters defined for each path name.) These path names are valid in the `INCLUDE_PATH_EXPR` and `EXCLUDE_PATH_EXPR` filters. Path names marked with an asterisk (*) are *only* valid in those filters; they cannot be used as values of the `SET_FILTER object_type_path` parameter.

Table 50–18 Object Type Path Names for Heterogeneous Object Types

Heterogeneous Type	Path Name (*=valid only in xxx_PATH_EXPR)	Scope
TABLE_EXPORT	AUDIT_OBJ	Object audits on the selected tables
TABLE_EXPORT	COMMENT	Table and column comments for the selected tables
TABLE_EXPORT	CONSTRAINT	Constraints (including referential constraints) on the selected tables
TABLE_EXPORT	*GRANT	Object grants on the selected tables
TABLE_EXPORT	INDEX	Indexes (including domain indexes) on the selected tables
TABLE_EXPORT	OBJECT_GRANT	Object grants on the selected tables
TABLE_EXPORT	REF_CONSTRAINT	Referential (foreign key) constraints on the selected tables
TABLE_EXPORT	STATISTICS	Statistics on the selected tables
TABLE_EXPORT	TABLE_DATA	Row data for the selected tables
TABLE_EXPORT	TRIGGER	Triggers on the selected tables
SCHEMA_EXPORT	ASSOCIATION	Statistics type associations for objects in the selected schemas
SCHEMA_EXPORT	AUDIT_OBJ	Audits on all objects in the selected schemas
SCHEMA_EXPORT	CLUSTER	Clusters in the selected schemas and their indexes
SCHEMA_EXPORT	COMMENT	Comments on all objects in the selected schemas

Table 50–18 (Cont.) Object Type Path Names for Heterogeneous Object Types

Heterogeneous Type	Path Name (*=valid only in xxx_PATH_EXPR)	Scope
SCHEMA_EXPORT	CONSTRAINT	Constraints (including referential constraints) on all objects in the selected schemas
SCHEMA_EXPORT	DB_LINK	Private database links in the selected schemas
SCHEMA_EXPORT	DEFAULT_ROLE	Default roles granted to users associated with the selected schemas
SCHEMA_EXPORT	DIMENSION	Dimensions in the selected schemas
SCHEMA_EXPORT	FUNCTION	Functions in the selected schemas and their dependent grants and audits
SCHEMA_EXPORT	*GRANT	Grants on objects in the selected schemas
SCHEMA_EXPORT	INDEX	Indexes (including domain indexes) on tables and clusters in the selected schemas
SCHEMA_EXPORT	INDEXTYPE	Indextypes in the selected schemas and their dependent grants and audits
SCHEMA_EXPORT	JAVA_SOURCE	Java sources in the selected schemas and their dependent grants and audits
SCHEMA_EXPORT	JOB	Jobs in the selected schemas
SCHEMA_EXPORT	LIBRARY	External procedure libraries in the selected schemas
SCHEMA_EXPORT	MATERIALIZED_VIEW	Materialized views in the selected schemas
SCHEMA_EXPORT	MATERIALIZED_VIEW_LOG	Materialized view logs on tables in the selected schemas
SCHEMA_EXPORT	OBJECT_GRANT	Grants on objects in the selected schemas
SCHEMA_EXPORT	OPERATOR	Operators in the selected schemas and their dependent grants and audits
SCHEMA_EXPORT	PACKAGE	Packages (both specification and body) in the selected schemas, and their dependent grants and audits
SCHEMA_EXPORT	PACKAGE_BODY	Package bodies in the selected schemas
SCHEMA_EXPORT	PACKAGE_SPEC	Package specifications in the selected schemas
SCHEMA_EXPORT	PASSWORD_HISTORY	The password history for users associated with the selected schemas

Table 50–18 (Cont.) Object Type Path Names for Heterogeneous Object Types

Heterogeneous Type	Path Name (*=valid only in xxx_PATH_EXPR)	Scope
SCHEMA_EXPORT	PROCEDURE	Procedures in the selected schemas and their dependent grants and audits
SCHEMA_EXPORT	REF_CONSTRAINT	Referential (foreign key) constraints on tables in the selected schemas
SCHEMA_EXPORT	REFRESH_GROUP	Refresh groups in the selected schemas
SCHEMA_EXPORT	SEQUENCE	Sequences in the selected schemas and their dependent grants and audits
SCHEMA_EXPORT	STATISTICS	Statistics on tables and indexes in the selected schemas
SCHEMA_EXPORT	SYNONYM	Private synonyms in the selected schemas
SCHEMA_EXPORT	TABLE	Tables in the selected schemas and their dependent objects (indexes, constraints, triggers, grants, audits, comments, table data, and so on)
SCHEMA_EXPORT	TABLE_DATA	Row data for tables in the selected schemas
SCHEMA_EXPORT	TABLESPACE_QUOTA	Tablespace quota granted to users associated with the selected schemas
SCHEMA_EXPORT	TRIGGER	Triggers on tables in the selected schemas
SCHEMA_EXPORT	TYPE	Types (both specification and body) in the selected schemas, and their dependent grants and audits
SCHEMA_EXPORT	TYPE_BODY	Type bodies in the selected schemas
SCHEMA_EXPORT	TYPE_SPEC	Type specifications in the selected schemas
SCHEMA_EXPORT	USER	User definitions for users associated with the selected schemas
SCHEMA_EXPORT	VIEW	Views in the selected schemas and their dependent objects (grants, constraints, comments, audits)
DATABASE_EXPORT	ASSOCIATION	Statistics type associations for objects in the database
DATABASE_EXPORT	AUDIT	Audits of SQL statements
DATABASE_EXPORT	AUDIT_OBJ	Audits on all objects in the database
DATABASE_EXPORT	CLUSTER	Clusters and their indexes
DATABASE_EXPORT	COMMENT	Comments on all objects
DATABASE_EXPORT	CONSTRAINT	Constraints (including referential constraints)

Table 50–18 (Cont.) Object Type Path Names for Heterogeneous Object Types

Heterogeneous Type	Path Name (*=valid only in xxx_PATH_EXPR)	Scope
DATABASE_EXPORT	CONTEXT	Application contexts
DATABASE_EXPORT	DB_LINK	Private and public database links
DATABASE_EXPORT	DEFAULT_ROLE	Default roles granted to users in the database
DATABASE_EXPORT	DIMENSION	Dimensions in the database
DATABASE_EXPORT	DIRECTORY	Directory objects in the database
DATABASE_EXPORT	FGA_POLICY	Fine-grained audit policies
DATABASE_EXPORT	FUNCTION	Functions
DATABASE_EXPORT	* GRANT	Object and system grants
DATABASE_EXPORT	INDEX	Indexes (including domain indexes) on tables and clusters
DATABASE_EXPORT	INDEXTYPE	Indextypes and their dependent grants and audits
DATABASE_EXPORT	JAVA_SOURCE	Java sources and their dependent grants and audits
DATABASE_EXPORT	JOB	Jobs
DATABASE_EXPORT	LIBRARY	External procedure libraries
DATABASE_EXPORT	MATERIALIZED_VIEW	Materialized views
DATABASE_EXPORT	MATERIALIZED_VIEW_LOG	Materialized view logs
DATABASE_EXPORT	OBJECT_GRANT	All object grants in the database
DATABASE_EXPORT	OPERATOR	Operators and their dependent grants and audits
DATABASE_EXPORT	PACKAGE	Packages (both specification and body) and their dependent grants and audits
DATABASE_EXPORT	PACKAGE_BODY	Package bodies
DATABASE_EXPORT	PACKAGE_SPEC	Package specifications
DATABASE_EXPORT	PASSWORD_HISTORY	Password histories for database users
DATABASE_EXPORT	*PASSWORD_VERIFY_FUNCTION	The password complexity verification function
DATABASE_EXPORT	PROCEDURE	Procedures and their dependent grants and objects
DATABASE_EXPORT	PROFILE	Profiles

Table 50–18 (Cont.) Object Type Path Names for Heterogeneous Object Types

Heterogeneous Type	Path Name (*=valid only in xxx_PATH_EXPR)	Scope
DATABASE_EXPORT	PROXY	Proxy authentications
DATABASE_EXPORT	REF_CONSTRAINT	Referential (foreign key) constraints on tables in the database
DATABASE_EXPORT	REFRESH_GROUP	Refresh groups
DATABASE_EXPORT	*RESOURCE_COST	Resource cost information
DATABASE_EXPORT	RLS_CONTEXT	Fine-grained access-control driving contexts
DATABASE_EXPORT	RLS_GROUP	Fine-grained access-control policy groups
DATABASE_EXPORT	RLS_POLICY	Fine-grained access-control policies
DATABASE_EXPORT	ROLE	Roles
DATABASE_EXPORT	ROLE_GRANT	Role grants to users in the database
DATABASE_EXPORT	ROLLBACK_SEGMENT	Rollback segments
DATABASE_EXPORT	*SCHEMA (named object)	Database schemas including for each schema all related and dependent objects: user definitions and their attributes (default roles, role grants, tablespace quotas, and so on), objects in the schema (tables, view, packages, types, and so on), and their dependent objects (grants, audits, indexes, constraints, and so on). The NAME and NAME_EXPR filters can be used with this object type path name to designate the database schemas to be fetched.
DATABASE_EXPORT	SEQUENCE	Sequences
DATABASE_EXPORT	STATISTICS	Statistics on tables and indexes
DATABASE_EXPORT	SYNONYM	Public and private synonyms
DATABASE_EXPORT	SYSTEM_GRANT	System privilege grants
DATABASE_EXPORT	TABLE	Tables and their dependent objects (indexes, constraints, triggers, grants, audits, comments, table data, and so on)
DATABASE_EXPORT	TABLE_DATA	Row data for all tables
DATABASE_EXPORT	TABLESPACE	Tablespace definitions
DATABASE_EXPORT	TABLESPACE_QUOTA	Tablespace quota granted to users in the database
DATABASE_EXPORT	TRIGGER	Triggers on the database, on schemas, and on schema objects
DATABASE_EXPORT	TRUSTED_DB_LINK	Trusted links

Table 50–18 (Cont.) Object Type Path Names for Heterogeneous Object Types

Heterogeneous Type	Path Name (*=valid only in xxx_PATH_EXPR)	Scope
DATABASE_EXPORT	TYPE	Types (both specification and body) and their dependent grants and audits
DATABASE_EXPORT	TYPE_BODY	Type bodies
DATABASE_EXPORT	TYPE_SPEC	Type specifications
DATABASE_EXPORT	USER	User definitions
DATABASE_EXPORT	VIEW	Views

Exceptions

- **INVALID_ARGVAL.** A NULL or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- **INVALID_OPERATION.** SET_FILTER was called after the first call to FETCH_XXX for the OPEN context. After the first call to FETCH_XXX is made, no further calls to SET_FILTER are permitted.
- **INCONSISTENT_ARGS.** The arguments are inconsistent. Possible inconsistencies include the following:
 - filter name not valid for the object type associated with the OPEN context
 - filter name not valid for the object_type_path
 - object_type_path not part of the collection designated by handle
 - filter value is the wrong datatype

SET_PARSE_ITEM Procedure

This procedure enables output parsing and specifies an object attribute to be parsed and returned.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)
- [Subprograms for Submission of XML to the Database](#)

Syntax

The following syntax applies when SET_PARSE_ITEM is used for object retrieval:

```
DBMS_METADATA.SET_PARSE_ITEM (
    handle      IN NUMBER,
    name        IN VARCHAR2,
    object_type IN VARCHAR2 DEFAULT NULL);
```

The following syntax applies when SET_PARSE_ITEM is used for XML submission:

```
DBMS_METADATA.SET_PARSE_ITEM (
    handle      IN NUMBER,
    name        IN VARCHAR2);
```

Parameters

Table 50–19 SET_PARSE_ITEM Procedure Parameters

Parameter	Description
handle	The handle returned from OPEN (or OPENW).
name	The name of the object attribute to be parsed and returned. See Table 50–20 for the attribute object type, name, and meaning.

Table 50–19 (Cont.) SET_PARSE_ITEM Procedure Parameters

Parameter	Description
object_type	<p>Designates the object type to which the parse item applies (this is an object type name, not a path name). By default, the parse item applies to the object type of the OPEN handle. When the OPEN handle designates a heterogeneous object type, behavior can be either of the following:</p> <ul style="list-style-type: none"> ▪ if object_type is omitted, the parse item applies to all object types within the heterogeneous collection ▪ if object_type is specified, the parse item only applies to that specific object type within the collection <p>This parameter only applies when SET_PARSE_ITEM is used for object retrieval.</p>

[Table 50–20](#) describes the object type, name, and meaning of the items available in the SET_PARSE_ITEM procedure.

Table 50–20 SET_PARSE_ITEM: Parse Items

Object Type	Name	Meaning
All objects	VERB	<p>If FETCH_XML_CLOB is called, no value is returned.</p> <p>If FETCH_DDL is called, then for every row in the sys.ku\$_ddl nested table returned by FETCH_DDL the verb in the corresponding ddlText is returned. If the ddlText is a SQL DDL statement, then the SQL verb (for example, CREATE, GRANT, AUDIT) is returned. If the ddlText is a procedure call (for example, DBMS_AQADM.CREATE_QUEUE_TABLE()) then the package.procedure-name is returned.</p>
All objects	OBJECT_TYPE	<p>If FETCH_XML_CLOB is called, an object type name from Table 50–11 is returned.</p> <p>If FETCH_DDL is called and the ddlText is a SQL DDL statement whose verb is CREATE or ALTER, the object type as used in the DDL statement is returned (for example, TABLE, PACKAGE_BODY, and so on). Otherwise, an object type name from Table 50–11 is returned.</p>
Schema objects	SCHEMA	The object schema is returned. If the object is not a schema object, no value is returned.
Named objects	NAME	The object name is returned. If the object is not a named object, no value is returned.

Table 50–20 (Cont.) SET_PARSE_ITEM: Parse Items

Object Type	Name	Meaning
TABLE, TABLE_DATA, INDEX	TABLESPACE	The name of the object's tablespace or, if the object is a partitioned table, the default tablespace is returned. For a TABLE_DATA object, this is always the tablespace where the rows are stored.
TRIGGER	ENABLE	If the trigger is enabled, ENABLE is returned. If the trigger is disabled, DISABLE is returned.
OBJECT_ GRANT, TABLESPACE_ QUOTA	GRANTOR	The grantor is returned.
Dependent objects (including domain index secondary tables)	BASE_OBJECT_NAME	The name of the base object is returned. If the object is not a dependent object, no value is returned.
Dependent objects (including domain index secondary tables)	BASE_OBJECT_SCHEMA	The schema of the base object is returned. If the object is not a dependent object, no value is returned.
Dependent objects (including domain index secondary tables)	BASE_OBJECT_TYPE	The object type of the base object is returned. If the object is not a dependent object, no value is returned.
Granted objects	GRANTEE	The grantee is returned. If the object is not a granted object, no value is returned.

Usage Notes

These notes apply when using SET_PARSE_ITEM to retrieve objects.

By default, the FETCH_XXX routines return an object's metadata as XML or creation DDL. By calling SET_PARSE_ITEM you can request that individual attributes of the object be returned as well.

You can call `SET_PARSE_ITEM` multiple times to ask for multiple items to be parsed and returned. Parsed items are returned in the `sys.ku$_parsed_items` nested table.

For `TABLE_DATA` objects, the following parse item return values are of interest:

If Object Is	NAME, SCHEMA	BASE_OBJECT_NAME, BASE_OBJECT_SCHEMA
nonpartitioned table	table name, schema	table name, schema
table partition	partition name, schema	table name, schema
nested table	storage table name, schema	name and schema of top-level table (<i>not</i> the parent nested table)

Tables are not usually thought of as dependent objects. However, secondary tables for domain indexes are dependent on the domain indexes. Consequently, the `BASE_OBJECT_NAME`, `BASE_OBJECT_SCHEMA` and `BASE_OBJECT_TYPE` parse items for secondary `TABLE` objects return the name, schema, and type of the domain index.

See Also:

- ["FETCH_xxx Functions"](#) on page 50-16
- *Oracle Database Utilities* for information about using the Metadata API

By default, the `CONVERT` and `PUT` procedures simply transform an object's XML metadata to DDL. By calling `SET_PARSE_ITEM` you can request that individual attributes of the object be returned as well.

Exceptions

- `INVALID_ARGVAL`. A `NULL` or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INVALID_OPERATION`. `SET_PARSE_ITEM` was called after the first call to `FETCH_xxx` for the `OPEN` context. After the first call to `FETCH_xxx` is made, no further calls to `SET_PARSE_ITEM` are permitted.
- `INCONSISTENT_ARGS`. The attribute name is not valid for the object type associated with the `OPEN` context.

SET_TRANSFORM_PARAM and SET_REMAP_PARAM Procedures

SET_TRANSFORM_PARAM and SET_REMAP_PARAM specify parameters to the XSLT stylesheet identified by transform_handle. Use them to modify or customize the output of the transform.

See Also: For more information about related subprograms:

- [Subprograms for Retrieval of Multiple Objects from the Database](#)
- [Subprograms for Submission of XML to the Database](#)

Syntax

```
DBMS_METADATA.SET_TRANSFORM_PARAM (
    transform_handle IN NUMBER,
    name             IN VARCHAR2,
    value            IN VARCHAR2),
object_type        IN VARCHAR2 DEFAULT NULL);
```

```
DBMS_METADATA.SET_TRANSFORM_PARAM (
    transform_handle IN NUMBER,
    name             IN VARCHAR2,
    value            IN BOOLEAN DEFAULT TRUE),
object_type        IN VARCHAR2 DEFAULT NULL);
```

```
DBMS_METADATA.SET_TRANSFORM_PARAM (
    transform_handle IN NUMBER,
    name             IN VARCHAR2,
    value            IN NUMBER,
    object_type      IN VARCHAR2 DEFAULT NULL);
```

```
DBMS_METADATA.SET_REMAP_PARAM (
    transform_handle IN NUMBER,
    name             IN VARCHAR2,
    old_value        IN VARCHAR2,
    new_value        IN VARCHAR2,
    object_type      IN VARCHAR2 DEFAULT NULL);
```

Parameters

[Table 50-21](#) describes the parameters for the SET_TRANSFORM_PARAM and SET_REMAP_PARAM procedures.

Table 50–21 SET_TRANSFORM_PARAM and SET_REMAP_PARAM Parameters

Parameters	Description
transform_handle	<p>Either (1) the handle returned from <code>ADD_TRANSFORM</code>, or (2) the enumerated constant <code>SESSION_TRANSFORM</code> that designates the DDL transform for the whole session.</p> <p>Note that the handle returned by <code>OPEN</code> is not a valid transform handle.</p> <p>For <code>SET_REMAP_PARAM</code>, the transform handle must designate the <code>MODIFY</code> transform.</p>
name	<p>The name of the parameter. Table 50–22 lists the transform parameters defined for the DDL transform, specifying the <code>object_type</code> it applies to, its datatype, and its meaning or effect. This includes its default value, if any, and whether the parameter is additive.</p> <p>Table 50–23 describes the parameters for the <code>MODIFY</code> transform in the <code>SET_TRANSFORM_PARAM</code> procedure.</p> <p>Table 50–24 describes the parameters for the <code>MODIFY</code> transform in the <code>SET_REMAP_PARAM</code> procedure.</p>
value	The value of the transform. This parameter is valid only for <code>SET_TRANSFORM_PARAM</code> .
old_value	The old value for the remapping. This parameter is valid only for <code>SET_REMAP_PARAM</code> .
new_value	The new value for the remapping. This parameter is valid only for <code>SET_REMAP_PARAM</code> .
object_type	<p>Designates the object type to which the transform or remap parameter applies. By default, it applies to the same object type as the transform. In cases where the transform applies to all object types within a heterogeneous collection, the following apply:</p> <ul style="list-style-type: none"> ■ If <code>object_type</code> is omitted, the parameter applies to all applicable object types within the heterogeneous collection. ■ If <code>object_type</code> is specified, the parameter only applies to that object type. <p>This allows a caller who has added a transform to a heterogeneous collection to specify different transform parameters for different object types within the collection.</p>

Table 50-22 describes the object type, name, datatype, and meaning of the parameters for the DDL transform in the `SET_TRANSFORM_PARAM` procedure.

Table 50-22 *SET_TRANSFORM_PARAM: Transform Parameters for the DDL Transform*

Object Type	Name	Datatype	Meaning
All objects	PRETTY	Boolean	If TRUE, format the output with indentation and line feeds. Defaults to TRUE.
All objects	SQLTERMINATOR	Boolean	If TRUE, append a SQL terminator (; or /) to each DDL statement. Defaults to FALSE.
TABLE	SEGMENT_ATTRIBUTES	Boolean	If TRUE, emit segment attributes (physical attributes, storage attributes, tablespace, logging). Defaults to TRUE.
TABLE	STORAGE	Boolean	If TRUE, emit storage clause. (Ignored if SEGMENT_ATTRIBUTES is FALSE.) Defaults to TRUE.
TABLE	TABLESPACE	Boolean	If TRUE, emit tablespace. (Ignored if SEGMENT_ATTRIBUTES is FALSE.) Defaults to TRUE.
TABLE	CONSTRAINTS	Boolean	If TRUE, emit all non-referential table constraints. Defaults to TRUE.
TABLE	REF_CONSTRAINTS	Boolean	If TRUE, emit all referential constraints (foreign keys). Defaults to TRUE.
TABLE	CONSTRAINTS_AS_ALTER	Boolean	If TRUE, emit table constraints as separate ALTER TABLE (and, if necessary, CREATE INDEX) statements. If FALSE, specify table constraints as part of the CREATE TABLE statement. Defaults to FALSE. Requires that CONSTRAINTS be TRUE.
TABLE	OID	Boolean	If TRUE, emit the OID clause for object tables. Defaults to FALSE.
TABLE	SIZE_BYTE_KEYWORD	Boolean	If TRUE, emit the BYTE keyword as part of the size specification of CHAR and VARCHAR2 columns that use byte semantics. If FALSE, omit the keyword. Defaults to FALSE.
INDEX	SEGMENT_ATTRIBUTES	Boolean	If TRUE, emit segment attributes (physical attributes, storage attributes, tablespace, logging). Defaults to TRUE.

Table 50–22 (Cont.) SET_TRANSFORM_PARAM: Transform Parameters for the DDL Transform

Object Type	Name	Datatype	Meaning
INDEX	STORAGE	Boolean	If TRUE, emit storage clause. (Ignored if SEGMENT_ATTRIBUTES is FALSE.) Defaults to TRUE.
INDEX	TABLESPACE	Boolean	If TRUE, emit tablespace. (Ignored if SEGMENT_ATTRIBUTES is FALSE.) Defaults to TRUE.
TYPE	SPECIFICATION	Boolean	If TRUE, emit the type specification. Defaults to TRUE.
TYPE	BODY	Boolean	If TRUE, emit the type body. Defaults to TRUE.
TYPE	OID	Boolean	If TRUE, emit the OID clause. Defaults to FALSE.
PACKAGE	SPECIFICATION	Boolean	If TRUE, emit the package specification. Defaults to TRUE.
PACKAGE	BODY	Boolean	If TRUE, emit the package body. Defaults to TRUE.
VIEW	FORCE	Boolean	If TRUE, use the FORCE keyword in the CREATE VIEW statement. Defaults to TRUE.
OUTLINE	INSERT	Boolean	If TRUE, emit the INSERT statements into the OLS dictionary tables that will create the outline and its hints. If FALSE, emit a CREATE OUTLINE statement. Defaults to FALSE. Note: This object type is being deprecated.
All objects	DEFAULT	Boolean	Calling SET_TRANSFORM_PARAM with this parameter set to TRUE has the effect of resetting all parameters for the transform to their default values. Setting this FALSE has no effect. There is no default.

Table 50–22 (Cont.) SET_TRANSFORM_PARAM: Transform Parameters for the DDL Transform

Object Type	Name	Datatype	Meaning
All objects	INHERIT	Boolean	If TRUE, inherits session-level parameters. Defaults to FALSE. If an application calls ADD_TRANSFORM to add the DDL transform, then by default the only transform parameters that apply are those explicitly set for that transform handle. This has no effect if the transform handle is the session transform handle.
ROLE	REVOKE_FROM	Text	The name of a user from whom the role must be revoked. If this is a non-null string and if the CREATE ROLE statement grants you the role, a REVOKE statement is emitted after the CREATE ROLE. Note: When you issue a CREATE ROLE statement, Oracle may grant you the role. You can use this transform parameter to undo the grant. Defaults to null string.
TABLESPACE	REUSE	Boolean	If TRUE, include the REUSE parameter for datafiles in a tablespace to indicate that existing files can be reused. Defaults to FALSE.

[Table 50–23](#) describes the object type, name, datatype, and meaning of the parameters for the MODIFY transform in the SET_TRANSFORM_PARAM procedure.

Table 50–23 SET_TRANSFORM_PARAM: Transform Parameters for the MODIFY Transform

Object Type	Name	Datatype	Meaning
All objects	OBJECT_ROW	Number	A number designating the object row for an object. The object in the document that corresponds to this number will be copied to the output document. This parameter is additive. By default, all objects are copied to the output document.

[Table 50-24](#) describes the object type, name, datatype, and meaning of the parameters for the MODIFY transform in the SET_REMAP_PARAM procedure.

Table 50-24 SET_REMAP_PARAM: Transform Parameters for the MODIFY Transform

Object Type	Name	Datatype	Meaning
LIBRARY, TABLESPACE, DIRECTORY	REMAP_DATAFILE	Text	<p>Objects in the document will have their filespecs renamed as follows: any filespec matching <code>old_value</code> will be changed to <code>new_value</code>. Filespecs should <i>not</i> be enclosed in quotes.</p> <p>This parameter is additive.</p> <p>By default, filespecs are not renamed.</p>
Schema Objects, Dependent Objects, Granted Objects, USER	REMAP_SCHEMA	Text	<p>Any schema object in the document whose name matches <code>old_value</code> will have its schema name changed to <code>new_value</code>.</p> <p>Any dependent object whose base object schema name matches <code>old_value</code> will have its base object schema name changed to <code>new_value</code>.</p> <p>Any granted object whose grantee name matches <code>old_value</code> will have its grantee name changed to <code>new_value</code>.</p> <p>Any user whose name matches <code>old_value</code> will have its name changed to <code>new_value</code>.</p> <p>This parameter is additive.</p> <p>By default, schemas are not remapped.</p>
TABLE, CLUSTER, CONSTRAINT, INDEX, ROLLBACK_ SEGMENT, MATERIALIZED _VIEW, MATERIALIZED _VIEW_LOG, TABLESPACE_ QUOTA	REMAP_TABLESPACE	Text	<p>Objects in the document will have their tablespaces renamed as follows: any tablespace name matching <code>old_value</code> will be changed to <code>new_value</code>.</p> <p>This parameter is additive.</p> <p>By default, tablespaces are not remapped.</p>

Exceptions

- `INVALID_ARGVAL`. A `NULL` or invalid value was supplied for an input parameter. The error message text identifies the parameter.
- `INVALID_OPERATION`. Either `SET_TRANSFORM_PARAM` or `SET_REMAP_PARAM` was called after the first call to `FETCH_XXX` for the `OPEN` context. After the first call to `FETCH_XXX` is made, no further calls to `SET_TRANSFORM_PARAM` or `SET_REMAP_PARAM` are permitted.
- `INCONSISTENT_ARGS`. The arguments are inconsistent. This can mean the following:
 - The transform parameter name is not valid for the object type associated with the `OPEN` context or for the transform associated with the transform handle.
 - The transform applies to all object types in a heterogeneous collection, but `object_type` is not part of the collection.

Usage Notes

XSLT allows parameters to be passed to stylesheets. You call `SET_TRANSFORM_PARAM` or `SET_REMAP_PARAM` to specify the value of a parameter to be passed to the stylesheet identified by `transform_handle`.

Normally, if you call `SET_TRANSFORM_PARAMETER` multiple times for the same parameter name, each call overrides the prior call. For example, the following sequence simply sets the `STORAGE` transform parameter to `TRUE`.

```
SET_TRANSFORM_PARAM(tr_handle, 'STORAGE', false);
SET_TRANSFORM_PARAM(tr_handle, 'STORAGE', true);
```

However, some transform parameters are additive which means that all specified parameter values are applied to the document, not just the last one. For example, the `OBJECT_ROW` parameter to the `MODIFY` transform is additive. If you specify the following, then both specified rows are copied to the output document.

```
SET_TRANSFORM_PARAM(tr_handle, 'OBJECT_ROW', 5);
SET_TRANSFORM_PARAM(tr_handle, 'OBJECT_ROW', 8);
```

The `REMAP_TABLESPACE` parameter is also additive. If you specify the following, then tablespaces `TBS1` and `TBS3` are changed to `TBS2` and `TBS4`, respectively.

```
SET_REMAP_PARAM(tr_handle, 'REMAP_TABLESPACE', 'TBS1', 'TBS2');
SET_REMAP_PARAM(tr_handle, 'REMAP_TABLESPACE', 'TBS3', 'TBS4');
```

The order in which the transformations are performed is undefined. For example, if you specify the following, the result is undefined.

```
SET_REMAP_PARAM(tr_handle, 'REMAP_TABLESPACE', 'TBS1', 'TBS2');  
SET_REMAP_PARAM(tr_handle, 'REMAP_TABLESPACE', 'TBS2', 'TBS3');
```

The `GET_DDL`, `GET_DEPENDENT_DDL`, and `GET_GRANTED_DDL` functions allow the casual browser to extract the creation DDL for an object. So that you can specify transform parameters, this package defines an enumerated constant `SESSION_TRANSFORM` as the handle of the DDL transform at the session level. You can call `SET_TRANSFORM_PARAM` using `DBMS_METADATA.SESSION_TRANSFORM` as the transform handle to set transform parameters for the whole session. `GET_DDL`, `GET_DEPENDENT_DDL`, and `GET_GRANTED_DDL` inherit these parameters when they invoke the DDL transform.

Note: The enumerated constant must be prefixed with the package name `DBMS_METADATA.SESSION_TRANSFORM`.

DBMS_MGWADM

DBMS_MGWADM defines the Messaging Gateway administrative interface. The package and object types are owned by SYS.

Note: You must run the `catmgw.sql` script to load the Messaging Gateway packages and types into the database.

See Also: *Oracle Streams Advanced Queuing User's Guide and Reference* contains information on loading database objects and using DBMS_MGWADM

This chapter contains the following topics:

- [Using DBMS_MGWADM](#)
 - [Constants](#)
 - [Types](#)
 - [Properties](#)
 - [Database Views](#)
- [Summary of DBMS_MGWADM Subprograms](#)

Using DBMS_MGWADM

- [Constants](#)
- [Types](#)
- [Properties](#)
- [Database Views](#)

Constants

Table 51-1 DBMS_MGWADM Constants—Propagation Types

Name	Type	Description
OUTBOUND_PROPAGATION	CONSTANT BINARY_INTEGER	Represents the propagation type for Oracle Streams AQ to non-Oracle propagation. The propagation source is a local Oracle Streams AQ queue and the destination is a queue in a foreign (non-Oracle) messaging system.
INBOUND_PROPAGATION	CONSTANT BINARY_INTEGER	Represents the propagation type for non-Oracle to Oracle Streams AQ propagation. The propagation source is a queue in a foreign (non-Oracle) messaging system and the destination is a local Oracle Streams AQ queue.

Table 51-2 DBMS_MGWADM Constants—Queue Domain Types

Name	Type	Description
DOMAIN_QUEUE	CONSTANT BINARY_INTEGER	Represents a queue destination. A JMS queue (point-to-point model) is classified as a queue.
DOMAIN_TOPIC	CONSTANT BINARY_INTEGER	Represents a topic destination. A JMS topic (publish-subscribe model) is classified as a topic.

Table 51–3 DBMS_MGWADM Constants—Force Values

Name	Type	Description
NO_FORCE	CONSTANT BINARY_INTEGER	Represents a normal, nonforced action
FORCE	CONSTANT BINARY_INTEGER	Represents a forced action

Table 51–4 DBMS_MGWADM Constants—Shutdown Modes

Name	Type	Description
SHUTDOWN_NORMAL	CONSTANT BINARY_INTEGER	Represents the normal shutdown mode
SHUTDOWN_IMMEDIATE	CONSTANT BINARY_INTEGER	Represents the immediate shutdown mode

Table 51–5 DBMS_MGWADM Constants—Cleanup Actions

Name	Type	Description
CLEAN_STARTUP_STATE	CONSTANT BINARY_INTEGER	Sets the Messaging Gateway agent to a known state so that it can be started
CLEAN_LOG_QUEUES	CONSTANT BINARY_INTEGER	Messaging Gateway agent will clean log queues for all configured messaging system links.
RESET_SUB_MISSING_LOG_REC	CONSTANT BINARY_INTEGER	Messaging Gateway agent recovers a Messaging Gateway subscriber that has failed due to a missing log record.
RESET_SUB_MISSING_MESSAGE	CONSTANT BINARY_INTEGER	Messaging Gateway agent recovers a Messaging Gateway subscriber that has failed due to a missing persistent source message.

Table 51–6 DBMS_MGWADM Constants—Logging Levels

Name	Type	Description
BASIC_LOGGING	CONSTANT BINARY_INTEGER	Represents the detail of logging information written to the log file. The logging level ranges from BASIC_LOGGING for standard (the least) information to TRACE_DEBUG_LOGGING for the greatest information.
TRACE_LITE_LOGGING	CONSTANT BINARY_INTEGER	
TRACE_HIGH_LOGGING	CONSTANT BINARY_INTEGER	
TRACE_DEBUG_LOGGING	CONSTANT BINARY_INTEGER	

Table 51-7 DBMS_MGWADM Constants—WebSphere MQ Interface Types

Name	Type	Description
MQSERIES_BASE_JAVA_INTERFACE	CONSTANT BINARY_INTEGER	Represents the Base Java interface for the WebSphere MQ messaging system

Table 51-8 DBMS_MGWADM Constants—Named Property Constants

Name	Type	Description
MGWPROP_PREFIX	CONSTANT VARCHAR2	A constant (MGWPROP\$_) for the reserved property name prefix
MGWPROP_REMOVE	CONSTANT VARCHAR2	A constant (MGWPROP\$_REMOVE) for the reserved property name used to remove an existing property
MGWPROP_REMOVE_ALL	CONSTANT VARCHAR2	A constant (MGWPROP\$_REMOVE_ALL) for the reserved property name used to remove all properties

Table 51-9 DBMS_MGWADM Constants—Other Constants

Name	Type	Description
NO_CHANGE	CONSTANT VARCHAR2	Indicates that an existing value should be preserved (not changed). This is used for certain APIs where the desire is to change one or more parameters but leave others unchanged.
JMS_QUEUE_CONNECTION	CONSTANT BINARY_INTEGER	Used to indicate that JMS queue connections will be used to access JMS destinations.
JMS_TOPIC_CONNECTION	CONSTANT BINARY_INTEGER	Used to indicate that JMS topic connections will be used to access JMS destinations.

Types

- [SYS.MGW_PROPERTY Type](#)
- [SYS.MGW_PROPERTIES Type](#)
- [SYS.MGW_MQSERIES_PROPERTIES Type](#)
- [SYS.MGW_TIBRV_PROPERTIES Type](#)

SYS.MGW_PROPERTY Type

This type specifies a named property. `SYS.MGW_PROPERTY` is used to specify optional properties for messaging links, foreign queues, and subscribers.

Syntax

```
TYPE SYS.MGW_PROPERTY IS OBJECT(
    name VARCHAR2(100),
    value VARCHAR2(1000),

    -- Methods
    STATIC FUNCTION CONSTRUCT
    RETURN SYS.MGW_PROPERTY,

    STATIC FUNCTION CONSTRUCT(
        p_name IN VARCHAR2,
        p_value IN VARCHAR2)
    RETURN SYS.MGW_PROPERTY );
```

Attributes

Table 51–10 *SYS.MGW_PROPERTY Attributes*

Attribute	Description
name	Property name
value	Property value

CONSTRUCT Method

This method constructs a new `MGW_PROPERTY` instance. All attributes are assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_PROPERTY;
```

CONSTRUCT Method, Initialized With Given Parameters

This method constructs a new `MGW_PROPERTY` instance initialized using the given parameters.

Syntax

```
STATIC FUNCTION CONSTRUCT(
    p_name    IN VARCHAR2,
    p_value   IN VARCHAR2)
RETURN SYS.MGW_PROPERTY;
```

Parameters

Table 51–11 *SYS.MGW_PROPERTY.CONSTRUCT Initialization Parameters*

Parameter	Description
<code>p_name</code>	Property name
<code>p_value</code>	Property value

SYS.MGW_PROPERTIES Type

This type specifies an array of properties.

Syntax

```
TYPE SYS.MGW_PROPERTIES AS VARRAY (100) OF SYS.MGW_PROPERTY;
```

Usage Notes

Unless noted otherwise, Messaging Gateway uses named properties as follows:

- Names with the `MGWPROP$_` prefix are reserved. They are used for special purposes and are invalid when used as a normal property name.
- A property name can exist only once in a property list; that is, a list can contain only one value for a given name. The name is case-insensitive.
- In general, a property list is order-independent, and the property names may appear in any order. An alter property list is an exception.

- You can use a new property list to alter an existing property list. Each new property modifies the original list in one of the following ways: adds a new property, modifies a property, removes a property, or removes all properties.

The alter list is processed in order, from the first element to the last element. Thus the order in which the elements appear in the alter list is meaningful, especially when the alter list is used to remove properties from an existing list.

The property name and value are used to determine how that element affects the original list. The following rules apply:

- Add or modify property

```
MGW_PROPERTY.NAME = property_name
MGW_PROPERTY.VALUE = property_value
```

If a property of the given name already exists, then the current value is replaced with the new value; otherwise the new property is added to the end of the list.

- Remove property

```
MGW_PROPERTY.NAME = 'MGWPROP$_REMOVE'
MGW_PROPERTY.VALUE = name_of_property_to_remove
```

No action is taken if the property name does not exist in the original list.

- Remove all properties

```
MGW_PROPERTY.NAME = 'MGWPROP$_REMOVE_ALL'
MGW_PROPERTY.VALUE = not used
```

The DBMS_MGWADM package defines constants to represent the reserved property names. See "[WebSphere MQ System Properties](#)" on page 51-12 for more information.

SYS.MGW_MQSERIES_PROPERTIES Type

This type specifies basic properties for a WebSphere MQ messaging system link.

Syntax

```
TYPE SYS.MGW_MQSERIES_PROPERTIES IS OBJECT (
  queue_manager      VARCHAR2(64),
  hostname           VARCHAR2(64),
  port               INTEGER,
  channel            VARCHAR2(64),
  interface_type     INTEGER,
```

```

max_connections    INTEGER,
username          VARCHAR2(64),
password          VARCHAR2(64),
inbound_log_queue VARCHAR2(64),
outbound_log_queue VARCHAR2(64),

-- Methods
STATIC FUNCTION construct
RETURN SYS.MGW_MQSERIES_PROPERTIES,

STATIC FUNCTION alter_construct
RETURN SYS.MGW_MQSERIES_PROPERTIES );

```

Attributes

Table 51–12 *SYS.MGW_MQSERIES_PROPERTIES* Attributes

Attribute	Description
queue_manager	The name of the WebSphere MQ queue manager
hostname	The host on which the WebSphere MQ messaging system resides. If hostname is NULL, then a WebSphere MQ bindings connection is used. If not NULL, then a client connection is used and requires that a port and channel be specified.
port	The port number. This is used only for client connections; that is, when hostname is not NULL.
channel	The channel used when establishing a connection to the queue manager. This is used only for client connections; that is, when hostname is not NULL.
interface_type	The type of messaging interface to use. Values: <ul style="list-style-type: none"> ■ DBMS_MGWADM.MQSERIES_BASE_JAVA_INTERFACE if the WebSphere MQ Base Java interface should be used. ■ DBMS_MGWADM.JMS_QUEUE_CONNECTION if the link is to be used for accessing JMS queues ■ DBMS_MGWADM.JMS_TOPIC_CONNECTION if the link is to be used for accessing JMS topics.
max_connections	The maximum number of messaging connections to the WebSphere MQ messaging system
username	The username used for authentication to the WebSphere MQ messaging system

Table 51–12 (Cont.) SYS.MGW_MQSERIES_PROPERTIES Attributes

Attribute	Description
password	The password used for authentication to the WebSphere MQ messaging system
inbound_log_queue	<p>The name of the WebSphere MQ queue used for propagation recovery purposes when this messaging link is used for inbound propagation; that is, when queues associated with this link serve as a propagation source:</p> <ul style="list-style-type: none"> <li data-bbox="648 496 1310 565">■ For MQSERIES_BASE_JAVA_INTERFACE, this is the name of a physical WebSphere MQ queue created using WebSphere MQ administration tools. <li data-bbox="648 588 1310 657">■ For JMS_QUEUE_CONNECTION interface, this is the name of a physical WebSphere MQ queue created using WebSphere MQ administration tools. <li data-bbox="648 680 1310 835">■ For JMS_TOPIC_CONNECTION interface, this specifies the name of a WebSphere MQ JMS topic. The physical WebSphere MQ queue used by subscribers of that topic must be created using WebSphere MQ administration tools. By default, the physical queue used is <code>SYSTEM.JMS.D.SUBSCRIBER.QUEUE</code>.
outbound_log_queue	<p>The name of the WebSphere MQ queue used for propagation recovery purposes when this messaging link is used for outbound propagation; that is, when queues associated with this link serve as a propagation destination:</p> <ul style="list-style-type: none"> <li data-bbox="648 979 1310 1048">■ For MQSERIES_BASE_JAVA_INTERFACE, this is the name of a physical WebSphere MQ queue created using WebSphere MQ administration tools. <li data-bbox="648 1071 1310 1140">■ For JMS_QUEUE_CONNECTION interface, this is the name of a physical WebSphere MQ queue created using WebSphere MQ administration tools. <li data-bbox="648 1163 1310 1324">■ For JMS_TOPIC_CONNECTION interface, this specifies the name of a WebSphere MQ JMS topic. The physical WebSphere MQ queue used by subscribers of that topic must be created using WebSphere MQ administration tools. By default, the physical queue used is <code>SYSTEM.JMS.D.SUBSCRIBER.QUEUE</code>.

CONSTRUCT Method

This method constructs a new `SYS.MGW_MQSERIES_PROPERTIES` instance. All attributes are assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_MQSERIES_PROPERTIES;
```

ALTER_CONSTRUCT Method

This method constructs a new `SYS.MGW_MQSERIES_PROPERTIES` instance for altering the properties of an existing messaging link. All attributes having a `VARCHAR2` data type are assigned a value of `DBMS_MGWADM.NO_CHANGE`. Attributes of other data types are assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION ALTER_CONSTRUCT
RETURN SYS.MGW_MQSERIES_PROPERTIES;
```

SYS.MGW_TIBRV_PROPERTIES Type

A type that specifies basic properties for a TIB/Rendezvous messaging system link. The Messaging Gateway agent creates a TIB/Rendezvous transport of type `TibrvRvdTransport` for each Messaging Gateway link.

Syntax

```
TYPE SYS.MGW_TIBRV_PROPERTIES IS OBJECT(
    service    VARCHAR2(128),
    daemon     VARCHAR2(128),
    network    VARCHAR2(256),
    cm_name    VARCHAR2(256),
    cm_ledger  VARCHAR2(256),

    -- Methods
    STATIC FUNCTION construct
    RETURN SYS.MGW_TIBRV_PROPERTIES,

    STATIC FUNCTION alter_construct
    RETURN SYS.MGW_TIBRV_PROPERTIES );
```

Attributes

Table 51–13 *SYS.MGW_TIBRV_PROPERTIES Attributes*

Attribute	Description
service	The service parameter for the rvd transport
daemon	The daemon parameter for the rvd transport
network	The network parameter for the rvd transport
cm_name	The CM correspondent name. Reserved for future use.
cm_ledger	The CM ledger file name. Reserved for future use.

CONSTRUCT Function

Constructs a new `SYS.MGW_TIBRV_PROPERTIES` instance. All attributes will be assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION construct
RETURN SYS.MGW_TIBRV_PROPERTIES;
```

ALTER_CONSTRUCT Function

Constructs a new `SYS.MGW_TIBRV_PROPERTIES` instance. This function is useful for altering the properties of an existing messaging link. All attributes having a `VARCHAR2` data type will be assigned a value of `DBMS_MGWADM.NO_CHANGE`. Attributes of other data types will be assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION alter_construct
RETURN SYS.MGW_TIBRV_PROPERTIES;
```

Properties

- [WebSphere MQ System Properties](#)
- [TIB/Rendezvous System Properties](#)
- [Optional Link Configuration Properties](#)
- [Optional Foreign Queue Configuration Properties](#)
- [Optional Subscriber Configuration Properties](#)

WebSphere MQ System Properties

This section summarizes basic and optional properties of WebSphere MQ related to Messaging Gateway links, foreign queues, and subscribers.

See Also: Your WebSphere MQ (MQSeries) documentation for more information

[Table 51-14](#) summarizes the basic configuration properties for a WebSphere MQ messaging link. The table indicates which properties of `SYS.MGW_MQSERIES_PROPERTIES` are optional (NULL allowed), which can be altered, and if alterable, which values can be dynamically changed.

See Also: "[SYS.MGW_MQSERIES_PROPERTIES Type](#)" on page 51-7

Table 51-14 *WebSphere MQ Link Properties*

Attribute	NULL Allowed?	Alter Value?	Dynamic?
queue_manager	no	no	no
hostname	yes (1)	no	no
port	yes (1)	no	no
channel	yes (1)	no	no
interface_type	yes (2)	no	no
max_connections	yes (3)	yes	yes
username	yes	yes	yes
password	yes	yes	yes

Table 51–14 (Cont.) WebSphere MQ Link Properties

Attribute	NULL Allowed?	Alter Value?	Dynamic?
<code>inbound_log_queue</code>	yes (4)	yes(4)	yes
<code>outbound_log_queue</code>	yes (5)	yes(5)	yes

Notes on Table 51–14

1. If `hostname` is `NULL`, then the port and channel must be `NULL`. If the hostname is not `NULL`, then the port and channel must be not `NULL`. If the hostname is `NULL`, then a WebSphere MQ bindings connection is used; otherwise a client connection is used.
2. If `interface_type` is `NULL`, then a default value of `DBMS_MGWADM.MQSERIES_BASE_JAVA_INTERFACE` is used.
3. If `max_connections` is `NULL`, then a default value of 1 is used.
4. Attribute `inbound_log_queue` can be `NULL` if the link is not used for inbound propagation. The log queue can be altered only when no inbound propagation subscriber references the link.
5. Attribute `outbound_log_queue` can be `NULL` if the link is not used for outbound propagation. The log queue can be altered only when no outbound propagation subscriber references the link.

[Table 51–15](#) summarizes the optional configuration properties supported when a WebSphere MQ Base Java interface is used to access the WebSphere MQ messaging system. [Table 51–16](#) summarizes the optional configuration properties supported when a WebSphere MQ JMS interface is used. Each table lists the property name, where that property applies, whether the property can be altered, and if alterable, whether the value can be dynamically changed. Only the properties listed in the tables are supported, and any extra properties will be ignored.

See Also: For more information on optional configuration properties:

- ["Optional Link Configuration Properties"](#) on page 51-16
- ["Optional Foreign Queue Configuration Properties"](#) on page 51-18
- ["Optional Subscriber Configuration Properties"](#) on page 51-19

Table 51–15 *Optional Configuration Properties for WebSphere MQ Base Java*

Property Name	Used For	Alter Value?	Dynamic?
MQ_ccsid	link	yes	no
MQ_ReceiveExit	link	yes	no
MQ_SendExit	link	yes	no
MQ_SecurityExit	link	yes	no
MQ_openOptions	foreign queue	no	no
MsgBatchSize	subscriber	yes	yes

Table 51–16 *Optional Configuration Properties for WebSphere MQ JMS*

Property Name	Used For	Alter Value?	Dynamic?
MQ_ccsid	link	yes	no
MQ_ReceiveExit	link	yes	no
MQ_SendExit	link	yes	no
MQ_SecurityExit	link	yes	no
MQ_ReceiveExitInit	link	yes	no
MQ_SendExitInit	link	yes	no
MQ_SecurityExitInit	link	yes	no
MQ_BrokerControlQueue	link	yes	no
MQ_BrokerPubQueue	link	yes	no
MQ_BrokerQueueManager	link	yes	no
MQ_BrokerVersion	link	yes	no
MQ_PubAckInterval	link	yes	no
MQ_JmsDurSubQueue	link	no	no
MQ_JmsTargetClient	foreign queue	no	no
MQ_JmsDurSubQueue	foreign queue	no	no
MsgBatchSize	subscriber	yes	yes
JMS_NoLocal	subscriber	no	no
JMS_DeliveryMode	subscriber	yes	yes

TIB/Rendezvous System Properties

This section summarizes basic and optional configuration properties of TIB/Rendezvous related to Messaging Gateway links, foreign queues and subscribers.

See Also: Your TIB/Rendezvous documentation for more information

Table 51-17 summarizes the basic configuration properties for a TIB/Rendezvous messaging link. It indicates which properties of `SYS.MGW_TIBRV_PROPERTIES` are optional (NULL allowed), which can be altered, and if alterable, which values can be dynamically changed.

See Also: "`SYS.MGW_TIBRV_PROPERTIES Type`" on page 51-10

Table 51-17 *TIB/Rendezvous Link Properties*

Attribute	NULL allowed?	Alter value?	Dynamic?
service	yes(1)	no	no
daemon	yes(1)	no	no
network	yes(1)	no	no
cm_name	yes(2)	no	no
cm_ledger	yes(2)	no	no

Notes on Table 51-17:

1. System default values will be used if `service`, `daemon`, or `network` are NULL.
2. The `cm_name` and `cm_ledger` attributes are reserved for future use when TIB/Rendezvous certified messages are supported. At present, a NULL must be specified for these parameters when a TIB/Rendezvous link is configured.

Table 51-18 summarizes the optional configuration properties supported when a TIB/Rendezvous messaging system is used. The table lists the property name, where that property applies, whether the property can be altered, and if alterable, whether the value can be dynamically changed. Only the properties listed in the table are supported, and any extra properties will be ignored.

Table 51–18 *Optional Properties for TIB/Rendezvous*

Property Name	Used For	Alter Value?	Dynamic?
RV_discardAmount	subscriber	yes	no
RV_limitPolicy	subscriber	yes	no
RV_maxEvents	subscriber	yes	no
AQ_MsgProperties	subscriber	yes	yes
MsgBatchSize	subscriber	yes	yes

See Also: For more information on optional configuration properties:

- ["Optional Link Configuration Properties"](#) on page 51-16
- ["Optional Foreign Queue Configuration Properties"](#) on page 51-18
- ["Optional Subscriber Configuration Properties"](#) on page 51-19

Registering a TIB/Rendezvous subject

`DBMS_MGWADM.register_foreign_queue` procedure is used to register a TIB/Rendezvous subject with the Messaging Gateway. The `provider_queue` parameter specifies a TIB/Rendezvous subject name. Wildcards are allowed in the subject name.

Optional Link Configuration Properties

This section describes optional link properties you can specify using the `options` parameter of `DBMS_MGWADM.create_msgsystem_link` and `DBMS_MGWADM.alter_msgsystem_link`. Each listing also indicates which messaging system might use that property.

MQ_BrokerControlQueue

Used by: WebSphere MQ JMS.

This property specifies the name of the broker control queue. It corresponds to WebSphere MQ JMS administration tool property `BROKERCONQ`. The default used by WebSphere MQ is `SYSTEM.BROKER.CONTROL.QUEUE`.

MQ_BrokerPubQueue

Used by: WebSphere MQ JMS

This property specifies the name of the broker publish queue. It corresponds to WebSphere MQ JMS administration tool property `BROKERPUBQ`. The default used by WebSphere MQ is `SYSTEM.BROKER.DEFAULT.STREAM`.

MQ_BrokerQueueManager

Used by: WebSphere MQ JMS

This property specifies the name of the broker queue manager. It corresponds to WebSphere MQ administration tool property `BROKERQMGR`. If not set, then no default will be used.

MQ_BrokerVersion

Used by: WebSphere MQ JMS

This property specifies the broker version number. It corresponds to WebSphere MQ JMS administration tool property `BROKERVER`. The default used by WebSphere MQ is 0.

MQ_ccsid

Used by: WebSphere MQ Base Java and WebSphere MQ JMS

This property specifies the character set identifier to be used. This should be the integer value of the character set (for example, 819) rather than a descriptive string. If it is not set, then the WebSphere MQ default character set 819 is used.

MQ_JmsDurSubQueue

Used by: WebSphere MQ JMS

This property applies to WebSphere MQ JMS topic links only. The `SYS.MGW_MQSERIES_PROPERITES` attributes, `inbound_log_queue` and `outbound_log_queue`, specify the names of WebSphere MQ JMS topics used for propagation logging. This property specifies the name of the WebSphere MQ queue from which durable subscription messages are retrieved by the log topic subscribers. The default queue used by WebSphere MQ is `SYSTEM.JMS.D.SUBSCRIBER.QUEUE`.

MQ_PubAckInterval

Used by: WebSphere MQ JMS

This property specifies the interval, in number of messages, between publish requests that require acknowledgment from the broker. It corresponds to WebSphere MQ JMS administration tool property `PUBACKINT`. The default used by WebSphere MQ is 25.

MQ_ReceiveExit

Used by: WebSphere MQ Base Java and WebSphere MQ JMS

This property specifies the fully qualified Java classname of a class implementing the `MQReceiveExit` interface. This class must be in the `CLASSPATH` of the Messaging Gateway agent. There is no default.

MQ_ReceiveExitInit

Used by: WebSphere MQ JMS

Initialization string that is passed by WebSphere MQ JMS to the constructor of the class specified by `MQ_ReceiveExit`. Corresponds to WebSphere MQ JMS administration tool property `RECEXITINIT`. There is no default.

MQ_SecurityExit

Used by: WebSphere MQ Base Java and WebSphere MQ JMS

This property specifies the fully qualified Java classname of a class implementing the `MQSecurityExit` interface. This class must be in the `CLASSPATH` of the Messaging Gateway agent. There is no default.

MQ_SecurityExitInit

Used by: WebSphere MQ JMS

Initialization string that is passed by WebSphere MQ JMS to the constructor of the class specified by `MQ_SecurityExit`. It corresponds to WebSphere MQ JMS administration tool property `SECEXITINIT`. There is no default.

MQ_SendExit

Used by: WebSphere MQ Base Java and WebSphere MQ JMS

This property specifies the fully qualified Java classname of a class implementing the `MQSendExit` interface. This class must be in the `CLASSPATH` of the Messaging Gateway agent. There is no default.

MQ_SendExitInit

Used by: WebSphere MQ JMS

Initialization string that is passed by WebSphere MQ JMS to the constructor of the class specified by `MQ_SendExit`. It corresponds to WebSphere MQ JMS administration tool property `SENDEXITINIT`. There is no default.

Optional Foreign Queue Configuration Properties

This section describes optional foreign queue properties that you can specify using the `options` parameter of `DBMS_MGWADM.register_foreign_queue`. Each listing also indicates which messaging system might use that property.

MQ_JmsDurSubQueue

Used by: WebSphere MQ JMS

A string representing the name of the WebSphere MQ queue from which durable subscription messages are retrieved by subscribers on this topic. It applies only to WebSphere MQ JMS topics. The default queue used by WebSphere MQ is `SYSTEM.JMS.D.SUBSCRIBER.QUEUE`.

MQ_JmsTargetClient

Used by: WebSphere MQ JMS

Supported values are `TRUE` and `FALSE`. This property is only used for outbound propagation to a JMS queue or topic. `TRUE` indicates that WebSphere MQ should store the message as a JMS message. `FALSE` indicates that WebSphere MQ should store the message in non-JMS format so that non-JMS applications can access it. Default is `TRUE`.

MQ_openOptions

Used by: WebSphere MQ Base Java

This property specifies the value used for the `openOptions` argument of the WebSphere MQ Base Java `MQQueueManager.accessQueue` method. No value is required. But if one is given, then the Messaging Gateway agent adds `MQOO_OUTPUT` to the specified value for an `enqueue (put)` operation. `MQOO_INPUT_SHARED` is added for a `dequeue (get)` operation. The default is `MQOO_OUTPUT` for an `enqueue/put` operation; `MQOO_INPUT_SHARED` for a `dequeue/get` operation.

Optional Subscriber Configuration Properties

This section describes optional subscriber properties that you can specify using the `options` parameter of `DBMS_MGWADM.add_subscriber` and `DBMS_MGWADM.alter_subscriber`. Each listing also indicates which messaging system might use that property

AQ_MsgProperties

Used by: TIB/Rendezvous

This property specifies how Oracle Streams AQ message properties will be used during message propagation. Supported values are `TRUE` and `FALSE`. The default value is `FALSE`.

For an outbound propagation subscriber, if the value is `TRUE` (case insensitive), then the Messaging Gateway agent will add a field for most Oracle Streams AQ message properties to the message propagated to the TIB/Rendezvous subject.

For an inbound propagation subscriber, if the value is `TRUE` (case insensitive), then the Messaging Gateway agent will search the source message for a field with a reserved name, and if it exists, use its value to set the corresponding Oracle Streams AQ message property. A default value will be used if the field does not exist or does not have an expected datatype.

See Also: *Oracle Streams Advanced Queuing User's Guide and Reference* for the message conversion details

JMS_DeliveryMode

Used by: WebSphere MQ JMS and Oracle JMS.

You can use this property when the propagation destination is a JMS messaging system. It sets the delivery mode of messages enqueued to the propagation destination queue by a `JMS MessageProducer`. Supported values are `PERSISTENT`, `NON_PERSISTENT` and `PRESERVE_MSG`. The default is `PRESERVE_MSG`.

- If its value is `PERSISTENT`, then the delivery mode will be `DeliveryMode.PERSISTENT`.
- If its value is `NON_PERSISTENT`, then the delivery mode will be `DeliveryMode.NON_PERSISTENT`.
- If its value is `PRESERVE_MSG`, then the delivery mode of the source JMS message will be used when the message is propagated to the destination queue.

JMS_NoLocal

Used by: WebSphere MQ JMS and Oracle JMS

You can use this property when the propagation source is a JMS messaging system. It sets the `noLocal` parameter of a `JMS TopicSubscriber`. Supported values are `TRUE` and `FALSE`. The default is `FALSE`.

- `TRUE` indicates that messages that have been published to this topic through the same Messaging Gateway link will not be propagated.
- `FALSE` indicates that such messages will be propagated from the topic.

MsgBatchSize

Used by: any

This property specifies the maximum number of messages, if available, to be propagated in one transaction. The default is 30.

RV_discardAmount

Used by: TIB/Rendezvous

This property specifies the discard amount of a queue. It is meaningful only for an inbound propagation subscriber. The default is 0.

RV_limitPolicy

Used by: TIB/Rendezvous

This property specifies the limit policy for resolving overflow of a queue limit. It is meaningful only for an inbound propagation subscriber. Supported values are DISCARD_NONE, DISCARD_FIRST, DISCARD_LAST and DISCARD_NEW. The default is DISCARD_NONE.

- If its value is DISCARD_NONE, then the limit policy is set to `TibrvQueue.DISCARD_NONE`.
- If its value is DISCARD_FIRST, then the limit policy is set to `TibrvQueue.DISCARD_FIRST`.
- If its value is DISCARD_LAST, then the limit policy is set to `TibrvQueue.DISCARD_LAST`.
- If its value is DISCARD_NEW, then the limit policy is set to `TibrvQueue.DISCARD_NEW`.

RV_maxEvents

Used by: TIB/Rendezvous

This property specifies the maximum event limit of a queue. It is meaningful only for an inbound propagation subscriber. The default is 0.

Database Views

The views listed in [Table 51–19](#) provide Messaging Gateway configuration, status, and statistical information. Unless otherwise indicated, the `SELECT` privilege is granted to `MGW_ADMINISTRATOR_ROLE` so that only Messaging Gateway administrators have access to the views. All views are owned by `SYS`.

Table 51–19 Database Views

Name	Description
MGW_GATEWAY View	Configuration and status information for Messaging Gateway
MGW_LINKS View	Names and types of messaging system links currently created
MGW_MQSERIES_LINKS View	Messaging system properties for WebSphere MQ links
MGW_TIBRV_LINKS View	Messaging system properties for TIB/Rendezvous links
MGW_FOREIGN_QUEUES View	Queue properties of registered queues
MGW_SUBSCRIBERS View	Subscriber properties, status, and statistical information
MGW_SCHEDULES View	Schedule properties and status

MGW_GATEWAY View

This view lists configuration and status information for Messaging Gateway, as shown in [Table 51–20](#).

Table 51–20 *MGW_GATEWAY View Properties*

Name	Type	Description
AGENT_STATUS	VARCHAR2	<p>Status of the Messaging Gateway agent. Values:</p> <ul style="list-style-type: none"> ■ NOT_STARTED means the Messaging Gateway agent has not been started. ■ START_SCHEDULED means Messaging Gateway agent has been scheduled to start. That is, Messaging Gateway has been started using DBMS_MGWADM.STARTUP, but the queued job used to start the Messaging Gateway agent has not yet run. ■ STARTING means Messaging Gateway agent is starting. That is, Messaging Gateway has been started using DBMS_MGWADM.STARTUP, the queued job has run, and the Messaging Gateway agent is starting up. ■ INITIALIZING means the Messaging Gateway agent has started and is initializing. ■ RUNNING means the Messaging Gateway agent is running. ■ SHUTTING_DOWN means the Messaging Gateway agent is shutting down. ■ BROKEN means an unexpected condition has been encountered that prevents the Messaging Gateway agent from starting. DBMS_MGWADM.CLEANUP_GATEWAY must be called before the agent can be started.
AGENT_PING	VARCHAR2	<p>Gateway agent ping status. Values:</p> <ul style="list-style-type: none"> ■ NULL means no ping attempt was made. ■ REACHABLE means ping attempt was successful. ■ UNREACHABLE means ping attempt failed. <p>AGENT_PING attempts to contact the Messaging Gateway agent. There is a short delay (up to 5 seconds) if the ping attempt fails. No ping is attempted if the AGENT_STATUS is NOT_STARTED or START_SCHEDULED.</p>
AGENT_JOB	NUMBER	<p>Job number of the queued job used to start the Messaging Gateway agent process. The job number is set when Messaging Gateway is started and cleared when it shuts down.</p>
AGENT_USER	VARCHAR2	<p>Database username used by the Messaging Gateway agent to connect to the database</p>

Table 51–20 (Cont.) MGW_GATEWAY View Properties

Name	Type	Description
AGENT_DATABASE	VARCHAR2	The database connect string used by the Messaging Gateway agent. NULL indicates that a local connection is used.
LAST_ERROR_DATE	DATE	Date of last Messaging Gateway agent error. The last error information is cleared when Messaging Gateway is started. It is set if the Messaging Gateway agent fails to start or terminates due to an abnormal condition.
LAST_ERROR_TIME	VARCHAR2	Time of last Messaging Gateway agent error
LAST_ERROR_MSG	VARCHAR2	Message for last Messaging Gateway agent error
MAX_CONNECTIONS	NUMBER	Maximum number of messaging connections to Oracle Database
MAX_MEMORY	NUMBER	Maximum heap size used by the Messaging Gateway agent (in MB)
MAX_THREADS	NUMBER	Maximum number of messaging threads created by the Messaging Gateway agent
AGENT_INSTANCE	NUMBER	The database instance on which the Messaging Gateway agent is currently running. This should be NULL if the agent is not running.
AGENT_START_TIME	TIMESTAMP	The time when the Messaging Gateway agent job currently running was started. This should be NULL if the agent is not running.

MGW_LINKS View

This view lists the names and types of messaging system links currently defined. [Table 51–21](#) lists the MGW_LINKS view properties.

Table 51–21 MGW_LINKS View Properties

Name	Type	Description
LINK_NAME	VARCHAR2	Name of the messaging system link
LINK_TYPE	VARCHAR2	Type of messaging system link. MQSERIES is for WebSphere MQ links. TIBRV is for TIB/Rendezvous links.
LINK_COMMENT	VARCHAR2	User comment for the link

MGW_MQSERIES_LINKS View

This view lists information for the WebSphere MQ messaging system links. The view includes most of the messaging system properties specified when the link is created. [Table 51-22](#) lists the MGW_MQSERIES_LINKS view properties.

Table 51-22 *MGW_MQSERIES_LINKS View Properties*

Name	Type	Description
LINK_NAME	VARCHAR2	Name of the messaging system link
QUEUE_MANAGER	VARCHAR2	Name of the WebSphere MQ queue manager
HOSTNAME	VARCHAR2	Name of the WebSphere MQ host
PORT	NUMBER	Port number
CHANNEL	VARCHAR2	Connection channel
INTERFACE_TYPE	VARCHAR2	Messaging interface type. BASE_JAVA is for WebSphere MQ Base Java interface. JMS_QUEUE_CONNECTION is for WebSphere MQ JMS queue connections. JMS_TOPIC_CONNECTION is for WebSphere MQ JMS topic connections.
MAX_CONNECTIONS	NUMBER	Maximum number of messaging connections
INBOUND_LOG_QUEUE	VARCHAR2	Inbound propagation log queue
OUTBOUND_LOG_QUEUE	VARCHAR2	Outbound propagation log queue
OPTIONS	SYS.MGW_PROPERTIES	Link options
LINK_COMMENT	VARCHAR2	User comment for the link

MGW_TIBRV_LINKS View

This view lists information for TIB/Rendezvous messaging system links. The view includes most of the messaging system properties specified when the link was created. [Table 51-23](#) lists the MGW_TIBRV_LINKS view properties.

Table 51-23 MGW_TIBRV_LINKS View Properties

Property Name	Type	Description
LINK_NAME	VARCHAR2	Name of the messaging system link
SERVICE	VARCHAR2	TIB/Rendezvous service parameter for rvd transport
DAEMON	VARCHAR2	TIB/Rendezvous daemon parameter for rvd transport
NETWORK	VARCHAR2	TIB/Rendezvous network parameter for rvd transport
CM_NAME	VARCHAR2	TIB/Rendezvous CM correspondent name
CM_LEDGER	VARCHAR2	TIB/Rendezvous CM ledger file name
OPTIONS	SYS.MGW_PROPERTIES	Link options
LINK_COMMENT	VARCHAR2	User comment for the link

MGW_FOREIGN_QUEUES View

This view lists information for foreign queues. The view includes most of the queue properties specified when the queue is registered. [Table 51-24](#) lists the MGW_FOREIGN_QUEUES view properties.

Table 51-24 MGW_FOREIGN_QUEUES View Properties

Name	Type	Description
NAME	VARCHAR2	Name of the registered queue
LINK_NAME	VARCHAR2	Name of the messaging system link
PROVIDER_QUEUE	VARCHAR2	Message provider (native) queue name
DOMAIN	VARCHAR2	Queue domain type. NULL means the queue domain type is automatically determined by the messaging system. QUEUE is for a queue (point-to-point) model. TOPIC is for a topic (publish-subscribe) model.
OPTIONS	SYS.MGW_PROPERTIES	Optional queue properties
QUEUE_COMMENT	VARCHAR2	User comment for the foreign queue

MGW_SUBSCRIBERS View

This view lists configuration and status information for Messaging Gateway subscribers. The view includes most of the subscriber properties specified when the subscriber is added, as well as other status and statistical information. [Table 51–25](#) lists the MGW_SUBSCRIBERS view properties.

Table 51–25 *MGW_SUBSCRIBERS View Properties*

Name	Type	Description
SUBSCRIBER_ID	VARCHAR2	Propagation subscriber identifier
PROPAGATION_TYPE	VARCHAR2	Propagation type. <code>OUTBOUND</code> is for Oracle Streams AQ to non-Oracle propagation. <code>INBOUND</code> is for non-Oracle to Oracle Streams AQ propagation.
QUEUE_NAME	VARCHAR2	Subscriber source queue
DESTINATION	VARCHAR2	Destination queue to which messages are propagated
RULE	VARCHAR2	Subscription rule
TRANSFORMATION	VARCHAR2	Transformation used for message conversion
EXCEPTION_QUEUE	VARCHAR2	Exception queue used for logging purposes
STATUS	VARCHAR2	Subscriber status. <code>ENABLED</code> means the subscriber is enabled. <code>DELETE_PENDING</code> means subscriber removal is pending, usually because <code>DBMS_MGWADM.REMOVE_SUBSCRIBER</code> has been called but certain cleanup tasks pertaining to this subscriber are still outstanding.
FAILURES	NUMBER	Number of propagation failures
LAST_ERROR_DATE	DATE	Date of last propagation error
LAST_ERROR_TIME	VARCHAR2	Time of last propagation error
LAST_ERROR_MSG	VARCHAR2	Message for last propagation error
PROPAGATED_MSGS	NUMBER	Number of messages propagated to the destination queue since the last time the agent was started
EXCEPTIONQ_MSGS	NUMBER	Number of messages moved to the propagation exception queue since the last time the agent was started
PROP_STYLE	VARCHAR2	Message propagation style. <code>NATIVE</code> is for native message propagation. <code>JMS</code> is for JMS message propagation.
OPTIONS	SYS.MGW_PROPERTIES	Subscriber options

MGW_SCHEDULES View

Table 51–26 *MGW_SCHEDULES View Properties*

Name	Type	Description
SCHEDULE_ID	VARCHAR2	Propagation schedule identifier
PROPAGATION_TYPE	VARCHAR2	Propagation type. OUTBOUND is for Oracle Streams AQ to non-Oracle propagation. INBOUND is for non-Oracle to Oracle Streams AQ propagation.
SOURCE	VARCHAR2	Propagation source
DESTINATION	VARCHAR2	Propagation destination
START_DATE	DATE	Reserved for future use
START_TIME	VARCHAR2	Reserved for future use
PROPAGATION_WINDOW	NUMBER	Reserved for future use
NEXT_TIME	VARCHAR2	Reserved for future use
LATENCY	NUMBER	Propagation window latency (in seconds)
SCHEDULE_DISABLED	VARCHAR2	Indicates whether the schedule is disabled. Y means the schedule is disabled. N means the schedule is enabled.

Summary of DBMS_MGWADM Subprograms

Table 51–27 DBMS_MGWADM Package Subprograms

Subprogram	Description
ADD_SUBSCRIBER Procedure on page 51-31	Adds a subscriber used to consume messages from a source queue for propagation to a destination
ALTER_AGENT Procedure on page 51-35	Alters Messaging Gateway agent parameters
ALTER_MSGSYSTEM_LINK Procedure for TIB/Rendezvous on page 51-36	Alters the properties of a TIB/Rendezvous messaging system link
ALTER_MSGSYSTEM_LINK Procedure for WebSphere MQ on page 51-38	Alters the properties of a WebSphere MQ messaging system link
ALTER_PROPAGATION_SCHEDULE Procedure on page 51-40	Alters a propagation schedule
ALTER_SUBSCRIBER Procedure on page 51-41	Alters the parameters of a subscriber used to consume messages from a source queue for propagation to a destination
CLEANUP_GATEWAY Procedure on page 51-44	Cleans up Messaging Gateway
CREATE_MSGSYSTEM_LINK Procedure for TIB/Rendezvous on page 51-47	Creates a messaging system link to a TIB/Rendezvous messaging system
CREATE_MSGSYSTEM_LINK Procedure for WebSphere MQ on page 51-48	Creates a messaging system link to a WebSphere MQ messaging system
DB_CONNECT_INFO Procedure on page 51-49	Configures connection information used by the Messaging Gateway agent for connections to Oracle Database
DISABLE_PROPAGATION_SCHEDULE Procedure on page 51-50	Disables a propagation schedule
ENABLE_PROPAGATION_SCHEDULE Procedure on page 51-51	Enables a propagation schedule

Table 51–27 (Cont.) DBMS_MGWADM Package Subprograms

Subprogram	Description
REGISTER_FOREIGN_QUEUE Procedure on page 51-52	Registers a non-Oracle queue entity in Messaging Gateway
REMOVE_MSGSYSTEM_LINK Procedure on page 51-54	Removes a messaging system link for a non-Oracle messaging system
REMOVE_SUBSCRIBER Procedure on page 51-55	Removes a subscriber used to consume messages from a source queue for propagation to a destination
RESET_SUBSCRIBER Procedure on page 51-56	Resets the propagation error state for a subscriber
SET_LOG_LEVEL Procedure on page 51-57	Dynamically alters the Messaging Gateway agent logging level
SCHEDULE_PROPAGATION Procedure on page 51-58	Schedules message propagation from a source to a destination
SHUTDOWN Procedure on page 51-60	Shuts down the Messaging Gateway agent
STARTUP Procedure on page 51-61	Starts the Messaging Gateway agent
UNREGISTER_FOREIGN_QUEUE Procedure on page 51-62	Removes a non-Oracle queue entity in Messaging Gateway
UNSCHEDULE_PROPAGATION Procedure on page 51-63	Removes a propagation schedule

ADD_SUBSCRIBER Procedure

This procedure adds a subscriber used to consume messages from a source queue for propagation to a destination.

Syntax

```
DBMS_MGWADM.ADD_SUBSCRIBER(
  subscriber_id      IN VARCHAR2,
  propagation_type  IN BINARY_INTEGER,
  queue_name        IN VARCHAR2,
  destination       IN VARCHAR2,
  rule              IN VARCHAR2 DEFAULT NULL,
  transformation    IN VARCHAR2 DEFAULT NULL,
  exception_queue   IN VARCHAR2 DEFAULT NULL,
  options           IN SYS.MGW_PROPERTIES DEFAULT NULL);
```

Parameters

Table 51–28 *ADD_SUBSCRIBER Procedure Parameters*

Parameter	Description
subscriber_id	Specifies a user-defined name that identifies this subscriber
propagation_type	Specifies the type of message propagation. DBMS_MGWADM.OUTBOUND_PROPAGATION is for Oracle Streams AQ to non-Oracle propagation. DBMS_MGWADM.INBOUND_PROPAGATION is for non-Oracle to Oracle Streams AQ propagation
queue_name	Specifies the source queue to which this subscriber is being added. The syntax and interpretation of this parameter depend on the value specified for propagation_type.
destination	Specifies the destination queue to which messages consumed by this subscriber are propagated. The syntax and interpretation of this parameter depend on the value specified for propagation_type.
rule	Specifies an optional subscription rule used by the subscriber to dequeue messages from the source queue. This is NULL if no rule is needed. The syntax and interpretation of this parameter depend on the value specified for propagation_type.

Table 51–28 (Cont.) ADD_SUBSCRIBER Procedure Parameters

Parameter	Description
<code>transformation</code>	Specifies the transformation needed to convert between the Oracle Streams AQ payload and an ADT defined by Messaging Gateway. The type of transformation needed depends on the value specified for <code>propagation_type</code> . If NULL, then the Oracle Streams AQ payload type must be supported by Messaging Gateway.
<code>exception_queue</code>	Specifies a queue used for exception message logging purposes. This queue must be on the same messaging system as the propagation source. If NULL, then an exception queue is not used and propagation stops if a problem occurs. The syntax and interpretation of this parameter depend on the value specified for <code>propagation_type</code> . The source queue and exception queue cannot be the same queue.
<code>options</code>	Optional subscriber properties. NULL if there are none. Typically these are lesser used configuration properties supported by the messaging system.

Usage Notes

See Also: "Messaging Gateway Message Transformation", in *Oracle Streams Advanced Queuing User's Guide and Reference* for more information regarding message conversion and transformation

If the non-Oracle messaging link being accessed for the subscriber uses a JMS interface, then the Messaging Gateway agent will use the Oracle JMS interface to access the Oracle Streams AQ queues. Otherwise the native Oracle Streams AQ interface will be used. Parameters are interpreted differently when the Messaging Gateway agent uses Oracle JMS for JMS connections.

Transformations are not currently supported if the Oracle JMS interface is used for propagation. The transformation parameter must be NULL.

See Also: For additional information regarding subscriber options

- ["WebSphere MQ System Properties"](#) on page 51-12
- ["TIB/Rendezvous System Properties"](#) on page 51-15

OUTBOUND_PROPAGATION Subscribers

The parameters for a subscriber used for outbound propagation are interpreted as follows:

- `queue_name` specifies the local Oracle Streams AQ queue that is the propagation source. This must have a syntax of `schema.queue`.
- `destination` specifies the foreign queue to which messages are propagated. This must have a syntax of `registered_queue@message_link`.
- `rule` specifies an optional Oracle Streams AQ subscriber rule if the native Oracle Streams AQ interface is used, or a JMS selector if the Oracle JMS interface is used. If `NULL`, then no rule or selector is used.
- `transformation` specifies the transformation used to convert the Oracle Streams AQ payload to an ADT defined by Messaging Gateway.

Messaging Gateway propagation dequeues messages from the Oracle Streams AQ queue using the transformation to convert the Oracle Streams AQ payload to a known ADT defined by Messaging Gateway. The message is then enqueued in the foreign messaging system based on the Messaging Gateway ADT.

- `exception_queue` specifies the name of a local Oracle Streams AQ queue to which messages are moved if an exception occurs. This must have a syntax of `schema.queue`.

If the native Oracle Streams AQ interface is used, then a subscriber will be added to the Oracle Streams AQ queue when this procedure is called, whether or not Messaging Gateway is running. The local subscriber will be of the form `sys.aq$_agent('MGW_subscriber_id', NULL, NULL)`.

If the Oracle JMS interface is used, then the Messaging Gateway agent will create a JMS durable subscriber with the name of `MGW_subscriber_id`. If the agent is not running when this procedure is called, then the durable subscriber will be created the next time the agent starts.

The exception queue has the following caveats:

- The user is responsible for creating the Oracle Streams AQ queue to be used as the exception queue.
- The payload type of the source and exception queue must match.
- The exception queue must be created as a queue type of `DBMS_AQADM.NORMAL_QUEUE` rather than `DBMS_AQADM.EXCEPTION_QUEUE`. Enqueue restrictions prevent Messaging Gateway propagation from using an

Oracle Streams AQ queue of type `EXCEPTION_QUEUE` as a Messaging Gateway exception queue.

INBOUND_PROPAGATION Subscribers

The parameters for a subscriber used for inbound propagation are interpreted as follows:

- `queue_name` specifies the foreign queue that is the propagation source. This must have a syntax of `registered_queue@message_link`.
- `destination` specifies the local Oracle Streams AQ queue to which messages are propagated. This must have a syntax of `schema.queue`.
- `rule` specifies an optional subscriber rule that is valid for the foreign messaging system. This is `NULL` if no rule is needed.
- `transformation` specifies the transformation used to convert an ADT defined by Messaging Gateway to the Oracle Streams AQ payload type.

Messaging Gateway propagation dequeues messages from the foreign messaging system and converts the message body to a known ADT defined by Messaging Gateway. The transformation is used to convert the Messaging Gateway ADT to an Oracle Streams AQ payload type when the message is enqueued to the Oracle Streams AQ queue.

- `exception_queue` specifies the name of a foreign queue to which messages are moved if an exception occurs. This must have a syntax of `registered_queue@message_link`.

Whether or not a subscriber is needed depends on the requirements of the non-Oracle messaging system. If a durable subscriber is necessary, then it will be created by the Messaging Gateway agent. If the agent is not running at the time this procedure is called, then the creation of the subscriber on the non-Oracle messaging system will occur when the agent next starts.

The exception queue has the following caveats:

- The exception queue must be a registered non-Oracle queue.
- The source and exception queues must use the same messaging system link.

ALTER_AGENT Procedure

This procedure configures Messaging Gateway agent parameters.

Syntax

```
DBMS_MGWADM.ALTER_AGENT (
    max_connections IN BINARY_INTEGER DEFAULT NULL,
    max_memory     IN BINARY_INTEGER DEFAULT NULL,
    max_threads    IN BINARY_INTEGER DEFAULT NULL);
```

Parameters

Table 51–29 ALTER_AGENT Procedure Parameters

Parameter	Description
max_connections	The maximum number of messaging connections to Oracle Database used by the Messaging Gateway agent. If it is NULL, then the current value is unchanged.
max_memory	The maximum heap size, in MB, used by the Messaging Gateway agent. If it is NULL, then the current value is unchanged.
max_threads	The number of messaging threads that the Messaging Gateway agent creates. If it is NULL, then the current value is unchanged.

Usage Notes

Default values for these configuration parameters are set when the Messaging Gateway agent is installed.

Changes to the `max_memory` and `max_threads` parameters take effect the next time the Messaging Gateway agent is active. If the Messaging Gateway agent is currently active, then it must be shut down and restarted for the changes to take effect.

ALTER_MSGSYSTEM_LINK Procedure for TIB/Rendezvous

Alters the properties of a TIB/Rendezvous messaging system link.

Syntax

```
DBMS_MGWADM.ALTER_MSGSYSTEM_LINK (
    linkname      IN  VARCHAR2,
    properties    IN  SYS.MGW_TIBRV_PROPERTIES,
    options       IN  SYS.MGW_PROPERTIES DEFAULT NULL,
    comment       IN  VARCHAR2 DEFAULT DBMS_MGWADM.NO_CHANGE );
```

Parameters

Table 51–30 ALTER_MSGSYSTEM_LINK Procedure Parameters for TIB/Rendezvous

Parameters	Description
linkname	The messaging system link name
properties	Basic properties for a TIB/Rendezvous messaging system link. If NULL, then no link properties will be changed.
options	Optional link properties. If NULL, then no options will be changed. If not NULL, then the properties specified in this list are combined with the current options properties to form a new set of link options.
comment	A user-specified description, or NULL if one is not desired. If DBMS_MGWADM.NO_CHANGE, then the current value will not be changed.

Usage Notes

To retain an existing value for a messaging link property with a VARCHAR2 data type, specify DBMS_MGWADM.NO_CHANGE for that particular property. To preserve an existing value for a property of another data type, specify NULL for that property.

The options parameter specifies a set of properties used to alter the current optional properties. Each property affects the current property list in a particular manner: add a new property, replace an existing property, remove an existing property, or remove all properties.

See Also: ["SYS.MGW_PROPERTIES Type"](#) on page 51-6

Some properties cannot be modified, and this procedure will fail if an attempt is made to alter such a property. For properties and options that can be changed, a few are dynamic, and Messaging Gateway uses the new values immediately. Others require the Messaging Gateway agent to be shut down and restarted before they take effect.

See Also: ["TIB/Rendezvous System Properties"](#) on page 51-15 for more information about the messaging system properties and options

ALTER_MSGSYSTEM_LINK Procedure for WebSphere MQ

This procedure alters the properties of a WebSphere MQ messaging system link.

Syntax

```
DBMS_MGWADM.ALTER_MSGSYSTEM_LINK (  
    linkname IN VARCHAR2,  
    properties IN SYS.MGW_MQSERIES_PROPERTIES,  
    options IN SYS.MGW_PROPERTIES DEFAULT NULL,  
    comment IN VARCHAR2 DEFAULT DBMS_MGWADM.NO_CHANGE);
```

Parameters

Table 51–31 ALTER_MSGSYSTEM_LINK Procedure Parameters for WebSphere MQ

Parameters	Description
linkname	The messaging system link name
properties	Basic properties for a WebSphere MQ messaging system link. If it is NULL, then no link properties are changed.
options	Optional link properties. NULL if no options are changed. If not NULL, then the properties specified in this list are combined with the current options properties to form a new set of link options.
comment	An optional description or NULL if not desired. If DBMS_MGWADM.NO_CHANGE is specified, then the current value is not changed.

Usage Notes

To retain an existing value for a messaging link property with a VARCHAR2 data type, specify DBMS_MGWADM.NO_CHANGE for that particular property. To preserve an existing value for a property of another data type, specify NULL for that property.

The options parameter specifies a set of properties used to alter the current optional properties. Each property affects the current property list in a particular manner: add a new property, replace an existing property, remove an existing property, or remove all properties.

See Also: ["SYS.MGW_PROPERTIES Type"](#) on page 51-6

Some properties cannot be modified, and this procedure will fail if an attempt is made to alter such a property. For properties and options that can be changed, a few are dynamic, and Messaging Gateway uses the new values immediately. Others require the Messaging Gateway agent to be shut down and restarted before they take effect.

See Also: ["WebSphere MQ System Properties"](#) on page 51-12 for more information about the messaging system properties and options

ALTER_PROPAGATION_SCHEDULE Procedure

This procedure alters a propagation schedule.

Syntax

```
DBMS_MGWADM.ALTER_PROPAGATION_SCHEDULE (  
    schedule_id  IN VARCHAR2,  
    duration     IN NUMBER DEFAULT NULL,  
    next_time    IN VARCHAR2 DEFAULT NULL,  
    latency      IN NUMBER DEFAULT NULL);
```

Parameters

Table 51–32 ALTER_PROPAGATION_SCHEDULE Procedure Parameters

Parameter	Description
schedule_id	Identifies the propagation schedule to be altered
duration	Reserved for future use
next_time	Reserved for future use
latency	<p>Specifies the polling interval, in seconds, used by the Messaging Gateway agent when checking for messages in the source queue. If no messages are available in the source queue, then the agent will not poll again until the polling interval has passed. Once the agent detects a message it will continue propagating messages as long as any are available.</p> <p>Values: NULL or value > 0. If latency is NULL, then the Messaging Gateway agent default polling interval will be used. The default polling interval is 5 seconds, but it can be overridden by the Messaging Gateway initialization file.</p>

Usage Notes

This procedure always overwrites the existing value for each parameter. If a given parameter is not specified, then the existing values are overwritten with the default value.

ALTER_SUBSCRIBER Procedure

This procedure alters the parameters of a subscriber used to consume messages from a source queue for propagation to a destination.

Syntax

```
DBMS_MGWADM.ALTER_SUBSCRIBER (
  subscriber_id  IN VARCHAR2,
  rule           IN VARCHAR2 DEFAULT DBMS_MGWADM.NO_CHANGE,
  transformation IN VARCHAR2 DEFAULT DBMS_MGWADM.NO_CHANGE,
  exception_queue IN VARCHAR2 DEFAULT DBMS_MGWADM.NO_CHANGE,
  options        IN SYS.MGW_PROPERTIES DEFAULT NULL );
```

Parameters

Table 51–33 ALTER_SUBSCRIBER Procedure Parameters

Parameter	Description
subscriber_id	Identifies the subscriber to be altered
rule	Specifies an optional subscription rule used by the subscriber to dequeue messages from the source queue. The syntax and interpretation of this parameter depend on the subscriber propagation type. A NULL value indicates that no subscription rule is needed. If DBMS_MGWADM.NO_CHANGE, then the current value is unchanged.
transformation	Specifies the transformation needed to convert between the Oracle Streams AQ payload and an ADT defined by Messaging Gateway. The type of transformation needed depends on the subscriber propagation type. A NULL value indicates that no transformation is needed. If DBMS_MGWADM.NO_CHANGE, then the current value is unchanged.

Table 51–33 (Cont.) ALTER_SUBSCRIBER Procedure Parameters

Parameter	Description
<code>exception_queue</code>	<p>Specifies a queue used for exception message logging. This queue must be on the same messaging system as the propagation source. If no exception queue is associated with the subscriber, then propagation stops if a problem occurs. The syntax and interpretation of this parameter depend on the subscriber propagation type.</p> <p>A <code>NULL</code> value indicates that no exception queue is used. If <code>DBMS_MGWADM.NO_CHANGE</code>, then the current value is unchanged.</p> <p>The source queue and exception queue cannot be the same queue.</p>
<code>options</code>	<p>Optional subscriber properties. If <code>NULL</code>, then no options will be changed. If not <code>NULL</code>, then the properties specified in this list are combined with the current optional properties to form a new set of subscriber options.</p>

Usage Notes

If the non-Oracle messaging link being accessed for the subscriber uses a JMS interface, then the Messaging Gateway agent will use the Oracle JMS interface to access the Oracle Streams AQ queues. Otherwise the native Oracle Streams AQ interface will be used. Parameters are interpreted differently when the Messaging Gateway agent uses Oracle JMS for JMS connections.

When propagating from a JMS source, the subscriber rule cannot be altered. Instead, the subscriber must be removed and added with the new rule. For JMS, changing the message selector on a durable subscription is equivalent to deleting and re-creating the subscription.

Transformations are not currently supported if the Oracle JMS interface is used for propagation. The transformation parameter must be `DBMS_MGWADM.NO_CHANGE` (the default value).

The `options` parameter specifies a set of properties used to alter the current optional properties. Each property affects the current property list in a particular manner: add a new property, replace an existing property, remove an existing property, or remove all properties.

See Also:

- ["SYS.MGW_PROPERTIES Type"](#) on page 51-6 for more information on the options parameter
- ["WebSphere MQ System Properties"](#) on page 51-12 for more information on WebSphere MQ subscriber options
- ["TIB/Rendezvous System Properties"](#) on page 51-15 for more information on TIB/Rendezvous subscriber options
- ["OUTBOUND_PROPAGATION Subscribers"](#) on page 51-33 for outbound propagation parameter interpretation
- ["INBOUND_PROPAGATION Subscribers"](#) on page 51-34 for inbound propagation parameter interpretation

CLEANUP_GATEWAY Procedure

This procedure cleans up Messaging Gateway. The procedure performs cleanup or recovery actions that may be needed when Messaging Gateway is left in some abnormal or unexpected condition. The `MGW_GATEWAY` view lists Messaging Gateway status and configuration information that pertains to the cleanup actions.

Syntax

```
DBMS_MGWADM.CLEANUP_GATEWAY(
  action IN BINARY_INTEGER
  sarg   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 51–34 *CLEANUP_GATEWAY Procedure Parameters*

Parameter	Description
<code>action</code>	The cleanup action to be performed. Values: <ul style="list-style-type: none"> ▪ <code>CLEAN_STARTUP_STATE</code> for Messaging Gateway start up state recovery. ▪ <code>CLEAN_LOG_QUEUES</code> for log queue cleanup. ▪ <code>RESET_SUB_MISSING_LOG_REC</code> for subscriber recovery due to missing log record. ▪ <code>RESET_SUB_MISSING_MESSAGE</code> for subscriber recovery due to missing message.
<code>sarg</code>	Optional argument whose meaning depends on the value specified for <code>action</code> . This should be <code>NULL</code> if it is not used for the specified action.

Usage Notes

CLEAN_STARTUP_STATE

`sarg` is not used and must be `NULL`.

The `CLEAN_STARTUP_STATE` action recovers Messaging Gateway to a known state when the Messaging Gateway agent has crashed or some other abnormal event occurs, and Messaging Gateway cannot be restarted. This should be done only when the Messaging Gateway agent has been started but appears to have crashed or has been nonresponsive for an extended period of time.

The `CLEAN_STARTUP_STATE` action may be needed when the `MGW_GATEWAY` view shows that the `AGENT_STATUS` value is something other than `NOT_STARTED` or `START_SCHEDULED`, and the `AGENT_PING` value is `UNREACHABLE` for an extended period of time.

If the `AGENT_STATUS` value is `BROKEN`, then the Messaging Gateway agent cannot be started until the problem has been resolved and the `CLEAN_STARTUP_STATE` action used to reset the agent status. A `BROKEN` status can indicate that the Messaging Gateway start job detected a Messaging Gateway agent already running. This condition that should never occur under normal use.

Cleanup tasks include:

- Removing the queued job used to start the external Messaging Gateway agent process.
- Setting certain configuration information to a known state. For example, setting the agent status to `NOT_STARTED`.

Execution of this command fails if:

- The agent status is `NOT_STARTED` or `START_SCHEDULED`.
- No shutdown attempt has been made prior to calling this procedure, except if the agent status is `STARTING`.
- The Messaging Gateway agent is successfully contacted.

The assumption is that the agent is active, and this procedure fails. If the agent does not respond after several attempts have been made, then the cleanup tasks are performed. This procedure takes at least several seconds and possibly up to one minute. This is expected behavior under conditions where this particular cleanup action is appropriate and necessary.

CLEAN_LOG_QUEUES

`sarg` is not used and must be `NULL`.

The Messaging Gateway agent will clean log queues for all configured messaging system links. The agent will temporarily stop all propagation activity and then remove all obsolete and bad log records from the log queues for all links. The procedure will fail if the Messaging Gateway agent is not running.

This cleanup action is automatically performed each time the Messaging Gateway agent is started.

Note: For Oracle Database 10g, the `CLEAN_LOG_QUEUES` action is performed only on agent startup. If this procedure is called when the agent is running, then the Messaging Gateway agent ignores it.

RESET_SUB_MISSING_LOG_REC

`sarg` specifies a Messaging Gateway subscriber ID to be reset. It must be not `NULL`.

The Messaging Gateway agent recovers a Messaging Gateway subscriber that has failed due to a missing log record. The agent will reset the source and destination log records. The procedure will fail if the Messaging Gateway agent is not running.

Caution: If the messages in the source queue had already been propagated to the destination queue, then this action may result in duplicate messages.

RESET_SUB_MISSING_MESSAGE

`sarg` specifies a Messaging Gateway subscriber ID to be reset. It must be not `NULL`.

The Messaging Gateway agent recovers a Messaging Gateway subscriber that has failed due to a missing persistent source message. The agent will treat the message as a non-persistent message and continue processing that subscriber. The procedure will fail if the Messaging Gateway agent is not running.

CREATE_MSGSYSTEM_LINK Procedure for TIB/Rendezvous

Creates a link to a TIB/Rendezvous messaging system.

Syntax

```
DBMS_MGWADM.CREATE_MSGSYSTEM_LINK (
  linkname      IN  VARCHAR2,
  properties    IN  SYS.MGW_TIBRV_PROPERTIES,
  options       IN  SYS.MGW_PROPERTIES DEFAULT NULL,
  comment       IN  VARCHAR2 DEFAULT NULL );
```

Parameters

Table 51–35 *CREATE_MSGSYSTEM_LINK Procedure Parameters for TIB/Rendezvous*

Parameter	Description
linkname	A user-defined name to identify this messaging system link
properties	Basic properties of a TIB/Rendezvous messaging system link.
options	Optional link properties. NULL if there are none. These are less frequently used configuration properties supported by the messaging system
comment	A user-specified description. NULL if one is not desired.

Usage Notes

See Also: ["TIB/Rendezvous System Properties"](#) on page 51-15 for more information about the messaging system properties and options

CREATE_MSGSYSTEM_LINK Procedure for WebSphere MQ

This procedure creates a messaging system link to a WebSphere MQ messaging system.

Syntax

```
DBMS_MGWADM.CREATE_MSGSYSTEM_LINK(  
    linkname      IN VARCHAR2,  
    properties    IN SYS.MGW_MQSERIES_PROPERTIES,  
    options       IN SYS.MGW_PROPERTIES DEFAULT NULL,  
    comment       IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 51–36 *CREATE_MSGSYSTEM_LINK Procedure Parameters for WebSphere MQ*

Parameter	Description
linkname	A user-defined name to identify the messaging system link
properties	Basic properties of a WebSphere MQ messaging system link
options	Optional link properties. NULL if there are none. These are less frequently used configuration properties supported by the messaging system.
comment	A user-specified description. NULL if one is not desired

Usage Notes

See Also: ["WebSphere MQ System Properties"](#) on page 51-12 for more information about the messaging system properties and options

DB_CONNECT_INFO Procedure

This procedure configures connection information used by the Messaging Gateway agent for connections to Oracle Database.

Syntax

```
DBMS_MGWADM.DB_CONNECT_INFO (
    username      IN VARCHAR2,
    password      IN VARCHAR2,
    database      IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 51–37 *DB_CONNECT_INFO Procedure Parameters*

Parameter	Description
username	The username used for connections to Oracle Database. NULL is not allowed
password	The password used for connections to Oracle Database. NULL is not allowed
database	The database connect string used by the Messaging Gateway agent. NULL indicates that a local connection should be used. Oracle strongly recommends that a not NULL value be specified. Usually it will be a net service name from <code>tnsnames.ora</code> .

Usage Notes

The Messaging Gateway agent connects to Oracle Database as the user configured by this procedure. An Oracle administrator should create the user, grant it the role `MGW_AGENT_ROLE`, and then call this procedure to configure Messaging Gateway. Role `MGW_AGENT_ROLE` is used to grant this user special privileges needed to access Messaging Gateway configuration information stored in the database, enqueue or dequeue messages to and from Oracle Streams AQ queues, and perform certain Oracle Streams AQ administration tasks.

DISABLE_PROPAGATION_SCHEDULE Procedure

This procedure disables a propagation schedule.

Syntax

```
DBMS_MGWADM.DISABLE_PROPAGATION_SCHEDULE (  
    schedule_id IN VARCHAR2 );
```

Parameters

Table 51–38 *DISABLE_PROPAGATION_SCHEDULE Procedure Parameters*

Parameter	Description
schedule_id	Identifies the propagation schedule to be disabled

ENABLE_PROPAGATION_SCHEDULE Procedure

This procedure enables a propagation schedule.

Syntax

```
DBMS_MGWADM.ENABLE_PROPAGATION_SCHEDULE (  
    schedule_id IN VARCHAR2 );
```

Parameters

Table 51–39 *ENABLE_PROPAGATION_SCHEDULE Procedure Parameters*

Parameter	Description
schedule_id	Identifies the propagation schedule to be enabled

REGISTER_FOREIGN_QUEUE Procedure

This procedure registers a non-Oracle queue entity in Messaging Gateway.

Syntax

```
DBMS_MGWADM.REGISTER_FOREIGN_QUEUE(
    name          IN VARCHAR2,
    linkname      IN VARCHAR2,
    provider_queue IN VARCHAR2 DEFAULT NULL,
    domain        IN INTEGER DEFAULT NULL,
    options       IN SYS.MGW_PROPERTIES DEFAULT NULL,
    comment       IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 51–40 REGISTER_FOREIGN_QUEUE Procedure Parameters

Parameters	Description
name	The registered queue name. This name identifies the foreign queue within Messaging Gateway and need not match the name of the queue in the foreign messaging system.
linkname	The link name for the messaging system on which this queue exists
provider_queue	The message provider (native) queue name. If <code>NULL</code> , then the value provided for the <code>name</code> parameter is used as the provider queue name.
domain	The domain type of the queue. <code>NULL</code> means the domain type is automatically determined based on the messaging system of the queue. <code>DOMAIN_QUEUE</code> is for a queue (point-to-point model). <code>DOMAIN_TOPIC</code> is for a topic (publish-subscribe model)
options	Optional queue properties
comment	A user-specified description. Can be <code>NULL</code> .

Usage Notes

This procedure does not create the physical queue in the non-Oracle messaging system. The non-Oracle queue must be created using the administration tools for that messaging system.

See Also:

- ["WebSphere MQ System Properties"](#) on page 51-12 for more information when registering queues for the WebSphere MQ messaging system
- ["TIB/Rendezvous System Properties"](#) on page 51-15 for more information when registering queues for the TIB/Rendezvous messaging system

REMOVE_MSGSYSTEM_LINK Procedure

This procedure removes a messaging system link for a non-Oracle messaging system.

Syntax

```
DBMS_MGWADM.REMOVE_MSGSYSTEM_LINK(  
    linkname IN VARCHAR2);
```

Parameters

Table 51–41 REMOVE_MSGSYSTEM_LINK Procedure Parameters

Parameters	Description
linkname	The messaging system link name

Usage Notes

All registered queues associated with this link must be removed before the messaging system link can be removed. This procedure fails if there is a registered foreign (non-Oracle) queue that references this link.

REMOVE_SUBSCRIBER Procedure

This procedure removes a subscriber used to consume messages from a source queue for propagation to a destination.

Syntax

```
DBMS_MGWADM.REMOVE_SUBSCRIBER (
  subscriber_id IN VARCHAR2,
  force         IN BINARY_INTEGER DEFAULT DBMS_MGWADM.NO_FORCE );
```

Parameters

Table 51–42 REMOVE_SUBSCRIBER Procedure Parameters

Parameter	Description
subscriber_id	Identifies the subscriber to be removed
force	Specifies whether this procedure should succeed even if Messaging Gateway is not able to perform all cleanup actions pertaining to this subscriber. <code>NO_FORCE</code> (0) means the subscriber is not removed if Messaging Gateway is unable to clean up successfully. <code>FORCE</code> (1) means the subscriber is removed, even though all cleanup actions may not be done. The Messaging Gateway agent uses various resources of Oracle Database and the non-Oracle messaging system for its propagation work. These resources are typically associated with each subscriber and need to be released when the subscriber is no longer needed. Therefore, this procedure should only be called when the Messaging Gateway agent is running and able to access the non-Oracle messaging system associated with this subscriber.

Usage Notes

For outbound propagation, a local subscriber is removed from the Oracle Streams AQ queue.

RESET_SUBSCRIBER Procedure

This procedure resets the propagation error state for a subscriber.

Syntax

```
DBMS_MGWADM.RESET_SUBSCRIBER (  
    subscriber_id IN VARCHAR2 );
```

Parameters

Table 51–43 *RESET_SUBSCRIBER Procedure Parameters*

Parameter	Description
subscriber_id	Identifies the subscriber

SET_LOG_LEVEL Procedure

This procedure dynamically alters the Messaging Gateway agent logging level. The Messaging Gateway agent must be running.

Syntax

```
DBMS_MGWADM.SET_LOG_LEVEL (  
    log_level IN BINARY_INTEGER);
```

Parameters

Table 51-44 SET_LOG_LEVEL Procedure Parameters

Parameter	Description
log_level	Level at which the Messaging Gateway agent logs information. BASIC_LOGGING generates the least information while TRACE_DEBUG_LOGGING generates the most information.

See Also: [Table 51-6, "DBMS_MGWADM Constants—Logging Levels"](#) on page 51-3 for details on the log_level parameter

SCHEDULE_PROPAGATION Procedure

This procedure schedules message propagation from a source to a destination. The schedule must be enabled and Messaging Gateway started in order for messages to be propagated.

Syntax

```
DBMS_MGWADM.SCHEDULE_PROPAGATION (
    schedule_id      IN VARCHAR2,
    propagation_type IN BINARY_INTEGER,
    source           IN VARCHAR2,
    destination      IN VARCHAR2,
    start_time       IN DATE DEFAULT SYSDATE,
    duration         IN NUMBER DEFAULT NULL,
    next_time        IN VARCHAR2 DEFAULT NULL,
    latency          IN NUMBER DEFAULT NULL);
```

Parameters

Table 51–45 *SCHEDULE_PROPAGATION Procedure Parameters*

Parameter	Description
<code>schedule_id</code>	Specifies a user-defined name that identifies the schedule
<code>propagation_type</code>	Specifies the type of message propagation. <code>DBMS_MGWADM.OUTBOUND_PROPAGATION</code> is for Oracle Streams AQ to non-Oracle propagation. <code>DBMS_MGWADM.INBOUND_PROPAGATION</code> is for non-Oracle to Oracle Streams AQ propagation.
<code>source</code>	Specifies the source queue whose messages are to be propagated. The syntax and interpretation of this parameter depend on the value specified for <code>propagation_type</code> .
<code>destination</code>	Specifies the destination queue to which messages are propagated. The syntax and interpretation of this parameter depend on the value specified for <code>propagation_type</code> .
<code>start_time</code>	Reserved for future use
<code>duration</code>	Reserved for future use

Table 51–45 (Cont.) SCHEDULE_PROPAGATION Procedure Parameters

Parameter	Description
<code>next_time</code>	Reserved for future use
<code>latency</code>	<p>Specifies the polling interval, in seconds, used by the Messaging Gateway agent when checking for messages in the source queue. If no messages are available in the source queue, then the agent will not poll again until the polling interval has passed. Once the agent detects a message it will continue propagating messages as long as any are available.</p> <p>Values: <code>NULL</code> or <code>value > 0</code>. If <code>latency</code> is <code>NULL</code>, then the Messaging Gateway agent default polling interval will be used. The default polling interval is 5 seconds but it can be overridden by the Messaging Gateway initialization file.</p>

Usage Notes

For outbound propagation, parameters are interpreted as follows:

- `source` specifies the local Oracle Streams AQ queue from which messages are propagated. This must have a syntax of `schema.queue`.
- `destination` specifies the foreign queue to which messages are propagated. This must have a syntax of `registered_queue@message_link`.

For inbound propagation, parameters are interpreted as follows:

- `source` specifies the foreign queue from which messages are propagated. This must have a syntax of `registered_queue@message_link`.
- `destination` specifies the local Oracle Streams AQ queue to which messages are propagated. This must have a syntax of `schema.queue`.

The schedule is set to an enabled state when it is created.

SHUTDOWN Procedure

This procedure shuts down the Messaging Gateway agent. No propagation activity occurs until Messaging Gateway is restarted.

Syntax

```
DBMS_MGWADM.SHUTDOWN (  
    smode IN BINARY_INTEGER DEFAULT DBMS_MGWADM.SHUTDOWN_NORMAL);
```

Parameters

Table 51–46 *SHUTDOWN Procedure Parameters*

Parameter	Description
smode	The shutdown mode. The only value currently supported is SHUTDOWN_NORMAL for normal shutdown. The Messaging Gateway agent may attempt to complete any propagation work currently in progress.

STARTUP Procedure

This procedure starts the Messaging Gateway agent. It must be called before any propagation activity can take place.

Syntax

```
DBMS_MGWADM.STARTUP(
    instance IN BINARY_INTEGER DEFAULT 0,
    force    IN BINARY_INTEGER DEFAULT DBMS_MGWADM.NO_FORCE);
```

Parameters

Table 51–47 *STARTUP Procedure Parameters*

Parameter	Description
instance	Specifies which instance can run the job queue job used to start the Messaging Gateway agent. If this is zero, then the job can be run by any instance.
force	If this is <code>DBMS_MGWADM.FORCE</code> , then any positive integer is acceptable as the job instance. If this is <code>DBMS_MGWADM.NO_FORCE</code> (the default), then the specified instance must be running; otherwise the routine raises an exception.

Usage Notes

The Messaging Gateway agent cannot be started until an agent user has been configured using `DB_CONNECT_INFO`.

This procedure submits a job queue job, which starts the Messaging Gateway agent when it runs. The `instance` and `force` parameters are used for job queue affinity, which you use to indicate whether a particular instance or any instance can run a submitted job.

UNREGISTER_FOREIGN_QUEUE Procedure

This procedure removes a non-Oracle queue entity in Messaging Gateway.

Syntax

```
DBMS_MGWADM.UNREGISTER_FOREIGN_QUEUE(  
    name          IN VARCHAR2,  
    linkname      IN VARCHAR2);
```

Parameters

Table 51–48 UNREGISTER_FOREIGN_QUEUE Procedure Parameters

Parameter	Description
name	The queue name
linkname	The link name for the messaging system on which the queue exists

Usage Notes

This procedure does not remove the physical queue in the non-Oracle messaging system.

All subscribers and schedules referencing this queue must be removed before it can be unregistered. This procedure fails if a subscriber or propagation schedule references the non-Oracle queue.

UNSCHEDULE_PROPAGATION Procedure

This procedure removes a propagation schedule.

Syntax

```
DBMS_MGWADM.UNSCHEDULE_PROPAGATION (  
    schedule_id    IN VARCHAR2 );
```

Parameters

Table 51–49 *UNSCHEDULE_PROPAGATION Procedure Parameters*

Parameter	Description
schedule_id	Identifies the propagation schedule to be removed

DBMS_MGWMSG

DBMS_MGWMSG provides:

- Object types used by the canonical message types to convert message bodies.
- Methods, constants, and subprograms for working with Messaging Gateway message types.

See Also: [Chapter 51, "DBMS_MGWADM"](#) which describes the Messaging Gateway administrative interface, `DBMS_MGWADM`

This chapter contains the following topics:

- [Using DBMS_MGWMSG](#)
 - [Security Model](#)
 - [Constants](#)
 - [Types](#)
- [Summary of DBMS_MGWMSG Subprograms](#)

Using DBMS_MGWMSG

- [Security Model](#)
- [Constants](#)
- [Types](#)

Security Model

The DBMS_MGWMSG packages and object types are owned by SYS.

Note: You must run the `catmgw.sql` script to load the Messaging Gateway packages and object types into the database. Refer to the *Oracle Streams Advanced Queuing User's Guide and Reference* for information on loading database objects and using DBMS_MGWMSG.

Constants

Table 52–1 DBMS_MGWMSG Constants: Value Types and Constants Representing the Type of Value for a SYS.MGW_NAME_VALUE_T Object

Value	Constant
TEXT_VALUE	CONSTANT BINARY_INTEGER := 1
RAW_VALUE	CONSTANT BINARY_INTEGER := 2
BOOLEAN_VALUE	CONSTANT BINARY_INTEGER := 3
BYTE_VALUE	CONSTANT BINARY_INTEGER := 4
SHORT_VALUE	CONSTANT BINARY_INTEGER := 5
INTEGER_VALUE	CONSTANT BINARY_INTEGER := 6
LONG_VALUE	CONSTANT BINARY_INTEGER := 7
FLOAT_VALUE	CONSTANT BINARY_INTEGER := 8
DOUBLE_VALUE	CONSTANT BINARY_INTEGER := 9
DATE_VALUE	CONSTANT BINARY_INTEGER := 10

Table 52–2 DBMS_MGWMSG Constants: Boolean Values—Constants Representing a Boolean as a Numeric Value

Value	Constant
BOOLEAN_FALSE	CONSTANT BINARY_INTEGER := 0
BOOLEAN_TRUE	CONSTANT BINARY_INTEGER := 1

Table 52–3 DBMS_MGWMSG Constants: Case Comparisons

Value	Constant
CASE_SENSITIVE	CONSTANT BINARY_INTEGER := 0
CASE_INSENSITIVE	CONSTANT BINARY_INTEGER := 1

Table 52–4 Constants for the TIB/Rendezvous field type

Value	Constant
TIBRVMSG_BOOL	CONSTANT INTEGER := 1
TIBRVMSG_F32	CONSTANT INTEGER := 2
TIBRVMSG_F64	CONSTANT INTEGER := 3
TIBRVMSG_I8	CONSTANT INTEGER := 4
TIBRVMSG_I16	CONSTANT INTEGER := 5
TIBRVMSG_I32	CONSTANT INTEGER := 6
TIBRVMSG_I64	CONSTANT INTEGER := 7
TIBRVMSG_IPADDR32	CONSTANT INTEGER := 8
TIBRVMSG_IPPORT16	CONSTANT INTEGER := 9
TIBRVMSG_DATETIME	CONSTANT INTEGER := 10
TIBRVMSG_F32ARRAY	CONSTANT INTEGER := 11
TIBRVMSG_F64ARRAY	CONSTANT INTEGER := 12
TIBRVMSG_I8ARRAY	CONSTANT INTEGER := 13
TIBRVMSG_I16ARRAY	CONSTANT INTEGER := 14
TIBRVMSG_I32ARRAY	CONSTANT INTEGER := 15
TIBRVMSG_I64ARRAY	CONSTANT INTEGER := 16

Table 52–4 (Cont.) Constants for the TIB/Rendezvous field type

Value	Constant
TIBRVMSG_OPAQUE	CONSTANT INTEGER := 17
TIBRVMSG_STRING	CONSTANT INTEGER := 18
TIBRVMSG_XML	CONSTANT INTEGER := 19

Types

- [SYS.MGW_NAME_VALUE_T Type](#)
- [SYS.MGW_NAME_VALUE_T Type-Attribute Mapping](#)
- [SYS.MGW_NAME_TYPE_ARRAY_T Type](#)
- [SYS.MGW_TEXT_VALUE_T Type](#)
- [SYS.MGW_RAW_VALUE_T Type](#)
- [SYS.MGW_BASIC_MSG_T Type](#)
- [SYS.MGW_NUMBER_ARRAY_T Type](#)
- [SYS.MGW_TIBRV_FIELD_T Type](#)
- [SYS.MGW_TIBRV_MSG_T Type](#)

SYS.MGW_NAME_VALUE_T Type

This type specifies a named value. The name attribute, type attribute, and one of the <>_value attributes are typically not NULL.

Syntax

```

TYPE SYS.MGW_NAME_VALUE_T IS OBJECT(
  name          VARCHAR2(250),
  type          INTEGER,
  integer_value INTEGER,
  number_value  NUMBER,
  text_value    VARCHAR2(4000),
  raw_value     RAW(2000),
  date_value    DATE,

  -- Methods
  STATIC FUNCTION CONSTRUCT
  RETURN SYS.MGW_NAME_VALUE_T,

```



```
STATIC FUNCTION CONSTRUCT_BOOLEAN (
    name   IN VARCHAR2,
    value  IN INTEGER )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_BYTE (
    name   IN VARCHAR2,
    value  IN INTEGER )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_SHORT (
    name   IN VARCHAR2,
    value  IN INTEGER )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_INTEGER (
    name   IN VARCHAR2,
    value  IN INTEGER )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_LONG (
    name   IN VARCHAR2,
    value  IN NUMBER )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_FLOAT (
    name   IN VARCHAR2,
    value  IN NUMBER )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_DOUBLE (
    name   IN VARCHAR2,
    value  IN NUMBER )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_TEXT (
    name   IN VARCHAR2,
    value  IN VARCHAR2 )
RETURN SYS.MGW_NAME_VALUE_T,
```

```
STATIC FUNCTION CONSTRUCT_RAW (
    name   IN VARCHAR2,
    value  IN RAW )
RETURN SYS.MGW_NAME_VALUE_T,
```

```

STATIC FUNCTION CONSTRUCT_DATE (
    name   IN VARCHAR2,
    value  IN DATE )
RETURN SYS.MGW_NAME_VALUE_T );

```

Attributes

Table 52–5 *SYS.MGW_NAME_VALUE_T Attributes*

Attribute	Description
name	Name associated with the value
type	Value type. Refer to the DBMS_MGWMSG.<>_VALUE constants in Table 52–1. This indicates which Java datatype and class are associated with the value. It also indicates which attribute stores the value.
integer_value	Stores a numeric integer value
number_value	Stores a numeric float or large integer value
text_value	Stores a text value
raw_value	Stores a RAW (bytes) value
date_value	Stores a date value

SYS.MGW_NAME_VALUE_T Type-Attribute Mapping

Table 52–6 shows the mapping between the value type and the attribute used to store the value.

Table 52–6 *SYS.MGW_NAME_VALUE_T Type Attribute Mapping*

Type	Value Stored in Attribute
DBMS_MGWMSG.TEXT_VALUE	text_value
DBMS_MGWMSG.RAW_VALUE	raw_value
DBMS_MGWMSG.BOOLEAN_VALUE	integer_value
DBMS_MGWMSG.BYTE_VALUE	integer_value
DBMS_MGWMSG.SHORT_VALUE	integer_value
DBMS_MGWMSG.INTEGER_VALUE	integer_value
DBMS_MGWMSG.LONG_VALUE	number_value

Table 52–6 (Cont.) SYS.MGW_NAME_VALUE_T Type Attribute Mapping

Type	Value Stored in Attribute
DBMS_MGWMSG.FLOAT_VALUE	number_value
DBMS_MGWMSG.DOUBLE_VALUE	number_value
DBMS_MGWMSG.DATE_VALUE	date_value

CONSTRUCT Method

This method constructs a new `SYS.MGW_NAME_VALUE_T` instance. All attributes are assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_NAME_VALUE_T;
```

CONSTRUCT_TYPE Methods

These methods construct a new `SYS.MGW_NAME_VALUE_T` instance initialized with the value of a specific type. Each method sets the `name` and `type` attributes and one of the `<>_value` attributes, as shown in the mappings in [Table 52–6](#).

Syntax

```
STATIC FUNCTION CONSTRUCT_<> (
    name   IN VARCHAR2,
    value  IN datatype )
RETURN SYS.MGW_NAME_VALUE_T;
```

Usage Notes

The `construct_boolean` method sets the `value` to either `DBMS_MGWMSG.BOOLEAN_TRUE` or `DBMS_MGWMSG.BOOLEAN_FALSE`.

SYS.MGW_NAME_TYPE_ARRAY_T Type

This type specifies an array of name-value pairs. An object of `SYS.MGW_NAME_VALUE_ARRAY_T` type can have up to 1024 elements.

Syntax

```
TYPE SYS.MGW_NAME_VALUE_ARRAY_T
AS VARRAY (1024) OF SYS.MGW_NAME_VALUE_T;
```

SYS.MGW_TEXT_VALUE_T Type

This type specifies a `TEXT` value. It can store a large value as a `CLOB` or a smaller value (size ≤ 4000) as `VARCHAR2`. Only one of the `< >_value` attributes should be set.

Syntax

```
TYPE SYS.MGW_TEXT_VALUE_T IS OBJECT(
    small_value VARCHAR2(4000),
    large_value CLOB,

    -- Methods
    STATIC FUNCTION CONSTRUCT
    RETURN SYS.MGW_TEXT_VALUE_T);
```

Attributes

Table 52–7 *SYS.MGW_TEXT_VALUE_T Attributes*

Attribute	Description
<code>small_value</code>	Small <code>TEXT</code> value. Used for values ≤ 4000 .
<code>large_value</code>	Large <code>TEXT</code> value. Used when the value is too large for the <code>small_value</code> attribute.

CONSTRUCT Method

This method constructs a new `SYS.MGW_TEXT_VALUE_T` instance. All attributes are assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_TEXT_VALUE_T;
```

SYS.MGW_RAW_VALUE_T Type

This type specifies a `RAW` value. This type can store a large value as a `BLOB` or a smaller value (size ≤ 2000) as `RAW`. You must set no more than one of the `< >_value` attributes.

Syntax

```
TYPE SYS.MGW_RAW_VALUE_T IS OBJECT(
```

```

    small_value RAW(2000),
    large_value BLOB,

--Methods
STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_RAW_VALUE_T);

```

Attributes

Table 52-8 SYS.MGW_RAW_VALUE_T Attributes

Attribute	Description
small_value	Small RAW (bytes) value <= 2000
large_value	Large RAW value. Used when the value is too large for the small_value attribute.

CONSTRUCT Method

This method constructs a new `SYS.MGW_RAW_VALUE_T` instance. All attributes are assigned a value of `NULL`.

Syntax

```

STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_RAW_VALUE_T;

```

SYS.MGW_BASIC_MSG_T Type

This is a canonical type for a basic `TEXT` or `RAW` message. Only a single `TEXT` or `RAW` value is typically set. An object of this type must not have both `TEXT` and `RAW` set to a not `NULL` value at the same time.

Syntax

```

TYPE SYS.MGW_BASIC_MSG_T IS OBJECT(
    header      SYS.MGW_NAME_VALUE_ARRAY_T,
    text_body   SYS.MGW_TEXT_VALUE_T,
    raw_body    SYS.MGW_RAW_VALUE_T,

--Methods
STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_BASIC_MSG_T);

```

Attributes

Table 52–9 *SYS.MGW_BASIC_MSG_T Attributes*

Attribute	Description
header	Message header information as an array of name-value pairs
text_body	Message body for a TEXT message
raw_body	Message body for a RAW (bytes) message

CONSTRUCT Method

This method constructs a new `SYS.MGW_BASIC_MSG_T` instance. All attributes are assigned a value of `NULL`.

Syntax

```
STATIC FUNCTION CONSTRUCT
RETURN SYS.MGW_BASIC_MSG_T;
```

SYS.MGW_NUMBER_ARRAY_T Type

A type that specifies an array of numbers.

Syntax

```
TYPE SYS.MGW_NUMBER_ARRAY_T AS VARRAY(1024) OF NUMBER;
```

SYS.MGW_TIBRV_FIELD_T Type

A type representing a TIB/Rendezvous message field, typically used in a read-only fashion to retrieve field information from a `SYS.MGW_TIBRV_MSG_T` instance.

Syntax

```
TYPE SYS.MGW_TIBRV_FIELD_T IS OBJECT(
    field_name      VARCHAR2(256),
    field_id        INTEGER,
    field_type      INTEGER,
    number_value    NUMBER,
    number_array_value SYS.MGW_NUMBER_ARRAY_T,
    text_value      VARCHAR2(4000),
    raw_value       RAW(2000),
    date_value      DATE,
    clob_value      CLOB,
```

```
blob_value      BLOB);
```

Attributes

Table 52–10 *SYS.MGW_TIBRV_FIELD_T Attributes*

Attribute	Description
field_name	Field name. This will be NULL if the field has no name.
field_id	Field identifier. If the field identifier is zero (0), then that field is considered not to have a field identifier. Otherwise the field identifier is a nonzero value that is unique for all fields of that message.
field_type	Field wire format datatype. The DBMS_MGWMSG.TIBRVMSG_<> constants represent valid values for this attribute. The value of this field discriminates which value attribute is used to store the field data.
number_value	Used to store a numeric value
number_array_value	Used to store a numeric array value
text_value	Used to store a small text value
raw_value	Used to store a small raw value
date_value	Used to store a date value
clob_value	Used to store a large text value. This is used when the text data will not fit in text_value, that is, when size is larger than 4000.
blob_value	Used to store a large raw value. This is used when the raw data will not fit in raw_value; that is, when size is larger than 2000.

SYS.MGW_TIBRV_FIELD_T Type and Attribute Mapping

[Table 52–11](#) describes the mapping in type SYS.MGW_TIBRV_FIELD_T between the field type and attribute used to store the value.

Table 52–11 *SYS.MGW_TIBRV_FIELD_T Type and Attribute Mapping*

Field Type (DBMS_MGWMSG constant)	Value Stored in Attribute
TIBRVMSG_BOOL	number_value
TIBRVMSG_F32	number_value
TIBRVMSG_F64	number_value

Table 52–11 (Cont.) SYS.MGW_TIBRV_FIELD_T Type and Attribute Mapping

Field Type (DBMS_MGWMSG constant)	Value Stored in Attribute
TIBRVMSG_I8	number_value
TIBRVMSG_I16	number_value
TIBRVMSG_I32	number_value
TIBRVMSG_I64	number_value
TIBRVMSG_IPADDR32	text_value
TIBRVMSG_IPPORT16	number_value
TIBRVMSG_DATETIME	date_value
TIBRVMSG_F32ARRAY	number_array_value
TIBRVMSG_F64ARRAY	number_array_value
TIBRVMSG_I8ARRAY	number_array_value
TIBRVMSG_I16ARRAY	number_array_value
TIBRVMSG_I32ARRAY	number_array_value
TIBRVMSG_I64ARRAY	number_array_value
TIBRVMSG_OPAQUE	raw_value or blob_value
TIBRVMSG_STRING	text_value or clob_value
TIBRVMSG_XML	raw_value or blob_value

SYS.MGW_TIBRV_MSG_T Type

A type representing a TIB/Rendezvous message. You must never directly reference the attributes of this type. Instead use the type methods.

Syntax

```
TYPE SYS.MGW_TIBRV_MSG_T IS OBJECT(
    send_subject    VARCHAR2(256),
    reply_subject   VARCHAR2(256),
    cm_time_limit   NUMBER,
    cm_sender_name  VARCHAR2(256),
    cm_sequence_num NUMBER,
    fields          SYS.MGW_TIBRV_IFIELDS_T,
    clob_data1      CLOB,
    clob_data2      CLOB,
```



```
        clob_data3      CLOB,
        blob_data1     BLOB,
        blob_data2     BLOB,
        blob_data3     BLOB,

    STATIC FUNCTION construct
    RETURN SYS.MGW_TIBRV_MSG_T,

    MEMBER PROCEDURE add_bool (
        name IN VARCHAR2,
        id   IN INTEGER,
        value IN INTEGER ),

    MEMBER PROCEDURE add_f32 (
        name IN VARCHAR2,
        id   IN INTEGER,
        value IN FLOAT ),

    MEMBER PROCEDURE add_f64 (
        name IN VARCHAR2,
        id   IN INTEGER,
        value IN DOUBLE ),

    MEMBER PROCEDURE add_i8 (
        name IN VARCHAR2,
        id   IN INTEGER,
        value IN INTEGER ),

    MEMBER PROCEDURE add_i16 (
        name IN VARCHAR2,
        id   IN INTEGER,
        value IN INTEGER ),

    MEMBER PROCEDURE add_i32 (
        name IN VARCHAR2,
        id   IN INTEGER,
        value IN INTEGER ),

    MEMBER PROCEDURE add_i64 (
        name IN VARCHAR2,
        id   IN INTEGER,
        value IN NUMBER ),

    MEMBER PROCEDURE add_ipaddr32 (
        name IN VARCHAR2,
```

```
        id    IN  INTEGER,
        value IN  VARCHAR2 ),

MEMBER PROCEDURE add_ipport16 (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  INTEGER ),

MEMBER PROCEDURE add_datetime (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  DATE ),

MEMBER PROCEDURE add_f32array (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  SYS.MGW_NUMBER_ARRAY_T ),

MEMBER PROCEDURE add_f64array (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  SYS.MGW_NUMBER_ARRAY_T ),

MEMBER PROCEDURE add_i8array (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  SYS.MGW_NUMBER_ARRAY_T ),

MEMBER PROCEDURE add_i16array (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  SYS.MGW_NUMBER_ARRAY_T ),

MEMBER PROCEDURE add_i32array (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  SYS.MGW_NUMBER_ARRAY_T ),

MEMBER PROCEDURE add_i64array (
    name  IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  SYS.MGW_NUMBER_ARRAY_T ),

MEMBER PROCEDURE add_string (
    name  IN  VARCHAR2,
```

```
        id    IN  INTEGER,
        value IN  VARCHAR2 ),

MEMBER PROCEDURE add_string (
    name IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  CLOB ),

MEMBER PROCEDURE add_opaque (
    name IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  RAW ),

MEMBER PROCEDURE add_opaque (
    name IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  BLOB ),

MEMBER PROCEDURE add_xml (
    name IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  RAW ),

MEMBER PROCEDURE add_xml (
    name IN  VARCHAR2,
    id    IN  INTEGER,
    value IN  BLOB ),

MEMBER PROCEDURE set_send_subject (
    value IN  VARCHAR2 ),

MEMBER PROCEDURE set_reply_subject (
    value IN  VARCHAR2 ),

MEMBER PROCEDURE set_cm_time_limit (
    value IN  NUMBER ),

MEMBER PROCEDURE set_cm_sender_name (
    value IN  VARCHAR2 ),

MEMBER PROCEDURE set_cm_sequence_num (
    value IN  NUMBER ),

MEMBER FUNCTION get_send_subject
RETURN VARCHAR2,
```

```
MEMBER FUNCTION get_reply_subject
RETURN VARCHAR2,

MEMBER FUNCTION get_cm_time_limit
RETURN NUMBER,

MEMBER FUNCTION get_cm_sender_name
RETURN VARCHAR2,

MEMBER FUNCTION get_cm_sequence_num
RETURN NUMBER,

MEMBER FUNCTION get_field_count
RETURN INTEGER,

MEMBER FUNCTION get_field (
    idx    IN INTEGER )
RETURN SYS.MGW_TIBRV_FIELD_T,

MEMBER FUNCTION get_field_by_name (
    name   IN VARCHAR2 )
RETURN SYS.MGW_TIBRV_FIELD_T,

MEMBER FUNCTION get_field_by_id (
    id     IN INTEGER )
RETURN SYS.MGW_TIBRV_FIELD_T,

MEMBER FUNCTION find_field_name (
    name   IN VARCHAR2,
    start_idx IN INTEGER )
RETURN INTEGER,

MEMBER FUNCTION find_field_id (
    id     IN INTEGER,
    start_idx IN INTEGER )
RETURN INTEGER
);
```

Attributes

Table 52–12 *SYS.MGW_TIBRV_MSG_T Type Attributes*

Attribute	Description
send_subject	Send subject name
reply_subject	Reply subject name
cm_time_limit	Time limit for a certified message
cm_sender_name	Sender name of a certified message
cm_sequence_num	Sequence number of a certified message
fields	Collection of message fields
clob_data1	Used to store a large text value
clob_data2	Used to store a large text value
clob_data3	Used to store a large text value
blob_data1	Used to store a large raw value
blob_data2	Used to store a large raw value
blob_data3	Used to store a large raw value

Construct Method

Constructs a new `SYS.MGW_TIBRV_MSG_T` instance. All attributes are set to `NULL`.

Syntax

```
STATIC FUNCTION construct
RETURN SYS.MGW_TIBRV_MSG_T;
```

ADD_<> Procedures

Adds a new field to the message.

Syntax

```
MEMBER PROCEDURE ADD_<> (
  name IN VARCHAR2,
  id   IN INTEGER,
  value IN datatype );
```

Parameters

Table 52–13 *SYS.MGW_TIBRV_MSG_T ADD_<> Method Parameters*

Parameter	Description
name	Field name
id	Field identifier
value	Field data

Table 52–14 shows, for each add method, the field type that will be assigned and valid values for the field data.

Table 52–14 *MGW_TIBRV_MSG_T Add Method Field Types*

Method Name	Field Type Assigned	Comment
add_bool	TIBRVMSG_BOOL	Valid values: 0 (false), 1 (true)
add_f32	TIBRVMSG_F32	n/a
add_f64	TIBRVMSG_F64	n/a
add_i8	TIBRVMSG_I8	Valid range: -128...127
add_i16	TIBRVMSG_I16	Valid range: -32768...32767
add_i32	TIBRVMSG_I32	Valid range: -2147483648... 2147483647
add_i64	TIBRVMSG_I64	n/a
add_ipaddr32	TIBRVMSG_IPADDR32	n/a
add_ipport16	TIBRVMSG_IPPORT16	n/a
add_datetime	TIBRVMSG_DATETIME	n/a
add_f32array	TIBRVMSG_F32ARRAY	n/a
add_f64array	TIBRVMSG_F64ARRAY	n/a
add_i8array	TIBRVMSG_I8ARRAY	Valid range: -128...127
add_i16array	TIBRVMSG_I16ARRAY	Valid range: -32768...32767
add_i32array	TIBRVMSG_I32ARRAY	Valid range: -2147483648... 2147483647
add_i64array	TIBRVMSG_I64ARRAY	n/a

Table 52–14 (Cont.) MGW_TIBRV_MSG_T Add Method Field Types

Method Name	Field Type Assigned	Comment
add_opaque	TIBRVMSG_OPAQUE	Value stored as RAW if size < 2000; otherwise value stored in BLOB
add_string	TIBRVMSG_STRING	Value stored as VARCHAR2 if size < 4000; otherwise value stored in CLOB
add_xml	TIBRVMSG_XML	Value stored as RAW if size < 2000; otherwise value stored in BLOB

SET_<> Methods

Accessor methods to set an instance attribute to a specific value.

Syntax

```
MEMBER PROCEDURE SET_<> (
    value IN datatype );
```

Parameters

Table 52–15 SYS.MGW_TIBRV_MSG_T SET_<> Method Parameters

Parameter	Description
value	Value to be assigned

GET_<> Methods

Accessor methods to retrieve the value for an instance attribute.

Syntax

```
MEMBER PROCEDURE GET_<>
RETURN datatype;
```

Parameters

None

Return Values

Returns the attribute value.

GET_FIELD_COUNT Procedure

Gets the number of message fields.

Syntax

```
MEMBER PROCEDURE get_field_count  
RETURN INTEGER;
```

Parameters

None

Return Values

Returns the number of fields, or zero (0) if there are none.

GET_FIELD Procedure

Retrieves field information for the field having a given field collection index. This method should only be called if `get_field_count()` returns a nonzero value and `idx` must specify a valid collection index; that is, $1 \leq idx \leq get_field_count()$.

Syntax

```
MEMBER PROCEDURE get_field (  
    idx    IN    INTEGER )  
RETURN SYS.MGW_TIBRV_FIELD_T;
```

Parameters

Table 52–16 *SYS.MGW_TIBRV_MSG_T GET_FIELD Procedure Parameters*

Parameter	Description
<code>idx</code>	Specifies the 1-based field collection index of the field to retrieve

Note: A 1-based index begins at one (1) instead of zero (0).

Return Values

Returns the field information.

GET_FIELD_BY_NAME Procedure

Retrieves field information for the first field that has a given field name. The name comparison is case-sensitive.

Syntax

```
MEMBER PROCEDURE get_field_by_name (
    name IN VARCHAR2 )
RETURN SYS.MGW_TIBRV_FIELD_T;
```

Parameters

Table 52–17 SYS.MGW_TIBRV_MSG_T GET_FIELD_BY_NAME Procedure Parameters

Parameter	Description
name	Specifies the field name to search for. This can be NULL to find the first field that does not have a field name.

Return Values

Returns the field information, or NULL if no match was found.

GET_FIELD_BY_ID Procedure

Retrieves field information for the first field that has a given field identifier.

A field can have either a unique identifier or no identifier. If the field identifier value is zero (0) or NULL, then the field is considered to have no identifier. Otherwise, the identifier is a nonzero value that is unique for all the fields of this message.

Syntax

```
MEMBER PROCEDURE get_field_by_id (
    id IN INTEGER )
RETURN SYS.MGW_TIBRV_FIELD_T;
```

Parameters

Table 52–18 *SYS.MGW_TIBRV_MSG_T GET_FIELD_BY_ID Procedure Parameters*

Parameter	Description
id	Specifies the field identifier to search for. This can be zero (0) or NULL to find the first field that does not have an identifier.

Return Values

Returns the field information, or NULL if no match was found.

FIND_FIELD_NAME Procedure

Searches for a field with a given field name, starting from a given index of the field collection. It returns the index of that field. The name comparison is case-sensitive. This function is useful for finding all the fields that have the same name.

Syntax

```
MEMBER PROCEDURE find_field_name (
    name          IN  VARCHAR2,
    start_idx     IN  INTEGER )
RETURN INTEGER;
```

Parameters

Table 52–19 *SYS.MGW_TIBRV_MSG_T FIND_FIELD_NAME Procedure Parameters*

Parameter	Description
name	Specifies the field name to search for. This can be NULL to search for a field that does not have a field name.
start_idx	Specifies the 1-based field collection index from which the search should start.

Return Values

Returns the field index (> 0) if a match was found, or zero (0) if no match was found.

FIND_FIELD_ID Procedure

Searches for a field with a given field identifier, starting from a given index of the field collection. It returns the index of that field.

Syntax

```
MEMBER PROCEDURE find_field_id (
    id          IN INTEGER,
    start_idx  IN INTEGER )
RETURN        INTEGER;
```

Parameters

Table 52–20 *SYS.MGW_TIBRV_MSG_T FIND_FIELD_ID Procedure Parameters*

Parameter	Description
id	Specifies the field identifier to search for. This can be zero (0) or NULL to find a field that does not have an identifier.
start_idx	Specifies the 1-based field collection index from which the search should start.

Return Values

Returns the field index (> 0) if a match was found, or zero (0) if no match was found.

Summary of DBMS_MGWMSG Subprograms

Table 52–21 DBMS_MGWMSG Package Subprograms

Subprogram	Description
NVARRAY_ADD Procedure on page 52-25	Appends a name-value element to the end of a name-value array
NVARRAY_GET Function on page 52-26	Gets the name-value element of the name you specify in <code>p_name</code> from a name-value array
NVARRAY_GET_BOOLEAN Function on page 52-27	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>BOOLEAN_VALUE</code> value type
NVARRAY_GET_BYTE Function on page 52-28	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>BYTE_VALUE</code> value type
NVARRAY_GET_SHORT Function on page 52-29	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>SHORT_VALUE</code> value type
NVARRAY_GET_INTEGER Function on page 52-30	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>INTEGER_VALUE</code> value type
NVARRAY_GET_LONG Function on page 52-31	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>LONG_VALUE</code> value type
NVARRAY_GET_FLOAT Function on page 52-32	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>FLOAT_VALUE</code> value type
NVARRAY_GET_DOUBLE Function on page 52-33	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>DOUBLE_VALUE</code> value type
NVARRAY_GET_TEXT Function on page 52-34	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>TEXT_VALUE</code> value type
NVARRAY_GET_RAW Function on page 52-35	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>RAW_VALUE</code> value type
NVARRAY_GET_DATE Function on page 52-36	Gets the value of the name-value array element that you specify in <code>p_name</code> and with the <code>DATE_VALUE</code> value type
NVARRAY_FIND_NAME Function on page 52-37	Searches a name-value array for the element with the name you specify in <code>p_name</code>
NVARRAY_FIND_NAME_TYPE Function on page 52-38	Searches a name-value array for an element with the name and value type you specify

NVARRAY_ADD Procedure

This procedure appends a name-value element to the end of a name-value array.

Syntax

```
DBMS_MGWMSG.NVARRAY_ADD (  
    p_array IN OUT SYS.MGW_NAME_VALUE_ARRAY_T,  
    p_value IN     SYS.MGW_NAME_VALUE_T );
```

Parameters

Table 52–22 *NVARRAY_ADD Procedure Parameters*

Parameter	Description
<code>p_array</code>	On input, the name-value array instance to modify. If <code>NULL</code> , then a new array is created. On output, the modified name-value array instance.
<code>p_value</code>	The value to add. If <code>NULL</code> , then <code>p_array</code> is not changed.

NVARARRAY_GET Function

This function gets the name-value element of the name you specify in `p_name` from a name-value array.

Syntax

```
DBMS_MGWMSG.NVARARRAY_GET (  
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,  
    p_name     IN VARCHAR2,  
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )  
RETURN SYS.MGW_NAME_VALUE_T;
```

Parameters

Table 52–23 *NVARARRAY_GET Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the matching element, or `NULL` if the specified name is not found.

NVARRAY_GET_BOOLEAN Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `BOOLEAN_VALUE` value type.

Syntax

```
DBMS_MGWMSG.NVARRAY_GET_BOOLEAN (
    p_array      IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name       IN VARCHAR2,
    p_compare    IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN INTEGER;
```

Parameters

Table 52–24 NVARRAY_GET_BOOLEAN Function Parameters

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARARRAY_GET_BYTE Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `BYTE_VALUE` value type .

Syntax

```
DBMS_MGWMSG.NVARARRAY_GET_BYTE (  
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,  
    p_name     IN VARCHAR2,  
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )  
RETURN INTEGER;
```

Parameters

Table 52–25 *NVARARRAY_GET_BYTE Function*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARRAY_GET_SHORT Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `SHORT_VALUE` value type.

Syntax

```
DBMS_MGWMSG.NVARRAY_GET_SHORT (
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name     IN VARCHAR2,
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN INTEGER;
```

Parameters

Table 52–26 *NVARRAY_GET_SHORT Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARARRAY_GET_INTEGER Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `INTEGER_VALUE` value type.

Syntax

```
DBMS_MGWMSG.NVARARRAY_GET_INTEGER (  
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,  
    p_name     IN VARCHAR2,  
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )  
RETURN INTEGER;
```

Parameters

Table 52–27 *NVARARRAY_GET_INTEGER Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARRAY_GET_LONG Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `LONG_VALUE` value type.

Syntax

```
DBMS_MGWMSG.NVARRAY_GET_LONG (
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name     IN VARCHAR2,
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN NUMBER;
```

Parameters

Table 52–28 *NVARRAY_GET_LONG Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARRAY_GET_FLOAT Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `FLOAT_VALUE` value type .

Syntax

```
DBMS_MGWMSG.NVARRAY_GET_FLOAT (
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name     IN VARCHAR2,
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN NUMBER;
```

Parameters

Table 52–29 *NVARRAY_GET_FLOAT Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARRAY_GET_DOUBLE Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `DOUBLE_VALUE` value type.

Syntax

```
DBMS_MGWMSG.NVARRAY_GET_DOUBLE (
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name     IN VARCHAR2,
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN NUMBER;
```

Parameters

Table 52–30 NVARRAY_GET_DOUBLE Function Parameters

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARRAY_GET_TEXT Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `TEXT_VALUE` value type.

Syntax

```
DBMS_MGWMSG.NVARRAY_GET_TEXT (
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name     IN VARCHAR2,
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN VARCHAR2;
```

Parameters

Table 52–31 *NVARRAY_GET_TEXT Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARRAY_GET_RAW Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `RAW_VALUE` value type.

Syntax

```
DBMS_MGWMSG.NVARRAY_GET_RAW (
    p_array      IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name       IN VARCHAR2,
    p_compare    IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN RAW;
```

Parameters

Table 52–32 *NVARRAY_GET_RAW Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARARRAY_GET_DATE Function

This function gets the value of the name-value array element that you specify in `p_name` and with the `DATE_VALUE` value type .

Syntax

```
DBMS_MGWMSG.NVARARRAY_GET_DATE (  
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,  
    p_name     IN VARCHAR2,  
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )  
RETURN DATE;
```

Parameters

Table 52–33 *NVARARRAY_GET_DATE Function Parameters*

Parameters	Description
<code>p_array</code>	The name-value array
<code>p_name</code>	The value name
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns the value, or `NULL` if either the specified name is not found or a type mismatch exists.

NVARRAY_FIND_NAME Function

This function searches a name-value array for the element with the name you specify in `p_name`.

Syntax

```
DBMS_MGWMSG.NVARRAY_FIND_NAME (
    p_array      IN SYS.MGW_NAME_VALUE_ARRAY_T,
    p_name       IN VARCHAR2,
    p_compare    IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )
RETURN BINARY_INTEGER;
```

Parameters

Table 52–34 *NVARRAY_FIND_NAME Function Parameters*

Parameters	Description
<code>p_array</code>	The name-value array to search
<code>p_name</code>	The name to find
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns a positive integer that is the array index of the matching element or zero (0) if the specified name is not found.

NVARARRAY_FIND_NAME_TYPE Function

This function searches a name-value array for an element with the name and value type you specify.

Syntax

```
DBMS_MGWMSG.NVARARRAY_FIND_NAME_TYPE (  
    p_array    IN SYS.MGW_NAME_VALUE_ARRAY_T,  
    p_name     IN VARCHAR2,  
    p_type     IN BINARY_INTEGER  
    p_compare  IN BINARY_INTEGER DEFAULT CASE_SENSITIVE )  
RETURN BINARY_INTEGER;
```

Parameters

Table 52–35 *NVARARRAY_FIND_NAME_TYPE Function Parameters*

Parameter	Description
<code>p_array</code>	The name-value array to search
<code>p_name</code>	The name to find
<code>p_type</code>	The value type. Refer to the value type constants in Table 52–1 on page 52-2.
<code>p_compare</code>	Name comparison method. Values are <code>CASE_SENSITIVE</code> and <code>CASE_INSENSITIVE</code> .

Return Values

Returns a positive integer that is the array index of the matching element, zero (0) if the specified name is not found, or negative one (-1) if the specified name is found but a type mismatch exists.

DBMS_MONITOR

The DBMS_MONITOR package let you use PL/SQL for controlling additional tracing and statistics gathering.

The chapter contains the following topics:

- [Summary of DBMS_MONITOR Subprograms](#)

Summary of DBMS_MONITOR Subprograms

Table 53–1 DBMS_MONITOR Package Subprograms

Subprogram	Description
CLIENT_ID_STAT_DISABLE Procedure on page 53-3	Disables statistic gathering previously enabled for a given Client Identifier
CLIENT_ID_STAT_ENABLE Procedure on page 53-4	Enables statistic gathering for a given Client Identifier
CLIENT_ID_TRACE_DISABLE Procedure on page 53-5	Disables the trace previously enabled for a given Client Identifier globally for the database
CLIENT_ID_TRACE_ENABLE Procedure on page 53-6	Enables the trace for a given Client Identifier globally for the database
SERV_MOD_ACT_STAT_DISABLE Procedure on page 53-7	Disables statistic gathering enabled for a given combination of Service Name, MODULE and ACTION
SERV_MOD_ACT_STAT_ENABLE Procedure on page 53-8	Enables statistic gathering for a given combination of Service Name, MODULE and ACTION
SERV_MOD_ACT_TRACE_DISABLE Procedure on page 53-10	Disables the trace for ALL enabled instances for a or a given combination of Service Name, MODULE and ACTION name globally
SERV_MOD_ACT_TRACE_ENABLE Procedure on page 53-12	Enables SQL tracing for a given combination of Service Name, MODULE and ACTION globally unless an <code>instance_name</code> is specified
SESSION_TRACE_DISABLE Procedure on page 53-14	Disables the previously enabled trace for a given database session identifier (SID) on the local instance
SESSION_TRACE_ENABLE Procedure on page 53-15	Enables the trace for a given database session identifier (SID) on the local instance

CLIENT_ID_STAT_DISABLE Procedure

This procedure will disable statistics accumulation for all instances and remove the accumulated results from V\$CLIENT_STATS view enabled by the CLIENT_ID_STAT_ENABLE Procedure.

Syntax

```
DBMS_MONITOR.CLIENT_ID_STAT_DISABLE(  
    client_id          IN  VARCHAR2);
```

Parameters

Table 53–2 CLIENT_ID_STAT_DISABLE Procedure Parameters

Parameter	Description
client_id	The Client Identifier for which statistic aggregation is disabled.

Examples

To disable accumulation:

```
EXECUTE DBMS_MONITOR.CLIENT_ID_STAT_DISABLE('janedoe');
```

CLIENT_ID_STAT_ENABLE Procedure

This procedure enables statistic gathering for a given Client Identifier. Statistics gathering is global for the database and persistent across instance starts and restarts. That is, statistics are enabled for all instances of the same database, including restarts. Statistics are viewable through V\$CLIENT_STATS views.

Syntax

```
DBMS_MONITOR.CLIENT_ID_STAT_ENABLE(  
    client_id          IN  VARCHAR2);
```

Parameters

Table 53–3 CLIENT_ID_STAT_ENABLE Procedure Parameters

Parameter	Description
client_id	The Client Identifier for which statistic aggregation is enabled.

Examples

To enable statistic accumulation for a client with a given client ID:

```
EXECUTE DBMS_MONITOR.CLIENT_ID_STAT_ENABLE('janedoe');
```

CLIENT_ID_TRACE_DISABLE Procedure

This procedure will disable tracing enabled by the CLIENT_ID_TRACE_ENABLE Procedure.

Syntax

```
DBMS_MONITOR.CLIENT_ID_TRACE_DISABLE(  
  client_id          IN  VARCHAR2);
```

Parameters

Table 53–4 CLIENT_ID_TRACE_DISABLE Procedure Parameters

Parameter	Description
client_id	The Client Identifier for which SQL tracing is disabled.

Examples

```
EXECUTE DBMS_MONITOR.CLIENT_ID_TRACE_DISABLE ('janedoe');
```

CLIENT_ID_TRACE_ENABLE Procedure

This procedure will enable the trace for a given client identifier globally for the database.

Syntax

```
DBMS_MONITOR.CLIENT_ID_TRACE_ENABLE(  
    client_id    IN  VARCHAR2,  
    waits       IN  BOOLEAN DEFAULT TRUE,  
    binds       IN  BOOLEAN DEFAULT FALSE);
```

Parameters

Table 53–5 CLIENT_ID_TRACE_ENABLE Procedure Parameters

Parameter	Description
client_id	Database Session Identifier for which SQL tracing is enabled.
waits	If TRUE, wait information is present in the trace.
binds	If TRUE, bind information is present in the trace.

Usage Notes

- The trace will be written to multiple trace files because more than one Oracle shadow process can work on behalf of a given client identifier.
- The tracing is enabled for all instances and persistent across restarts.

Examples

```
EXECUTE DBMS_MONITOR.CLIENT_ID_TRACE_ENABLE('janedoe', TRUE,  
FALSE);
```


SERV_MOD_ACT_STAT_DISABLE Procedure

This procedure will disable statistics accumulation and remove the accumulated results from V\$SERV_MOD_ACT_STATS view. Statistics disabling is persistent for the database. That is, service statistics are disabled for instances of the same database (plus dblinks that have been activated as a result of the enable).

Syntax

```
DBMS_MONITOR.SERV_MOD_ACT_STAT_DISABLE(
  service_name    IN VARCHAR2,
  module_name     IN VARCHAR2,
  action_name     IN VARCHAR2 DEFAULT ALL_ACTIONS);
```

Parameters

Table 53–6 *SERV_MOD_ACT_STAT_DISABLE Procedure Parameters*

Parameter	Description
service_name	Name of the service for which statistic aggregation is disabled.
module_name	Name of the MODULE. An additional qualifier for the service. It is a required parameter.
action_name	Name of the ACTION. An additional qualifier for the Service and MODULE name. Omitting the parameter (or supplying ALL_ACTIONS constant) means enabling aggregation for all Actions for a given Server/Module combination. In this case, statistics are aggregated on the module level.

SERV_MOD_ACT_STAT_ENABLE Procedure

This procedure enables statistic gathering for a given combination of Service Name, MODULE and ACTION. Calling this procedure enables statistic gathering for a hierarchical combination of Service name, MODULE name, and ACTION name on all instances for the same database. Statistics are accessible by means of the V\$SERV_MOD_ACT_STATS view.

Syntax

```
DBMS_MONITOR.SERV_MOD_ACT_STAT_ENABLE(
    service_name    IN VARCHAR2,
    module_name     IN VARCHAR2,
    action_name     IN VARCHAR2 DEFAULT ALL_ACTIONS);
```

Parameters

Table 53–7 *SERV_MOD_ACT_STAT_ENABLE Procedure Parameters*

Parameter	Description
service_name	Name of the service for which statistic aggregation is enabled.
module_name	Name of the MODULE. An additional qualifier for the service. It is a required parameter.
action_name	Name of the ACTION. An additional qualifier for the Service and MODULE name. Omitting the parameter (or supplying ALL_ACTIONS constant) means enabling aggregation for all Actions for a given Server/Module combination. In this case, statistics are aggregated on the module level.

Usage Notes

Enabling statistic aggregation for the given combination of Service/Module/Action names is slightly complicated by the fact that the Module/Action values can be empty strings which are indistinguishable from NULLs. For this reason, we adopt the following conventions:

A special constant (unlikely to be a real action names) is defined:

```
ALL_ACTIONS constant VARCHAR2 := '###ALL_ACTIONS';
```

Using `ALL_ACTIONS` for a module specification means that aggregation is enabled for all actions with a given module name, while using `NULL` (or empty string) means that aggregation is enabled for an action whose name is an empty string.

Examples

To enable statistic accumulation for a given combination of Service name and MODULE:

```
EXECUTE DBMS_MONITOR.SERV_MOD_ACT_STAT_ENABLE( 'APPS1', 'PAYROLL' );
```

To enable statistic accumulation for a given combination of Service name, MODULE and ACTION:

```
EXECUTE  
DBMS_MONITOR.SERV_MOD_ACT_STAT_ENABLE( 'APPS1', 'GLEDGER', 'DEBIT_ENTRY' );
```

If both of the preceding commands are issued, statistics are accumulated as follows:

- For the `APPS1` service, because accumulation for each Service Name is the default.
- For all actions in the `PAYROLL` Module.
- For the `DEBIT_ENTRY` Action within the `GLEDGER` Module.

SERV_MOD_ACT_TRACE_DISABLE Procedure

This procedure will disable the trace at ALL enabled instances for a given combination of Service Name, MODULE, and ACTION name globally.

Syntax

```
DBMS_MONITOR.SERV_MOD_ACT_TRACE_DISABLE(  
    service_name    IN VARCHAR2,  
    module_name     IN VARCHAR2,  
    action_name     IN VARCHAR2 DEFAULT ALL_ACTIONS,  
    instance_name   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 53–8 *SERV_MOD_ACT_TRACE_DISABLE Procedure Parameters*

Parameter	Description
<code>service_name</code>	Name of the service for which tracing is disabled.
<code>module_name</code>	Name of the MODULE. An additional qualifier for the service.
<code>action_name</code>	Name of the ACTION. An additional qualifier for the Service and MODULE name.
<code>instance_name</code>	If set, this restricts tracing to the named <code>instance_name</code> .

Usage Notes

Specifying `NULL` for the `module_name` parameter means that statistics will no longer be accumulated for the sessions which do not set the `MODULE` attribute.

Examples

To enable tracing for a Service named APPS1:

```
EXECUTE DBMS_MONITOR.SERV_MOD_ACT_TRACE_ENABLE('APPS1',  
    DBMS_MONITOR.ALL_MODULES, DBMS_MONITOR.ALL_ACTIONS, TRUE,  
    FALSE, NULL);
```

To disable tracing specified in the previous step:

```
EXECUTE DBMS_MONITOR.SERV_MOD_ACT_TRACE_DISABLE('APPS1');
```

To enable tracing for a given combination of Service and MODULE (all ACTIONS):

```
EXECUTE DBMS_MONITOR.SERV_MOD_ACT_TRACE_ENABLE('APPS1', 'PAYROLL',  
DBMS_MONITOR.ALL_ACTIONS, TRUE, FALSE, NULL);
```

To disable tracing specified in the previous step:

```
EXECUTE DBMS_MONITOR.SERV_MOD_ACT_TRACE_DISABLE('APPS1', 'PAYROLL');
```

SERV_MOD_ACT_TRACE_ENABLE Procedure

This procedure will enable SQL tracing for a given combination of Service Name, MODULE and ACTION globally unless an `instance_name` is specified.

Syntax

```
DBMS_MONITOR.SERV_MOD_ACT_TRACE_ENABLE(
  service_name  IN VARCHAR2,
  module_name   IN VARCHAR2 DEFAULT ANY_MODULE,
  action_name   IN VARCHAR2 DEFAULT ANY_ACTION,
  waits         IN BOOLEAN DEFAULT TRUE,
  binds        IN BOOLEAN DEFAULT FALSE,
  instance_name IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 53–9 *SERV_MOD_ACT_TRACE_ENABLE Procedure Parameters*

Parameter	Description
<code>service_name</code>	Name of the service for which tracing is enabled.
<code>module_name</code>	Name of the MODULE. An optional additional qualifier for the service.
<code>action_name</code>	Name of the ACTION. An optional additional qualifier for the Service and MODULE name.
<code>waits</code>	If TRUE, wait information is present in the trace.
<code>binds</code>	If TRUE, bind information is present in the trace.
<code>instance_name</code>	If set, this restricts tracing to the named <code>instance_name</code> .

Usage Notes

- The procedure enables a trace for a given combination of Service, MODULE and ACTION name. The specification is strictly hierarchical: Service Name or Service Name/MODULE, or Service Name, MODULE, and ACTION name must be specified. Omitting a qualifier behaves like a wild-card, so that not specifying an ACTION means all ACTIONS. Using the ALL_ACTIONS constant achieves the same purpose.
- This tracing is useful when an application MODULE and optionally known ACTION is experiencing poor service levels.

- By default, tracing is enabled globally for the database. The `instance_name` parameter is provided to restrict tracing to named instances that are known, for example, to exhibit poor service levels.
- Tracing information is present in multiple trace files and you must use the `trcsess` tool to collect it into a single file.
- Specifying `NULL` for the `module_name` parameter means that statistics will be accumulated for the sessions which do not set the `MODULE` attribute.

Examples

To enable tracing for a Service named `APPS1`:

```
EXECUTE DBMS_MONITOR.SERV_MOD_ACT_TRACE_ENABLE('APPS1',  
                                               DBMS_MONITOR.ALL_MODULES, DBMS_MONITOR.ALL_ACTIONS, TRUE,  
                                               FALSE, NULL);
```

To enable tracing for a given combination of Service and `MODULE` (all `ACTIONS`):

```
EXECUTE DBMS_MONITOR.SERV_MOD_ACT_TRACE_ENABLE('APPS1', 'PAYROLL',  
                                               DBMS_MONITOR.ALL_ACTIONS, TRUE, FALSE, NULL);
```

SESSION_TRACE_DISABLE Procedure

This procedure will disable the trace for a given database session at the local instance.

Syntax

```
DBMS_MONITOR.SESSION_TRACE_DISABLE(  
    session_id      IN      BINARY_INTEGER DEFAULT NULL,  
    serial_num      IN      BINARY_INTEGER DEFAULT NULL);
```

Parameters

Table 53–10 *SESSION_TRACE_DISABLE Procedure Parameters*

Parameter	Description
session_id	Name of the service for which SQL trace is disabled.
serial_num	Serial number for this session.

Usage Notes

If `serial_num` is `NULL` but `session_id` is specified, a session with a given `session_id` is no longer traced irrespective of its serial number. If both `session_id` and `serial_num` are `NULL`, the current user session is no longer traced. It is illegal to specify `NULL` `session_id` and non-`NULL` `serial_num`. In addition, the `NULL` values are default and can be omitted.

Examples

To enable tracing for a client with a given client session ID:

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE(7,4634, TRUE, FALSE);
```

To disable tracing specified in the previous step:

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_DISABLE(7,4634);;
```


SESSION_TRACE_ENABLE Procedure

This procedure enables a SQL trace for the given Session ID on the local instance

Syntax

```
DBMS_MONITOR.SESSION_TRACE_ENABLE(
    session_id  IN  BINARY_INTEGER DEFAULT NULL,
    serial_num  IN  BINARY_INTEGER DEFAULT NULL,
    waits       IN  BOOLEAN DEFAULT TRUE,
    binds       IN  BOOLEAN DEFAULT FALSE)
```

Parameters

Table 53–11 *SESSION_TRACE_ENABLE Procedure Parameters*

Parameter	Description
session_id	Database Session Identifier for which SQL tracing is enabled.
serial_num	Serial number for this session.
waits	If TRUE, wait information is present in the trace.
binds	If TRUE, bind information is present in the trace.

Usage Notes

The procedure enables a trace for a given database session, and is still useful for client/server applications. The trace is enabled only on the instance to which the caller is connected, since database sessions do not span instances. This tracing is strictly local to an instance.

If `serial_num` is NULL but `session_id` is specified, a session with a given `session_id` is traced irrespective of its serial number. If both `session_id` and `serial_num` are NULL, the current user session is traced. It is illegal to specify NULL `session_id` and non-NULL `serial_num`. In addition, the NULL values are default and can be omitted.

Examples

To enable tracing for a client with a given client session ID:

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE(7,4634, TRUE, FALSE);
```

To disable tracing specified in the previous step:

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_DISABLE(7,4634);
```

Either

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE(5);
```

or

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE(5, NULL);
```

traces the session with session ID of 5, while either

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE();
```

or

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE(NULL, NULL);
```

traces the current user session. Also,

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE(NULL, NULL, TRUE, TRUE);
```

traces the current user session including waits and binds. The same can be also expressed using keyword syntax:

```
EXECUTE DBMS_MONITOR.SESSION_TRACE_ENABLE(binds=>TRUE);
```

DBMS_MVIEW

DBMS_MVIEW enables you to understand capabilities for materialized views and potential materialized views, including their rewrite availability. It also enables you to refresh materialized views that are not part of the same refresh group and purge logs.

Note: DBMS_SNAPSHOT is a synonym for DBMS_MVIEW.

See Also:

- *Oracle Database Advanced Replication* for more information about using materialized views in a replication environment
- *Oracle Data Warehousing Guide* for more information about using materialized views in a data warehousing environment

This chapter contains the following topics:

- [Using DBMS_MVIEW](#)
 - [Operational Notes](#)
 - [Rules and Limits](#)
- [Summary of DBMS_MVIEW Subprograms](#)

Using DBMS_MVIEW

- [Operational Notes](#)
- [Rules and Limits](#)

Operational Notes

If a query is less than 256 characters long, you can invoke `EXPLAIN_REWRITE` using the `EXECUTE` command from `SQL*PLUS`. Otherwise, the recommended method is to use a PL/SQL `BEGIN . . END` block, as shown in the examples in `/rdbms/demo/smxrw.sql`.

Rules and Limits

The `EXPLAIN_REWRITE` procedure cannot accept queries longer than 32627 characters. These restrictions also apply when passing the defining query of a materialized view to the `EXPLAIN_MVIEW` procedure.

Summary of DBMS_MVIEW Subprograms

Table 54–1 DBMS_MVIEW Package Subprograms

Subprogram	Description
BEGIN_TABLE_REORGANIZATION Procedure on page 54-5	Performs a process to preserve materialized view data needed for refresh
END_TABLE_REORGANIZATION Procedure on page 54-6	Ensures that the materialized view data for the master table is valid and that the master table is in the proper state
ESTIMATE_MVIEW_SIZE Procedure on page 54-7	Estimates the size of a materialized view that you might create, in bytes and rows
EXPLAIN_MVIEW Procedure on page 54-8	Explains what is possible with a materialized view or potential materialized view
EXPLAIN_REWRITE Procedures on page 54-10	Explains why a query failed to rewrite or why the optimizer chose to rewrite a query with a particular materialized view
I_AM_A_REFRESH Function on page 54-12	Returns the value of the I_AM_REFRESH package state
PMARKER Function on page 54-13	Returns a partition marker from a rowid, and is used for Partition Change Tracking (PCT)
PURGE_DIRECT_LOAD_LOG Procedure on page 54-14	Purges rows from the direct loader log after they are no longer needed by any materialized views (used with data warehousing)
PURGE_LOG Procedure on page 54-15	Purges rows from the materialized view log
PURGE_MVIEW_FROM_LOG Procedure on page 54-16	Purges rows from the materialized view log
REFRESH Procedure on page 54-18	Refreshes one or more materialized views that are not members of the same refresh group
REFRESH_ALL_MVIEWS Procedure on page 54-21	Refreshes all materialized views that do not reflect changes to their master table or master materialized view
REFRESH_DEPENDENT Procedure on page 54-23	Refreshes all table-based materialized views that depend on a specified master table or master materialized view, or list of master tables or master materialized views

Table 54–1 (Cont.) DBMS_MVIEW Package Subprograms (Cont.)

Subprogram	Description
REGISTER_MVIEW Procedure on page 54-26	Enables the administration of individual materialized views
UNREGISTER_MVIEW Procedure on page 54-29	Enables the administration of individual materialized views once invoked at a master site or master materialized view site to unregister a materialized view

BEGIN_TABLE_REORGANIZATION Procedure

This procedure performs a process to preserve materialized view data needed for refresh. It must be called before a master table is reorganized.

Syntax

```
DBMS_MVIEW.BEGIN_TABLE_REORGANIZATION (  
    tabowner    IN    VARCHAR2,  
    tabname     IN    VARCHAR2);
```

Parameters

Table 54–2 *BEGIN_TABLE_REORGANIZATION Procedure Parameters*

Parameter	Description
tabowner	Owner of the table being reorganized.
tabname	Name of the table being reorganized.

END_TABLE_REORGANIZATION Procedure

This procedure ensures that the materialized view data for the master table is valid and that the master table is in the proper state. It must be called after a master table is reorganized.

Syntax

```
DBMS_MVIEW.END_TABLE_REORGANIZATION (  
    tabowner    IN    VARCHAR2,  
    tabname     IN    VARCHAR2);
```

Parameters

Table 54-3 *END_TABLE_REORGANIZATION Procedure Parameters*

Parameter	Description
tabowner	Owner of the table being reorganized.
tabname	Name of the table being reorganized.

ESTIMATE_MVIEW_SIZE Procedure

This procedure estimates the size of a materialized view that you might create, in bytes and number of rows.

Syntax

```
DBMS_MVIEW. ESTIMATE_MVIEW_SIZE (  
    stmt_id      IN  VARCHAR2,  
    select_clause IN  VARCHAR2,  
    num_rows     OUT NUMBER,  
    num_bytes    OUT NUMBER);
```

Parameters

Table 54–4 ESTIMATE_MVIEW_SIZE Procedure Parameters

Parameter	Datatype	Description
stmt_id	NUMBER	Arbitrary string used to identify the statement in an EXPLAIN PLAN.
select_clause	STRING	The SELECT statement to be analyzed.
num_rows	NUMBER	Estimated cardinality.
num_bytes	NUMBER	Estimated number of bytes.

EXPLAIN_MVIEW Procedure

This procedure enables you to learn what is possible with a materialized view or potential materialized view. For example, you can determine if a materialized view is fast refreshable and what types of query rewrite you can perform with a particular materialized view.

Using this procedure is straightforward. You simply call `DBMS_MVIEW.EXPLAIN_MVIEW`, passing in as parameters the schema and materialized view name for an existing materialized view. Alternatively, you can specify the `SELECT` string or `CREATE MATERIALIZED VIEW` statement for a potential materialized view. The materialized view or potential materialized view is then analyzed and the results are written into either a table called `MV_CAPABILITIES_TABLE`, which is the default, or to an array called `MSG_ARRAY`.

The procedure is overloaded:

- The first version is for explaining an existing or potential materialized view with output to `MV_CAPABILITIES_TABLE`.
- The second version is for explaining an existing or potential materialized view with output to a `VARRAY`:

Syntax

```
DBMS_MVIEW.EXPLAIN_MVIEW (
    mv          IN VARCHAR2,
    statement_id IN VARCHAR2:= NULL);
```

```
DBMS_MVIEW.EXPLAIN_MVIEW (
    mv          IN VARCHAR2,
    msg_array   OUT SYS.ExplainMVArrayType);
```

Parameters

Table 54–5 *EXPLAIN_MVIEW Procedure Parameters*

Parameter	Description
<code>mv</code>	The name of an existing materialized view (optionally qualified with the owner name separated by a ".") or a <code>SELECT</code> statement or a <code>CREATE MATERIALIZED VIEW</code> statement for a potential materialized view.

Table 54–5 *EXPLAIN_MVIEW Procedure Parameters*

Parameter	Description
<code>statement_id</code>	A client-supplied unique identifier to associate output rows with specific invocations of <code>EXPLAIN_MVIEW</code> .
<code>msg_array</code>	The PL/SQL varray that receives the output. Use this parameter to direct <code>EXPLAIN_MVIEW</code> 's output to a PL/SQL VARRAY rather than <code>MV_CAPABILITIES_TABLE</code> .

Usage Notes

You must run the `utlxmlv.sql` script to create `MV_CAPABILITIES_TABLE` in the current schema prior to calling `EXPLAIN_MVIEW` except when you direct output to a VARRAY. The script is found in the `admin` directory.

EXPLAIN_REWRITE Procedures

This procedure enables you to learn why a query failed to rewrite, or, if it rewrites, which materialized views will be used. Using the results from the procedure, you can take the appropriate action needed to make a query rewrite if at all possible. The query specified in the `EXPLAIN_REWRITE` statement is never actually executed.

Syntax

You can obtain the output from `EXPLAIN_REWRITE` in two ways. The first is to use a table, while the second is to create a `VARRAY`. The following shows the basic syntax for using an output table:

```
DBMS_MVIEW.EXPLAIN_REWRITE (
    query          IN [VARCHAR2 | CLOB],
    mv             IN VARCHAR2,
    statement_id   IN VARCHAR2;
```

If you want to direct the output of `EXPLAIN_REWRITE` to a `VARRAY`, instead of a table, then the procedure should be called as follows:

```
DBMS_MVIEW.EXPLAIN_REWRITE (
    query          IN [VARCHAR2 | CLOB],
    mv             IN VARCHAR2,
    msg_array      IN OUT SYS.RewriteArrayType);
```

Parameters

Table 54–6 *EXPLAIN_REWRITE Procedure Parameters*

Parameter	Description
<code>query</code>	SQL <code>SELECT</code> statement to be explained.
<code>mv</code>	The fully qualified name of an existing materialized view in the form of <code>SCHEMA.MV</code> .
<code>statement_id</code>	A client-supplied unique identifier to distinguish output messages.
<code>msg_array</code>	The PL/SQL varray that receives the output. Use this parameter to direct <code>EXPLAIN_REWRITE</code> 's output to a PL/SQL <code>VARRAY</code> .

Usage Notes

To obtain the output into a table, you must run the `utl_xrw.sql` script before calling `EXPLAIN_REWRITE`. This script creates a table named `REWRITE_TABLE` in the current schema.

I_AM_A_REFRESH Function

This function returns the value of the `I_AM_REFRESH` package state.

Syntax

```
DBMS_MVIEW.I_AM_A_REFRESH  
RETURN BOOLEAN;
```

Return Values

A return value of `true` indicates that all local replication triggers for materialized views are effectively disabled in this session because each replication trigger first checks this state. A return value of `false` indicates that these triggers are enabled.

PMARKER Function

This function returns a partition marker from a rowid. It is used for Partition Change Tracking (PCT).

Syntax

```
DBMS_MVIEW.PMARKER(  
    rid IN ROWID)  
RETURN NUMBER;
```

Parameters

Table 54–7 *PMARKER Procedure Parameters*

Parameter	Description
rid	The rowid of a row entry in a master table.

PURGE_DIRECT_LOAD_LOG Procedure

This procedure removes entries from the direct loader log after they are no longer needed for any known materialized view. This procedure usually is used in environments using Oracle's data warehousing technology.

See Also: *Oracle Data Warehousing Guide* for more information

Syntax

```
DBMS_MVIEW.PURGE_DIRECT_LOAD_LOG( );
```


PURGE_LOG Procedure

This procedure purges rows from the materialized view log.

Syntax

```
DBMS_MVIEW.PURGE_LOG (
  master      IN   VARCHAR2,
  num         IN   BINARY_INTEGER := 1,
  flag        IN   VARCHAR2      := 'NOP');
```

Parameters

Table 54–8 *PURGE_LOG Procedure Parameters*

Parameter	Description
master	Name of the master table or master materialized view.
num	<p>Number of least recently refreshed materialized views whose rows you want to remove from materialized view log. For example, the following statement deletes rows needed to refresh the two least recently refreshed materialized views:</p> <pre>DBMS_MVIEW.PURGE_LOG('master_table', 2);</pre> <p>To delete all rows in the materialized view log, indicate a high number of materialized views to disregard, as in this example:</p> <pre>DBMS_MVIEW.PURGE_LOG('master_table', 9999);</pre> <p>This statement completely purges the materialized view log that corresponds to <code>master_table</code> if fewer than 9999 materialized views are based on <code>master_table</code>. A simple materialized view whose rows have been purged from the materialized view log must be completely refreshed the next time it is refreshed.</p>
flag	<p>Specify <code>delete</code> to guarantee that rows are deleted from the materialized view log for at least one materialized view. This parameter can override the setting for the parameter <code>num</code>. For example, the following statement deletes rows from the materialized view log that has dependency rows in the least recently refreshed materialized view:</p> <pre>DBMS_MVIEW.PURGE_LOG('master_table', 1, 'delete');</pre>

PURGE_MVIEW_FROM_LOG Procedure

This procedure is called on the master site or master materialized view site to delete the rows in materialized view refresh related data dictionary tables maintained at the master for the specified materialized view identified by its `mview_id` or the combination of the `mviewowner`, `mviewname`, and the `mviewsite`. If the materialized view specified is the oldest materialized view to have refreshed from any of the master tables or master materialized views, then the materialized view log is also purged. This procedure does not unregister the materialized view.

Syntax

```
DBMS_MVIEW.PURGE_MVIEW_FROM_LOG (  
  mview_id      IN   BINARY_INTEGER |  
  mviewowner    IN   VARCHAR2,  
  mviewname     IN   VARCHAR2,  
  mviewsite     IN   VARCHAR2);
```

Note: This procedure is overloaded. The `mview_id` parameter is mutually exclusive with the three remaining parameters: `mviewowner`, `mviewname`, and `mviewsite`.

Parameters

Table 54–9 PURGE_MVIEW_FROM_LOG Procedure Parameters

Parameter	Description
<code>mview_id</code>	<p>If you want to execute this procedure based on the identification of the target materialized view, specify the materialized view identification using the <code>mview_id</code> parameter. Query the <code>DBA_BASE_TABLE_MVIEWS</code> view at the materialized view log site for a listing of materialized view IDs.</p> <p>Executing this procedure based on the materialized view identification is useful if the target materialized view is not listed in the list of registered materialized views (<code>DBA_REGISTERED_MVIEWS</code>).</p>
<code>mviewowner</code>	<p>If you do not specify a <code>mview_id</code>, enter the owner of the target materialized view using the <code>mviewowner</code> parameter. Query the <code>DBA_REGISTERED_MVIEWS</code> view at the materialized view log site to view the materialized view owners.</p>
<code>mviewname</code>	<p>If you do not specify a <code>mview_id</code>, enter the name of the target materialized view using the <code>mviewname</code> parameter. Query the <code>DBA_REGISTERED_MVIEWS</code> view at the materialized view log site to view the materialized view names.</p>
<code>mviewsite</code>	<p>If you do not specify a <code>mview_id</code>, enter the site of the target materialized view using the <code>mviewsite</code> parameter. Query the <code>DBA_REGISTERED_MVIEWS</code> view at the materialized view log site to view the materialized view sites.</p>

Usage Notes

If there is an error while purging one of the materialized view logs, the successful purge operations of the previous materialized view logs are not rolled back. This is to minimize the size of the materialized view logs. In case of an error, this procedure can be invoked again until all the materialized view logs are purged.

REFRESH Procedure

This procedure refreshes a list of materialized views.

Syntax

```
DBMS_MVIEW.REFRESH (
  { list          IN      VARCHAR2,
    | tab         IN      DBMS_UTILITY.UNCL_ARRAY, }
  method         IN      VARCHAR2      := NULL,
  rollback_seg   IN      VARCHAR2      := NULL,
  push_deferred_rpc IN    BOOLEAN      := true,
  refresh_after_errors IN    BOOLEAN    := false,
  purge_option    IN      BINARY_INTEGER := 1,
  parallelism    IN      BINARY_INTEGER := 0,
  heap_size      IN      BINARY_INTEGER := 0,
  atomic_refresh IN      BOOLEAN        := true,
  nested         IN      BOOLEAN        := false);
```

Note: This procedure is overloaded. The `list` and `tab` parameters are mutually exclusive.

Parameters

Table 54–10 REFRESH Procedure Parameters

Parameter	Description
<code>list</code> <code>tab</code>	<p>Comma-delimited list of materialized views that you want to refresh. (Synonyms are not supported.) These materialized views can be located in different schemas and have different master tables or master materialized views. However, all of the listed materialized views must be in your local database.</p> <p>Alternatively, you may pass in a PL/SQL index-by table of type <code>DBMS_UTILITY.UNCL_ARRAY</code>, where each element is the name of a materialized view.</p>

Table 54–10 (Cont.) REFRESH Procedure Parameters

Parameter	Description
method	<p>A string of refresh methods indicating how to refresh the listed materialized views. An <i>f</i> indicates fast refresh, <i>?</i> indicates force refresh, <i>C</i> or <i>c</i> indicates complete refresh, and <i>A</i> or <i>a</i> indicates always refresh. <i>A</i> and <i>C</i> are equivalent. <i>P</i> or <i>p</i> refreshes by recomputing the rows in the materialized view affected by changed partitions in the detail tables.</p> <p>If a materialized view does not have a corresponding refresh method (that is, if more materialized views are specified than refresh methods), then that materialized view is refreshed according to its default refresh method. For example, consider the following EXECUTE statement within SQL*Plus:</p> <pre> DBMS_MVIEW.REFRESH ('countries_mv,regions_mv,hr.employees_mv','cf'); </pre> <p>This statement performs a complete refresh of the <code>countries_mv</code> materialized view, a fast refresh of the <code>regions_mv</code> materialized view, and a default refresh of the <code>hr.employees</code> materialized view.</p>
rollback_seg	Name of the materialized view site rollback segment to use while refreshing materialized views.
push_deferred_rpc	Used by updatable materialized views only. Set this parameter to <code>true</code> if you want to push changes from the materialized view to its associated master tables or master materialized views before refreshing the materialized view. Otherwise, these changes may appear to be temporarily lost.
refresh_after_errors	If this parameter is <code>true</code> , an updatable materialized view continues to refresh even if there are outstanding conflicts logged in the DEFERROR view for the materialized view's master table or master materialized view. If this parameter is <code>true</code> and <code>atomic_refresh</code> is <code>false</code> , this procedure continues to refresh other materialized views if it fails while refreshing a materialized view.
purge_option	If you are using the parallel propagation mechanism (in other words, parallelism is set to 1 or greater), 0 means do not purge, 1 means lazy purge, and 2 means aggressive purge. In most cases, lazy purge is the optimal setting. Set purge to aggressive to trim the queue if multiple master replication groups are pushed to different target sites, and updates to one or more replication groups are infrequent and infrequently pushed. If all replication groups are infrequently updated and pushed, then set this parameter to 0 and occasionally execute PUSH with this parameter set to 2 to reduce the queue.

Table 54–10 (Cont.) REFRESH Procedure Parameters

Parameter	Description
parallelism	0 specifies serial propagation. $n > 1$ specifies parallel propagation with n parallel processes. 1 specifies parallel propagation using only one parallel process.
heap_size	Maximum number of transactions to be examined simultaneously for parallel propagation scheduling. Oracle automatically calculates the default setting for optimal performance. Note: Do not set this parameter unless directed to do so by Oracle Support Services.
atomic_refresh	If this parameter is set to <code>true</code> , then the list of materialized views is refreshed in a single transaction. All of the refreshed materialized views are updated to a single point in time. If the refresh fails for any of the materialized views, none of the materialized views are updated. If this parameter is set to <code>false</code> , then each of the materialized views is refreshed in a separate transaction.
nested	If <code>true</code> , then perform nested refresh operations for the specified set of materialized views. Nested refresh operations refresh all the depending materialized views and the specified set of materialized views based on a dependency order to ensure the nested materialized views are truly fresh with respect to the underlying base tables.

REFRESH_ALL_MVIEWS Procedure

This procedure refreshes all materialized views that have the following properties:

- The materialized view has not been refreshed since the most recent change to a master table or master materialized view on which it depends.
- The materialized view and all of the master tables or master materialized views on which it depends are local.
- The materialized view is in the view DBA_MVIEWS.

This procedure is intended for use with data warehouses.

Syntax

```
DBMS_MVIEW.REFRESH_ALL_MVIEWS (
  number_of_failures    OUT    BINARY_INTEGER,
  method                IN     VARCHAR2         := NULL,
  rollback_seg         IN     VARCHAR2         := NULL,
  refresh_after_errors IN     BOOLEAN          := false,
  atomic_refresh       IN     BOOLEAN          := true);
```

Parameters

Table 54–11 REFRESH_ALL_MVIEWS Procedure Parameters

Parameter	Description
number_of_failures	Returns the number of failures that occurred during processing.
method	A single refresh method indicating the type of refresh to perform for each materialized view that is refreshed. F or f indicates fast refresh, ? indicates force refresh, C or c indicates complete refresh, and A or a indicates always refresh. A and C are equivalent. If no method is specified, a materialized view is refreshed according to its default refresh method. P or p refreshes by recomputing the rows in the materialized view affected by changed partitions in the detail tables.
rollback_seg	Name of the materialized view site rollback segment to use while refreshing materialized views.

Table 54–11 (Cont.) REFRESH_ALL_MVIEWS Procedure Parameters

Parameter	Description
<code>refresh_after_errors</code>	If this parameter is <code>true</code> , an updatable materialized view continues to refresh even if there are outstanding conflicts logged in the <code>DEFERROR</code> view for the materialized view's master table or master materialized view. If this parameter is <code>true</code> and <code>atomic_refresh</code> is <code>false</code> , this procedure continues to refresh other materialized views if it fails while refreshing a materialized view.
<code>atomic_refresh</code>	<p>If this parameter is set to <code>true</code>, then the refreshed materialized views are refreshed in a single transaction. All of the refreshed materialized views are updated to a single point in time. If the refresh fails for any of the materialized views, none of the materialized views are updated.</p> <p>If this parameter is set to <code>false</code>, then each of the refreshed materialized views is refreshed in a separate transaction.</p>

REFRESH_DEPENDENT Procedure

This procedure refreshes all materialized views that have the following properties:

- The materialized view depends on a master table or master materialized view in the list of specified masters.
- The materialized view has not been refreshed since the most recent change to a master table or master materialized view on which it depends.
- The materialized view and all of the master tables or master materialized views on which it depends are local.
- The materialized view is in the view DBA_MVIEWS.

This procedure is intended for use with data warehouses.

Syntax

```
DBMS_MVIEW.REFRESH_DEPENDENT (
    number_of_failures    OUT    BINARY_INTEGER,
    { list                IN     VARCHAR2,
      | tab               IN     DBMS_UTILITY.UNCL_ARRAY, }
    method               IN     VARCHAR2      := NULL,
    rollback_seg         IN     VARCHAR2      := NULL,
    refresh_after_errors IN     BOOLEAN       := false,
    atomic_refresh       IN     BOOLEAN       := true,
    nested               IN     BOOLEAN       := false);
```

Note: This procedure is overloaded. The `list` and `tab` parameters are mutually exclusive.

Parameters

Table 54–12 REFRESH_DEPENDENT Procedure Parameters

Parameter	Description
number_of_failures	Returns the number of failures that occurred during processing.

Table 54–12 (Cont.) REFRESH_DEPENDENT Procedure Parameters

Parameter	Description
<code>list tab</code>	<p>Comma-delimited list of master tables or master materialized views on which materialized views can depend. (Synonyms are not supported.) These tables and the materialized views that depend on them can be located in different schemas. However, all of the tables and materialized views must be in your local database.</p> <p>Alternatively, you may pass in a PL/SQL index-by table of type <code>DBMS_UTILITY.UNCL_ARRAY</code>, where each element is the name of a table.</p>
<code>method</code>	<p>A string of refresh methods indicating how to refresh the dependent materialized views. All of the materialized views that depend on a particular table are refreshed according to the refresh method associated with that table. <code>F</code> or <code>f</code> indicates fast refresh, <code>?</code> indicates force refresh, <code>C</code> or <code>c</code> indicates complete refresh, and <code>A</code> or <code>a</code> indicates always refresh. <code>A</code> and <code>C</code> are equivalent. <code>P</code> or <code>p</code> refreshes by recomputing the rows in the materialized view affected by changed partitions in the detail tables.</p> <p>If a table does not have a corresponding refresh method (that is, if more tables are specified than refresh methods), then any materialized view that depends on that table is refreshed according to its default refresh method. For example, the following <code>EXECUTE</code> statement within <code>SQL*Plus</code>:</p> <pre>DBMS_MVIEW.REFRESH_DEPENDENT ('employees,departments,hr.regions','cf');</pre> <p>performs a complete refresh of the materialized views that depend on the <code>employees</code> table, a fast refresh of the materialized views that depend on the <code>departments</code> table, and a default refresh of the materialized views that depend on the <code>hr.regions</code> table.</p>
<code>rollback_seg</code>	Name of the materialized view site rollback segment to use while refreshing materialized views.
<code>refresh_after_errors</code>	If this parameter is <code>true</code> , an updatable materialized view continues to refresh even if there are outstanding conflicts logged in the <code>DEFERROR</code> view for the materialized view's master table or master materialized view. If this parameter is <code>true</code> and <code>atomic_refresh</code> is <code>false</code> , this procedure continues to refresh other materialized views if it fails while refreshing a materialized view.

Table 54–12 (Cont.) REFRESH_DEPENDENT Procedure Parameters

Parameter	Description
<code>atomic_refresh</code>	<p>If this parameter is set to <code>true</code>, then the refreshed materialized views are refreshed in a single transaction. All of the refreshed materialized views are updated to a single point in time. If the refresh fails for any of the materialized views, none of the materialized views are updated.</p> <p>If this parameter is set to <code>false</code>, then each of the refreshed materialized views is refreshed in a separate transaction.</p>
<code>nested</code>	<p>If <code>true</code>, then perform nested refresh operations for the specified set of tables. Nested refresh operations refresh all the depending materialized views of the specified set of tables based on a dependency order to ensure the nested materialized views are truly fresh with respect to the underlying base tables.</p>

REGISTER_MVIEW Procedure

This procedure enables the administration of individual materialized views. It is invoked at a master site or master materialized view site to register a materialized view.

Note that, typically, a materialized view is registered automatically during materialized view creation. You should only run this procedure to manually register a materialized view if the automatic registration failed or if the registration information was deleted.

Syntax

```
DBMS_MVIEW.REGISTER_MVIEW (
  mviewowner  IN   VARCHAR2,
  mviewname   IN   VARCHAR2,
  mviewsite   IN   VARCHAR2,
  mview_id    IN   DATE | BINARY_INTEGER,
  flag        IN   BINARY_INTEGER,
  qry_txt     IN   VARCHAR2,
  rep_type    IN   BINARY_INTEGER := DBMS_MVIEW.REG_UNKNOWN);
```

Parameters

Table 54–13 REGISTER_MVIEW Procedure Parameters

Parameter	Description
mviewowner	Owner of the materialized view.
mviewname	Name of the materialized view.
mviewsite	Name of the materialized view site for a materialized view registering at an Oracle database version 8.x and higher master site or master materialized view site. This name should not contain any double quotes.
mview_id	The identification number of the materialized view. Specify an Oracle database version 8.x and higher materialized view as a BINARY_INTEGER. Specify an Oracle database version 7 materialized view registering at an Oracle database version 8.x and higher master sites or master materialized view sites as a DATE.

Table 54–13 REGISTER_MVIEW Procedure Parameters

Parameter	Description
flag	<p>A constant that describes the properties of the materialized view being registered. Valid constants that can be assigned include the following:</p> <p>DBMS_MVIEW.REG_ROWID_MVIEW for a rowid materialized view</p> <p>DBMS_MVIEW.REG_PRIMARY_KEY_MVIEW for a primary key materialized view</p> <p>DBMS_MVIEW.REG_OBJECT_ID_MVIEW for an object id materialized view</p> <p>DBMS_MVIEW.REG_FAST_REFRESHABLE_MVIEW for a materialized view that can be fast refreshed</p> <p>DBMS_MVIEW.REG_UPDATABLE_MVIEW for a materialized view that is updatable</p> <p>A materialized view can have more than one of these properties. In this case, use the plus sign (+) to specify more than one property. For example, if a primary key materialized view can be fast refreshed, you can enter the following for this parameter:</p> <p>DBMS_MVIEW.REG_PRIMARY_KEY_MVIEW + DBMS_MVIEW.REG_FAST_REFRESHABLE_MVIEW</p> <p>You can determine the properties of a materialized view by querying the ALL_MVIEWS data dictionary view.</p>
qry_txt	The first 32,000 bytes of the materialized view definition query.
rep_type	<p>Version of the materialized view. Valid constants that can be assigned include the following:</p> <p>DBMS_MVIEW.REG_V7_SNAPSHOT if the materialized view is at an Oracle database version 7 site</p> <p>DBMS_MVIEW.REG_V8_SNAPSHOT if the materialized view is at an Oracle database version 8.x or higher site</p> <p>DBMS_MVIEW.REG_UNKNOWN (the default) if you do not know whether the materialized view is at an Oracle database version 7 site or an Oracle database version 8.x (or higher) site</p>

Usage Notes

This procedure is invoked at the master site or master materialized view site by a remote materialized view site using a remote procedure call. If REGISTER_MVIEW is called multiple times with the same mviewowner, mviewname, and mviewsite, then the most recent values for mview_id, flag, and qry_txt are stored. If a query exceeds the maximum VARCHAR2 size, then qry_txt contains the first 32000 characters of the query and the remainder is truncated. When invoked manually,

the value of `mview_id` must be looked up in the materialized view data dictionary views by the person who calls the procedure.

UNREGISTER_MVIEW Procedure

This procedure enables the administration of individual materialized views. It is invoked at a master site or master materialized view site to unregister a materialized view.

Syntax

```
DBMS_MVIEW.UNREGISTER_MVIEW (  
    mviewowner      IN   VARCHAR2,  
    mviewname       IN   VARCHAR2,  
    mviewsite       IN   VARCHAR2);
```

Parameters

Table 54–14 UNREGISTER_MVIEW Procedure Parameters

Parameters	Description
mviewowner	Owner of the materialized view.
mviewname	Name of the materialized view.
mviewsite	Name of the materialized view site.

DBMS_OBFUSCATION_TOOLKIT

DBMS_OBFUSCATION_TOOLKIT enables an application to encrypt data using either the Data Encryption Standard (DES) or the Triple DES algorithms.

This chapter contains the following topics:

- [Using DBMS_OBFUSCATION_TOOLKIT](#)
 - [Overview](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_OBFUSCATION Subprograms](#)

Using DBMS_OBFUSCATION_TOOLKIT

- [Overview](#)
- [Security Model](#)
- [Operational Notes](#)

Overview

The Data Encryption Standard (DES), also known as the Data Encryption Algorithm (DEA) by the American National Standards Institute (ANSI) and DEA-1 by the International Standards Organization (ISO), has been a worldwide encryption standard for over 20 years. The banking industry has also adopted DES-based standards for transactions between private financial institutions, and between financial institutions and private individuals. DES will eventually be replaced by a new Advanced Encryption Standard (AES).

DES is a symmetric key cipher; that is, the same key is used to encrypt data as well as decrypt data. DES encrypts data in 64-bit blocks using a 56-bit key. The DES algorithm ignores 8 bits of the 64-bit key that is supplied; however, you must supply a 64-bit key to the algorithm.

Triple DES (3DES) is a far stronger cipher than DES; the resulting ciphertext (encrypted data) is much harder to break using an exhaustive search: 2^{112} or 2^{168} attempts instead of 2^{56} attempts. Triple DES is also not as vulnerable to certain types of cryptanalysis as is DES.

Security Model

Oracle installs this package in the SYS schema. You can then grant package access to existing users and roles as needed. The package also grants access to the PUBLIC role so no explicit grant needs to be done.

Operational Notes

- [Key Management](#)
- [Storing the Key in the Database](#)
- [Storing the Key in the Operating System](#)
- [User-Supplied Keys](#)

Key Management

Key management, including both generation and secure storage of cryptographic keys, is one of the most important aspects of encryption. If keys are poorly chosen or stored improperly, then it is far easier for a malefactor to break the encryption. Rather than using an exhaustive key search attack (that is, cycling through all the possible keys in hopes of finding the correct decryption key), cryptanalysts typically seek weaknesses in the choice of keys, or the way in which keys are stored.

Key generation is an important aspect of encryption. Typically, keys are generated automatically through a random-number generator. Provided that the random number generation is cryptographically secure, this can be an acceptable form of key generation. However, if random numbers are not cryptographically secure, but have elements of predictability, the security of the encryption may be easily compromised.

The `DBMS_OBFUSCATION_TOOLKIT` package includes tools for generating random material that can be used for encryption keys, but it does not provide a mechanism for maintaining them. Care must be taken by the application developer to ensure the secure generation and storage of encryption keys used with this package. Furthermore, the encryption and decryption done by the `DBMS_OBFUSCATION_TOOLKIT` takes place on the server, not the client. If the key is passed over the connection between the client and the server, the connection must be protected by using network encryption. Otherwise, the key is vulnerable to capture over the wire. See *Oracle Advanced Security Administrator's Guide* for information about configuring and using network encryption for Oracle Net.

Key storage is one of the most important, yet difficult aspects of encryption and one of the hardest to manage properly. To recover data encrypted with a symmetric key, the key must be accessible to the application or user seeking to decrypt data. The key needs to be easy enough to retrieve that users can access encrypted data when they need to without significant performance degradation. The key also needs to be secure enough that it is not easily recoverable by unauthorized users trying to access encrypted data that they are not supposed to see.

The three options available are:

- Store the key in the database
- Store the key in the operating system
- Have the user manage the key

Storing the Key in the Database

Storing the keys in the database cannot always provide bullet-proof security if you are trying to protect data against the DBA accessing encrypted data (since an all-privileged DBA can access tables containing encryption keys), but it can provide security against the casual snooper, or against someone compromising the database files on the operating system. Furthermore, the security you can obtain by storing keys in the database does not have to be bullet-proof in order to be extremely useful.

For example, suppose you want to encrypt an employee's social security number, one of the columns in table `EMP`. You could encrypt each employee's SSN using a key which is stored in a separate column in `EMP`. However, anyone with `SELECT` access on the `EMP` table could retrieve the encryption key and decrypt the matching social security number. Alternatively, you could store the encryption keys in another table, and use a package to retrieve the correct key for the encrypted data item, based on a primary key-foreign key relationship between the tables.

You can envelope both the `DBMS_OBFUSCATION_TOOLKIT` package and the procedure to retrieve the encryption keys supplied to the package. Furthermore, the encryption key itself could be transformed in some way (for example, XORed with the foreign key to the `EMP` table) so that the key itself is not stored in easily recoverable form.

Oracle recommends using the wrap utility of PL/SQL to obfuscate the code within a PL/SQL package itself that does the encryption. That prevents people from breaking the encryption by looking at the PL/SQL code that handles keys, calls encrypting routines, and so on. In other words, use the wrap utility to obfuscate the PL/SQL packages themselves. This scheme is secure enough to prevent users with `SELECT` access to `EMP` from reading unencrypted sensitive data, and a DBA from easily retrieving encryption keys and using them to decrypt data in the `EMP` table. It can be made more secure by changing encryption keys regularly, or having a better key storage algorithm (so the keys themselves are encrypted, for example).

Storing the Key in the Operating System

Storing keys in a flat file in the operating system is another option. You can make callouts from PL/SQL, which you can use to retrieve encryption keys. If you store keys in a file and make callouts to retrieve the keys, the security of your encrypted data is only as secure as the protection of the key file on the operating system. Of course, a user retrieving keys from the operating system would have to be able to either access the Oracle database files (to decrypt encrypted data), or be able to gain access to the table in which the encrypted data is stored as a legitimate user.

User-Supplied Keys

If you ask a user to supply the key, it is crucial that you use network encryption, such as that provided by Oracle Advanced Security, so the key is not passed from client to server in the clear. The user must remember the key, or your data is not recoverable.

Summary of DBMS_OBFUSCATION Subprograms

Table 55–1 *DBMS_OBFUSCATION Package Subprograms*

Subprogram	Description
DES3DECRYPT Procedures and Functions on page 55-7	Generates the decrypted form of the input data
DES3ENCRYPT Procedures and Functions on page 55-10	Generates the encrypted form of the input data by passing it through the Triple DES encryption algorithm
DES3GETKEY Procedures and Functions on page 55-13	Takes a random value and uses it to generate an encryption key, using Triple DES
DESDECRYPT Procedures and Functions on page 55-14	Generates the decrypted form of the input data
DESENCRYPT Procedures and Functions on page 55-16	Generates the encrypted form of the input data
DESGETKEY Procedures and Functions on page 55-18	Takes a random value and uses it to generate an encryption key
MD5 Procedures and Functions on page 55-19	Generates MD5 hashes of data

DES3DECRYPT Procedures and Functions

These subprograms generate the decrypted form of the input data.

For a discussion of the initialization vector that you can use with this procedure, see the section, "[DES3ENCRYPT Procedures and Functions](#)" on page 55-10.

Syntax

```
DBMS_OBFUSCATION_TOOLKIT.DES3Decrypt(
  input          IN  RAW,
  key            IN  RAW,
  decrypted_data OUT  RAW,
  which          IN  PLS_INTEGER DEFAULT TwoKeyMode
  iv            IN  RAW          DEFAULT NULL);
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3Decrypt(
  input_string  IN  VARCHAR2,
  key_string    IN  VARCHAR2,
  decrypted_string OUT VARCHAR2,
  which         IN  PLS_INTEGER DEFAULT TwoKeyMode
  iv_string     IN  VARCHAR2   DEFAULTL NULL);
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3Decrypt(
  input      IN  RAW,
  key        IN  RAW,
  which      IN  PLS_INTEGER DEFAULT TwoKeyMode
  iv        IN  RAW          DEFAULT NULL)
RETURN RAW;
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3Decrypt(
  input_string IN  VARCHAR2,
  key_string   IN  VARCHAR2,
  which        IN  PLS_INTEGER DEFAULT TwoKeyMode
  iv_string    IN  VARCHAR2   DEFAULT NULL)
RETURN VARCHAR2;
```

Parameters

Table 55–2 *DES3DECRYPT Parameters for Raw Data*

Parameter	Description
input	Data to be decrypted

Table 55–2 *DES3DECRYPT Parameters for Raw Data*

Parameter	Description
key	Decryption key
decrypted_data	Decrypted data
which	If = 0, (default), then TwoKeyMode is used. If = 1, then ThreeKeyMode is used.
iv	Initialization vector
input_string	String to be decrypted
key_string	Decryption key string
decrypted_string	Decrypted string
iv_string	Initialization vector

Usage Notes

If the input data or key given to the `DES3DECRYPT` procedure is empty, then the procedure raises the error `ORA-28231 "Invalid input to Obfuscation toolkit."`

If the input data given to the `DES3DECRYPT` procedure is not a multiple of 8 bytes, the procedure raises the error `ORA-28232 "Invalid input size for Obfuscation toolkit."` `ORA-28233` is NOT applicable for the `DES3DECRYPT` function.

If the key length is missing or is less than 8 bytes, then the procedure raises the error `ORA-28234 "Key length too short."` Note that if larger keys are used, extra bytes are ignored. So a 9-byte key will not generate an exception.

If an incorrect value is specified for the `WHICH` parameter, `ORA-28236 "Invalid Triple DES mode"` is generated. Only the values 0 (`TwoKeyMode`) and 1 (`ThreeKeyMode`) are valid.

Restrictions

You must supply a single key of either 128 bits for a 2-key implementation (of which only 112 are used), or a single key of 192 bits for a 3-key implementation (of which 168 bits are used). Oracle automatically truncates the supplied key into 56-bit lengths for decryption. This key length is fixed and cannot be altered.

Note: Both the key length limitation and the prevention of multiple encryption passes are requirements of U.S. regulations governing the export of cryptographic products.

DES3ENCRYPT Procedures and Functions

These subprograms generate the encrypted form of the input data by passing it through the Triple DES (3DES) encryption algorithm.

Oracle's implementation of 3DES supports either a 2-key or 3-key implementation, in outer cipher-block-chaining (CBC) mode.

Syntax

```
DBMS_OBFUSCATION_TOOLKIT.DES3Encrypt(  
  input      IN      RAW,  
  key        IN      RAW,  
  encrypted_data OUT    RAW,  
  which      IN      PLS_INTEGER DEFAULT TwoKeyMode  
  iv         IN      RAW          DEFAULT NULL);
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3Encrypt(  
  input_string IN      VARCHAR2,  
  key_string   IN      VARCHAR2,  
  encrypted_string OUT  VARCHAR2,  
  which        IN      PLS_INTEGER DEFAULT TwoKeyMode  
  iv_string    IN      VARCHAR2   DEFAULT NULL);
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3Encrypt(  
  input      IN RAW,  
  key        IN RAW,  
  which      IN PLS_INTEGER DEFAULT TwoKeyMode  
  iv         IN RAW          DEFAULT NULL)  
RETURN RAW;
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3Encrypt(  
  input_string IN VARCHAR2,  
  key_string   IN VARCHAR2,  
  which        IN PLS_INTEGER DEFAULT TwoKeyMode  
  iv_string    IN VARCHAR2   DEFAULT NULL)  
RETURN VARCHAR2;
```

Parameters

Table 55–3 *DES3ENCRYPT Parameters Procedure and Function*

Parameter	Description
input	Data to be encrypted.
key	Encryption key.
encrypted_data	Encrypted data.
which	If = 0, (default), then <code>TwoKeyMode</code> is used. If = 1, then <code>ThreeKeyMode</code> is used.
iv	Initialization vector.
input_string	String to be encrypted.
key_string	Encryption key string.
encrypted_string	Encrypted string.
iv_string	Initialization vector.

Usage Notes

If you are using Oracle's 3DES interface with a 2-key implementation, you must supply a single key of 128 bits as an argument to the `DES3ENCRYPT` procedure. With a 3-key implementation, you must supply a single key of 192 bits. Oracle then breaks the supplied key into two 64-bit keys. As with DES, the 3DES algorithm throws away 8 bits of each derived key. However, you must supply a single 128-bit key for the 2-key 3DES implementation or a single 192-bit key for the 3-key 3DES implementation; otherwise the package will raise an error. The `DES3ENCRYPT` procedure uses the 2-key implementation by default.

You also have the option of providing an *initialization vector* (IV) with the `DES3ENCRYPT` procedure. An IV is a block of random data prepended to the data you intend to encrypt. The IV has no meaning. It is there to make each message unique. Prepending an IV to your input data avoids starting encrypted blocks of data with common header information, which may give cryptanalysts information they can use to decrypt your data.

If the input data or key given to the PL/SQL `DES3ENCRYPT` procedure is empty, then the procedure raises the error `ORA-28231 "Invalid input to Obfuscation toolkit."`

If the input data given to the `DES3ENCRYPT` procedure is not a multiple of 8 bytes, the procedure raises the error `ORA-28232 "Invalid input size for Obfuscation toolkit."`

If you try to double encrypt data using the `DES3ENCRYPT` procedure, then the procedure raises the error `ORA-28233 "Double encryption not supported."`

If the key length is missing or is less than 8 bytes, then the procedure raises the error `ORA-28234 "Key length too short."` Note that if larger keys are used, extra bytes are ignored. So a 9-byte key will not generate an exception.

If an incorrect value is specified for the `which` parameter, `ORA-28236 "Invalid Triple DES mode"` is generated. Only the values 0 (`TwoKeyMode`) and 1 (`ThreeKeyMode`) are valid.

Restrictions

The `DES3ENCRYPT` procedure has two restrictions. The first is that the DES key length for encryption is fixed at 128 bits (for 2-key DES) or 192 bits (for 3-key DES); you cannot alter these key lengths.

The second is that you cannot execute multiple passes of encryption using 3DES. (Note: the 3DES algorithm itself encrypts data multiple times; however, you cannot call the `DES3ENCRYPT` function itself more than once to encrypt the same data using 3DES.)

Note: Both the key length limitation and the prevention of multiple encryption passes are requirements of U.S. regulations governing the export of cryptographic products.

DES3GETKEY Procedures and Functions

These subprograms take a random value and uses it to generate an encryption key. For Triple DES, you specify the mode so that the returned key has the proper length.

Syntax

```
DBMS_OBFUSCATION_TOOLKIT.DES3GetKey(
  which      IN   PLS_INTEGER DEFAULT TwoKeyMode,
  seed       IN   RAW,
  key        OUT  RAW);
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3GetKey(
  which      IN   PLS_INTEGER DEFAULT TwoKeyMode,
  seed_string IN  VARCHAR2,
  key        OUT  VARCHAR2);
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3GetKey(
  which IN PLS_INTEGER DEFAULT TwoKeyMode,
  seed IN RAW)
RETURN RAW;
```

```
DBMS_OBFUSCATION_TOOLKIT.DES3GetKey(
  which      IN   PLS_INTEGER DEFAULT TwoKeyMode,
  seed_string IN  VARCHAR2)
RETURN VARCHAR2;
```

Parameters

Table 55–4 *DES3GETKEY Procedure and Function Parameters*

Parameter	Description
which	If = 0, (default), then TwoKeyMode is used. If = 1, then ThreeKeyMode is used.
seed	A value at least 80 characters long.
key	Encryption key.
seed_string	A value at least 80 characters long.
key	Encryption key.

DESDECRYPT Procedures and Functions

These subprograms generate the decrypted form of the input data.

Syntax

```
DBMS_OBFUSCATION_TOOLKIT.DESDecrypt(  
    input          IN  RAW,  
    key            IN  RAW,  
    decrypted_data OUT RAW);
```

```
DBMS_OBFUSCATION_TOOLKIT.DESDecrypt(  
    input_string   IN  VARCHAR2,  
    key_string     IN  VARCHAR2,  
    decrypted_string OUT VARCHAR2);
```

```
DBMS_OBFUSCATION_TOOLKIT.DESDecrypt(  
    input          IN  RAW,  
    key            IN  RAW)  
RETURN RAW;
```

```
DBMS_OBFUSCATION_TOOLKIT.DESDecrypt(  
    input_string   IN  VARCHAR2,  
    key_string     IN  VARCHAR2)  
RETURN VARCHAR2;
```

Parameters

Table 55–5 *DESDECRYPT Procedure and Function Parameters*

Parameter	Description
input	Data to be decrypted.
key	Decryption key.
decrypted_data	Decrypted data.
input_string	String to be decrypted.
key_string	Decryption key string.
decrypted_string	Decrypted string.

Usage Notes

If the input data or key given to the PL/SQL DESDECRYPT function is empty, then Oracle raises ORA error 28231 "Invalid input to Obfuscation toolkit."

If the input data given to the DESDECRYPT function is not a multiple of 8 bytes, Oracle raises ORA error 28232 "Invalid input size for Obfuscation toolkit."

If the key length is missing or is less than 8 bytes, then the procedure raises the error ORA-28234 "Key length too short." Note that if larger keys are used, extra bytes are ignored. So a 9-byte key will not generate an exception.

Note: ORA-28233 is not applicable to the DESDECRYPT function.

Restrictions

The DES key length for encryption is fixed at 64 bits (of which 56 bits are used); you cannot alter this key length.

Note: The key length limitation is a requirement of U.S. regulations governing the export of cryptographic products.

DESENCRYPT Procedures and Functions

These subprograms generate the encrypted form of the input data.

Syntax

```
DBMS_OBFUSCATION_TOOLKIT.DESEncrypt(  
    input          IN    RAW,  
    key            IN    RAW,  
    encrypted_data OUT  RAW);
```

```
DBMS_OBFUSCATION_TOOLKIT.DESEncrypt(  
    input_string   IN    VARCHAR2,  
    key_string     IN    VARCHAR2,  
    encrypted_string OUT VARCHAR2);
```

```
DBMS_OBFUSCATION_TOOLKIT.DESEncrypt(  
    input          IN RAW,  
    key            IN RAW)  
RETURN RAW;
```

```
DBMS_OBFUSCATION_TOOLKIT.DESEncrypt(  
    input_string IN VARCHAR2,  
    key_string  IN VARCHAR2)  
RETURN VARCHAR2;
```

Parameters

Table 55–6 *DESENCRYPT Procedure and Function Parameters*

Parameter	Description
input	Data to be encrypted.
key	Encryption key.
encrypted_data	Encrypted data.
input_string	String to be encrypted.
key_string	Encryption key string.
encrypted_string	Encrypted string.

Usage Notes

The DES algorithm encrypts data in 64-bit blocks using a 56-bit key. The DES algorithm throws away 8 bits of the supplied key (the particular bits which are thrown away is beyond the scope of this documentation). However, when using the algorithm, you must supply a 64-bit key or the package will raise an error.

If the input data or key given to the PL/SQL `DESEncrypt` procedure is empty, then the procedure raises the error `ORA-28231 "Invalid input to Obfuscation toolkit"`.

If the input data given to the `DESEncrypt` procedure is not a multiple of 8 bytes, the procedure raises the error `ORA-28232 "Invalid input size for Obfuscation toolkit."`

If you try to double-encrypt data using the `DESEncrypt` procedure, then the procedure raises the error `ORA-28233 "Double encryption not supported."`

If the key length is missing or is less than 8 bytes, then the procedure raises the error `ORA-28234 "Key length too short."` Note that if larger keys are used, extra bytes are ignored. So a 9-byte key will not generate an exception.

Restrictions

The `DESEncrypt` procedure has the following restrictions:

- The DES key length for encryption is fixed at 56 bits; you cannot alter this key length.
- You cannot execute multiple passes of encryption. That is, you cannot re-encrypt previously encrypted data by calling the function twice.

Note: Both the key length limitation and the prevention of multiple encryption passes are requirements of U.S. regulations governing the export of cryptographic products.

DESGETKEY Procedures and Functions

These subprograms take a random value and use it to generate an encryption key.

Syntax

```
DBMS_OBFUSCATION_TOOLKIT.DESGetKey(  
    seed          IN   RAW,  
    key           OUT  RAW);
```

```
DBMS_OBFUSCATION_TOOLKIT.DESGetKey(  
    seed_string  IN   VARCHAR2,  
    key          OUT  VARCHAR2);
```

```
DBMS_OBFUSCATION_TOOLKIT.DESGetKey(  
    seed IN RAW)  
RETURN RAW;
```

```
DBMS_OBFUSCATION_TOOLKIT.DESGetKey(  
    seed_string IN VARCHAR2)  
RETURN VARCHAR2;
```

Parameters

Table 55–7 *DESGETKEY Procedure and Function Parameters*

Parameter	Description
seed	A value at least 80 characters long.
key	Encryption key.
seed_string	A value at least 80 characters long.
key	Encryption key.

MD5 Procedures and Functions

These subprograms generate MD5 hashes of data. The MD5 algorithm ensures data integrity by generating a 128-bit cryptographic message digest value from given data.

Syntax

```
DBMS_OBFUSCATION_TOOLKIT.MD5 (
    input          IN RAW,
    checksum       OUT raw_checksum);

DBMS_OBFUSCATION_TOOLKIT.MD5 (
    input_string   IN VARCHAR2,
    checksum_string OUT varchar2_checksum);

DBMS_OBFUSCATION_TOOLKIT.MD5 (
    input          IN RAW)
RETURN raw_checksum;

DBMS_OBFUSCATION_TOOLKIT.MD5 (
    input_string   IN VARCHAR2)
RETURN varchar2_checksum;
```

Parameters

Table 55–8 MD5 Procedure and Function Parameters

Parameter Name	Description
input	Data to be hashed
checksum	128-bit cryptographic message digest
input_string	Data to be hashed
checksum_string	128-bit cryptographic message digest

DBMS_ODCI package contains a single user function related to the use of Data Cartridges.

See Also:

- *Oracle Data Cartridge Developer's Guide*

This chapter contains the following topic:

- [Summary of DBMS_ODCI Subprograms](#)

Summary of DBMS_ODCI Subprograms

Table 56–1 *DBMS_ODCI Package Subprograms*

Subprogram	Description
ESTIMATE_CPU_UNITS Function on page 56-3	Returns the approximate number of CPU instructions (in thousands) corresponding to a specified time interval (in seconds)

ESTIMATE_CPU_UNITS Function

This function returns the approximate number of CPU instructions (in thousands) corresponding to a specified time interval (in seconds). This information can be used to associate the CPU cost with a user-defined function for the extensible optimizer.

The function takes as input the elapsed time of the user function, measures CPU units by multiplying the elapsed time by the processor speed of the machine, and returns the approximate number of CPU instructions that should be associated with the user function. For a multiprocessor machine, ESTIMATE_CPU_UNITS considers the speed of a single processor.

Syntax

```
DBMS_ODCI.ESTIMATE_CPU_UNITS(  
    elapsed_time    NUMBER)  
    RETURN NUMBER;
```

Parameters

Parameter	Description
elapsed_time	The elapsed time in seconds that it takes to execute a function.

Usage Notes

When associating CPU cost with a user-defined function, use the full number of CPU units rather than the number of *thousands* of CPU units returned by ESTIMATE_CPU_UNITS; multiply the number returned by ESTIMATE_CPU_UNITS by 1,000.

DBMS_OFFLINE_OG

The DBMS_OFFLINE_OG package contains the public interface for offline instantiation of master groups.

This chapter contains the following topics:

- [Documentation of DBMS_OFFLINE_OG](#)

Documentation of DBMS_OFFLINE_OG

For a complete description of this package within the context of Replication, see DBMS_OFFLINE_OG in the *Oracle Database Advanced Replication Management API Reference*.

Note: With Oracle 10g Release 1 (10.1), the `DBMS_OLAP` package has been replaced with improved technology. While Oracle recommends you not begin development using `DBMS_OLAP`, Oracle continues to support `DBMS_OLAP`, and your existing applications using `DBMS_OLAP` will continue to work.

- If you are developing new or substantially modified applications and had previously used the Summary Advisor in `DBMS_OLAP`, you should now use the SQLAccess Advisor described in [Chapter 12, "DBMS_ADVISOR"](#).
 - If you had previously used `DBMS_OLAP.VALIDATE_DIMENSION`, you should now use `DBMS_DIMENSION.VALIDATE_DIMENSION` described in [Chapter 32, "DBMS_DIMENSION"](#).
 - If you had previously used `DBMS_OLAP.ESTIMATE_MVIEW_SIZE`, you should now use `DBMS_MVIEW.ESTIMATE_MVIEW_SIZE` described in [Chapter 54, "DBMS_MVIEW"](#)
-
-

The `DBMS_OLAP` package, presented here for reasons of backward compatibility, provides a collection of materialized view analysis and advisory functions that are callable from any PL/SQL program. Some of the functions generate output tables.

See Also: *Oracle Data Warehousing Guide* for more information.

This chapter contains the following topics:

- [Using DBMS_OLAP](#)
 - [Overview](#)
 - [Views](#)
 - [Views](#)
 - [Deprecated Subprograms](#)
- [Summary of DBMS_OLAP Subprograms](#)

Using DBMS_OLAP

- [Overview](#)
- [Views](#)
- [Deprecated Subprograms](#)

Overview

DBMS_OLAP performs seven major functions, which include materialized view strategy recommendation, materialized view strategy evaluation, reporting and script generation, repository management, workload management, filter management, and dimension validation.

To perform materialized view strategy recommendation and evaluation functions, the workload information can either be provided by the user or synthesized by the Advisor engine. In the former case, cardinality information of all tables and materialized views referenced in the workload are required. In the latter case, dimension objects must be present and cardinality information for all dimension tables, fact tables, and materialized views are required. Cardinality information should be gathered with the `DBMS_STATS.GATHER_TABLE_STATS` procedure. Once these functions are completed, the analysis results can be presented with the reporting and script generation function.

The workload management function handles three types of workload, which are user-specified workload, SQL cache workload, and Oracle Trace workload. To process the user-specified workload, a user-defined workload table must be present in the user's schema. To process Oracle Trace workload, the Oracle Trace formatter must be run to preprocess collected workload statistics into default V-tables in the user's schema.

Views

Several views are created when using DBMS_OLAP. All are in the `SYSTEM` schema. To access these views, you must have a DBA role.

SYSTEM.MVIEW_EVALUATIONS

Table 58–1 SYSTEM.MVIEW_EVALUATIONS

Column	NULL?	Datatype	Description
RUNID	NOT NULL	NUMBER	Run id identifying a unique Advisor call.
MVIEW_OWNER	-	VARCHAR2(30)	Owner of materialized view.
MVIEW_NAME	-	VARCHAR2(30)	Name of an existing materialized view in this database.
RANK	NOT NULL	NUMBER	Rank of this materialized view in descending order of benefit_to_cost_ratio.
STORAGE_IN_BYTES	-	NUMBER	Size of the materialized view in bytes.
FREQUENCY	-	NUMBER	Number of times this materialized view appears in the workload.
CUMULATIVE_BENEFIT	-	NUMBER	The cumulative benefit of the materialized view.
BENEFIT_TO_COST_RATIO	NOT NULL	NUMBER	The ratio of cumulative_benefit to storage_in_bytes.

SYSTEM.MVIEW_EXCEPTIONS

Table 58–2 SYSTEM.MVIEW_EXCEPTIONS

Column	NULL?	Datatype	Description
RUNID	-	NUMBER	Run id identifying a unique advisor call.
OWNER	-	VARCHAR2(30)	Owner name.
TABLE_NAME	-	VARCHAR2(30)	Table name.
DIMENSION_NAME	-	VARCHAR2(30)	Dimension name.
RELATIONSHIP	-	VARCHAR2(11)	Violated relation name.
BAD_ROWID	-	ROWID	Location of offending entry.

SYSTEM.MVIEW_FILTER

Table 58–3 SYSTEM.MVIEW_FILTER

Column	NULL?	Datatype	Description
FILTERID	NOT NULL	NUMBER	Unique number used to identify the operation that used this filter.
SUBFILTERNUM	NOT NULL	NUMBER	A unique id number that groups all filter items together. A corresponding filter header record can be found in the MVIEW_LOG table.
SUBFILTERTYPE	-	VARCHAR2(12)	Filter item number.
STR_VALUE	-	VARCHAR2(1028)	String attribute for items that require strings.
NUM_VALUE1	-	NUMBER	Numeric low for items that require numbers.
NUM_VALUE2	-	NUMBER	Numeric high for items that require numbers.
DATE_VALUE1	-	DATE	Date low for items that require dates.
DATE_VALUE2	-	DATE	Date high for items that require dates.

SYSTEM.MVIEW_FILTERINSTANCE

Table 58–4 SYSTEM.MVIEW_FILTERINSTANCE

Column	NULL?	Datatype	Description
RUNID	NOT NULL	NUMBER	Unique number used to identify the operation that used this filter.
FILTERID	-	NUMBER	A unique id number that groups all filter items together. A corresponding filter header record can be found in the MVIEW_LOG table.
SUBFILTERNUM	-	NUMBER	Filter item number.
SUBFILTERTYPE	-	VARCHAR2(12)	Filter item type.
STR_VALUE	-	VARCHAR2(1028)	String attribute for items that require strings.
NUM_VALUE1	-	NUMBER	Numeric low for items that require numbers.

Table 58–4 (Cont.) SYSTEM.MVIEW_FILTERINSTANCE

Column	NULL?	Datatype	Description
NUM_VALUE2	-	NUMBER	Numeric high for items that require numbers.
DATE_VALUE1	-	DATE	Date low for items that require dates.
DATE_VALUE2	-	DATE	Date high for items that require dates.

SYSTEM.MVIEW_LOG

Table 58–5 SYSTEM.MVIEW_LOG

Column	NULL?	Datatype	Description
ID	NOT NULL	NUMBER	Unique number used to identify the table entry. The number must be created using the CREATE_ID routine.
FILTERID	-	NUMBER	Optional filter id. Zero indicates no user-supplied filter has been applied to the operation.
RUN_BEGIN	-	DATE	Date at which the operation began.
RUN_END	-	DATE	Date at which the operation ended.
TYPE	-	VARCHAR2(11)	A name that identifies the type of operation.
STATUS	-	VARCHAR2(11)	The current operational status.
MESSAGE	-	VARCHAR2(2000)	Informational message indicating current operation or condition.
COMPLETED	-	NUMBER	Number of steps completed by operation.
TOTAL	-	NUMBER	Total number steps to be performed.
ERROR_CODE	-	VARCHAR2(20)	Oracle error code in the event of an error.

SYSTEM.MVIEW_RECOMMENDATIONS

Table 58–6 SYSTEM.MVIEW_RECOMMENDATIONS

Column	NULL?	Datatype	Description
RUNID	–	NUMBER	Run id identifying a unique advisor call.
ALL_TABLES	–	VARCHAR2 (2000)	A comma-delimited list of fully qualified table names for structured recommendations.
FACT_TABLES	–	VARCHAR2 (1000)	A comma-delimited list of grouping levels, if any, for structured recommendation.
GROUPING_LEVELS	–	VARCHAR2 (2000)	–
QUERY_TEXT	–	LONG	Query text of materialized view if RECOMMENDED_ACTION is CREATE; null otherwise.
RECOMMENDATION_NUMBER	NOT NULL	NUMBER	Unique identifier for this recommendation.
RECOMMENDED_ACTION	–	VARCHAR2 (6)	CREATE, RETAIN, or DROP.
MVIEW_OWNER	–	VARCHAR2 (30)	Owner of the materialized view if RECOMMENDED_ACTION is RETAIN or DROP; null otherwise.
MVIEW_NAME	–	VARCHAR2 (30)	Name of the materialized view if RECOMMENDED_ACTION is RETAIN or DROP; null otherwise.
STORAGE_IN_BYTES	–	NUMBER	Actual or estimated storage in bytes.
PCT_PERFORMANCE_GAIN	–	NUMBER	The expected incremental improvement in performance obtained by accepting this recommendation relative to the initial condition, assuming that all previous recommendations have been accepted, or NULL if unknown.
BENEFIT_TO_COST_RATIO	NOT NULL	NUMBER	Ratio of the incremental improvement in performance to the size of the materialized view in bytes, or NULL if unknown.

SYSTEM.MVIEW_WORKLOAD**Table 58–7 SYSTEM.MVIEW_WORKLOAD**

Column	NULL?	Datatype	Description
APPLICATION	–	VARCHAR2 (30)	Optional application name for the query.
CARDINALITY	–	NUMBER	Total cardinality of all of tables in query.
WORKLOADID	–	NUMBER	Workload id identifying a unique sampling.
FREQUENCY	–	NUMBER	Number of times query executed.
IMPORT_TIME	–	DATE	Date at which item was collected.
LASTUSE	–	DATE	Last date of execution.
OWNER	–	VARCHAR2 (30)	User who last executed query.
PRIORITY	–	NUMBER	User-supplied ranking of query.
QUERY	–	LONG	Query text.
QUERYID	–	NUMBER	Id number identifying a unique query.
RESPONSETIME	–	NUMBER	Execution time in seconds.
RESULTSIZE	–	NUMBER	Total bytes selected by the query.

Deprecated Subprograms

The DBMS_OLAP subprograms have been replaced with improved technology: see [Chapter 12, "DBMS_ADVISOR"](#), [Chapter 32, "DBMS_DIMENSION"](#) and [Chapter 54, "DBMS_MVIEW"](#). All DBMS_OLAP subprograms are obsolete with Oracle 10g Release 1 (10.1), and while Oracle will continue to support them, they are documented only for reasons of backward compatibility.

- [ADD_FILTER_ITEM Procedure](#)
- [CREATE_ID Procedure](#)
- [ESTIMATE_MVIEW_SIZE Procedure](#)
- [EVALUATE_MVIEW_STRATEGY Procedure](#)
- [GENERATE_MVIEW_REPORT Procedure](#)
- [GENERATE_MVIEW_SCRIPT Procedure](#)
- [LOAD_WORKLOAD_CACHE Procedure](#)
- [LOAD_WORKLOAD_TRACE Procedure](#)
- [PURGE_FILTER Procedure](#)
- [PURGE_RESULTS Procedure](#)
- [PURGE_WORKLOAD Procedure](#)
- [RECOMMEND_MVIEW_STRATEGY Procedure](#)
- [SET_CANCELLED Procedure](#)
- [VALIDATE_DIMENSION Procedure](#)
- [VALIDATE_WORKLOAD_CACHE Procedure](#)
- [VALIDATE_WORKLOAD_TRACE Procedure](#)
- [VALIDATE_WORKLOAD_USER Procedure](#)

Summary of DBMS_OLAP Subprograms

Note: The DBMS_OLAP subprograms have been replaced with improved technology:

- If you are developing new or substantially modified applications and had previously used the Summary Advisor in DBMS_OLAP, you should now use the SQLAccess Advisor described in [Chapter 12, "DBMS_ADVISOR"](#).
 - If you had previously used DBMS_OLAP.VALIDATE_DIMENSION, you should now use DBMS_DIMENSION.VALIDATE_DIMENSION described in [Chapter 32, "DBMS_DIMENSION"](#).
 - If you had previously used DBMS_OLAP.ESTIMATE_MVIEW_SIZE, you should now use DBMS_MVIEW.ESTIMATE_MVIEW_SIZE described in [Chapter 54, "DBMS_MVIEW"](#)
-

Table 58–8 DBMS_OLAP Package Subprograms

Subprogram	Description
ADD_FILTER_ITEM Procedure on page 58-12	Filters the contents being used during the recommendation process [see Deprecated Subprograms on page 58-9]
CREATE_ID Procedure on page 58-14	Generates an internal ID used by a new workload collection, a new filter, or a new advisor run [see Deprecated Subprograms on page 58-9]
ESTIMATE_MVIEW_SIZE Procedure on page 58-15	Estimates the size of a materialized view that you might create, in bytes and rows [see Deprecated Subprograms on page 58-9]
EVALUATE_MVIEW_STRATEGY Procedure on page 58-16	Measures the utilization of each existing materialized view [see Deprecated Subprograms on page 58-9]
GENERATE_MVIEW_REPORT Procedure on page 58-17	Generates an HTML-based report on the given Advisor run [see Deprecated Subprograms on page 58-9]
GENERATE_MVIEW_SCRIPT Procedure on page 58-18	Generates a simple script containing the SQL commands to implement Summary Advisor recommendations [see Deprecated Subprograms on page 58-9]
LOAD_WORKLOAD_CACHE Procedure on page 58-19	Obtains a SQL cache workload [see Deprecated Subprograms on page 58-9]

Table 58–8 (Cont.) DBMS_OLAP Package Subprograms

Subprogram	Description
LOAD_WORKLOAD_TRACE Procedure on page 58-21	Loads a workload collected by Oracle Trace [see Deprecated Subprograms on page 58-9]
LOAD_WORKLOAD_USER Procedure on page 58-23	Loads a user-defined workload [see Deprecated Subprograms on page 58-9]
PURGE_FILTER Procedure on page 58-24	Deletes a specific filter or all filters [see Deprecated Subprograms on page 58-9]
PURGE_RESULTS Procedure on page 58-25	Removes all results or those for a specific run [see Deprecated Subprograms on page 58-9]
PURGE_WORKLOAD Procedure on page 58-26	Deletes all workloads or a specific collection [see Deprecated Subprograms on page 58-9]
RECOMMEND_MVIEW_STRATEGY Procedure on page 58-27	Generates a set of recommendations about which materialized views should be created, retained, or dropped [see Deprecated Subprograms on page 58-9]
SET_CANCELLED Procedure on page 58-29	Stops the Advisor if it takes too long returning results [see Deprecated Subprograms on page 58-9]
VALIDATE_DIMENSION Procedure on page 58-30	Verifies that the relationships specified in a <code>dimension</code> are correct [see Deprecated Subprograms on page 58-9]
VALIDATE_WORKLOAD_CACHE Procedure on page 58-32	Validates the SQL Cache workload before performing load operations [see Deprecated Subprograms on page 58-9]
VALIDATE_WORKLOAD_TRACE Procedure on page 58-33	Validates the Oracle Trace workload before performing load operations [see Deprecated Subprograms on page 58-9]
VALIDATE_WORKLOAD_USER Procedure on page 58-34	Validates the user-supplied workload before performing load operations [see Deprecated Subprograms on page 58-9]

ADD_FILTER_ITEM Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure adds a new filter item to an existing filter to make it more restrictive. It also creates a filter to restrict what is analyzed for the workload.

Syntax

```
ADD_FILTER_ITEM (  
    filter_id      IN NUMBER,  
    filter_name   IN VARCHAR2,  
    string_list   IN VARCHAR2,  
    number_min    IN NUMBER,  
    number_max    IN NUMBER,  
    date_min      IN VARCHAR2,  
    date_max      IN VARCHAR2);
```

Parameters

Table 58–9 *ADD_FILTER_ITEM Procedure Parameters*

Parameter	Description
filter_id	An ID that uniquely describes the filter. It is generated by the DBMS_OLAP.CREATE_ID procedure.

Table 58–9 (Cont.) ADD_FILTER_ITEM Procedure Parameters

Parameter	Description
filter_name	<ul style="list-style-type: none"> ■ APPLICATION: String-workload's application column. An example of how to load a SQL Cache workload follows. ■ Basetable: String-based tables referenced by workload queries. Name must be fully qualified including owner and table name (for example, SH.SALES). ■ CARDINALITY: Numerical-sum of cardinality of the referenced base tables. ■ FREQUENCY: Numerical-workload's frequency column. ■ LASTUSE: Date-workload's lastuse column. Not used by SQL Cache workload. ■ OWNER: String-workload's owner column. Expected in uppercase unless owner defined explicitly to be not all in uppercase. ■ PRIORITY: Numerical-workload's priority column. Not used by SQL Cache workload. ■ RESPONSETIME: Numerical-workload's response time column. Not used by SQL Cache workload. ■ SCHEMA: String-based schema referenced by workload filter. ■ TRACENAME: String-list of oracle trace collection names. Only used by a Trace Workload.
string_list	A comma-delimited list of strings. This parameter is only used by the filter items of the string type.
number_min	The lower bound of a numerical range. NULL represents the lowest possible value. This parameter is only used by the parameters of the numerical type.
number_max	The upper bound of a numerical range, NULL for no upper bound. NULL represents the highest possible value. This parameter is only used by the parameters of the numerical type.
date_min	The lower bound of a date range. NULL represents the lowest possible date value. This parameter is only used by the parameters of the date type.
date_max	The upper bound of a date range. NULL represents the highest possible date value. This parameter is only used by the parameters of the date type.

CREATE_ID Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure creates a unique identifier, which is used to identify a filter, a workload or results of an advisor or dimension validation run.

Syntax

```
CALL DBMS_OLAP.CREATE_ID (  
    id          OUT NUMBER);
```

Parameters

Table 58–10 *CREATE_ID Procedure Parameters*

Parameter	Description
id	The unique identifier that can be used to identify a filter, a workload, or an Advisor run.

ESTIMATE_MVIEW_SIZE Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure estimates the size of a materialized view that you might create, in bytes and number of rows.

Syntax

```
DBMS_OLAP. ESTIMATE_MVIEW_SIZE (
  stmt_id      IN VARCHAR2,
  select_clause IN VARCHAR2,
  num_rows     OUT NUMBER,
  num_bytes    OUT NUMBER);
```

Parameters

Table 58–11 ESTIMATE_MVIEW_SIZE Procedure Parameters

Parameter	Description
stmt_id	Arbitrary string used to identify the statement in an EXPLAIN PLAN.
select_clause	The SELECT statement to be analyzed.
num_rows	Estimated cardinality.
num_bytes	Estimated number of bytes.

EVALUATE_MVIEW_STRATEGY Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure measures the utilization of each existing materialized view based on the materialized view usage statistics collected from the workload. The `workload_id` is optional. If not provided, `EVALUATE_MVIEW_STRATEGY` uses a hypothetical workload.

Syntax

```
DBMS_OLAP.EVALUATE_MVIEW_STRATEGY (
run_id          IN NUMBER,
workload_id    IN NUMBER,
filter_id      IN NUMBER);
```

Parameters

Table 58–12 *EVALUATE_MVIEW_STRATEGY Procedure Parameters*

Parameter	Description
<code>run_id</code>	An ID generated by the <code>DBMS_OLAP.CREATE_ID</code> procedure to identify results of a run.
<code>workload_id</code>	An optional workload ID that maps to a workload in the current repository. Use the parameter <code>DBMS_OLAP.WORKLOAD_ALL</code> to choose all workloads.
<code>filter_id</code>	Specify filter for the workload to be used. The value <code>DBMS_OLAP.FILTER_NONE</code> indicates no filtering.

Usage Notes

Periodically, the unused results can be purged from the system by calling the `DBMS_OLAP.PURGE_RESULTS` procedure.

GENERATE_MVIEW_REPORT Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure generates an HTML-based report on the given Advisor run.

Syntax

```
DBMS_OLAP.GENERATE_MVIEW_REPORT (
  filename      IN VARCHAR2,
  id            IN NUMBER,
  flags        IN NUMBER);
```

Parameters

Table 58–13 *GENERATE_MVIEW_REPORT Procedure Parameters*

Parameter	Description
filename	Fully qualified output file name to receive HTML data. Note that the Oracle server restricts file access within Oracle stored procedures. See the "Security and Performance" section of the Java Developer's Guide for more information on file permissions.
id	An ID that identifies an advisor run. Or use the parameter <code>DBMS_OLAP.RUNID_ALL</code> to indicate all advisor runs should be reported.
flags	Bit masked flags indicating what sections should be reported <ul style="list-style-type: none"> ■ <code>DBMS_OLAP.RPT_ACTIVITY</code> -- Overall activities ■ <code>DBMS_OLAP.RPT_JOURNAL</code> -- Runtime journals ■ <code>DBMS_OLAP.RPT_WORKLOAD_FILTER</code> -- Filters ■ <code>DBMS_OLAP.RPT_WORKLOAD_DETAIL</code> -- Workload information ■ <code>DBMS_OLAP.RPT_WORKLOAD_QUERY</code> -- Workload query information ■ <code>DBMS_OLAP.RPT_RECOMMENDATION</code> -- Recommendations ■ <code>DBMS_OLAP.RPT_USAGE</code> -- Materialized view usage ■ <code>DBMS_OLAP.RPT_ALL</code> -- All sections

GENERATE_MVIEW_SCRIPT Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure generates a simple script containing the SQL commands to implement Summary Advisor recommendations.

Syntax

```
DBMS_OLAP.GENERATE_MVIEW_SCRIPT(  
    filename    IN VARCHAR2,  
    id          IN NUMBER,  
    tspace     IN VARCHAR2);
```

Parameters

Table 58-14 *GENERATE_MVIEW_SCRIPT Procedure Parameters*

Parameter	Description
filename	Fully qualified output file name to receive HTML data. Note that the Oracle server restricts file access within Oracle stored procedures. See the "Security and Performance" section of the Java Developer's Guide for more information on file permissions.
id	An ID that identifies an advisor run. The parameter <code>DBMS_OLAP.RUNID_ALL</code> indicates all advisor runs should be reported.
tspace	Optional tablespace name to use when creating materialized views.

LOAD_WORKLOAD_CACHE Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure loads a SQL cache workload.

Syntax

```
DBMS_OLAP.LOAD_WORKLOAD_CACHE (
    workload_id  IN NUMBER,
    flags        IN NUMBER,
    filter_id    IN NUMBER,
    application  IN VARCHAR2,
    priority     IN NUMBER);
```

Parameters

Table 58–15 *LOAD_WORKLOAD_CACHE Procedure Parameters*

Parameter	Description
workload_id	Fully qualified output file name to receive HTML data. Note that the Oracle server restricts file access within Oracle stored procedures. See the "Security and Performance" section of the Java Developer's Guide for more information on file permission.
flags	<ul style="list-style-type: none"> ▪ <code>DBMS_OLAP.WORKLOAD_OVERWRITE</code>: The load routine will explicitly remove any existing queries from the workload that are owned by the specified collection ID. ▪ <code>DBMS_OLAP.WORKLOAD_APPEND</code>: The load routine preserves any existing queries in the workload. Any queries collected by the load operation will be appended to the end of the specified workload. ▪ <code>DBMS_OLAP.WORKLOAD_NEW</code>: The load routine assumes there are no existing queries in the workload. If it finds an existing workload element, the call will fail with an error. <p>Note: the flags have the same behavior irrespective of the <code>LOAD_WORKLOAD</code> operation.</p>
filter_id	Specify filter for the workload to be loaded.
application	The default business application name. This value will be used for a query if one is not found in the target workload.

Table 58–15 (Cont.) LOAD_WORKLOAD_CACHE Procedure Parameters

Parameter	Description
<code>priority</code>	The default business priority to be assigned to every query in the target workload.

LOAD_WORKLOAD_TRACE Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure loads an Oracle Trace workload.

Syntax

```
DBMS_OLAP.LOAD_WORKLOAD_TRACE (
    workload_id  IN NUMBER,
    flags        IN NUMBER,
    filter_id    IN NUMBER,
    application  IN VARCHAR2,
    priority     IN NUMBER,
    owner_name   IN VARCHAR2);
```

Parameters

Table 58–16 *LOAD_WORKLOAD_TRACE Procedure Parameters*

Parameter	Description
collectionid	Fully qualified output file name to receive HTML data. Note that the Oracle server restricts file access within Oracle stored procedures. See the "Security and Performance" section of the Java Developer's Guide for more information on file permission.
flags	<ul style="list-style-type: none"> ■ <code>DBMS_OLAP.WORKLOAD_OVERWRITE</code>: The load routine will explicitly remove any existing queries from the workload that are owned by the specified collection ID. ■ <code>DBMS_OLAP.WORKLOAD_APPEND</code>: The load routine preserves any existing queries in the workload. Any queries collected by the load operation will be appended to the end of the specified workload. ■ <code>DBMS_OLAP.WORKLOAD_NEW</code>: The load routine assumes there are no existing queries in the workload. If it finds an existing workload element, the call will fail with an error. <p>Note: the flags have the same behavior irrespective of the <code>LOAD_WORKLOAD</code> operation.</p>
filter_id	Specify filter for the workload to be loaded.
application	The default business application name. This value will be used for a query if one is not found in the target workload.

Table 58–16 (Cont.) LOAD_WORKLOAD_TRACE Procedure Parameters

Parameter	Description
<code>priority</code>	The default business priority to be assigned to every query in the target workload.
<code>owner_name</code>	The schema that contains the Oracle Trace data. If omitted, the current user will be used.

LOAD_WORKLOAD_USER Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure loads a user-defined workload.

Syntax

```
DBMS_OLAP.LOAD_WORKLOAD_USER (
  workload_id  IN    NUMBER,
  flags        IN    NUMBER,
  filter_id    IN    NUMBER,
  owner_name   IN    VARCHAR2,
  table_name   IN    VARCHAR2);
```

Parameters

Table 58–17 *LOAD_WORKLOAD_USER Procedure Parameters*

Parameter	Description
workload_id	The required id that was returned by the DBMS_OLAP.CREATE_ID call.
flags	<ul style="list-style-type: none"> ▪ DBMS_OLAP.WORKLOAD_OVERWRITE: The load routine will explicitly remove any existing queries from the workload that are owned by the specified collection ID ▪ DBMS_OLAP.WORKLOAD_APPEND: The load routine preserves any existing queries in the workload. Any queries collected by the load operation will be appended to the end of the specified workload ▪ DBMS_OLAP.WORKLOAD_NEW: The load routine assumes there are no existing queries in the workload. If it finds an existing workload element, the call will fail with an error <p>Note: the flags have the same behavior irrespective of the LOAD_WORKLOAD operation.</p>
filter_id	Specify filter for the workload to be loaded.
owner_name	The schema that contains the user supplied table or view.
table_name	The table or view name containing valid workload data.

PURGE_FILTER Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure removes a filter at any time. You can delete a specific filter or all filters.

Syntax

```
DBMS_OLAP.PURGE_FILTER (  
    filter_id    IN    NUMBER);
```

Parameters

Table 58–18 *PURGE_FILTER Procedure Parameters*

Parameter	Description
<code>filter_id</code>	The parameter <code>DBMS_OLAP.FILTER_ALL</code> indicates all filters should be removed.

PURGE_RESULTS Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

Many procedures in the DBMS_OLAP package generate output in system tables, such as recommendation results for RECOMMEND_MVIEW_STRATEGY and evaluation results for EVALUATE_MVIEW_STRATEGY, and dimension validation results for VALIDATE_DIMENSION. When these outputs are no longer required, they should be removed using the procedure PURGE_RESULTS. You can remove all results or those for a specific run.

Syntax

```
DBMS_OLAP.PURGE_RESULTS (
    run_id    IN    NUMBER);
```

Parameters

Table 58–19 *PURGE_RESULTS Procedure Parameters*

Parameter	Description
run_id	An ID generated with the DBMS_OLAP.CREATE_ID procedure. The ID should be associated with a RECOMMEND_MVIEW_STRATEGY or a EVALUATE_MVIEW_STRATEGY or a VALIDATE_DIMENSION run. Use the value DBMS_OLAP.RUNID_ALL to specify all such runs.

PURGE_WORKLOAD Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure removes workloads when they are no longer needed. You can delete all workloads or a specific collection.

Syntax

```
DBMS_OLAP.PURGE_WORKLOAD (  
    workload_id IN NUMBER);
```

Parameters

Table 58–20 *DBMS_OLAP.PURGE_WORKLOAD Procedure Parameters*

Parameter	Description
workload_id	An ID number originally assigned by the create_id call. If the value of workload_id is set to DBMS_OLAP.WORKLOAD_ALL, then all workloads for the current user will be deleted.

RECOMMEND_MVIEW_STRATEGY Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure generates a set of recommendations about which materialized views should be created, retained, or dropped, based on information in the workload (gathered by Oracle Trace, the user workload, or the SQL cache), and an analysis of table and column cardinality statistics gathered by the `DBMS_STATS.GATHER_TABLE_STATS` procedure.

`RECOMMEND_MVIEW_STRATEGY` requires that you have run the `GATHER_TABLE_STATS` procedure to gather table and column cardinality statistics and have collected and formatted the workload statistics.

The workload is aggregated to determine the count of each request in the workload, and this count is used as a weighting factor during the optimization process. If the `workload_id` is not provided, then `RECOMMEND_MVIEW_STRATEGY` uses a hypothetical workload based on dimension definitions and other embedded statistics.

The space of all dimensional materialized views that include the specified fact tables identifies the set of materialized views that optimize performance across the workload. The recommendation results are stored in system tables, which can be accessed through the view `SYSTEM.MVIEW_RECOMMENDATIONS`.

Syntax

```
DBMS_OLAP.RECOMMEND_MVIEW_STRATEGY (  
    run_id           IN NUMBER,  
    workload_id     IN NUMBER,  
    filter_id       IN NUMBER,  
    storage_in_bytes IN NUMBER,  
    retention_pct   IN NUMBER,  
    retention_list  IN VARCHAR2,  
    fact_table_filter IN VARCHAR2);
```

Parameters

Table 58–21 *RECOMMEND_MVIEW_STRATEGY Procedure Parameters*

Parameter	Description
<code>run_id</code>	An ID generated by the <code>DBMS_OLAP.CREATE_ID</code> procedure to uniquely identify results of a run.
<code>workload_id</code>	An optional workload ID that maps to a workload in the current repository. Use the parameter <code>DBMS_OLAP.WORKLOAD_ALL</code> to choose all workloads. If the <code>workload_id</code> is set to <code>NULL</code> , the call will use a hypothetical workload.
<code>filter_id</code>	An optional filter ID that maps to a set of user-supplied filter items. Use the parameter <code>DBMS_OLAP.FILTER_NONE</code> to avoid filtering.
<code>storage_in_bytes</code>	Maximum storage, in bytes, that can be used for storing materialized views. This number must be nonnegative.
<code>retention_pct</code>	Number between 0 and 100 that specifies the percent of existing materialized view storage that must be retained, based on utilization on the actual or hypothetical workload. A materialized view is retained if the cumulative space, ranked by utilization, is within the retention threshold specified (or if it is explicitly listed in <code>retention_list</code>). Materialized views that have a <code>NULL</code> utilization (for example, nondimensional materialized views) are always retained.
<code>retention_list</code>	Comma-delimited list of materialized view table names. A drop recommendation is not made for any materialized view that appears in this list.
<code>fact_table_filter</code>	Optional list of fact tables used to filter real or ideal workload.

Usage Notes

Periodically, the unused results can be purged from the system by calling the `PURGE_RESULTS` procedure.

SET_CANCELLED Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

If the Summary Advisor takes too long to make its recommendations using the procedures `RECOMMEND_MVIEW_STRATEGY`, you can stop it by calling the procedure `SET_CANCELLED` and passing in the `run_id` for this recommendation process.

Syntax

```
DBMS_OLAP.SET_CANCELLED (  
    run_id      IN NUMBER);
```

Parameters

Table 58–22 *DBMS_OLAP.SET_CANCELLED Procedure Parameters*

Parameter	Description
<code>run_id</code>	Id that uniquely identifies an advisor analysis operation. This call can be used to cancel a long running workload collection as well as an Advisor analysis session.

VALIDATE_DIMENSION Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure verifies that the hierarchical and attribute relationships, and join relationships, specified in an existing dimension object are correct. This provides a fast way to ensure that referential integrity is maintained.

The validation results are stored in system tables, which can be accessed through the view `SYSTEM.MVIEW_EXCEPTIONS`.

Syntax

```
DBMS_OLAP.VALIDATE_DIMENSION (
    dimension_name    IN VARCHAR2,
    dimension_owner   IN VARCHAR2,
    incremental       IN BOOLEAN,
    check_nulls       IN BOOLEAN,
    run_id            IN NUMBER);
```

Parameters

Table 58–23 VALIDATE_DIMENSION Procedure Parameters

Parameter	Description
<code>dimension_name</code>	Name of the dimension to analyze.
<code>dimension_owner</code>	Name of the dimension owner.
<code>incremental</code>	If <code>TRUE</code> , then tests are performed only for the rows specified in the <code>sumdelta\$</code> table for tables of this dimension; otherwise, check all rows.
<code>check_nulls</code>	<ul style="list-style-type: none"> ▪ If <code>TRUE</code>, then all level columns are verified to be nonnull; otherwise, this check is omitted. ▪ Specify <code>FALSE</code> when nonnullness is guaranteed by other means, such as <code>NOT NULL</code> constraints.
<code>run_id</code>	An ID generated by the <code>DBMS_OLAP.CREATE_ID</code> procedure to identify a run.

Usage Notes

Periodically, the unused results can be purged from the system by calling the `PURGE_RESULTS` procedure.

VALIDATE_WORKLOAD_CACHE Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure validates the SQL Cache workload before performing load operations.

Syntax

```
DBMS_OLAP.VALIDATE_WORKLOAD_CACHE (  
    valid          OUT NUMBER,  
    error         OUT VARCHAR2);
```

Parameters

Table 58–24 VALIDATE_WORKLOAD_USER Procedure Parameters

Parameter	Description
valid	Return DBMS_OLAP.VALID or DBMS_OLAP.INVALID Indicate whether a workload is valid.
error	VARCHAR2, return error set.

VALIDATE_WORKLOAD_TRACE Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure validates the Oracle Trace workload before performing load operations.

Syntax

```
DBMS_OLAP.VALIDATE_WORKLOAD_TRACE (
    owner_name      IN  VARCHAR2,
    valid           OUT NUMBER,
    error          OUT VARCHAR2);
```

Parameters

Table 58–25 *VALIDATE_WORKLOAD_TRACE Procedure Parameters*

Parameter	Description
owner_name	Owner of the trace workload table.
valid	Return DBMS_OLAP.VALID or DBMS_OLAP.INVALID Indicate whether a workload is valid.
error	VARCHAR2, return error text.

VALIDATE_WORKLOAD_USER Procedure

Note: See [Deprecated Subprograms](#) on page 58-9.

This procedure validates the user-supplied workload before performing load operations.

Syntax

```
DBMS_OLAP.VALIDATE_WORKLOAD_USER (  
    owner_name      IN VARCHAR2,  
    table_name      IN VARCHAR2,  
    valid           OUT NUMBER,  
    error           OUT VARCHAR2);
```

Parameters

Table 58–26 VALIDATE_WORKLOAD_USER Procedure Parameters

Parameter	Description
owner_name	Owner of the user workload table.
table_name	User workload table name.
valid	Return DBMS_OLAP.VALID or DBMS_OLAP.INVALID Indicate whether a workload is valid.
error	VARCHAR2, return error set.

DBMS_OUTLN

The `DBMS_OUTLN` package, synonymous with `OUTLN_PKG`, contains the functional interface for subprograms associated with the management of stored outlines.

See Also: For more information about using the `DBMS_OUTLN` package, see *Using Plan Stability* in *Oracle Database Performance Tuning Guide*.

This chapter contains the following topics:

- [Using DBMS_OUTLN](#)
 - [Overview](#)
 - [Security Model](#)
- [Summary of DBMS_OUTLN Subprograms](#)

Using DBMS_OUTLN

- [Overview](#)
- [Security Model](#)

Overview

A stored outline is the stored data that pertains to an execution plan for a given SQL statement. It enables the optimizer to repeatedly re-create execution plans that are equivalent to the plan originally generated along with the outline. The data stored in an outline consists, in part, of a set of hints that are used to achieve plan stability.

Security Model

DBMS_OUTLN contains management procedures that should be available to appropriate users only. EXECUTE privilege is not extended to the general user community unless the DBA explicitly does so.

PL/SQL functions that are available for outline management purposes can be executed only by users with EXECUTE privilege on the procedure (or package).

Summary of DBMS_OUTLN Subprograms

Table 59–1 DBMS_OUTLN Package Subprograms

Subprogram	Description
CLEAR_USED Procedure on page 59-4	Clears the outline 'used' flag
CREATE_OUTLINE Procedure on page 59-5	Generates outlines from the shared cursor identified by hash value and child number
DROP_BY_CAT Procedure on page 59-6	Drops outlines that belong to a specified category
DROP_UNUSED Procedure on page 59-7	Drops outlines that have never been applied in the compilation of a SQL statement
EXACT_TEXT_SIGNATURES Procedure on page 59-8	Updates outline signatures to those that compute based on exact text matching
UPDATE_BY_CAT Procedure on page 59-9	Changes the category of outlines in one category to a new category
UPDATE_SIGNATURES Procedure on page 59-10	Updates outline signatures to the current version's signature

CLEAR_USED Procedure

This procedure clears the outline 'used' flag.

Syntax

```
DBMS_OUTLN.CLEAR_USED (  
    name      IN      VARCHAR2);
```

Parameters

Table 59–2 *CLEAR_USED Procedure Parameters*

Parameter	Description
name	Name of the outline.

CREATE_OUTLINE Procedure

This procedure generates an outline from the shared cursor identified by hash value and child number.

Syntax

```
DBMS_OUTLN.CREATE_OUTLINE (  
    hash_value    IN NUMBER,  
    child_number  IN NUMBER,  
    category      IN VARCHAR2 DEFAULT 'DEFAULT' );
```

Parameters

Table 59–3 *CREATE_OUTLINE Procedure Parameters*

Parameter	Description
hash_value	Hash value identifying the target shared cursor.
child_number	Child number of the target shared cursor.
category	Category in which to create outline (optional).

DROP_BY_CAT Procedure

This procedure drops outlines that belong to a particular category. While outlines are put into the `DEFAULT` category unless otherwise specified, users have the option of grouping their outlines into groups called categories.

Syntax

```
DBMS_OUTLN.DROP_BY_CAT (  
    cat VARCHAR2);
```

Parameters

Table 59–4 *DROP_BY_CAT Procedure Parameters*

Parameter	Description
cat	Category of outlines to drop.

Usage Notes

This procedure purges a category of outlines in a single call.

Examples

This example drops all outlines in the `DEFAULT` category:

```
DBMS_OUTLN.DROP_BY_CAT('DEFAULT');
```

DROP_UNUSED Procedure

This procedure drops outlines that have never been applied in the compilation of a SQL statement.

Syntax

```
DBMS_OUTLN.DROP_UNUSED;
```

Usage Notes

You can use `DROP_UNUSED` for outlines generated by an application for one-time use SQL statements created as a result of dynamic SQL. These outlines are never used and take up valuable disk space.

EXACT_TEXT_SIGNATURES Procedure

This procedure updates outline signatures to those that compute based on exact text matching.

Syntax

```
DBMS. OUTLN. EXACT_TEXT_SIGNATURES ;
```

Usage Notes

This procedure is relevant only for downgrading an outline to 8.1.6 or earlier.

UPDATE_BY_CAT Procedure

This procedure changes the category of all outlines in one category to a new category.

Syntax

```
DBMS.OUTLN.UPDATE_BY_CAT (  
    oldcat    VARCHAR2 default 'DEFAULT',  
    newcat    VARCHAR2 default 'DEFAULT');
```

Parameters

Table 59–5 *UPDATE_BY_CAT Procedure Parameters*

Parameter	Description
oldcat	The current category of outlines.
newcat	The new category of outlines.

UPDATE_SIGNATURES Procedure

This procedure updates outline signatures to the current version's signature.

Syntax

```
DBMS . OUTLN . UPDATE_SIGNATURES ;
```

Usage Notes

You should execute this procedure if you have imported outlines generated in an earlier release to ensure that the signatures are compatible with the current release's computation algorithm.

DBMS_OUTLN_EDIT

The DBMS_OUTLN_EDIT package is an invoker's rights package.

See Also: For more information about using the DBMS_OUTLN_EDIT package, see UsingPlan Stability in *Oracle Database Performance Tuning Guide*.

This chapter contains the following topic:

- [Summary of DBMS_OUTLN_EDIT Subprograms](#)

Summary of DBMS_OUTLN_EDIT Subprograms

Table 60–1 *DBMS_OUTLN_EDIT Package Subprograms*

Subprogram	Description
CHANGE_JOIN_POS Procedure on page 60-3	Changes the join position for the hint identified by outline name and hint number to the position specified by <code>newpos</code>
CREATE_EDIT_TABLES Procedure on page 60-4	Creates outline editing tables in calling a user's schema
DROP_EDIT_TABLES Procedure on page 60-5	Drops outline editing tables in calling the user's schema
GENERATE_SIGNATURE Procedure on page 60-6	Generates a signature for the specified SQL text
REFRESH_PRIVATE_OUTLINE Procedure on page 60-7	Refreshes the in-memory copy of the outline, synchronizing its data with the edits made to the outline hints

CHANGE_JOIN_POS Procedure

This function changes the join position for the hint identified by outline name and hint number to the position specified by `newpos`.

Syntax

```
DBMS_OUTLN_EDIT.CHANGE_JOIN_POS (  
    name      VARCHAR2  
    hintno    NUMBER  
    newpos    NUMBER);
```

Parameters

Table 60–2 *CHANGE_JOIN_POS Procedure Parameters*

Parameter	Description
<code>name</code>	Name of the private outline to be modified.
<code>hintno</code>	Hint number to be modified.
<code>newpos</code>	New join position for the target hint.

CREATE_EDIT_TABLES Procedure

This procedure creates outline editing tables in calling a user's schema.

Syntax

```
DBMS_OUTLN_EDIT.CREATE_EDIT_TABLES;
```

Usage Notes

Beginning with release 10i you will not need to use this statement because the outline editing tables will already exist as temporary tables in the SYSTEM schema.

DROP_EDIT_TABLES Procedure

This procedure drops outline editing tables in calling the user's schema.

Syntax

```
DBMS_OUTLN_EDIT.DROP_EDIT_TABLES;
```

GENERATE_SIGNATURE Procedure

This procedure generates a signature for the specified SQL text.

Syntax

```
DBMS_OUTLN.GENERATE_SIGNATURE (  
    sqltxt      IN  VARCHAR2,  
    signature   OUT RAW);
```

Parameters

Table 60–3 *GENERATE_SIGNATURE Procedure Parameters*

Parameter	Description
sqltxt	The specified SQL.
signature	The signature to be generated.

REFRESH_PRIVATE_OUTLINE Procedure

This procedure refreshes the in-memory copy of the outline, synchronizing its data with the edits made to the outline hints.

Syntax

```
DBMS_OUTLN_EDIT.REFRESH_PRIVATE_OUTLINE (  
    name IN VARCHAR2);
```

Parameters

Table 60–4 REFRESH_PRIVATE_OUTLINE Procedure Parameters

Parameter	Description
name	Name of the private outline to be refreshed.

The `DBMS_OUTPUT` package enables you to send messages from stored procedures, packages, and triggers. The package is especially useful for displaying PL/SQL debugging information.

This chapter contains the following topics:

- [Using DBMS_OUTPUT](#)
 - [Security Model](#)
 - [Types](#)
 - [Operational Notes](#)
 - [Exceptions](#)
 - [Deprecated Subprograms](#)
 - [Exceptions](#)
- [Summary of DBMS_OUTPUT Subprograms](#)

Using DBMS_OUTPUT

- [Security Model](#)
- [Types](#)
- [Operational Notes](#)
- [Exceptions](#)
- [Deprecated Subprograms](#)
- [Examples](#)

Security Model

At the end of this script, a public synonym (DBMS_OUTPUT) is created and EXECUTE permission on this package is granted to public.

Types

Type CHARARR is a table type.

Operational Notes

The [PUT_LINE Procedures](#) and [PUT_LINE Procedures](#) in this package enable you to place information in a buffer that can be read by another trigger, procedure, or package. In a separate PL/SQL procedure or anonymous block, you can display the buffered information by calling the [GET_LINE Procedure](#).

If you do not call GET_LINE, or if you do not display the messages on your screen in SQL*Plus or Enterprise Manager, then the buffered messages are ignored. A trigger might want to print out some debugging information. To do this, the trigger would do:

```
DBMS_OUTPUT.PUT_LINE('I got here: '||:new.col||' is the new value');
```

If you have enabled the DBMS_OUTPUT package, then this PUT_LINE would be buffered, and you could, after executing the statement (presumably some INSERT, DELETE, or UPDATE that caused the trigger to fire), get the line of information back. For example:


```
BEGIN
  DBMS_OUTPUT.GET_LINE(:buffer, :status);
END;
```

It could then display the buffer on the screen. You repeat calls to `GET_LINE` until status comes back as nonzero. For better performance, you should use calls to [GET_LINES Procedure](#) which can return an array of lines.

Enterprise Manager and SQL*Plus implement a `SET SERVEROUTPUT ON` command to know whether to make calls to `GET_LINE(S)` after issuing `INSERT`, `UPDATE`, `DELETE` or anonymous PL/SQL calls (these are the only ones that can cause triggers or stored procedures to be executed).

Note: Messages sent using `DBMS_OUTPUT` are not actually sent until the sending subprogram or trigger completes. There is no mechanism to flush output during the execution of a procedure.

Exceptions

`DBMS_OUTPUT` subprograms raise the application error `ORA-20000`, and the output procedures can return the following errors:

Table 61-1 *DBMS_OUTPUT Errors*

Error	Description
ORA-10027:	Buffer overflow
ORA-10028:	Line length overflow

Deprecated Subprograms

The [PUT Procedures](#) that take a number are obsolete and, while currently supported, are included in this release for legacy reasons only.

Examples

Example 1: Debugging Stored Procedures and Triggers

The `DBMS_OUTPUT` package is commonly used to debug stored procedures and triggers. This package can also be used to enable you to retrieve information about

an object and format this output, as shown in ["Example 2: Retrieving Information About an Object"](#) on page 61-5.

This function queries the employee table and returns the total salary for a specified department. The function includes several calls to the PUT_LINE procedure:

```
CREATE FUNCTION dept_salary (dnum NUMBER) RETURN NUMBER IS
  CURSOR emp_cursor IS
    SELECT sal, comm FROM emp WHERE deptno = dnum;
  total_wages    NUMBER(11, 2) := 0;
  counter        NUMBER(10) := 1;
BEGIN

  FOR emp_record IN emp_cursor LOOP
    emp_record.comm := NVL(emp_record.comm, 0);
    total_wages := total_wages + emp_record.sal
      + emp_record.comm;
    DBMS_OUTPUT.PUT_LINE('Loop number = ' || counter ||
      ' ; Wages = ' || TO_CHAR(total_wages)); /* Debug line */
    counter := counter + 1; /* Increment debug counter */
  END LOOP;
  /* Debug line */
  DBMS_OUTPUT.PUT_LINE('Total wages = ' ||
    TO_CHAR(total_wages));
  RETURN total_wages;

END dept_salary;
```

Assume the EMP table contains the following rows:

EMPNO	SAL	COMM	DEPT
1002	1500	500	20
1203	1000		30
1289	1000		10
1347	1000	250	20

Assume the user executes the following statements in the Enterprise Manager SQL Worksheet input pane:

```
SET SERVEROUTPUT ON
VARIABLE salary NUMBER;
EXECUTE :salary := dept_salary(20);
```

The user would then see the following information displayed in the output pane:

```
Loop number = 1; Wages = 2000
```

```

Loop number = 2; Wages = 3250
Total wages = 3250

```

PL/SQL procedure successfully executed.

Example 2: Retrieving Information About an Object

In this example, the user has used the `EXPLAIN PLAN` command to retrieve information about the execution plan for a statement and has stored it in `PLAN_TABLE`. The user has also assigned a statement ID to this statement. The example `EXPLAIN_OUT` procedure retrieves the information from this table and formats the output in a nested manner that more closely depicts the order of steps undergone in processing the SQL statement.

```

/*****
/* Create EXPLAIN_OUT procedure. User must pass STATEMENT_ID to */
/* to procedure, to uniquely identify statement.                */
*****/
CREATE OR REPLACE PROCEDURE explain_out
  (statement_id IN VARCHAR2) AS

  -- Retrieve information from PLAN_TABLE into cursor EXPLAIN_ROWS.

  CURSOR explain_rows IS
    SELECT level, id, position, operation, options,
           object_name
    FROM plan_table
    WHERE statement_id = explain_out.statement_id
    CONNECT BY PRIOR id = parent_id
           AND statement_id = explain_out.statement_id
    START WITH id = 0
    ORDER BY id;

BEGIN

  -- Loop through information retrieved from PLAN_TABLE:

  FOR line IN explain_rows LOOP

    -- At start of output, include heading with estimated cost.

    IF line.id = 0 THEN
      DBMS_OUTPUT.PUT_LINE ('Plan for statement '
        || statement_id
        || ', estimated cost = ' || line.position);
    END IF;
  END LOOP;
END;

```

```
END IF;

-- Output formatted information. LEVEL determines indentation level.

DBMS_OUTPUT.PUT_LINE (lpad(' ',2*(line.level-1)) ||
    line.operation || ' ' || line.options || ' ' ||
    line.object_name);
END LOOP;

END;
```

See Also: [Chapter 155, "UTL_FILE"](#)

Summary of DBMS_OUTPUT Subprograms

Table 61–2 *DBMS_OUTPUT Package Subprograms*

Subprogram	Description
DISABLE Procedure on page 61-8	Disables message output
ENABLE Procedure on page 61-9	Enables message output
GET_LINE Procedure on page 61-10	Retrieves one line from buffer
GET_LINES Procedure on page 61-10	Retrieves an array of lines, from buffer
PUT Procedures on page 61-13	Places a line in the buffer
PUT_LINE Procedures on page 61-15	Places partial line in buffer
NEW_LINE Procedure on page 61-12	Terminates a line created with <code>PUT</code>

Note: The [PUT Procedures](#) that take a number are obsolete and, while currently supported, are included in this release for legacy reasons only.

DISABLE Procedure

This procedure disables calls to `PUT`, `PUT_LINE`, `NEW_LINE`, `GET_LINE`, and `GET_LINES`, and purges the buffer of any remaining information.

As with `ENABLE`, you do not need to call this procedure if you are using the `SERVEROUTPUT` option of Enterprise Manager or SQL*Plus.

Syntax

```
DBMS_OUTPUT.DISABLE;
```

Pragmas

```
pragma restrict_references(disable,WNDS,RNDS);
```

ENABLE Procedure

This procedure enables calls to PUT, PUT_LINE, NEW_LINE, GET_LINE, and GET_LINES. Calls to these procedures are ignored if the DBMS_OUTPUT package is not enabled.

Syntax

```
DBMS_OUTPUT.ENABLE (
    buffer_size IN INTEGER DEFAULT 20000);
```

Pragmas

```
pragma restrict_references(enable,WNDS,RNDS);
```

Parameters

Table 61–3 *ENABLE Procedure Parameters*

Parameter	Description
buffer_size	Amount of information, in bytes, to buffer.

Usage Notes

Note: It is not necessary to call this procedure when you use the SERVEROUTPUT option of Enterprise Manager or SQL*Plus.

If there are multiple calls to ENABLE, then buffer_size is the largest of the values specified. The maximum size is 1,000,000, and the minimum is 2,000.

Exceptions

Table 61–4 *ENABLE Procedure Exceptions*

Error	Description
ORA-20000: ,	Buffer overflow, limit of <buffer_limit> bytes.
ORU-10027:	

GET_LINE Procedure

This procedure retrieves a single line of buffered information.

Syntax

```
DBMS_OUTPUT.GET_LINE (  
    line    OUT VARCHAR2,  
    status  OUT INTEGER);
```

Parameters

Table 61–5 *GET_LINE Procedure Parameters*

Parameter	Description
<code>line</code>	Returns a single line of buffered information, excluding a final newline character: The maximum length is 255 bytes.
<code>status</code>	If the call completes successfully, then the status returns as 0. If there are no more lines in the buffer, then the status is 1.

Usage Notes

- You can choose to retrieve from the buffer a single line or an array of lines. Call the `GET_LINE` procedure to retrieve a single line of buffered information. To reduce the number of calls to the server, call the `GET_LINES` procedure to retrieve an array of lines from the buffer.
- You can choose to automatically display this information if you are using Enterprise Manager or SQL*Plus by using the special `SET SERVEROUTPUT ON` command.
- After calling `GET_LINE` or `GET_LINES`, any lines not retrieved before the next call to `PUT`, `PUT_LINE`, or `NEW_LINE` are discarded to avoid confusing them with the next message.

GET_LINES Procedure

This procedure retrieves an array of lines from the buffer.

Syntax

```
DBMS_OUTPUT.GET_LINES (
    lines      OUT CHARARR,
    numlines   IN OUT INTEGER);
```

Parameters

Table 61–6 *GET_LINES Procedure Parameters*

Parameter	Description
lines	Returns an array of lines of buffered information. CHARARR is a table of VARCHAR2(255). The maximum length of each line in the array is 255 bytes.
numlines	Number of lines you want to retrieve from the buffer. After retrieving the specified number of lines, the procedure returns the number of lines actually retrieved. If this number is less than the number of lines requested, then there are no more lines in the buffer.

Usage Notes

- You can choose to retrieve from the buffer a single line or an array of lines. Call the GET_LINE procedure to retrieve a single line of buffered information. To reduce the number of calls to the server, call the GET_LINES procedure to retrieve an array of lines from the buffer.
- You can choose to automatically display this information if you are using Enterprise Manager or SQL*Plus by using the special SET SERVEROUTPUT ON command.
- After calling GET_LINE or GET_LINES, any lines not retrieved before the next call to PUT, PUT_LINE, or NEW_LINE are discarded to avoid confusing them with the next message.

NEW_LINE Procedure

This procedure puts an end-of-line marker. `GET_LINE(S)` returns "lines" as delimited by "newlines". Every call to `PUT_LINE` or `NEW_LINE` generates a line that is returned by `GET_LINE(S)`.

Syntax

```
DBMS_OUTPUT.NEW_LINE;
```

Exceptions

Table 61–7 *NEW_LINE Procedure Exceptions*

Error	Description
ORA-20000, ORU-10027:	Buffer overflow, limit of <buf_limit> bytes.
ORA-20000, ORU-10028:	Line length overflow, limit of 255 bytes for each line.

PUT Procedures

This procedure places a line in the buffer.

Note: The PUT procedure that takes a NUMBER is obsolete and, while currently supported, is included in this release for legacy reasons only.

Syntax

```
DBMS_OUTPUT.PUT      (item IN VARCHAR2);
```

```
DBMS_OUTPUT.PUT      (item IN NUMBER);
```

Parameters

Table 61–8 *PUT and PUT_LINE Procedure Parameters*

Parameter	Description
item	Item to buffer.

Exceptions

Table 61–9 *PUT and PUT_LINE Procedure Exceptions*

Error	Description
ORA-20000, ORU-10027:	Buffer overflow, limit of <buf_limit> bytes.
ORA-20000, ORU-10028:	Line length overflow, limit of 255 bytes for each line.

Usage Notes

- You can build a line of information piece by piece by making multiple calls to PUT, or place an entire line of information into the buffer by calling PUT_LINE.
- When you call PUT_LINE the item you specify is automatically followed by an end-of-line marker. If you make calls to PUT to build a line, then you must add your own end-of-line marker by calling NEW_LINE. GET_LINE and GET_LINES do not return lines that have not been terminated with a newline character.

- If your line exceeds the buffer limit, then you receive an error message.
- Output that you create using `PUT` or `PUT_LINE` is buffered. The output cannot be retrieved until the PL/SQL program unit from which it was buffered returns to its caller.

For example, Enterprise Manager or SQL*Plus do not display `DBMS_OUTPUT` messages until the PL/SQL program completes. There is no mechanism for flushing the `DBMS_OUTPUT` buffers within the PL/SQL program. For example:

```
SQL> SET SERVER OUTPUT ON
SQL> BEGIN
      2 DBMS_OUTPUT.PUT_LINE ('hello');
      3 DBMS_LOCK.SLEEP (10);
      4 END;
```

PUT_LINE Procedures

This procedure places a partial line in the buffer.

Note: The `PUT_LINE` procedure that takes a `NUMBER` is obsolete and, while currently supported, is included in this release for legacy reasons only.

Syntax

```
DBMS_OUTPUT.PUT_LINE (item IN VARCHAR2);
```

```
DBMS_OUTPUT.PUT      (item IN NUMBER);
```

Parameters

Table 61–10 *PUT and PUT_LINE Procedure Parameters*

Parameter	Description
item	Item to buffer.

Exceptions

Table 61–11 *PUT and PUT_LINE Procedure Exceptions*

Error	Description
ORA-20000, ORU-10027:	Buffer overflow, limit of <buf_limit> bytes.
ORA-20000, ORU-10028:	Line length overflow, limit of 255 bytes for each line.

Usage Notes

- You can build a line of information piece by piece by making multiple calls to `PUT`, or place an entire line of information into the buffer by calling `PUT_LINE`.
- When you call `PUT_LINE` the item you specify is automatically followed by an end-of-line marker. If you make calls to `PUT` to build a line, then you must add your own end-of-line marker by calling `NEW_LINE`. `GET_LINE` and `GET_LINES` do not return lines that have not been terminated with a newline character.

- If your line exceeds the buffer limit, then you receive an error message.
- Output that you create using `PUT` or `PUT_LINE` is buffered. The output cannot be retrieved until the PL/SQL program unit from which it was buffered returns to its caller.

For example, Enterprise Manager or SQL*Plus do not display `DBMS_OUTPUT` messages until the PL/SQL program completes. There is no mechanism for flushing the `DBMS_OUTPUT` buffers within the PL/SQL program. For example:

```
SQL> SET SERVER OUTPUT ON
SQL> BEGIN
    2 DBMS_OUTPUT.PUT_LINE ('hello');
    3 DBMS_LOCK.SLEEP (10);
    4 END;
```

DBMS_PCLXUTIL

The `DBMS_PCLXUTIL` package provides intra-partition parallelism for creating partition-wise local indexes. `DBMS_PCLXUTIL` circumvents the limitation that, for local index creation, the degree of parallelism is restricted to the number of partitions as only one slave process for each partition is used.

See Also: There are several rules concerning partitions and indexes. For more information, see *Oracle Database Concepts* and *Oracle Database Administrator's Guide*.

This chapter contains the following topics:

- [Using DBMS_PCLXUTIL](#)
 - [Overview](#)
 - [Operational Notes](#)
 - [Rules and Limits](#)
- [Summary of DBMS_PCLXUTIL Subprograms](#)

Using DBMS_PCLXUTIL

- [Overview](#)
- [Operational Notes](#)
- [Rules and Limits](#)

Overview

DBMS_PCLXUTIL uses the DBMS_JOB package to provide a greater degree of parallelism for creating a local index for a partitioned table. This is achieved by asynchronous inter-partition parallelism using the background processes (with DBMS_JOB), in combination with intra-partition parallelism using the parallel query slave processes.

DBMS_PCLXUTIL works with both range and range-hash composite partitioning.

The DBMS_PCLXUTIL package can be used during the following DBA tasks:

1. Local index creation

The procedure BUILD_PART_INDEX assumes that the dictionary information for the local index already exists. This can be done by issuing the create index SQL command with the UNUSABLE option.

```
CREATE INDEX <idx_name> on <tab_name>(…) local(…) unusable;
```

This causes the dictionary entries to be created without "building" the index itself, the time consuming part of creating an index. Now, invoking the procedure BUILD_PART_INDEX causes a concurrent build of local indexes with the specified degree of parallelism.

```
EXECUTE dbms_pclxutil.build_part_index(4,4,<tab_name>,<idx_name>,FALSE);
```

For composite partitions, the procedure automatically builds local indexes for all subpartitions of the composite table.

2. Local index maintenance

By marking desired partitions usable or unusable, the BUILD_PART_INDEX procedure also enables selective rebuilding of local indexes. The `force_opt` parameter provides a way to override this and build local indexes for all partitions.

```
ALTER INDEX <idx_name> local(...) unusable;
```

Rebuild only the desired (sub)partitions (that are marked unusable):

```
EXECUTE dbms_pclxutil.build_part_index(4,4,<tab_name>,<idx_name>,FALSE);
```

Rebuild all (sub)partitions using `force_opt = TRUE`:

```
EXECUTE dbms_pclxutil.build_part_index(4,4,<tab_name>,<idx_name>,TRUE);
```

A progress report is produced, and the output appears on screen when the program is ended (because the `DBMS_OUTPUT` package writes messages to a buffer first, and flushes the buffer to the screen only upon termination of the program).

Operational Notes

`DBMS_PCLXUTIL` submits a job for each partition. It is the responsibility of the user/dba to control the number of concurrent jobs by setting the `INIT.ORA` parameter `JOB_QUEUE_PROCESSES` correctly. There is minimal error checking for correct syntax. Any errors are reported in the job queue process trace files.

Rules and Limits

Note: For range partitioning, the minimum compatibility mode is 8.0; for range-hash composite partitioning, the minimum compatibility mode is 8i.

Because `DBMS_PCLXUTIL` uses the `DBMS_JOB` package, you must be aware of the following limitations pertaining to `DBMS_JOB`:

- You must decide appropriate values for the `job_queue_processes` initialization parameter. Clearly, if the job processes are not started before calling `BUILD_PART_INDEX()`, then the package will not function properly. The background processes are specified by the following `init.ora` parameters:


```
job_queue_processes=n    #the number of background processes = n
```
- Failure conditions are reported only in the trace files (a `DBMS_JOB` limitation), making it impossible to give interactive feedback to the user. This package

prints a failure message, removes unfinished jobs from the queue, and requests the user to take a look at the `j*.trc` trace files.

Summary of DBMS_PCLXUTIL Subprograms

Table 62–1 DBMS_PCLXUTIL Package Subprograms

Subprogram	Description
BUILD_PART_INDEX Procedure on page 62-6	Provides intra-partition parallelism for creating partition-wise local indexes

BUILD_PART_INDEX Procedure

This procedure provides intra-partition parallelism for creating partition-wise local indexes.

Syntax

```
DBMS_PCLXUTIL.BUILD_PART_INDEX (
  jobs_per_batch IN NUMBER   DEFAULT 1,
  procs_per_job  IN NUMBER   DEFAULT 1,
  tab_name       IN VARCHAR2 DEFAULT NULL,
  idx_name       IN VARCHAR2 DEFAULT NULL,
  force_opt      IN BOOLEAN  DEFAULT FALSE);
```

Parameters

Table 62–2 *BUILD_PART_INDEX Procedure Parameters*

Parameter	Description
jobs_per_batch	The number of concurrent partition-wise "local index builds".
procs_per_job	The number of parallel query slaves to be utilized for each local index build (1 <= procs_per_job <= max_slaves).
tab_name	The name of the partitioned table (an exception is raised if the table does not exist or not partitioned).
idx_name	The name given to the local index (an exception is raised if a local index is not created on the table tab_name).
force_opt	If TRUE, then force rebuild of all partitioned indexes; otherwise, rebuild only the partitions marked 'UNUSABLE'.

Examples

Suppose a table PROJECT is created with two partitions PROJ001 and PROJ002, along with a local index IDX.

A call to the procedure BUILD_PART_INDEX(2,4,'PROJECT','IDX',TRUE) produces the following output:

```
SQLPLUS> EXECUTE dbms_pclxutil.build_part_index(2,4,'PROJECT','IDX',TRUE);
Statement processed.
INFO: Job #21 created for partition PROJ002 with 4 slaves
INFO: Job #22 created for partition PROJ001 with 4 slaves
```

The `DBMS_PIPE` package lets two or more sessions in the same instance communicate. Oracle pipes are similar in concept to the pipes used in UNIX, but Oracle pipes are not implemented using the operating system pipe mechanisms.

This chapter contains the following topics:

- [Using DBMS_PIPE](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Operational Notes](#)
 - [Exceptions](#)
 - [Examples](#)
- [Summary of DBMS_PIPE Subprograms](#)

Using DBMS_PIPE

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Operational Notes](#)
- [Exceptions](#)
- [Examples](#)

Overview

Pipe functionality has several potential applications:

- **External service interface:** You can communicate with user-written services that are external to the RDBMS. This can be done effectively in a shared server process, so that several instances of the service are executing simultaneously. Additionally, the services are available asynchronously. The requestor of the service does not need to block a waiting reply. The requestor can check (with or without time out) at a later time. The service can be written in any of the 3GL languages that Oracle supports.
- **Independent transactions:** The pipe can communicate to a separate session which can perform an operation in an independent transaction (such as logging an attempted security violation detected by a trigger).
- **Alerters (non-transactional):** You can post another process without requiring the waiting process to poll. If an "after-row" or "after-statement" trigger were to alert an application, then the application would treat this alert as an indication that the data probably changed. The application would then read the data to get the current value. Because this is an "after" trigger, the application would want to do a "SELECT FOR UPDATE" to make sure it read the correct data.
- **Debugging:** Triggers and stored procedures can send debugging information to a pipe. Another session can keep reading out of the pipe and display it on the screen or write it to a file.
- **Concentrator:** This is useful for multiplexing large numbers of users over a fewer number of network connections, or improving performance by concentrating several user-transactions into one DBMS transaction.

Security Model

Security can be achieved by use of `GRANT EXECUTE` on the `DBMS_PIPE` package by creating a pipe using the `private` parameter in the `CREATE_PIPE` function and by writing cover packages that only expose particular features or pipenames to particular users or roles.

Depending upon your security requirements, you may choose to use either [Public Pipes](#) or [Private Pipes](#).

Constants

```
maxwait    constant integer := 86400000; /* 1000 days */
```

This is the maximum time to wait attempting to send or receive a message.

Operational Notes

Information sent through Oracle pipes is buffered in the system global area (SGA). All information in pipes is lost when the instance is shut down.

Caution: Pipes are independent of transactions. Be careful using pipes when transaction control can be affected.

The operation of `DBMS_PIPE` is considered with regard to the following topics:

- [Public Pipes](#)
- [Writing and Reading Pipes](#)
- [Private Pipes](#)

Public Pipes

You may create a public pipe either implicitly or explicitly. For *implicit* public pipes, the pipe is automatically created when it is referenced for the first time, and it disappears when it no longer contains data. Because the pipe descriptor is stored in the SGA, there is some space usage overhead until the empty pipe is aged out of the cache.

You create an *explicit* public pipe by calling the `CREATE_PIPE` function with the `private` flag set to `FALSE`. You must deallocate explicitly-created pipes by calling the `REMOVE_PIPE` function.

The domain of a public pipe is the schema in which it was created, either explicitly or implicitly.

Writing and Reading Pipes

Each public pipe works asynchronously. Any number of schema users can write to a public pipe, as long as they have `EXECUTE` permission on the `DBMS_PIPE` package, and they know the name of the public pipe. However, once buffered information is read by one user, it is emptied from the buffer, and is not available for other readers of the same pipe.

The sending session builds a message using one or more calls to the `PACK_MESSAGE` procedure. This procedure adds the message to the session's local message buffer. The information in this buffer is sent by calling the `SEND_MESSAGE` function, designating the pipe name to be used to send the message. When `SEND_MESSAGE` is called, all messages that have been stacked in the local buffer are sent.

A process that wants to receive a message calls the `RECEIVE_MESSAGE` function, designating the pipe name from which to receive the message. The process then calls the `UNPACK_MESSAGE` procedure to access each of the items in the message.

Private Pipes

You explicitly create a private pipe by calling the `CREATE_PIPE` function. Once created, the private pipe persists in shared memory until you explicitly deallocate it by calling the `REMOVE_PIPE` function. A private pipe is also deallocated when the database instance is shut down.

You cannot create a private pipe if an implicit pipe exists in memory and has the same name as the private pipe you are trying to create. In this case, `CREATE_PIPE` returns an error.

Access to a private pipe is restricted to:

- Sessions running under the same userid as the creator of the pipe
- Stored subprograms executing in the same userid privilege domain as the pipe creator
- Users connected as `SYSDBA`

An attempt by any other user to send or receive messages on the pipe, or to remove the pipe, results in an immediate error. Any attempt by another user to create a pipe with the same name also causes an error.

As with public pipes, you must first build your message using calls to `PACK_MESSAGE` before calling `SEND_MESSAGE`. Similarly, you must call `RECEIVE_MESSAGE` to retrieve the message before accessing the items in the message by calling `UNPACK_MESSAGE`.

Exceptions

DBMS_PIPE package subprograms can return the following errors:

Table 63–1 DBMS_PIPE Errors

Error	Description
ORA-23321:	Pipename may not be null. This can be returned by the <code>CREATE_PIPE</code> function, or any subprogram that takes a pipe name as a parameter.
ORA-23322:	Insufficient privilege to access pipe. This can be returned by any subprogram that references a private pipe in its parameter list.

Examples

- [Example 1: Debugging](#)
- [Example 2: Execute System Commands](#)
- [Example 3: External Service Interface](#)

Example 1: Debugging

This example shows the procedure that a PL/SQL program can call to place debugging information in a pipe.

```
CREATE OR REPLACE PROCEDURE debug (msg VARCHAR2) AS
    status NUMBER;
BEGIN
    DBMS_PIPE.PACK_MESSAGE(LENGTH(msg));
    DBMS_PIPE.PACK_MESSAGE(msg);
    status := DBMS_PIPE.SEND_MESSAGE('plsqli_debug');
    IF status != 0 THEN
        raise_application_error(-20099, 'Debug error');
```

```
    END IF;  
END debug;
```

The following Pro*C code receives messages from the PLSQL_DEBUG pipe in ["Example 1: Debugging"](#) and displays the messages. If the Pro*C session is run in a separate window, then it can be used to display any messages that are sent to the debug procedure from a PL/SQL program executing in a separate session.

```
#include <stdio.h>  
#include <string.h>  
  
EXEC SQL BEGIN DECLARE SECTION;  
    VARCHAR username[20];  
    int      status;  
    int      msg_length;  
    char     retval[2000];  
EXEC SQL END DECLARE SECTION;  
  
EXEC SQL INCLUDE SQLCA;  
  
void sql_error();  
  
main()  
{  
  
-- Prepare username:  
    strcpy(username.arr, "SCOTT/TIGER");  
    username.len = strlen(username.arr);  
  
    EXEC SQL WHENEVER SQLERROR DO sql_error();  
    EXEC SQL CONNECT :username;  
  
    printf("connected\n");  
  
-- Start an endless loop to look for and print messages on the pipe:  
    FOR (;;)   
    {  
        EXEC SQL EXECUTE  
            DECLARE  
                len INTEGER;  
                typ INTEGER;  
                sta INTEGER;  
                chr VARCHAR2(2000);  
            BEGIN  
                chr := '';
```

```

        sta := dbms_pipe.receive_message('plsql_debug');
        IF sta = 0 THEN
            DBMS_PIPE.UNPACK_MESSAGE(len);
            DBMS_PIPE.UNPACK_MESSAGE(chr);
        END IF;
        :status := sta;
        :retval := chr;
        IF len IS NOT NULL THEN
            :msg_length := len;
        ELSE
            :msg_length := 2000;
        END IF;
    END;
END-EXEC;
IF (status == 0)
    printf("\n%.*s\n", msg_length, retval);
ELSE
    printf("abnormal status, value is %d\n", status);
}
}

void sql_error()
{
    char msg[1024];
    int rlen, len;
    len = sizeof(msg);
    sqlglm(msg, &len, &rlen);
    printf("ORACLE ERROR\n");
    printf("%.*s\n", rlen, msg);
    exit(1);
}

```

Example 2: Execute System Commands

This example shows PL/SQL and Pro*C code let a PL/SQL stored procedure (or anonymous block) call PL/SQL procedures to send commands over a pipe to a Pro*C program that is listening for them.

The Pro*C program sleeps and waits for a message to arrive on the named pipe. When a message arrives, the Pro*C program processes it, carrying out the required action, such as executing a UNIX command through the *system()* call or executing a SQL command using embedded SQL.

DAEMON.SQL is the source code for the PL/SQL package. This package contains procedures that use the DBMS_PIPE package to send and receive message to and

from the Pro*C daemon. Note that full handshaking is used. The daemon always sends a message back to the package (except in the case of the STOP command). This is valuable, because it allows the PL/SQL procedures to be sure that the Pro*C daemon is running.

You can call the DAEMON packaged procedures from an anonymous PL/SQL block using SQL*Plus or Enterprise Manager. For example:

```
SQLPLUS> variable rv number
SQLPLUS> execute :rv := DAEMON.EXECUTE_SYSTEM('ls -la');
```

On a UNIX system, this causes the Pro*C daemon to execute the command `system("ls -la")`.

Remember that the daemon needs to be running first. You might want to run it in the background, or in another window beside the SQL*Plus or Enterprise Manager session from which you call it.

The DAEMON.SQL also uses the DBMS_OUTPUT package to display the results. For this example to work, you must have execute privileges on this package.

DAEMON.SQL Example. This is the code for the PL/SQL DAEMON package:

```
CREATE OR REPLACE PACKAGE daemon AS
  FUNCTION execute_sql(command VARCHAR2,
                      timeout NUMBER DEFAULT 10)
    RETURN NUMBER;

  FUNCTION execute_system(command VARCHAR2,
                          timeout NUMBER DEFAULT 10)
    RETURN NUMBER;

  PROCEDURE stop(timeout NUMBER DEFAULT 10);
END daemon;
/
CREATE OR REPLACE PACKAGE BODY daemon AS

  FUNCTION execute_system(command VARCHAR2,
                          timeout NUMBER DEFAULT 10)

  RETURN NUMBER IS

    status      NUMBER;
    result      VARCHAR2(20);
    command_code NUMBER;
    pipe_name   VARCHAR2(30);
  BEGIN
```

```
pipe_name := DBMS_PIPE.UNIQUE_SESSION_NAME;

DBMS_PIPE.PACK_MESSAGE('SYSTEM');
DBMS_PIPE.PACK_MESSAGE(pipe_name);
DBMS_PIPE.PACK_MESSAGE(command);
status := DBMS_PIPE.SEND_MESSAGE('daemon', timeout);
IF status <> 0 THEN
    RAISE_APPLICATION_ERROR(-20010,
        'Execute_system: Error while sending. Status = ' ||
        status);
END IF;

status := DBMS_PIPE.RECEIVE_MESSAGE(pipe_name, timeout);
IF status <> 0 THEN
    RAISE_APPLICATION_ERROR(-20011,
        'Execute_system: Error while receiving.
        Status = ' || status);
END IF;

DBMS_PIPE.UNPACK_MESSAGE(result);
IF result <> 'done' THEN
    RAISE_APPLICATION_ERROR(-20012,
        'Execute_system: Done not received.');
```

```
END IF;

DBMS_PIPE.UNPACK_MESSAGE(command_code);
DBMS_OUTPUT.PUT_LINE('System command executed. result = ' ||
    command_code);
RETURN command_code;
END execute_system;

FUNCTION execute_sql(command VARCHAR2,
    timeout NUMBER DEFAULT 10)
RETURN NUMBER IS

    status      NUMBER;
    result      VARCHAR2(20);
    command_code NUMBER;
    pipe_name   VARCHAR2(30);

BEGIN
    pipe_name := DBMS_PIPE.UNIQUE_SESSION_NAME;

    DBMS_PIPE.PACK_MESSAGE('SQL');
    DBMS_PIPE.PACK_MESSAGE(pipe_name);
```

```
DBMS_PIPE.PACK_MESSAGE(command);
status := DBMS_PIPE.SEND_MESSAGE('daemon', timeout);
IF status <> 0 THEN
    RAISE_APPLICATION_ERROR(-20020,
        'Execute_sql: Error while sending. Status = ' || status);
END IF;

status := DBMS_PIPE.RECEIVE_MESSAGE(pipe_name, timeout);

IF status <> 0 THEN
    RAISE_APPLICATION_ERROR(-20021,
        'execute_sql: Error while receiving.
        Status = ' || status);
END IF;

DBMS_PIPE.UNPACK_MESSAGE(result);
IF result <> 'done' THEN
    RAISE_APPLICATION_ERROR(-20022,
        'execute_sql: done not received. ');
END IF;

DBMS_PIPE.UNPACK_MESSAGE(command_code);
DBMS_OUTPUT.PUT_LINE
    ('SQL command executed. sqlcode = ' || command_code);
RETURN command_code;
END execute_sql;

PROCEDURE stop(timeout NUMBER DEFAULT 10) IS
    status NUMBER;
BEGIN
    DBMS_PIPE.PACK_MESSAGE('STOP');
    status := DBMS_PIPE.SEND_MESSAGE('daemon', timeout);
    IF status <> 0 THEN
        RAISE_APPLICATION_ERROR(-20030,
            'stop: error while sending. status = ' || status);
    END IF;
END stop;
END daemon;
```

daemon.pc Example. This is the code for the Pro*C daemon. You must precompile this using the Pro*C Precompiler, Version 1.5.x or later. You must also specify the `USERID` and `SQLCHECK` options, as the example contains embedded PL/SQL code.

Note: To use a VARCHAR output host variable in a PL/SQL block, you must initialize the length component before entering the block.

```
proc iname=daemon userid=scott/tiger sqlcheck=semantics
```

Then C-compile and link in the normal way.

```
#include <stdio.h>
#include <string.h>

EXEC SQL INCLUDE SQLCA;

EXEC SQL BEGIN DECLARE SECTION;
    char *uid = "scott/tiger";
    int status;
    VARCHAR command[20];
    VARCHAR value[2000];
    VARCHAR return_name[30];
EXEC SQL END DECLARE SECTION;

void
connect_error()
{
    char msg_buffer[512];
    int msg_length;
    int buffer_size = 512;

    EXEC SQL WHENEVER SQLEERROR CONTINUE;
    sqlglm(msg_buffer, &buffer_size, &msg_length);
    printf("Daemon error while connecting:\n");
    printf("%.*s\n", msg_length, msg_buffer);
    printf("Daemon quitting.\n");
    exit(1);
}

void
sql_error()
{
    char msg_buffer[512];
    int msg_length;
    int buffer_size = 512;
```

```
EXEC SQL WHENEVER SQLERROR CONTINUE;
sqlglm(msg_buffer, &buffer_size, &msg_length);
printf("Daemon error while executing:\n");
printf("%.s\n", msg_length, msg_buffer);
printf("Daemon continuing.\n");
}
main()
{
command.len = 20; /*initialize length components*/
value.len = 2000;
return_name.len = 30;
EXEC SQL WHENEVER SQLERROR DO connect_error();
EXEC SQL CONNECT :uid;
printf("Daemon connected.\n");

EXEC SQL WHENEVER SQLERROR DO sql_error();
printf("Daemon waiting...\n");
while (1) {
EXEC SQL EXECUTE
BEGIN
:status := DBMS_PIPE.RECEIVE_MESSAGE('daemon');
IF :status = 0 THEN
DBMS_PIPE.UNPACK_MESSAGE(:command);
END IF;
END;
END-EXEC;
IF (status == 0)
{
command.arr[command.len] = '\0';
IF (!strcmp((char *) command.arr, "STOP"))
{
printf("Daemon exiting.\n");
break;
}

ELSE IF (!strcmp((char *) command.arr, "SYSTEM"))
{
EXEC SQL EXECUTE
BEGIN
DBMS_PIPE.UNPACK_MESSAGE(:return_name);
DBMS_PIPE.UNPACK_MESSAGE(:value);
END;
END-EXEC;
value.arr[value.len] = '\0';
printf("Will execute system command '%s'\n", value.arr);
```



```
status = system(value.arr);
EXEC SQL EXECUTE
    BEGIN
        DBMS_PIPE.PACK_MESSAGE('done');
        DBMS_PIPE.PACK_MESSAGE(:status);
        :status := DBMS_PIPE.SEND_MESSAGE(:return_name);
    END;
END-EXEC;

IF (status)
{
    printf
        ("Daemon error while responding to system command.");
    printf("  status: %d\n", status);
}
}
ELSE IF (!strcmp((char *) command.arr, "SQL")) {
    EXEC SQL EXECUTE
        BEGIN
            DBMS_PIPE.UNPACK_MESSAGE(:return_name);
            DBMS_PIPE.UNPACK_MESSAGE(:value);
        END;
    END-EXEC;
    value.arr[value.len] = '\0';
    printf("Will execute sql command '%s'\n", value.arr);

    EXEC SQL WHENEVER SQLERROR CONTINUE;
    EXEC SQL EXECUTE IMMEDIATE :value;
    status = sqlca.sqlcode;

    EXEC SQL WHENEVER SQLERROR DO sql_error();
    EXEC SQL EXECUTE
        BEGIN
            DBMS_PIPE.PACK_MESSAGE('done');
            DBMS_PIPE.PACK_MESSAGE(:status);
            :status := DBMS_PIPE.SEND_MESSAGE(:return_name);
        END;
    END-EXEC;

    IF (status)
    {
        printf("Daemon error while responding to sql command.");
        printf("  status: %d\n", status);
    }
}
```

```

    }
    ELSE
    {
        printf
            ("Daemon error: invalid command '%s' received.\n",
             command.arr);
    }
}
ELSE
{
    printf("Daemon error while waiting for signal.");
    printf(" status = %d\n", status);
}
}
EXEC SQL COMMIT WORK RELEASE;
exit(0);

```

Example 3: External Service Interface

Put the user-written 3GL code into an OCI or Precompiler program. The program connects to the database and executes PL/SQL code to read its request from the pipe, computes the result, and then executes PL/SQL code to send the result on a pipe back to the requestor.

Below is an example of a stock service request. The recommended sequence for the arguments to pass on the pipe for all service requests is:

protocol_version	VARCHAR2	- '1', 10 bytes or less
returnpipe	VARCHAR2	- 30 bytes or less
service	VARCHAR2	- 30 bytes or less
arg1	VARCHAR2/NUMBER/DATE	
...		
argn	VARCHAR2/NUMBER/DATE	

The recommended format for returning the result is:

success	VARCHAR2	- 'SUCCESS' if OK, otherwise error message
arg1	VARCHAR2/NUMBER/DATE	
...		
argn	VARCHAR2/NUMBER/DATE	

The "stock price request server" would do, using OCI or PRO* (in pseudo-code):

```

<loop forever>
    BEGIN dbms_stock_server.get_request(:stocksymbol); END;

```

```

<figure out price based on stocksymbol (probably from some radio
    signal), set error if can't find such a stock>
BEGIN dbms_stock_server.return_price(:error, :price); END;

```

A client would do:

```
BEGIN :price := stock_request('YOURCOMPANY'); end;
```

The stored procedure, dbms_stock_server, which is called by the preceding "stock price request server" is:

```

CREATE OR REPLACE PACKAGE dbms_stock_server IS
  PROCEDURE get_request(symbol OUT VARCHAR2);
  PROCEDURE return_price(errormsg IN VARCHAR2, price IN VARCHAR2);
END;

CREATE OR REPLACE PACKAGE BODY dbms_stock_server IS
  returnpipe  VARCHAR2(30);

  PROCEDURE returnerror(reason VARCHAR2) IS
    s INTEGER;
  BEGIN
    dbms_pipe.pack_message(reason);
    s := dbms_pipe.send_message(returnpipe);
    IF s <> 0 THEN
      raise_application_error(-20000, 'Error:' || to_char(s) ||
        ' sending on pipe');
    END IF;
  END;

  PROCEDURE get_request(symbol OUT VARCHAR2) IS
    protocol_version VARCHAR2(10);
    s                 INTEGER;
    service           VARCHAR2(30);
  BEGIN
    s := dbms_pipe.receive_message('stock_service');
    IF s <> 0 THEN
      raise_application_error(-20000, 'Error:' || to_char(s) ||
        ' reading pipe');
    END IF;
    dbms_pipe.unpack_message(protocol_version);
    IF protocol_version <> '1' THEN
      raise_application_error(-20000, 'Bad protocol: ' ||
        protocol_version);
    END IF;
  END;

```

```
    dbms_pipe.unpack_message(returnpipe);
    dbms_pipe.unpack_message(service);
    IF service != 'getprice' THEN
        returnerror('Service ' || service || ' not supported');
    END IF;
    dbms_pipe.unpack_message(symbol);
END;

PROCEDURE return_price(errormsg in VARCHAR2, price in VARCHAR2) IS
    s INTEGER;
BEGIN
    IF errormsg is NULL THEN
        dbms_pipe.pack_message('SUCCESS');
        dbms_pipe.pack_message(price);
    ELSE
        dbms_pipe.pack_message(errormsg);
    END IF;
    s := dbms_pipe.send_message(returnpipe);
    IF s <> 0 THEN
        raise_application_error(-20000, 'Error:' || to_char(s) ||
            ' sending on pipe');
    END IF;
END;
END;
```

The procedure called by the client is:

```
CREATE OR REPLACE FUNCTION stock_request (symbol VARCHAR2)
    RETURN VARCHAR2 IS
    s          INTEGER;
    price     VARCHAR2(20);
    errormsg  VARCHAR2(512);
BEGIN
    dbms_pipe.pack_message('1'); -- protocol version
    dbms_pipe.pack_message(dbms_pipe.unique_session_name); -- return pipe
    dbms_pipe.pack_message('getprice');
    dbms_pipe.pack_message(symbol);
    s := dbms_pipe.send_message('stock_service');
    IF s <> 0 THEN
        raise_application_error(-20000, 'Error:' || to_char(s) ||
            ' sending on pipe');
    END IF;
    s := dbms_pipe.receive_message(dbms_pipe.unique_session_name);
    IF s <> 0 THEN
        raise_application_error(-20000, 'Error:' || to_char(s) ||
```

```
        ' receiving on pipe');  
END IF;  
dbms_pipe.unpack_message(errormsg);  
IF errormsg <> 'SUCCESS' THEN  
    raise_application_error(-20000, errormsg);  
END IF;  
dbms_pipe.unpack_message(price);  
RETURN price;  
END;
```

You would typically only grant execute on `dbms_stock_service` to the stock service application server, and would only grant execute on `stock_request` to those users allowed to use the service.

See Also: [Chapter 13, "DBMS_ALERT"](#)

Summary of DBMS_PIPE Subprograms

Table 63–2 DBMS_PIPE Package Subprograms

Subprogram	Description
CREATE_PIPE Function on page 63-19	Creates a pipe (necessary for private pipes)
PACK_MESSAGE Procedures on page 63-21	Builds message in local buffer
SEND_MESSAGE Function on page 63-23	Sends message on named pipe: This implicitly creates a public pipe if the named pipe does not exist
RECEIVE_MESSAGE Function on page 63-26	Copies message from named pipe into local buffer
NEXT_ITEM_TYPE Function on page 63-28	Returns datatype of next item in buffer
UNPACK_MESSAGE Procedures on page 63-29	Accesses next item in buffer
REMOVE_PIPE Function on page 63-31	Removes the named pipe
PURGE Procedure on page 63-33	Purges contents of named pipe
RESET_BUFFER Procedure on page 63-34	Purges contents of local buffer
UNIQUE_SESSION_NAME Function on page 63-35	Returns unique session name

CREATE_PIPE Function

This function explicitly creates a public or private pipe. If the `private` flag is `TRUE`, then the pipe creator is assigned as the owner of the private pipe.

Explicitly-created pipes can only be removed by calling `REMOVE_PIPE`, or by shutting down the instance.

Syntax

```
DBMS_PIPE.CREATE_PIPE (
    pipename      IN VARCHAR2,
    maxpipesize  IN INTEGER DEFAULT 8192,
    private       IN BOOLEAN DEFAULT TRUE)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(create_pipe,WNDS,RNDS);
```

Parameters

Table 63–3 CREATE_PIPE Function Parameters

Parameter	Description
<code>pipename</code>	<p>Name of the pipe you are creating.</p> <p>You must use this name when you call <code>SEND_MESSAGE</code> and <code>RECEIVE_MESSAGE</code>. This name must be unique across the instance.</p> <p>Caution: Do not use pipe names beginning with <code>ORA\$</code>. These are reserved for use by procedures provided by Oracle. Pipename should not be longer than 128 bytes, and is case insensitive. At this time, the name cannot contain Globalization Support characters.</p>

Table 63–3 (Cont.) CREATE_PIPE Function Parameters

Parameter	Description
maxpipesize	<p>The maximum size allowed for the pipe, in bytes.</p> <p>The total size of all of the messages on the pipe cannot exceed this amount. The message is blocked if it exceeds this maximum. The default maxpipesize is 8192 bytes.</p> <p>The maxpipesize for a pipe becomes a part of the characteristics of the pipe and persists for the life of the pipe. Callers of SEND_MESSAGE with larger values cause the maxpipesize to be increased. Callers with a smaller value use the existing, larger value.</p>
private	<p>Uses the default, TRUE, to create a private pipe.</p> <p>Public pipes can be implicitly created when you call SEND_MESSAGE.</p>

Return Values

Table 63–4 CREATE_PIPE Function Return Values

Return	Description
0	<p>Successful.</p> <p>If the pipe already exists and the user attempting to create it is authorized to use it, then Oracle returns 0, indicating success, and any data already in the pipe remains.</p> <p>If a user connected as SYSDBA/SYSOPER re-creates a pipe, then Oracle returns status 0, but the ownership of the pipe remains unchanged.</p>
ORA-23322	<p>Failure due to naming conflict.</p> <p>If a pipe with the same name exists and was created by a different user, then Oracle signals error ORA-23322, indicating the naming conflict.</p>

Exceptions

Table 63–5 CREATE_PIPE Function Exception

Exception	Description
Null pipe name	Permission error: Pipe with the same name already exists, and you are not allowed to use it.

PACK_MESSAGE Procedures

This procedure builds your message in the local message buffer. To send a message, first make one or more calls to `PACK_MESSAGE`. Then, call `SEND_MESSAGE` to send the message in the local buffer on the named pipe.

The procedure is overloaded to accept items of type `VARCHAR2`, `NCHAR`, `NUMBER`, `DATE`, `RAW` and `ROWID` items. In addition to the data bytes, each item in the buffer requires one byte to indicate its type, and two bytes to store its length. One additional byte is needed to terminate the message. The overhead for all types other than `VARCHAR` is 4 bytes.

Syntax

```
DBMS_PIPE.PACK_MESSAGE (  
    item IN VARCHAR2);  
  
DBMS_PIPE.PACK_MESSAGE (  
    item IN NCHAR);  
  
DBMS_PIPE.PACK_MESSAGE (  
    item IN NUMBER);  
  
DBMS_PIPE.PACK_MESSAGE (  
    item IN DATE);  
  
DBMS_PIPE.PACK_MESSAGE_RAW (  
    item IN RAW);  
  
DBMS_PIPE.PACK_MESSAGE_ROWID (  
    item IN ROWID);
```

Pragmas

```
pragma restrict_references(pack_message,WNDS,RNDS);  
pragma restrict_references(pack_message_raw,WNDS,RNDS);  
pragma restrict_references(pack_message_rowid,WNDS,RNDS);
```

Parameters

Table 63–6 *PACK_MESSAGE Procedure Parameters*

Parameter	Description
<code>item</code>	Item to pack into the local message buffer.

Usage Notes

In Oracle database version 8.x, the char-set-id (2 bytes) and the char-set-form (1 byte) are stored with each data item. Therefore, the overhead when using Oracle database version 8.x is 7 bytes.

When you call `SEND_MESSAGE` to send this message, you must indicate the name of the pipe on which you want to send the message. If this pipe already exists, then you must have sufficient privileges to access this pipe. If the pipe does not already exist, then it is created automatically.

Exceptions

ORA-06558 is raised if the message buffer overflows (currently 4096 bytes). Each item in the buffer takes one byte for the type, two bytes for the length, plus the actual data. There is also one byte needed to terminate the message.

SEND_MESSAGE Function

This function sends a message on the named pipe.

The message is contained in the local message buffer, which was filled with calls to `PACK_MESSAGE`. You can create a pipe explicitly using `CREATE_PIPE`, otherwise, it is created implicitly.

Syntax

```
DBMS_PIPE.SEND_MESSAGE (
    pipename      IN VARCHAR2,
    timeout       IN INTEGER DEFAULT MAXWAIT,
    maxpipesize   IN INTEGER DEFAULT 8192)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(send_message,WNDS,RNDS);
```

Parameters

Table 63–7 SEND_MESSAGE Function Parameters

Parameter	Description
<code>pipename</code>	<p>Name of the pipe on which you want to place the message.</p> <p>If you are using an explicit pipe, then this is the name that you specified when you called <code>CREATE_PIPE</code>.</p> <p>Caution: Do not use pipe names beginning with 'ORA\$'. These names are reserved for use by procedures provided by Oracle. Pipename should not be longer than 128 bytes, and is case-insensitive. At this time, the name cannot contain Globalization Support characters.</p>
<code>timeout</code>	<p>Time to wait while attempting to place a message on a pipe, in seconds.</p> <p>The default value is the constant <code>MAXWAIT</code>, which is defined as 86400000 (1000 days).</p>

Table 63–7 (Cont.) SEND_MESSAGE Function Parameters

Parameter	Description
maxpipesize	<p>Maximum size allowed for the pipe, in bytes.</p> <p>The total size of all the messages on the pipe cannot exceed this amount. The message is blocked if it exceeds this maximum. The default is 8192 bytes.</p> <p>The maxpipesize for a pipe becomes a part of the characteristics of the pipe and persists for the life of the pipe. Callers of SEND_MESSAGE with larger values cause the maxpipesize to be increased. Callers with a smaller value simply use the existing, larger value.</p> <p>Specifying maxpipesize as part of the SEND_MESSAGE procedure eliminates the need for a separate call to open the pipe. If you created the pipe explicitly, then you can use the optional maxpipesize parameter to override the creation pipe size specifications.</p>

Return Values

Table 63–8 SEND_MESSAGE Function Return Values

Return	Description
0	<p>Success.</p> <p>If the pipe already exists and the user attempting to create it is authorized to use it, then Oracle returns 0, indicating success, and any data already in the pipe remains.</p> <p>If a user connected as SYSDBS/SYSOPER re-creates a pipe, then Oracle returns status 0, but the ownership of the pipe remains unchanged.</p>
1	<p>Timed out.</p> <p>This procedure can timeout either because it cannot get a lock on the pipe, or because the pipe remains too full to be used. If the pipe was implicitly-created and is empty, then it is removed.</p>
3	<p>An interrupt occurred.</p> <p>If the pipe was implicitly created and is empty, then it is removed.</p>
ORA-23322	<p>Insufficient privileges.</p> <p>If a pipe with the same name exists and was created by a different user, then Oracle signals error ORA-23322, indicating the naming conflict.</p>

Exceptions

Table 63–9 *SEND_MESSAGE Function Exception*

Exception	Description
Null pipe name	Permission error. Insufficient privilege to write to the pipe. The pipe is private and owned by someone else.

RECEIVE_MESSAGE Function

This function copies the message into the local message buffer.

Syntax

```
DBMS_PIPE.RECEIVE_MESSAGE (  
    pipename      IN VARCHAR2,  
    timeout       IN INTEGER      DEFAULT maxwait)  
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(receive_message,WNDS,RNDS);
```

Parameters

Table 63–10 RECEIVE_MESSAGE Function Parameters

Parameter	Description
pipename	Name of the pipe on which you want to receive a message. Names beginning with ORA\$ are reserved for use by Oracle
timeout	Time to wait for a message, in seconds. The default value is the constant MAXWAIT, which is defined as 86400000 (1000 days). A timeout of 0 lets you read without blocking.

Return Values

Table 63–11 RECEIVE_MESSAGE Function Return Values

Return	Description
0	Success
1	Timed out. If the pipe was implicitly-created and is empty, then it is removed.
2	Record in the pipe is too large for the buffer. (This should not happen.)
3	An interrupt occurred.
ORA-23322	User has insufficient privileges to read from the pipe.

Usage Notes

To receive a message from a pipe, first call `RECEIVE_MESSAGE`. When you receive a message, it is removed from the pipe; hence, a message can only be received once. For implicitly-created pipes, the pipe is removed after the last record is removed from the pipe.

If the pipe that you specify when you call `RECEIVE_MESSAGE` does not already exist, then Oracle implicitly creates the pipe and waits to receive the message. If the message does not arrive within a designated timeout interval, then the call returns and the pipe is removed.

After receiving the message, you must make one or more calls to `UNPACK_MESSAGE` to access the individual items in the message. The `UNPACK_MESSAGE` procedure is overloaded to unpack items of type `DATE`, `NUMBER`, `VARCHAR2`, and there are two additional procedures to unpack `RAW` and `ROWID` items. If you do not know the type of data that you are attempting to unpack, then call `NEXT_ITEM_TYPE` to determine the type of the next item in the buffer.

Exceptions

Table 63–12 *RECEIVE_MESSAGE Function Exceptions*

Exception	Description
Null pipe name	Permission error. Insufficient privilege to remove the record from the pipe. The pipe is owned by someone else.

NEXT_ITEM_TYPE Function

This function determines the datatype of the next item in the local message buffer.

After you have called `RECEIVE_MESSAGE` to place pipe information in a local buffer, call `NEXT_ITEM_TYPE`.

Syntax

```
DBMS_PIPE.NEXT_ITEM_TYPE  
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(next_item_type,WNDS,RNDS);
```

Return Values

Table 63–13 *NEXT_ITEM_TYPE* Function Return Values

Return	Description
0	No more items
6	NUMBER
9	VARCHAR2
11	ROWID
12	DATE
23	RAW

UNPACK_MESSAGE Procedures

This procedure retrieves items from the buffer.

After you have called `RECEIVE_MESSAGE` to place pipe information in a local buffer, call `UNPACK_MESSAGE`.

Note: The `UNPACK_MESSAGE` procedure is overloaded to return items of type `VARCHAR2`, `NCHAR`, `NUMBER`, or `DATE`. There are two additional procedures to unpack `RAW` and `ROWID` items.

Syntax

```
DBMS_PIPE.UNPACK_MESSAGE (  
    item OUT VARCHAR2);  
  
DBMS_PIPE.UNPACK_MESSAGE (  
    item OUT NCHAR);  
  
DBMS_PIPE.UNPACK_MESSAGE (  
    item OUT NUMBER);  
  
DBMS_PIPE.UNPACK_MESSAGE (  
    item OUT DATE);  
  
DBMS_PIPE.UNPACK_MESSAGE_RAW (  
    item OUT RAW);  
  
DBMS_PIPE.UNPACK_MESSAGE_ROWID (  
    item OUT ROWID);
```

Pragmas

```
pragma restrict_references(unpack_message,WNDS,RNDS);  
pragma restrict_references(unpack_message_raw,WNDS,RNDS);  
pragma restrict_references(unpack_message_rowid,WNDS,RNDS);
```

Parameters

Table 63–14 *UNPACK_MESSAGE Procedure Parameters*

Parameter	Description
<code>item</code>	Argument to receive the next unpacked item from the local message buffer.

Exceptions

ORA-06556 or 06559 are generated if the buffer contains no more items, or if the item is not of the same type as that requested.

REMOVE_PIPE Function

This function removes explicitly-created pipes.

Pipes created implicitly by `SEND_MESSAGE` are automatically removed when empty. However, pipes created explicitly by `CREATE_PIPE` are removed only by calling `REMOVE_PIPE`, or by shutting down the instance. All unconsumed records in the pipe are removed before the pipe is deleted.

This is similar to calling `PURGE` on an implicitly-created pipe.

Syntax

```
DBMS_PIPE.REMOVE_PIPE (
    pipename IN VARCHAR2)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(remove_pipe,WNDS,RNDS);
```

Parameters

Table 63–15 REMOVE_PIPE Function Parameters

Parameter	Description
pipename	Name of pipe that you want to remove.

Return Values

Table 63–16 REMOVE_PIPE Function Return Values

Return	Description
0	Success If the pipe does not exist, or if the pipe already exists and the user attempting to remove it is authorized to do so, then Oracle returns 0, indicating success, and any data remaining in the pipe is removed.
ORA-23322	Insufficient privileges. If the pipe exists, but the user is not authorized to access the pipe, then Oracle signals error ORA-23322, indicating insufficient privileges.

Exceptions

Table 63–17 *REMOVE_PIPE Function Exception*

Exception	Description
Null pipe name	Permission error: Insufficient privilege to remove pipe. The pipe was created and is owned by someone else.

PURGE Procedure

This procedure empties the contents of the named pipe.

An empty implicitly-created pipe is aged out of the shared global area according to the least-recently-used algorithm. Thus, calling `PURGE` lets you free the memory associated with an implicitly-created pipe.

Syntax

```
DBMS_PIPE.PURGE (
    pipename IN VARCHAR2);
```

Pragmas

```
pragma restrict_references(purge,WNDS,RNDS);
```

Parameters

Table 63–18 *PURGE Procedure Parameters*

Parameter	Description
pipename	Name of pipe from which to remove all messages. The local buffer may be overwritten with messages as they are discarded. Pipename should not be longer than 128 bytes, and is case-insensitive.

Usage Notes

Because `PURGE` calls `RECEIVE_MESSAGE`, the local buffer might be overwritten with messages as they are purged from the pipe. Also, you can receive an `ORA-23322 (insufficient privileges)` error if you attempt to purge a pipe with which you have insufficient access rights.

Exceptions

Permission error if pipe belongs to another user.

RESET_BUFFER Procedure

This procedure resets the `PACK_MESSAGE` and `UNPACK_MESSAGE` positioning indicators to 0.

Because all pipes share a single buffer, you may find it useful to reset the buffer before using a new pipe. This ensures that the first time you attempt to send a message to your pipe, you do not inadvertently send an expired message remaining in the buffer.

Syntax

```
DBMS_PIPE.RESET_BUFFER;
```

Pragmas

```
pragma restrict_references(reset_buffer,WNDS,RNDS);
```

UNIQUE_SESSION_NAME Function

This function receives a name that is unique among all of the sessions that are currently connected to a database.

Multiple calls to this function from the same session always return the same value. You might find it useful to use this function to supply the `PIPENAME` parameter for your `SEND_MESSAGE` and `RECEIVE_MESSAGE` calls.

Syntax

```
DBMS_PIPE.UNIQUE_SESSION_NAME  
    RETURN VARCHAR2;
```

Pragmas

```
pragma restrict_references(unique_session_name,WNDS,RNDS,WNPS);
```

Return Values

This function returns a unique name. The returned name can be up to 30 bytes.

DBMS_PROFILER

The `DBMS_PROFILER` package provides an interface to profile existing PL/SQL applications and identify performance bottlenecks. You can then collect and persistently store the PL/SQL profiler data.

This chapter contains the following topics:

- [Using DBMS_PROFILER](#)
 - [Overview](#)
 - [Security Model](#)
 - [Operational Notes](#)
 - [Exceptions](#)
- [Summary of DBMS_PROFILER Subprograms](#)

Using DBMS_PROFILER

- [Overview](#)
- [Security Model](#)
- [Operational Notes](#)
- [Exceptions](#)

Overview

This package enables the collection of profiler (performance) data for performance improvement or for determining code coverage for PL/SQL applications. Application developers can use code coverage data to focus their incremental testing efforts.

With this interface, you can generate profiling information for all named library units that are executed in a session. The profiler gathers information at the PL/SQL virtual machine level. This information includes the total number of times each line has been executed, the total amount of time that has been spent executing that line, and the minimum and maximum times that have been spent on a particular execution of that line.

Note: It is possible to infer the code coverage figures for PL/SQL units for which data has been collected.

The profiling information is stored in database tables. This enables querying on the data: you can build customizable reports (summary reports, hottest lines, code coverage data, and so on. And you can analyze the data.

The `PROFTAB.SQL` script creates tables with the columns, datatypes, and definitions as shown in [Table 64–1](#), [Table 64–2](#), and [Table 64–3](#).

Table 64–1 Columns in Table `PLSQL_PROFILER_RUNS`

Column	Datatype	Definition
<code>runid</code>	NUMBER PRIMARY KEY	Unique run identifier from <code>plsql_profiler_runnumber</code>
<code>related_run</code>	NUMBER	Runid of related run (for client/server correlation)

Table 64–1 (Cont.) Columns in Table PLSQL_PROFILER_RUNS

Column	Datatype	Definition
run_owner	VARCHAR2(32)	User who started run
run_date	DATE	Start time of run
run_comment	VARCHAR2(2047)	User provided comment for this run
run_total_time	NUMBER	Elapsed time for this run in nanoseconds
run_system_info	VARCHAR2(2047)	Currently unused
run_comment1	VARCHAR2(2047)	Additional comment
spare1	VARCHAR2(256)	Unused

Table 64–2 Columns in Table PLSQL_PROFILER_UNITS

Column	Datatype	Definition
runid	NUMBER	Primary key, references plsql_profiler_runs,
unit_number	NUMBER	Primary key, internally generated library unit #
unit_type	VARCHAR2(32)	Library unit type
unit_owner	VARCHAR2(32)	Library unit owner name
unit_name	VARCHAR2(32)	Library unit name timestamp on library unit
unit_timestamp	DATE	In the future will be used to detect changes to unit between runs
total_time	NUMBER	Total time spent in this unit in nanoseconds. The profiler does not set this field, but it is provided for the convenience of analysis tools.
spare1	NUMBER	Unused
spare2	NUMBER	Unused

Table 64–3 Columns in Table PLSQL_PROFILER_DATA

Column	Datatype	Definition
runid	NUMBER	Primary key, unique (generated) run identifier
unit_number	NUMBER	Primary key, internally generated library unit number

Table 64–3 (Cont.) Columns in Table PLSQL_PROFILER_DATA

Column	Datatype	Definition
line#	NUMBER	Primary key, not null, line number in unit
total_occur	NUMBER	Number of times line was executed
total_time	NUMBER	Total time spent executing line in nanoseconds
min_time	NUMBER	Minimum execution time for this line in nanoseconds
max_time	NUMBER	Maximum execution time for this line in nanoseconds
spare1	NUMBER	Unused
spare2	NUMBER	Unused
spare3	NUMBER	Unused
spare4	NUMBER	Unused

With Oracle database version 8.x, a sample textual report writer (profrep.sql) is provided with the PL/SQL demo scripts.

Security Model

The profiler only gathers data for units for which a user has `CREATE` privilege; you cannot use the package to profile units for which `EXECUTE ONLY` access has been granted. In general, if a user can debug a unit, the same user can profile it. However, a unit can be profiled whether or not it has been compiled `DEBUG`. Oracle advises that modules that are being profiled should be compiled `DEBUG`, since this provides additional information about the unit in the database.

Note: `DBMS_PROFILER` treats any program unit that is compiled in `NATIVE` mode as if you do not have `CREATE` privilege, that is, you will not get any output.

Operational Notes

- [Typical Run](#)
- [Two Methods of Exception Generation](#)

Typical Run

Improving application performance is an iterative process. Each iteration involves the following steps:

1. Running the application with one or more benchmark tests with profiler data collection enabled.
2. Analyzing the profiler data and identifying performance problems.
3. Fixing the problems.

The PL/SQL profiler supports this process using the concept of a "run". A run involves running the application through benchmark tests with profiler data collection enabled. You can control the beginning and the ending of a run by calling the `START_PROFILER` and `STOP_PROFILER` functions.

A typical run involves:

- Starting profiler data collection in the run.
- Executing PL/SQL code for which profiler and code coverage data is required.
- Stopping profiler data collection, which writes the collected data for the run into database tables

Note: The collected profiler data is not automatically stored when the user disconnects. You must issue an explicit call to the `FLUSH_DATA` or the `STOP_PROFILER` function to store the data at the end of the session. Stopping data collection stores the collected data.

As the application executes, profiler data is collected in memory data structures that last for the duration of the run. You can call the `FLUSH_DATA` function at intermediate points during the run to get incremental data and to free memory for allocated profiler data structures.

Flushing the collected data involves storing collected data in database tables. The tables should already exist in the profiler user's schema. The `PROFTAB.SQL` script creates the tables and other data structures required for persistently storing the profiler data.

Note that running `PROFTAB.SQL` drops the current tables. The `PROFTAB.SQL` script is in the `RDBMS/ADMIN` directory. Some PL/SQL operations, such as the first execution of a PL/SQL unit, may involve I/O to catalog tables to load the byte code

for the PL/SQL unit being executed. Also, it may take some time executing package initialization code the first time a package procedure or function is called.

To avoid timing this overhead, "*warm up*" the database before collecting profile data. To do this, run the application once without gathering profiler data.

You can allow profiling across all users of a system, for example, to profile all users of a package, independent of who is using it. In such cases, the SYSADMIN should use a modified `PROFLOAD.SQL` script which:

- Creates the profiler tables and sequence
- Grants `SELECT/INSERT/UPDATE` on those tables and sequence to all users
- Defines public synonyms for the tables and sequence

Note: Do not alter the actual fields of the tables.

See Also: ["FLUSH_DATA Function and Procedure"](#) on page 64-9.

Two Methods of Exception Generation

Each routine in this package has two versions that allow you to determine how errors are reported.

- A function that returns success/failure as a status value and will never raise an exception
- A procedure that returns normally if it succeeds and raises an exception if it fails

In each case, the parameters of the function and procedure are identical. Only the method by which errors are reported differs. If there is an error, there is a correspondence between the error codes that the functions return, and the exceptions that the procedures raise.

To avoid redundancy, the following section only provides details about the functional form.

Exceptions

Table 64–4 *DBMS_PROFILER Exceptions*

Exception	Description
version_mismatch	Corresponds to error_version.
profiler_error	Corresponds to either "error_param" or "error_io".

A 0 return value from any function denotes successful completion; a nonzero return value denotes an error condition. The possible errors are as follows:

- 'A subprogram was called with an incorrect parameter.'
`error_param constant binary_integer := 1;`
- 'Data flush operation failed. Check whether the profiler tables have been created, are accessible, and that there is adequate space.'
`error_io constant binary_integer := 2;`
- There is a mismatch between package and database implementation. Oracle returns this error if an incorrect version of the `DBMS_PROFILER` package is installed, and if the version of the profiler package cannot work with this database version. The only recovery is to install the correct version of the package.
`error_version constant binary_integer := -1;`

Summary of DBMS_PROFILER Subprograms

Table 64–5 *DBMS_PROFILER Package Subprograms*

Subprogram	Description
FLUSH_DATA Function and Procedure on page 64-9	Flushes profiler data collected in the user's session
GET_VERSION Procedure on page 64-10	Gets the version of this API
INTERNAL_VERSION_CHECK Function on page 64-11	Verifies that this version of the DBMS_PROFILER package can work with the implementation in the database
PAUSE_PROFILER Function and Procedure on page 64-12	Pauses profiler data collection
RESUME_PROFILER Function and Procedure on page 64-13	Resumes profiler data collection
START_PROFILER Functions and Procedures on page 64-14	Starts profiler data collection in the user's session
STOP_PROFILER Function and Procedure on page 64-15	Stops profiler data collection in the user's session

FLUSH_DATA Function and Procedure

This function flushes profiler data collected in the user's session. The data is flushed to database tables, which are expected to preexist.

Note: Use the PROFTAB.SQL script to create the tables and other data structures required for persistently storing the profiler data.

Syntax

```
DBMS_PROFILER.FLUSH_DATA  
    RETURN BINARY_INTEGER;
```

```
DBMS_PROFILER.FLUSH_DATA;
```

GET_VERSION Procedure

This procedure gets the version of this API.

Syntax

```
DBMS_PROFILER.GET_VERSION (  
    major OUT BINARY_INTEGER,  
    minor OUT BINARY_INTEGER);
```

Parameters

Table 64–6 *GET_VERSION Procedure Parameters*

Parameter	Description
major	Major version of DBMS_PROFILER.
minor	Minor version of DBMS_PROFILER.

INTERNAL_VERSION_CHECK Function

This function verifies that this version of the DBMS_PROFILER package can work with the implementation in the database.

Syntax

```
DBMS_PROFILER.INTERNAL_VERSION_CHECK  
RETURN BINARY_INTEGER;
```

PAUSE_PROFILER Function and Procedure

This function pauses profiler data collection.

Syntax

```
DBMS_PROFILER.PAUSE_PROFILER  
    RETURN BINARY_INTEGER;
```

```
DBMS_PROFILER.PAUSE_PROFILER;
```

RESUME_PROFILER Function and Procedure

This function resumes profiler data collection.

Syntax

```
DBMS_PROFILER.RESUME_PROFILER  
    RETURN BINARY_INTEGER;  
  
DBMS_PROFILER.RESUME_PROFILER;
```

START_PROFILER Functions and Procedures

This function starts profiler data collection in the user's session.

There are two overloaded forms of the `START_PROFILER` function; one returns the run number of the started run, as well as the result of the call. The other does not return the run number. The first form is intended for use with GUI-based tools controlling the profiler.

Syntax

```
DBMS_PROFILER.START_PROFILER(  
    run_comment    IN VARCHAR2 := sysdate,  
    run_comment1   IN VARCHAR2 := '',  
    run_number     OUT BINARY_INTEGER)  
RETURN BINARY_INTEGER;
```

```
DBMS_PROFILER.START_PROFILER(  
    run_comment IN VARCHAR2 := sysdate,  
    run_comment1 IN VARCHAR2 := '')  
RETURN BINARY_INTEGER;
```

```
DBMS_PROFILER.START_PROFILER(  
    run_comment    IN VARCHAR2 := sysdate,  
    run_comment1   IN VARCHAR2 := '',  
    run_number     OUT BINARY_INTEGER);
```

```
DBMS_PROFILER.START_PROFILER(  
    run_comment IN VARCHAR2 := sysdate,  
    run_comment1 IN VARCHAR2 := '');
```

Parameters

Table 64–7 *START_PROFILER Function Parameters*

Parameter	Description
<code>run_comment</code>	Each profiler run can be associated with a comment. For example, the comment could provide the name and version of the benchmark test that was used to collect data.
<code>run_number</code>	Stores the number of the run so you can store and later recall the run's data.
<code>run_comment1</code>	Allows you to make interesting comments about the run.

STOP_PROFILER Function and Procedure

This function stops profiler data collection in the user's session.

This function has the side effect of flushing data collected so far in the session, and it signals the end of a run.

Syntax

```
DBMS_PROFILER.STOP_PROFILER  
    RETURN BINARY_INTEGER;  
  
DBMS_PROFILER.STOP_PROFILER;
```

DBMS_PROPAGATION_ADM

The `DBMS_PROPAGATION_ADM` package, one of a set of Streams packages, provides administrative interfaces for configuring a propagation from a source queue to a destination queue.

See Also: *Oracle Streams Concepts and Administration* and *Oracle Streams Replication Administrator's Guide* for more information about this package and propagations

This chapter contains the following topic:

- [Summary of DBMS_PROPAGATION_ADM Subprograms](#)

Summary of DBMS_PROPAGATION_ADM Subprograms

Table 65–1 *DBMS_PROPAGATION_ADM Package Subprograms*

Subprogram	Description
ALTER_PROPAGATION Procedure on page 65-3	Adds, alters, or removes a rule set for a propagation
CREATE_PROPAGATION Procedure on page 65-6	Creates a propagation and specifies the source queue, destination queue, and rule set for the propagation
DROP_PROPAGATION Procedure on page 65-11	Drops a propagation

Note: All procedures commit unless specified otherwise.

ALTER_PROPAGATION Procedure

This procedure adds, alters, or removes a rule set for a propagation.

See Also: *Oracle Streams Concepts and Administration* and [Chapter 82, "DBMS_RULE_ADM"](#) for more information about rules and rule sets

Syntax

```
DBMS_PROPAGATION_ADM.ALTER_PROPAGATION(  
    propagation_name      IN  VARCHAR2,  
    rule_set_name         IN  VARCHAR2  DEFAULT NULL,  
    remove_rule_set      IN  BOOLEAN   DEFAULT false,  
    negative_rule_set_name IN  VARCHAR2  DEFAULT NULL,  
    remove_negative_rule_set IN  BOOLEAN  DEFAULT false);
```

Parameters

Table 65–2 ALTER_PROPAGATION Procedure Parameters

Parameter	Description
<code>propagation_name</code>	The name of the propagation you are altering. You must specify an existing propagation name. Do not specify an owner.
<code>rule_set_name</code>	<p>The name of the positive rule set for the propagation. The positive rule set contains the rules that instruct the propagation to propagate events.</p> <p>If you want to use a positive rule set for the propagation, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a positive rule set in the <code>hr</code> schema named <code>prop_rules</code>, enter <code>hr.prop_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code> and the <code>remove_rule_set</code> parameter is set to <code>false</code>, then retains any existing positive rule set. If you specify <code>NULL</code> and the <code>remove_rule_set</code> parameter is set to <code>true</code>, then removes any existing positive rule set.</p>
<code>remove_rule_set</code>	<p>If <code>true</code>, then removes the positive rule set for the specified propagation. If you remove a positive rule set for a propagation, and the propagation does not have a negative rule set, then the propagation propagates all events.</p> <p>If you remove a positive rule set for a propagation, and a negative rule set exists for the propagation, then the propagation propagates all events in its queue that are not discarded by the negative rule set.</p> <p>If <code>false</code>, then retains the positive rule set for the specified propagation.</p> <p>If the <code>rule_set_name</code> parameter is non-<code>NULL</code>, then this parameter should be set to <code>false</code>.</p>

Table 65–2 (Cont.) ALTER_PROPAGATION Procedure Parameters

Parameter	Description
<code>negative_rule_set_name</code>	<p>The name of the negative rule set for the propagation. The negative rule set contains the rules that instruct the propagation to discard events.</p> <p>If you want to use a negative rule set for the propagation, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a negative rule set in the <code>hr</code> schema named <code>neg_rules</code>, enter <code>hr.neg_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code> and the <code>remove_negative_rule_set</code> parameter is set to <code>false</code>, then retains any existing negative rule set. If you specify <code>NULL</code> and the <code>remove_negative_rule_set</code> parameter is set to <code>true</code>, then removes any existing negative rule set.</p> <p>If you specify both a positive and a negative rule set for a propagation, then the negative rule set is always evaluated first.</p>
<code>remove_negative_rule_set</code>	<p>If <code>true</code>, then removes the negative rule set for the specified propagation. If you remove a negative rule set for a propagation, and the propagation does not have a positive rule set, then the propagation propagates all events.</p> <p>If you remove a negative rule set for a propagation, and a positive rule set exists for the propagation, then the propagation propagates all events in its queue that are not discarded by the positive rule set.</p> <p>If <code>false</code>, then retains the negative rule set for the specified propagation.</p> <p>If the <code>negative_rule_set_name</code> parameter is non-<code>NULL</code>, then this parameter should be set to <code>false</code>.</p>

CREATE_PROPAGATION Procedure

This procedure creates a propagation and specifies the source queue, destination queue, and any rule set for the propagation. A propagation propagates events in a local source queue to a destination queue. The destination queue may or may not be in the same database as the source queue.

This procedure also starts propagation and establishes a default schedule for its propagation job. The default schedule has the following properties:

- The start time is `SYSDATE ()`.
- The duration is `NULL`, which means infinite.
- The next time is `NULL`, which means that propagation restarts as soon as it finishes the current duration.
- The latency is five seconds, which is the wait time for a message to be propagated to a destination queue after it is enqueued into a queue with no messages requiring propagation to the same destination queue.

See Also:

- [Chapter 82, "DBMS_RULE_ADM"](#)
- *Oracle Streams Concepts and Administration*

Syntax

```
DBMS_PROPAGATION_ADM.CREATE_PROPAGATION(  
    propagation_name      IN  VARCHAR2,  
    source_queue          IN  VARCHAR2,  
    destination_queue     IN  VARCHAR2,  
    destination_dblink    IN  VARCHAR2 DEFAULT NULL,  
    rule_set_name         IN  VARCHAR2 DEFAULT NULL,  
    negative_rule_set_name IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 65–3 *CREATE_PROPAGATION Procedure Parameters*

Parameter	Description
<code>propagation_name</code>	<p>The name of the propagation you are creating. A <code>NULL</code> setting is not allowed. Do not specify an owner.</p> <p>Note: The <code>propagation_name</code> setting cannot be altered after the propagation is created.</p>
<code>source_queue</code>	<p>The name of the source queue, specified as [<code>schema_name</code>.]<code>queue_name</code>. The current database must contain the source queue.</p> <p>For example, to specify a source queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter. If the schema is not specified, then the current user is the default.</p>
<code>destination_queue</code>	<p>The name of the destination queue, specified as [<code>schema_name</code>.]<code>queue_name</code>.</p> <p>For example, to specify a destination queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter. If the schema is not specified, then the current user is the default.</p>
<code>destination_dblink</code>	<p>The name of the database link that will be used by the propagation. The database link is from the database that contains the source queue to the database that contains the destination queue.</p> <p>If <code>NULL</code>, then the source queue and destination queue must be in the same database.</p> <p>Note: Connection qualifiers are not allowed.</p>

Table 65–3 (Cont.) CREATE_PROPAGATION Procedure Parameters

Parameter	Description
<code>rule_set_name</code>	<p>The name of the positive rule set for the propagation. The positive rule set contains the rules that instruct the propagation to propagate events.</p> <p>If you want to use a positive rule set for the propagation, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a positive rule set in the <code>hr</code> schema named <code>prop_rules</code>, enter <code>hr.prop_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code>, and no negative rule set exists for the propagation, then the propagation propagates all events in its queue.</p> <p>If you specify <code>NULL</code>, and a negative rule set exists for the propagation, then the propagation propagates all events in its queue that are not discarded by the negative rule set.</p>
<code>negative_rule_set_name</code>	<p>The name of the negative rule set for the propagation. The negative rule set contains the rules that instruct the propagation to discard events.</p> <p>If you want to use a negative rule set for the propagation, then you must specify an existing rule set in the form <code>[schema_name.]rule_set_name</code>. For example, to specify a negative rule set in the <code>hr</code> schema named <code>neg_rules</code>, enter <code>hr.neg_rules</code>. If the schema is not specified, then the current user is the default.</p> <p>An error is returned if the specified rule set does not exist. You can create a rule set and add rules to it using the <code>DBMS_STREAMS_ADM</code> package or the <code>DBMS_RULE_ADM</code> package.</p> <p>If you specify <code>NULL</code>, and no positive rule set exists for the propagation, then the propagation propagates all events in its queue.</p> <p>If you specify <code>NULL</code>, and a positive rule set exists for the propagation, then the propagation propagates all events in its queue that are not discarded by the positive rule set.</p> <p>If you specify both a positive and a negative rule set for a propagation, then the negative rule set is always evaluated first.</p>

Usage Notes

If no propagation job exists for the database link specified when this procedure is run, then a propagation job is created for use by the propagation. If a propagation job is created, then the user who runs this procedure owns the propagation job. If a propagation job already exists for the specified database link, then the existing propagation job is used.

You can administer a propagation job using the following procedures in the DBMS_AQADM package:

- To alter the default schedule for a propagation job, use the ALTER_PROPAGATION_SCHEDULE procedure.
- To stop propagation, use the DISABLE_PROPAGATION_SCHEDULE procedure and specify the source queue for the `queue_name` parameter and the database link for the `destination` parameter.
- To restart propagation, use the ENABLE_PROPAGATION_SCHEDULE procedure and specify the source queue for the `queue_name` parameter and the database link for the `destination` parameter. Restarting propagation may be necessary if a propagation job is disabled automatically due to errors.

These types of changes affect all propagations that use the propagation job.

The user who owns the source queue is the user who propagates events. This user must have the necessary privileges to propagate events. These privileges include the following:

- Execute privilege on the rule set used by the propagation
- Execute privilege on all rule-based transformation functions used in the rule set
- Enqueue privilege on the destination queue if the destination queue is in the same database

If the propagation propagates events to a destination queue in a remote database, then the owner of the source queue must be able to use the propagation's database link and the user to which the database link connects at the remote database must have enqueue privilege on the destination queue.

Note:

- Currently, a single propagation job propagates all events that use a particular database link, even if the database link is used by multiple propagations to propagate events to multiple destination queues.
 - The source queue owner performs the propagation, but the propagation job is owned by the user who creates it. These two users may or may not be the same.
-
-

DROP_PROPAGATION Procedure

This procedure drops a propagation and deletes all captured and user-enqueued events for the destination queue in the source queue. This procedure also removes the schedule for propagation from the source queue to the destination queue.

Syntax

```
DBMS_PROPAGATION_ADM.DROP_PROPAGATION(
    propagation_name      IN VARCHAR2,
    drop_unused_rule_sets IN BOOLEAN DEFAULT false);
```

Parameters

Table 65–4 *DROP_PROPAGATION Procedure Parameters*

Parameter	Description
propagation_name	The name of the propagation you are dropping. You must specify an existing propagation name. Do not specify an owner.
drop_unused_rule_sets	If <code>true</code> , then drops any rule sets, positive and negative, used by the specified propagation if these rule sets are not used by any other Streams client, which includes capture processes, propagations, apply processes, and messaging clients. If this procedure drops a rule set, then this procedure also drops any rules in the rule set that are not in another rule set. If <code>false</code> , then does not drop the rule sets used by the specified propagation, and the rule sets retain their rules.

Usage Notes

When you use this procedure to drop a propagation, information about rules created for the propagation using the `DBMS_STREAMS_ADM` package is removed from the data dictionary views for Streams rules. Information about such a rule is removed even if the rule is not in either rule set for the propagation.

See Also: *Oracle Streams Concepts and Administration* for more information about Streams data dictionary views

The following are the data dictionary views for Streams rules:

- `ALL_STREAMS_GLOBAL_RULES`

- DBA_STREAMS_GLOBAL_RULES
- ALL_STREAMS_MESSAGE_RULES
- DBA_STREAMS_MESSAGE_RULES
- ALL_STREAMS_SCHEMA_RULES
- DBA_STREAMS_SCHEMA_RULES
- ALL_STREAMS_TABLE_RULES
- DBA_STREAMS_TABLE_RULES

Note: When you drop a propagation, the propagation job used by the propagation is dropped automatically, if no other propagations are using the propagation job.

DBMS_RANDOM

The `DBMS_RANDOM` package provides a built-in random number generator. `DBMS_RANDOM` is not intended for cryptography.

This chapter contains the following topics:

- [Using DBMS_RANDOM](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_RANDOM Subprograms](#)

Using DBMS_RANDOM

- [Security Model](#)
- [Operational Notes](#)

Security Model

This package should be installed as SYS. By default, the package is initialized with the current user name, current time down to the second, and the current session.

Operational Notes

- `DBMS_RANDOM.RANDOM` produces integers in $[-2^{31}, 2^{31})$.
- `DBMS_RANDOM.VALUE` produces numbers in $[0,1)$ with 38 digits of precision.

`DBMS_RANDOM` can be explicitly initialized, but does not need to be initialized before calling the random number generator. It will automatically initialize with the date, userid, and process id if no explicit initialization is performed.

If this package is seeded twice with the same seed, then accessed in the same way, it will produce the same results in both cases.

In some cases, such as when testing, you may want the sequence of random numbers to be the same on every run. In that case, you seed the generator with a constant value by calling one of the overloads of `DBMS_RANDOM.SEED`. To produce different output for every run, simply omit the call to "Seed" and the system will choose a suitable seed for you.

Summary of DBMS_RANDOM Subprograms

Table 66–1 DBMS_RANDOM Package Subprograms

Subprogram	Description
INITIALIZE Procedure on page 66-4	Initializes the package with a seed value
NORMAL Function on page 66-5	Returns random numbers in a normal distribution
RANDOM Procedure on page 66-6	Generates a random number
SEED Procedures on page 66-7	Resets the seed
STRING Function on page 66-8	Gets a random string
TERMINATE Procedure on page 66-9	Terminates package
VALUE Functions on page 66-10	This function gets a random number, greater than or equal to 0 and less than 1, with 38 digits to the right of the decimal (38-digit precision), while the overloaded function gets a random Oracle number x, where x is greater than or equal to low and less than high

Note: The [INITIALIZE Procedure](#), [RANDOM Procedure](#) and the [TERMINATE Procedure](#) are all obsolete and, while currently supported, are included in this release for legacy reasons only.

INITIALIZE Procedure

This procedure initializes the generator (but see [Usage Notes](#)).

Syntax

```
DBMS_RANDOM.INITIALIZE (  
    val IN BINARY_INTEGER);
```

Pragmas

```
PRAGMA restrict_references (initialize, WNDS)
```

Parameters

Table 66–2 INITIALIZE Procedure Parameters

Parameter	Description
val	The seed number used to generate a random number.

Usage Notes

This procedure is obsolete as it simply calls the [SEED Procedures](#) on page 66-7.

NORMAL Function

This function returns random numbers in a standard normal distribution.

Syntax

```
DBMS_RANDOM.NORMAL  
RETURN NUMBER;
```

Pragmas

```
PRAGMA restrict_references (normal, WNDS)
```

Return Values

Table 66–3 *NORMAL Procedure Parameters*

Parameter	Description
number	Returns a random number.

RANDOM Procedure

This procedure generates a random number (but see [Usage Notes](#)).

Syntax

```
DBMS_RANDOM.RANDOM  
    RETURN binary_integer;
```

Pragmas

```
PRAGMA restrict_references (random, WNDS)
```

Return Values

Table 66–4 *RANDOM Procedure Parameters*

Parameter	Description
binary_integer	Returns a random integer greater or equal to $-\text{power}(2,31)$ and less than $\text{power}(2,31)$.

Usage Notes

This procedure is obsolete and, although it is currently supported, it should not be used.

SEED Procedures

This procedure resets the seed.

Syntax

```
DBMS_RANDOM.SEED (  
    seed IN BINARY_INTEGER);
```

```
DBMS_RANDOM.SEED (  
    seed IN VARCHAR2);
```

Pragmas

```
PRAGMA restrict_references (seed, WNDS);
```

Parameters

Table 66–5 SEED Procedure Parameters

Parameter	Description
seed	Seed number or string used to generate a random number.

Usage Notes

The seed can be a string up to length 2000.

STRING Function

This function gets a random string.

Syntax

```
DBMS_RANDOM.STRING  
  opt IN CHAR,  
  len IN NUMBER)  
RETURN VARCHAR2;
```

Pragmas

```
PRAGMA restrict_references (string, WNDS)
```

Parameters

Table 66–6 *STRING Function Parameters*

Parameter	Description
opt	Specifies what the returning string looks like: <ul style="list-style-type: none">▪ 'u', 'U' - returning string in uppercase alpha characters▪ 'l', 'L' - returning string in lowercase alpha characters▪ 'a', 'A' - returning string in mixed case alpha characters▪ 'x', 'X' - returning string in uppercase alpha-numeric characters▪ 'p', 'P' - returning string in any printable characters. Otherwise the returning string is in uppercase alpha characters.
len	The length of the returning string.

Return Values

Table 66–7 *STRING Function Parameters*

Parameter	Description
VARCHAR2	Returns a VARCHAR2.

TERMINATE Procedure

When you are finished with the package, call the `TERMINATE` procedure (but see [Usage Notes](#))

Syntax

```
DBMS_RANDOM.TERMINATE
```

Usage Notes

This procedure performs no function and, although it is currently supported, it is obsolete and should not be used.

VALUE Functions

The basic function gets a random number, greater than or equal to 0 and less than 1, with 38 digits to the right of the decimal (38-digit precision). Alternatively, you can get a random Oracle number *x*, where *x* is greater than or equal to *low* and less than *high*.

Syntax

```
DBMS_RANDOM.VALUE  
  RETURN NUMBER;
```

```
DBMS_RANDOM.VALUE(  
  low IN NUMBER,  
  high IN NUMBER)  
  RETURN NUMBER;
```

Parameters

Table 66–8 VALUE Function Parameters

Parameter	Description
<i>low</i>	The lowest number in a range from which to generate a random number. The number generated may be equal to <i>low</i> .
<i>high</i>	The highest number below which to generate a random number. The number generated will be less than <i>high</i> .

Return Values

Table 66–9 VALUE Function Parameters

Parameter	Description
NUMBER	Returns an Oracle Number.

DBMS_RECTIFIER_DIFF

The DBMS_RECTIFIER_DIFF package provides an interface used to detect and resolve data inconsistencies between two replicated sites.

- [Documentation of DBMS_RECTIFIER_DIFF](#)

Documentation of DBMS_RECTIFIER_DIFF

For a complete description of this package within the context of Replication, see DBMS_RECTIFIER_DIFF in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_REDEFINITION

The `DBMS_REDEFINITION` package provides an interface to perform an online redefinition of tables.

See Also: *Oracle Database Administrator's Guide for more information.*

This chapter contains the following topics:

- [Using DBMS_REDEFINITION](#)
 - [Overview](#)
 - [Constants](#)
 - [Operational Notes](#)
- [Summary of DBMS_REDEFINITION Subprograms](#)

Using DBMS_REDEFINITION

- [Overview](#)
- [Constants](#)
- [Operational Notes](#)

Overview

To achieve online redefinition, incrementally maintainable local materialized views are used. Materialized view logs need to be defined on the master tables to support incrementally maintainable materialized views. These logs keep track of the changes to the master tables and are used by the materialized views during refresh synchronization.

Constants

The following constants are defined for this package:

- `cons_orig_params` constant PLS_INTEGER := 1;
- `cons_use_pk` constant BINARY_INTEGER := 1;
- `cons_use_rowid` constant BINARY_INTEGER := 2;
- `cons_index` constant PLS_INTEGER := 2;
- `cons_constraint` constant PLS_INTEGER := 3;
- `cons_trigger` constant PLS_INTEGER := 4;

Operational Notes

- `cons_use_pk` and `cons_use_rowid` are constants used as input to the "options_flag" parameter in both the [START_REDEF_TABLE Procedure](#) and [CAN_REDEF_TABLE Procedure](#). `cons_use_rowid` is used to indicate that the redefinition should be done using rowids while `cons_use_pk` implies that the redefinition should be done using primary keys or pseudo-primary keys (which are unique keys with all component columns having NOT NULL constraints).

- `cons_index`, `cons_trigger` and `cons_constraint` are used to specify the type of the dependent object being (un)registered in [REGISTER_DEPENDENT_OBJECT Procedure](#) and [UNREGISTER_DEPENDENT_OBJECT Procedure](#) (parameter "dep_type").

`cons_index ==>` dependent object is of type INDEX

`cons_trigger ==>` dependent object is of type TRIGGER

`cons_constraint==>` dependent object type is of type CONSTRAINT

- `cons_orig_params` as used as input to the "copy_indexes" parameter in [COPY_TABLE_DEPENDENTS Procedure](#). Using this parameter implies that the indexes on the original table be copied onto the interim table using the same storage parameters as that of the original index.

Summary of DBMS_REDEFINITION Subprograms

Table 68–1 *DBMS_REDEFINITION Package Subprograms*

Subprogram	Description
ABORT_REDEF_TABLE Procedure on page 68-5	Cleans up errors that occur during the redefinition process.
CAN_REDEF_TABLE Procedure on page 68-6	Determines if a given table can be redefined online.
COPY_TABLE_DEPENDENTS Procedure on page 68-7	Copies the dependent objects of the original table onto the interim table.
FINISH_REDEF_TABLE Procedure on page 68-9	Completes the redefinition process.
REGISTER_DEPENDENT_OBJECT Procedure on page 68-10	Registers a dependent object (index, trigger or constraint) on the table being redefined and the corresponding dependent object on the interim table.
START_REDEF_TABLE Procedure on page 68-11	Initiates the redefinition process.
SYNC_INTERIM_TABLE Procedure on page 68-13	Keeps the interim table synchronized with the original table.
UNREGISTER_DEPENDENT_OBJECT Procedure on page 68-14	Unregisters a dependent object (index, trigger or constraint) on the table being redefined and the corresponding dependent object on the interim table.

ABORT_REDEF_TABLE Procedure

This procedure cleans up errors that occur during the redefinition process. This procedure can also be used to terminate the redefinition process any time after `start_redef_table` has been called and before `finish_redef_table` is called.

Syntax

```
DBMS_REDEFINITION.ABORT_REDEF_TABLE (  
    uname          IN VARCHAR2,  
    orig_table     IN VARCHAR2,  
    int_table      IN VARCHAR2);
```

Parameters

Table 68–2 *ABORT_REDEF_TABLE Procedure Parameters*

Parameter	Description
<code>uname</code>	The schema name of the tables.
<code>orig_table</code>	The name of the table to be redefined.
<code>int_table</code>	The name of the interim table.

CAN_REDEF_TABLE Procedure

This procedure determines if a given table can be redefined online. This is the first step of the online redefinition process. If the table is not a candidate for online redefinition, an error message is raised.

Syntax

```
DBMS_REDEFINITION.CAN_REDEF_TABLE (  
    uname          IN  VARCHAR2,  
    tname          IN  VARCHAR2,  
    options_flag   IN  PLS_INTEGER := 1);
```

Parameters

Table 68–3 CAN_REDEF_TABLE Procedure Parameters

Parameter	Description
uname	The schema name of the table.
tname	The name of the table to be redefined.
options_flag	Indicates the type of redefinition method to use. If the value of this flag is <code>dbms_redefinition.cons_use_pk</code> , then the redefinition is done using primary keys or pseudo-primary keys (unique keys with all component columns having <code>NOT NULL</code> constraints). If the value of this flag is <code>dbms_redefinition.cons_use_rowid</code> , then the redefinition is done using rowids. The default method of redefinition is using primary keys.

Exceptions

If the table is not a candidate for online redefinition, an error message is raised.

COPY_TABLE_DEPENDENTS Procedure

This procedure clones the dependent objects of the table being redefined onto the interim table and registers the dependent objects. This procedure does not clone the already registered dependent objects.

This API will be used to clone the dependent objects like grants, triggers, constraints and privileges from the table being redefined onto the interim table (which represents the post-redefinition table).

All cloned referential constraints involving the interim tables will be created disabled (they will be automatically enabled after the redefinition) and all triggers on interim tables will not fire till the redefinition is completed. After the redefinition is complete, the cloned objects will be renamed to the corresponding pre-redefinition names of the objects (from which they were cloned from).

Syntax

```
DBMS_REDEFINITION.COPY_TABLE_DEPENDENTS(
  uname           IN VARCHAR2,
  orig_table      IN VARCHAR2,
  int_table       IN VARCHAR2,
  copy_indexes   IN PLS_INTEGER := 0,
  copy_triggers  IN BOOLEAN := TRUE,
  copy_constraints IN BOOLEAN := TRUE,
  copy_privileges IN BOOLEAN := TRUE,
  ignore_errors  IN BOOLEAN := FALSE,
  num_errors     OUT PLS_INTEGER);
```

Parameters

Table 68–4 *COPY_TABLE_DEPENDENTS Procedure Parameters*

Parameter	Description
uname	The schema name of the tables.
orig_table	The name of the table being redefined.
int_table	The name of the interim table.

Table 68–4 (Cont.) COPY_TABLE_DEPENDENTS Procedure Parameters

Parameter	Description
copy_indexes	A flag indicating whether to copy the indexes <ul style="list-style-type: none"> ■ 0 - don't copy any index ■ <code>dbms_redefinition.cons_orig_params</code> - copy the indexes using the physical parameters of the source indexes
copy_triggers	TRUE implies clone triggers, FALSE implies do nothing
copy_constraints	TRUE implies clone constraints, FALSE implies do nothing
copy_privileges	TRUE implies clone privileges, FALSE implies do nothing
ignore_errors	TRUE implies if an error occurs while cloning a particular dependent object, then skip that object and continue cloning other dependent objects. FALSE implies that the cloning process should stop upon encountering an error.
num_errors	The number of errors that occurred while cloning dependent objects

Usage Notes

It is the user's responsibility that the cloned dependent objects are unaffected by the redefinition. All the triggers will be cloned and it is the user's responsibility that the cloned triggers are unaffected by the redefinition.

FINISH_REDEF_TABLE Procedure

This procedure completes the redefinition process. Before this step, you can create new indexes, triggers, grants, and constraints on the interim table. The referential constraints involving the interim table must be disabled. After completing this step, the original table is redefined with the attributes and data of the interim table. The original table is locked briefly during this procedure.

Syntax

```
DBMS_REDEFINITION.FINISH_REDEF_TABLE (  
    uname          IN VARCHAR2,  
    orig_table     IN VARCHAR2,  
    int_table      IN VARCHAR2);
```

Parameters

Table 68–5 *FINISH_REDEF_TABLE Procedure Parameters*

Parameters	Description
uname	The schema name of the tables.
orig_table	The name of the table to be redefined.
int_table	The name of the interim table.

REGISTER_DEPENDENT_OBJECT Procedure

This procedure registers a dependent object (index, trigger or constraint) on the table being redefined and the corresponding dependent object on the interim table.

Syntax

```
DBMS_REDEFINITION.REGISTER_DEPENDENT_OBJECT(  
    uname           IN VARCHAR2,  
    orig_table      IN VARCHAR2,  
    int_table       IN VARCHAR2,  
    dep_type        IN PLS_INTEGER,  
    dep_owner       IN VARCHAR2,  
    dep_orig_name   IN VARCHAR2,  
    dep_int_name    IN VARCHAR2);
```

Parameters

Table 68–6 REGISTER_DEPENDENT_OBJECT Procedure Parameters

Parameters	Description
uname	The schema name of the tables.
orig_table	The name of the table to be redefined.
int_table	The name of the interim table.
dep_type	The type of the dependent object.
dep_owner	The owner of the dependent object.
dep_orig_name	The name of the original dependent object.
dep_int_name	The name of the interim dependent object.

Usage Notes

- Attempting to register an already registered object will raise an error.
- Registering a dependent object will automatically remove that object from `DBA_REDEFINITION_ERRORS` if an entry exists for that object.

START_REDEF_TABLE Procedure

After verifying that the table can be redefined online, you manually create an empty interim table (in the same schema as the table to be redefined) with the desired attributes of the post-redefinition table, and then call this procedure to initiate the redefinition.

Syntax

```
DBMS_REDEFINITION.START_REDEF_TABLE (
    uname           IN VARCHAR2,
    orig_table      IN VARCHAR2,
    int_table       IN VARCHAR2,
    col_mapping     IN VARCHAR2 := NULL,
    options_flag    IN BINARY_INTEGER := 1
    orderby_cols   IN VARCHAR2 := NULL );
```

Parameters

Table 68–7 *START_REDEF_TABLE Procedure Parameters*

Parameter	Description
uname	The schema name of the tables.
orig_table	The name of the table to be redefined.
int_table	The name of the interim table.
col_mapping	The mapping information from the columns in the original table to the columns in the interim table. (This is similar to the column list on the <code>SELECT</code> clause of a query.) If <code>NULL</code> , all the columns in the original table are selected and have the same name after redefinition.
options_flag	Indicates the type of redefinition method to use. If the value of this flag is <code>dbms_redefinition.cons_use_pk</code> , then the redefinition is done using primary keys or pseudo-primary keys (unique keys with all component columns having <code>NOT NULL</code> constraints). If the value of this flag is <code>dbms_redefinition.cons_use_rowid</code> , then the redefinition is done using rowids. The default method of redefinition is using primary keys.

Table 68–7 (Cont.) START_REDEF_TABLE Procedure Parameters

Parameter	Description
<code>orderby_cols</code>	This optional parameter accepts the list of columns (along with the optional keyword(s) ascending/descending) with which to order by the rows during the initial instantiation of the interim table (the order by is only done for the initial instantiation and not for subsequent synchronizations)

SYNC_INTERIM_TABLE Procedure

This procedure keeps the interim table synchronized with the original table. This step is useful in minimizing the amount of synchronization needed to be done by `finish_redef_table` before completing the online redefinition. This procedure can be called between long running operations (such as create index) on the interim table to sync it up with the data in the original table and speed up subsequent operations.

Syntax

```
DBMS_REDEFINITION.SYNC_INTERIM_TABLE (  
    uname          IN VARCHAR2,  
    orig_table     IN VARCHAR2,  
    int_table      IN VARCHAR2);
```

Parameters

Table 68–8 *SYNC_INTERIM_TABLE Procedure Parameters*

Parameter	Description
<code>uname</code>	The schema name of the table.
<code>orig_table</code>	The name of the table to be redefined.
<code>int_table</code>	The name of the interim table.

UNREGISTER_DEPENDENT_OBJECT Procedure

This procedure unregisters a dependent object (index, trigger or constraint) on the table being redefined and the corresponding dependent object on the interim table.

Syntax

```
DBMS_REDEFINITION.UNREGISTER_DEPENDENT_OBJECT(  
    uname           IN VARCHAR2,  
    orig_table      IN VARCHAR2,  
    int_table       IN VARCHAR2,  
    dep_type        IN PLS_INTEGER,  
    dep_owner       IN VARCHAR2,  
    dep_orig_name   IN VARCHAR2,  
    dep_int_name    IN VARCHAR2);
```

Parameters

Table 68–9 UNREGISTER_DEPENDENT_OBJECT Procedure Parameters

Parameters	Description
uname	The schema name of the tables.
orig_table	The name of the table to be redefined.
int_table	The name of the interim table.
dep_type	The type of the dependent object.
dep_owner	The owner of the dependent object.
dep_orig_name	The name of the original dependent object.
dep_int_name	The name of the interim dependent object.

DBMS_REFRESH

The `DBMS_REFRESH` package enables you to create groups of materialized views that can be refreshed together to a transactionally consistent point in time.

- [Documentation of DBMS_REFRESH](#)

Documentation of DBMS_REFRESH

For a complete description of this package within the context of Replication, see `DBMS_REFRESH` in the *Oracle Database Advanced Replication Management API Reference*.

The `DBMS_REPAIR` package contains data corruption repair procedures that enable you to detect and repair corrupt blocks in tables and indexes. You can address corruptions where possible and continue to use objects while you attempt to rebuild or repair them.

See Also: For detailed information about using the `DBMS_REPAIR` package, see *Oracle Database Administrator's Guide*.

This chapter contains the following topics:

- [Using DBMS_REPAIR](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Exceptions](#)
 - [Examples](#)
- [Summary of DBMS_REPAIR Subprograms](#)

Using DBMS_REPAIR

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Exceptions](#)
- [Examples](#)

Overview

Note: The DBMS_REPAIR package is intended for use by database administrators only. It is not intended for use by application developers.

Security Model

The package is owned by SYS. Execution privilege is not granted to other users.

Constants

The DBMS_REPAIR package defines several enumerated constants that should be used for specifying parameter values. Enumerated constants must be prefixed with the package name. For example, DBMS_REPAIR.TABLE_OBJECT.

[Table 70–1](#) lists the parameters and the enumerated constants.

Table 70–1 DBMS_REPAIR Constants

Parameter	Constant
object_type	TABLE_OBJECT, INDEX_OBJECT, CLUSTER_OBJECT
action	CREATE_ACTION, DROP_ACTION, PURGE_ACTION
table_type	REPAIR_TABLE, ORPHAN_TABLE
flags	SKIP_FLAG, NOSKIP_FLAG

Note: The default `table_name` will be `REPAIR_TABLE` when `table_type` is `REPAIR_TABLE`, and will be `ORPHAN_KEY_TABLE` when `table_type` is `ORPHAN_TABLE`.

Exceptions

Table 70–2 *DBMS_REPAIR Exceptions*

Exception	Description	Action
942	Reported by <code>DBMS_REPAIR.ADMIN_TABLES</code> during a <code>DROP_ACTION</code> when the specified table doesn't exist.	-
955	Reported by <code>DBMS_REPAIR.CREATE_ACTION</code> when the specified table already exists.	-
24120	An invalid parameter was passed to the specified <code>DBMS_REPAIR</code> procedure.	Specify a valid parameter value or use the parameter's default.
24122	An incorrect block range was specified.	Specify correct values for the <code>BLOCK_START</code> and <code>BLOCK_END</code> parameters.
24123	An attempt was made to use the specified feature, but the feature is not yet implemented.	Do not attempt to use the feature.
24124	An invalid <code>ACTION</code> parameter was specified.	Specify <code>CREATE_ACTION</code> , <code>PURGE_ACTION</code> or <code>DROP_ACTION</code> for the <code>ACTION</code> parameter.
24125	An attempt was made to fix corrupt blocks on an object that has been dropped or truncated since <code>DBMS_REPAIR.CHECK_OBJECT</code> was run.	Use <code>DBMS_REPAIR.ADMIN_TABLES</code> to purge the repair table and run <code>DBMS_REPAIR.CHECK_OBJECT</code> to determine whether there are any corrupt blocks to be fixed.
24127	<code>TABLESPACE</code> parameter specified with an <code>ACTION</code> other than <code>CREATE_ACTION</code> .	Do not specify <code>TABLESPACE</code> when performing actions other than <code>CREATE_ACTION</code> .
24128	A partition name was specified for an object that is not partitioned.	Specify a partition name only if the object is partitioned.

Table 70–2 (Cont.) DBMS_REPAIR Exceptions

Exception	Description	Action
24129	An attempt was made to pass a table name parameter without the specified prefix.	Pass a valid table name parameter.
24130	An attempt was made to specify a repair or orphan table that does not exist.	Specify a valid table name parameter.
24131	An attempt was made to specify a repair or orphan table that does not have a correct definition.	Specify a table name that refers to a properly created table.
24132	An attempt was made to specify a table name is greater than 30 characters long.	Specify a valid table name parameter.

Examples

```
/* Fix the bitmap status for all the blocks in table mytab in schema sys */  
  
EXECUTE DBMS_REPAIR.SEGMENT_FIX_STATUS('SYS', 'MYTAB');  
  
/* Mark block number 45, filenumber 1 for table mytab in sys schema as FULL.*/  
  
EXECUTE DBMS_REPAIR.SEGMENT_FIX_STATUS('SYS', 'MYTAB', TABLE_OBJECT,1, 45, 1);
```

Summary of DBMS_REPAIR Subprograms

Table 70–3 DBMS_REPAIR Package Subprograms

Subprogram	Description
ADMIN_TABLES Procedure on page 70-6	Provides administrative functions for the DBMS_REPAIR package repair and orphan key tables, including create, purge, and drop functions
CHECK_OBJECT Procedure on page 70-8	Detects and reports corruptions in a table or index
DUMP_ORPHAN_KEYS Procedure on page 70-10	Reports on index entries that point to rows in corrupt data blocks
FIX_CORRUPT_BLOCKS Procedure on page 70-12	Marks blocks software corrupt that have been previously detected as corrupt by CHECK_OBJECT
REBUILD_FREELISTS Procedure on page 70-14	Rebuilds an object's freelists
SEGMENT_FIX_STATUS Procedure on page 70-15	Fixes the corrupted state of a bitmap entry
SKIP_CORRUPT_BLOCKS Procedure on page 70-17	Sets whether to ignore blocks marked corrupt during table and index scans or to report ORA-1578 when blocks marked corrupt are encountered

ADMIN_TABLES Procedure

This procedure provides administrative functions for the `DBMS_REPAIR` package repair and orphan key tables.

Syntax

```
DBMS_REPAIR.ADMIN_TABLES (
    table_name IN    VARCHAR2,
    table_type IN    BINARY_INTEGER,
    action      IN    BINARY_INTEGER,
    tablespace IN    VARCHAR2 DEFAULT NULL);
```

Parameters

Table 70-4 ADMIN_TABLES Procedure Parameters

Parameter	Description
<code>table_name</code>	Name of the table to be processed. Defaults to <code>ORPHAN_KEY_TABLE</code> or <code>REPAIR_TABLE</code> based on the specified <code>table_type</code> . When specified, the table name must have the appropriate prefix: <code>ORPHAN_</code> or <code>REPAIR_</code> .
<code>table_type</code>	Type of table; must be either <code>ORPHAN_TABLE</code> or <code>REPAIR_TABLE</code> . See " Constants " on page 70-2.
<code>action</code>	Indicates what administrative action to perform. Must be either <code>CREATE_ACTION</code> , <code>PURGE_ACTION</code> , or <code>DROP_ACTION</code> . If the table already exists, and if <code>CREATE_ACTION</code> is specified, then an error is returned. <code>PURGE_ACTION</code> indicates to delete all rows in the table that are associated with non-existent objects. If the table does not exist, and if <code>DROP_ACTION</code> is specified, then an error is returned. When <code>CREATE_ACTION</code> and <code>DROP_ACTION</code> are specified, an associated view named <code>DBA_<table_name></code> is created and dropped respectively. The view is defined so that rows associated with non-existent objects are eliminated. Created in the <code>SYS</code> schema. See " Constants " on page 70-2.

Table 70–4 (Cont.) ADMIN_TABLES Procedure Parameters

Parameter	Description
tablespace	Indicates the tablespace to use when creating a table. By default, the SYS default tablespace is used. An error is returned if the tablespace is specified and if the action is not CREATE_ACTION.

CHECK_OBJECT Procedure

This procedure checks the specified objects and populates the repair table with information about corruptions and repair directives.

Validation consists of block checking all blocks in the object.

Syntax

```
DBMS_REPAIR.CHECK_OBJECT (
    schema_name      IN  VARCHAR2,
    object_name      IN  VARCHAR2,
    partition_name   IN  VARCHAR2      DEFAULT NULL,
    object_type      IN  BINARY_INTEGER DEFAULT TABLE_OBJECT,
    repair_table_name IN  VARCHAR2      DEFAULT 'REPAIR_TABLE',
    flags           IN  BINARY_INTEGER DEFAULT NULL,
    relative_fno    IN  BINARY_INTEGER DEFAULT NULL,
    block_start     IN  BINARY_INTEGER DEFAULT NULL,
    block_end       IN  BINARY_INTEGER DEFAULT NULL,
    corrupt_count   OUT BINARY_INTEGER);
```

Parameters

Table 70-5 CHECK_OBJECT Procedure Parameters

Parameter	Description
schema_name	Schema name of the object to be checked.
object_name	Name of the table or index to be checked.
partition_name	Partition or subpartition name to be checked. If this is a partitioned object, and if <code>partition_name</code> is not specified, then all partitions and subpartitions are checked. If this is a partitioned object, and if the specified partition contains subpartitions, then all subpartitions are checked.
object_type	Type of the object to be processed. This must be either <code>TABLE_OBJECT</code> (default) or <code>INDEX_OBJECT</code> . See "Constants" on page 70-2.
repair_table_name	Name of the repair table to be populated. The table must exist in the <code>SYS</code> schema. Use the <code>admin_tables</code> procedure to create a repair table. The default name is <code>REPAIR_TABLE</code> .

Table 70–5 (Cont.) CHECK_OBJECT Procedure Parameters

Parameter	Description
flags	Reserved for future use.
relative_fno	Relative file number: Used when specifying a block range.
block_start	First block to process if specifying a block range. May be specified only if the object is a single table, partition, or subpartition.
block_end	Last block to process if specifying a block range. May be specified only if the object is a single table, partition, or subpartition. If only one of <code>block_start</code> or <code>block_end</code> is specified, then the other defaults to the first or last block in the file respectively.
corrupt_count	Number of corruptions reported.

Usage Notes

You may optionally specify a DBA range, partition name, or subpartition name when you want to check a portion of an object.

DUMP_ORPHAN_KEYS Procedure

This procedure reports on index entries that point to rows in corrupt data blocks. For each such index entry encountered, a row is inserted into the specified orphan table.

If the repair table is specified, then any corrupt blocks associated with the base table are handled in addition to all data blocks that are marked software corrupt. Otherwise, only blocks that are marked corrupt are handled.

This information may be useful for rebuilding lost rows in the table and for diagnostic purposes.

Syntax

```
DBMS_REPAIR.DUMP_ORPHAN_KEYS (
  schema_name      IN  VARCHAR2,
  object_name      IN  VARCHAR2,
  partition_name   IN  VARCHAR2      DEFAULT NULL,
  object_type      IN  BINARY_INTEGER DEFAULT INDEX_OBJECT,
  repair_table_name IN  VARCHAR2      DEFAULT 'REPAIR_TABLE',
  orphan_table_name IN  VARCHAR2      DEFAULT 'ORPHAN_KEYS_TABLE',
  flags           IN  BINARY_INTEGER DEFAULT NULL,
  key_count       OUT BINARY_INTEGER);
```

Parameters

Table 70–6 *DUMP_ORPHAN_KEYS Procedure Parameters*

Parameter	Description
schema_name	Schema name.
object_name	Object name.
partition_name	Partition or subpartition name to be processed. If this is a partitioned object, and if <code>partition_name</code> is not specified, then all partitions and subpartitions are processed. If this is a partitioned object, and if the specified partition contains subpartitions, then all subpartitions are processed.
object_type	Type of the object to be processed. The default is <code>INDEX_OBJECT</code> . See " Constants " on page 70-2.

Table 70–6 (Cont.) DUMP_ORPHAN_KEYS Procedure Parameters

Parameter	Description
<code>repair_table_name</code>	Name of the repair table that has information regarding corrupt blocks in the base table. The specified table must exist in the <code>SYS</code> schema. The <code>admin_tables</code> procedure is used to create the table.
<code>orphan_table_name</code>	Name of the orphan key table to populate with information regarding each index entry that refers to a row in a corrupt data block. The specified table must exist in the <code>SYS</code> schema. The <code>admin_tables</code> procedure is used to create the table.
<code>flags</code>	Reserved for future use.
<code>key_count</code>	Number of index entries processed.

FIX_CORRUPT_BLOCKS Procedure

This procedure fixes the corrupt blocks in specified objects based on information in the repair table that was previously generated by the `check_object` procedure.

Prior to effecting any change to a block, the block is checked to ensure the block is still corrupt. Corrupt blocks are repaired by marking the block software corrupt. When a repair is effected, the associated row in the repair table is updated with a fix timestamp.

Syntax

```
DBMS_REPAIR.FIX_CORRUPT_BLOCKS (
  schema_name      IN  VARCHAR2,
  object_name      IN  VARCHAR2,
  partition_name   IN  VARCHAR2      DEFAULT NULL,
  object_type      IN  BINARY_INTEGER DEFAULT TABLE_OBJECT,
  repair_table_name IN  VARCHAR2      DEFAULT 'REPAIR_TABLE',
  flags           IN  BINARY_INTEGER DEFAULT NULL,
  fix_count       OUT BINARY_INTEGER);
```

Parameters

Table 70-7 *FIX_CORRUPT_BLOCKS Procedure Parameters*

Parameter	Description
<code>schema_name</code>	Schema name.
<code>object_name</code>	Name of the object with corrupt blocks to be fixed.
<code>partition_name</code>	Partition or subpartition name to be processed. If this is a partitioned object, and if <code>partition_name</code> is not specified, then all partitions and subpartitions are processed. If this is a partitioned object, and if the specified partition contains subpartitions, then all subpartitions are processed.
<code>object_type</code>	Type of the object to be processed. This must be either <code>TABLE_OBJECT</code> (default) or <code>INDEX_OBJECT</code> . See " Constants " on page 70-2.
<code>repair_table_name</code>	Name of the repair table with the repair directives. Must exist in the <code>SYS</code> schema.
<code>flags</code>	Reserved for future use.

Table 70-7 (Cont.) FIX_CORRUPT_BLOCKS Procedure Parameters

Parameter	Description
<code>fix_count</code>	Number of blocks fixed.

REBUILD_FREELISTS Procedure

This procedure rebuilds the freelists for the specified object. All free blocks are placed on the master freelist. All other freelists are zeroed.

If the object has multiple freelist groups, then the free blocks are distributed among all freelists, allocating to the different groups in round-robin fashion.

Syntax

```
DBMS_REPAIR.REBUILD_FREELISTS (  
    schema_name    IN VARCHAR2,  
    object_name    IN  VARCHAR2,  
    partition_name IN VARCHAR2 DEFAULT NULL,  
    object_type    IN BINARY_INTEGER DEFAULT TABLE_OBJECT);
```

Parameters

Table 70–8 REBUILD_FREELISTS Procedure Parameters

Parameter	Description
schema_name	Schema name.
object_name	Name of the object whose freelists are to be rebuilt.
partition_name	Partition or subpartition name whose freelists are to be rebuilt. If this is a partitioned object, and partition_name is not specified, then all partitions and subpartitions are processed. If this is a partitioned object, and the specified partition contains subpartitions, then all subpartitions are processed.
object_type	Type of the object to be processed. This must be either TABLE_OBJECT (default) or INDEX_OBJECT. See "Constants" on page 70-2.

SEGMENT_FIX_STATUS Procedure

With this procedure you can fix the corrupted state of a bitmap entry. The procedure either recalculates the state based on the current contents of the corresponding block or sets the state to a specific value.

Syntax

```
DBMS_REPAIR.SEGMENT_FIX_STATUS (
    segment_owner   IN VARCHAR2,
    segment_name    IN VARCHAR2,
    segment_type    IN BINARY_INTEGER DEFAULT TABLE_OBJECT,
    file_number     IN BINARY_INTEGER DEFAULT NULL,
    block_number    IN BINARY_INTEGER DEFAULT NULL,
    status_value    IN BINARY_INTEGER DEFAULT NULL,
    partition_name  IN VARCHAR2 DEFAULT NULL,);
```

Parameters

Table 70–9 *SEGMENT_FIX_STATUS Procedure Parameters*

Parameter	Description
schema_owner	Schema name of the segment.
segment_name	Segment name.
partition_name	Optional. Name of an individual partition. NULL for nonpartitioned objects. Default is NULL.
segment_type	Optional Type of the segment (for example, TABLE_OBJECT or INDEX-OBJECT). Default is NULL.
file_number	(optional) The tablespace-relative file number of the data block whose status has to be fixed. If omitted, all the blocks in the segment will be checked for state correctness and fixed.
block_number	(optional) The file-relative block number of the data block whose status has to be fixed. If omitted, all the blocks in the segment will be checked for state correctness and fixed.

Table 70–9 (Cont.) SEGMENT_FIX_STATUS Procedure Parameters

Parameter	Description
<code>status_value</code>	<p>(optional) The value to which the block status described by the <code>file_number</code> and <code>block_number</code> will be set. If omitted, the status will be set based on the current state of the block. This is almost always the case, but if there is a bug in the calculation algorithm, the value can be set manually. Status values:</p> <ul style="list-style-type: none">■ 1 = block is full■ 2 = block is 0-25% free■ 3 = block is 25-50% free■ 4 = block is 50-75% free■ 5 = block is 75-100% free <p>The status for bitmap blocks, segment headers, and extent map blocks cannot be altered. The status for blocks in a fixed hash area cannot be altered. For index blocks, there are only two possible states: 1 = block is full and 3 = block has free space.</p>

SKIP_CORRUPT_BLOCKS Procedure

This procedure enables or disables the skipping of corrupt blocks during index and table scans of the specified object.

When the object is a table, skip applies to the table and its indexes. When the object is a cluster, it applies to all of the tables in the cluster, and their respective indexes.

Note: When Oracle performs an index range scan on a corrupt index after DBMS_REPAIR.SKIP_CORRUPT_BLOCKS has been set for the base table, corrupt branch blocks and root blocks are not skipped. Only corrupt non-root leaf blocks are skipped.

Syntax

```
DBMS_REPAIR.SKIP_CORRUPT_BLOCKS (
  schema_name  IN VARCHAR2,
  object_name  IN VARCHAR2,
  object_type  IN BINARY_INTEGER DEFAULT TABLE_OBJECT,
  flags        IN BINARY_INTEGER DEFAULT SKIP_FLAG);
```

Parameters

Table 70–10 SKIP_CORRUPT_BLOCKS Procedure Parameters

Parameter	Description
schema_name	Schema name of the object to be processed.
object_name	Name of the object.
object_type	Type of the object to be processed. This must be either TABLE_OBJECT (default) or CLUSTER_OBJECT. See " Constants " on page 70-2.
flags	If SKIP_FLAG is specified, then it turns on the skip of software corrupt blocks for the object during index and table scans. If NOSKIP_FLAG is specified, then scans that encounter software corrupt blocks return an ORA-1578. See " Constants " on page 70-2.

DBMS_REPCAT

The DBMS_REPCAT package provides routines to administer and update the replication catalog and environment.

- [Documentation of DBMS_REPCAT](#)

Documentation of DBMS_REPCAT

For a complete description of this package within the context of Replication, see `DBMS_REPCAT` in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_REPCAT_ADMIN

The DBMS_REPCAT_ADMIN package enables you to create users with the privileges needed by the symmetric replication facility.

- [Documentation of DBMS_REPCAT_ADMIN](#)

Documentation of DBMS_REPCAT_ADMIN

For a complete description of this package within the context of Replication, see `DBMS_REPCAT_ADMIN` in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_REPCAT_INSTANTIATE

The DBMS_REPCAT_INSTANTIATE package instantiates deployment templates.

- [Documentation of DBMS_REPCAT_INSTANTIATE](#)

Documentation of DBMS_REPCAT_INSTANTIATE

For a complete description of this package within the context of Replication, see `DBMS_REPCAT_INSTANTIATE` in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_REPCAT_RGT

The DBMS_REPCAT_RGT package controls the maintenance and definition of refresh group templates.

- [Documentation of DBMS_REPCAT_RGT](#)

Documentation of DBMS_REPCAT_RGT

For a complete description of this package within the context of Replication, see `DBMS_REPCAT_RGT` in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_REPUTIL

The DBMS_REPUTIL package contains subprograms to generate shadow tables, triggers, and packages for table replication, as well as subprograms to generate wrappers for replication of standalone procedure invocations and packaged procedure invocations. This package is referenced only by the generated code.

- [Documentation of DBMS_REPUTIL](#)

Documentation of DBMS_REPUTIL

For a complete description of this package within the context of Replication, see `DBMS_REPUTIL` in the *Oracle Database Advanced Replication Management API Reference*.

DBMS_RESOURCE_MANAGER

The `DBMS_RESOURCE_MANAGER` package maintains plans, consumer groups, and plan directives. It also provides semantics so that you may group together changes to the plan schema.

See Also: For more information on using the Database Resource Manager, see *Oracle Database Administrator's Guide*.

This chapter contains the following topics:

- [Using DBMS_RESOURCE_MANAGER](#)
 - [Security Model](#)
 - [Constants](#)
 - [Examples](#)
- [Summary of DBMS_RESOURCE_MANAGER Subprograms](#)

Using DBMS_RESOURCE_MANAGER

- [Security Model](#)
- [Constants](#)
- [Examples](#)

Security Model

The invoker must have the `ADMINISTER_RESOURCE_MANAGER` system privilege to execute these procedures. The procedures to grant and revoke this privilege are in the package [DBMS_RESOURCE_MANAGER_PRIVS](#).

Constants

Table 76–1 Constants - Names and Oracle Enterprise Manager Abbreviations

Constant	Definition
<code>client_machine</code>	<code>CONSTANT VARCHAR2(30) := 'CLIENT_MACHINE';</code>
<code>client_os_user</code>	<code>CONSTANT VARCHAR2(30) := 'CLIENT_OS_USER';</code>
<code>client_program</code>	<code>CONSTANT VARCHAR2(30) := 'CLIENT_PROGRAM';</code>
<code>module_name</code>	<code>CONSTANT VARCHAR2(30) := 'MODULE_NAME';</code>
<code>module_name_action</code>	<code>CONSTANT VARCHAR2(30) := 'MODULE_NAME_ACTION';</code>
<code>oracle_user</code>	<code>CONSTANT VARCHAR2(30) := 'ORACLE_USER';</code>
<code>service_module</code>	<code>CONSTANT VARCHAR2(30) := 'SERVICE_MODULE';</code>
<code>service_module_action</code>	<code>CONSTANT VARCHAR2(30) := 'SERVICE_MODULE_ACTION';</code>
<code>service_name</code>	<code>CONSTANT VARCHAR2(30) := 'SERVICE_NAME';</code>


Examples

One of the advantages of plans is that they can refer to each other. The entries in a plan can either be consumer groups or subplans. For example, the following is also a set of valid CPU plan directives:

Table 76-2 MYDB PLAN CPU Plan Directives

Subplan/Group	CPU_Level 1
MAILDB Plan	30%
BUGDB Plan	70%

If these plan directives were in effect and there were an infinite number of runnable sessions in all consumer groups, then the MAILDB plan would be assigned 30% of the available CPU resources, while the BUGDB plan would be assigned 70% of the available CPU resources. Breaking this further down, sessions in the "Postman" consumer group would be run 12% (40% of 30%) of the time, while sessions in the "Online" consumer group would be run 56% (80% of 70%) of the time. [Figure 76-1](#) diagram depicts this scenario:

Figure 76-1 Resource Manager Scenario

Conceptually the active sessions are underneath the consumer groups. In other words, a session belongs to a resource consumer group, and this consumer group is used by a plan to determine allocation of processing resources.

A multiplan (plan with one or more subplans) definition of CPU plan directives cannot be collapsed into a single plan with one set of plan directives, because each plan is its own entity. The CPU quanta that is allotted to a plan or subplan gets used only within that plan, unless that plan contains no consumer groups with active sessions. Therefore, in this example, if the Bug Maintenance Group did not use any of its quanta, then it would get recycled within that plan, thus going back to level 1

within the BUGDB PLAN. If the multiplan definition in the preceding example got collapsed into a single plan with multiple consumer groups, then there would be no way to explicitly recycle the Bug Maintenance Group's unused quanta. It would have to be recycled globally, thus giving the mail sessions an opportunity to use it.

The resources for a database can be partitioned at a high level among multiple applications and then repartitioned within an application. If a given group within an application does not need all the resources it is assigned, then the resource is only repartitioned within the same application.

The following example uses the default plan and consumer group allocation methods:

```
BEGIN
DBMS_RESOURCE_MANAGER.CREATE_PENDING_AREA();
DBMS_RESOURCE_MANAGER.CREATE_PLAN(PLAN => 'bugdb_plan',
    COMMENT => 'Resource plan/method for bug users sessions');
DBMS_RESOURCE_MANAGER.CREATE_PLAN(PLAN => 'maildb_plan',
    COMMENT => 'Resource plan/method for mail users sessions');
DBMS_RESOURCE_MANAGER.CREATE_PLAN(PLAN => 'mydb_plan',
    COMMENT => 'Resource plan/method for bug and mail users sessions');
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(CONSUMER_GROUP => 'Bug_Online_
group',
    COMMENT => 'Resource consumer group/method for online bug users sessions');
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(CONSUMER_GROUP => 'Bug_Batch_group',
COMMENT => 'Resource consumer group/method for bug users sessions who run batch
jobs');
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(CONSUMER_GROUP => 'Bug_Maintenance_
group',
    COMMENT => 'Resource consumer group/method for users sessions who maintain
the bug db');
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(CONSUMER_GROUP => 'Mail_users_
group',
    COMMENT => 'Resource consumer group/method for mail users sessions');
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(CONSUMER_GROUP => 'Mail_Postman_
group',
    COMMENT => 'Resource consumer group/method for mail postman');
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(CONSUMER_GROUP => 'Mail_Maintenance_
group',
    COMMENT => 'Resource consumer group/method for users sessions who maintain
the mail
db');
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'bugdb_plan', GROUP_OR_
SUBPLAN => 'Bug_Online_group',
    COMMENT => 'online bug users sessions at level 1', CPU_P1 => 80, CPU_P2=> 0,
```



```

    PARALLEL_DEGREE_LIMIT_P1 => 8);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'bugdb_plan', GROUP_OR_
SUBPLAN => 'Bug_Batch_group',
    COMMENT => 'batch bug users sessions at level 1', CPU_P1 => 20, CPU_P2 => 0,
    PARALLEL_DEGREE_LIMIT_P1 => 2);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'bugdb_plan', GROUP_OR_
SUBPLAN => 'Bug_Maintenance_group',
    COMMENT => 'bug maintenance users sessions at level 2', CPU_P1 => 0, CPU_P2
=> 100, PARALLEL_DEGREE_LIMIT_P1 => 3);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'bugdb_plan', GROUP_OR_
SUBPLAN => 'OTHER_GROUPS',
    COMMENT => 'all other users sessions at level 3', CPU_P1 => 0, CPU_P2 => 0,
CPU_P3 => 100);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'maildb_plan', GROUP_OR_
SUBPLAN => 'Mail_Postman_group',
    COMMENT => 'mail postman at level 1', CPU_P1 => 40, CPU_P2 => 0,
    PARALLEL_DEGREE_LIMIT_P1 => 4);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'maildb_plan', GROUP_OR_
SUBPLAN => 'Mail_users_group',
    COMMENT => 'mail users sessions at level 2', CPU_P1 => 0, CPU_P2 => 80,
    PARALLEL_DEGREE_LIMIT_P1 => 4);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'maildb_plan', GROUP_OR_
SUBPLAN => 'Mail_Maintenance_group',
    COMMENT => 'mail maintenance users sessions at level 2', CPU_P1 => 0, CPU_P2
=> 20,
    PARALLEL_DEGREE_LIMIT_P1 => 2);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'maildb_plan', GROUP_OR_
SUBPLAN => 'OTHER_GROUPS',
    COMMENT => 'all other users sessions at level 3', CPU_P1 => 0, CPU_P2 => 0,
CPU_P3 => 100);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'mydb_plan', GROUP_OR_
SUBPLAN => 'maildb_plan',
    COMMENT=> 'all mail users sessions at level 1', CPU_P1 => 30);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(PLAN => 'mydb_plan', GROUP_OR_
SUBPLAN => 'bugdb_plan',
    COMMENT => 'all bug users sessions at level 1', CPU_P1 => 70);
DBMS_RESOURCE_MANAGER.VALIDATE_PENDING_AREA();
DBMS_RESOURCE_MANAGER.SUBMIT_PENDING_AREA();
END;

```

The preceding call to `VALIDATE_PENDING_AREA` is optional, because the validation is implicitly done in `SUBMIT_PENDING_AREA`.

```

BEGIN
DBMS_RESOURCE_MANAGER.CREATE_PENDING_AREA();

```

```
DBMS_RESOURCE_MANAGER.CREATE_PLAN(  
  PLAN => 'bugdb_plan',  
  COMMENT => 'Resource plan/method for bug users sessions');  
DBMS_RESOURCE_MANAGER.CREATE_PLAN(  
  PLAN => 'maildb_plan',  
  COMMENT => 'Resource plan/method for mail users sessions');  
  
DBMS_RESOURCE_MANAGER.CREATE_PLAN(  
  PLAN => 'mydb_plan',  
  COMMENT => 'Resource plan/method for bug and mail users sessions');  
  
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(  
  CONSUMER_GROUP => 'Bug_Online_group',  
  COMMENT => 'Resource consumer group/method for online bug users sessions');  
  
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(  
  CONSUMER_GROUP => 'Bug_Batch_group',  
  COMMENT => 'Resource consumer group/method for bug users sessions who run  
batch jobs');  
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(  
  CONSUMER_GROUP => 'Bug_Maintenance_group',  
  COMMENT => 'Resource consumer group/method for users sessions who maintain  
the bug db');  
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(  
  CONSUMER_GROUP => 'Mail_users_group',  
  COMMENT => 'Resource consumer group/method for mail users sessions');  
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(  
  CONSUMER_GROUP => 'Mail_Postman_group',  
  COMMENT => 'Resource consumer group/method for mail postman');  
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP(  
  CONSUMER_GROUP => 'Mail_Maintenance_group',  
  COMMENT => 'Resource consumer group/method for users sessions who maintain  
the mail  
db');  
  
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(  
  PLAN => 'bugdb_plan', GROUP_OR_SUBPLAN => 'Bug_Online_group',  
  COMMENT => 'online bug users sessions at level 1',  
  CPU_P1 => 80, CPU_P2=> 0,  
  PARALLEL_DEGREE_LIMIT_P1 => 8);  
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(  
  PLAN => 'bugdb_plan', GROUP_OR_SUBPLAN => 'Bug_Batch_group',  
  COMMENT => 'batch bug users sessions at level 1',  
  CPU_P1 => 20, CPU_P2 => 0,
```

```
PARALLEL_DEGREE_LIMIT_P1 => 2);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'bugdb_plan', GROUP_OR_SUBPLAN => 'Bug_Maintenance_group',
  COMMENT => 'bug maintenance users sessions at level 2',
  CPU_P1 => 0, CPU_P2 => 100,
  PARALLEL_DEGREE_LIMIT_P1 => 3);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'bugdb_plan', GROUP_OR_SUBPLAN => 'OTHER_GROUPS',
  COMMENT => 'all other users sessions at level 3',
  CPU_P1 => 0, CPU_P2 => 0, CPU_P3 => 100);

DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'maildb_plan', GROUP_OR_SUBPLAN => 'Mail_Postman_group',
  COMMENT => 'mail postman at level 1',
  CPU_P1 => 40, CPU_P2 => 0,
  PARALLEL_DEGREE_LIMIT_P1 => 4);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'maildb_plan', GROUP_OR_SUBPLAN => 'Mail_users_group',
  COMMENT => 'mail users sessions at level 2',
  CPU_P1 => 0, CPU_P2 => 80,
  PARALLEL_DEGREE_LIMIT_P1 => 4);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'maildb_plan', GROUP_OR_SUBPLAN => 'Mail_Maintenance_group',
  COMMENT => 'mail maintenance users sessions at level 2',
  CPU_P1 => 0, CPU_P2 => 20,
  PARALLEL_DEGREE_LIMIT_P1 => 2);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'maildb_plan', GROUP_OR_SUBPLAN => 'OTHER_GROUPS',
  COMMENT => 'all other users sessions at level 3',
  CPU_P1 => 0, CPU_P2 => 0, CPU_P3 => 100);

DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'mydb_plan', GROUP_OR_SUBPLAN => 'maildb_plan',
  COMMENT=> 'all mail users sessions at level 1',
  CPU_P1 => 30);
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE(
  PLAN => 'mydb_plan', GROUP_OR_SUBPLAN => 'bugdb_plan',
  COMMENT => 'all bug users sessions at level 1',
  CPU_P1 => 70);

DBMS_RESOURCE_MANAGER.VALIDATE_PENDING_AREA();
DBMS_RESOURCE_MANAGER.SUBMIT_PENDING_AREA();
END;
/
```

Summary of DBMS_RESOURCE_MANAGER Subprograms

Table 76–3 DBMS_RESOURCE_MANAGER Package Subprograms

Subprogram	Description
CLEAR_PENDING_AREA Procedure on page 76-10	Clears the work area for the resource manager
CREATE_CONSUMER_GROUP Procedure on page 76-11	Creates entries which define resource consumer groups
CREATE_PENDING_AREA Procedure on page 76-12	Creates a work area for changes to resource manager objects
CREATE_PLAN Procedure on page 76-14	Creates entries which define resource plans
CREATE_PLAN_DIRECTIVE Procedure on page 76-16	Creates resource plan directives
CREATE_SIMPLE_PLAN Procedure on page 76-19	Creates a single-level resource plan containing up to eight consumer groups in one step
DELETE_CONSUMER_GROUP Procedure on page 76-20	Deletes entries which define resource consumer groups
DELETE_PLAN Procedure on page 76-21	Deletes the specified plan as well as all the plan directives it refers to
DELETE_PLAN_CASCADE Procedure on page 76-23	Deletes the specified plan as well as all its descendants (plan directives, subplans, consumer groups)
DELETE_PLAN_DIRECTIVE Procedure on page 76-22	Deletes resource plan directives
SET_CONSUMER_GROUP_MAPPING Procedure on page 76-24	Adds, deletes, or modifies pairs for the login and run-time attribute mappings
SET_CONSUMER_GROUP_MAPPING_PRI Procedure on page 76-25	Creates the session attribute mapping priority list
SET_INITIAL_CONSUMER_GROUP Procedure on page 76-27	Assigns the initial resource consumer group for a user

Table 76-3 (Cont.) DBMS_RESOURCE_MANAGER Package Subprograms

Subprogram	Description
SUBMIT_PENDING_AREA Procedure on page 76-29	Submits pending changes for the resource manager
SWITCH_CONSUMER_GROUP_FOR_SESS Procedure on page 76-30	Changes the resource consumer group of a specific session
SWITCH_CONSUMER_GROUP_FOR_USER Procedure on page 76-31	Changes the resource consumer group for all sessions with a given user name
SWITCH_PLAN Procedure on page 76-32	Sets the current resource manager plan
UPDATE_CONSUMER_GROUP Procedure on page 76-33	Updates entries which define resource consumer groups
UPDATE_PLAN Procedure on page 76-34	Updates entries which define resource plans
UPDATE_PLAN_DIRECTIVE Procedure on page 76-35	Updates resource plan directives
VALIDATE_PENDING_AREA Procedure on page 76-38	Validates pending changes for the resource manager

CLEAR_PENDING_AREA Procedure

This procedure lets you clear pending changes for the resource manager.

Syntax

```
DBMS_RESOURCE_MANAGER.CLEAR_PENDING_AREA;
```

CREATE_CONSUMER_GROUP Procedure

This procedure lets you create entries which define resource consumer groups.

Syntax

```
DBMS_RESOURCE_MANAGER.CREATE_CONSUMER_GROUP (
  consumer_group IN VARCHAR2,
  comment        IN VARCHAR2,
  cpu_mth       IN VARCHAR2 DEFAULT 'ROUND-ROBIN');
```

Parameters

Table 76–4 CREATE_CONSUMER_GROUP Procedure Parameters

Parameter	Description
consumer_group	The name of the consumer group.
comment	The user's comment.
cpu_mth	The resource allocation method for distributing CPU among sessions in the consumer group. The default is ROUND-ROBIN, which uses a round-robin scheduler to ensure sessions are fairly executed. RUN-TO-COMPLETION specifies that sessions with the largest active time are scheduled ahead of other sessions

CREATE_PENDING_AREA Procedure

This procedure lets you make changes to resource manager objects.

All changes to the plan schema must be done within a pending area. The pending area can be thought of as a "scratch" area for plan schema changes. The administrator creates this pending area, makes changes as necessary, possibly validates these changes, and only when the submit is completed do these changes become active.

Syntax

```
DBMS_RESOURCE_MANAGER.CREATE_PENDING_AREA;
```

Usage Notes

You may, at any time while the pending area is active, view the current plan schema with your changes by selecting from the appropriate user views.

At any time, you may clear the pending area if you want to stop the current changes. You may also call the `VALIDATE` procedure to confirm whether the changes you has made are valid. You do not have to do your changes in a given order to maintain a consistent group of entries. These checks are also implicitly done when the pending area is submitted.

Note: Oracle allows "orphan" consumer groups (in other words, consumer groups that have no plan directives that refer to them). This is in anticipation that an administrator may want to create a consumer group that is not currently being used, but will be used in the future.

The following rules must be adhered to, and they are checked whenever the validate or submit procedures are executed:

- No plan schema may contain any loops.
- All plans and consumer groups referred to by plan directives must exist.
- All plans must have plan directives that refer to either plans or consumer groups.
- All percentages in any given level must not add up to greater than 100 for the emphasis resource allocation method.

- No plan may be deleted that is currently being used as a top plan by an active instance.
- For Oracle8i, the plan directive parameter, `parallel_degree_limit_pl`, may only appear in plan directives that refer to consumer groups (that is, not at subplans).
- There cannot be more than 32 plan directives coming from any given plan (that is, no plan can have more than 32 children).
- There cannot be more than 32 consumer groups in any active plan schema.
- Plans and consumer groups use the same namespace; therefore, no plan can have the same name as any consumer group.
- There must be a plan directive for `OTHER_GROUPS` somewhere in any active plan schema. This ensures that a session not covered by the currently active plan is allocated resources as specified by the `OTHER_GROUPS` directive.

If any of the preceding rules are broken when checked by the `VALIDATE` or `SUBMIT` procedures, then an informative error message is returned. You may then make changes to fix the problem(s) and reissue the `validate` or `submit` procedures.

CREATE_PLAN Procedure

This procedure creates entries which define resource plans.

Syntax

```
DBMS_RESOURCE_MANAGER.CREATE_PLAN (
    plan                IN VARCHAR2,
    comment             IN VARCHAR2,
    cpu_mth            IN VARCHAR2 DEFAULT 'EMPHASIS',
    active_sess_pool_mth IN VARCHAR2 DEFAULT 'ACTIVE_SESS_POOL_ABSOLUTE',
    parallel_degree_limit_mth IN VARCHAR2 DEFAULT
        'PARALLEL_DEGREE_LIMIT_ABSOLUTE',
    queueing_mth       IN VARCHAR2 DEFAULT 'FIFO_TIMEOUT',);
```

Parameters

Table 76–5 CREATE_PLAN Procedure Parameters

Parameter	Description
plan	The name of the resource plan.
comment	User's comment.
cpu_mth	The resource allocation method for specifying how much CPU each consumer group or sub plan gets. EMPHASIS , the default method, is for multilevel plans that use percentages to specify how CPU is distributed among consumer groups. RATIO is for single-level plans that use ratios to specify how CPU is distributed.
active_sess_pool_mth	The Active session pool resource allocation method. Limits the number of active sessions. All other sessions are inactive and wait in a queue to be activated. ACTIVE_SESS_POOL_ABSOLUTE is the default and only method available.
parallel_degree_limit_mth	The resource allocation method for specifying a limit on the degree of parallelism of any operation. PARALLEL_DEGREE_LIMIT_ABSOLUTE is the default and only method available.
queueing_mth	The Queuing resource allocation method. Controls order in which queued inactive sessions will execute. FIFO_TIMEOUT is the default and only method available.

Usage Notes

If you want to use any default resource allocation method, then you do not need not specify it when creating or updating a plan.

CREATE_PLAN_DIRECTIVE Procedure

This procedure lets you create resource plan directives.

Syntax

```
DBMS_RESOURCE_MANAGER.CREATE_PLAN_DIRECTIVE (
  plan                IN VARCHAR2,
  group_or_subplan    IN VARCHAR2,
  comment             IN VARCHAR2,
  cpu_p1              IN NUMBER   DEFAULT NULL,
  cpu_p2              IN NUMBER   DEFAULT NULL,
  cpu_p3              IN NUMBER   DEFAULT NULL,
  cpu_p4              IN NUMBER   DEFAULT NULL,
  cpu_p5              IN NUMBER   DEFAULT NULL,
  cpu_p6              IN NUMBER   DEFAULT NULL,
  cpu_p7              IN NUMBER   DEFAULT NULL,
  cpu_p8              IN NUMBER   DEFAULT NULL,
  active_sess_pool_p1 IN NUMBER   DEFAULT NULL,
  queueing_p1        IN NUMBER   DEFAULT NULL,
  parallel_degree_limit_p1 IN NUMBER DEFAULT NULL,
  switch_group       IN VARCHAR2  DEFAULT NULL,
  switch_time        IN NUMBER     DEFAULT NULL,
  switch_estimate    IN BOOLEAN   DEFAULT FALSE,
  max_est_exec_time  IN NUMBER     DEFAULT NULL,
  undo_pool          IN NUMBER     DEFAULT NULL,
  max_idle_time      IN NUMBER     DEFAULT NULL,
  max_idle_blocker_time IN NUMBER  DEFAULT NULL,
  switch_time_in_call IN NUMBER     DEFAULT NULL);
```

Parameters

Table 76–6 CREATE_PLAN_DIRECTIVE Procedure Parameters

Parameter	Description
plan	The name of the resource plan.
group_or_subplan	The name of the consumer group or subplan.
comment	Comment for the plan directive.
cpu_p1	For EMPHASIS, specifies the CPU percentage at the first level. For RATIO, specifies the weight of cpu usage. Default is NULL for all CPU parameters.

Table 76–6 (Cont.) CREATE_PLAN_DIRECTIVE Procedure Parameters

Parameter	Description
cpu_p2	For EMPHASIS, specifies the CPU percentage at the second level. Not applicable for RATIO.
cpu_p3	For EMPHASIS, specifies the CPU percentage at the third level. Not applicable for RATIO.
cpu_p4	For EMPHASIS, specifies the CPU percentage at the fourth level. Not applicable for RATIO.
cpu_p5	For EMPHASIS, specifies the CPU percentage at the fifth level. Not applicable for RATIO.
cpu_p6	For EMPHASIS, specifies the CPU percentage at the sixth level. Not applicable for RATIO.
cpu_p7	For EMPHASIS, specifies the CPU percentage at the seventh level. Not applicable for RATIO.
cpu_p8	For EMPHASIS, specifies the CPU percentage at the eighth level. Not applicable for RATIO.
active_sess_pool_p1	Specifies maximum number of concurrently active sessions for a consumer group. Default is NULL, which means unlimited.
queueing_p1	Specified time (in seconds) after which a job in the inactive session queue (waiting for execution) will time out. Default is NULL, which means unlimited.
parallel_degree_limit_p1	Specifies a limit on the degree of parallelism for any operation. Default is NULL, which means unlimited.
switch_group	Specifies consumer group to which this session is switched if other switch criteria is met. Default is NULL. If the group name is 'CANCEL_SQL', the current call will be canceled when other switch criteria are met. If the group name is 'KILL_SESSION', the session will be killed when other switch criteria are met.
switch_time	Specifies time (in seconds) that a session can execute before an action is taken. Default is NULL, which means unlimited.
switch_estimate	If TRUE, tells Oracle to use its execution time estimate to automatically switch the consumer group of an operation before beginning its execution. Default is FALSE.

Table 76–6 (Cont.) CREATE_PLAN_DIRECTIVE Procedure Parameters

Parameter	Description
<code>max_est_exec_time</code>	Specifies the maximum execution time (in seconds) allowed for a session. If the optimizer estimates that an operation will take longer than <code>MAX_EST_EXEC_TIME</code> , the operation is not started and ORA-07455 is issued. If the optimizer does not provide an estimate, this directive has no effect. Default is <code>NULL</code> , which means unlimited.
<code>undo_pool</code>	Sets a maximum in kilobytes (K) on the total amount of undo generated by a consumer group. Default is <code>NULL</code> , which means unlimited.
<code>max_idle_time</code>	Indicates the maximum session idle time. Default is <code>NULL</code> , which means unlimited.
<code>max_idle_blocker_time</code>	The maximum amount of time in seconds that a session can be idle while blocking another session's acquisition of a resource.
<code>switch_time_in_call</code>	Specifies time (in seconds) that a session can execute before an action is taken. At the end of the top call, the consumer group of the session is restored to its original consumer group. Default is <code>NULL</code> , which means unlimited. Both <code>SWITCH_TIME_IN_CALL</code> and <code>SWITCH_TIME</code> cannot be specified.

Usage Notes

- All parameters default to `NULL`. However, for the `EMPHASIS CPU` resource allocation method, this case would starve all the users.
- For `max_idle_time` and `max_idle_blocker_time`, PMON will check these limits once a minute. If it finds a session that has exceeded one of the limits, it will forcibly kill the session and clean up all its state.
- The parameter `switch_time_in_call` is mostly useful for three-tier applications where the mid-tier server is implementing session pooling. By using `switch_time_in_call`, the resource usage of one client will not affect a future client that happens to be executed on the same session.

CREATE_SIMPLE_PLAN Procedure

This procedure creates a single-level resource plan containing up to eight consumer groups in one step. You do not need to create a pending area manually before creating a resource plan, or use the `CREATE_CONSUMER_GROUP` and `CREATE_RESOURCE_PLAN_DIRECTIVES` procedures separately.

Syntax

```
DBMS_RESOURCE_MANAGER.CREATE_SIMPLE_PLAN (  
    SIMPLE_PLAN      IN  VARCHAR2  DEFAULT,  
    CONSUMER_GROUP1 IN  VARCHAR2  DEFAULT,  
    GROUP1_CPU      IN  NUMBER     DEFAULT,  
    CONSUMER_GROUP2 IN  VARCHAR2  DEFAULT,  
    GROUP2_CPU      IN  NUMBER     DEFAULT,  
    CONSUMER_GROUP3 IN  VARCHAR2  DEFAULT,  
    GROUP3_CPU      IN  NUMBER     DEFAULT,  
    CONSUMER_GROUP4 IN  VARCHAR2  DEFAULT,  
    GROUP4_CPU      IN  NUMBER     DEFAULT,  
    CONSUMER_GROUP5 IN  VARCHAR2  DEFAULT,  
    GROUP5_CPU      IN  NUMBER     DEFAULT,  
    CONSUMER_GROUP6 IN  VARCHAR2  DEFAULT,  
    GROUP6_CPU      IN  NUMBER     DEFAULT,  
    CONSUMER_GROUP7 IN  VARCHAR2  DEFAULT,  
    GROUP7_CPU      IN  NUMBER     DEFAULT,  
    CONSUMER_GROUP8 IN  VARCHAR2  DEFAULT,  
    GROUP8_CPU      IN  NUMBER     DEFAULT);
```

DELETE_CONSUMER_GROUP Procedure

This procedure lets you delete entries which define resource consumer groups.

Syntax

```
DBMS_RESOURCE_MANAGER.DELETE_CONSUMER_GROUP (  
    consumer_group IN VARCHAR2);
```

Parameters

Table 76–7 *DELETE_CONSUMER_GROUP Procedure Parameters*

Parameters	Description
consumer_group	The name of the consumer group to be deleted.

DELETE_PLAN Procedure

This procedure deletes the specified plan as well as all the plan directives to which it refers.

Syntax

```
DBMS_RESOURCE_MANAGER.DELETE_PLAN (  
    plan IN VARCHAR2);
```

Parameters

Table 76–8 *DELETE_PLAN Procedure Parameters*

Parameter	Description
plan	The name of the resource plan to delete.

DELETE_PLAN_DIRECTIVE Procedure

This procedure lets you delete resource plan directives.

Syntax

```
DBMS_RESOURCE_MANAGER.DELETE_PLAN_DIRECTIVE (  
    plan            IN VARCHAR2,  
    group_or_subplan IN VARCHAR2);
```

Parameters

Table 76–9 *DELETE_PLAN_DIRECTIVE Procedure Parameters*

Parameter	Description
plan	The name of the resource plan.
group_or_subplan	The name of the group or subplan.

DELETE_PLAN_CASCADE Procedure

This procedure deletes the specified plan and all of its descendants (plan directives, subplans, consumer groups). Mandatory objects and directives are not deleted.

Syntax

```
DBMS_RESOURCE_MANAGER.DELETE_PLAN_CASCADE (  
    plan IN VARCHAR2);
```

Parameters

Table 76–10 *DELETE_PLAN_CASCADE Procedure Parameters*

Parameters	Description
plan	The name of the plan.

Usage Notes

If `DELETE_PLAN_CASCADE` encounters any error, then it rolls back, and nothing is deleted.

SET_CONSUMER_GROUP_MAPPING Procedure

This procedure adds, deletes, or modifies entries that map sessions to consumer groups, based on the session's login and runtime attributes.

Syntax

```
DBMS_RESOURCE_MANAGER.SET_CONSUMER_GROUP_MAPPING(  
    attribute      IN VARCHAR2,  
    value          IN VARCHAR2,  
    consumer_group IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 76–11 SET_CONSUMER_GROUP_MAPPING Procedure Parameters

Parameters	Description
attribute	The mapping attribute to add/modify. It can be one of the Constants listed.
value	The attribute value to match.
consumer_group	The name of the mapped consumer group, or NULL to delete a mapping.

Usage Notes

If no mapping exists for the given attribute and value, a mapping to the given consumer group will be created. If a mapping already exists for the given attribute and value, the mapped consumer group will be updated to the one given. If the `consumer_group` argument is NULL, then any mapping from the given attribute and value will be deleted.

SET_CONSUMER_GROUP_MAPPING_PRI Procedure

Multiple attributes of a session can be used to map the session to a consumer group. This procedure prioritizes the attribute mappings.

Syntax

```
DBMS_RESOURCE_MANAGER.SET_CONSUMER_GROUP_MAPPING_PRI(
  explicit           IN NUMBER,
  oracle_user       IN NUMBER,
  service_name      IN NUMBER,
  client_os_user    IN NUMBER,
  client_program    IN NUMBER,
  client_machine    IN NUMBER,
  module_name       IN NUMBER,
  module_name_action IN NUMBER,
  service_module    IN NUMBER,
  service_module_action IN NUMBER);
```

Parameters

PRIORITY
Table 76–12 SET_CONSUMER_GROUP_MAPPING_PRI Procedure Parameters

Parameters	Description
explicit	The priority of the explicit mapping.
oracle_user	The priority of the Oracle user name mapping.
service_name	The priority of the client service name mapping.
client_os_user	The priority of the client operating system user name mapping.
client_program	The priority of the client program mapping.
client_machine	The priority of the client machine mapping.
module_name	The priority of the application module name mapping.
module_name_action	The priority of the application module name and action mapping.
service_module	The priority of the service name and application module name mapping.
module_name_action	The priority of the service name, application module name, and application action mapping.

Usage Notes

Each priority value must be a unique integer from 1 to 10. Together, they establish an ordering where 1 is the highest priority and 10 is the lowest.

SET_INITIAL_CONSUMER_GROUP Procedure

The initial consumer group of a user is the consumer group to which any session created by that user initially belongs. This procedure sets the initial resource consumer group for a user.

Syntax

```
DBMS_RESOURCE_MANAGER.SET_INITIAL_CONSUMER_GROUP (
    user          IN VARCHAR2,
    consumer_group IN VARCHAR2);
```

Parameters

Table 76–13 SET_INITIAL_CONSUMER_GROUP Procedure Parameters

Parameters	Description
user	The name of the user.
consumer_group	The user's initial consumer group.

Usage Notes

The ADMINISTER_RESOURCE_MANAGER or the ALTER USER system privilege are required to be able to execute this procedure. The user, or PUBLIC, must be directly granted switch privilege to a consumer group before it can be set to be the user's initial consumer group. Switch privilege for the initial consumer group cannot come from a role granted to that user.

Note: These semantics are similar to those for ALTER USER DEFAULT ROLE.

If the initial consumer group for a user has never been set, then the user's initial consumer group is automatically the consumer group: DEFAULT_CONSUMER_GROUP.

DEFAULT_CONSUMER_GROUP has switch privileges granted to PUBLIC; therefore, all users are automatically granted switch privilege for this consumer group. Upon deletion of a consumer group, all users having the deleted group as their initial consumer group now have DEFAULT_CONSUMER_GROUP as their initial consumer

group. All currently active sessions belonging to a deleted consumer group are switched to `DEFAULT_CONSUMER_GROUP`.

SUBMIT_PENDING_AREA Procedure

This procedure lets you submit pending changes for the resource manager. It clears the pending area after validating and committing the changes (if valid).

Note: A call to `SUBMIT_PENDING_AREA` may fail even if `VALIDATE_PENDING_AREA` succeeds. This may happen if a plan being deleted is loaded by an instance after a call to `VALIDATE_PENDING_AREA`, but before a call to `SUBMIT_PENDING_AREA`.

Syntax

```
DBMS_RESOURCE_MANAGER.SUBMIT_PENDING_AREA;
```

SWITCH_CONSUMER_GROUP_FOR_SESS Procedure

This procedure lets you change the resource consumer group of a specific session. It also changes the consumer group of any (PQ) slave sessions that are related to the top user session.

Syntax

```
DBMS_RESOURCE_MANAGER.SWITCH_CONSUMER_GROUP_FOR_SESS (  
    session_id      IN NUMBER,  
    session_serial  IN NUMBER,  
    consumer_group  IN VARCHAR2);
```

Parameters

Table 76–14 SWITCH_CONSUMER_GROUP_FOR_SESS Procedure Parameters

Parameter	Description
session_id	SID column from the view V\$SESSION.
session_serial	SERIAL# column from view V\$SESSION.
consumer_group	The name of the consumer group to switch to.

SWITCH_CONSUMER_GROUP_FOR_USER Procedure

This procedure lets you change the resource consumer group for all sessions with a given user ID. It also change the consumer group of any (PQ) slave sessions that are related to the top user session.

Syntax

```
DBMS_RESOURCE_MANAGER.SWITCH_CONSUMER_GROUP_FOR_USER (
    user          IN VARCHAR2,
    consumer_group IN VARCHAR2);
```

Parameters

Table 76–15 SWITCH_CONSUMER_GROUP_FOR_USER Procedure Parameters

Parameter	Description
user	The name of the user.
consumer_group	The name of the consumer group to switch to.

Usage Notes

The [SWITCH_CONSUMER_GROUP_FOR_SESS Procedure](#) and SWITCH_CONSUMER_GROUP_FOR_USER procedures let you to raise or lower the allocation of CPU resources of certain sessions or users. This provides a functionality similar to the `nice` command on UNIX.

These procedures cause the session to be moved into the newly specified consumer group immediately.

SWITCH_PLAN Procedure

This procedure sets the current resource manager plan.

Syntax

```
DBMS_RESOURCE_MANAGER.SWITCH_PLAN(  
    plan_name      IN      VARCHAR2,  
    sid            IN      VARCHAR2 DEFAULT '*');
```

Parameters

Table 76–16 SWITCH_PLAN_GROUP_FOR_USER Procedure Parameters

Parameter	Description
plan_name	The name of the plan to which to switch.
sid	The sid parameter is relevant only in a Real Application Clusters environment. This parameter lets you to change the plan for a particular instance. Specify the sid of the instance where you want to change the plan. Or specify '*' if you want Oracle to change the plan for all instances.

UPDATE_CONSUMER_GROUP Procedure

This procedure lets you update entries which define resource consumer groups.

Syntax

```
DBMS_RESOURCE_MANAGER.UPDATE_CONSUMER_GROUP (  
    consumer_group IN VARCHAR2,  
    new_comment    IN VARCHAR2 DEFAULT NULL,  
    new_cpu_mth    IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 76–17 *UPDATE_CONSUMER_GROUP Procedure Parameter*

Parameter	Description
consumer_group	The name of consumer group.
new_comment	New user's comment.
new_cpu_mth	The name of new method for CPU resource allocation.

Usage Notes

If the parameters to the UPDATE_CONSUMER_GROUP procedure are not specified, then they remain unchanged in the data dictionary.

UPDATE_PLAN Procedure

This procedure updates entries which define resource plans.

Syntax

```
DBMS_RESOURCE_MANAGER.UPDATE_PLAN (
    plan                               IN VARCHAR2,
    new_comment                         IN VARCHAR2 DEFAULT NULL,
    new_cpu_mth                         IN VARCHAR2 DEFAULT NULL,
    new_active_sess_pool_mth           IN VARCHAR2 DEFAULT NULL,
    new_parallel_degree_limit_mth      IN VARCHAR2 DEFAULT NULL,
    new_queueing_mth                   IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 76–18 UPDATE_PLAN Procedure Parameters

Parameter	Description
plan	The name of resource plan.
new_comment	New user's comment.
new_cpu_mth	The name of new allocation method for CPU resources.
new_active_sess_pool_mth	The name of new method for maximum active sessions.
new_parallel_degree_limit_mth	The name of new method for degree of parallelism.
new_queueing_mth	Specifies type of queuing policy to use with active session pool feature.

Usage Notes

- If the parameters to [UPDATE_PLAN Procedure](#) are not specified, then they remain unchanged in the data dictionary.
- If you want to use any default resource allocation method, then you do not need not specify it when creating or updating a plan.

UPDATE_PLAN_DIRECTIVE Procedure

This procedure lets you update resource plan directives.

Syntax

```
DBMS_RESOURCE_MANAGER.UPDATE_PLAN_DIRECTIVE (
  plan                IN VARCHAR2,
  group_or_subplan    IN VARCHAR2,
  new_comment         IN VARCHAR2 DEFAULT NULL,
  new_cpu_p1         IN NUMBER   DEFAULT NULL,
  new_cpu_p2         IN NUMBER   DEFAULT NULL,
  new_cpu_p3         IN NUMBER   DEFAULT NULL,
  new_cpu_p4         IN NUMBER   DEFAULT NULL,
  new_cpu_p5         IN NUMBER   DEFAULT NULL,
  new_cpu_p6         IN NUMBER   DEFAULT NULL,
  new_cpu_p7         IN NUMBER   DEFAULT NULL,
  new_cpu_p8         IN NUMBER   DEFAULT NULL,
  new_active_sess_pool_p1 IN NUMBER DEFAULT NULL,
  new_queueing_p1    IN NUMBER   DEFAULT NULL,
  new_parallel_degree_limit_p1 IN NUMBER DEFAULT NULL,
  new_switch_group   IN VARCHAR2 DEFAULT NULL,
  new_switch_time    IN NUMBER   DEFAULT NULL,
  new_switch_estimate IN BOOLEAN  DEFAULT FALSE,
  new_max_est_exec_time IN NUMBER  DEFAULT NULL,
  new_undo_pool      IN NUMBER   DEFAULT NULL,
  new_max_idle_time  IN NUMBER   DEFAULT NULL,
  new_max_idle_blocker_time IN NUMBER DEFAULT NULL,
  new_switch_time_in_call IN NUMBER  DEFAULT NULL);
```

Parameters

Table 76–19 UPDATE_PLAN_DIRECTIVE Procedure Parameters

Parameter	Description
plan	The name of the resource plan.
group_or_subplan	The name of the consumer group or subplan.
new_comment	Comment for the plan directive.
new_cpu_p1	For EMPHASIS, specifies the CPU percentage at the first level. For RATIO, specifies the weight of CPU usage. Default is NULL for all CPU parameters.

Table 76–19 (Cont.) UPDATE_PLAN_DIRECTIVE Procedure Parameters

Parameter	Description
<code>new_cpu_p2</code>	For EMPHASIS, specifies the CPU percentage at the second level. Not applicable for RATIO.
<code>new_cpu_p3</code>	For EMPHASIS, specifies the CPU percentage at the third level. Not applicable for RATIO.
<code>new_cpu_p4</code>	For EMPHASIS, specifies the CPU percentage at the fourth level. Not applicable for RATIO.
<code>new_cpu_p5</code>	For EMPHASIS, specifies the CPU percentage at the fifth level. Not applicable for RATIO.
<code>new_cpu_p6</code>	For EMPHASIS, specifies the CPU percentage at the sixth level. Not applicable for RATIO.
<code>new_cpu_p7</code>	For EMPHASIS, specifies the CPU percentage at the seventh level. Not applicable for RATIO.
<code>new_cpu_p8</code>	For EMPHASIS, specifies the CPU percentage at the eighth level. Not applicable for RATIO.
<code>new_active_sess_pool_p1</code>	Specifies maximum number of concurrently active sessions for a consumer group. Default is NULL, which means unlimited.
<code>new_queueing_p1</code>	Specified time (in seconds) after which a job in the inactive session queue (waiting for execution) will time out. Default is NULL, which means unlimited.
<code>new_switch_group</code>	Specifies a limit on the degree of parallelism for any operation. Default is NULL, which means unlimited.
<code>new_switch_time</code>	Specifies consumer group to which this session is switched if other switch criteria is met. Default is NULL. If the group name is 'CANCEL_SQL', the current call will be canceled when other switch criteria are met. If the group name is 'KILL_SESSION', the session will be killed when other switch criteria are met.
<code>new_switch_estimate</code>	Specifies time (in seconds) that a session can execute before an action is taken. Default is NULL, which means unlimited.
<code>new_max_est_exec_time</code>	If TRUE, tells Oracle to use its execution time estimate to automatically switch the consumer group of an operation before beginning its execution. Default is FALSE.
<code>new_undo_pool</code>	Specifies the maximum execution time (in seconds) allowed for a session. If the optimizer estimates that an operation will take longer than MAX_EST_EXEC_TIME, the operation is not started and ORA-07455 is issued. If the optimizer does not provide an estimate, this directive has no effect. Default is NULL, which means unlimited.

Table 76–19 (Cont.) UPDATE_PLAN_DIRECTIVE Procedure Parameters

Parameter	Description
<code>new_parallel_degree_limit_pl</code>	Sets a maximum in kilobytes (K) on the total amount of undo generated by a consumer group. Default is NULL, which means unlimited.
<code>new_max_idle_time</code>	Indicates the maximum session idle time. Default is NULL, which means unlimited.
<code>new_max_idle_blocker_time</code>	The maximum amount of time in seconds that a session can be idle while blocking another session's acquisition of a resource.
<code>new_switch_time_in_call</code>	Specifies time (in seconds) that a session can execute before an action is taken. At the end of the top call, the consumer group of the session is restored to its original consumer group. Default is NULL, which means unlimited. Both <code>SWITCH_TIME_IN_CALL</code> and <code>SWITCH_TIME</code> cannot be specified.

Usage Notes

- If the parameters for `UPDATE_PLAN_DIRECTIVE` are left unspecified, then they remain unchanged in the data dictionary.
- For `new_max_idle_time` and `new_max_idle_blocker_time`, PMON will check these limits once a minute. If it finds a session that has exceeded one of the limits, it will forcibly kill the session and clean up all its state.
- The parameter `new_switch_time_in_call` is mostly useful for three-tier applications where the mid-tier server is implementing session pooling. By turning on `new_switch_time_in_call`, the resource usage of one client will not affect the consumer group of a future client that happens to be executed on the same session.

VALIDATE_PENDING_AREA Procedure

This procedure lets you validate pending changes for the resource manager.

Syntax

```
DBMS_RESOURCE_MANAGER.VALIDATE_PENDING_AREA;
```

DBMS_RESOURCE_MANAGER_PRIVS

The `DBMS_RESOURCE_MANAGER_PRIVS` package maintains privileges associated with the Resource Manager.

See Also: For more information on using the Database Resource Manager, see *Oracle Database Administrator's Guide*.

This chapter contains the following topics:

- [Summary of DBMS_RESOURCE_MANAGER_PRIVS Subprograms](#)

Summary of DBMS_RESOURCE_MANAGER_PRIVS Subprograms

Table 77-1 *DBMS_RESOURCE_MANAGER_PRIVS Package Subprograms*

Subprogram	Description
GRANT_SWITCH_CONSUMER_GROUP Procedure on page 77-3	Grants the privilege to switch to resource consumer groups
GRANT_SYSTEM_PRIVILEGE Procedure on page 77-5	Performs a grant of a system privilege
REVOKE_SWITCH_CONSUMER_GROUP Procedure on page 77-6	Revokes the privilege to switch to resource consumer groups.
REVOKE_SYSTEM_PRIVILEGE Procedure on page 77-8	Performs a revoke of a system privilege

GRANT_SWITCH_CONSUMER_GROUP Procedure

This procedure grants the privilege to switch to a resource consumer group.

Syntax

```
DBMS_RESOURCE_MANAGER_PRIVS.GRANT_SWITCH_CONSUMER_GROUP (
    grantee_name   IN VARCHAR2,
    consumer_group IN VARCHAR2,
    grant_option   IN BOOLEAN);
```

Parameters

Table 77–2 GRANT_SWITCH_CONSUMER_GROUP Procedure Parameters

Parameter	Description
grantee_name	Name of the user or role to whom privilege is to be granted.
consumer_group	Name of consumer group.
grant_option	TRUE if grantee should be allowed to grant access, FALSE otherwise.

Usage Notes

If you grant permission to switch to a particular consumer group to a user, then that user can immediately switch their current consumer group to the new consumer group.

If you grant permission to switch to a particular consumer group to a role, then any users who have been granted that role and have enabled that role can immediately switch their current consumer group to the new consumer group.

If you grant permission to switch to a particular consumer group to PUBLIC, then any user can switch to that consumer group.

If the `grant_option` parameter is TRUE, then users granted switch privilege for the consumer group may also grant switch privileges for that consumer group to others.

In order to set the initial consumer group of a user, you must grant the switch privilege for that group to the user.

See Also: [Chapter 76, "DBMS_RESOURCE_MANAGER"](#)

Examples

```
BEGIN
DBMS_RESOURCE_MANAGER_PRIVS.GRANT_SWITCH_CONSUMER_GROUP (
  'scott', 'mail_maintenance_group', true);
DBMS_RESOURCE_MANAGER.CREATE_PENDING_AREA();
DBMS_RESOURCE_MANAGER.set_consumer_group_mapping(
  dbms_resource_manager.oracle_user, 'scott', 'mail_maintenance_group');
DBMS_RESOURCE_MANAGER.SUBMIT_PENDING_AREA();
END;
/
```

GRANT_SYSTEM_PRIVILEGE Procedure

This procedure performs a grant of a system privilege to a user or role.

Syntax

```
DBMS_RESOURCE_MANAGER_PRIVS.GRANT_SYSTEM_PRIVILEGE (
  grantee_name   IN VARCHAR2,
  privilege_name IN VARCHAR2 DEFAULT 'ADMINISTER_RESOURCE_MANAGER',
  admin_option   IN BOOLEAN);
```

Parameters

Table 77–3 GRANT_SYSTEM_PRIVILEGE Procedure Parameters

Parameter	Description
grantee_name	Name of the user or role to whom privilege is to be granted.
privilege_name	Name of the privilege to be granted.
admin_option	TRUE if the grant is with admin_option, FALSE otherwise.

Usage Notes

Currently, Oracle provides only one system privilege for the Resource Manager: ADMINISTER_RESOURCE_MANAGER. Database administrators have this system privilege with the admin option. The grantee and the revokee can either be a user or a role. Users that have been granted the system privilege with the admin option can also grant this privilege to others.

Examples

The following call grants this privilege to a user called scott without the admin option:

```
BEGIN
DBMS_RESOURCE_MANAGER_PRIVS.GRANT_SYSTEM_PRIVILEGE (
  grantee_name => 'scott',
  privilege_name => 'ADMINISTER_RESOURCE_MANAGER',
  admin_option => FALSE);
END;
/
```

REVOKE_SWITCH_CONSUMER_GROUP Procedure

This procedure revokes the privilege to switch to a resource consumer group.

Syntax

```
DBMS_RESOURCE_MANAGER_PRIVS.REVOKE_SWITCH_CONSUMER_GROUP (  
    revokee_name    IN VARCHAR2,  
    consumer_group IN VARCHAR2);
```

Parameters

Table 77–4 REVOKE_SWITCH_CONSUMER_GROUP Procedure Parameter

Parameter	Description
revokee_name	Name of user/role from which to revoke access.
consumer_group	Name of consumer group.

Usage Notes

If you revoke a user's switch privilege for a particular consumer group, then any subsequent attempts by that user to switch to that consumer group will fail.

If you revoke the initial consumer group from a user, then that user will automatically be part of the `DEFAULT_CONSUMER_GROUP` consumer group when logging in.

If you revoke the switch privilege for a consumer group from a role, then any users who only had switch privilege for the consumer group through that role will not be able to switch to that consumer group.

If you revoke the switch privilege for a consumer group from `PUBLIC`, then any users who could previously only use the consumer group through `PUBLIC` will not be able to switch to that consumer group.

Examples

The following example revokes the privileges to switch to `mail_maintenance_group` from Scott:

```
BEGIN  
DBMS_RESOURCE_MANAGER_PRIVS.REVOKE_SWITCH_CONSUMER_GROUP (  
    'scott', 'mail_maintenance_group');
```


END;
/

REVOKE_SYSTEM_PRIVILEGE Procedure

This procedure performs a revoke of a system privilege from a user or role.

Syntax

```
DBMS_RESOURCE_MANAGER_PRIVS.REVOKE_SYSTEM_PRIVILEGE (  
    revokee_name    IN VARCHAR2,  
    privilege_name  IN VARCHAR2 DEFAULT 'ADMINISTER_RESOURCE_MANAGER');
```

Parameters

Table 77–5 REVOKE_SYSTEM_PRIVILEGE Procedure Parameters

Parameter	Description
<code>revokee_name</code>	Name of the user or role from whom privilege is to be revoked.
<code>privilege_name</code>	Name of the privilege to be revoked.

Examples

The following call revokes the `ADMINISTER_RESOURCE_MANAGER` from user `scott`:

```
BEGIN  
DBMS_RESOURCE_MANAGER_PRIVS.REVOKE_SYSTEM_PRIVILEGE ('scott');  
END;  
/
```

DBMS_RESUMABLE

With the `DBMS_RESUMABLE` package, you can suspend large operations that run out of space or reach space limits after executing for a long time, fix the problem, and make the statement resume execution. In this way you can write applications without worrying about running into space-related errors.

This chapter contains the following topics:

- [Using DBMS_RESUMABLE](#)
 - [Operational Notes](#)
- [Summary of DBMS_RESUMABLE Subprograms](#)

Using DBMS_RESUMABLE

- [Operational Notes](#)

Operational Notes

When you suspend a statement, you should log the suspension in the alert log. You should also register a procedure to be executed when the statement is suspended. Using a view, you can monitor the progress of the statement and indicate whether the statement is currently executing or suspended.

Suspending a statement automatically results in suspending the transaction. Thus all transactional resources are held during a statement suspend and resume. When the error condition disappears, the suspended statement automatically resumes execution. A resumable space allocation can be suspended and resumed multiple times during execution.

A suspension timeout interval is associated with resumable space allocations. A resumable space allocation that is suspended for the timeout interval (the default is two hours) wakes up and returns an exception to the user. A suspended statement may be forced to throw an exception using the `DBMS_RESUMABLE.ABORT()` procedure.

Summary of DBMS_RESUMABLE Subprograms

Table 78–1 DBMS_RESUMABLE Package Subprograms

Subprogram	Description
ABORT Procedure on page 78-4	Aborts a suspended resumable space allocation
GET_SESSION_TIMEOUT Function on page 78-5	Returns the current timeout value of the resumable space allocations for a session with <code>session_id</code>
GET_TIMEOUT Function on page 78-6	Returns the current timeout value of resumable space allocations for the current session
SET_SESSION_TIMEOUT Procedure on page 78-7	Sets the timeout of resumable space allocations for a session with <code>session_id</code>
SET_TIMEOUT Procedure on page 78-8	Sets the timeout of resumable space allocations for the current session
SPACE_ERROR_INFO Function on page 78-9	Looks for space-related errors in the error stack, otherwise returning <code>FALSE</code>

ABORT Procedure

This procedure aborts a suspended resumable space allocation. The parameter `session_id` is the session ID in which the statement is executed. For a parallel DML/DDL, `session_id` is any session ID that participates in the parallel DML/DDL. This operation is guaranteed to succeed. The procedure can be called either inside or outside of the `AFTER SUSPEND` trigger.

Syntax

```
DBMS_RESUMABLE.ABORT (  
    session_id IN NUMBER);
```

Parameters

Table 78–2 ABORT Procedure Parameters

Parameter	Description
<code>session_id</code>	The session identifier of the resumable space allocation.

Usage Notes

To call an `ABORT` procedure, you must be the owner of the session with `session_id`, have `ALTER SYSTEM` privileges, or be a DBA.

GET_SESSION_TIMEOUT Function

This function returns the current timeout value of resumable space allocations for a session with `session_id`.

Syntax

```
DBMS_RESUMABLE.GET_SESSION_TIMEOUT (
    session_id IN NUMBER)
RETURN NUMBER;
```

Parameters

Table 78–3 GET_SESSION_TIMEOUT Function Parameters

Parameter	Description
<code>session_id</code>	The session identifier of the resumable space allocation.

Return Values

Table 78–4 REQUEST Function Return Values

Return Value	Description
NUMBER	The current timeout value of resumable space allocations for a session with <code>session_id</code> . The timeout is returned in seconds.

Usage Notes

If `session_id` does not exist, the `GET_SESSION_TIMEOUT` function returns -1.

GET_TIMEOUT Function

This function returns the current timeout value of resumable space allocations for the current session.

Syntax

```
DBMS_RESUMABLE.GET_TIMEOUT  
RETURN NUMBER;
```

Return Values

Table 78–5 *GET_TIMEOUT Function Return Values*

Return Value	Description
NUMBER	The current timeout value of resumable space allocations for the current session . The returned value is in seconds.

Usage Notes

If the current session is not resumable enabled, the `GET_TIMEOUT` function returns -1.

SET_SESSION_TIMEOUT Procedure

This procedure sets the timeout of resumable space allocations for a session with `session_id`. The new timeout setting applies to the session immediately. If `session_id` does not exist, no operation occurs.

Syntax

```
DBMS_RESUMABLE.SET_SESSION_TIMEOUT (  
    session_id IN NUMBER,  
    timeout    IN NUMBER);
```

Parameters

Table 78–6 *SET_SESSION_TIMEOUT Procedure Parameters*

Parameter	Description
<code>session_id</code>	The session identifier of the resumable space allocation.
<code>timeout</code>	The timeout of the resumable space allocation.

SET_TIMEOUT Procedure

This procedure sets the timeout of resumable space allocations for the current session. The new timeout setting applies to the session immediately.

Syntax

```
DBMS_RESUMABLE.SET_TIMEOUT (  
    timeout IN NUMBER);
```

Parameters

Table 78–7 *SET_TIMEOUT Procedure Parameters*

Parameter	Description
timeout	The timeout of the resumable space allocation.

SPACE_ERROR_INFO Function

This function looks for space-related errors in the error stack. If it cannot find a space related error, it will return `FALSE`. Otherwise, `TRUE` is returned and information about the particular object that causes the space error is returned.

Syntax

```
DBMS_RESUMABLE.SPACE_ERROR_INFO
  error_type      OUT VARCHAR2,
  object_type     OUT VARCHAR2,
  object_owner    OUT VARCHAR2,
  table_space_name OUT VARCHAR2,
  object_name     OUT VARCHAR2,
  sub_object_name OUT VARCHAR2)
RETURN BOOLEAN;
```

Parameters

Table 78–8 *SPACE_ERROR_INFO Function Parameters*

Parameter	Description
<code>error_type</code>	The space error type. It will be one of the following: <ul style="list-style-type: none"> ■ NO MORE SPACE ■ MAX EXTENTS REACHED ■ SPACE QUOTA EXCEEDED

Table 78–8 (Cont.) SPACE_ERROR_INFO Function Parameters

Parameter	Description
object_type	<p>The object type. It will be one of the following:</p> <ul style="list-style-type: none"> ■ TABLE ■ INDEX ■ CLUSTER ■ TABLE SPACE ■ ROLLBACK SEGMENT ■ UNDO SEGMENT ■ LOB SEGMENT ■ TEMP SEGMENT ■ INDEX PARTITION ■ TABLE PARTITION ■ LOB PARTITION ■ TABLE SUBPARTITION ■ INDEX SUBPARTITION ■ LOB SUBPARTITION <p>The type can also be NULL if it does not apply.</p>
object_owner	The owner of the object. NULL if it cannot be determined.
table_space_name	The table space where the object resides. NULL if it cannot be determined.
object_name	The name of rollback segment, temp segment, table, index, or cluster.
sub_object_name	The partition name or sub-partition name of LOB, TABLE, or INDEX. NULL if it cannot be determined.

The `DBMS_RLS` package contains the fine-grained access control administrative interface, which is used to implement Virtual Private Database (VPD). `DBMS_RLS` is available with the Enterprise Edition only.

See Also: *Oracle Database Security Guide* for usage information on `DBMS_RLS`.

This chapter contains the following topics:

- [Using DBMS_RLS](#)
 - [Overview](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_RLS Subprograms](#)

Using DBMS_RLS

Overview

The functionality to support fine-grained access control is based on dynamic predicates, where security rules are not embedded in views, but are acquired at the statement parse time, when the base table or view is referenced in a DML statement.

A dynamic predicate for a table, view, or synonym is generated by a PL/SQL function, which is associated with a security policy through a PL/SQL interface. For example:

```
DBMS_RLS.ADD_POLICY (  
    'hr', 'employees', 'emp_policy', 'hr', 'emp_sec', 'select');
```

Whenever the `EMPLOYEES` table, under the `HR` schema, is referenced in a query or subquery (`SELECT`), the server calls the `EMP_SEC` function (under the `HR` schema). This function returns a predicate specific to the current user for the `EMP_POLICY` policy. The policy function may generate the predicates based on the session environment variables available during the function call. These variables usually appear in the form of application contexts. The policy can specify any combination of security-relevant columns and of these statement types: `INDEX`, `SELECT`, `INSERT`, `UPDATE`, or `DELETE`.

The server then produces a transient view with the text:

```
SELECT * FROM hr.employees WHERE P1
```

Here, `P1` (for example, where `SAL > 10000`, or even a subquery) is the predicate returned from the `EMP_SEC` function. The server treats the `EMPLOYEES` table as a view and does the view expansion just like the ordinary view, except that the view text is taken from the transient view instead of the data dictionary.

If the predicate contains subqueries, then the owner (definer) of the policy function is used to resolve objects within the subqueries and checks security for those objects. In other words, users who have access privilege to the policy-protected objects do not need to know anything about the policy. They do not need to be granted object privileges for any underlying security policy. Furthermore, the users do not require `EXECUTE` privilege on the policy function, because the server makes the call with the function definer's right.

Note: The transient view can preserve the updatability of the parent object because it is derived from a single table or view with predicate only; that is, no JOIN, ORDER BY, GROUP BY, and so on.

DBMS_RLS also provides the interface to drop or enable security policies. For example, you can drop or enable the EMP_POLICY with the following PL/SQL statements:

```
DBMS_RLS.DROP_POLICY('hr', 'employees', 'emp_policy');
DBMS_RLS.ENABLE_POLICY('hr', 'employees', 'emp_policy', FALSE);
```

Security Model

A security check is performed when the transient view is created with a subquery. The schema owning the policy function, which generates the dynamic predicate, is the transient view's definer for security check and object lookup.

Operational Notes

The DBMS_RLS procedures cause current DML transactions, if any, to commit before the operation. However, the procedures do not cause a commit first if they are inside a DDL event trigger. With DDL transactions, the DBMS_RLS procedures are part of the DDL transaction.

For example, you may create a trigger for CREATE TABLE. Inside the trigger, you may add a column through ALTER TABLE, and you can add a policy through DBMS_RLS. All these operations are in the same transaction as CREATE TABLE, even though each one is a DDL statement. The CREATE TABLE succeeds only if the trigger is completed successfully.

Views of current cursors and corresponding predicates are available from v\$vpd_policies.

A synonym can reference only a view or a table.

Summary of DBMS_RLS Subprograms

Table 79–1 DBMS_RLS Subprograms Package Subprograms

Subprogram	Description
ADD_POLICY Procedure on page 79-5	Adds a fine-grained access control policy to a table, view, or synonym
DROP_POLICY Procedure on page 79-10	Drops a fine-grained access control policy from a table, view, or synonym
REFRESH_POLICY Procedure on page 79-11	Causes all the cached statements associated with the policy to be reparsed
ENABLE_POLICY Procedure on page 79-12	Enables or disables a fine-grained access control policy
CREATE_POLICY_GROUP Procedure on page 79-13	Creates a policy group
ADD_GROUPED_POLICY Procedure on page 79-14	Adds a policy associated with a policy group
ADD_POLICY_CONTEXT Procedure on page 79-17	Adds the context for the active application
DELETE_POLICY_GROUP Procedure on page 79-19	Deletes a policy group
DROP_GROUPED_POLICY Procedure on page 79-20	Drops a policy associated with a policy group
DROP_POLICY_CONTEXT Procedure on page 79-21	Drops a driving context from the object so that it will have one less driving context
ENABLE_GROUPED_POLICY Procedure on page 79-22	Enables or disables a row-level group security policy
DISABLE_GROUPED_POLICY Procedure on page 79-23	Disables a row-level group security policy
REFRESH_GROUPED_POLICY Procedure on page 79-24	Reparses the SQL statements associated with a refreshed policy

ADD_POLICY Procedure

This procedure adds a fine-grained access control policy to a table, view, or synonym.

The procedure causes the current transaction, if any, to commit before the operation is carried out. However, this does not cause a commit first if it is inside a DDL event trigger.

See Also: [Operational Notes](#) on page 79-3

A COMMIT is also performed at the end of the operation.

Syntax

```
DBMS_RLS.ADD_POLICY (
    object_schema          IN VARCHAR2 NULL,
    object_name           IN VARCHAR2,
    policy_name           IN VARCHAR2,
    function_schema       IN VARCHAR2 NULL,
    policy_function       IN VARCHAR2,
    statement_types       IN VARCHAR2 NULL,
    update_check          IN BOOLEAN FALSE,
    enable                 IN BOOLEAN TRUE,
    static_policy         IN BOOLEAN FALSE,
    policy_type           IN BINARY_INTEGER NULL,
    long_predicate        IN BOOLEAN FALSE,
    sec_relevant_cols     IN VARCHAR2,
    sec_relevant_cols_opt IN BINARY_INTEGER NULL);
```

Parameters

Table 79–2 ADD_POLICY Procedure Parameters

Parameter	Description
object_schema	Schema containing the table, view, or synonym (current default schema, if NULL).
object_name	Name of table, view, or synonym to which the policy is added.
policy_name	Name of policy to be added. It must be unique for the same table or view.
function_schema	Schema of the policy function (current default schema, if NULL).

Table 79-2 (Cont.) ADD_POLICY Procedure Parameters (Cont.)

Parameter	Description
<code>policy_function</code>	Name of a function which generates a predicate for the policy. If the function is defined within a package, then the name of the package must be present.
<code>statement_types</code>	Statement types to which the policy applies. It can be any combination of <code>INDEX</code> , <code>SELECT</code> , <code>INSERT</code> , <code>UPDATE</code> , or <code>DELETE</code> . The default is to apply to all of these types except <code>INDEX</code> .
<code>update_check</code>	Optional argument for <code>INSERT</code> or <code>UPDATE</code> statement types. The default is <code>FALSE</code> . Setting <code>update_check</code> to <code>TRUE</code> causes the server to also check the policy against the value after insert or update.
<code>enable</code>	Indicates if the policy is enabled when it is added. The default is <code>TRUE</code> .
<code>static_policy</code>	The default is <code>FALSE</code> . If it is set to <code>TRUE</code> , the server assumes that the policy function for the static policy produces the same predicate string for anyone accessing the object, except for <code>SYS</code> or the privilege user who has the <code>EXEMPT ACCESS POLICY</code> privilege.
<code>policy_type</code>	Default is <code>NULL</code> , which means <code>policy_type</code> is decided by the value of <code>static_policy</code> . The available policy types are listed in Table 79-3 . Specifying any of these policy types overrides the value of <code>static_policy</code> .
<code>long_predicate</code>	Default is <code>FALSE</code> , which means the policy function can return a predicate with a length of up to 4000 bytes. <code>TRUE</code> means the predicate text string length can be up to 32K bytes. Policies existing prior to the availability of this parameter retain a 32K limit.
<code>sec_relevant_cols</code>	Enables column-level Virtual Private Database (VPD), which enforces security policies when a column containing sensitive information is referenced in a query. Applies to tables and views, but not to synonyms. Specify a list of comma- or space-separated valid column names of the policy-protected object. The policy is enforced only if a specified column is referenced (or, for an abstract datatype column, its attributes are referenced) in the user SQL statement or its underlying view definition. Default is all the user-defined columns for the object.
<code>sec_relevant_cols_opt</code>	Use with <code>sec_relevant_cols</code> to display all rows for column-level VPD filtered queries (<code>SELECT</code> only), but where sensitive columns appear as <code>NULL</code> . Default is set to <code>NULL</code> , which allows the filtering defined with <code>sec_relevant_cols</code> to take effect. Set to <code>dbms_rls.ALL_ROWS</code> to display all rows, but with sensitive column values, which are filtered by <code>sec_relevant_cols</code> , displayed as <code>NULL</code> . See " Usage Notes " on page 79-7 for restrictions and additional information about this option.

Table 79-3 DBMS_RLS.ADD_POLICY Policy Types

Policy Type	Description
STATIC	Predicate is assumed to be the same regardless of the runtime environment. Static policy functions are executed once and then cached in SGA. Statements accessing the same object do not reexecute the policy function. However, each execution of the same cursor could produce a different row set even for the same predicate because the predicate may filter the data differently based on attributes such as SYS_CONTEXT or SYSDATE. Applies to only one object.
SHARED_STATIC	Same as STATIC except that the server first looks for a cached predicate generated by the same policy function of the same policy type. Shared across multiple objects.
CONTEXT_SENSITIVE	Server re-evaluates the policy function at statement execution time if it detects context changes since the last use of the cursor. For session pooling where multiple clients share a database session, the middle tier must reset context during client switches. Note that the server does not cache the value returned by the function for this policy type; it always executes the policy function on statement parsing. Applies to only one object.
SHARED_CONTEXT_SENSITIVE	Same as CONTEXT_SENSITIVE except that the server first looks for a cached predicate generated by the same policy function of the same policy type within the same database session. If the predicate is found in the session memory, the policy function is not reexecuted and the cached value is valid until session private application context changes occur. Shared across multiple objects.
DYNAMIC	The default policy type. Server assumes the predicate may be affected by any system or session environment at any time, and so always reexecutes the policy function on each statement parsing or execution. Applies to only one object.

Usage Notes

- SYS is free of any security policy.
- The policy functions which generate dynamic predicates are called by the server. Following is the interface for the function:

```
FUNCTION policy_function (object_schema IN VARCHAR2, object_name VARCHAR2)
RETURN VARCHAR2
--- object_schema is the schema owning the table of view.
--- object_name is the name of table, view, or synonym to which the policy
applies.
```

- The policy functions must have the purity level of `WNDS` (write no database state).

See Also: The *Oracle Database Application Developer's Guide - Fundamentals* has more details about the `RESTRICT_REFERENCES` pragma.

- Dynamic predicates generated out of different policies for the same object have the combined effect of a conjunction (`ANDed`) of all the predicates.
- The security check and object lookup are performed against the owner of the policy function for objects in the subqueries of the dynamic predicates.
- If the function returns a zero length predicate, then it is interpreted as no restriction being applied to the current user for the policy.
- When a table alias is required (for example, parent object is a type table) in the predicate, the name of the table or view itself must be used as the name of the alias. The server constructs the transient view as something like

```
"select c1, c2, ... from tab tab where <predicate>"
```
- Validity of the function is checked at runtime for ease of installation and other dependency issues during import and export.
- Column-level VPD column masking behavior (specified with `sec_relevant_cols_opt => dbms_rls.ALL_ROWS`) is fundamentally different from all other VPD policies, which return only a subset of rows. Instead the column masking behavior returns all rows specified by the user's query, but the sensitive column values display as `NULL`. The restrictions for this option are as follows:
 - Only applies to `SELECT` statements
 - Unlike regular VPD predicates, the masking condition that is generated by the policy function must be a simple boolean expression.
 - If your application performs calculations, or does not expect `NULL` values, then you should use the default behavior of column-level VPD, which is specified with the `sec_relevant_cols` parameter.
 - If you use `UPDATE AS SELECT` with this option, then only the values in the columns you are allowed to see will be updated.
 - This option may prevent some rows from displaying. For example:

```
select * from employees
```

```
where salary = 10
```

This query may not return rows if the `salary` column returns a `NULL` value because the column masking option has been set.

Examples

As the first of two examples, the following creates a policy that applies to the `hr.employee` table. This is a column-level VPD policy that will be enforced only if a `SELECT` or an `INDEX` statement refers to the `salary`, `birthdate`, or `SSN` columns of the table explicitly, or implicitly through a view. It is also a `CONTEXT_SENSITIVE` policy, so the server will invoke the policy function `hr.hrfun` at parse time. During execution, it will only invoke the function if there has been any session private context change since the last use of the statement cursor. The predicate generated by the policy function must not exceed 4000 bytes, the default length limit, since the `long_predicate` parameter is omitted from the call.

```
BEGIN
dbms_ols.add_policy(object_schema => 'hr',
                    object_name => 'employee',
                    policy_name => 'hr_policy',
                    function_schema => 'hr',
                    policy_function => 'hrfun',
                    statement_types => 'select,index',
                    policy_type => dbms_ols.CONTEXT_SENSITIVE,
                    sec_relevant_cols=> 'salary,birthdate,ssn');
END;
/
```

As the second example, the following command creates another policy that applies to the same object for hosting, so users can access only data based on their subscriber ID. Since it is defined as a `SHARED_STATIC` policy type, the server will first try to find the predicate in the SGA cache. The server will only invoke the policy function, `subfun`, if that search fails.

```
BEGIN
dbms_ols.add_policy(object_schema => 'hr',
                    object_name => 'employee',
                    policy_name => 'hosting_policy',
                    function_schema => 'hr',
                    policy_function => 'subfun',
                    policy_type => dbms_ols.SHARED_STATIC);
END;
/
```

DROP_POLICY Procedure

This procedure drops a fine-grained access control policy from a table, view, or synonym.

The procedure causes the current transaction, if any, to commit before the operation is carried out. However, this does not cause a commit first if it is inside a DDL event trigger.

See Also: [Operational Notes](#) on page 79-3

A COMMIT is also performed at the end of the operation.

Syntax

```
DBMS_RLS.DROP_POLICY (  
    object_schema IN VARCHAR2 NULL,  
    object_name   IN VARCHAR2,  
    policy_name   IN VARCHAR2);
```

Parameters

Table 79-4 DROP_POLICY Procedure Parameters

Parameter	Description
object_schema	Schema containing the table, view or synonym (current default schema if NULL).
object_name	Name of table, view, or synonym.
policy_name	Name of policy to be dropped from table, view, or synonym.

REFRESH_POLICY Procedure

This procedure causes all the cached statements associated with the policy to be reparsed. This guarantees that the latest change to this policy will have immediate effect after the procedure is executed.

The procedure causes the current transaction, if any, to commit before the operation is carried out. However, this does not cause a commit first if it is inside a DDL event trigger.

See Also: [Operational Notes](#) on page 79-3

A COMMIT is also performed at the end of the operation.

Syntax

```
DBMS_RLS.REFRESH_POLICY (
    object_schema IN VARCHAR2 NULL,
    object_name   IN VARCHAR2 NULL,
    policy_name   IN VARCHAR2 NULL);
```

Parameters

Table 79-5 REFRESH_POLICY Procedure Parameters

Parameter	Description
object_schema	Schema containing the table, view, or synonym.
object_name	Name of table, view, or synonym with which the policy is associated.
policy_name	Name of policy to be refreshed.

Usage Notes

The procedure returns an error if it tries to refresh a disabled policy.

ENABLE_POLICY Procedure

This procedure enables or disables a fine-grained access control policy. A policy is enabled when it is created.

The procedure causes the current transaction, if any, to commit before the operation is carried out. However, this does not cause a commit first if it is inside a DDL event trigger.

See Also: [Operational Notes](#) on page 79-3

A COMMIT is also performed at the end of the operation.

Syntax

```
DBMS_RLS.ENABLE_POLICY (  
    object_schema IN VARCHAR2 NULL,  
    object_name   IN VARCHAR2,  
    policy_name   IN VARCHAR2,  
    enable        IN BOOLEAN);
```

Parameters

Table 79–6 *ENABLE_POLICY Procedure Parameters*

Parameter	Description
object_schema	Schema containing table, view, or synonym (current default schema if NULL).
object_name	Name of table, view, or synonym with which the policy is associated.
policy_name	Name of policy to be enabled or disabled.
enable	TRUE to enable the policy, FALSE to disable the policy.

CREATE_POLICY_GROUP Procedure

This procedure creates a policy group.

Syntax

```
DBMS_RLS.CREATE_POLICY_GROUP (  
    object_schema    VARCHAR2,  
    object_name      VARCHAR2,  
    policy_group     VARCHAR2);
```

Parameters

Table 79–7 CREATE_POLICY_GROUP Procedure Parameters

Parameter	Description
object_schema	Schema containing the table, view, or synonym.
object_name	Name of the table, view, or synonym to which the policy is added.
policy_group	Name of the policy group that the policy belongs to.

Usage Notes

The group must be unique for each table or view.

ADD_GROUPED_POLICY Procedure

This procedure adds a policy associated with a policy group.

Syntax

```
DBMS_RLS.ADD_GROUPED_POLICY(
    object_schema  VARCHAR2,
    object_name    VARCHAR2,
    policy_group   VARCHAR2,
    policy_name    VARCHAR2,
    function_schema VARCHAR2,
    policy_function VARCHAR2,
    statement_types VARCHAR2,
    update_check   BOOLEAN,
    enabled        BOOLEAN,
    static_policy  IN BOOLEAN FALSE,
    policy_type    IN BINARY_INTEGER NULL,
    long_predicate IN BOOLEAN FALSE,
    sec_relevant_cols IN VARCHAR2);
```

Parameters

Table 79–8 ADD_GROUPED_POLICY Procedure Parameters

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym to which the policy is added.
policy_group	The name of the policy group that the policy belongs to.
policy_name	The name of the policy; must be unique for the same table or view.
function_schema	The schema owning the policy function.
policy_function	The name of the function that generates a predicate for the policy. If the function is defined within a package, the name of the package must be present.
statement_types	Statement types to which the policy applies. It can be any combination of INDEX, SELECT, INSERT, UPDATE, or DELETE. The default is to apply to all of these types except INDEX.

Table 79–8 (Cont.) ADD_GROUPED_POLICY Procedure Parameters

Parameter	Description
update_check	For INSERT and UPDATE statements only, setting update_check to TRUE causes the server to check the policy against the value after INSERT or UPDATE.
enable	Indicates if the policy is enable when it is added. The default is TRUE.
static_policy	The default is FALSE. If it is set to TRUE, the server assumes that the policy function for the static policy produces the same predicate string for anyone accessing the object, except for SYS or the privilege user who has the EXEMPT ACCESS POLICY privilege.
policy_type	Default is NULL, which means policy_type is decided by the value of static_policy. The available policy types are listed in Table 79–3 . Specifying any of these policy types overrides the value of static_policy.
long_predicate	Default is FALSE, which means the policy function can return a predicate with a length of up to 4000 bytes. TRUE means the predicate text string length can be up to 32K bytes. Policies existing prior to the availability of this parameter retain a 32K limit.
sec_relevant_cols	Enables column-level Virtual Private Database (VPD), which enforces security policies when a column containing sensitive information is referenced in a query. Applies to tables and views, but not to synonyms. Specify a list of comma- or space-separated valid column names of the policy-protected object. The policy is enforced only if a specified column is referenced (or, for an abstract datatype column, its attributes are referenced) in the user SQL statement or its underlying view definition. Default is all the user-defined columns for the object.
sec_relevant_cols_opt	Use with sec_relevant_cols to display all rows for column-level VPD filtered queries (SELECT only), but where sensitive columns appear as NULL. Default is set to NULL, which allows the filtering defined with sec_relevant_cols to take effect. Set to dbms_ols.ALL_ROWS to display all rows, but with sensitive column values, which are filtered by sec_relevant_cols, displayed as NULL. See " Usage Notes " on page 79-7 for restrictions and additional information about this option.

Usage Notes

- This procedure adds a policy to the specified table, view, or synonym and associates the policy with the specified policy group.

- The policy group must have been created by using the [CREATE_POLICY_GROUP Procedure](#) on page 79-13.
- The policy name must be unique within a policy group for a specific object.
- Policies from the default policy group, `SYS_DEFAULT`, are always executed regardless of the active policy group; however, fine-grained access control policies do not apply to users with `EXEMPT ACCESS POLICY` system privilege.

ADD_POLICY_CONTEXT Procedure

This procedure adds the context for the active application.

Syntax

```
DBMS_RLS.ADD_POLICY_CONTEXT (
    object_schema  VARCHAR2,
    object_name    VARCHAR2,
    namespace     VARCHAR2,
    attribute      VARCHAR2);
```

Parameters

Table 79–9 ADD_POLICY_CONTEXT Procedure Parameters

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym to which the policy is added.
namespace	The namespace of the driving context
attribute	The attribute of the driving context.

Usage Notes

Note the following:

- This procedure indicates the application context that drives the enforcement of policies; this is the context that determines which application is running.
- The driving context can be session or global.
- At execution time, the server retrieves the name of the active policy group from the value of this context.
- There must be at least one driving context defined for each object that has fine-grained access control policies; otherwise, all policies for the object will be executed.
- Adding multiple context to the same object will cause policies from multiple policy groups to be enforced.
- If the driving context is `NULL`, policies from all policy groups are used.

- If the driving context is a policy group with policies, all enabled policies from that policy group will be applied, along with all policies from the `SYS_DEFAULT` policy group.
- To add a policy to table `hr.employees` in group `access_control_group`, the following command is issued:

```
DBMS_RLS.ADD_GROUPED_POLICY('hr','employees','access_control_
group','policy1','SYS','HR.ACCESS');
```

DELETE_POLICY_GROUP Procedure

This procedure deletes a policy group.

Syntax

```
DBMS_RLS.DELETE_POLICY_GROUP (  
    object_schema  VARCHAR2,  
    object_name    VARCHAR2,  
    policy_group   VARCHAR2);
```

Parameters

Table 79–10 *DELETE_POLICY_GROUP Procedure Parameters*

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym to which the policy is added.
policy_group	The name of the policy group that the policy belongs to.

Usage Notes

Note the following:

- This procedure deletes a policy group for the specified table, view, or synonym.
- No policy can be in the policy group.

DROP_GROUPED_POLICY Procedure

This procedure drops a policy associated with a policy group.

Syntax

```
DBMS_RLS.DROP_GROUPED_POLICY (  
    object_schema  VARCHAR2,  
    object_name    VARCHAR2,  
    policy_group   VARCHAR2,  
    policy_name    VARCHAR2);
```

Parameters

Table 79-11 *DROP_GROUPED_POLICY Procedure Parameters*

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym to which the policy is dropped.
policy_group	The name of the policy group that the policy belongs to.
policy_name	The name of the policy.

DROP_POLICY_CONTEXT Procedure

This procedure drops a driving context from the object so that it will have one less driving context.

Syntax

```
DBMS_RLS.DROP_POLICY_CONTEXT (  
    object_schema  VARCHAR2,  
    object_name    VARCHAR2,  
    namespace      VARCHAR2,  
    attribute      VARCHAR2);
```

Parameters

Table 79–12 *DROP_POLICY_CONTEXT Procedure Parameters*

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym to which the policy is dropped.
namespace	The namespace of the driving context.
attribute	The attribute of the driving context.

ENABLE_GROUPED_POLICY Procedure

This procedure enables or disables a row-level group security policy.

Syntax

```
DBMS_RLS.ENABLE_GROUPED_POLICY (  
    object_schema  VARCHAR2,  
    object_name    VARCHAR2,  
    group_name     VARCHAR2,  
    policy_name    VARCHAR2,  
    enable         BOOLEAN);
```

Parameters

Table 79–13 *ENABLE_GROUPED_POLICY Procedure Parameters*

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym with which the policy is associated.
group_name	The name of the group of the policy.
policy_name	The name of the policy to be enabled or disabled.
enable	TRUE enables the policy; FALSE disables the policy.

Usage Notes

- The procedure causes the current transaction, if any, to commit before the operation is carried out.
- A commit is performed at the end of the operation.
- A policy is enabled when it is created.

DISABLE_GROUPED_POLICY Procedure

This procedure disables a row-level group security policy.

Syntax

```
DBMS_RLS.DISABLE_GROUPED_POLICY (
  object_schema  VARCHAR2,
  object_name    VARCHAR2,
  group_name     VARCHAR2,
  policy_name    VARCHAR2);
```

Parameters

Table 79–14 *ENABLE_GROUPED_POLICY Procedure Parameters*

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym with which the policy is associated.
group_name	The name of the group of the policy.
policy_name	The name of the policy to be enabled or disabled.

Usage Notes

- The procedure causes the current transaction, if any, to commit before the operation is carried out.
- A commit is performed at the end of the operation.
- A policy is disabled when this procedure is executed or when the `ENABLE_GROUPED_POLICY` procedure is executed with "enable" set to `FALSE`.

REFRESH_GROUPED_POLICY Procedure

This procedure reparses the SQL statements associated with a refreshed policy.

Syntax

```
DBMS_RLS.REFRESH_GROUPED_POLICY (  
    object_schema    VARCHAR2,  
    object_name      VARCHAR2,  
    group_name       VARCHAR2,  
    policy_name      VARCHAR2);
```

Parameters

Table 79–15 REFRESH_GROUPED_POLICY Procedure Parameters

Parameter	Description
object_schema	The schema containing the table, view, or synonym.
object_name	The name of the table, view, or synonym with which the policy is associated.
group_name	The name of the group of the policy.
policy_name	The name of the policy.

Usage Notes

- This procedure causes all the cached statements associated with the policy to be reparsed. This guarantees that the latest change to the policy has immediate effect after the procedure is executed.
- The procedure causes the current transaction, if any, to commit before the operation is carried out.
- A commit is performed at the end of the operation.
- The procedure returns an error if it tries to refresh a disabled policy.

DBMS_ROWID

The `DBMS_ROWID` package lets you create `ROWIDs` and obtain information about `ROWIDs` from PL/SQL programs and SQL statements. You can find the data block number, the object number, and other `ROWID` components without writing code to interpret the base-64 character external `ROWID`. `DBMS_ROWID` is intended for upgrading from Oracle database version 7 to Oracle database version 8.X.

Note: `DBMS_ROWID` is not to be used with universal `ROWIDs` (`UROWIDs`).

This chapter contains the following topics:

- [Using DBMS_ROWID](#)
 - [Security Model](#)
 - [Types](#)
 - [Exceptions](#)
 - [Exceptions](#)
 - [Examples](#)
- [Summary of DBMS_ROWID Subprograms](#)

Using DBMS_ROWID

- [Security Model](#)
- [Types](#)
- [Exceptions](#)
- [Operational Notes](#)
- [Examples](#)

Security Model

This package runs with the privileges of calling user, rather than the package owner SYS.

Types

- [Extension and Restriction Types](#)
- [Verification Types](#)
- [Object Types](#)
- [Conversion Types](#)

Extension and Restriction Types

The types are as follows:

- RESTRICTED—restricted ROWID
- EXTENDED—extended ROWID

For example:

```
rowid_type_restricted constant integer := 0;  
rowid_type_extended   constant integer := 1;
```

Note: Extended ROWIDs are only used in Oracle database version 8.Xi and higher.

Verification Types

Table 80–1 Verification Types

Result	Description
VALID	Valid ROWID
INVALID	Invalid ROWID

For example:

```
rowid_is_valid   constant integer := 0;
rowid_is_invalid constant integer := 1;
```

Object Types

Table 80–2 Object Types

Result	Description
UNDEFINED	Object Number not defined (for restricted ROWIDs)

For example:

```
rowid_object_undefined constant integer := 0;
```

Conversion Types

Table 80–3 Conversion Types

Result	Description
INTERNAL	Convert to/from column of ROWID type
EXTERNAL	Convert to/from string format

For example:

```
rowid_convert_internal constant integer := 0;
rowid_convert_external constant integer := 1;
```

Exceptions

Table 80–4 Exceptions

Exception	Description
ROWID_INVALID	Invalid rowid format
ROWID_BAD_BLOCK	Block is beyond end of file

For example:

```
ROWID_INVALID exception;
  pragma exception_init(ROWID_INVALID, -1410);
```

```
ROWID_BAD_BLOCK exception;
  pragma exception_init(ROWID_BAD_BLOCK, -28516);
```

Operational Notes

- Some of the functions in this package take a single parameter, such as a ROWID. This can be a character or a PL/SQL ROWID, either restricted or extended, as required.
- You can call the DBMS_ROWID functions and procedures from PL/SQL code, and you can also use the functions in SQL statements.

Note: ROWID_INFO is a procedure. It can only be used in PL/SQL code.

- You can use functions from the DBMS_ROWID package just like built-in SQL functions; in other words, you can use them wherever you can use an expression. In this example, the ROWID_BLOCK_NUMBER function is used to return just the block number of a single row in the EMP table:

```
SELECT DBMS_ROWID.ROWID_BLOCK_NUMBER(rowid)
FROM emp
WHERE ename = 'KING';
```

- If Oracle returns the error "ORA:452, 0, 'Subprogram '%s' violates its associated pragma' for pragma restrict_references, it could mean the violation is due to:
 - A problem with the current procedure or function

- Calling a procedure or function without a pragma or due to calling one with a less restrictive pragma
- Calling a package procedure or function that touches the initialization code in a package or that sets the default values

Examples

This example returns the ROWID for a row in the EMP table, extracts the data object number from the ROWID, using the ROWID_OBJECT function in the DBMS_ROWID package, then displays the object number:

```
DECLARE
  object_no  INTEGER;
  row_id     ROWID;
  ...
BEGIN
  SELECT ROWID INTO row_id FROM emp
     WHERE empno = 7499;
  object_no := DBMS_ROWID.ROWID_OBJECT(row_id);
  DBMS_OUTPUT.PUT_LINE('The obj. # is '|| object_no);
  ...
```

Summary of DBMS_ROWID Subprograms

Table 80–5 *DBMS_ROWID Package Subprograms*

Subprogram	Description
ROWID_BLOCK_NUMBER Function on page 80-7	Returns the block number of a ROWID
ROWID_CREATE Function on page 80-8	Creates a ROWID, for testing only
ROWID_INFO Procedure on page 80-10	Returns the type and components of a ROWID
ROWID_OBJECT Function on page 80-12	Returns the object number of the extended ROWID
ROWID_RELATIVE_FNO Function on page 80-13	Returns the file number of a ROWID
ROWID_ROW_NUMBER Function on page 80-14	Returns the row number
ROWID_TO_ABSOLUTE_FNO Function on page 80-15	Returns the absolute file number associated with the ROWID for a row in a specific table
ROWID_TO_EXTENDED Function on page 80-17	Converts a ROWID from restricted format to extended
ROWID_TO_RESTRICTED Function on page 80-19	Converts an extended ROWID to restricted format
ROWID_TYPE Function on page 80-20	Returns the ROWID type: 0 is restricted, 1 is extended
ROWID_VERIFY Function on page 80-21	Checks if a ROWID can be correctly extended by the ROWID_TO_EXTENDED function

ROWID_BLOCK_NUMBER Function

This function returns the database block number for the input ROWID.

Syntax

```
DBMS_ROWID.ROWID_BLOCK_NUMBER (
    row_id      IN   ROWID,
    ts_type_in  IN   VARCHAR2 DEFAULT 'SMALLFILE')
RETURN NUMBER;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_block_number, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 80–6 ROWID_BLOCK_NUMBER Function Parameters

Parameter	Description
row_id	ROWID to be interpreted.
ts_type_in	The type of the tablespace (bigfile/smallfile) to which the row belongs.

Examples

The example SQL statement selects the block number from a ROWID and inserts it into another table:

```
INSERT INTO T2 (SELECT dbms_rowid.rowid_block_number(ROWID, 'BIGFILE')
FROM some_table
WHERE key_value = 42);
```

ROWID_CREATE Function

This function lets you create a ROWID, given the component parts as parameters.

This is useful for testing ROWID operations, because only the Oracle Server can create a valid ROWID that points to data in a database.

Syntax

```
DBMS_ROWID.ROWID_CREATE (  
    rowid_type      IN NUMBER,  
    object_number   IN NUMBER,  
    relative_fno    IN NUMBER,  
    block_number    IN NUMBER,  
    row_number      IN NUMBER)  
RETURN ROWID;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_create,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 80–7 ROWID_CREATE Function Parameters

Parameter	Description
rowid_type	Type (restricted or extended). Set the <code>rowid_type</code> parameter to 0 for a restricted ROWID. Set it to 1 to create an extended ROWID. If you specify <code>rowid_type</code> as 0, then the required <code>object_number</code> parameter is ignored, and <code>ROWID_CREATE</code> returns a restricted ROWID.
object_number	Data object number (<code>rowid_object_undefined</code> for restricted).
relative_fno	Relative file number.
block_number	Block number in this file.
row_number	Returns row number in this block.

Examples

Create a dummy extended ROWID:

```
my_rowid := DBMS_ROWID.ROWID_CREATE(1, 9999, 12, 1000, 13);
```

Find out what the `rowid_object` function returns:

```
obj_number := DBMS_ROWID.ROWID_OBJECT(my_rowid);
```

The variable `obj_number` now contains 9999.

ROWID_INFO Procedure

This procedure returns information about a ROWID, including its type (restricted or extended), and the components of the ROWID. This is a procedure, and it cannot be used in a SQL statement.

Syntax

```
DBMS_ROWID.ROWID_INFO (
    rowid_in          IN   ROWID,
    ts_type_in       IN   VARCHAR2 DEFAULT 'SMALLFILE',
    rowid_type       OUT  NUMBER,
    object_number    OUT  NUMBER,
    relative_fno     OUT  NUMBER,
    block_number     OUT  NUMBER,
    row_number       OUT  NUMBER);
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_info,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 80–8 ROWID_INFO Procedure Parameters

Parameter	Description
rowid_in	ROWID to be interpreted. This determines if the ROWID is a restricted (0) or extended (1) ROWID.
ts_type_in	The type of the tablespace (bigfile/smallfile) to which the row belongs.
rowid_type	Returns type (restricted/extended).
object_number	Returns data object number (rowid_object_undefined for restricted).
relative_fno	Returns relative file number.
block_number	Returns block number in this file.
row_number	Returns row number in this block.

See Also: ["ROWID_TYPE Function"](#) on page 80-20

Examples

This example reads back the values for the ROWID that you created in the ROWID_CREATE:

```
DBMS_ROWID.ROWID_INFO(my_rowid, 'BIGFILE', rid_type, obj_num, file_num, block_
num, row_num);
```

```
DBMS_OUTPUT.PUT_LINE('The type is ' || rid_type);
DBMS_OUTPUT.PUT_LINE('Data object number is ' || obj_num);
-- and so on...
```

ROWID_OBJECT Function

This function returns the data object number for an extended ROWID. The function returns zero if the input ROWID is a restricted ROWID.

Syntax

```
DBMS_ROWID.ROWID_OBJECT (  
    rowid_id IN ROWID)  
RETURN NUMBER;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_object, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 80–9 ROWID_OBJECT Function Parameters

Parameter	Description
row_id	ROWID to be interpreted.

Note: The ROWID_OBJECT_UNDEFINED constant is returned for restricted ROWIDs.

Examples

```
SELECT dbms_rowid.rowid_object(ROWID)  
FROM emp  
WHERE empno = 7499;
```


ROWID_RELATIVE_FNO Function

This function returns the relative file number of the ROWID specified as the IN parameter. (The file number is relative to the tablespace.)

Syntax

```
DBMS_ROWID.ROWID_RELATIVE_FNO (
    rowid_id      IN   ROWID,
    ts_type_in    IN   VARCHAR2 DEFAULT 'SMALLFILE')
RETURN NUMBER;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_relative_fno,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 80–10 ROWID_RELATIVE_FNO Function Parameters

Parameter	Description
row_id	ROWID to be interpreted.
ts_type_in	The type of the tablespace (bigfile/smallfile) to which the row belongs.

Examples

The example PL/SQL code fragment returns the relative file number:

```
DECLARE
    file_number    INTEGER;
    rowid_val      ROWID;
BEGIN
    SELECT ROWID INTO rowid_val
    FROM dept
    WHERE loc = 'Boston';
    file_number :=
        dbms_rowid.rowid_relative_fno(rowid_val, 'SMALLFILE');
    ...
```

ROWID_ROW_NUMBER Function

This function extracts the row number from the ROWID IN parameter.

Syntax

```
DBMS_ROWID.ROWID_ROW_NUMBER (  
    row_id IN ROWID)  
RETURN NUMBER;
```

Pragmas

```
PRAGMA RESTRICT_REFERENCES(rowid_row_number, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 80–11 ROWID_ROW_NUMBER Function Parameters

Parameter	Description
row_id	ROWID to be interpreted.

Examples

Select a row number:

```
SELECT dbms_rowid.rowid_row_number(ROWID)  
FROM emp  
WHERE ename = 'ALLEN';
```

ROWID_TO_ABSOLUTE_FNO Function

This function extracts the absolute file number from a ROWID, where the file number is absolute for a row in a given schema and table. The schema name and the name of the schema object (such as a table name) are provided as IN parameters for this function.

Syntax

```
DBMS_ROWID.ROWID_TO_ABSOLUTE_FNO (
    row_id      IN ROWID,
    schema_name IN VARCHAR2,
    object_name IN VARCHAR2)
RETURN NUMBER;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_to_absolute_fno,WNDS,WNPS,RNPS);
```

Parameters

Table 80–12 ROWID_TO_ABSOLUTE_FNO Function Parameters

Parameter	Description
row_id	ROWID to be interpreted.
schema_name	Name of the schema which contains the table.
object_name	Table name.

Examples

```
DECLARE
    abs_fno      INTEGER;
    rowid_val    CHAR(18);
    object_name  VARCHAR2(20) := 'EMP';
BEGIN
    SELECT ROWID INTO rowid_val
    FROM emp
    WHERE empno = 9999;
    abs_fno := dbms_rowid.rowid_to_absolute_fno(
        rowid_val, 'SCOTT', object_name);
```

Note: For partitioned objects, the name must be a table name, not a partition or a sub/partition name.

ROWID_TO_EXTENDED Function

This function translates a restricted ROWID that addresses a row in a schema and table that you specify to the extended ROWID format. Later, it may be removed from this package into a different place.

Syntax

```
DBMS_ROWID.ROWID_TO_EXTENDED (
    old_rowid      IN ROWID,
    schema_name    IN VARCHAR2,
    object_name    IN VARCHAR2,
    conversion_type IN INTEGER)
RETURN ROWID;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_to_extended,WNDS,WNPS,RNPS);
```

Parameters

Table 80–13 ROWID_TO_EXTENDED Function Parameters

Parameter	Description
old_rowid	ROWID to be converted.
schema_name	Name of the schema which contains the table (optional).
object_name	Table name (optional).
conversion_type	The following constants are defined: rowid_convert_internal (:=0) rowid_convert_external (:=1)

Return Values

ROWID_TO_EXTENDED returns the ROWID in the extended character format. If the input ROWID is NULL, then the function returns NULL. If a zero-valued ROWID is supplied (00000000.0000.0000), then a zero-valued restricted ROWID is returned.

Examples

Assume that there is a table called `RIDS` in the schema `SCOTT`, and that the table contains a column `ROWID_COL` that holds `ROWID`s (restricted), and a column `TABLE_COL` that point to other tables in the `SCOTT` schema. You can convert the `ROWID`s to extended format with the statement:

```
UPDATE SCOTT.RIDS
   SET rowid_col =
      dbms_rowid.rowid_to_extended (
         rowid_col, 'SCOTT', TABLE_COL, 0);
```

Usage Notes

If the schema and object names are provided as `IN` parameters, then this function verifies `SELECT` authority on the table named, and converts the restricted `ROWID` provided to an extended `ROWID`, using the data object number of the table. That `ROWID_TO_EXTENDED` returns a value, however, does not guarantee that the converted `ROWID` actually references a valid row in the table, either at the time that the function is called, or when the extended `ROWID` is actually used.

If the schema and object name are not provided (are passed as `NULL`), then this function attempts to fetch the page specified by the restricted `ROWID` provided. It treats the file number stored in this `ROWID` as the absolute file number. This can cause problems if the file has been dropped, and its number has been reused prior to the migration. If the fetched page belongs to a valid table, then the data object number of this table is used in converting to an extended `ROWID` value. This is very inefficient, and Oracle recommends doing this only as a last resort, when the target table is not known. The user must still know the correct table name at the time of using the converted value.

If an extended `ROWID` value is supplied, the data object number in the input extended `ROWID` is verified against the data object number computed from the table name parameter. If the two numbers do not match, the `INVALID_ROWID` exception is raised. If they do match, the input `ROWID` is returned.

See Also: The [ROWID_VERIFY Function](#) has a method to determine if a given `ROWID` can be converted to the extended format.

ROWID_TO_RESTRICTED Function

This function converts an extended ROWID into restricted ROWID format.

Syntax

```
DBMS_ROWID.ROWID_TO_RESTRICTED (  
    old_rowid      IN ROWID,  
    conversion_type IN INTEGER)  
RETURN ROWID;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_to_restricted,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 80–14 *ROWID_TO_RESTRICTED Function Parameters*

Parameter	Description
old_rowid	ROWID to be converted.
conversion_type	The following constants are defined: rowid_convert_internal (:=0) rowid_convert_external (:=1)

ROWID_TYPE Function

This function returns 0 if the ROWID is a restricted ROWID, and 1 if it is extended.

Syntax

```
DBMS_ROWID.ROWID_TYPE (  
    rowid_id IN ROWID)  
RETURN NUMBER;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_type,WNDS,RNDS,WNPS,RNPS);
```

Parameters

Table 80–15 ROWID_TYPE Function Parameters

Parameter	Description
row_id	ROWID to be interpreted.

Examples

```
IF DBMS_ROWID.ROWID_TYPE(my_rowid) = 1 THEN  
    my_obj_num := DBMS_ROWID.ROWID_OBJECT(my_rowid);
```


ROWID_VERIFY Function

This function verifies the ROWID. It returns 0 if the input restricted ROWID can be converted to extended format, given the input schema name and table name, and it returns 1 if the conversion is not possible.

Note: You can use this function in a WHERE clause of a SQL statement, as shown in the example.

Syntax

```
DBMS_ROWID.ROWID_VERIFY (
    rowid_in          IN ROWID,
    schema_name       IN VARCHAR2,
    object_name       IN VARCHAR2,
    conversion_type   IN INTEGER
) RETURN NUMBER;
```

Pragmas

```
pragma RESTRICT_REFERENCES(rowid_verify,WNDS,WNPS,RNPS);
```

Parameters

Table 80–16 ROWID_VERIFY Function Parameters

Parameter	Description
rowid_in	ROWID to be verified.
schema_name	Name of the schema which contains the table.
object_name	Table name.
conversion_type	The following constants are defined: rowid_convert_internal (:=0) rowid_convert_external (:=1)

Examples

Considering the schema in the example for the ROWID_TO_EXTENDED function, you can use the following statement to find bad ROWIDs prior to conversion. This enables you to fix them beforehand.

```
SELECT ROWID, rowid_col
FROM SCOTT.RIDS
WHERE dbms_rowid.rowid_verify(rowid_col, NULL, NULL, 0) =1;
```

See Also: [Chapter 161, "UTL_RAW"](#), [Chapter 163, "UTL_REF"](#)

The `DBMS_RULE` package contains subprograms that enable the evaluation of a rule set for a specified event.

See Also:

- [Chapter 181, "Rule TYPES"](#) for more information about the types used with the `DBMS_RULE` package
- [Chapter 82, "DBMS_RULE_ADM"](#) and *Oracle Streams Concepts and Administration* for more information about this package and rules

This chapter contains the following topics:

- [Using DBMS_RULE](#)
 - [Security Model](#)
- [Summary of DBMS_RULE Subprograms](#)

Using DBMS_RULE

- [Security Model](#)

Security Model

PUBLIC is granted execute privilege on this package.

Summary of DBMS_RULE Subprograms

Table 81-1 DBMS_RULE Package Subprograms

Subprogram	Description
CLOSE_ITERATOR Procedure on page 81-4	Closes an open iterator
EVALUATE Procedures on page 81-5	Evaluates the rules in the specified rule set that use the evaluation context specified
GET_NEXT_HIT Function on page 81-10	Returns the next rule that evaluated to <code>TRUE</code> from a true rules iterator, or returns the next rule that evaluated to <code>MAYBE</code> from a maybe rules iterator; returns <code>NULL</code> if there are no more rules that evaluated to <code>TRUE</code> or <code>MAYBE</code> .

CLOSE_ITERATOR Procedure

This procedure closes an open iterator.

Syntax

```
DBMS_RULE.CLOSE_ITERATOR(  
    iterator IN NUMBER);
```

Parameter

Table 81–2 *CLOSE_ITERATOR Procedure Parameter*

Parameter	Description
<code>iterator</code>	The iterator to be closed

Usage Notes

This procedure requires an open iterator that was returned by an earlier call to `DBMS_RULE.EVALUATE` in the same session. The user who runs this procedure does not require any privileges on the rule set being evaluated.

Closing an iterator frees resources, such as memory, associated with the iterator. Therefore, Oracle recommends that you close an iterator when it is no longer needed.

See Also: ["EVALUATE Procedures"](#) on page 81-5

EVALUATE Procedures

This procedure evaluates the rules in the specified rule set that use the evaluation context specified for a specified event.

This procedure is overloaded. The `true_rules` and `maybe_rules` parameters are mutually exclusive with the `true_rules_iterator` and `maybe_rules_iterator` parameters. In addition, the procedure with the `true_rules` and `maybe_rules` parameters includes the `stop_on_first_hit` parameter, but the other procedure does not.

Syntax

```
DBMS_RULE.EVALUATE(
    rule_set_name      IN  VARCHAR2,
    evaluation_context IN  VARCHAR2,
    event_context      IN  SYS.RE$NV_LIST           DEFAULT NULL,
    table_values       IN  SYS.RE$TABLE_VALUE_LIST  DEFAULT NULL,
    column_values      IN  SYS.RE$COLUMN_VALUE_LIST DEFAULT NULL,
    variable_values    IN  SYS.RE$VARIABLE_VALUE_LIST DEFAULT NULL,
    attribute_values   IN  SYS.RE$ATTRIBUTE_VALUE_LIST DEFAULT NULL,
    stop_on_first_hit  IN  BOOLEAN                 DEFAULT false,
    simple_rules_only  IN  BOOLEAN                 DEFAULT false,
    true_rules         OUT SYS.RE$RULE_HIT_LIST,
    maybe_rules        OUT SYS.RE$RULE_HIT_LIST);
```

```
DBMS_RULE.EVALUATE(
    rule_set_name      IN  VARCHAR2,
    evaluation_context IN  VARCHAR2,
    event_context      IN  SYS.RE$NV_LIST           DEFAULT NULL,
    table_values       IN  SYS.RE$TABLE_VALUE_LIST  DEFAULT NULL,
    column_values      IN  SYS.RE$COLUMN_VALUE_LIST DEFAULT NULL,
    variable_values    IN  SYS.RE$VARIABLE_VALUE_LIST DEFAULT NULL,
    attribute_values   IN  SYS.RE$ATTRIBUTE_VALUE_LIST DEFAULT NULL,
    simple_rules_only  IN  BOOLEAN                 DEFAULT false,
    true_rules_iterator OUT BINARY_INTEGER,
    maybe_rules_iterator OUT BINARY_INTEGER);
```

Parameters

Table 81–3 *EVALUATE Procedure Parameters*

Parameter	Description
<code>rule_set_name</code>	Name of the rule set in the form <code>[schema_name.]rule_set_name</code> . For example, to evaluate all of the rules in a rule set named <code>hr_rules</code> in the <code>hr</code> schema, enter <code>hr.hr_rules</code> for this parameter. If the schema is not specified, then the schema of the current user is used.
<code>evaluation_context</code>	An evaluation context name in the form <code>[schema_name.]evaluation_context_name</code> . If the schema is not specified, then the name of the current user is used. Only rules that use the specified evaluation context are evaluated.
<code>event_context</code>	A list of name-value pairs that identify events that cause evaluation
<code>table_values</code>	Contains the data for table rows using the table aliases specified when the evaluation context was created. Each table alias in the list must be unique.
<code>column_values</code>	Contains the partial data for table rows. It must not contain column values for tables, whose values are already specified in <code>table_values</code> .
<code>variable_values</code>	A list containing the data for variables. The only way for an explicit variable value to be known is to specify its value in this list. If an implicit variable value is not specified in the list, then the function used to obtain the value of the implicit variable is invoked. If an implicit variable value is specified in the list, then this value is used and the function is not invoked.
<code>attribute_values</code>	Contains the partial data for variables. It must not contain attribute values for variables whose values are already specified in <code>variable_values</code> .
<code>stop_on_first_hit</code>	If <code>true</code> , then the rules engine stops evaluation as soon as it finds a <code>TRUE</code> rule. If <code>true</code> and there are no <code>TRUE</code> rules, then the rules engine stops evaluation as soon as it finds a rule that may evaluate to <code>TRUE</code> given more data. If <code>false</code> , then the rules engine continues to evaluate rules even after it finds a <code>TRUE</code> rule.

Table 81–3 (Cont.) EVALUATE Procedure Parameters

Parameter	Description
<code>simple_rules_only</code>	<p>If <code>true</code>, then only those rules that are simple enough to be evaluated fast (without issuing SQL) are considered for evaluation.</p> <p>If <code>false</code>, then evaluates all rules.</p>
<code>true_rules</code>	<p>Receives the output of the <code>EVALUATE</code> procedure into a varray of <code>RE\$RULE_HIT_LIST</code> type.</p> <p>If no rules evaluate to <code>TRUE</code>, then <code>true_rules</code> is empty.</p> <p>If at least one rule evaluates to <code>TRUE</code> and <code>stop_on_first_hit</code> is <code>true</code>, then <code>true_rules</code> contains one rule that evaluates to <code>TRUE</code>.</p> <p>If <code>stop_on_first_hit</code> is <code>false</code>, then <code>true_rules</code> contains all rules that evaluate to <code>TRUE</code>.</p>
<code>maybe_rules</code>	<p>If all rules can be evaluated completely, without requiring any additional data, then <code>maybe_rules</code> is empty.</p> <p>If <code>stop_on_first_hit</code> is <code>true</code>, then if there is at least one rule that may evaluate to <code>TRUE</code> given more data, and no rules evaluate to <code>TRUE</code>, then <code>maybe_rules</code> contains one rule that may evaluate to <code>TRUE</code>.</p> <p>If <code>stop_on_first_hit</code> is <code>false</code>, then <code>maybe_rules</code> contains all rules that may evaluate to <code>TRUE</code> given more data.</p>
<code>true_rules_iterator</code>	Contains the iterator for accessing rules that are <code>TRUE</code>
<code>maybe_rules_iterator</code>	Contains the iterator for accessing rules that may be <code>TRUE</code> given additional data or the ability to issue SQL

Usage Notes

Note: Rules in the rule set that use an evaluation context different from the one specified are not considered for evaluation.

The rules in the rule set are evaluated using the data specified for `table_values`, `column_values`, `variable_values`, and `attribute_values`. These values must refer to tables and variables in the specified evaluation context. Otherwise, an error is raised.

The caller may specify, using `stop_on_first_hit`, if evaluation must stop as soon as the first `TRUE` rule or the first `MAYBE` rule (if there are no `TRUE` rules) is found.

The caller may also specify, using `simple_rules_only`, if only rules that are simple enough to be evaluated fast (which means without SQL) should be considered for evaluation. This makes evaluation faster, but causes rules that cannot be evaluated without SQL to be returned as `MAYBE` rules.

Partial evaluation is supported. The `EVALUATE` procedure can be called with data for only some of the tables, columns, variables, or attributes. In such a case, rules that cannot be evaluated because of a lack of data are returned as `MAYBE` rules, unless they can be determined to be `TRUE` or `FALSE` based on the values of one or more simple expressions within the rule. For example, given a value of 1 for attribute `"a.b"` of variable `"x"`, a rule with the following rule condition can be returned as `TRUE`, without a value for table `"tab"`:

```
(:x.a.b = 1) or (tab.c > 10)
```

The results of an evaluation are the following:

- `TRUE` rules, which is the list of rules that evaluate to `TRUE` based on the given data. These rules are returned either in the `OUT` parameter `true_rules`, which returns all of the rules that evaluate to `TRUE`, or in the `OUT` parameter `true_rules_iterator`, which returns each rule that evaluates to `TRUE` one at a time.
- `MAYBE` rules, which is the list of rules that could not be evaluated for one of the following reasons:
 - The rule refers to data that was unavailable. For example, a variable attribute `"x.a.b"` is specified, but no value is specified for the variable `"x"`, the attribute `"a"`, or the attribute `"a.b"`.
 - The rule is not simple enough to be evaluated fast (without SQL) and `simple_rules_only` is specified as `true`, or partial data is available.

Maybe rules are returned either in the `OUT` parameter `maybe_rules`, which returns all of the rules that evaluate to `MAYBE`, or in the `OUT` parameter `maybe_rules_iterator`, which returns each rule that evaluates to `MAYBE` one at a time.

The caller may specify whether the procedure returns all of the rules that evaluate to `TRUE` and `MAYBE` for the event or an iterator for rules that evaluate to `TRUE` and `MAYBE`. A true rules iterator enables the client to fetch each rule that evaluates to

TRUE one at a time, and a maybe rules iterator enables the client to fetch each rule that evaluates to MAYBE one at a time.

If you use an iterator, then you use the GET_NEXT_HIT function in the DBMS_RULE package to retrieve the next rule that evaluates to TRUE or MAYBE from an iterator. Oracle recommends that you close an iterator if it is no longer needed to free resources, such as memory, used by the iterator. An iterator can be closed in the following ways:

- The CLOSE_ITERATOR procedure in the DBMS_RULE package is run with the iterator specified.
- The iterator returns NULL because no more rules evaluate to TRUE or MAYBE.
- The session in which the iterator is running ends.

To run the DBMS_RULE.EVALUATE procedure, a user must meet at least one of the following requirements:

- Have EXECUTE_ON_RULE_SET privilege on the rule set
- Have EXECUTE_ANY_RULE_SET system privilege
- Be the rule set owner

Note: The rules engine does not invoke any actions. An action context can be returned with each returned rule, but the client of the rules engine must invoke any necessary actions.

See Also:

- [Chapter 181, "Rule TYPES"](#) for more information about the types used with the DBMS_RULE package
- ["GET_NEXT_HIT Function"](#) on page 81-10
- ["CLOSE_ITERATOR Procedure"](#) on page 81-4

GET_NEXT_HIT Function

This function returns the next rule that evaluated to `TRUE` from a true rules iterator, or returns the next rule that evaluated to `MAYBE` from a maybe rules iterator. The function returns `NULL` if there are no more rules that evaluated to `TRUE` or `MAYBE`.

Syntax

```
DBMS_RULE.GET_NEXT_HIT(  
    iterator IN NUMBER)  
RETURN SYS.RE$RULE_HIT;
```

Parameter

Table 81–4 *GET_NEXT_HIT Procedure Parameter*

Parameter	Description
<code>iterator</code>	The iterator from which the rule that evaluated to <code>TRUE</code> or <code>MAYBE</code> is retrieved

Usage Notes

This procedure requires an open iterator that was returned by an earlier call to `DBMS_RULE.EVALUATE` in the same session. The user who runs this procedure does not require any privileges on the rule set being evaluated.

When an iterator returns `NULL`, it is closed automatically. If an open iterator is no longer needed, then use the `CLOSE_ITERATOR` procedure in the `DBMS_RULE` package to close it.

Note: This function raises an error if the rule set being evaluated was modified after the call to the `DBMS_RULE.EVALUATE` procedure that returned the iterator. Modifications to a rule set include added rules to the rule set, changing existing rules in the rule set, dropping rules from the rule set, and dropping the rule set.

See Also:

- [Chapter 181, "Rule TYPES"](#) for more information about the types used with the DBMS_RULE package
- ["EVALUATE Procedures"](#) on page 81-5
- ["CLOSE_ITERATOR Procedure"](#) on page 81-4

DBMS_RULE_ADM

The `DBMS_RULE_ADM` package provides the administrative interfaces for creating and managing rules, rule sets, and rule evaluation contexts.

See Also:

- [Chapter 181, "Rule TYPES"](#) for more information about the types used with the `DBMS_RULE_ADM` package
- [Chapter 81, "DBMS_RULE"](#) and *Oracle Streams Concepts and Administration* for more information about this package and rules

This chapter contains the following topics:

- [Using DBMS_RULE_ADM](#)
 - [Security Model](#)
- [Summary of DBMS_RULE_ADM Subprograms](#)

Using DBMS_RULE_ADM

- [Security Model](#)

Security Model

PUBLIC is granted execute privilege on this package.

Summary of DBMS_RULE_ADM Subprograms

Table 82–1 DBMS_RULE_ADM Package Subprograms

Subprogram	Description
ADD_RULE Procedure on page 82-4	Adds the specified rule to the specified rule set
ALTER_RULE Procedure on page 82-6	Changes one or more aspects of the specified rule
CREATE_EVALUATION_CONTEXT Procedure on page 82-9	Creates a rule evaluation context
CREATE_RULE Procedure on page 82-11	Creates a rule with the specified name
CREATE_RULE_SET Procedure on page 82-13	Creates a rule set with the specified name
DROP_EVALUATION_CONTEXT Procedure on page 82-15	Drops the rule evaluation context with the specified name
DROP_RULE Procedure on page 82-16	Drops the rule with the specified name
DROP_RULE_SET Procedure on page 82-17	Drops the rule set with the specified name
GRANT_OBJECT_PRIVILEGE Procedure on page 82-18	Grants the specified object privilege on the specified object to the specified user or role
GRANT_SYSTEM_PRIVILEGE Procedure on page 82-20	Grants the specified system privilege to the specified user or role
REMOVE_RULE Procedure on page 82-22	Removes the specified rule from the specified rule set
REVOKE_OBJECT_PRIVILEGE Procedure on page 82-24	Revokes the specified object privilege on the specified object from the specified user or role
REVOKE_SYSTEM_PRIVILEGE Procedure on page 82-25	Revokes the specified system privilege from the specified user or role

Note: All procedures commit unless specified otherwise.

ADD_RULE Procedure

This procedure adds the specified rule to the specified rule set.

Syntax

```
DBMS_RULE_ADM.ADD_RULE(
    rule_name          IN  VARCHAR2,
    rule_set_name     IN  VARCHAR2,
    evaluation_context IN  VARCHAR2  DEFAULT NULL,
    rule_comment      IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 82–2 ADD_RULE Procedure Parameters

Parameter	Description
<code>rule_name</code>	The name of the rule you are adding to the rule set, specified as <code>[schema_name.]rule_name</code> . For example, to add a rule named <code>all_a</code> in the <code>hr</code> schema, enter <code>hr.all_a</code> for this parameter. If the schema is not specified, then the current user is the default.
<code>rule_set_name</code>	The name of the rule set to which you are adding the rule, specified as <code>[schema_name.]rule_set_name</code> . For example, to add the rule to a rule set named <code>apply_rules</code> in the <code>hr</code> schema, enter <code>hr.apply_rules</code> for this parameter. If the schema is not specified, then the current user is the default.
<code>evaluation_context</code>	An evaluation context name in the form <code>[schema_name.]evaluation_context_name</code> . If the schema is not specified, then the current user is the default. Only specify an evaluation context if the rule itself does not have an evaluation context and you do not want to use the rule set's evaluation context for the rule.
<code>rule_comment</code>	Optional description, which may contain the reason for adding the rule to the rule set

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Have `ALTER_ON_RULE_SET` privilege on the rule set
- Have `ALTER_ANY_RULE_SET` system privilege

- Be the owner of the rule set

Also, the rule set owner must meet at least one of the following requirements:

- Have `EXECUTE_ON_RULE` privilege on the rule
- Have `EXECUTE_ANY_RULE` system privilege
- Be the rule owner

If the rule has no evaluation context and no evaluation context is specified when you run this procedure, then rule uses the evaluation context associated with the rule set. In such a case, the rule owner must have the necessary privileges on all the base objects accessed by the rule using the evaluation context.

If an evaluation context is specified, then the rule set owner must meet at least one of the following requirements:

- Have `EXECUTE_ON_EVALUATION_CONTEXT` privilege on the evaluation context
- Have `EXECUTE_ANY_EVALUATION_CONTEXT` system privilege, and the owner of the evaluation context must not be `SYS`
- Be the evaluation context owner

Also, the rule owner must have the necessary privileges on all the base objects accessed by the rule using the evaluation context.

ALTER_RULE Procedure

This procedure changes one or more aspects of the specified rule.

Syntax

```
DBMS_RULE_ADM.ALTER_RULE(
    rule_name          IN  VARCHAR2,
    condition          IN  VARCHAR2          DEFAULT NULL,
    evaluation_context IN  VARCHAR2          DEFAULT NULL,
    remove_evaluation_context IN  BOOLEAN      DEFAULT false,
    action_context     IN  SYS.RE$NV_LIST    DEFAULT NULL,
    remove_action_context IN  BOOLEAN        DEFAULT false,
    rule_comment       IN  VARCHAR2          DEFAULT NULL,
    remove_rule_comment IN  BOOLEAN          DEFAULT false);
```

Parameters

Table 82–3 ALTER_RULE Procedure Parameters

Parameter	Description
rule_name	The name of the rule you are altering, specified as [<i>schema_name</i> .] <i>rule_name</i> . For example, to alter a rule named <i>all_a</i> in the <i>hr</i> schema, enter <i>hr.all_a</i> for this parameter. If the schema is not specified, then the current user is the default.
condition	The condition to be associated with the rule. If non-NULL, then the rule's condition is changed.
evaluation_context	An evaluation context name in the form [<i>schema_name</i> .] <i>evaluation_context_name</i> . If the schema is not specified, then the current user is the default. If non-NULL, then the rule's evaluation context is changed.
remove_evaluation_context	If <i>true</i> , then sets the evaluation context for the rule to NULL, which effectively removes the evaluation context from the rule. If <i>false</i> , then retains any evaluation context for the specified rule. If the <i>evaluation_context</i> parameter is non-NULL, then this parameter should be set to <i>false</i> .

Table 82–3 (Cont.) ALTER_RULE Procedure Parameters

Parameter	Description
<code>action_context</code>	If non-NULL, then changes the action context associated with the rule. A rule action context is information associated with a rule that is interpreted by the client of the rules engine when the rule is evaluated.
<code>remove_action_context</code>	If <code>true</code> , then sets the action context for the rule to <code>NULL</code> , which effectively removes the action context from the rule. If <code>false</code> , then retains any action context for the specified rule. If the <code>action_context</code> parameter is non-NULL, then this parameter should be set to <code>false</code> .
<code>rule_comment</code>	If non-NULL, then changes the description of the rule
<code>remove_rule_comment</code>	If <code>true</code> , then sets the comment for the rule to <code>NULL</code> , which effectively removes the comment from the rule. If <code>false</code> , then retains any comment for the specified rule. If the <code>rule_comment</code> parameter is non-NULL, then this parameter should be set to <code>false</code> .

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Have `ALTER_ON_RULE` privilege on the rule
- Have `ALTER_ANY_RULE` system privilege
- Be the owner of the rule being altered

If an evaluation context is specified, then the rule owner must meet at least one of the following requirements:

- Have `EXECUTE_ON_EVALUATION_CONTEXT` privilege on the evaluation context
- Have `EXECUTE_ANY_EVALUATION_CONTEXT` system privilege, and the owner of the evaluation context must not be `SYS`
- Be the evaluation context owner

Also, the rule owner must have the necessary privileges on all the base objects accessed by the rule using the evaluation context.

See Also: [Chapter 181, "Rule TYPES"](#) for more information about the types used with the `DBMS_RULE_ADM` package

CREATE_EVALUATION_CONTEXT Procedure

This procedure creates a rule evaluation context. A rule evaluation context defines external data that can be referenced in rule conditions. The external data can either exist as variables or as table data.

Syntax

```
DBMS_RULE_ADM.CREATE_EVALUATION_CONTEXT(
  evaluation_context_name      IN  VARCHAR2,
  table_aliases                IN  SYS.RE$TABLE_ALIAS_LIST   DEFAULT NULL,
  variable_types               IN  SYS.RE$VARIABLE_TYPE_LIST  DEFAULT NULL,
  evaluation_function           IN  VARCHAR2                  DEFAULT NULL,
  evaluation_context_comment   IN  VARCHAR2                  DEFAULT NULL);
```

Parameters

Table 82–4 CREATE_EVALUATION_CONTEXT Procedure Parameters

Parameter	Description
evaluation_context_name	The name of the evaluation context you are creating, specified as [<i>schema_name</i> .] <i>evaluation_context_name</i> . For example, to create an evaluation context named <code>dept_eval_context</code> in the <code>hr</code> schema, enter <code>hr.dept_eval_context</code> for this parameter. If the schema is not specified, then the current user is the default.
table_aliases	Table aliases that specify the tables in an evaluation context. The table aliases can be used to reference tables in rule conditions.
variable_types	A list of variables for the evaluation context
evaluation_function	An optional function that will be called to evaluate rules using the evaluation context. It must have the same form as the <code>DBMS_RULE.EVALUATE</code> procedure. If the schema is not specified, then the current user is the default. See "Usage Notes" for more information about the evaluation function.
evaluation_context_comment	An optional description of the rule evaluation context.

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Be the owner of the evaluation context being created and have `CREATE_EVALUATION_CONTEXT_OBJ` system privilege
- Have `CREATE_ANY_EVALUATION_CONTEXT` system privilege

See Also: [Chapter 181, "Rule TYPES"](#) for more information about the types used with the `DBMS_RULE_ADM` package

The evaluation function must have the following signature:

```
FUNCTION evaluation_function_name(
  rule_set_name      IN   VARCHAR2,
  evaluation_context IN   VARCHAR2,
  event_context      IN   SYS.RE$NV_LIST           DEFAULT NULL,
  table_values       IN   SYS.RE$TABLE_VALUE_LIST  DEFAULT NULL,
  column_values      IN   SYS.RE$COLUMN_VALUE_LIST DEFAULT NULL,
  variable_values    IN   SYS.RE$VARIABLE_VALUE_LIST DEFAULT NULL,
  attribute_values   IN   SYS.RE$ATTRIBUTE_VALUE_LIST DEFAULT NULL,
  stop_on_first_hit  IN   BOOLEAN                 DEFAULT false,
  simple_rules_only  IN   BOOLEAN                 DEFAULT false,
  true_rules         OUT  SYS.RE$RULE_HIT_LIST,
  maybe_rules        OUT  SYS.RE$RULE_HIT_LIST);
RETURN BINARY_INTEGER;
```

Note: Each parameter is required and must have the specified datatype. However, you can change the names of the parameters.

The return value of the function must be one of the following:

- `DBMS_RULE_ADM.EVALUATION_SUCCESS`: The user specified evaluation function completed the rule set evaluation successfully. The rules engine returns the results of the evaluation obtained by the evaluation function to the rules engine client using the `DBMS_RULE.EVALUATE` procedure.
- `DBMS_RULE_ADM.EVALUATION_CONTINUE`: The rules engine evaluates the rule set as if there were no evaluation function. The evaluation function is not used, and any results returned by the evaluation function are ignored.
- `DBMS_RULE_ADM.EVALUATION_FAILURE`: The user specified evaluation function failed. Rule set evaluation stops, and an error is raised.

CREATE_RULE Procedure

This procedure creates a rule.

Syntax

```
DBMS_RULE_ADM.CREATE_RULE(
    rule_name          IN  VARCHAR2,
    condition          IN  VARCHAR2,
    evaluation_context IN  VARCHAR2          DEFAULT NULL,
    action_context     IN  SYS.RE$NV_LIST   DEFAULT NULL,
    rule_comment       IN  VARCHAR2          DEFAULT NULL);
```

Parameters

Table 82–5 CREATE_RULE Procedure Parameters

Parameter	Description
rule_name	The name of the rule you are creating, specified as [<i>schema_name</i> .] <i>rule_name</i> . For example, to create a rule named <i>all_a</i> in the <i>hr</i> schema, enter <i>hr.all_a</i> for this parameter. If the schema is not specified, then the current user is the default.
condition	The condition to be associated with the rule. A condition evaluates to TRUE or FALSE and can be any condition allowed in the WHERE clause of a SELECT statement. For example, the following is a valid rule condition: <pre>department_id = 30</pre> <p>Note: Do not include the word "WHERE" in the condition.</p>
evaluation_context	An optional evaluation context name in the form [<i>schema_name</i> .] <i>evaluation_context_name</i> , which is associated with the rule. If the schema is not specified, then the current user is the default. If <i>evaluation_context</i> is not specified, then the rule inherits the evaluation context from its rule set.
action_context	The action context associated with the rule. A rule action context is information associated with a rule that is interpreted by the client of the rules engine when the rule is evaluated.
rule_comment	An optional description of the rule

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Be the owner of the rule being created and have the `CREATE_RULE_OBJ` system privilege
- Have `CREATE_ANY_RULE` system privilege

If an evaluation context is specified, then the rule owner must meet at least one of the following requirements:

- Have `EXECUTE_ON_EVALUATION_CONTEXT` privilege on the evaluation context
- Have `EXECUTE_ANY_EVALUATION_CONTEXT` system privilege, and the owner of the evaluation context must not be `SYS`.
- Be the evaluation context owner

Also, the rule owner must have the necessary privileges on all the base objects accessed by the rule using the evaluation context.

See Also: [Chapter 181, "Rule TYPES"](#) for more information about the types used with the `DBMS_RULE_ADM` package

CREATE_RULE_SET Procedure

This procedure creates a rule set.

Syntax

```
DBMS_RULE_ADM.CREATE_RULE_SET(
    rule_set_name      IN  VARCHAR2,
    evaluation_context IN  VARCHAR2  DEFAULT NULL,
    rule_set_comment   IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 82–6 CREATE_RULE_SET Procedure Parameters

Parameter	Description
rule_set_name	The name of the rule set you are creating, specified as [<i>schema_name</i> .] <i>rule_set_name</i> . For example, to create a rule set named <i>apply_rules</i> in the <i>hr</i> schema, enter <i>hr.apply_rules</i> for this parameter. If the schema is not specified, then the current user is the default.
evaluation_context	An optional evaluation context name in the form [<i>schema_name</i> .] <i>evaluation_context_name</i> , which applies to all rules in the rule set that are not associated with an evaluation context explicitly. If the schema is not specified, then the current user is the default.
rule_set_comment	An optional description of the rule set

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Be the owner of the rule set being created and have `CREATE_RULE_SET_OBJ` system privilege
- Have `CREATE_ANY_RULE_SET` system privilege

If an evaluation context is specified, then the rule set owner must meet at least one of the following requirements:

- Have `EXECUTE_ON_EVALUATION_CONTEXT` privilege on the evaluation context

- Have `EXECUTE_ANY_EVALUATION_CONTEXT` system privilege, and the owner of the evaluation context must not be `SYS`
- Be the evaluation context owner

DROP_EVALUATION_CONTEXT Procedure

This procedure drops a rule evaluation context.

Syntax

```
DBMS_RULE_ADM.DROP_EVALUATION_CONTEXT(
    evaluation_context_name IN VARCHAR2,
    force                    IN BOOLEAN DEFAULT false);
```

Parameters

Table 82–7 DROP_EVALUATION_CONTEXT Procedure Parameters

Parameter	Description
evaluation_context_name	<p>The name of the evaluation context you are dropping, specified as <code>[schema_name.]evaluation_context_name</code>.</p> <p>For example, to drop an evaluation context named <code>dept_eval_context</code> in the <code>hr</code> schema, enter <code>hr.dept_eval_context</code> for this parameter. If the schema is not specified, then the current user is the default.</p>
force	<p>If <code>true</code>, then removes the rule evaluation context from all rules and rule sets that use it.</p> <p>If <code>false</code> and no rules or rule sets use the rule evaluation context, then drops the rule evaluation context.</p> <p>If <code>false</code> and one or more rules or rule sets use the rule evaluation context, then raises an exception.</p> <p>Caution: Setting <code>force</code> to <code>true</code> can result in rules and rule sets that do not have an evaluation context. If neither a rule nor the rule set it is in has an evaluation context, and no evaluation context was specified for the rule by the <code>ADD_RULE</code> procedure, then the rule cannot be evaluated.</p>

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Be the owner of the evaluation context
- Have `DROP_ANY_EVALUATION_CONTEXT` system privilege

DROP_RULE Procedure

This procedure drops a rule.

Syntax

```
DBMS_RULE_ADM.DROP_RULE(  
    rule_name IN VARCHAR2,  
    force     IN BOOLEAN  DEFAULT false);
```

Parameters

Table 82–8 DROP_RULE Procedure Parameters

Parameter	Description
rule_name	The name of the rule you are dropping, specified as [<i>schema_name</i> .] <i>rule_name</i> . For example, to drop a rule named <i>all_a</i> in the <i>hr</i> schema, enter <i>hr.all_a</i> for this parameter. If the schema is not specified, then the current user is the default.
force	If <i>true</i> , then removes the rule from all rule sets that contain it. If <i>false</i> and no rule sets contain the rule, then drops the rule. If <i>false</i> and one or more rule sets contain the rule, then raises an exception.

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Be the owner of the rule
- Have `DROP_ANY_RULE` system privilege

Note:

- To remove a rule from a rule set without dropping the rule from the database, use the `REMOVE_RULE` procedure.
 - The rule evaluation context associated with the rule, if any, is not dropped when you run this procedure.
-
-

DROP_RULE_SET Procedure

This procedure drops a rule set.

Syntax

```
DBMS_RULE_ADM.DROP_RULE_SET(
    rule_set_name IN VARCHAR2,
    delete_rules  IN BOOLEAN  DEFAULT false);
```

Parameters

Table 82–9 DROP_RULE_SET Procedure Parameters

Parameter	Description
<code>rule_set_name</code>	The name of the rule set you are dropping, specified as [<i>schema_name</i> .] <i>rule_set_name</i> . For example, to drop a rule set named <code>apply_rules</code> in the <code>hr</code> schema, enter <code>hr.apply_rules</code> for this parameter. If the schema is not specified, then the current user is the default.
<code>delete_rules</code>	If <code>true</code> , then also drops any rules that are in the rule set. If any of the rules in the rule set are also in another rule set, then these rules are not dropped. If <code>false</code> , then the rules in the rule set are retained.

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Have `DROP_ANY_RULE_SET` system privilege
- Be the owner of the rule set

Note: The rule evaluation context associated with the rule set, if any, is not dropped when you run this procedure.

GRANT_OBJECT_PRIVILEGE Procedure

This procedure grants the specified object privilege on the specified object to the specified user or role. If a user owns the object, then the user automatically is granted all privileges on the object, with grant option.

Syntax

```
DBMS_RULE_ADM.GRANT_OBJECT_PRIVILEGE(
  privilege      IN BINARY_INTEGER,
  object_name    IN VARCHAR2,
  grantee        IN VARCHAR2,
  grant_option   IN BOOLEAN    DEFAULT false);
```

Parameters

Table 82–10 GRANT_OBJECT_PRIVILEGE Procedure Parameters

Parameter	Description
privilege	The name of the object privilege to grant to the grantee on the object. See "Usage Notes" on page 82-18 for the available object privileges.
object_name	The name of the object for which you are granting the privilege to the grantee, specified as <code>[schema_name.]object_name</code> . For example, to grant the privilege on a rule set named <code>apply_rules</code> in the <code>hr</code> schema, enter <code>hr.apply_rules</code> for this parameter. If the schema is not specified, then the current user is the default. The object must be an existing rule, rule set, or evaluation context.
grantee	The name of the user or role for which the privilege is granted. The specified user cannot be the owner of the object.
grant_option	If <code>true</code> , then the specified user or users granted the specified privilege can grant this privilege to others. If <code>false</code> , then the specified user or users granted the specified privilege cannot grant this privilege to others.

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Be the owner of the object on which the privilege is granted

- Have the same privilege as the privilege being granted with the grant option

In addition, if the object is a rule set, then the user must have `EXECUTE` privilege on all the rules in the rule set with grant option or must own the rules in the rule set.

Table 82–11 lists the object privileges.

Table 82–11 Object Privileges for Evaluation Contexts, Rules, and Rule Sets

Privilege	Description
<code>SYS.DBMS_RULE_ADM.ALL_ON_EVALUATION_CONTEXT</code>	Alter and execute a particular evaluation context in another user's schema
<code>SYS.DBMS_RULE_ADM.ALL_ON_RULE</code>	Alter and execute a particular rule in another user's schema
<code>SYS.DBMS_RULE_ADM.ALL_ON_RULE_SET</code>	Alter and execute a particular rule set in another user's schema
<code>SYS.DBMS_RULE_ADM.ALTER_ON_EVALUATION_CONTEXT</code>	Alter a particular evaluation context in another user's schema
<code>SYS.DBMS_RULE_ADM.ALTER_ON_RULE</code>	Alter a particular rule in another user's schema
<code>SYS.DBMS_RULE_ADM.ALTER_ON_RULE_SET</code>	Alter a particular rule set in another user's schema
<code>SYS.DBMS_RULE_ADM.EXECUTE_ON_EVALUATION_CONTEXT</code>	Execute a particular evaluation context in another user's schema
<code>SYS.DBMS_RULE_ADM.EXECUTE_ON_RULE</code>	Execute a particular rule in another user's schema
<code>SYS.DBMS_RULE_ADM.EXECUTE_ON_RULE_SET</code>	Execute a particular rule set in another user's schema

Examples

For example, to grant the HR user the privilege to alter a rule named `hr_dml` in the `strmadmin` schema, enter the following:

```
BEGIN
  DBMS_RULE_ADM.GRANT_OBJECT_PRIVILEGE(
    privilege    => SYS.DBMS_RULE_ADM.ALTER_ON_RULE,
    object_name  => 'strmadmin.hr_dml',
    grantee      => 'hr',
    grant_option => false);
END;
/
```

GRANT_SYSTEM_PRIVILEGE Procedure

This procedure grant the specified system privilege to the specified user or role.

Syntax

```
DBMS_RULE_ADM.GRANT_SYSTEM_PRIVILEGE(
    privilege      IN  BINARY_INTEGER,
    grantee        IN  VARCHAR2,
    grant_option   IN  BOOLEAN    DEFAULT false);
```

Parameters

Table 82–12 GRANT_SYSTEM_PRIVILEGE Procedure Parameters

Parameter	Description
privilege	The name of the system privilege to grant to the grantee.
grantee	The name of the user or role for which the privilege is granted
grant_option	If <code>true</code> , then the specified user or users granted the specified privilege can grant the system privilege to others. If <code>false</code> , then the specified user or users granted the specified privilege cannot grant the system privilege to others.

Usage Notes

[Table 82–13](#) lists the system privileges.

Table 82–13 System Privileges for Evaluation Contexts, Rules, and Rule Sets

Privilege	Description
<code>SYS.DBMS_RULE_ADM.ALTER_ANY_EVALUATION_CONTEXT</code>	Alter any evaluation context owned by any user
<code>SYS.DBMS_RULE_ADM.ALTER_ANY_RULE</code>	Alter any rule owned by any user
<code>SYS.DBMS_RULE_ADM.ALTER_ANY_RULE_SET</code>	Alter any rule set owned by any user
<code>SYS.DBMS_RULE_ADM.CREATE_ANY_EVALUATION_CONTEXT</code>	Create a new evaluation context in any schema
<code>SYS.DBMS_RULE_ADM.CREATE_EVALUATION_CONTEXT_OBJ</code>	Create a new evaluation context in the grantee's schema
<code>SYS.DBMS_RULE_ADM.CREATE_ANY_RULE</code>	Create a new rule in any schema

Table 82–13 System Privileges for Evaluation Contexts, Rules, and Rule Sets

Privilege	Description
<code>SYS.DBMS_RULE_ADM.CREATE_RULE_OBJ</code>	Create a new rule in the grantee's schema
<code>SYS.DBMS_RULE_ADM.CREATE_ANY_RULE_SET</code>	Create a new rule set in any schema
<code>SYS.DBMS_RULE_ADM.CREATE_RULE_SET_OBJ</code>	Create a new rule set in the grantee's schema
<code>SYS.DBMS_RULE_ADM.DROP_ANY_EVALUATION_CONTEXT</code>	Drop any evaluation context in any schema
<code>SYS.DBMS_RULE_ADM.DROP_ANY_RULE</code>	Drop any rule in any schema
<code>SYS.DBMS_RULE_ADM.DROP_ANY_RULE_SET</code>	Drop any rule set in any schema
<code>SYS.DBMS_RULE_ADM.EXECUTE_ANY_EVALUATION_CONTEXT</code>	Execute any evaluation context owned by any user
<code>SYS.DBMS_RULE_ADM.EXECUTE_ANY_RULE</code>	Execute any rule owned by any user
<code>SYS.DBMS_RULE_ADM.EXECUTE_ANY_RULE_SET</code>	Execute any rule set owned by any user

For example, to grant the `strmadmin` user the privilege to create a rule set in any schema, enter the following:

```
BEGIN
  DBMS_RULE_ADM.GRANT_SYSTEM_PRIVILEGE(
    privilege => SYS.DBMS_RULE_ADM.CREATE_ANY_RULE_SET,
    grantee   => 'strmadmin',
    grant_option => false);
END;
/
```

Note: When you grant a privilege on "ANY" object (for example, `ALTER_ANY_RULE`), and the initialization parameter `O7_DICTIONARY_ACCESSIBILITY` is set to `false`, you give the user access to that type of object in all schemas, except the `SYS` schema. By default, the initialization parameter `O7_DICTIONARY_ACCESSIBILITY` is set to `false`.

If you want to grant access to an object in the `SYS` schema, then you can grant object privileges explicitly on the object. Alternatively, you can set the `O7_DICTIONARY_ACCESSIBILITY` initialization parameter to `true`. Then privileges granted on "ANY" object will allow access to any schema, including `SYS`.

REMOVE_RULE Procedure

This procedure removes the specified rule from the specified rule set.

Syntax

```
DBMS_RULE_ADM.REMOVE_RULE(  
    rule_name           IN VARCHAR2,  
    rule_set_name      IN VARCHAR2,  
    evaluation_context IN VARCHAR2 DEFAULT NULL,  
    all_evaluation_contexts IN BOOLEAN DEFAULT false);
```

Parameters

Table 82–14 REMOVE_RULE Procedure Parameters

Parameter	Description
rule_name	The name of the rule you are removing from the rule set, specified as [<i>schema_name</i> .] <i>rule_name</i> . For example, to remove a rule named <i>all_a</i> in the <i>hr</i> schema, enter <i>hr.all_a</i> for this parameter. If the schema is not specified, then the current user is the default.
rule_set_name	The name of the rule set from which you are removing the rule, specified as [<i>schema_name</i> .] <i>rule_set_name</i> . For example, to remove the rule from a rule set named <i>apply_rules</i> in the <i>hr</i> schema, enter <i>hr.apply_rules</i> for this parameter. If the schema is not specified, then the current user is the default.

Table 82–14 REMOVE_RULE Procedure Parameters

Parameter	Description
<code>evaluation_context_name</code>	<p>The name of the evaluation context associated with the rule you are removing, specified as [<i>schema_name</i>].<i>evaluation_context_name</i>. For example, to specify an evaluation context named <code>dept_eval_context</code> in the <code>hr</code> schema, enter <code>hr.dept_eval_context</code> for this parameter. If the schema is not specified, then the current user is the default.</p> <p>If an evaluation context was specified for the rule you are removing when you added the rule to the rule set using the <code>ADD_RULE</code> procedure, then specify the same evaluation context. If you added the same rule more than once with different evaluation contexts, then specify the rule with the evaluation context you want to remove. If you specify an evaluation context that is not associated with the rule, then an error is raised.</p> <p>Specify <code>NULL</code> if you did not specify an evaluation context when you added the rule to the rule set. If you specify <code>NULL</code> and there are one or more evaluation contexts associated with the rule, then an error is raised.</p>
<code>all_evaluation_contexts</code>	<p>If <code>true</code>, then the rule is removed from the rule set with all of its associated evaluation contexts.</p> <p>If <code>false</code>, then only the rule with the specified evaluation context is removed.</p> <p>This parameter is relevant only if the same rule is added more than once to the rule set with different evaluation contexts.</p>

Usage Notes

To run this procedure, a user must meet at least one of the following requirements:

- Have `ALTER_ON_RULE_SET` privilege on the rule set
- Have `ALTER_ANY_RULE_SET` system privilege
- Be the owner of the rule set

Note: This procedure does not drop a rule from the database. To drop a rule from the database, use the `DROP_RULE` procedure.

REVOKE_OBJECT_PRIVILEGE Procedure

This procedure revokes the specified object privilege on the specified object from the specified user or role.

Syntax

```
DBMS_RULE_ADM.REVOKE_OBJECT_PRIVILEGE(  
    privilege    IN    BINARY_INTEGER,  
    object_name  IN    VARCHAR2,  
    revokee     IN    VARCHAR2);
```

Parameters

Table 82–15 REVOKE_OBJECT_PRIVILEGE Procedure Parameters

Parameter	Description
privilege	The name of the object privilege on the object to revoke from the revokee. See " GRANT_OBJECT_PRIVILEGE Procedure " on page 82-18 for a list of the object privileges.
object_name	The name of the object for which you are revoking the privilege from the revokee, specified as [<i>schema_name</i> .] <i>object_name</i> . For example, to revoke an object privilege on a rule set named <code>apply_rules</code> in the <code>hr</code> schema, enter <code>hr.apply_rules</code> for this parameter. If the schema is not specified, then the current user is the default. The object must be an existing rule, rule set, or evaluation context.
revokee	The name of the user or role from which the privilege is revoked. The user who owns the object cannot be specified.

REVOKE_SYSTEM_PRIVILEGE Procedure

Revokes the specified system privilege from the specified user or role.

Syntax

```
DBMS_RULE_ADM.REVOKE_SYSTEM_PRIVILEGE(  
    privilege IN BINARY_INTEGER,  
    revokee   IN VARCHAR2);
```

Parameters

Table 82–16 *REVOKE_SYSTEM_PRIVILEGE Procedure Parameters*

Parameter	Description
privilege	The name of the system privilege to revoke from the revokee. See " GRANT_SYSTEM_PRIVILEGE Procedure " on page 82-20 for a list of the system privileges.
revokee	The name of the user or role from which the privilege is revoked

DBMS_SCHEDULER

The `DBMS_SCHEDULER` package provides a collection of scheduling functions and procedures that are callable from any PL/SQL program.

See Also: *Oracle Database Administrator's Guide* for more information regarding how to use `DBMS_SCHEDULER`

This chapter contains the following topics:

- [Using DBMS_SCHEDULER](#)
 - [Rules and Limits](#)
- [Summary of DBMS_SCHEDULER Subprograms](#)

Using DBMS_SCHEDULER

- [Rules and Limits](#)

Rules and Limits

The following rules apply when using the DBMS_SCHEDULER package:

- Only SYS can do anything in SYS schema.
- Several of the procedures accept comma-delimited lists of object names. When a list of names is provided, the Scheduler will stop executing the list on the very first object that returns an error. This means that the Scheduler will not perform the task on the objects in the list after the one that caused the error. For example, `DBMS_SCHEDULER.STOP_JOB ('job1, job2, job3, sys.jobclass1, sys.jobclass2, sys.jobclass3');` If job3 could not be stopped, then job1 and job2 will be stopped, but the jobs in jobclass1, jobclass2, and jobclass3 will not be stopped.
- Performing an action on an object that does not exist returns a PL/SQL exception stating that the object does not exist.

Summary of DBMS_SCHEDULER Subprograms

Table 83–1 DBMS_SCHEDULER Package Subprograms

Subprogram	Description
ADD_WINDOW_GROUP_MEMBER Procedure on page 83-6	Adds a window to an existing window group
CLOSE_WINDOW Procedure on page 83-7	Closes an open Scheduler window prematurely
COPY_JOB Procedure on page 83-8	Copies an existing job
CREATE_JOB Procedures on page 83-9	Creates a job
CREATE_JOB_CLASS Procedure on page 83-14	Creates a job class
CREATE_PROGRAM Procedure on page 83-17	Creates a program
CREATE_SCHEDULE Procedure on page 83-20	Creates a schedule
CREATE_WINDOW Procedures on page 83-26	Creates a window
CREATE_WINDOW_GROUP Procedure on page 83-29	Creates a new window group
DEFINE_ANYDATA_ARGUMENT Procedure on page 83-30	Defines a program argument whose value is of a complex type and must be passed encapsulated in an <code>AnyData</code> object
DEFINE_METADATA_ARGUMENT Procedure on page 83-32	Defines a special metadata argument for the program. You can retrieve specific Scheduler metadata through this argument
DEFINE_PROGRAM_ARGUMENT Procedure on page 83-33	Defines a program argument whose value can be passed as a string literal to the program
DISABLE Procedure on page 83-35	Disables a program, job, window, or window group

Table 83–1 (Cont.) DBMS_SCHEDULER Package Subprograms

Subprogram	Description
DROP_JOB Procedure on page 83-38	Drops a job or all jobs in a job class
DROP_JOB_CLASS Procedure on page 83-39	Drops a job class
DROP_PROGRAM Procedure on page 83-40	Drops a program
DROP_PROGRAM_ARGUMENT Procedures on page 83-41	Drops a program argument
DROP_SCHEDULE Procedure on page 83-42	Drops a schedule
DROP_WINDOW Procedure on page 83-43	Drops a window
DROP_WINDOW_GROUP Procedure on page 83-44	Drops a window group
ENABLE Procedure on page 83-45	Enables a program, job, window, or window group
EVALUATE_CALENDAR_STRING Procedure on page 83-46	Evaluates the calendar string and tells you what the next execution date of a job or window will be
GENERATE_JOB_NAME Function on page 83-48	Generates a unique name for a job. This enables you to identify jobs by adding a prefix, so, for example, Sally's jobs would be named <code>sally1</code> , <code>sally2</code> , and so on
GET_ATTRIBUTE Procedure on page 83-49	Retrieves the value of an attribute of a Scheduler object
GET_SCHEDULER_ATTRIBUTE Procedure on page 83-50	Retrieves the value of a Scheduler attribute
OPEN_WINDOW Procedure on page 83-51	Opens a window prematurely. The window is opened immediately for the duration
PURGE_LOG Procedure on page 83-53	Purges specific rows from the job and window logs
REMOVE_WINDOW_GROUP_MEMBER Procedure on page 83-54	Removes a window from an existing window group. This fails if the specified window is not a member of the given group

Table 83–1 (Cont.) DBMS_SCHEDULER Package Subprograms

Subprogram	Description
RESET_JOB_ARGUMENT_VALUE Procedures on page 83-55	Resets the current value assigned to an argument defined with the associated program
RUN_JOB Procedure on page 83-56	Runs a job immediately
SET_ATTRIBUTE Procedure on page 83-58	Changes an attribute of a Scheduler object
SET_ATTRIBUTE_NULL Procedure on page 83-68	Changes an attribute of a Scheduler object to NULL
SET_JOB_ANYDATA_VALUE Procedures on page 83-69	Sets the value of a job argument encapsulated in an AnyData object
SET_JOB_ARGUMENT_VALUE Procedures on page 83-71	Sets the value of a job argument
SET_SCHEDULER_ATTRIBUTE Procedure on page 83-73	Sets the value of a Scheduler attribute
STOP_JOB Procedure on page 83-76	Stops a currently running job or all jobs in a job class

ADD_WINDOW_GROUP_MEMBER Procedure

This procedure adds one or more windows to an existing window group.

Syntax

```
DBMS_SCHEDULER.ADD_WINDOW_GROUP_MEMBER (  
    group_name          IN VARCHAR2,  
    window_list        IN VARCHAR2);
```

Parameters

Table 83–2 ADD_WINDOW_GROUP_MEMBER Procedure Parameters

Parameter	Description
group_name	The name of the window group.
window_list	The name of the window or windows.

Usage Notes

If an already open window is added to a window group, the Scheduler will not pick up jobs that point to this window group until the next window in the window group opens.

Adding a window to a group requires the `MANAGE SCHEDULER` privilege.

Note that a window group cannot be a member of another window group.

CLOSE_WINDOW Procedure

This procedure closes an open window prematurely. A closed window means that it is no longer in effect. When a window is closed, the Scheduler will switch the resource plan to the one that was in effect outside the window or in the case of overlapping windows to another window.

Syntax

```
DBMS_SCHEDULER.CLOSE_WINDOW (  
    window_name          IN VARCHAR2);
```

Parameters

Table 83–3 *CLOSE_WINDOW Procedure Parameters*

Parameter	Description
window_name	The name of the window.

Usage Notes

If you try to close a window that does not exist or is not open, an error is generated.

A job that is running will not stop when the window it is running in closes unless the attribute `stop_on_close` was set to `TRUE` for the job. However, the resources allocated to the job may change because the resource plan may change.

When a running job has a window group as its schedule, the job will not be stopped when its window is closed if another window that is also a member of the same window group then becomes active. This is the case even if the job has the attribute `stop_on_close` set to `TRUE`.

Closing a window requires the `MANAGE SCHEDULER` privilege.

COPY_JOB Procedure

This procedure copies all attributes of an existing job to a new job. The new job is created disabled, while the state of the existing job is unaltered.

Syntax

```
DBMS_SCHEDULER.COPY_JOB (  
    old_job          IN VARCHAR2,  
    new_job         IN VARCHAR2);
```

Parameters

Table 83–4 *COPY_JOB Procedure Parameters*

Parameter	Description
old_job	The name of the existing job.
new_job	The name of the new job.

CREATE_JOB Procedures

This procedure creates a job.

The procedure is overloaded. The different functionality of each form of syntax is presented along with the syntax declaration.

Syntax

Creates a job in a single call without using an existing program or schedule:

```
DBMS_SCHEDULER.CREATE_JOB (
  job_name          IN VARCHAR2,
  job_type          IN VARCHAR2,
  job_action        IN VARCHAR2,
  number_of_arguments IN PLS_INTEGER          DEFAULT 0,
  start_date        IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
  repeat_interval   IN VARCHAR2              DEFAULT NULL,
  end_date          IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
  job_class         IN VARCHAR2              DEFAULT 'DEFAULT_JOB_CLASS',
  enabled           IN BOOLEAN                DEFAULT FALSE,
  auto_drop         IN BOOLEAN                DEFAULT TRUE,
  comments          IN VARCHAR2              DEFAULT NULL);
```

Creates a job using a named schedule object and a named program object:

```
DBMS_SCHEDULER.CREATE_JOB (
  job_name          IN VARCHAR2,
  program_name      IN VARCHAR2,
  schedule_name     IN VARCHAR2,
  job_class         IN VARCHAR2              DEFAULT 'DEFAULT_JOB_CLASS',
  enabled           IN BOOLEAN                DEFAULT FALSE,
  auto_drop         IN BOOLEAN                DEFAULT TRUE,
  comments          IN VARCHAR2              DEFAULT NULL);
```

Creates a job using a named program object and an inlined schedule:

```
DBMS_SCHEDULER.CREATE_JOB (
  job_name          IN VARCHAR2,
  program_name      IN VARCHAR2,
  start_date        IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
  repeat_interval   IN VARCHAR2              DEFAULT NULL,
  end_date          IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
  job_class         IN VARCHAR2              DEFAULT 'DEFAULT_JOB_CLASS',
  enabled           IN BOOLEAN                DEFAULT FALSE,
```

```

auto_drop          IN BOOLEAN          DEFAULT TRUE,
comments          IN VARCHAR2        DEFAULT NULL);

```

Creates a job using a named schedule object and an inlined program or program:

```

DBMS_SCHEDULER.CREATE_JOB (
  job_name          IN VARCHAR2,
  schedule_name    IN VARCHAR2,
  job_type         IN VARCHAR2,
  job_action       IN VARCHAR2,
  number_of_arguments IN PLS_INTEGER  DEFAULT 0,
  job_class        IN VARCHAR2        DEFAULT 'DEFAULT_JOB_CLASS',
  enabled         IN BOOLEAN          DEFAULT FALSE,
  auto_drop       IN BOOLEAN          DEFAULT TRUE,
  comments        IN VARCHAR2        DEFAULT NULL);

```

Parameters

Table 83–5 CREATE_JOB Procedure Parameters

Parameter	Description
job_name	<p>This attribute specifies the name of the job and uniquely identifies the job. The name has to be unique in the SQL namespace. For example, a job cannot have the same name as a table in a schema.</p> <p>If <code>job_name</code> is not specified, an error is generated. If you want to have a name generated by the Scheduler, you can use the <code>GENERATE_JOB_NAME</code> procedure to generate a name and then use the output in the <code>CREATE_JOB</code> procedure. The <code>GENERATE_JOB_NAME</code> procedure call generates a number from a sequence, which is the job name. You can prefix the number with a string. The job name will then be the string with the number from the sequence appended to it. See "GENERATE_JOB_NAME Function" on page 83-48 for more information.</p>

Table 83–5 (Cont.) CREATE_JOB Procedure Parameters(Cont.)

Parameter	Description
job_type	<p>This attribute specifies the type of job that you are creating. If it is not specified, an error is generated. The three supported values are:</p> <p><code>plsql_block</code></p> <p>This specifies that the job is an anonymous PL/SQL block. Job or program arguments are not supported when the job or program type is <code>plsql_block</code>. In this case, the number of arguments must be 0.</p> <p><code>stored_procedure</code></p> <p>This specifies that the job is an external PL/SQL procedure. By reusing PL/SQL's External Procedure feature, this can also be a Java stored procedure or an external C routine.</p> <p><code>executable</code></p> <p>This specifies that the job is a job external to the database. External jobs are anything that can be executed from the operating system's command line. Anydata arguments are not supported with a job or program type of <code>executable</code>.</p>
job_action	<p>This attribute specifies the action of the job. The following actions are possible:</p> <p>For a PL/SQL block, the action is to execute PL/SQL code. These blocks must end with a semi-colon. For example, <code>my_proc();</code> or <code>BEGIN my_proc(); END;</code> or <code>DECLARE arg pls_integer := 10; BEGIN my_proc2(arg); END;</code>. Note that the Scheduler wraps <code>job_action</code> in its own block and passes the following to PL/SQL for execution: <code>DECLARE ... BEGIN job_action END;</code> This is done to declare some internal Scheduler variables.</p> <p>For a stored procedure, the action is the name of the stored procedure. You have to specify the schema if the procedure resides in another schema than the job.</p> <p>PL/SQL functions or procedures with <code>INOUT</code> or <code>OUT</code> arguments are not supported as <code>job_action</code> when the job or program type is <code>stored_procedure</code>.</p> <p>For an executable, the action is the name of the external executable, including the full path name and any command-line arguments.</p> <p>If <code>job_action</code> is not specified, an error is generated when creating the job.</p>

Table 83–5 (Cont.) CREATE_JOB Procedure Parameters(Cont.)

Parameter	Description
number_of_arguments	This attribute specifies the number of arguments that the job expects. The range is 0-255, with the default being 0.
program_name	The name of the program associated with this job.
start_date	<p>This attribute specifies the first date on which this job is scheduled to start. If <code>start_date</code> and <code>repeat_interval</code> are left null, then the job is scheduled to run as soon as the job is enabled.</p> <p>For repeating jobs that use a calendaring expression to specify the repeat interval, <code>start_date</code> is used as a reference date. The first time the job will be scheduled to run is the first match of the calendaring expression that is on or after the current date.</p> <p>The Scheduler cannot guarantee that a job will execute on an exact time because the system may be overloaded and thus resources unavailable.</p>
repeat_interval	<p>This attribute specifies how often the job should repeat. You can specify the repeat interval by using calendaring or PL/SQL expressions.</p> <p>The expression specified is evaluated to determine the next time the job should run. If <code>repeat_interval</code> is not specified, the job will run only once at the specified start date. See Table 83–9 for further information.</p>
schedule_name	The name of the schedule, window, or window group associated with this job.
end_date	<p>This attribute specifies the date after which the job will expire and will no longer be executed. When <code>end_date</code> is reached, the job is disabled. The <code>STATE</code> of the job will be set to <code>COMPLETED</code>, and the <code>enabled</code> flag will be set to <code>FALSE</code>.</p> <p>If no value for <code>end_date</code> is specified, the job will repeat forever unless <code>max_runs</code> or <code>max_failures</code> is set, in which case the job stops when either value is reached.</p> <p>The value for <code>end_date</code> must be after the value for <code>start_date</code>. If it is not, an error is generated when the job is enabled.</p>
job_class	This attribute specifies the job class that the job belongs to. If no job class is specified, then the job is assigned to the default class. Note that the owner of a job must have <code>EXECUTE</code> privileges on a job class in order to run a job using the resources of that class. If an invalid value for <code>job_class</code> is specified, an error is generated.
comments	This attribute specifies a comment about the job. By default, this attribute is <code>NULL</code> .

Table 83–5 (Cont.) CREATE_JOB Procedure Parameters(Cont.)

Parameter	Description
enabled	This attribute specifies whether the job is created enabled or not. The possible settings are <code>TRUE</code> or <code>FALSE</code> . By default, this attribute is set to <code>FALSE</code> and, therefore, the job is created as disabled. A disabled job means that the metadata about the job has been captured and the job exists as a database object but the Scheduler will ignore it and the job coordinator will not pick the job for processing. In order for the job coordinator to process the job, the job has to be enabled. You can enable a job by setting this argument to <code>TRUE</code> or by using the <code>ENABLE</code> procedure.
auto_drop	This flag specifies whether the job will be automatically dropped once it has been executed for non-repeating jobs or when its status is changed to <code>COMPLETED</code> for repeating jobs. The metadata is removed from the database if this flag is set to <code>TRUE</code> . If this flag is set to <code>FALSE</code> , the jobs are not dropped and their metadata is kept until the job is explicitly dropped and can be queried using the <code>*_SCHEDULER_JOBS</code> views. This metadata can be removed from the table using the <code>DROP_JOB</code> procedure. By default, jobs are created with <code>auto_drop</code> set to <code>TRUE</code> .

Usage Notes

Jobs are created disabled by default, thus you must explicitly enable them so they will become active and scheduled.

To create a job in your own schema, you need to have the `CREATE JOB` privilege. A user with the `CREATE ANY JOB` privilege can create a job in any schema.

Associating a job with a particular class or program requires `EXECUTE` privileges for that class.

CREATE_JOB_CLASS Procedure

This procedure creates a job class. Job classes are created in the SYS schema.

Syntax

```
DBMS_SCHEDULER.CREATE_JOB_CLASS (
  job_class_name          IN VARCHAR2,
  resource_consumer_group IN VARCHAR2 DEFAULT NULL,
  service                 IN VARCHAR2 DEFAULT NULL,
  logging_level           IN PLS_INTEGER DEFAULT NULL,
  log_history              IN PLS_INTEGER DEFAULT NULL,
  comments                IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 83–6 CREATE_JOB_CLASS Procedure Parameters

Parameter	Description
job_class_name	<p>The name of the class being created. A schema other than SYS cannot be specified.</p> <p>This attribute specifies the name of the job class and uniquely identifies the job class. The name has to be unique in the SQL namespace. For example, a job class cannot have the same name as a table in a schema.</p>
resource_consumer_group	<p>This attribute specifies the resource consumer group this class is associated with. A resource consumer group is a set of synchronous or asynchronous sessions that are grouped together based on their processing needs. A job class has a many-to-one relationship with a resource consumer group. The resource consumer group that the job class associates with will determine the resources that will be allocated to the job class.</p> <p>If the resource consumer group that a job class is associated with is dropped, the job class will then be associated with the default resource consumer group.</p> <p>If no resource consumer group is specified, the job class is associated with the default resource consumer group.</p> <p>If the specified resource consumer group does not exist when creating the job class, an error occurs.</p> <p>If resource_consumer_group is specified, you cannot specify a service (it must be NULL). Also, if a service is specified, resource_consumer_group must be NULL.</p>

Table 83–6 (Cont.) CREATE_JOB_CLASS Procedure Parameters(Cont.)

Parameter	Description
service	<p>This attribute specifies the service the job class belongs to. The service that a job class belongs to specifies that the jobs in this class will have affinity to the particular service specified. In a RAC environment, this means that the jobs in this class will only run on those database instances that are assigned to the specific service.</p> <p>If the service that a job class belongs to is dropped, the job class will then belong to the default service.</p> <p>If no service is specified, the job class will belong to the default service, which means it will have no service affinity and any one of the database instances within the cluster might run the job.</p> <p>If the specified service does not exist when creating the job class, then an error occurs.</p>
logging_level	<p>This attribute specifies how much information is logged. The three possible options are:</p> <p><code>DBMS_SCHEDULER.LOGGING_OFF</code></p> <p>No logging will be performed for any jobs in this class.</p> <p><code>DBMS_SCHEDULER.LOGGING_RUNS</code></p> <p>The Scheduler will write detailed information to the job log for all runs of each job in this class.</p> <p><code>DBMS_SCHEDULER.LOGGING_FULL</code></p> <p>In addition to recording every run of a job, the Scheduler will record all operations performed on all jobs in this class. In other words, every time a job is created, enabled, disabled, altered, and so on will be recorded in the log.</p>

Table 83–6 (Cont.) CREATE_JOB_CLASS Procedure Parameters(Cont.)

Parameter	Description
log_history	<p>This enables you to control the amount of logging the Scheduler performs. To prevent the job log and the window log from growing indiscriminately, the Scheduler has an attribute that specifies how much history (in days) to keep. Once a day, the Scheduler will automatically purge all log entries from both the job log as well as the window log that are older than the specified history. The default is 30 days.</p> <p>You can change the default by using the <code>SET_SCHEDULER_ATTRIBUTE</code> procedure. For example, to change it to 90 days, issue the following statement:</p> <pre>DBMS_SCHEDULER.SET_SCHEDULER_ATTRIBUTE ('log_history', '90');</pre> <p>The range of valid values is 1 through 999.</p>
comments	<p>This attribute is for an optional comment about the job class. By default, this attribute is <code>NULL</code>.</p>

Usage Notes

For users to create jobs that belong to a job class, the job owner must have `EXECUTE` privileges on the job class. Therefore, after the job class has been created, `EXECUTE` privileges must be granted on the job class so that users create jobs belonging to that class. You can also grant the `EXECUTE` privilege to a role.

Creating a job class requires the `MANAGE SCHEDULER` system privilege.

CREATE_PROGRAM Procedure

This procedure creates a program.

Syntax

```
DBMS_SCHEDULER.CREATE_PROGRAM (
    program_name          IN VARCHAR2,
    program_type          IN VARCHAR2,
    program_action        IN VARCHAR2,
    number_of_arguments  IN PLS_INTEGER DEFAULT 0,
    enabled                IN BOOLEAN DEFAULT FALSE,
    comments               IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 83–7 CREATE_PROGRAM Procedure Parameters

Parameter	Description
program_name	This attribute specifies a unique identifier for the program. The name has to be unique in the SQL namespace. For example, a program cannot have the same name as a table in a schema. If no name is specified, then an error occurs.
program_type	This attribute specifies the type of program you are creating. If it is not specified then you will get an error. There are three supported values for program_type: <p>plsql_block: This specifies that the program is a PL/SQL block. Job or program arguments are not supported when the job or program type is plsql_block. In this case, the number of arguments must be 0.</p> <p>stored_procedure: This specifies that the program is a stored procedure. It can be a PL/SQL, Java, or a C routine outside the database. PL/SQL functions or procedures with INOUT or OUT arguments are not supported as job_action when the job or program type is stored_procedure.</p> <p>executable: This specifies that the program is external to the database. External programs implies anything that can be executed from the operating system's command line. AnyData arguments are not supported with job or program type executable</p>

Table 83–7 (Cont.) CREATE_PROGRAM Procedure Parameters(Cont.)

Parameter	Description
program_action	<p>This attribute specifies the action of the program. The following actions are possible:</p> <p>For a PL/SQL block, the action is to execute PL/SQL code. These blocks must end with a semi-colon. For example, <code>my_proc();</code> or <code>BEGIN my_proc(); END;</code> or <code>DECLARE arg pls_integer := 10; BEGIN my_proc2(arg); END;</code>. Note that the Scheduler wraps <code>job_action</code> in its own block and passes the following to PL/SQL for execution: <code>DECLARE ... BEGIN job_action END;</code> This is done to declare some internal Scheduler variables.</p> <p>For a stored procedure, the action is the name of the stored procedure. You have to specify the schema if the procedure resides in another schema than the job.</p> <p>For an executable, the action is the name of the external executable, including the full path name and any command-line arguments.</p> <p>If <code>program_action</code> is not specified, an error is generated</p> <p>If it is an anonymous block, special Scheduler metadata may be accessed using the following variable names: <code>job_name</code>, <code>job_owner</code>, <code>job_start</code>, <code>window_start</code>, <code>window_end</code>. For more information on these, see the information regarding <code>define_metadata_argument</code>.</p>
number_of_arguments	<p>This attribute specifies the number of arguments the program takes. If this parameter is not specified then the default will be 0. A program can have a maximum of 255 number of arguments.</p> <p>If the <code>program_type</code> is <code>PLSQL_BLOCK</code>, this field is ignored.</p>
enabled	<p>This flag specifies whether the program should be created enabled or not. If the flag is set to <code>TRUE</code>, then validity checks will be made and the program will be created <code>ENABLED</code> should all the checks be successful. By default, this flag is set to <code>FALSE</code>, which means that the program is not created enabled. You can also call the <code>ENABLE</code> procedure to enable the program before it can be used.</p>
comments	<p>A comment about the program. By default, this attribute is <code>NULL</code>.</p>

Usage Notes

To create a program in his own schema, a user needs the `CREATE JOB` privilege. A user with the `CREATE ANY JOB` privilege can create a program in any schema. A program is created in a disabled state by default (unless the `enabled` field is set to `TRUE`). It cannot be executed by a job until it is enabled.

For other users to use your programs, they must have `EXECUTE` privileges, therefore once a program has been created, you have to grant `EXECUTE` privilege on it.

CREATE_SCHEDULE Procedure

This procedure creates a schedule.

Syntax

```
DBMS_SCHEDULER.CREATE_SCHEDULE (
    schedule_name          IN VARCHAR2,
    start_date             IN TIMESTAMP WITH TIMEZONE DEFAULT NULL,
    repeat_interval        IN VARCHAR2,
    end_date               IN TIMESTAMP WITH TIMEZONE DEFAULT NULL,
    comments               IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 83–8 CREATE_SCHEDULE Procedure Parameters

Parameter	Description
schedule_name	This attribute specifies a unique identifier for the schedule. The name has to be unique in the SQL namespace. For example, a schedule cannot have the same name as a table in a schema. If no name is specified, then an error occurs.
start_date	This attribute specifies the first date on which this schedule becomes valid. For a repeating schedule, the value for start_date is a reference date. In this case, the start of the schedule is not the start_date. It depends on the repeat interval specified. start_date is used to determine the first instance of the schedule. If start_date is specified in the past and no value for repeat_interval is specified, the schedule is invalid. For a repeating job or window, start_date can be derived from the repeat_interval, if it is not specified.
repeat_interval	This attribute specifies how often the schedule should repeat. It is expressed using a calendar expression. See Table 83–9 for further information. PL/SQL expressions are not allowed as repeat intervals for named schedules.
end_date	The date after which jobs will not run and windows will not open. A non-repeating schedule that has no end_date will be valid forever. end_date has to be after the start_date. If this is not the case, then an error will be generated when the schedule is created.
comments	This attribute specifies an optional comment about the schedule. By default, this attribute is NULL.

Syntax for repeat_interval

Calendar Syntax The calendaring syntax is as follows:

```
repeat_interval = frequency_clause
[";" interval_clause] [";" bymonth_clause] [";" byweekno_clause]
[";" byyearday_clause] [";" bymonthday_clause] [";" byday_clause]
[";" byhour_clause] [";" byminute_clause] [";" bysecond_clause]

frequency_clause = "FREQ" "=" frequency
frequency = "YEARLY" | "MONTHLY" | "WEEKLY" | "DAILY" |
"HOURLY" | "MINUTELY" | "SECONDLY"
interval_clause = "INTERVAL" "=" intervalnum
intervalnum = 1 through 99
bymonth_clause = "BYMONTH" "=" monthlist
monthlist = monthday ( "," monthday) *
month = numeric_month | char_month
numeric_month = 1 | 2 | 3 ... 12
char_month = "JAN" | "FEB" | "MAR" | "APR" | "MAY" | "JUN" |
"JUL" | "AUG" | "SEP" | "OCT" | "NOV" | "DEC"
byweekno_clause = "BYWEEKNO" "=" weeknumber_list
weeknumber_list = weekday ( "," weeknumber)*
week = [minus] weekno
minus = "-"
weekno = 1 through 53
byyearday_clause = "BYYEARDAY" "=" yearday_list
yearday_list = yearday ( "," yearday)*
yearday = [minus] yeardaynum
yeardaynum = 1 through 366
bymonthday_clause = "BYMONTHDAY" "=" monthday_list
monthday_list = monthday ( "," monthday) *
monthday = [minus] monthdaynum
monthdaynum = 1 through 31
byday_clause = "BYDAY" "=" byday_list
byday_list = byday ( "," byday)*
byday = [weekdaynum] day
weekdaynum = [minus] daynum
daynum = 1 through 53 /* if frequency is yearly */
daynum = 1 through 5 /* if frequency is monthly */
day = "MON" | "TUE" | "WED" | "THU" | "FRI" | "SAT" | "SUN"
byhour_clause = "BYHOUR" "=" hour_list
hour_list = hour ( "," hour)*
hour = 0 through 23
byminute_clause = "BYMINUTE" "=" minute_list
minute_list = minute ( "," minute)*
```

```

minute = 0 through 59
bysecond_clause = "BYSECOND" "=" second_list
second_list = second ( " ," second)*
second = 0 through 59

```

In calendaring syntax, * means 0 or more.

Table 83–9 Values for repeat_interval

Name	Description
freq	This specifies the type of recurrence. It must be specified. The possible values are YEARLY, MONTHLY, WEEKLY, DAILY, HOURLY, MINUTELY, and SECONDLY.
interval	This specifies a positive integer representing how often the recurrence repeats. The default is 1, which means every second for secondly, every day for daily, and so on. The maximum value is 999.
bymonth	This specifies which month or months you want the job to execute in. You can use numbers such as 1 for January and 3 for March, as well as three-letter abbreviations such as FEB for February and JUL for July.
byweekno	This specifies the week of the year as a number. It follows ISO-8601, which defines the week as starting with Monday and ending with Sunday; and the first week of a year as the first week, which is mostly within the Gregorian year. That last definition is equivalent to the following two variants: the week that contains the first Thursday of the Gregorian year; and the week containing January 4th. The ISO-8601 week numbers are integers from 1 to 52 or 53; parts of week 1 may be in the previous calendar year; parts of week 52 may be in the following calendar year; and if a year has a week 53, parts of it must be in the following calendar year. As an example, in the year 1998 the ISO week 1 began on Monday December 29th, 1997; and the last ISO week (week 53) ended on Sunday January 3rd, 1999. So December 29th, 1997, is in the ISO week 1998-01; and January 1st, 1999, is in the ISO week 1998-53. byweekno is only valid for YEARLY. Examples of invalid specifications are "FREQ=YEARLY; BYWEEKNO=1; BYMONTH=12" and "FREQ=YEARLY; BYWEEKNO=53; BYMONTH=1".
byyearday	This specifies the day of the year as a number. Valid values are 1 to 366. An example is 69, which is March 10 (31 for January, 28 for February, and 10 for March). 69 evaluates to March 10 for non-leap years and March 9 in leap years. -2 will always evaluate to December 30th independent of whether it is a leap year.

Table 83–9 (Cont.) Values for repeat_interval

Name	Description
bymonthday	This specifies the day of the month as a number. Valid values are 1 to 31. An example is 10, which means the 10th day of the selected month. You can use the minus sign (-) to count backward from the last day, so, for example, <code>BYMONTHDAY=-1</code> means the last day of the month and <code>BYMONTHDAY=-2</code> means the next to last day of the month.
byday	This specifies the day of the week from Monday to Sunday in the form MON, TUE, and so on. Using numbers, you can specify the 26th Friday of the year, if using a YEARLY frequency, or the 4th THU of the month, using a MONTHLY frequency. Using the minus sign, you can say the second to last Friday of the month. For example, <code>-1 FRI</code> is the last Friday of the month.
byhour	This specifies the hour on which the job is to run. Valid values are 0 to 23. As an example, 10 means 10AM.
byminute	This specifies the minute on which the job is to run. Valid values are 0 to 59. As an example, 45 means 45 minutes past the chosen hour.
bysecond	This specifies the second on which the job is to run. Valid values are 0 to 59. As an example, 30 means 30 seconds past the chosen minute.

Usage Notes

This procedure requires the `CREATE JOB` privilege to create a schedule in one's own schema or the `CREATE ANY JOB` privilege to create a schedule in someone else's schema by specifying `schema.schedule_name`. Once a schedule has been created, it can be used by other users. The schedule is created with access to `PUBLIC`. Therefore, there is no need to explicitly grant access to the schedule.

repeat_interval

When using a calendaring expression, consider the following rules:

- The calendar string must start with the frequency clause. All other clauses are optional and can be put in any order.
- All clauses are separated by a semi-colon and each clause can be present at most once.
- Spaces are allowed between syntax elements and the strings are case insensitive.
- The list of values for a specific `BY` clause do not need to be ordered.

- When not enough **BY** clauses are present to determine what the next date is, this information is retrieved from the start date. For example, "FREQ=YEARLY" with a start date of 02/15/2003 becomes "FREQ=YEARLY;BYMONTH=FEB;BYMONTHDAY=15", which means every year on the 15th of February.

"FREQ=YEARLY;BYMONTH=JAN,JUL" with start date 01/21/2003 becomes "FREQ=YEARLY;BYMONTH=JAN,JUL;BYMONTHDAY=21", which means every year on January 21 and July 21.

- The **byweekno** clause is only allowed if the frequency is **YEARLY**. It cannot be used with other frequencies. When it is present, it will return all days in that week number. If you want to limit it to specific days within the week, you have to add a **BYDAY** clause. For example, "FREQ=YEARLY;BYWEEKNO=2" with a start date of 01/01/2003 will return:

01/06/2003, 01/07/2003, 01/08/2003, 01/09/2003, 01/10/2003, 01/11/2003,
01/12/2003, 01/05/2004, 01/06/2004, 01/07/2004, and so on.

Note that when the **byweekno** clause is used, it is possible that the dates returned are from a year other than the current year. For example, if returning dates for the year 2004 and the calendar string is

"FREQ=YEARLY;BYWEEKNO=1,53" for the specified week numbers in 2004, it will return the dates:

12/29/03, 12/30/03, 12/31/03, 01/01/04, 01/02/04, 01/03/04, 01/04/04,
12/27/04, 12/28/04, 12/29/04, 12/30/04, 12/31/04, 01/01/05, 01/02/05

- For those **BY** clauses that do not have a consistent range of values, you can count backward by putting a "-" in front of the numeric value. For example, specifying **BYMONTHDAY=31** will not give you the last day of every month, because not every month has 31 days. Instead, **BYMONTHDAY=-1** will give you the last day of the month.

This is not supported for **BY** clauses that are fixed in size. In other words, **bymonth**, **byhour**, **byminute**, and **bysecond** are not supported.

- The basic values for the **byday** clause are the days of the week. When the frequency is **YEARLY**, or **MONTHLY**, you are allowed to specify a positive or negative number in front of each day of the week. In the case of **YEARLY**, **BYDAY=40MON**, indicates the 40th Monday of the year. In the case of **MONTHLY**, **BYDAY=-2SAT**, indicates the second to last Saturday of the month.

Note that positive or negative numbers in front of the weekdays are not supported for other frequencies and that in the case of yearly, the number

ranges from -53 ... -1, 1 ... 53, whereas for the monthly frequency it is limited to -5 ... -1, 1... 5.

If no number is present in front of the weekday it specifies, every occurrence of that weekday in the specified frequency.

- The first day of the week is Monday.
- The calendaring syntax does not allow you to specify a time zone. Instead the scheduler retrieves the time zone from the `start_date` argument. If jobs must follow daylight savings adjustments you must make sure that you specify a region name for the time zone of the `start_date`. For example specifying the `start_date` time zone as 'US/Eastern' in New York will make sure that daylight saving adjustments are automatically applied. If instead the time zone of the `start_date` is set to an absolute offset, such as '-5:00', daylight savings adjustments are not followed and your job execution will be off by an hour half of the year.
- When `start_date` is NULL, the scheduler will determine the time zone for the repeat interval as follows:
 1. It will check whether the session time zone is a region name. The session time zone can be set by either:
 - - issuing an ALTER SESSION statement, for example:

```
SQL> ALTER SESSION SET time_zone = 'Asia/Shanghai';
```
 - - or by setting the ORA_SDTZ environment variable.
 2. If the session time zone is an absolute offset instead of a region name, the scheduler will use the value of the DEFAULT_TIMEZONE scheduler attribute. For more information see the [SET_SCHEDULER_ATTRIBUTE Procedure](#).
 3. If the DEFAULT_TIMEZONE attribute is NULL, the scheduler will use the time zone of systimestamp when the job or window is enabled.

CREATE_WINDOW Procedures

This procedure creates a Scheduler window consisting of a recurring time window and an associated resource plan.

The procedure is overloaded. The different functionality of each form of syntax is presented along with the syntax declaration.

Syntax

Creates a window using a named schedule object:

```
DBMS_SCHEDULER.CREATE_WINDOW (
    window_name          IN VARCHAR2,
    resource_plan        IN VARCHAR2,
    schedule_name        IN VARCHAR2,
    duration              IN INTERVAL DAY TO SECOND,
    window_priority      IN VARCHAR2          DEFAULT 'LOW',
    comments              IN VARCHAR2          DEFAULT NULL);
```

Creates a window using an inlined schedule:

```
DBMS_SCHEDULER.CREATE_WINDOW (
    window_name          IN VARCHAR2,
    resource_plan        IN VARCHAR2,
    start_date           IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
    repeat_interval      IN VARCHAR2,
    end_date             IN TIMESTAMP WITH TIME ZONE DEFAULT NULL,
    duration             IN INTERVAL DAY TO SECOND,
    window_priority      IN VARCHAR2          DEFAULT 'LOW',
    comments             IN VARCHAR2          DEFAULT NULL);
```

Parameters

Table 83–10 CREATE_WINDOW Procedure Parameters

Parameter	Description
window_name	This attribute uniquely identifies the window, and is of the form [SYS.]name. The name has to be unique in the SQL namespace, thus no other database object should have the same name.

Table 83–10 (Cont.) CREATE_WINDOW Procedure Parameters(Cont.)

Parameter	Description
resource_plan	<p>This attribute specifies the resource plan. When creating a window, a resource plan enables you to specify how resources will be allocated among the various job classes during this window by associating a resource plan with it. When the window opens, the system switches to the specified resource plan. When the window closes, the system switches to the appropriate resource plan. In most cases, this is the resource plan that was in effect before the window opened, but it can also be the resource plan of yet another window.</p> <p>Besides using windows to automatically switch resource plans, you can also manually activate a plan by using the <code>ALTER SYSTEM SET RESOURCE_MANAGER_PLAN</code> statement. For certain emergency scenarios, you do not want the Scheduler to switch resource plans. When the preceding statement is used with the <code>force</code> option, the Scheduler will not be allowed to switch resource plans. It will still attempt to do so, but a runtime error will be written to the window log.</p> <p>Only one resource plan can be associated with a window. If no resource plan is associated with the window during its creation, the resource plan that is in effect when the window opens will stay in effect for the duration of the window.</p> <p>If the window is open and the resource plan is dropped, then the resource allocation for the duration of the window is not affected.</p> <p>A runtime error will occur when a window is about to open and the resource plan associated with this window has been dropped.</p>
start_date	<p>This attribute specifies the first date on which this window is scheduled to open. If the value for <code>start_date</code> specified is in the past or is not specified, the window opens as soon as it is created.</p> <p>For repeating windows that use a calendaring expression to specify the repeat interval, the value for <code>start_date</code> is a reference date. The first time the window opens depends on the repeat interval specified and the value for <code>start_date</code>.</p>
duration	<p>This attribute specifies how long the window will be open for. For example, 'interval '5' hour' for five hours. There is no default value for this attribute. Therefore, if none is specified when creating the window, an error occurs. The duration is of type interval day to seconds and ranges from one minute to 99 days.</p>
schedule_name	<p>The name of the schedule associated with the window.</p>

Table 83–10 (Cont.) CREATE_WINDOW Procedure Parameters(Cont.)

Parameter	Description
repeat_interval	<p>This attribute specifies how often the window should repeat. It is expressed using the Scheduler's calendaring syntax.</p> <p>A PL/SQL expression cannot be used to specify the repeat interval for a window.</p> <p>The expression specified is evaluated to determine the next time the window should open. If no repeat_interval is specified, the window will open only once at the specified start date.</p>
end_date	<p>This attribute specifies the date after which the window will no longer open. When the value for end_date is reached, the window is disabled. In the *_SCHEDULER_WINDOWS views, the enabled flag of the window will be set to FALSE.</p> <p>A non-repeating window that has no value for end_date opens only once for the duration of the window. For a repeating window, if no end_date is specified then the window will keep repeating forever.</p> <p>The end_date has to be after the start_date. If this is not the case, then an error is generated when the window is created.</p>
window_priority	<p>This attribute is only relevant when two windows overlap. Because only one window can be in effect at one time, the window priority will be used to determine which window will be opened. The two possible values for this attribute are high and low. A high priority window has precedence over a low priority window, which implies that the low priority window does not open if it overlaps with a high priority window. By default, a window is created with a priority of low.</p>
comments	<p>This attribute specifies an optional comment about the window. By default, this attribute is NULL.</p>

Usage Notes

Creating a window requires the `MANAGE SCHEDULER` privilege. Windows always reside in the `SYS` schema.

CREATE_WINDOW_GROUP Procedure

This procedure creates a new window group.

Syntax

```
DBMS_SCHEDULER.CREATE_WINDOW_GROUP (
    group_name          IN VARCHAR2,
    window_list        IN VARCHAR2 DEFAULT NULL,
    comments            IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 83–11 CREATE_WINDOW_GROUP Procedure Parameters

Parameter	Description
group_name	The name of the window group.
window_list	A list of the windows assigned to the window group. If a window that does not exist is specified then, an error is generated and the window group is not created. Windows can also be added using the ADD_WINDOW_GROUP_MEMBER procedure. A window group cannot be a member of another window group. Can be NULL.
comments	A comment about the window group.

Usage Notes

Creating a window group requires the `MANAGE SCHEDULER` privilege. Window groups reside in the `SYS` schema. Window groups, like windows, are created with access to `PUBLIC`, therefore, no privileges are required to access window groups.

A window group cannot contain another window group

DEFINE_ANYDATA_ARGUMENT Procedure

This procedure defines a program argument whose value is of a complex type and must be encapsulated within an AnyData object.

Syntax

```
DBMS_SCHEDULER.DEFINE_ANYDATA_ARGUMENT (
    program_name          IN VARCHAR2,
    argument_position     IN PLS_INTEGER,
    argument_name         IN VARCHAR2 DEFAULT NULL,
    argument_type         IN VARCHAR2,
    default_value         IN SYS.ANYDATA,
    out_argument          IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–12 *DEFINE_ANYDATA_ARGUMENT Procedure Parameters*

Parameter	Description
program_name	The name of the program to be altered. A program with this name must exist.
argument_name	The name of the argument being set. It is optional, but must be unique if it is specified, so no other argument must exist with this name for this program if it is non-NULL.
argument_position	This specifies the position of the argument when it is being passed to the executable, and is required. Argument numbers go from one up to the number_of_arguments specified for the program. This must be unique, so it will replace any argument already defined at this position.
argument_type	The type of argument being defined. This is not verified or used by the Scheduler. It is only used by the user of the program when deciding what value to assign to the argument.
default_value	The default value to be assigned to the argument encapsulated within an AnyData object. This is optional.
out_argument	This parameter is reserved for future use. It must be set to FALSE.

Usage Notes

Defining a program argument requires that you be the owner of the program or have `ALTER` privileges on that program. You can also define a program argument if you have the `CREATE ANY JOB` privilege.

DEFINE_METADATA_ARGUMENT Procedure

This procedure defines a special metadata argument for the program. You can retrieve specific Scheduler metadata through this argument. You cannot set values for jobs using this argument. Valid metadata attributes are: `job_name`, `job_owner`, `job_start`, `window_start`, and `window_end`.

Syntax

```
DBMS_SCHEDULER.DEFINE_METADATA_ARGUMENT (
    program_name          IN VARCHAR2,
    metadata_attribute    IN VARCHAR2,
    argument_position     IN PLS_INTEGER,
    argument_name         IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 83–13 *DEFINE_METADATA_ARGUMENT Procedure Parameters*

Parameter	Description
<code>program_name</code>	The name of the program to be altered.
<code>metadata_attribute</code>	The metadata to be retrieved.
<code>argument_position</code>	Specifies the position of the argument when it is being passed to the executable, and is required. This cannot be greater than the <code>number_of_arguments</code> specified for the program. This must be unique, so it will replace any argument already defined at this position.
<code>argument_name</code>	The name of the argument being set. It is optional. This must be unique if it is specified, so no other argument must exist with this name for this program if it is non-NULL.

Usage Notes

Defining a program argument requires that you be the owner of the program or have `ALTER` privileges on that program. You can also define a program argument if you have the `CREATE ANY JOB` privilege.

DEFINE_PROGRAM_ARGUMENT Procedure

This procedure defines program arguments. This does not affect whether a program is enabled or not. Defining a program argument can be used to assign a default value or a name to the argument.

This procedure is overloaded. The different functionality of each form of syntax is presented along with the syntax declaration.

Syntax

Defines a program argument with a default value:

```
PROCEDURE define_program_argument(
    program_name          IN VARCHAR2,
    argument_position     IN PLS_INTEGER,
    argument_name         IN VARCHAR2 DEFAULT NULL,
    argument_type         IN VARCHAR2,
    out_argument          IN BOOLEAN DEFAULT FALSE);
```

Defines a program argument without a default value:

```
PROCEDURE define_anydata_argument(
    program_name          IN VARCHAR2,
    argument_position     IN PLS_INTEGER,
    argument_name         IN VARCHAR2 DEFAULT NULL,
    argument_type         IN VARCHAR2,
    default_value         IN SYS.ANYDATA,
    out_argument          IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–14 *DEFINE_PROGRAM_ARGUMENT Procedure Parameters*

Parameter	Description
program_name	The name of the program to be altered. A program with this name must exist.
argument_name	The name of the argument being set. It is optional, but must be unique if it is specified, so no other argument must exist with this name for this program if it is non-NULL.

Table 83–14 (Cont.) DEFINE_PROGRAM_ARGUMENT Procedure Parameters

Parameter	Description
<code>argument_position</code>	This specifies the position of the argument when it is being passed to the executable, and is required. Argument numbers go from one up to the <code>number_of_arguments</code> specified for the program. This must be unique so it will replace any argument already defined at this position.
<code>argument_type</code>	The type of argument being defined. This is not verified or used by the Scheduler. It is only used by the user of the program when deciding what value to assign to the argument.
<code>default_value</code>	The default value to be assigned to the argument if none is specified by the job.
<code>out_argument</code>	This parameter is reserved for future use. It must be set to <code>FALSE</code> .

Usage Notes

All program arguments from 1 to the `number_of_arguments` value must be defined before a program can be enabled.

Defining a program argument requires that you be the owner of the program or have `ALTER` privileges on that program. You can also define a program argument if you have the `CREATE ANY JOB` privilege.

DISABLE Procedure

This procedure disables a program, job, window, or window group.

Syntax

```
DBMS_SCHEDULER.DISABLE (
    name          IN VARCHAR2,
    force         IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–15 *DISABLE Procedure Parameters*

Parameter	Description
name	<p>The name of the object being disabled. Can be a comma-delimited list.</p> <p>If a job class name is specified, then all the jobs in the job class are disabled. The job class is not disabled.</p> <p>If a window group name is specified, then the window group will be disabled, but the windows that are members of the window group, will not be disabled.</p>
force	Whether to ignore dependencies. See preceding notes for more information.

Usage Notes

Disabling an object that is already disabled does not generate an error. Because the `DISABLE` procedure is used for several Scheduler objects, when disabling windows and window groups, they must be preceded by `SYS`.

The purpose of the `force` option is to point out dependencies. No dependent objects are altered.

To run `DISABLE` for a window or window group, you must have the `MANAGE SCHEDULER` privilege. Otherwise, you must be the owner of the object being disabled or have `ALTER` privileges on that object or have the `CREATE ANY JOB` privilege.

Job

Disabling a job means that, although the metadata of the job is there, it should not run and the job coordinator will not pick up these jobs for processing. When a job is disabled, its `state` in the job queue is changed to `disabled`.

If `force` is set to `FALSE` and the job is currently running, an error is returned.

If `force` is set to `TRUE`, the job is disabled, but the currently running instance is allowed to finish.

Program

When a program is disabled, the status is changed to `disabled`. A disabled program implies that, although the metadata is still there, jobs that point to this program cannot run.

If `force` is set to `FALSE`, the program must be unreferenced by any job otherwise an error will occur.

If `force` is set to `TRUE`, those jobs that point to the program will not be disabled, however, they will fail at runtime because their program will not be valid.

Running jobs that point to the program are not affected by the `DISABLE` call, and are allowed to continue

Any argument that pertains to the program will not be affected when the program is disabled.

Window

This means that the window will not open, however, the metadata of the window is still there, so it can be reenabled.

If `force` is set to `FALSE`, the window must not be open or referenced by any job otherwise an error will occur.

If `force` is set to `TRUE`, disabling a window that is open will succeed but the window will not be closed. It will prevent the window from opening in the future until it is re-enabled.

When the window is disabled, those jobs that have the window as their schedule will not be disabled.

Window Group

When a window group is disabled, jobs, other than a running job, that has the window group as its schedule will not run even if the member windows open.

However, if the job had one of the window group members as its schedule, it would still run.

The metadata of the window group is still there, so it can be reenabled. Note that the members of the window group will still open.

If `force` is set to `FALSE`, the window group must not have any members that are open or referenced by any job otherwise an error will occur.

If `force` is set to `TRUE`:

- The window group is disabled and the open window will be not closed or disabled. It will be allowed to continue to its end.
- The window group is disabled but those jobs that have the window group as their schedule will not be disabled.

DROP_JOB Procedure

This procedure drops a job or all jobs in a job class. It results in the job being removed from the job queue, its metadata being removed, and no longer being visible in the *_SCHEDULER_JOBS views. Therefore, no more runs of the job will be executed. Dropping a job also drops all argument values set for that job.

Syntax

```
DBMS_SCHEDULER.DROP_JOB (  
    job_name          IN VARCHAR2,  
    force             IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–16 *DROP_JOB Procedure Parameters*

Parameter	Description
job_name	The name of a job or job class. Can be a comma-delimited list. For a job class, the SYS schema should be specified. If the name of a job class is specified, the jobs that belong to that job class are dropped, but the job class itself is not dropped.
force	If <i>force</i> is set to FALSE, and an instance of the job is running at the time of the call, the call results in an error. If <i>force</i> is set to TRUE, the Scheduler attempts to first stop (issues the STOP_JOB call) the running job instance and then drop the job.

DROP_JOB_CLASS Procedure

This procedure drops a job class. Dropping a job class means that all the metadata about the job class is removed from the database.

Syntax

```
DBMS_SCHEDULER.DROP_JOB_CLASS (
    job_class_name      IN VARCHAR2,
    force               IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–17 vDROP_JOB_CLASS Procedure Parameters

Parameter	Description
<code>job_class_name</code>	The name of the job class. Can be a comma-delimited list.
<code>force</code>	<p>If <code>force</code> is set to <code>FALSE</code>, a class must be unreferenced by any jobs to be dropped otherwise an error will occur.</p> <p>If <code>force</code> is set to <code>TRUE</code>, jobs belonging to the class are disabled and their class is set to the default class. Only if this is successful will the class be dropped.</p> <p>Running jobs that belong to the job class are not affected.</p>

Usage Notes

Dropping a class requires the `MANAGE SCHEDULER` system privilege.

`DROP_JOB` requires that you be the owner of the job or have `ALTER` privileges on that job. You can also drop a job if you have the `CREATE ANY JOB` privilege.

DROP_PROGRAM Procedure

This procedure drops a program. Any arguments that pertain to the program are also dropped when the program is dropped.

Syntax

```
DBMS_SCHEDULER.DROP_PROGRAM (  
    program_name          IN VARCHAR2,  
    force                 IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–18 *DROP_PROGRAM Procedure Parameters*

Parameter	Description
program_name	The name of the program to be dropped. Can be a comma-delimited list.
force	If <i>force</i> is set to <code>FALSE</code> , the program must be unreferenced by any job otherwise an error will occur. If <i>force</i> is set to <code>TRUE</code> , all jobs referencing the program are disabled before dropping the program. Running jobs that point to the program are not affected by the <code>DROP_PROGRAM</code> call, and are allowed to continue.

Usage Notes

Dropping a program requires that you be the owner of the program or have `ALTER` privileges on that program. You can also drop a program if you have the `CREATE ANY JOB` privilege.

DROP_PROGRAM_ARGUMENT Procedures

This procedure drops a program argument. An argument can be specified by either name (if one has been given) or position.

The procedure is overloaded. The different functionality of each form of syntax is presented along with the syntax declaration.

Syntax

Drops a program argument either by position:

```
DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT (
    program_name          IN VARCHAR2,
    argument_position     IN PLS_INTEGER);
```

Drops a program argument either by name:

```
DBMS_SCHEDULER.DROP_PROGRAM_ARGUMENT (
    program_name          IN VARCHAR2,
    argument_name         IN VARCHAR2);
```

Parameters

Table 83–19 *DROP_PROGRAM_ARGUMENT Procedure Parameters*

Parameter	Description
program_name	The name of the program to be altered. A program with this name must exist.
argument_name	The name of the argument being dropped.
argument_position	The position of the argument to be dropped.

Usage Notes

Dropping a program argument requires that you be the owner of the program or have ALTER privileges on that program. You can also define a program argument if you have the CREATE ANY JOB privilege.

DROP_SCHEDULE Procedure

This procedure drops a schedule.

Syntax

```
DBMS_SCHEDULER.DROP_SCHEDULE (  
    schedule_name    IN VARCHAR2,  
    force            IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–20 *DROP_SCHEDULE Procedure Parameters*

Parameter	Description
<code>schedule_name</code>	The name of the schedule. Can be a comma-delimited list.
<code>force</code>	If <code>force</code> is set to <code>FALSE</code> , the schedule must be unreferenced by any job or window otherwise an error will occur. If <code>force</code> is set to <code>TRUE</code> , any jobs or windows that use this schedule will be disabled before the schedule is dropped Running jobs and open windows that point to the schedule are not affected.

Usage Notes

You must be the owner of the schedule being dropped or have `ALTER` privileges for the schedule or the `CREATE ANY JOB` privilege.

DROP_WINDOW Procedure

This procedure drops a window. All metadata about the window is removed from the database. All references to the window are removed from window groups.

Syntax

```
DBMS_SCHEDULER.DROP_WINDOW (
    window_name          IN VARCHAR2,
    force                IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–21 *DROP_WINDOW Procedure Parameters*

Parameter	Description
window_name	The name of the window. Can be a comma-delimited list.
force	<p>If <code>force</code> is set to <code>FALSE</code>, the window must not be open or referenced by any job otherwise an error will occur.</p> <p>If <code>force</code> is set to <code>TRUE</code>, the window will be dropped and those jobs that have the window as their schedule will be disabled. However, jobs that have a window group of which the dropped window was a member as their schedule will not be disabled. If the window is open then, the Scheduler attempts to first close the window and then drop it. When the window is closed, normal close window rules apply.</p> <p>Running jobs that have the window as their schedule will be allowed to continue, unless the <code>stop_on_window_close</code> flag was set to <code>TRUE</code> for the job. If this is the case, the job will be stopped when the window is dropped.</p>

Usage Notes

Dropping a window requires the `MANAGE SCHEDULER` privilege.

DROP_WINDOW_GROUP Procedure

This procedure drops a window group but not the windows that are members of this window group.

Syntax

```
DBMS_SCHEDULER.DROP_WINDOW_GROUP (  
    group_name          IN VARCHAR2  
    force               IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–22 *DROP_WINDOW_GROUP Procedure Parameters*

Parameter	Description
group_name	The name of the window group.
force	<p>If <code>force</code> is set to <code>FALSE</code>, the window group must be unreferenced by any job otherwise an error will occur.</p> <p>If <code>force</code> is set to <code>TRUE</code>, the window group will be dropped and those jobs that have the window group as their schedule will be disabled. Running jobs that have the window group as their schedule are allowed to continue, even if the <code>stop_on_window_close</code> flag was set to <code>TRUE</code> when for the job.</p> <p>If a member of the window group that is being dropped is open, the window group can still be dropped.</p>

Usage Notes

If you want to drop all the windows that are members of this group but not the window group itself, you can use the `DROP_WINDOW` procedure and provide name of the window group to the call.

To drop a window group, you must have the `MANAGE SCHEDULER` privilege.

ENABLE Procedure

This procedure enables a program, job, window, or window group. When an object is enabled, the enabled flag is set to `TRUE`. By default, jobs and programs are created disabled and windows and window groups are created enabled.

Validity checks are performed before enabling an object. If the check fails, the object is not enabled, and an appropriate error is returned. This procedure does not return an error if the object was already enabled.

Syntax

```
DBMS_SCHEDULER.ENABLE (
    name                IN VARCHAR2);
```

Parameters

Table 83–23 *ENABLE Procedure Parameters*

Parameter	Description
name	<p>The name of the Scheduler object being enabled. Can be a comma-delimited list.</p> <p>If a job class name is specified, then all the jobs in the job class are enabled.</p> <p>If a window group name is specified, then the window group will be enabled, but the windows that are members of the window group, will not be enabled.</p>

Usage Notes

Because the `ENABLE` procedure is used for several Scheduler objects, when enabling windows or window groups, they must be preceded by `SYS`.

To run `ENABLE` for a window or window group, you must have the `MANAGE SCHEDULER` privilege. Otherwise, you must be the owner of the object being enabled or have `ALTER` privileges on that object or have the `CREATE ANY JOB` privilege.

EVALUATE_CALENDAR_STRING Procedure

You can define repeat intervals of jobs, windows or schedules using the Scheduler's calendar syntax. This procedure evaluates the calendar string and tells you what the next execution date of a job or window will be. This is very useful for testing the correct definition of the calendar string without having to actually schedule the job or window.

This procedure can also be used to get multiple steps of the repeat interval by passing the `next_run_date` returned by one invocation as the `return_date_after` argument of the next invocation of this procedure.

Syntax

```
DBMS_SCHEDULER.EVALUATE_CALENDAR_STRING (
    calendar_string    IN  VARCHAR2,
    start_date         IN  TIMESTAMP WITH TIME ZONE,
    return_date_after  IN  TIMESTAMP WITH TIME ZONE,
    next_run_date      OUT TIMESTAMP WITH TIME ZONE);
```

Parameters

Table 83–24 *EVALUATE_CALENDAR_STRING Procedure Parameters*

Parameter	Description
<code>calendar_string</code>	The calendar string to be evaluated.
<code>start_date</code>	The date after which the repeat interval becomes valid. It can also be used to fill in specific items that are missing from the calendar string. Can optionally be <code>NULL</code> .
<code>return_date_after</code>	With the <code>start_date</code> and the calendar string, the Scheduler has sufficient information to determine all valid execution dates. By setting this argument, the Scheduler knows which one of all possible matches to return. When a <code>NULL</code> value is passed for this argument, the Scheduler automatically fills in <code>sys_timestamp</code> as its value.
<code>next_run_date</code>	The first timestamp that matches the calendar string and start date that occurs after the value passed in for the <code>return_date_after</code> argument.

Examples

The following code fragment can be used to determine the next five dates a job will run given a specific calendar string.

```
SET SERVEROUTPUT ON;
ALTER SESSION set NLS_DATE_FORMAT = 'DD-MON-YYYY HH24:MI:SS';

Session altered.

DECLARE
start_date          TIMESTAMP;
return_date_after  TIMESTAMP;
next_run_date      TIMESTAMP;
BEGIN
start_date :=
    to_timestamp_tz('01-JAN-2003 10:00:00','DD-MON-YYYY HH24:MI:SS');
return_date_after := start_date;
FOR i IN 1..5 LOOP
    DBMS_SCHEDULER.EVALUATE_CALENDAR_STRING(
        'FREQ=DAILY;BYHOUR=9;BYMINUTE=30;BYDAY=MON,TUE,WED,THU,FRI',
        start_date, return_date_after, next_run_date);
    DBMS_OUTPUT.PUT_LINE('next_run_date: ' || next_run_date);
    return_date_after := next_run_date;
END LOOP;
END;
/

next_run_date: 02-JAN-03 09.30.00.000000 AM
next_run_date: 03-JAN-03 09.30.00.000000 AM
next_run_date: 06-JAN-03 09.30.00.000000 AM
next_run_date: 07-JAN-03 09.30.00.000000 AM
next_run_date: 08-JAN-03 09.30.00.000000 AM

PL/SQL procedure successfully completed.
```

GENERATE_JOB_NAME Function

This function returns a unique name for a job. The name will be of the form {prefix}N where N is a number from a sequence. If no prefix is specified, the generated name will, by default, be JOB\$_1, JOB\$_2, JOB\$_3, and so on. If 'SCOTT' is specified as the prefix, the name will be SCOTT1, SCOTT2, and so on.

Syntax

```
DBMS_SCHEDULER.GENERATE_JOB_NAME (  
    prefix          IN VARCHAR2 DEFAULT 'JOB$_') RETURN VARCHAR2;
```

Parameters

Table 83–25 *GENERATE_JOB_NAME Procedure Parameters*

Parameter	Description
prefix	The name of the prefix being returned.

Usage Notes

If the prefix is explicitly set to NULL, the name will be just the sequence number. In order to successfully use such numeric names, they must be surrounded by double quotes throughout the DBMS_SCHEDULER calls. A prefix cannot be longer than 18 characters and cannot end with a digit.

Note that, even though the GENERATE_JOB_NAME function will never return the same job name twice, there is a small chance that the returned name happens to match an already existing database object.

GET_ATTRIBUTE Procedure

This procedure retrieves the value of an attribute of a Scheduler object. It is overloaded to output values of the following types: VARCHAR2, TIMESTAMP WITH TIMEZONE, BOOLEAN, PLS_INTEGER, and INTERVAL DAY TO SECOND.

Syntax

```
DBMS_SCHEDULER.GET_ATTRIBUTE (
    name          IN VARCHAR2,
    attribute     IN VARCHAR2,
    value        OUT [VARCHAR2, TIMESTAMP WITH TIMEZONE,
                    PLS_INTEGER, BOOLEAN, INTERVAL DAY TO SECOND]);
```

Parameters

Table 83–26 *GET_ATTRIBUTE Procedure Parameters*

Parameter	Description
name	The name of the object.
attribute	The attribute being retrieved.
value	The existing value of the attribute.

Usage Notes

To run GET_ATTRIBUTE for a job class, you must have the MANAGE SCHEDULER privilege or have EXECUTE privileges on the class. For a schedule, window, or a window group, no privileges are necessary. Otherwise, you must be the owner of the object or have ALTER or EXECUTE privileges on that object or have the CREATE ANY JOB privilege.

GET_SCHEDULER_ATTRIBUTE Procedure

This procedure retrieves the value of a Scheduler attribute. The attributes you can retrieve are `max_job_slave_processes`, `log_history`, and `current_open_window`. The Scheduler attribute `current_open_window` can only be retrieved (it can never be set) and it will contain the name of the currently active window, if any.

Syntax

```
DBMS_SCHEDULER.GET_SCHEDULER_ATTRIBUTE (  
    attribute      IN VARCHAR2,  
    value         OUT VARCHAR2);
```

Parameters

Table 83–27 *GET_SCHEDULER_ATTRIBUTE Procedure Parameters*

Parameter	Description
<code>attribute</code>	The name of the Scheduler attribute.
<code>value</code>	The existing value of the attribute.

Usage Notes

To run `GET_SCHEDULER_ATTRIBUTE`, you must have the `MANAGE SCHEDULER` privilege.

OPEN_WINDOW Procedure

This procedure opens a window independent of its schedule. This window will open and the resource plan associated with it, will take effect immediately for the duration specified or for the normal duration of the window if no duration is given. Only an enabled window can be manually opened.

Syntax

```
DBMS_SCHEDULER.OPEN_WINDOW (
    window_name          IN VARCHAR2,
    duration              IN INTERVAL DAY TO SECOND,
    force                IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–28 OPEN_WINDOW Procedure Parameters

Parameter	Description
window_name	The name of the window.
duration	The duration of the window. It is of type interval day to second. If it is not specified, then the window will be opened for the regular duration as specified in the window metadata.
force	<p>If <code>force</code> is set to <code>FALSE</code>, opening an already open window, will generate an error.</p> <p>If <code>force</code> is set to <code>TRUE</code>:</p> <p>You can open a window that is already open. The window stays open for the duration specified in the call, from the time the <code>OPEN_WINDOW</code> command was issued. Consider an example to illustrate this. <code>window1</code> was created with a duration of four hours. It has now been open for two hours. If at this point you reopen <code>window1</code> using the <code>OPEN_WINDOW</code> call and do not specify a duration, then <code>window1</code> will be open for another four hours because it was created with that duration. If you specified a duration of 30 minutes, the window will close in 30 minutes.</p> <p>The Scheduler automatically closes any window that is open at that time, even if it has a higher priority. For the duration of this manually opened window, the Scheduler does not open any other scheduled windows even if they have a higher priority.</p>

Usage Notes

If there are jobs running when the window opens, the resources allocated to them might change due to the switch in resource plan.

Opening a window manually has no impact on regular scheduled runs of the window. The next open time of the window is not updated, and will be as determined by the regular scheduled opening.

When a window that was manually opened closes, the rules about overlapping windows are applied to determine which other window should be opened at that time if any at all.

A window can fail to open if the resource plan has been manually switched using the `ALTER SYSTEM` statement with the `force` option.

Opening a window requires the `MANAGE SCHEDULER` privilege for that window.

PURGE_LOG Procedure

By default, the Scheduler automatically purges all rows in the job log and window log that are older than 30 days. The `PURGE_LOG` procedure is used to purge additional rows from the job and window log.

Syntax

```
DBMS_SCHEDULER.PURGE_LOG (
  log_history          IN PLS_INTEGER  DEFAULT 0,
  which_log           IN VARCHAR2     DEFAULT 'JOB_AND_WINDOW_LOG',
  job_name            IN VARCHAR2     DEFAULT NULL);
```

Parameters

Table 83–29 *PURGE_LOG Procedure Parameters*

Parameter	Description
<code>log_history</code>	This specifies how much history (in days) to keep. The valid range is 0 - 999. If set to 0, no history is kept.
<code>which_log</code>	This specifies which type of log. Valid values for <code>which_log</code> are <code>job_log</code> , <code>window_log</code> , and <code>job_and_window_log</code> .
<code>job_name</code>	This specifies which job-specific entries must be purged from the job log. This can be a comma-delimited list of job names and job classes. Whenever <code>job_name</code> has a value other than <code>NULL</code> , the <code>which_log</code> argument implicitly includes the job log.

Examples

The following will completely purge all rows from both the job log and the window log:

```
DBMS_SCHEDULER.PURGE_LOG();
```

The following will purge all rows from the window log that are older than 5 days:

```
DBMS_SCHEDULER.PURGE_LOG(5, 'window_log');
```

The following will purge all rows from the window log that are older than 1 day and all rows from the job log that are related to jobs in `jobclass1` and are older than 1 day:

```
DBMS_SCHEDULER>PURGE_LOG(1, 'job_and_window_log', 'sys.jobclass1');
```

REMOVE_WINDOW_GROUP_MEMBER Procedure

This procedure removes one or more windows from an existing window group.

Syntax

```
DBMS_SCHEDULER.REMOVE_WINDOW_GROUP_MEMBER (  
    group_name          IN VARCHAR2,  
    window_list        IN VARCHAR2);
```

Parameters

Table 83–30 REMOVE_WINDOW_GROUP_MEMBER Procedure Parameters

Parameter	Description
group_name	The name of the window group.
window_list	The name of the window or windows.

Usage Notes

If any of the windows specified is either invalid, does not exist, or is not a member of the given group, the call fails. Removing a window from a group requires the `MANAGE SCHEDULER` privilege.

Dropping an open window from a window group has no impact on running jobs that has the window as its schedule since the jobs would only be stopped when a window closes.

RESET_JOB_ARGUMENT_VALUE Procedures

This procedure resets (clears) the value previously set to an argument for a job.

RESET_JOB_ARGUMENT_VALUE is overloaded.

Syntax

Clears a previously set job argument value by argument position:

```
DBMS_SCHEDULER.RESET_JOB_ARGUMENT_VALUE (
    job_name           IN VARCHAR2,
    argument_position  IN PLS_INTEGER);
```

Clears a previously set job argument value by argument name:

```
DBMS_SCHEDULER.RESET_JOB_ARGUMENT_VALUE (
    job_name           IN VARCHAR2,
    argument_name      IN VARCHAR2);
```

Parameters

Table 83–31 RESET_JOB_ARGUMENT_VALUE Procedure Parameters

Parameter	Description
job_name	The name of the job being queried.
argument_position	The position of the program argument being altered.
argument_name	The name of the program argument being altered.

Usage Notes

If the corresponding program argument has no default value, the job will be disabled. Resetting a program argument of a job belonging to another user requires ALTER privileges on that job. Arguments can be specified by position or by name.

RESET_JOB_ARGUMENT_VALUE requires that you be the owner of the job or have ALTER privileges on that job. You can also set a job argument value if you have the CREATE ANY JOB privilege.

RUN_JOB Procedure

This procedure runs a job immediately.

Syntax

```
DBMS_SCHEDULER.RUN_JOB (
    job_name          IN VARCHAR2,
    use_current_session IN BOOLEAN DEFAULT TRUE);
```

Parameters

Table 83–32 *RUN_JOB Procedure Parameters*

Parameter	Description
job_name	The name of the job being run.
use_current_session	<p>This specifies whether the job run should occur in the same session as the one that the procedure was invoked from.</p> <p>When use_current_session is set to TRUE:</p> <ul style="list-style-type: none"> -You can test a job and see any possible errors on the command line. -run_count, last_start_date, last_run_duration, and failure_count are not updated. -RUN_JOB can be run in parallel with a regularly scheduled job run. <p>When use_current_session is set to FALSE:</p> <ul style="list-style-type: none"> -You need to check the job log to find error information. -run_count, last_start_date, last_run_duration, and failure_count are updated. -RUN_JOB fails if a regularly scheduled job is running.

Usage Notes

A job must be enabled for RUN_JOB to run. The job can be run in two different modes. One is in the current user session. In this case, the call to RUN_JOB will block until it has completed the job. Any errors that occur during the execution of the job will be returned as errors to the RUN_JOB procedure. The other option is to run the job immediately like a regular job. In this case, RUN_JOB returns immediately and the job will be picked up by the coordinator and passed on to a job slave for execution. The scheduler views and logs must be queried for the outcome of the job.

Multiple user sessions can use `RUN_JOB` in their sessions simultaneously when `use_current_session` is set to `TRUE`.

`RUN_JOB` requires that you be the owner of the job or have `ALTER` privileges on that job. You can also run a job if you have the `CREATE ANY JOB` privilege.

SET_ATTRIBUTE Procedure

This procedure changes an attribute of a Scheduler object. It is overloaded to accept values of the following types: VARCHAR2, TIMESTAMP WITH TIMEZONE, BOOLEAN, PLS_INTEGER, and INTERVAL DAY TO SECOND. To set an attribute to NULL, the SET_ATTRIBUTE_NULL procedure should be used. What attributes can be set depends on the object being altered. With the exception of the object name, all object attributes can be changed.

SET_ATTRIBUTE is overloaded.

Syntax

```
DBMS_SCHEDULER.SET_ATTRIBUTE (  
    name           IN VARCHAR2,  
    attribute      IN VARCHAR2,  
    value          IN [VARCHAR2, TIMESTAMP WITH TIMEZONE,  
                     PLS_INTEGER, BOOLEAN, INTERVAL DAY TO SECOND]);
```

Parameters

Table 83–33 SET_ATTRIBUTE Procedure Parameters

Parameter	Description
name	The name of the object.
attribute	See Table 83–34 , Table 83–35 , Table 83–36 , Table 83–37 , Table 83–38 , and Table 83–38 .
value	The new value being set for the attribute. This cannot be NULL. To set an attribute value to NULL, use the SET_ATTRIBUTE_NULL procedure.

Usage Notes

If an object is altered and it was in the enabled state, the Scheduler will first disable it, make the change and then re-enable it. If any errors are encountered during the enable process, the object is not re-enabled and an error is generated.

If an object is altered and it was in the disabled, it will remain disabled after it is altered.

To run SET_ATTRIBUTE for a window, window group, or job class, you must have the MANAGE_SCHEDULER privilege. Otherwise, you must be the owner of the object

being altered or have ALTER privileges on that object or have the CREATE ANY JOB privilege.

Job

If there is a running instance of the job when the SET_ATTRIBUTE call is made, it is not affected by the call. The change is only seen in future runs of the job.

If any of the schedule attributes of a job are altered while the job is running, the time of the next job run will be scheduled using the new schedule attributes. Schedule attributes of a job include schedule_name, start_date, end_date, and repeat_interval.

If any of the program attributes of a job are altered while the job is running, the new program attributes will take effect the next time the job runs. Program attributes of a job include program_name, job_action, job_type, and number_of_arguments. This is also the case for job argument values that have been set.

Granting ALTER on a job will let a user alter all attributes of that job except its program attributes (program_name, job_type, job_action, program_action, and number_of_arguments) and will not allow a user to use a PL/SQL expression to specify the schedule for a job.

We recommend you not to alter a job that was automatically created for you by the database. Jobs that were created by the database have the column SYSTEM set to TRUE in several views.

Program

If any currently running jobs use the program that is altered, they will continue to run with the program definition prior to the alter. The job will run with the new program definition the next time the job executes.

Schedule

If a schedule is altered, the change will not affect running jobs and open windows that use this schedule. The change will only be in effect the next time the jobs runs or the window opens.

Job Class

With the exception of the default job class, all job classes can be altered. To alter a job class, you must have the MANAGE_SCHEDULER privilege.

When a job class is altered, running jobs that belong to the class are not affected. The change only takes effect for jobs that have not started running yet.

Window

When a window is altered, it does not affect an active window. The changes only take effect the next time the window opens.

To change resource plans, you must first set the `RESOURCE_MANAGER_PLAN` initialization parameter in the `init.ora` file or issue an `ALTER SYSTEM SET RESOURCE_MANAGER_PLAN = my_plan` statement before the window opens.

Job Attribute Values

[Table 83–34](#) lists job attribute values.

Table 83–34 Job Attribute Values

Name	Description
logging_level	<p>This attribute specifies how much information is logged. The three possible options are:</p> <p><code>DBMS_SCHEDULER.LOGGING_OFF</code></p> <p>No logging will be performed for any jobs in this class.</p> <p><code>DBMS_SCHEDULER.LOGGING_RUNS</code></p> <p>The Scheduler will write detailed information to the job log for all runs of each job in this class.</p> <p><code>DBMS_SCHEDULER.LOGGING_FULL</code></p> <p>In addition to recording every run of a job, the Scheduler will record all operations performed on all jobs in this class. In other words, every time a job is created, enabled, disabled, altered, and so on will be recorded in the log.</p>

Table 83–34 (Cont.) Job Attribute Values

Name	Description
restartable	<p>This attribute specifies whether a job can be restarted in case of failure. By default, jobs are restartable and this attribute is set to <code>TRUE</code>. Setting this to <code>TRUE</code> means that if a job fails while running, it will be restarted from the beginning point of the job.</p> <p>Note that setting this attribute to <code>TRUE</code> might lead to data inconsistencies in some situations, for example, if data is committed within a job.</p> <p>Retries on errors are not counted as regular runs. The run count or failure count is not incremented until the job succeeds or has failed all its six retries.</p> <p>The restartable attribute is used by the Scheduler to determine whether to retry the job not only on regular application errors, but after a database malfunction as well. The Scheduler will retry the job a maximum of six times. The first time, it will wait for one second and multiply this wait time with a factor of 10 each time thereafter.</p> <p>Both the run count and failure count are incremented by 1 if the job has failed all its six retries. If the job immediately succeeds, or it succeeds on one of its retries, run count is incremented by 1.</p> <p>The Scheduler will stop retrying a job when:</p> <ul style="list-style-type: none"> -one of the retries succeeds -all of its six retries have failed -the next retry would occur after the next regularly scheduled run of the job <p>The Scheduler no longer retries the job if the next scheduled retry is past the next regularly scheduled run for repeating jobs.</p>
max_failures	<p>This attribute specifies the number of times a job can fail on consecutive scheduled runs before it is automatically disabled. Once a job is disabled, it is no longer executed and its <code>STATE</code> is set to <code>BROKEN</code> in the <code>*_SCHEDULER_JOB</code> views.</p> <p><code>max_failures</code> can be an integer between 1 to 1,000,000. By default, it is set to <code>NULL</code>, which indicates that new instances of the job will be started regardless of how many previous instances have failed.</p>
max_runs	<p>This attribute specifies the maximum number of consecutive scheduled runs of the job. Once <code>max_runs</code> is reached, the job is disabled and its state is changed to <code>COMPLETED</code>.</p> <p><code>max_runs</code> can be an integer between 1 and 1,000,000. By default, it is set to <code>NULL</code>, which means that it will repeat forever or until <code>end_date</code> or <code>max_failures</code> is reached.</p>

Table 83–34 (Cont.) Job Attribute Values

Name	Description
job_weight	<p>This attribute is for expert users of parallel technology only. If your job will be using parallel technology, you can set the value of this attribute to the degree of parallelism of your SQL inside the job.</p> <p>job_weight has a range of 1-100, with 1 being the default</p>
instance_stickiness	<p>This attribute should only be used for a database running in RAC mode. By default, it is set to TRUE. If you set instance_stickiness to TRUE, jobs start running on the instance with the lightest load and the Scheduler thereafter attempts to run on the instance that it last ran on. If that instance is either down or so overloaded that it will not start new jobs for a significant period of time, another instance will run the job. If the interval between runs is large, instance_stickiness will be ignored and the job will be handled as if it were a non-sticky job.</p> <p>If instance_stickiness is set to FALSE, each instance of the job runs on the first instance available.</p> <p>For non-RAC environments, this attribute is not useful because there is only one instance.</p>
stop_on_window_close	<p>This attribute only applies if the schedule of a job is a window or a window group. Setting this attribute to TRUE implies that the job should be stopped once the associated window is closed. The job is stopped using the stop_job procedure with force set to FALSE.</p> <p>By default, stop_on_window_close is set to FALSE. Therefore, if you do not set this attribute, the job will be allowed to continue after the window closes.</p> <p>Note that, although the job is allowed to continue, its resource allocation will probably change because closing a window generally also implies a change in resource plans.</p>
job_priority	<p>This attribute specifies the priority of this job relative to other jobs in the same class as this job. If multiple jobs within a class are scheduled to be executed at the same time, the job priority determines the order in which jobs from that class are picked up for execution by the job coordinator. It can be a value from 1 through 5, with 1 being the first to be picked up for job execution.</p> <p>If no job priority is specified when creating a job, the default priority of 3 is assigned to it.</p>

Table 83–34 (Cont.) Job Attribute Values

Name	Description
schedule_limit	<p>In heavily loaded systems, jobs are not always started at their scheduled time. This attribute enables you to have the Scheduler not start a job at all if the delay in starting the job is larger than the interval specified. It can be a value of 1 minute to 99 days. For example, if a job was supposed to start at noon and the schedule limit is set to 60 minutes, the job will not be run if it has not started to run by 1PM.</p> <p>If <code>schedule_limit</code> is not specified, the job is executed at some later date as soon as there are resources available to run it. By default, this attribute is set to null, which indicates that the job can be run at any time after its scheduled time. A scheduled job run that is skipped because of this attribute does not count against the number of runs and failures of the job. An entry in the job log will be made to reflect the skipped run.</p>
program_name	<p>The name of a program object to use with this job. If this is set, <code>job_action</code>, <code>job_type</code> and <code>number_of_arguments</code> should be NULL.</p>
job_action	<p>This is a string specifying the action. The possible values are:</p> <p>PLSQL_BLOCK: a PLSQL anonymous block</p> <p>STORED_PROCEDURE: name of the database stored procedure (C, Java or PL/SQL), optionally qualified with a schema and/or package name).</p> <p>EXECUTABLE: Name of an executable of shell script including the full path name and any command-line flags to it.</p> <p>If this is set, <code>program_name</code> should be NULL.</p>
job_type	<p>The type of this job. Can be any of: PLSQL_BLOCK, STORED_PROCEDURE, and EXECUTABLE.</p> <p>If this is set, <code>program_name</code> should be NULL.</p>
number_of_arguments	<p>The number of arguments if the program is inlined. If this is set, <code>program_name</code> should be NULL.</p>
schedule_name	<p>The name of a schedule or window or window group to use as the schedule for this job. If this is set, <code>end_date</code>, <code>start_date</code> and <code>repeat_interval</code> should all be NULL.</p>
repeat_interval	<p>Either a PL/SQL function returning the next date on which to run, or calendar syntax expression. If this is set, <code>schedule_name</code> should be NULL.</p>
start_date	<p>The original date on which this job started or will be scheduled to start. If this is set, <code>schedule_name</code> should be NULL.</p>
end_date	<p>The date after which the job will no longer run. It will be dropped if <code>auto_drop</code> is set or disabled with the state changed to COMPLETED if it is. If this is set, <code>schedule_name</code> should be NULL.</p>

Table 83–34 (Cont.) Job Attribute Values

Name	Description
job_class	The class this job is associated with.
comments	An optional comment.
auto_drop	Whether the job should be dropped after having completed.

Program Attribute Values

[Table 83–35](#) lists program attribute values.

Table 83–35 Program Attribute Values

Name	Description
program_action	This is a string specifying the action. The possible values are: PLSQL_BLOCK: a PLSQL anonymous block STORED_PROCEDURE: name of the database stored procedure (C, Java or PL/SQL), optionally qualified with a schema and/or package name). EXECUTABLE: Full path name including the name of the operating system executable or shell script.
program_type	The type of program. This must be one of the following supported program types: PLSQL_BLOCK, STORED_PROCEDURE, and EXECUTABLE.
number_of_arguments	The number of arguments of the program that can be set by any job using it, these arguments must be defined before the program can be enabled.
comments	An optional comment. This can describe what the program does, or give usage details.

Job Class Values

[Table 83–36](#) lists job class attribute values.

Table 83–36 Job Class Attribute Values

Name	Description
resource_consumer_group	The resource consumer group a class is associated with. If resource_consumer_group is set, service must be NULL.

Table 83–36 (Cont.) Job Class Attribute Values

Name	Description
service	The service the job class belongs to. The default is <code>NULL</code> , which implies the default service. This should be the name of the service database object and not the service name as defined in <code>tnsnames.ora</code> . If service is set, <code>resource_consumer_group</code> must be <code>NULL</code> .
logging_level	<p>This attribute specifies how much information is logged. The three possible options are:</p> <p><code>DBMS_SCHEDULER.LOGGING_OFF</code></p> <p>No logging will be performed for any jobs in this class.</p> <p><code>DBMS_SCHEDULER.LOGGING_RUNS</code></p> <p>The Scheduler will write detailed information to the job log for all runs of each job in this class.</p> <p><code>DBMS_SCHEDULER.LOGGING_FULL</code></p> <p>In addition to recording every run of a job, the Scheduler will record all operations performed on all jobs in this class. In other words, every time a job is created, enabled, disabled, altered, and so on will be recorded in the log.</p>
log_history	<p>This enables you to control the amount of logging the Scheduler performs. To prevent the job log and the window log from growing indiscriminately, the Scheduler has an attribute that specifies how much history (in days) to keep. Once a day, the Scheduler will automatically purge all log entries from both the job log as well as the window log that are older than the specified history. The default is 30 days.</p> <p>You can change the default by using the <code>SET_SCHEDULER_ATTRIBUTE</code> procedure. For example, to change it to 90 days, issue the following statement:</p> <pre>DBMS_SCHEDULER.SET_SCHEDULER_ATTRIBUTE ('log_history','90');</pre> <p>The range of valid values is 1 through 999.</p>
comments	An optional comment about the class.

Window Attribute Values

[Table 83–37](#) lists window attribute values.

Table 83–37 Window Attribute Values

Name	Description
resource_plan	The resource plan to be associated with a window. When the window opens, the system will switch to using this resource plan. When the window closes, the original resource plan will be restored. If a resource plan has been made active with the <code>force</code> option, no resource plan switch will occur.
window_priority	The priority of the window. Must be one of <code>LOW</code> (default) or <code>HIGH</code> .
duration	The duration of the window.
schedule_name	The name of a schedule to use with this window. If this is set, <code>start_date</code> , <code>end_date</code> , and <code>repeat_interval</code> must all be <code>NULL</code> .
repeat_interval	A string using the calendar syntax. PL/SQL date functions are not allowed. If this is set, <code>schedule_name</code> must be <code>NULL</code> .
start_date	The next date on which this window is scheduled to open. If this is set, <code>schedule_name</code> must be <code>NULL</code> .
end_date	The date after which the window will no longer open. If this is set, <code>schedule_name</code> must be <code>NULL</code> .
comments	An optional comment about the window.

Program Window Group Values

[Table 83–38](#) lists program window group values.

Table 83–38 Window Group Attribute Values

Name	Description
comments	An optional comment about the window group.

Schedule Attribute Values

[Table 83–39](#) lists schedule attribute values.

Table 83–39 Schedule Attribute Values

Name	Description
repeat_interval	An expression using the calendar syntax.
comments	An optional comment.

Table 83–39 (Cont.) Schedule Attribute Values

Name	Description
end_date	The cutoff date after which the schedule will not specify any dates.
start_date	The start or reference date used by the calendar syntax.

SET_ATTRIBUTE_NULL Procedure

This procedure sets an attribute of a Scheduler object to `NULL`. What attributes can be set depends on the object being altered. If the object is enabled, it will be disabled before being altered and be reenabled afterward. If the object cannot be re-enabled, an error is generated and the object will be left in a disabled state.

Syntax

```
DBMS_SCHEDULER.SET_ATTRIBUTE_NULL (  
    name           IN VARCHAR2,  
    attribute      IN VARCHAR2);
```

Parameters

Table 83–40 *SET_ATTRIBUTE_NULL Procedure Parameters*

Parameter	Description
<code>name</code>	The name of the object.
<code>attribute</code>	The attribute being changed.

Usage Notes

To run `SET_ATTRIBUTE_NULL` for a window, window group, or job class, you must have the `MANAGE SCHEDULER` privilege. Otherwise, you must be the owner of the object being altered or have `ALTER` privileges on that object or have the `CREATE ANY JOB` privilege.

SET_JOB_ANYDATA_VALUE Procedures

This procedure sets a value to an argument of the associated program for a job, encapsulated in an `AnyData` object. It overrides any default value set for the program argument. This does not affect whether the job is enabled or not. `NULL` is a valid assignment for a program argument. Arguments can be specified by position or by name. No type checking of the argument is done at any time by the Scheduler.

`SET_JOB_ANYDATA_VALUE` is overloaded.

Syntax

Sets a program argument by its position.

```
DBMS_SCHEDULER.SET_JOB_ANYDATA_VALUE (
    job_name           IN VARCHAR2,
    argument_position  IN PLS_INTEGER,
    argument_value     IN SYS.ANYDATA);
```

Sets a program argument by its name.

```
DBMS_SCHEDULER.SET_JOB_ANYDATA_VALUE (
    job_name           IN VARCHAR2,
    argument_name      IN VARCHAR2,
    argument_value     IN SYS.ANYDATA);
```

Parameters

Table 83–41 *SET_JOB_ANYDATA_VALUE Procedure Parameters*

Parameter	Description
<code>job_name</code>	The name of the job to be altered.
<code>argument_name</code>	The name of the program argument being set.
<code>argument_position</code>	The position of the program argument being set.
<code>argument_value</code>	The new value to be assigned to the program argument, encapsulated in an <code>AnyData</code> object.

Usage Notes

SET_JOB_ANYDATA_VALUE requires that you be the owner of the job or have ALTER privileges on that job. You can also set a job argument value if you have the CREATE ANY JOB privilege.

SET_JOB_ARGUMENT_VALUE Procedures

This procedure sets a value to an argument of the associated program for a job. It overrides any default value set for the program argument. This does not affect whether a job is enabled or not. NULL is a valid assignment for a program argument. Arguments can be specified by position or by name. No type checking of the argument is done at any time by the Scheduler.

SET_JOB_ARGUMENT_VALUE is overloaded.

Syntax

Sets an argument value by position:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE (
    job_name           IN VARCHAR2,
    argument_position  IN PLS_INTEGER,
    argument_value     IN VARCHAR2);
```

Sets an argument value by name:

```
DBMS_SCHEDULER.SET_JOB_ARGUMENT_VALUE (
    job_name           IN VARCHAR2,
    argument_name      IN VARCHAR2,
    argument_value     IN VARCHAR2);
```

Parameters

Table 83–42 SET_JOB_ARGUMENT_VALUE Procedure Parameters

Parameter	Description
job_name	The name of the job to be altered.
argument_name	The name of the program argument being set.
argument_position	The position of the program argument being set.
argument_value	The new value to be set for the program argument. To set a non-VARCHAR value, use the SET_JOB_ANYDATA_ARGUMENT_VALUE procedure.

Usage Notes

SET_JOB_ARGUMENT_VALUE requires that you be the owner of the job or have ALTER privileges on that job. You can also set a job argument value if you have the CREATE ANY JOB privilege.

SET_SCHEDULER_ATTRIBUTE Procedure

This procedure sets the value of a Scheduler attribute. This takes effect immediately but the resulting changes may not be seen immediately. The attributes you can set are `default_timezone`, `max_job_slave_processes` and `log_history`.

Syntax

```
DBMS_SCHEDULER.SET_SCHEDULER_ATTRIBUTE (  
    attribute      IN VARCHAR2,  
    value         IN VARCHAR2);
```

Parameters

Table 83–43 SET_SCHEDULER_ATTRIBUTE Procedure Parameters

Parameter	Description
attribute	<p>The name of the Scheduler attribute. Possible values are:</p> <ul style="list-style-type: none"> <p>■ <code>default_timezone</code>: It is very important that this attribute is set. Whenever a <code>repeat_interval</code> is specified without setting the <code>start_date</code>, the scheduler needs to know which time zone it must apply to the repeat interval syntax. For example, if the repeat interval is specified as</p> <pre>"FREQ=DAILY;BYHOUR=22"</pre> <p>the job will repeat every day at 10pm, but 10pm in which time zone? If no <code>start_date</code> is specified the scheduler will pick up the time zone from this <code>default_timezone</code> attribute. If you want your job or window to follow daylight savings adjustments, you must set this attribute to the proper region name. For instance, if your database resides in Paris, you would set this to 'Europe/Warsaw'.</p> <p>Daylight saving adjustments will not be followed if you specify an absolute offset, for instance '-8:00' would only be correct for half of the year in San Francisco. If no value is specified for this attribute, the scheduler uses the time zone of <code>sysimestamp</code> when the job or window is enabled. This is always an absolute offset and will not follow daylight savings adjustments.</p> <p>■ <code>log_history</code>: This enables you to control the amount of logging the Scheduler performs.</p> <p>■ <code>max_job_slave_processes</code>: This enables you to set a maximum number of slave processes for a particular system configuration and load. The default value is <code>NULL</code>, and the valid range is 1-999.</p> <p>Even though the Scheduler automatically determines what the optimum number of slave processes is for a given system configuration and load, you still might want to set a fixed limit on the Scheduler. If this is the case, you can set this attribute.</p> <p>Although the number set by <code>max_job_slave_processes</code> is a real maximum, it does not mean the Scheduler will start the specified number of slaves. For example, even though this attribute is set to 10, the Scheduler might still determine that is should not start more than 3 slave processes. However, if it wants to start 15, but it is set to 10, it will not start more than 10.</p>
value	The new value of the attribute.

Usage Notes

To run `SET_SCHEDULER_ATTRIBUTE`, you must have the `MANAGE SCHEDULER` privilege.

STOP_JOB Procedure

This procedure stops currently running jobs or all jobs in a job class. Any instance of the job will be stopped. After stopping the job, the state of a one-time job will be set to `SUCCEEDED` whereas the state of a repeating job will be set to `SCHEDULED` or `COMPLETED` depending on whether the next run of the job is scheduled.

Syntax

```
DBMS_SCHEDULER.STOP_JOB (  
    job_name          IN VARCHAR2  
    force             IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 83–44 STOP_JOB Procedure Parameters

Parameter	Description
job_name	The name of the job or job class. Can be a comma-delimited list. For a job class, the <code>SYS</code> schema should be specified. If the name of a job class is specified, the jobs that belong to that job class are stopped. The job class is not affected by this call.
force	If <code>force</code> is set to <code>FALSE</code> , the Scheduler tries to gracefully stop the job using an interrupt mechanism. This method gives control back to the slave process, which can update the status of the job in the job queue to stopped. If this fails, an error is returned. If <code>force</code> is set to <code>TRUE</code> , the Scheduler will immediately terminate the job slave. Oracle recommends that <code>STOP_JOB</code> with <code>force</code> set to <code>TRUE</code> be used only after a <code>STOP_JOB</code> with <code>force</code> set to <code>FALSE</code> has failed. Use of the <code>force</code> option requires the <code>MANAGE SCHEDULER</code> system privilege. Setting <code>force</code> to <code>TRUE</code> is not supported for jobs of type executable.

Usage Notes

`STOP_JOB` without the `force` option requires that you be the owner of the job or have `ALTER` privileges on that job. You can also stop a job if you have the `CREATE ANY JOB` or `MANAGE SCHEDULER` privilege.

`STOP_JOB` with the `force` option requires that have the `MANAGE SCHEDULER` privilege.

DBMS_SERVER_ALERT

The DBMS_SERVER_ALERT package let you issue alerts when some threshold has been violated. If the warning threshold is reached, this generates a severity level 5 alert. If the critical threshold is reached, this generates a severity level 1 alert.

The chapter contains the following topics:

- [Using DBMS_SERVER_ALERT](#)
 - [Object Types Defined as Constants](#)
 - [Relational Operators Defined as Constants](#)
 - [Supported Metrics](#)
- [Summary of DBMS_SERVER_ALERT Subprograms](#)

Using DBMS_SERVER_ALERT

- [Object Types Defined as Constants](#)
- [Relational Operators Defined as Constants](#)
- [Supported Metrics](#)

Object Types Defined as Constants

You can qualify the metrics by an individual object for the following object types.

Table 84–1 *Object Types Defined as Constants*

Constant	Description
OBJECT_TYPE_SYSTEM	Metrics collected on the system level for each instance.
OBJECT_TYPE_FILE	Metrics collected on the file level. These are used for AVERAGE_FILE_READ_TIME and AVERAGE_FILE_WRITE_TIME metrics.
OBJECT_TYPE_SERVICE	Metrics collected on the service level. Currently ELAPSED_TIME_PER_CALL and CPU_TIME_PER_CALL are collected.
OBJECT_TYPE_TABLESPACE	Metrics collected on the tablespace level. Currently only TABLESPACE_PCT_FULL is collected.
OBJECT_TYPE_EVENT_CLASS	Metrics collected on wait event class level. Currently supported metrics are AVG_USERS_WAITING and DB_TIME_WAITING.
OBJECT_TYPE_SESSION	Metrics collected on the session level. Currently only BLOCKED_USERS is collected. The threshold can only be set at the instance level, which means that no object name should be specified when setting the threshold for this type of metric.

Relational Operators Defined as Constants

You can specify a relational comparison operator to determine whether or not a given metric's value violates the threshold setting. The server will support the following operators.

Table 84–2 Relational Operators Defines as Constants

Constant	Description
OPERATOR_CONTAINS	A metrics value contained in a list of threshold values is considered a violation.
OPERATOR_DO_NOT_CHECK	Will not apply default threshold to OBJECT_TYPE_TABLESPACE .
OPERATOR_EQ	A metrics value equal to the threshold one is considered a violation.
OPERATOR_GE	A metrics value greater or equal than the threshold is considered a violation.
OPERATOR_GT	A metrics value greater than the threshold is considered a violation.
OPERATOR_LE	A metrics value less or equal than the threshold is considered a violation.
OPERATOR_LT	A metrics value less than the threshold is considered a violation.
OPERATOR_NE	A metrics value not equal to the threshold one is considered a violation.

Supported Metrics

Table 84–3 List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
SQL_SRV_RESPONSE_TIME	Service Response (for each execution)	Seconds
BUFFER_CACHE_HIT	Buffer Cache Hit (%)	% of cache accesses
LIBRARY_CACHE_HIT	Library Cache Hit (%)	% of cache accesses
LIBRARY_CACHE_MISS	Library Cache Miss (%)	% of cache accesses
MEMORY_SORTS_PCT	Sorts in Memory (%)	% of sorts
REDO_ALLOCATION_HIT	Redo Log Allocation Hit	% of redo allocations
TRANSACTION_RATE	Number of Transactions (for each second)	Transactions for each Second
PHYSICAL_READS_SEC	Physical Reads (for each second)	Reads for each Second

Table 84-3 (Cont.) List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
PHYSICAL_READS_TXN	Physical Reads (for each transaction)	Reads for each Transaction
PHYSICAL_WRITES_SEC	Physical Writes (for each second)	Writes for each Second
PHYSICAL_WRITES_TXN	Physical Writes (for each transaction)	Writes for each Transaction
PHYSICAL__READS_DIR_SEC	Direct Physical Reads (for each second)	Reads for each Second
PHYSICAL_READS_DIR_TXN	Direct Physical Reads (for each transaction)	Reads for each Transaction
PHYSICAL_WRITES_DIR_SEC	Direct Physical Writes (for each second)	Writes for each Second
PHYSICAL_WRITES_DIR_TXN	Direct Physical Writes (for each transaction)	Writes for each Transaction
PHYSICAL_READS_LOB_SEC	Direct LOB Physical Reads (for each second)	Reads for each Second
PHYSICAL_READS_LOB_TXN	Direct LOB Physical Reads (for each transaction)	Reads for each Transaction
PHYSICAL_WRITES_LOB_SEC	Direct LOB Physical Writes (for each second)	Writes for each Second
PHYSICAL_WRITES_LOB_TXN	Direct LOB Physical Writes (for each transaction)	Writes for each Transaction
REDO_GENERATED_SEC	Redo Generated (for each second)	Redo Bytes for each Second
REDO_GENERATED_TXN	Redo Generated (for each transaction)	Redo Bytes for each Transaction
DATABASE_WAIT_TIME	Database Wait Time (%)	% of all database time
DATABASE_CPU_TIME	Database CPU Time (%)	% of all database time
LOGONS_SEC	Cumulative Logons (for each second)	Logons for each Second
LOGONS_TXN	Cumulative Logons (for each transaction)	Logons for each Transaction
LOGONS_CURRENT	Current Number of Logons	Number of Logons
OPEN_CURSORS_SEC	Cumulative Open Cursors (for each second)	Cursors for each Second

Table 84-3 (Cont.) List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
OPEN_CURSORS_TXN	Cumulative Open Cursors (for each transaction)	Cursors for each Transaction
OPEN_CURSORS_CURRENT	Current Number of Cursors	Number of Cursors
USER_COMMITS_SEC	User Commits (for each second)	Commits for each Second
USER_COMMITS_TXN	User Commits (for each transaction)	Commits for each Transaction
USER_ROLLBACKS_SEC	User Rollbacks (for each second)	Rollbacks for each Second
USER_ROLLBACKS_TXN	User Rollbacks (for each transaction)	Rollbacks for each Transaction
USER_CALLS_SEC	User Calls (for each second)	Calls for each Second
USER_CALLS_TXN	User Calls (for each transaction)	Calls for each Transaction
RECURSIVE_CALLS_SEC	Recursive Calls (for each second)	Calls for each Second
RECURSIVE_CALLS_TXN	Recursive Calls (for each transaction)	Calls for each Transaction
SESS_LOGICAL_READS_SEC	Session Logical Reads (for each second)	Reads for each Second
SESS_LOGICAL_READS_TXN	Session Logical Reads (for each transaction)	Reads for each Transaction
DBWR_CKPT_SEC	DBWR Checkpoints (for each second)	Checkpoints for each Second
LOG_SWITCH_SEC	Background Checkpoints (for each second)	Checkpoints for each Second
REDO_WRITES_SEC	Redo Writes (for each second)	Writes for each Second
REDO_WRITES_TXN	Redo Writes (for each transaction)	Writes for each Transaction
LONG_TABLE_SCANS_SEC	Scans on Long Tables (for each second)	Scans for each Second
LONG_TABLE_SCANS_TXN	Scans on Long Tables (for each transaction)	Scans for each Transaction
TOTAL_TABLE_SCANS_SEC	Total Table Scans (for each second)	Scans for each Second
TOTAL_TABLE_SCANS_TXN	Total Table Scans (for each transaction)	Scans for each Transaction
FULL_INDEX_SCANS_SEC	Fast Full Index Scans (for each second)	Scans for each Second

Table 84–3 (Cont.) List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
FULL_INDEXE_SCANS_TXN	Fast Full Index Scans (for each transaction)	Scans for each Transaction
TOTAL_INDEX_SCANS_SEC	Total Index Scans (for each second)	Scans for each Second
TOTAL_INDEX_SCANS_TXN	Total Index Scans (for each transaction)	Scans for each Transaction
TOTAL_PASES_SEC	Total Parses (for each second)	Parses for each Second
TOTAL_PASES_TXN	Total Parses(for each transaction)	Parses for each Transaction
HARD_PASES_SEC	Hard Parses(for each second)	Parses for each Second
HARD_PASES_TXN	Hard Parses(for each transaction)	Parses for each Transaction
PARSE_FAILURES_SEC	Parse Failures (for each second)	Parses for each Second
PARSE_FAILURES_TXN	Parse Failures (for each transaction)	Parses for each Transaction
DISK_SORT_SEC	Sorts to Disk (for each second)	Sorts for each Second
DISK_SORT_TXN	Sorts to Disk (for each transaction)	Sorts for each Transaction
ROWS_PER_SORT	Rows Processed for each Sort	Rows for each Sort
EXECUTE_WITHOUT_PARSE	Executes Performed Without Parsing	% of all executes
SOFT_PARSE_PCT	Soft Parse (%)	% of all parses
CURSOR_CACHE_HIT	Cursor Cache Hit (%)	% of soft parses
USER_CALLS_PCT	User Calls (%)	% of all calls
TXN_COMMITTED_PCT	Transactions Committed (%)	% of all transactions
NETWORK_BYTES_SEC	Network Bytes, for each second	Bytes for each Second
RESPONSE_TXN	Response (for each transaction)	Seconds for each Transaction
DATA_DICT_HIT	Data Dictionary Hit (%)	% of dictionary accesses
DATA_DICT_MISS	Data Dictionary Miss (%)	% of dictionary accesses
SHARED_POOL_FREE_PCT	Shared Pool Free(%)	% of shared pool
AVERAGE_FILE_READ_TIME	Average File Read Time	Microseconds
AVERAGE_FILE_WRITE_TIME	Average File Write Time	Microseconds
DISK_IO	Disk I/O	Milliseconds

Table 84-3 (Cont.) List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
PROCESS_LIMIT_PCT	Process Limit Usage (%)	% of maximum value
SESSION_LIMIT_PCT	Session Limit Usage (%)	% of maximum value
USER_LIMIT_PCT	User Limit Usage (%)	% of maximum value
AVG_USERS_WAITING	Average Number of Users Waiting on a Class of Wait Events	Count of sessions
DB_TIME_WAITING	Percent of Database Time Spent Waiting on a Class of Wait Events	% of Database Time
APPL_DESGN_WAIT_SCT	Application Design Wait (by session count)	Count of sessions
APPL_DESGN_WAIT_TIME	Application Design Wait (by time)	Microseconds
PHYS_DESGN_WAIT_SCT	Physical Design Wait (by session count)	Count of sessions
PHYS_DESGN_WAIT_TIME	Physical Design Wait (by time)	Microseconds
CONTENTION_WAIT_SCT	Internal Contention Wait (by session count)	Count of sessions
CONTENTION_WAIT_TIME	Internal Contention Wait (by time)	Microseconds
PSERVICE_WAIT_SCT	Process Service Wait (by session count)	Count of sessions
PSERVICE_WAIT_TIME	Process Service Wait (by time)	Microseconds
NETWORK_MSG_WAIT_SCT	Network Message Wait (by session count)	Count of sessions
NETWORK_MSG_WAIT_TIME	Network Message Wait (by time)	Microseconds
DISK_IO_WAIT_SCT	Disk I/O Wait (by session count)	Count of sessions
OS_SERVICE_WAIT_SCT	Operating System Service Wait (by session count)	Count of sessions
OS_SERVICE_WAIT_TIME	Operating System Service Wait (by time)	Microseconds
DBR_IO_LIMIT_WAIT_SCT	Resource Mgr I/O Limit Wait (by session count)	Count of sessions
DBR_IO_LIMIT_WAIT_TIME	Resource Mgr I/O Limit Wait (by time)	Microseconds

Table 84–3 (Cont.) List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
DBR_CPU_LIMIT_WAIT_SCT	Resource Mgr CPU Limit Wait (by session count)	Count of sessions
DBR_CPU_LIMIT_WAIT_TIME	Resource Mgr CPU Limit Wait (by time)	Microseconds
DBR_USR_LIMIT_WAIT_SCT	Resource Mgr User Limit Wait (by session count)	Count of sessions
DBR_USR_LIMIT_WAIT_TIME	Resource Mgr User Limit Wait (by time)	Microseconds
OS_SCHED_CPU_WAIT_SCT	Operating System Scheduler CPU Wait (by session count)	Count of sessions
OS_SCHED_CPU__WAIT_TIME	Operating System Scheduler CPU Wait (by time)	Microseconds
CLUSTER_MSG_WAIT_SCT	Cluster Messaging Wait (by session count)	Count of sessions
CLUSTER_MSG_WAIT_TIME	Cluster Messaging Wait (by time)	Microseconds
OTHER_WAIT_SCT	Other Waits (by session count)	Count of sessions
OTHER_WAIT_TIME	Other Waits (by time)	Microseconds
ENQUEUE_TIMEOUTS_SEC	Enqueue Timeouts (for each second)	Timeouts for each Second
ENQUEUE_TIMEOUTS_TXN	Enqueue Timeouts (for each transaction)	Timeouts for each Transaction
ENQUEUE_WAITS_SEC	Enqueue Waits (for each second)	Waits for each Second
ENQUEUE_WAITS_TXN	Enqueue Waits (for each transaction)	Waits for each Transaction
ENQUEUE_DEADLOCKS_SEC	Enqueue Deadlocks (for each second)	Deadlocks for each Second
ENQUEUE_DEADLOCKS_TXN	Enqueue Deadlocks (for each transaction)	Deadlocks for each Transaction
ENQUEUE_REQUESTS_SEC	Enqueue Requests (for each second)	Requests for each Second
ENQUEUE_REQUESTS_TXN	Enqueue Requests (for each transaction)	Requests for each Transaction
DB_BLKGETS_SEC	DB Block Gets (for each second)	Gets for each Second

Table 84–3 (Cont.) List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
DB_BLKGETS_TXN	DB Block Gets (for each transaction)	Gets for each Transaction
CONSISTENT_GETS_SEC	Consistent Gets (for each second)	Gets for each Second
CONSISTENT_GETS_TXN	Consistent Gets (for each transaction)	Gets for each Transaction
DB_BLKCHANGES_SEC	DB Block Changes (for each second)	Changes for each Second
DB_BLKCHANGES_TXN	DB Block Changes (for each transaction)	Changes for each Transaction
CONSISTENT_CHANGES_SEC	Consistent Changes (for each second)	Changes for each Second
CONSISTENT_CHANGES_TXN	Consistent Changes (for each transaction)	Changes for each Transaction
SESSION_CPU_SEC	Database CPU (for each second)	Microseconds for each Second
SESSION_CPU_TXN	Database CPU (for each transaction)	Microseconds for each Transaction
CR_BLOCKS_CREATED_SEC	CR Blocks Created (for each second)	Blocks for each Second
CR_BLOCKS_CREATED_TXN	CR Blocks Created (for each transaction)	Blocks for each Transaction
CR_RECORDS_APPLIED_SEC	CR Undo Records Applied (for each second)	Records for each Second
CR_RECORDS_APPLIED_TXN	CR Undo Records Applied (for each transaction)	Records for each Transaction
RB_RECORDS_APPLIED_SEC	Rollback Undo Records Applied (for each second)	Records for each Second
RB_RECORDS_APPLIED_TXN	Rollback Undo Records Applied (for each transaction)	Records for each Transaction
LEAF_NODE_SPLITS_SEC	Leaf Node Splits (for each second)	Splits for each Second
LEAF_NODE_SPLITS_TXN	Leaf Node Splits (for each transaction)	Splits for each Transaction
BRANCH_NODE_SPLITS_SEC	Branch Node Splits (for each second)	Splits for each Second
BRANCH_NODE_SPLITS_TXN	Branch Node Splits (for each transaction)	Splits for each Transaction

Table 84–3 (Cont.) List of Supported Metrics

Metrics Name (Internal)	Metrics Name (External)	Units
GC_BLOCKS_CORRUPT	Global Cache Blocks Corrupt	Blocks
GC_BLOCKS_LOST	Global Cache Blocks Lost	Blocks
GC_AVG_CR_GET_TIME	Global Cache CR Request	Milliseconds
GC_AVG_CUR_GET_TIME	Global Cache Current Request	Milliseconds
PX_DOWNGRADED_SEC	Downgraded Parallel Operations (for each second)	Operations for each Second
PX_DOWNGRADED_25_SEC	Downgraded to 25% and more (for each second)	Operations for each Second
PX_DOWNGRADED_50_SEC	Downgraded to 50% and more (for each second)	Operations for each Second
PX_DOWNGRADED_75_SEC	Downgraded to 75% and more (for each second)	Operations for each Second
PX_DOWNGRADED_SER_SEC	Downgraded to serial (for each second)	Operations for each Second
BLOCKED_USERS	Number of Users blocked by some Session	Number of Users
PGA_CACHE_HIT	PGA Cache Hit (%)	% bytes processed in PGA
ELAPSED_TIME_PER_CALL	Elapsed time for each user call for each service	Microseconds for each call
CPU_TIME_PER_CALL	CPU time for each user call for each service	Microseconds for each call
TABLESPACE_PCT_FULL	Tablespace space usage	% full

Summary of DBMS_SERVER_ALERT Subprograms

Table 84-4 DBMS_SERVER_ALERT Package Subprograms

Subprogram	Description
EXPAND_MESSAGE Function on page 84-12	Expands alert messages
GET_THRESHOLD Procedure on page 84-13	Gets threshold settings for given metrics
SET_THRESHOLD Procedure on page 84-14	Set warning and critical thresholds for given metrics

EXPAND_MESSAGE Function

This function expands alert messages.

Syntax

```
DBMS_SERVER_ALERT.EXPAND_MESSAGE(  
    user_language      IN   VARCHAR2,  
    message_id        IN   NUMBER,  
    argument_1        IN   VARCHAR2,  
    argument_2        IN   VARCHAR2,  
    argument_3        IN   VARCHAR2,  
    argument_4        IN   VARCHAR2,  
    argument_5        IN   VARCHAR2)  
RETURN VARCHAR2;
```

Parameters

Table 84–5 *EXPAND_MESSAGE Procedure Parameters*

Parameter	Description
user_language	The language of the current session.
message_id	Id of the alert message
argument_1	The first argument in the alert message.
argument_2	The second argument in the alert message.
argument_3	The third argument in the alert message.
argument_4	The fourth argument in the alert message.
argument_5	The fifth argument in the alert message.

GET_THRESHOLD Procedure

This procedure gets the threshold setting for given metrics.

Syntax

```
DBMS_SERVER_ALERT.GET_THRESHOLD(
  metrics_id           IN  NUMBER,
  warning_operator     OUT NUMBER,
  warning_value        OUT VARCHAR2,
  critical_operator    OUT NUMBER,
  critical_value       OUT VARCHAR2,
  observation_period   OUT NUMBER,
  consecutive_occurrences OUT NUMBER,
  instance_name        IN  VARCHAR2,
  object_type          IN  NUMBER,
  object_name          IN  VARCHAR2);
```

Parameters

Table 84–6 *GET_THRESHOLD Procedure Parameters*

Parameter	Description
metrics_id	The internal name of the metrics.
warning_operator	The operator for the comparing the actual value with the warning threshold.
warning_value	The warning threshold value.
critical_operator	The operator for the comparing the actual value with the critical threshold.
critical_value	The critical threshold value.
observation_period	The period at which the metrics values are computed and verified against the threshold setting.
consecutive_occurrences	The number of observation periods the metrics value should violate the threshold value before the alert is issued.
instance_name	The name of the instance for which the threshold is set. This is NULL for database-wide alerts.
object_type	Either OBJECT_TYPE_SYSTEM or OBJECT_TYPE_SERVICE.
object_name	The name of the object.

SET_THRESHOLD Procedure

This procedure will set warning and critical thresholds for given metrics.

Syntax

```
DBMS_SERVER_ALERT.SET_THRESHOLD(
    metrics_id           IN    NUMBER,
    warning_operator    IN    NUMBER,
    warning_value       IN    VARCHAR2,
    critical_operator   IN    NUMBER,
    critical_value      IN    VARCHAR2,
    observation_period  IN    NUMBER,
    consecutive_occurrences IN NUMBER,
    instance_name      IN    VARCHAR2,
    object_type        IN    NUMBER,
    object_name        IN    VARCHAR2);
```

Parameters

Table 84–7 SET_THRESHOLD Procedure Parameters

Parameter	Description
metrics_id	The internal name of the metrics.
warning_operator	The operator for the comparing the actual value with the warning threshold (such as OPERATOR_GE).
warning_value	The warning threshold value. This is NULL if no warning threshold is set. A list of values may be specified for OPERATOR_CONTAINS.
critical_operator	The operator for the comparing the actual value with the critical threshold.
critical_value	The critical threshold value. This is NULL if not set. A list of values may be specified for OPERATOR_CONTAINS.
observation_period	The period at which the metrics values are computed and verified against the threshold setting. The valid range is 1 to 60 minutes.
consecutive_occurrences	The number of observation periods the metrics value should violate the threshold value before the alert is issued.
instance_name	The name of the instance for which the threshold is set. This is NULL for database-wide alerts.

Table 84–7 (Cont.) SET_THRESHOLD Procedure Parameters

Parameter	Description
object_type	See Object Types Defined as Constants on page 84-2.
object_name	The name of the object. This is NULL for SYSTEM.

The DBMS_SERVICE package lets you create, delete, activate and deactivate services for a single instance.

The chapter contains the following topics:

- [Using DBMS_SERVICE](#)
 - [Security Model](#)
- [Summary of DBMS_SERVICE Subprograms](#)

See Also:

- *Oracle Real Application Clusters Administrator's Guide for administering services in Real Application Clusters.*

Using DBMS_SERVICE

- [Security Model](#)

Security Model

The client using this package should have the ALTER SYSTEM execution privilege and the V\$SESSION table read privilege.

Summary of DBMS_SERVICE Subprograms

Table 85–1 DBMS_SERVICE Package Subprograms

Subprogram	Description
CREATE_SERVICE Procedure on page 85-4	Creates service
DELETE_SERVICE Procedure on page 85-5	Deletes service
DISCONNECT_SESSION Procedure on page 85-6	Disconnects service
START_SERVICE Procedure on page 85-7	Activates service
STOP_SERVICE Procedure on page 85-8	Stops service

CREATE_SERVICE Procedure

This procedure creates a service name in the data dictionary. Services are also created in the data dictionary implicitly when you set the service in the `service_names` parameter or by means of the `ALTER SYSTEM SET service_names` command.

Syntax

```
DBMS_SERVICE.CREATE_SERVICE(  
    service_name IN VARCHAR2,  
    network_name IN VARCHAR2);
```

Parameters

Table 85–2 *CREATE_SERVICE Procedure Parameters*

Parameter	Description
<code>service_name</code>	The name of the service limited to 64 characters in the Data Dictionary.
<code>network_name</code>	The network name of the service as used in SQLNet connect descriptors for client connections.

Examples

```
DBMS_SERVICE.CREATE_SERVICE('ernie.us.oracle.com', 'ernie.us.oracle.com');
```

DELETE_SERVICE Procedure

This procedure deletes a service from the data dictionary.

Syntax

```
DBMS_SERVICE.DELETE_SERVICE(  
    service_name  IN VARCHAR2);
```

Parameters

Table 85–3 *DELETE_SERVICE Procedure Parameters*

Parameter	Description
service_name	The name of the service limited to 64 characters in the Data Dictionary.

Examples

```
DBMS_SERVICE.DELETE_SERVICE('ernie.us.oracle.com');
```

DISCONNECT_SESSION Procedure

This procedure disconnects sessions with the named service at the current instance.

Syntax

```
DBMS_SERVICE.DISCONNECT_SESSION(  
    service_name    IN VARCHAR2);
```

Parameters

Table 85–4 *DISCONNECT_SESSION Procedure Parameters*

Parameter	Description
service_name	The name of the service limited to 64 characters in the Data Dictionary

Usage Notes

This procedure can be used in the context of a single instance as well as with Real Application Clusters.

Examples

```
DBMS_SERVICE.DISCONNECT_SESSION('ernie.us.oracle.com');
```

This disconnects sessions with service_name 'ernie.us.oracle.com'.

START_SERVICE Procedure

This procedure starts a service.

Syntax

```
DBMS_SERVICE.START_SERVICE(  
    service_name IN VARCHAR2,  
    instance_name IN VARCHAR2);
```

Parameters

Table 85-5 *START_SERVICE Procedure Parameters*

Parameter	Description
service_name	The name of the service limited to 64 characters in the Data Dictionary.
instance_name	The name of the instance where the service should be activated (optional).

Examples

```
DBMS_SERVICE.START_SERVICE('ernie.us.oracle.com');
```

STOP_SERVICE Procedure

This procedure stops a service.

Syntax

```
DBMS_SERVICE.STOP_SERVICE(  
    service_name  IN VARCHAR2, I  
    instance_name IN VARCHAR2);
```

Parameters

Table 85–6 *STOP_SERVICE Procedure Parameters*

Parameter	Description
service_name	The name of the service limited to 64 characters in the Data Dictionary.
instance_name	The name of the instance where the service should be stopped (optional).

Examples

```
DBMS_SERVICE.STOP_SERVICE('ernie.us.oracle.com');
```

DBMS_SESSION

This package provides access to SQL `ALTER SESSION` and `SET ROLE` statements, and other session information, from PL/SQL. You can use `DBMS_SESSION` to set preferences and security levels.

This chapter contains the following topics:

- [Using DBMS_SESSION](#)
 - [Security Model](#)
 - [Operational Notes](#)
- [Summary of DBMS_SESSION Subprograms](#)

Using DBMS_SESSION

- [Security Model](#)
- [Operational Notes](#)

Security Model

This package runs with the privileges of the calling user, rather than the package owner SYS.

Operational Notes

You should not attempt to turn `close_cached_open_cursors` on or off.

Summary of DBMS_SESSION Subprograms

Table 86–1 DBMS_SESSION Package Subprograms

Subprogram	Description
CLEAR_CONTEXT Procedure on page 86-5	Clears the context
CLEAR_ALL_CONTEXT Procedure on page 86-6	Clears all context information
CLEAR_IDENTIFIER Procedure on page 86-7	Clears the identifier
CLOSE_DATABASE_LINK Procedure on page 86-8	Closes database link
FREE_UNUSED_USER_MEMORY Procedure on page 86-9	Lets you reclaim unused memory after performing operations requiring large amounts of memory
IS_ROLE_ENABLED Function on page 86-12	Determines if the named role is enabled for the session.
IS_SESSION_ALIVE Function on page 86-13	Determines if the specified session is active
LIST_CONTEXT Procedures on page 86-14	Returns a list of active namespace and context for the current session
MODIFY_PACKAGE_STATE Procedure on page 86-15	Performs actions on the session state of PL/SQL program units that are active in the session
RESET_PACKAGE Procedure on page 86-21	Deinstantiates all packages in the session
SET_CONTEXT Procedure on page 86-23	Sets or resets the value of a context attribute
SET_IDENTIFIER on page 86-25	Sets the identifier
SET-NLS Procedure on page 86-26	Sets Globalization Support (NLS)
SET_ROLE Procedure on page 86-27	Sets role
SET_SQL_TRACE Procedure on page 86-28	Turns tracing on or off

Table 86–1 (Cont.) DBMS_SESSION Package Subprograms

Subprogram	Description
SWITCH_CURRENT_CONSUMER_GROUP Procedure on page 86-29	Facilitates changing the current resource consumer group of a user's current session
UNIQUE_SESSION_ID Function on page 86-30	Returns an identifier that is unique for all sessions currently connected to this database

CLEAR_CONTEXT Procedure

Syntax

```
DBMS_SESSION.CLEAR_CONTEXT
  namespace          VARCHAR2,
  client_identifier  VARCHAR2
  attribute          VARCHAR2);
```

Parameters

Table 86-2 CLEAR_CONTEXT Procedure Parameters

Parameter	Description
namespace	<p>The namespace in which the application context is to be cleared. Required.</p> <p>For a session-local context, namespace must be specified. If namespace is defined as Session Local Context, then client_identifier is optional since it is only associated with a globally accessed context.</p> <p>For a globally accessed context, namespace must be specified. NULL is a valid value for client_identifier because a session with no identifier set can see a context that looks like the (namespace, attribute, value, username, null) set using SET_CONTEXT.</p>
client_identifier	Applies to a global context and is optional for other types of contexts; 64-byte maximum.
attribute	The specific attribute in the namespace to be cleared. Optional. the default is NULL. If you specify attribute as NULL, then (namespace, attribute, value) for that namespace are cleared from the session. If attribute is not specified, then all context information that has the namespace and client_identifier arguments is cleared.

Usage Notes

This procedure must be invoked directly or indirectly by the trusted package.

CLEAR_ALL_CONTEXT Procedure

Syntax

```
DBMS_SESSION.CLEAR_ALL_CONTEXT  
  namespace          VARCHAR2);
```

Parameters

Table 86-3 *CLEAR_ALL_CONTEXT Procedure Parameters*

Parameter	Description
namespace	The namespace where the application context information is to be cleared. Required.

Usage Notes

This procedure must be invoked directly or indirectly by the trusted package.

CLEAR_IDENTIFIER Procedure

This procedure removes the `set_client_id` in the session.

Syntax

```
DBMS_SESSION.CLEAR_IDENTIFIER;
```

Usage Notes

This procedure is executable by public.

CLOSE_DATABASE_LINK Procedure

This procedure closes an open database link. It is equivalent to the following SQL statement:

```
ALTER SESSION CLOSE DATABASE LINK <name>
```

Syntax

```
DBMS_SESSION.CLOSE_DATABASE_LINK (  
    dblink VARCHAR2);
```

Parameters

Table 86–4 *CLOSE_DATABASE_LINK Procedure Parameters*

Parameter	Description
dblink	Name of the database link to close.

FREE_UNUSED_USER_MEMORY Procedure

This procedure reclaims unused memory after performing operations requiring large amounts of memory (more than 100K).

Examples of operations that use large amounts of memory include:

- Large sorting where entire `sort_area_size` is used and `sort_area_size` is hundreds of KB.
- Compiling large PL/SQL packages, procedures, or functions.
- Storing hundreds of KB of data within PL/SQL indexed tables.

You can monitor user memory by tracking the statistics "session UGA memory" and "session PGA memory" in the `v$sesstat` or `v$statname` fixed views. Monitoring these statistics also shows how much memory this procedure has freed.

Note: This procedure should only be used in cases where memory is at a premium. It should be used infrequently and judiciously.

Syntax

```
DBMS_SESSION.FREE_UNUSED_USER_MEMORY;
```

Return Values

The behavior of this procedure depends upon the configuration of the server operating on behalf of the client:

- **Dedicated server:** This returns unused PGA memory and session memory to the operating system. Session memory is allocated from the PGA in this configuration.
- **Shared server:** This returns unused session memory to the `shared_pool`. Session memory is allocated from the `shared_pool` in this configuration.

Usage Notes

In order to free memory using this procedure, the memory must not be in use.

After an operation allocates memory, only the same type of operation can reuse the allocated memory. For example, after memory is allocated for sort, even if the sort is complete and the memory is no longer in use, only another sort can reuse the

sort-allocated memory. For both sort and compilation, after the operation is complete, the memory is no longer in use, and the user can call this procedure to free the unused memory.

An indexed table implicitly allocates memory to store values assigned to the indexed table's elements. Thus, the more elements in an indexed table, the more memory the RDBMS allocates to the indexed table. As long as there are elements within the indexed table, the memory associated with an indexed table is in use.

The scope of indexed tables determines how long their memory is in use. Indexed tables declared globally are indexed tables declared in packages or package bodies. They allocate memory from session memory. For an indexed table declared globally, the memory remains in use for the lifetime of a user's login (lifetime of a user's session), and is freed after the user disconnects from ORACLE.

Indexed tables declared locally are indexed tables declared within functions, procedures, or anonymous blocks. These indexed tables allocate memory from PGA memory. For an indexed table declared locally, the memory remains in use for as long as the user is still running the procedure, function, or anonymous block in which the indexed table is declared. After the procedure, function, or anonymous block is finished running, the memory is then available for other locally declared indexed tables to use (in other words, the memory is no longer in use).

Assigning an uninitialized, "empty" indexed table to an existing index table is a method to explicitly re-initialize the indexed table and the memory associated with the indexed table. After this operation, the memory associated with the indexed table is no longer in use, making it available to be freed by calling this procedure. This method is particularly useful on indexed tables declared globally which can grow during the lifetime of a user's session, as long as the user no longer needs the contents of the indexed table.

The memory rules associated with an indexed table's scope still apply; this method and this procedure, however, allow users to intervene and to explicitly free the memory associated with an indexed table.

Examples

The following PL/SQL illustrates the method and the use of procedure `FREE_UNUSED_USER_MEMORY`.

```
CREATE PACKAGE foobar
  type number_idx_tbl is table of number indexed by binary_integer;

  store1_table number_idx_tbl;    -- PL/SQL indexed table
  store2_table number_idx_tbl;    -- PL/SQL indexed table
```



```
store3_table number_idx_tbl;    -- PL/SQL indexed table
...
END;          -- end of foobar

DECLARE
...
empty_table number_idx_tbl;    -- uninitialized ("empty") version
BEGIN
FOR i in 1..1000000 loop
store1_table(i) := i;          -- load data
END LOOP;
...
store1_table := empty_table;   -- "truncate" the indexed table
...
-
dbms_session.free_unused_user_memory; -- give memory back to system

store1_table(1) := 100;        -- index tables still declared;
store2_table(2) := 200;        -- but truncated.
...
END;
```

IS_ROLE_ENABLED Function

This function determines if the named role is enabled for this session.

Syntax

```
DBMS_SESSION.IS_ROLE_ENABLED (  
    rolename    VARCHAR2)  
RETURN BOOLEAN;
```

Parameters

Table 86–5 *IS_ROLE_ENABLED Function Parameters*

Parameter	Description
rolename	Name of the role.

Return Values

Table 86–6 *IS_ROLE_ENABLED Function Return Values*

Return	Description
is_role_enabled	TRUE or FALSE, depending on whether the role is enabled.

IS_SESSION_ALIVE Function

This function determines if the specified session is active.

Syntax

```
DBMS_SESSION.IS_SESSION_ALIVE (  
    uniqueid VARCHAR2)  
RETURN BOOLEAN;
```

Parameters

Table 86–7 *IS_SESSION_ALIVE Function Parameters*

Parameter	Description
uniqueid	Unique ID of the session: This is the same one as returned by UNIQUE_SESSION_ID.

Return Values

Table 86–8 *IS_SESSION_ALIVE Function Return Values*

Return	Description
is_session_alive	TRUE or FALSE, depending on whether the session is active.

LIST_CONTEXT Procedures

This procedure returns a list of active namespaces and contexts for the current session.

Syntax

```
TYPE AppCtxRecTyp IS RECORD (
    namespace VARCHAR2(30),
    attribute VARCHAR2(30),
    value      VARCHAR2(256));

TYPE AppCtxTabTyp IS TABLE OF AppCtxRecTyp INDEX BY BINARY_INTEGER;

DBMS_SESSION.LIST_CONTEXT (
    list OUT AppCtxTabTyp,
    size OUT NUMBER);
```

Parameters

Table 86–9 LIST_CONTEXT Procedure Parameters

Parameter	Description
list	Buffer to store a list of application context set in the current session.

Return Values

Table 86–10 LIST_CONTEXT Procedure Return Values

Return	Description
list	A list of (namespace, attribute, values) set in current session.
size	Returns the number of entries in the buffer returned.

Usage Notes

The context information in the list appears as a series of <namespace> <attribute> <value>. Because list is a table type variable, its size is dynamically adjusted to the size of returned list.

MODIFY_PACKAGE_STATE Procedure

This procedure can be used to perform various actions (as specified by the `action_flags` parameter) on the session state of all PL/SQL program units active in the session. This takes effect after the PL/SQL call that made the current invocation finishes running. The procedure uses the `DBMS_SESSION` constants listed in [Table 86-12](#).

Syntax

```
DBMS_SESSION.MODIFY_PACKAGE_STATE(  
    action_flags IN PLS_INTEGER);
```

Parameters

Table 86–11 *MODIFY_PACKAGE_STATE Procedure Parameters*

Parameter	Description
action_flags	<p>Bit flags that determine the action taken on PL/SQL program units:</p> <p>DBMS_SESSION.FREE_ALL_RESOURCES (or 1)—frees all memory associated with each of the previously run PL/SQL programs from the session. Clears the current values of any package globals and closes cached cursors. On subsequent use, the PL/SQL program units are reinstantiated and package globals are reinitialized. Invoking <code>MODIFY_PACKAGE_STATE</code> with the <code>DBMS_SESSION.FREE_ALL_RESOURCES</code> parameter provides functionality identical to the <code>DBMS_SESSION.RESET_PACKAGE()</code> interface.</p> <p>DBMS_SESSION.REINITIALIZE (or 2)—reinitializes packages without actually being freed and recreated from scratch. Instead the package memory is reused. In terms of program semantics, the <code>DBMS_SESSION.REINITIALIZE</code> flag is similar to the <code>DBMS_SESSION.FREE_ALL_RESOURCES</code> flag in that both have the effect of reinitializing all packages.</p> <p>However, <code>DBMS_SESSION.REINITIALIZE</code> should exhibit better performance than the <code>DBMS_SESSION.FREE_ALL_RESOURCES</code> option because:</p> <ul style="list-style-type: none"> ▪ Packages are reinitialized without actually being freed and recreated from scratch. Instead the package memory gets reused. ▪ Any open cursors are closed, semantically speaking. However, the cursor resource is not actually freed. It is simply returned to the PL/SQL cursor cache. The cursor cache is not flushed. Hence, cursors corresponding to frequently accessed static SQL in PL/SQL remains cached in the PL/SQL cursor cache and the application does not incur the overhead of opening, parsing, and closing a new cursor for those statements on subsequent use. ▪ The session memory for PL/SQL modules without global state (such as types, stored-procedures) will not be freed and recreated.

Usage Notes

See the parameter descriptions in [Table 86-11](#) for the differences between the flags and why `DBMS_SESSION.REINITIALIZE` exhibits better performance than `DBMS_SESSION.FREE_ALL_RESOURCES`.

Table 86-12 *Action_flags Constants for MODIFY_PACKAGE_STATE*

Constant	Description
<code>FREE_ALL_RESOURCES</code>	<code>PLS_INTEGER := 1</code>
<code>REINITIALIZE</code>	<code>PLS_INTEGER := 2</code>

- Reinitialization refers to the process of resetting all package variables to their initial values and running the initialization block (if any) in the package bodies. Consider the package:

```

package P is
  n number;
  m number := P2.foo;
  d date := SYSDATE;
  cursor c is select * from emp;
  procedure bar;
end P;
/
package body P is
  v varchar2(20) := 'hello';
  procedure bar is
  begin
    ...
  end;
  procedure init_pkg is
  begin
    ....
  end;
begin
  -- initialization block
  init_pkg;
  ...
  ...
end P;
/

```

For the package P, reinitialization involves:

- Setting `P.n` to `NULL`
 - Invoking function `P2.foo` and setting `P.m` to the value returned from `P2.foo`
 - Setting `P.d` to the return value of `SYSDATE` built-in
 - Closing cursor `P.c` if it was previously opened
 - Setting `P.v` to 'hello'
 - Running the initialization block in the package body
- The reinitialization for a package is done only if the package is actually referenced subsequently. Furthermore, the packages are reinitialized in the order in which they are referenced subsequently.
 - When using `FREE_ALL_RESOURCES` or `REINITIALIZE`, make sure that resetting package variable values does not affect the application.
 - Because `DBMS_SESSION.REINITIALIZE` does not actually cause all the package state to be freed, in some situations, the application could use significantly more session memory than if the `FREE_ALL_RESOURCES` flag or the `RESET_PACKAGE` procedure had been used. For instance, after performing `DBMS_SESSION.MODIFY_PACKAGE_STATE(DBMS_SESSION.REINITIALIZE)`, if the application does not refer to many of the packages that were previously referenced, then the session memory for those packages will remain until the end of the session (or until `DBMS_SESSION.RESET_PACKAGE` is called).
 - Because the client-side PL/SQL code cannot reference remote package variables or constants, you must explicitly use the values of the constants. For example, `DBMS_SESSION.MODIFY_PACKAGE_STATE(DBMS_SESSION.REINITIALIZE)` does not compile on the client because it uses the constant `DBMS_SESSION.REINITIALIZE`.
 Instead, use `DBMS_SESSION.MODIFY_PACKAGE_STATE(2)` on the client, because the argument is explicitly provided.

Examples

This example illustrates the use of `DBMS_SESSION.MODIFY_PACKAGE_STATE`. Consider a package `P` with some global state (a cursor `c` and a number `cnt`). When the package is first initialized, the package variable `cnt` is 0 and the cursor `c` is `CLOSED`. Then, in the session, change the value of `cnt` to 111 and also execute an `OPEN` operation on the cursor. If you call `print_status` to display the state of the package, you see that `cnt` is 111 and that the cursor is `OPEN`. Next, call `DBMS_`

SESSION.MODIFY_PACKAGE_STATE. If you print the status of the package P again using print_status, you see that cnt is 0 again and the cursor is CLOSED. If the call to DBMS_SESSION.MODIFY_PACKAGE_STATE had not been made, then the second print_status would have printed 111 and OPEN.

```
create or replace package P is
  cnt    number := 0;
  cursor c is select * from emp;
  procedure print_status;
end P;
/
show errors;
```

```
create or replace package body P is
  procedure print_status is
  begin
    dbms_output.put_line('P.cnt = ' || cnt);
    if c%ISOPEN then
      dbms_output.put_line('P.c is OPEN');
    else
      dbms_output.put_line('P.c is CLOSED');
    end if;
  end;
end P;
/
show errors;
```

```
SQL> set serveroutput on;
SQL> begin
  2  P.cnt := 111;
  3  open p.c;
  4  P.print_status;
  5  end;
  6  /
```

```
P.cnt = 111
P.c is OPEN
```

PL/SQL procedure successfully completed.

```
SQL> begin
  2  dbms_session.modify_package_state(dbms_session.reinitialize);
  3  end;
  4  /
```

PL/SQL procedure successfully completed.

```
SQL> set serveroutput on;
SQL>
SQL> begin
  2   P.print_status;
  3   end;
  4   /
P.cnt = 0
P.c is CLOSED

PL/SQL procedure successfully completed.
```

RESET_PACKAGE Procedure

This procedure deinstantiates all packages in this session. It frees the package state.

Note: See "[MODIFY_PACKAGE_STATE Procedure](#)" on page 86-15. The `MODIFY_PACKAGE_STATE` interface, introduced in Oracle9i, provides an equivalent of the `RESET_PACKAGE` capability. It is an efficient, lighter-weight variant for reinitializing the state of all PL/SQL packages in the session.

Memory used for caching the execution state is associated with all PL/SQL functions, procedures, and packages that were run in a session.

For packages, this collection of memory holds the current values of package variables and controls the cache of cursors opened by the respective PL/SQL programs. A call to `RESET_PACKAGE` frees the memory associated with each of the previously run PL/SQL programs from the session, and, consequently, clears the current values of any package globals and closes any cached cursors.

`RESET_PACKAGE` can also be used to reliably restart a failed program in a session. If a program containing package variables fails, then it is hard to determine which variables need to be reinitialized. `RESET_PACKAGE` guarantees that all package variables are reset to their initial values.

Syntax

```
DBMS_SESSION.RESET_PACKAGE;
```

Usage Notes

Because the amount of memory consumed by all executed PL/SQL can become large, you might use `RESET_PACKAGE` to trim down the session memory footprint at certain points in your database application. However, make sure that resetting package variable values will not affect the application. Also, remember that later execution of programs that have lost their cached memory and cursors will perform slower, because they need to re-create the freed memory and cursors.

`RESET_PACKAGE` does not free the memory, cursors, and package variables immediately when called.

Note: `RESET_PACKAGE` only frees the memory, cursors, and package variables *after* the PL/SQL call that made the invocation finishes running.

For example, PL/SQL procedure P1 calls PL/SQL procedure P2, and P2 calls `RESET_PACKAGE`. The `RESET_PACKAGE` effects do not occur until procedure P1 finishes execution (the PL/SQL call ends).

Examples

This SQL*Plus script runs a large program with many PL/SQL program units that may or may not use global variables, but it doesn't need them beyond this execution:

```
EXECUTE large_plsql_program1;
```

To free up PL/SQL cached session memory:

```
EXECUTE DBMS_SESSION.RESET_PACKAGE;
```

To run another large program:

```
EXECUTE large_plsql_program2;
```

SET_CONTEXT Procedure

This procedure sets the context, of which there are four types: session local, globally initialized, externally initialized, and globally accessed.

Of its five parameters, only the first three are required; the final two parameters are optional, used only in globally accessed contexts. Further parameter information appears in the parameter table and the usage notes.

Syntax

```
DBMS_SESSION.SET_CONTEXT (
    namespace VARCHAR2,
    attribute  VARCHAR2,
    value      VARCHAR2,
    username   VARCHAR2,
    client_id  VARCHAR2 );
```

Parameters

Table 86–13 SET_CONTEXT Procedure Parameters

Parameter	Description
namespace	The namespace of the application context to be set, limited to 30 bytes.
attribute	The attribute of the application context to be set, limited to 30 bytes.
value	The value of the application context to be set, limited to 4 kilobytes.
username	The database username attribute of the application context. Default: NULL
client_id	The application-specific client_id attribute of the application context (64-byte maximum). Default: NULL

Usage Notes

Note the following:

- For 8i compatibility, only the first three parameters are used.
- The first three parameters are required for all types of context.

- The `username` parameter must be a valid SQL identifier
- The `client_id` parameter must be a string of at most 64 bytes. It is case-sensitive and must match the argument provided for `set_identifier`.
- If the `namespace` parameter is a global context namespace, then the `username` parameter is matched against the current database user name in the session, and the `client_id` parameter will be matched against the current `client_id` in the session. If these parameters are not set, NULL is assumed, enabling any user to see the context values.
- This procedure must be invoked directly or indirectly by the trusted package
- The caller of SET_CONTEXT must be in the calling stack of a procedure that has been associated to the context namespace through a CREATE CONTEXT statement. The checking of the calling stack does not cross a DBMS boundary.
- No limit applies to the number of attributes that can be set in a namespace. An attribute retains its value during the user's session unless it is reset by the user.

SET_IDENTIFIER

This procedure sets the client ID in the session.

Syntax

```
DBMS_SESSION.SET_IDENTIFIER (  
    client_id VARCHAR2);
```

Parameters

Table 86–14 SET_IDENTIFIER Procedure Parameters

Parameter	Description
client_id	The application-specific identifier of the current database session.

Usage Notes

Note the following:

- SET_IDENTIFIER initializes the current session with a client identifier to identify the associated global application context
- client_id is case sensitive; it must match the client_id parameter in the set_context
- This procedure is executable by public

SET_NLS Procedure

This procedure sets up your Globalization Support (NLS). It is equivalent to the following SQL statement:

```
ALTER SESSION SET <nls_parameter> = <value>
```

Syntax

```
DBMS_SESSION.SET_NLS (  
    param VARCHAR2,  
    value VARCHAR2);
```

Parameters

Table 86–15 *SET_NLS Procedure Parameters*

Parameter	Description
param	Globalization Support parameter. The parameter name must begin with 'NLS'.
value	Parameter value. If the parameter is a text literal, then it needs embedded single-quotes. For example, "set_nls(nls_date_format,'''DD-MON-YY''")".

SET_ROLE Procedure

This procedure enables and disables roles. It is equivalent to the `SET ROLE SQL` statement.

Syntax

```
DBMS_SESSION.SET_ROLE (  
    role_cmd VARCHAR2);
```

Parameters

Table 86–16 *SET_ROLE Procedure Parameters*

Parameter	Description
role_cmd	This text is appended to "set role" and then run as SQL.

SET_SQL_TRACE Procedure

This procedure turns tracing on or off. It is equivalent to the following SQL statement:

```
ALTER SESSION SET SQL_TRACE ...
```

Syntax

```
DBMS_SESSION.SET_SQL_TRACE (  
    sql_trace boolean);
```

Parameters

Table 86–17 SET_SQL_TRACE Procedure Parameters

Parameter	Description
sql_trace	TRUE turns tracing on, FALSE turns tracing off.

SWITCH_CURRENT_CONSUMER_GROUP Procedure

This procedure changes the current resource consumer group of a user's current session.

This lets you switch to a consumer group if you have the switch privilege for that particular group. If the caller is another procedure, then this enables the user to switch to a consumer group for which the owner of that procedure has switch privilege.

Syntax

```
DBMS_SESSION.switch_current_consumer_group (
    new_consumer_group      IN VARCHAR2,
    old_consumer_group      OUT VARCHAR2,
    initial_group_on_error  IN  BOOLEAN);
```

Parameters

Table 86–18 SWITCH_CURRENT_CONSUMER_GROUP Procedure Parameters

Parameter	Description
<code>new_consumer_group</code>	Name of consumer group to which you want to switch.
<code>old_consumer_group</code>	Name of the consumer group from which you just switched out.
<code>initial_group_on_error</code>	If TRUE, then sets the current consumer group of the caller to his/her initial consumer group in the event of an error.

Return Values

This procedure outputs the old consumer group of the user in the parameter `old_consumer_group`.

Note: You can switch back to the old consumer group later using the value returned in `old_consumer_group`.

UNIQUE_SESSION_ID Function

This function returns an identifier that is unique for all sessions currently connected to this database. Multiple calls to this function during the same session always return the same result.

Syntax

```
DBMS_SESSION.UNIQUE_SESSION_ID  
RETURN VARCHAR2;
```

Pragmas

```
pragma restrict_references(unique_session_id,WNDS,RNDS,WNPS);
```

Return Values

Table 86–19 UNIQUE_SESSION_ID Function Return Values

Return	Description
unique_session_ id	Returns up to 24 bytes.

Exceptions

Table 86–20 SWITCH_CURRENT_CONSUMER_GROUP Procedure Exceptions

Exception	Description
29368	Non-existent consumer group.
1031	Insufficient privileges.
29396	Cannot switch to OTHER_GROUPS consumer group.

Usage Notes

The owner of a procedure must have privileges on the group from which a user was switched (`old_consumer_group`) in order to switch them back. There is one exception: The procedure can always switch the user back to his/her initial consumer group (skipping the privilege check).

By setting `initial_group_on_error` to `TRUE`, `SWITCH_CURRENT_CONSUMER_GROUP` puts the current session into the default group, if it can't put it into the group

designated by `new_consumer_group`. The error associated with the attempt to move a session into `new_consumer_group` is raised, even though the current consumer group has been changed to the initial consumer group.

Examples

```
CREATE OR REPLACE PROCEDURE high_priority_task is
  old_group varchar2(30);
  prev_group varchar2(30);
  curr_user varchar2(30);
BEGIN
  -- switch invoker to privileged consumer group. If we fail to do so, an
  -- error will be thrown, but the consumer group will not change
  -- because 'initial_group_on_error' is set to FALSE

  dbms_session.switch_current_consumer_group('tkrogrp1', old_group, FALSE);
  -- set up exception handler (in the event of an error, we do not want to
  -- return to caller while leaving the session still in the privileged
  -- group)

  BEGIN
    -- perform some operations while under privileged group

  EXCEPTION
    WHEN OTHERS THEN
      -- It is possible that the procedure owner does not have privileges
      -- on old_group. 'initial_group_on_error' is set to TRUE to make sure
      -- that the user is moved out of the privileged group in such a
      -- situation

      dbms_session.switch_current_consumer_group(old_group,prev_group,TRUE);
      RAISE;
    END;

  -- we've succeeded. Now switch to old_group, or if cannot do so, switch
  -- to caller's initial consumer group

  dbms_session.switch_current_consumer_group(old_group,prev_group,TRUE);
END high_priority_task;
/
```

DBMS_SHARED_POOL

The `DBMS_SHARED_POOL` package provides access to the shared pool, which is the shared memory area where cursors and PL/SQL objects are stored. `DBMS_SHARED_POOL` enables you to display the sizes of objects in the shared pool, and mark them for keeping or unkeeping in order to reduce memory fragmentation.

This chapter contains the following topics:

- [Using DBMS_SHARED_POOL](#)
 - [Overview](#)
 - [Operational Notes](#)
- [Summary of DBMS_SHARED_POOL Subprograms](#)

Using DBMS_SHARED_POOL

- [Overview](#)
- [Operational Notes](#)

Overview

The procedures provided here may be useful when loading large PL/SQL objects. When large PL/SQL objects are loaded, users response time is affected because of the large number of smaller objects that need to be aged out from the shared pool to make room (due to memory fragmentation). In some cases, there may be insufficient memory to load the large objects.

DBMS_SHARED_POOL is also useful for frequently executed triggers. You may want to keep compiled triggers on frequently used tables in the shared pool.

Additionally, DBMS_SHARED_POOL supports sequences. Sequence numbers are lost when a sequence is aged out of the shared pool. DBMS_SHARED_POOL is useful for keeping sequences in the shared pool and thus preventing the loss of sequence numbers.

Operational Notes

To create DBMS_SHARED_POOL, run the DBMSPOOL.SQL script. The PRVTPPOOL.PLB script is automatically executed after DBMSPOOL.SQL runs. These scripts are *not* run by CATPROC.SQL.

Summary of DBMS_SHARED_POOL Subprograms

Table 87-1 DBMS_SHARED_POOL Package Subprograms

Subprogram	Description
ABORTED_REQUEST_THRESHOLD Procedure on page 87-4	Sets the aborted request threshold for the shared pool
KEEP Procedure on page 87-5	Keeps an object in the shared pool
SIZES Procedure on page 87-7	Shows objects in the shared pool that are larger than the specified size
UNKEEP Procedure on page 87-8	Unkeeps the named object

ABORTED_REQUEST_THRESHOLD Procedure

This procedure sets the aborted request threshold for the shared pool.

Syntax

```
DBMS_SHARED_POOL.ABORTED_REQUEST_THRESHOLD (  
    threshold_size NUMBER);
```

Parameters

Table 87–2 ABORTED_REQUEST_THRESHOLD Procedure Parameters

Parameter	Description
threshold_size	Size, in bytes, of a request which does not try to free unpinned (not "unkeep-ed") memory within the shared pool. The range of threshold_size is 5000 to ~2 GB inclusive.

Exceptions

An exception is raised if the threshold is not in the valid range.

Usage Notes

Usually, if a request cannot be satisfied on the free list, then the RDBMS tries to reclaim memory by freeing objects from the LRU list and checking periodically to see if the request can be fulfilled. After finishing this step, the RDBMS has performed a near equivalent of an 'ALTER SYSTEM FLUSH SHARED_POOL'.

Because this impacts all users on the system, this procedure "localizes" the impact to the process failing to find a piece of shared pool memory of size greater than thresh_hold size. This user gets the 'out of memory' error without attempting to search the LRU list.

KEEP Procedure

This procedure keeps an object in the shared pool. Once an object has been kept in the shared pool, it is not subject to aging out of the pool. This may be useful for frequently used large objects. When large objects are brought into the shared pool, several objects may need to be aged out to create a contiguous area large enough.

Syntax

```
DBMS_SHARED_POOL.KEEP (
    name VARCHAR2,
    flag CHAR      DEFAULT 'P');
```

Parameters

Table 87–3 KEEP Procedure Parameters

Parameter	Description
name	<p>Name of the object to keep.</p> <p>The value for this identifier is the concatenation of the address and hash_value columns from the v\$sqlarea view. This is displayed by the SIZES procedure.</p> <p>Currently, TABLE and VIEW objects may not be kept.</p>
flag	<p>(Optional) If this is not specified, then the package assumes that the first parameter is the name of a package/procedure/function and resolves the name.</p> <p>Set to 'P' or 'p' to fully specify that the input is the name of a package/procedure/function.</p> <p>Set to 'T' or 't' to specify that the input is the name of a type.</p> <p>Set to 'R' or 'r' to specify that the input is the name of a trigger.</p> <p>Set to 'Q' or 'q' to specify that the input is the name of a sequence.</p> <p>In case the first argument is a cursor address and hash-value, the parameter should be set to any character except 'P' or 'p' or 'Q' or 'q' or 'R' or 'r' or 'T' or 't'.</p>

Exceptions

An exception is raised if the named object cannot be found.

Usage Notes

There are two kinds of objects:

- PL/SQL objects, triggers, sequences, and types which are specified by name
- SQL cursor objects which are specified by a two-part number (indicating a location in the shared pool).

For example:

```
DBMS_SHARED_POOL.KEEP('scott.hispackage')
```

This keeps package `HISPACKAGE`, owned by `SCOTT`. The names for PL/SQL objects follow SQL rules for naming objects (for example, delimited identifiers and multibyte names are allowed). A cursor can be kept by `DBMS_SHARED_POOL.KEEP('0034CFFF, 20348871')`. The complete hexadecimal address must be in the first 8 characters.

SIZES Procedure

This procedure shows objects in the `shared_pool` that are larger than the specified size. The name of the object is also given, which can be used as an argument to either the `KEEP` or `UNKEEP` calls.

Syntax

```
DBMS_SHARED_POOL.SIZES (  
    minsize NUMBER);
```

Parameters

Table 87–4 SIZES Procedure Parameters

Parameter	Description
<code>minsize</code>	Size, in kilobytes, over which an object must be occupying in the shared pool, in order for it to be displayed.

Usage Notes

Issue the `SQLDBA` or `SQLPLUS` `'SET SERVEROUTPUT ON SIZE XXXXX'` command prior to using this procedure so that the results are displayed.

UNKEEP Procedure

This procedure unkeeps the named object.

Syntax

```
DBMS_SHARED_POOL.UNKEEP (  
    name VARCHAR2,  
    flag CHAR      DEFAULT 'P');
```

Caution: This procedure may not be supported in the future if automatic mechanisms are implemented to make this unnecessary.

Parameters

Table 87–5 UNKEEP Procedure Parameters

Parameter	Description
name	Name of the object to unkeep. See description of the name object for the <code>KEEP</code> procedure.
flag	See description of the flag parameter for the <code>KEEP</code> procedure.

Exceptions

An exception is raised if the named object cannot be found.

The `DBMS_SPACE` package enables you to analyze segment growth and space requirements.

This chapter contains the following topics:

- [Using DBMS_SPACE](#)
 - [Security Model](#)
- [Summary of DBMS_SPACE Subprograms](#)

Using DBMS_SPACE

- [Security Model](#)

Security Model

This package runs with `SYS` privileges. The execution privilege is granted to `PUBLIC`. Subprograms in this package run under the caller security. The user must have `ANALYZE` privilege on the object.

Summary of DBMS_SPACE Subprograms

Table 88–1 DBMS_SPACE Package Subprograms

Subprogram	Description
CREATE_INDEX_COST Procedure on page 88-4	Determines the cost of creating an index on an existing table
CREATE_TABLE_COST Procedures on page 88-5	Determines the size of the table given various attributes.
FREE_BLOCKS Procedure on page 88-7	Returns information about free blocks in an object (table, index, or cluster)
OBJECT_DEPENDENT_SEGMENTS Function on page 88-10	Returns the list of segments that are associated with the object
OBJECT_GROWTH_TREND Function on page 88-13	A table function where each row describes the space usage of the object at a specific point in time
SPACE_USAGE Procedure on page 88-15	Returns information about free blocks in a auto segment space managed segment
UNUSED_SPACE Procedure on page 88-18	Returns information about unused space in an object (table, index, or cluster)

CREATE_INDEX_COST Procedure

This procedure determines the cost of creating an index on an existing table. The input is the DDL statement that will be used to create the index. The procedure will output the storage required to create the index.

Syntax

```
DBMS_SPACE.CREATE_INDEX_COST (  
    ddl          IN    VARCHAR2,  
    used_bytes   OUT   NUMBER,  
    alloc_bytes  OUT   NUMBER,  
    plan_table   IN    VARCHAR2 DEFAULT NULL);
```

Pragmas

```
pragma restrict_references(free_blocks,WNDS);
```

Parameters

Table 88–2 CREATE_INDEX_COST Procedure Parameters

Parameter	Description
ddl	The create index DDL statement
used_bytes	The number of bytes representing the actual index data
alloc_bytes	Size of the index when created in the tablespace
plan_table	Which plan table to use, default NULL

Usage Notes

- The table on which the index is created must already exist.
- The computation of the index size depends on statistics gathered on the segment.
- It is imperative that the table must have been analyzed recently.
- In the absence of correct statistics, the results may be inaccurate, although the procedure will not raise any errors.

CREATE_TABLE_COST Procedures

This procedure is used in capacity planning to determine the size of the table given various attributes. The size of the object can vary widely based on the tablespace storage attributes, tablespace block size, and so on. There are two overloads of this procedure.

- The first version takes the column information of the table as argument and output the table size.
- The second version takes the average row size of the table and outputs the table size.

This procedure can be used on tablespace of dictionary managed and locally managed extent management as well as manual and auto segment space management.

Syntax

```

DBMS_SPACE.CREATE_TABLE_COST (
    tablespace_name    IN VARCHAR2,
    avg_row_size       IN NUMBER,
    row_count          IN NUMBER,
    pct_free           IN NUMBER,
    used_bytes         OUT NUMBER,
    alloc_bytes        OUT NUMBER);

DBMS_SPACE.CREATE_TABLE_COST (
    tablespace_name    IN VARCHAR2,
    colinfos           IN CREATE_TABLE_COST_COLUMNS,
    row_count          IN NUMBER,
    pct_free           IN NUMBER,
    used_bytes         OUT NUMBER,
    alloc_bytes        OUT NUMBER);

CREATE TYPE create_table_cost_colinfo IS OBJECT (
    COL_TYPE    VARCHAR(200),
    COL_SIZE    NUMBER);

```

Parameters

Table 88–3 *FREE_BLOCKS Procedure Parameters*

Parameter	Description
<code>tablespace_name</code>	The tablespace in which the object will be created. The default is <code>SYSTEM</code> tablespace.
<code>avg_row_size</code>	The anticipated average row size in the table.
<code>colinfos</code>	The description of the columns.
<code>row_count</code>	The anticipated number of rows in the table .
<code>pct_free</code>	The percentage of free space in each block for future expansion of existing rows due to updates.
<code>used_bytes</code>	The space used by user data.
<code>alloc_bytes</code>	The size of the object taking into account the tablespace extent characteristics.

Usage Notes

- The `used_bytes` represent the actual bytes used by the data. This includes the overhead due to the block metadata, `pctfree` etc.
- The `alloc_bytes` represent the size of the table when it is created in the tablespace. This takes into account, the size of the extents in the tablespace and tablespace extent management properties.

FREE_BLOCKS Procedure

This procedure returns information about free blocks in an object (table, index, or cluster). See "[SPACE_USAGE Procedure](#)" for returning free block information in a auto segment space managed segment.

Syntax

```
DBMS_SPACE.FREE_BLOCKS (
  segment_owner      IN  VARCHAR2,
  segment_name       IN  VARCHAR2,
  segment_type       IN  VARCHAR2,
  freelist_group_id  IN  NUMBER,
  free_blks          OUT NUMBER,
  scan_limit         IN  NUMBER DEFAULT NULL,
  partition_name     IN  VARCHAR2 DEFAULT NULL);
```

Pragmas

```
pragma restrict_references(free_blocks,WNDS);
```

Parameters

Table 88–4 *FREE_BLOCKS Procedure Parameters*

Parameter	Description
segment_owner	Schema name of the segment to be analyzed.
segment_name	Segment name of the segment to be analyzed.

Table 88–4 (Cont.) FREE_BLOCKS Procedure Parameters

Parameter	Description
segment_type	Type of the segment to be analyzed (TABLE, INDEX, or CLUSTER): TABLE TABLE PARTITION TABLE SUBPARTITION INDEX INDEX PARTITION INDEX SUBPARTITION CLUSTER LOB LOB PARTITION LOB SUBPARTITION
freelist_group_id	Freelist group (instance) whose free list size is to be computed.
free_blks	Returns count of free blocks for the specified group.
scan_limit	Maximum number of free list blocks to read (optional). Use a scan limit of X you are interested only in the question, "Do I have X blocks on the free list?"
partition_name	Partition name of the segment to be analyzed. This is only used for partitioned tables; the name of subpartition should be used when partitioning is composite.

Examples

Example 1

The following declares the necessary bind variables and executes.

```
DBMS_SPACE.UNUSED_SPACE('SCOTT', 'EMP', 'TABLE', :total_blocks,
    :total_bytes, :unused_blocks, :unused_bytes, :lastextf,
    :last_extb, :lastusedblock);
```

This fills the unused space information for bind variables in EMP table in SCOTT schema.

Example 2

The following uses the CLUS cluster in SCOTT schema with 4 freelist groups. It returns the number of blocks in freelist group 3 in CLUS.

```
DBMS_SPACE.FREE_BLOCKS('SCOTT', 'CLUS', 'CLUSTER', 3, :free_blocks);
```

Note: An error is raised if `scan_limit` is not a positive number.

OBJECT_DEPENDENT_SEGMENTS Function

This table function, given an object, returns the list of segments that are associated with the object.

Syntax

```
DBMS_SPACE.OBJECT_DEPENDENT_SEGMENTS(  
    objowner    IN    VARCHAR2,  
    objname     IN    VARCHAR2,  
    partname    IN    VARCHAR2,  
    objtype     IN    NUMBER)  
RETURN dependent_segments_table PIPELINED;
```

Parameters

Table 88–5 *OBJECT_DEPENDENT_SEGMENTS Function Parameters*

Parameter	Description
objowner	The schema containing the object.
objname	The name of the object.
partname	The name of the partition.

Table 88–5 (Cont.) OBJECT_DEPENDENT_SEGMENTS Function Parameters

Parameter	Description
objtype	<p>Type of the object:</p> <ul style="list-style-type: none"> ■ OBJECT_TYPE_TABLE constant positive := 1; ■ OBJECT_TYPE_NESTED_TABLE constant positive := 2; ■ OBJECT_TYPE_INDEX constant positive := 3; ■ OBJECT_TYPE_CLUSTER constant positive := 4; ■ OBJECT_TYPE_TABLE_PARTITION constant positive := 7; ■ OBJECT_TYPE_INDEX_PARTITION constant positive := 8; ■ OBJECT_TYPE_TABLE_SUBPARTITION constant positive := 9; ■ OBJECT_TYPE_INDEX_SUBPARTITION constant positive := 10; ■ OBJECT_TYPE_MV constant positive := 13; ■ OBJECT_TYPE_MVLOG constant positive := 14;

Return Values

The content of one row of a dependent_segments_table:

```
TYPE object_dependent_segment IS RECORD (
    segment_owner    VARCHAR2(100),
    segment_name     VARCHAR2(100),
    segment_type     VARCHAR2(100),
    tablespace_name  VARCHAR2(100),
    partition_name   VARCHAR2(100));
```

Table 88–6 OBJECT_DEPENDENT_SEGMENT Type Parameters

Parameter	Description
segment_owner	The schema containing the segment.
segment_name	The name of the segment.

Table 88–6 (Cont.) OBJECT_DEPENDENT_SEGMENT Type Parameters

Parameter	Description
<code>segment_type</code>	The type of the segment, such as table, index or LOB.
<code>partition_name</code>	The name of the partition, if any.

OBJECT_GROWTH_TREND Function

This is a table function. The output will be in the form of one or more rows where each row describes the space usage of the object at a specific point in time. Either the space usage totals will be retrieved from Automatic Workload Repository Facilities (AWRF), or the current space usage will be computed and combined with space usage deltas retrieved from AWRF.

Syntax

```
DBMS_SPACE.OBJECT_GROWTH_TREND (
  object_owner      IN   VARCHAR2,
  object_name       IN   VARCHAR2,
  object_type       IN   VARCHAR2,
  partition_name    IN   VARCHAR2 DEFAULT NULL,
  start_time        IN   TIMESTAMP DEFAULT NULL,
  end_time          IN   TIMESTAMP DEFAULT NULL,
  interval          IN   DSINTERVAL_UNCONSTRAINED DEFAULT NULL,
  skip_interpolated IN   VARCHAR2 DEFAULT 'FALSE',
  timeout_seconds   IN   NUMBER DEFAULT NULL,
  single_datapoint_flag IN VARCHAR2 DEFAULT 'TRUE')
RETURN object_growth_trend_table PIPELINED;
```

Parameters

Table 88-7 OBJECT_GROWTH_TREND Function Parameters

Parameter	Description
object_owner	The schema containing the object.
object_name	The name of the object.
object_type	The name of the object.
partition_name	The name of the partition.
start_time	Statistics generated after this time will be used in regenerating the growth trend.
end_time	Statistics generated until this time will be used in generating the growth trend.
interval	The interval at which to sample.
skip_interpolated	Whether interpolation of missing values should be skipped.

Table 88–7 (Cont.) OBJECT_GROWTH_TREND Function Parameters

Parameter	Description
timeout_seconds	The timeout value for the function in seconds.
single_data_point_flag	Whether in the absence of statistics the segment should be sampled.

Return Values

The `object_growth_trend_row` and `object_growth_trend_table` are used by the `OBJECT_GROWTH_TREND` table function to describe its output.

```
TYPE object_growth_trend_row IS RECORD(
    timepoint      TIMESTAMP,
    space_usage    NUMBER,
    space_alloc    NUMBER,
    quality        VARCHAR(20));
```

Table 88–8 OBJECT_GROWTH_TREND_ROW Type Parameters

Parameter	Description
timepoint	The time at which the statistic was recorded.
space_usage	The size of the segment including overhead and unused space.
space_alloc	The space used by data.
quality	The quality of result: "GOOD", "INTERPOLATED", "PROJECTION".

```
TYPE object_growth_trend_table IS TABLE OF object_growth_trend_row;
```

SPACE_USAGE Procedure

This procedure shows the space usage of data blocks under the segment High Water Mark. The bitmap blocks, segment header, and extent map blocks are not accounted for by this procedure. This procedure can only be used on tablespaces that are created with auto segment space management.

Syntax

```
DBMS_SPACE.SPACE_USAGE(
  segment_owner      IN  VARCHAR2,
  segment_name       IN  VARCHAR2,
  segment_type       IN  VARCHAR2,
  unformatted_blocks OUT NUMBER,
  unformatted_bytes  OUT NUMBER,
  fs1_blocks         OUT NUMBER,
  fs1_bytes         OUT NUMBER,
  fs2_blocks         OUT NUMBER,
  fs2_bytes         OUT NUMBER,
  fs3_blocks         OUT NUMBER,
  fs3_bytes         OUT NUMBER,
  fs4_blocks         OUT NUMBER,
  fs4_bytes         OUT NUMBER,
  full_blocks        OUT NUMBER,
  full_bytes         OUT NUMBER,
  partition_name     IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 88–9 SPACE_USAGE Procedure Parameters

Parameter	Description
segment_owner	Schema name of the segment to be analyzed
segment_name	Name of the segment to be analyzed
partition_name	Partition name of the segment to be analyzed
segment_type	Type of the segment to be analyzed (TABLE, INDEX, or CLUSTER)
unformatted_blocks	Total number of blocks that are unformatted
unformatted bytes	Total number of bytes that are unformatted

Table 88–9 (Cont.) SPACE_USAGE Procedure Parameters

Parameter	Description
fs1_blocks	Number of blocks that has at least 0 to 25% free space
fs1_bytes	Number of bytes that has at least 0 to 25% free space
fs2_blocks	Number of blocks that has at least 25 to 50% free space
fs2_bytes	Number of bytes that has at least 25 to 50% free space
fs3_blocks	Number of blocks that has at least 50 to 75% free space
fs3_bytes	Number of bytes that has at least 50 to 75% free space
fs4_blocks	Number of blocks that has at least 75 to 100% free space
fs4_bytes	Number of bytes that has at least 75 to 100% free space
full_blocks	Total number of blocks that are full in the segment
full_bytes	Total number of bytes that are full in the segment

Examples

```

variable unf number;
variable unfb number;
variable fs1 number;
variable fs1b number;
variable fs2 number;
variable fs2b number;
variable fs3 number;
variable fs3b number;
variable fs4 number;
variable fs4b number;
variable full number;
variable fullb number;

begin
dbms_space.space_usage('U1', 'T',
                      'TABLE',
                      :unf, :unfb,
                      :fs1, :fs1b,
                      :fs2, :fs2b,
                      :fs3, :fs3b,
                      :fs4, :fs4b,
                      :full, :fullb);

end;
/

```

```
print unf ;
print unfb ;
print fs4 ;
print fs4b;
print fs3 ;
print fs3b;
print fs2 ;
print fs2b;
print fs1 ;
print fs1b;
print full;
print fullb;
```

UNUSED_SPACE Procedure

This procedure returns information about unused space in an object (table, index, or cluster).

Syntax

```
DBMS_SPACE.UNUSED_SPACE (  
    segment_owner      IN VARCHAR2,  
    segment_name       IN VARCHAR2,  
    segment_type       IN VARCHAR2,  
    total_blocks       OUT NUMBER,  
    total_bytes        OUT NUMBER,  
    unused_blocks      OUT NUMBER,  
    unused_bytes       OUT NUMBER,  
    last_used_extent_file_id OUT NUMBER,  
    last_used_extent_block_id OUT NUMBER,  
    last_used_block    OUT NUMBER,  
    partition_name     IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 88–10 *UNUSED_SPACE Procedure Parameters*

Parameter	Description
segment_owner	Schema name of the segment to be analyzed.
segment_name	Segment name of the segment to be analyzed.

Table 88–10 UNUSED_SPACE Procedure Parameters

Parameter	Description
segment_type	Type of the segment to be analyzed (TABLE, INDEX, or CLUSTER): <ul style="list-style-type: none"> ■ TABLE ■ TABLE PARTITION ■ TABLE SUBPARTITION ■ INDEX ■ INDEX PARTITION ■ INDEX SUBPARTITION ■ CLUSTER ■ LOB ■ LOB PARTITION ■ LOB SUBPARTITION
total_blocks	Returns total number of blocks in the segment.
total_bytes	Returns total number of blocks in the segment, in bytes.
unused_blocks	Returns number of blocks which are not used.
unused_bytes	Returns, in bytes, number of blocks which are not used.
last_used_extent_file_id	Returns the file ID of the last extent which contains data.
last_used_extent_block_id	Returns the block ID of the last extent which contains data.
last_used_block	Returns the last block within this extent which contains data.
partition_name	Partition name of the segment to be analyzed. This is only used for partitioned tables; the name of subpartition should be used when partitioning is compose.

DBMS_SPACE_ADMIN

The DBMS_SPACE_ADMIN package provides functionality for locally managed tablespaces.

See Also: *Oracle Database Administrator's Guide* for an example and description of using DBMS_SPACE_ADMIN.

This chapter contains the following topics:

- [Using DBMS_SPACE_ADMIN](#)
 - [Security Model](#)
 - [Constants](#)
 - [Operational Notes](#)
- [Summary of DBMS_SPACE_ADMIN Subprograms](#)

Using DBMS_SPACE_ADMIN

- [Security Model](#)
- [Constants](#)
- [Operational Notes](#)

Security Model

This package runs with `SYS` privileges; therefore, any user who has privilege to execute the package can manipulate the bitmaps.

Constants

Table 89–1 DBMS_SPACE_ADMIN Constants

Constant	Description
SEGMENT_VERIFY Procedure	Verifies that the space owned by segment is appropriately reflected in the bitmap as used.
<code>SEGMENT_VERIFY_EXTENTS_GLOBAL</code>	Verifies that the space owned by segment is appropriately reflected in the bitmap as used and that no other segment claims any of this space to be used by it.
<code>SEGMENT_MARK_CORRUPT</code>	Marks a temporary segment as corrupt whereby facilitating its elimination from the dictionary (without space reclamation).
<code>SEGMENT_MARK_VALID</code>	Marks a corrupt temporary segment as valid. It is useful when the corruption in the segment extent map or elsewhere has been resolved and the segment can be dropped normally.
<code>SEGMENT_DUMP_EXTENT_MAP</code>	Dumps the extent map for a given segment.
<code>TABLESPACE_VERIFY_BITMAP</code>	Verifies the bitmap of the tablespace with extent maps of the segments in that tablespace to make sure everything is consistent.

Table 89–1 DBMS_SPACE_ADMIN Constants

Constant	Description
TABLESPACE_EXTENT_ MAKE_FREE	Makes this range (extent) of space free in the bitmaps.
TABLESPACE_EXTENT_ MAKE_USED	Makes this range (extent) of space used in the bitmaps.

Operational Notes

Before you migrate the `SYSTEM` tablespace, you should migrate any dictionary-managed tablespaces that you may want to use in read/write mode to locally managed. After the `SYSTEM` tablespace is migrated, you cannot change dictionary-managed tablespaces to read/write.

See Also:

- *Oracle Database Administrator's Guide*
- ["TABLESPACE_MIGRATE_TO_LOCAL Procedure"](#) on page 89-13

Before migrating the `SYSTEM` tablespace, the following conditions must be met. These conditions are enforced by the `TABLESPACE_MIGRATE_TO_LOCAL` procedure, except for the cold backup.

- The database must have a default temporary tablespace that is not `SYSTEM`.
- Dictionary-managed tablespaces cannot have any rollback segments.
- A locally managed tablespace must have at least one online rollback segment. If you are using automatic undo management, an undo tablespace must be online.
- All tablespaces—except the tablespace containing the rollback segment or the undo tablespace—must be read-only.
- You must have a cold backup of the database.
- The system must be in restricted mode.

Summary of DBMS_SPACE_ADMIN Subprograms

Table 89-2 DBMS_SPACE_ADMIN Package Subprograms

Subprogram	Description
SEGMENT_CORRUPT Procedure on page 89-5	Marks the segment corrupt or valid so that appropriate error recovery can be done
SEGMENT_DROP_CORRUPT Procedure on page 89-6	Drops a segment currently marked corrupt (without reclaiming space)
SEGMENT_DUMP Procedure on page 89-7	Dumps the segment header and extent maps of a given segment
SEGMENT_VERIFY Procedure on page 89-8	Verifies the consistency of the extent map of the segment
TABLESPACE_FIX_BITMAPS Procedure on page 89-10	Marks the appropriate DBA range (extent) as free or used in bitmap
TABLESPACE_FIX_SEGMENT_STATES Procedure on page 89-11	Fixes the state of the segments in a tablespace in which migration was aborted
TABLESPACE_MIGRATE_FROM_LOCAL Procedure on page 89-12	Migrates a locally-managed tablespace to dictionary-managed tablespace
TABLESPACE_MIGRATE_TO_LOCAL Procedure on page 89-13	Migrates a tablespace from dictionary managed format to locally managed format
TABLESPACE_REBUILD_BITMAPS Procedure on page 89-15	Rebuilds the appropriate bitmaps
TABLESPACE_REBUILD_QUOTAS Procedure on page 89-16	Rebuilds quotas for given tablespace
TABLESPACE_RELOCATE_BITMAPS Procedure on page 89-17	Relocates the bitmaps to the destination specified
TABLESPACE_VERIFY Procedure on page 89-19	Verifies that the bitmaps and extent maps for the segments in the tablespace are in sync

SEGMENT_CORRUPT Procedure

This procedure marks the segment corrupt or valid so that appropriate error recovery can be done. It cannot be used on the SYSTEM tablespace.

Syntax

```
DBMS_SPACE_ADMIN.SEGMENT_CORRUPT (
  tablespace_name      IN   VARCHAR2,
  header_relative_file IN   POSITIVE,
  header_block         IN   POSITIVE,
  corrupt_option       IN   POSITIVE DEFAULT SEGMENT_MARK_CORRUPT);
```

Parameters

Table 89–3 *SEGMENT_CORRUPT Procedure Parameters*

Parameter	Description
tablespace_name	Name of tablespace in which segment resides.
header_relative_file	Relative file number of segment header.
header_block	Block number of segment header.
corrupt_option	SEGMENT_MARK_CORRUPT (default) or SEGMENT_MARK_VALID.

Examples

The following example marks the segment as corrupt:

```
EXECUTE DBMS_SPACE_ADMIN.SEGMENT_CORRUPT('USERS', 4, 33, 3);
```

Alternately, the next example marks a corrupt segment valid:

```
EXECUTE DBMS_SPACE_ADMIN.SEGMENT_CORRUPT('USERS', 4, 33, 4);
```

SEGMENT_DROP_CORRUPT Procedure

This procedure drops a segment currently marked corrupt (without reclaiming space). For this to work, the segment should have been marked *temporary*. To mark a corrupt segment as temporary, issue a DROP command on the segment.

Syntax

```
DBMS_SPACE_ADMIN.SEGMENT_DROP_CORRUPT (  
    tablespace_name      IN    VARCHAR2,  
    header_relative_file IN    POSITIVE,  
    header_block         IN    POSITIVE);
```

Parameters

Table 89–4 *SEGMENT_DROP_CORRUPT Procedure Parameters*

Parameter	Description
<code>tablespace_name</code>	Name of tablespace in which segment resides.
<code>header_relative_file</code>	Relative file number of segment header.
<code>header_block</code>	Block number of segment header.

Usage Notes

The procedure cannot be used on the `SYSTEM` tablespace.

The space for the segment is not released, and it must be fixed by using the [TABLESPACE_FIX_BITMAPS Procedure](#) or the [TABLESPACE_REBUILD_BITMAPS Procedure](#).

Examples

```
EXECUTE DBMS_SPACE_ADMIN.SEGMENT_DROP_CORRUPT('USERS', 4, 33);
```


SEGMENT_DUMP Procedure

This procedure dumps the segment header and extent map blocks of the given segment.

Syntax

```
DBMS_SPACE_ADMIN.SEGMENT_DUMP (
    tablespace_name      IN   VARCHAR2,
    header_relative_file IN   POSITIVE,
    header_block         IN   POSITIVE,
    dump_option          IN   POSITIVE DEFAULT SEGMENT_DUMP_EXTENT_MAP);
```

Parameters

Table 89–5 *SEGMENT_DUMP Procedure Parameters*

Parameter	Description
tablespace_name	Name of tablespace in which segment resides.
header_relative_file	Relative file number of segment header.
header_block	Block number of segment header.
dump_option	SEGMENT_DUMP_EXTENT_MAP.

Examples

```
EXECUTE DBMS_SPACE_ADMIN.SEGMENT_DUMP('USERS', 4, 33);
```

SEGMENT_VERIFY Procedure

This procedure verifies that the extent map of the segment is consistent with the bitmap.

Syntax

```
DBMS_SPACE_ADMIN.SEGMENT_VERIFY (
  tablespace_name      IN    VARCHAR2,
  header_relative_file IN    POSITIVE,
  header_block        IN    POSITIVE,
  verify_option        IN    POSITIVE DEFAULT SEGMENT_VERIFY_EXTENTS);
```

Parameters

Table 89–6 *SEGMENT_VERIFY Procedure Parameters*

Parameters	Description
tablespace_name	Name of tablespace in which segment resides.
header_relative_file	Relative file number of segment header.
header_block	Block number of segment header.
verify_option	What kind of check to do: SEGMENT_VERIFY_EXTENTS or SEGMENT_VERIFY_EXTENTS_GLOBAL.

Usage Notes

Anomalies are output as dba-range, bitmap-block, bitmap-block-range, anomaly-information, in the trace file for all dba-ranges found to have incorrect space representation. The kinds of problems which would be reported are free space not considered free, used space considered free, and the same space considered used by multiple segments.

Examples

The following example verifies that the segment with segment header at relative file number 4, block number 33, has its extent maps and bitmaps in sync.

```
EXECUTE DBMS_SPACE_ADMIN.SEGMENT_VERIFY('USERS', 4, 33, 1);
```

Note: All DBMS_SPACE_ADMIN package examples use the tablespace USERS which contains SCOTT.EMP.

TABLESPACE_FIX_BITMAPS Procedure

This procedure marks the appropriate DBA range (extent) as free or used in bitmap. It cannot be used on the SYSTEM tablespace.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_FIX_BITMAPS (
    tablespace_name      IN      VARCHAR2,
    dbarange_relative_file IN      POSITIVE,
    dbarange_begin_block IN      POSITIVE,
    dbarange_end_block   IN      POSITIVE,
    fix_option           IN      POSITIVE);
```

Parameters

Table 89-7 TABLESPACE_FIX_BITMAPS Procedure Parameters

Parameter	Description
tablespace_name	Name of tablespace.
dbarange_relative_file	Relative file number of DBA range (extent).
dbarange_begin_block	Block number of beginning of extent.
dbarange_end_block	Block number (inclusive) of end of extent.
fix_option	TABLESPACE_EXTENT_MAKE_FREE or TABLESPACE_EXTENT_MAKE_USED.

Examples

The following example marks bits for 50 blocks for relative file number 4, beginning at block number 33 and ending at 83, as USED in bitmaps.

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_FIX_BITMAPS('USERS', 4, 33, 83, 7);
```

Alternately, specifying an option of 8 marks the bits FREE in bitmaps. The BEGIN and END blocks should be in extent boundary and should be extent multiple. Otherwise, an error is raised.

TABLESPACE_FIX_SEGMENT_STATES Procedure

Use this procedure to fix the state of the segments in a tablespace in which migration was aborted. During tablespace migration to or from local, the segments are put in a transient state. If migration is aborted, the segment states are corrected by SMON when event 10906 is set. Database with segments in such a transient state cannot be downgraded. The procedure can be used to fix the state of such segments.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_FIX_SEGMENT_STATES (
    tablespace_name    IN    VARCHAR);
```

Parameters

Table 89–8 TABLESPACE_FIX_SEGMENT_STATES Procedure Parameters

Parameter Name	Purpose
tablespace_name	Name of the tablespace whose segments need to be fixed.

Usage Notes

The tablespace must be kept online and read/write when this procedure is called.

Examples

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_FIX_SEGMENT_STATES('TS1');
```

TABLESPACE_MIGRATE_FROM_LOCAL Procedure

This procedure migrates a locally-managed tablespace to a dictionary-managed tablespace. You cannot use this procedure for `SYSTEM` tablespace.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_MIGRATE_FROM_LOCAL (  
    tablespace_name          IN    VARCHAR2);
```

Parameter

Table 89–9 *TABLESPACE_MIGRATE_FROM_LOCAL Procedure Parameter*

Parameter	Description
tablespace_name	Name of tablespace.

Usage Notes

The tablespace must be kept online and read/write during migration. Migration of temporary tablespaces and migration of `SYSTEM` tablespaces are not supported.

Examples

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_MIGRATE_FROM_LOCAL('USERS');
```

TABLESPACE_MIGRATE_TO_LOCAL Procedure

Use this procedure to migrate the tablespace from a dictionary-managed format to a locally managed format. Tablespaces migrated to locally managed format are user managed.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_MIGRATE_TO_LOCAL (
    tablespace_name    IN    VARCHAR,
    allocation_unit    IN    INTEGER,
    relative_fno       IN    INTEGER);
```

Parameters

Table 89–10 TABLESPACE_MIGRATE_TO_LOCAL Procedure Parameters

Parameter Name	Purpose
tablespace_name	Name of the tablespace to be migrated.
allocation_unit	Unit size (which is the size of the smallest possible chunk of space that can be allocated) in the tablespace.
relative_fno	Relative File Number of the file where the bitmap blocks should be placed (optional).

Usage Notes

Note: Do not migrate the `SYSTEM` tablespace without a clear understanding of the conditions that must be met. Refer to [Operational Notes](#) on page 89-3.

The tablespace must be kept online and read/write during migration. Note that temporary tablespaces cannot be migrated.

Allocation Unit may be specified optionally. The default is calculated by the system based on the highest common divisor of all extents (used or free) for the tablespace. This number is further trimmed based on the `MINIMUM_EXTENT` for the tablespace (5 if `MINIMUM_EXTENT` is not specified). Thus, the calculated value will not be larger than the `MINIMUM_EXTENT` for the tablespace. The last free extent in every file will be ignored for GCD calculation. If you specify the unit size, it has to be a

factor of the UNIT size calculated by the system, otherwise an error message is returned.

The Relative File Number parameter is used to place the bitmaps in a desired file. If space is not found in the file, an error is issued. The datafile specified should be part of the tablespace being migrated. If the datafile is not specified then the system will choose a datafile in which to place the initial bitmap blocks. If space is not found for the initial bitmaps, an error will be raised.

Examples

To migrate a tablespace 'TS1' with minimum extent size 1m, use

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_MIGRATE_TO_LOCAL('TS1', 512, 2);
```

The bitmaps will be placed in file with relative file number 2.

TABLESPACE_REBUILD_BITMAPS Procedure

This procedure rebuilds the appropriate bitmaps. If no bitmap block DBA is specified, then it rebuilds all bitmaps for the given tablespace.

The procedure cannot be used on the SYSTEM tablespace.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_REBUILD_BITMAPS (
    tablespace_name      IN    VARCHAR2,
    bitmap_relative_file IN    POSITIVE  DEFAULT NULL,
    bitmap_block         IN    POSITIVE  DEFAULT NULL);
```

Parameters

Table 89–11 TABLESPACE_REBUILD_BITMAPS Procedure Parameters

Parameter	Description
tablespace_name	Name of tablespace.
bitmap_relative_file	Relative file number of bitmap block to rebuild.
bitmap_block	Block number of bitmap block to rebuild.

Usage Notes

Note: Only full rebuild is supported.

Examples

The following example rebuilds bitmaps for all the files in the USERS tablespace.

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_REBUILD_BITMAPS('USERS');
```

TABLESPACE_REBUILD_QUOTAS Procedure

This procedure rebuilds quotas for the given tablespace.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_REBUILD_QUOTAS (  
    tablespace_name          IN    VARCHAR2);
```

Parameters

Table 89–12 *TABLESPACE_REBUILD_QUOTAS Procedure Parameters*

Parameter	Description
tablespace_name	Name of tablespace.

Examples

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_REBUILD_QUOTAS('USERS');
```

TABLESPACE_RELOCATE_BITMAPS Procedure

Use this procedure to relocate the bitmaps to the destination specified.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_RELOCATE_BITMAPS (
    tablespace_name  IN      VARCHAR,
    relative_fno     IN      NUMBER,
    block_number     IN      NUMBER);
```

Parameters

Table 89–13 TABLESPACE_RELOCATE_BITMAPS Procedure Parameters

Parameter Name	Purpose
tablespace_name	Name of Tablespace.
relative_fno	Relative File Number of the destination file.
block_number	Block Number of the destination dba.

Usage Notes

Migration of a tablespace from dictionary managed to locally managed format could result in the creation of SPACE HEADER segment that contains the bitmap blocks. The SPACE HEADER segment is treated as user data. If the user wishes to explicitly resize a file at or below the space header segment, an error is issued. Use the `tablespace_relocate_bitmaps` command to move the control information to a different destination and then resize the file.

This procedure cannot be used on the SYSTEM tablespace.

The tablespace must be kept online and read/write during relocation of bitmaps. This can be done only on migrated locally managed tablespaces.

Examples

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_RELOCATE_BITMAPS('TS1', 3, 4);
```

Moves the bitmaps to file 3, block 4.

Note: The source and the destination addresses should not overlap. The destination block number is rounded down to the unit boundary. If there is user data in that location an error is raised.

TABLESPACE_VERIFY Procedure

This procedure verifies that the bitmaps and extent maps for the segments in the tablespace are in sync.

Syntax

```
DBMS_SPACE_ADMIN.TABLESPACE_VERIFY (  
    tablespace_name      IN    VARCHAR2,  
    verify_option        IN    POSITIVE DEFAULT TABLESPACE_VERIFY_BITMAP);
```

Parameters

Table 89–14 TABLESPACE_VERIFY Procedure Parameters

Parameter	Description
tablespace_name	Name of tablespace.
verify_option	TABLESPACE_VERIFY_BITMAP.

Examples

```
EXECUTE DBMS_SPACE_ADMIN.TABLESPACE_VERIFY('USERS');
```


The `DBMS_SQL` package provides an interface to use dynamic SQL to parse any data manipulation language (DML) or data definition language (DDL) statement using PL/SQL. For example, you can enter a `DROP TABLE` statement from within a stored procedure by using the `PARSE` procedure supplied with the `DBMS_SQL` package.

See Also: For more information on native dynamic SQL, see *PL/SQL User's Guide and Reference*.

For a comparison of `DBMS_SQL` and native dynamic SQL, see *Oracle Database Application Developer's Guide - Fundamentals*.

This chapter contains the following topics:

- [Using DBMS_SQL](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Types](#)
 - [Exceptions](#)
 - [Operational Notes](#)
 - [Examples](#)
- [Summary of DBMS_SQL Subprograms](#)

Using DBMS_SQL

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Types](#)
- [Exceptions](#)
- [Operational Notes](#)
- [Examples](#)

Overview

Oracle lets you to write stored procedures and anonymous PL/SQL blocks that use dynamic SQL. Dynamic SQL statements are not embedded in your source program; rather, they are stored in character strings that are input to, or built by, the program at runtime. This enables you to create more general-purpose procedures. For example, dynamic SQL lets you create a procedure that operates on a table whose name is not known until runtime.

Native dynamic SQL is an alternative to DBMS_SQL that lets you place dynamic SQL statements directly into PL/SQL blocks. In most situations, native dynamic SQL is easier to use and performs better than DBMS_SQL. However, there are some tasks that can only be performed using DBMS_SQL.

The ability to use dynamic SQL from within stored procedures generally follows the model of the Oracle Call Interface (OCI).

See Also: *Oracle Call Interface Programmer's Guide*

PL/SQL differs somewhat from other common programming languages, such as C. For example, addresses (also called pointers) are not user-visible in PL/SQL. As a result, there are some differences between the Oracle Call Interface and the DBMS_SQL package. These differences include the following:

- The OCI uses bind by address, while the DBMS_SQL package uses bind by value.

- With `DBMS_SQL` you must call `VARIABLE_VALUE` to retrieve the value of an `OUT` parameter for an anonymous block, and you must call `COLUMN_VALUE` after fetching rows to actually retrieve the values of the columns in the rows into your program.
- The current release of the `DBMS_SQL` package does not provide `CANCEL` cursor procedures.
- Indicator variables are not required, because `NULLS` are fully supported as values of a PL/SQL variable.

A sample usage of the `DBMS_SQL` package follows. For users of the Oracle Call Interfaces, this code should seem fairly straightforward.

Security Model

`DBMS_SQL` is compiled with `AUTHID CURRENT_USER`.

Any `DBMS_SQL` subprograms called from an anonymous PL/SQL block are run using the privileges of the current user.

See Also: For more information about invoking subprograms using either Invoker or Definer Rights, see *PL/SQL User's Guide and Reference*

Constants

```
v6 constant INTEGER      := 0;
native constant INTEGER := 1;
v7 constant INTEGER      := 2;
```

Types

General Types

- [DESC_REC](#), [DESC_TAB](#)
- [VARCHAR2A](#), [DESC_REC2](#)
- [VARCHAR2_TABLE](#)

Bulk SQL Types

- [BFILE_TABLE](#)

- [BINARY_DOUBLE_TABLE](#)
- [BLOB_TABLE](#)
- [CLOB_TABLE](#)
- [DATE_TABLE](#)
- [INTERVAL_DAY_TO_SECOND_TABLE](#)
- [INTERVAL_YEAR_TO_MONTH_TABLE](#)
- [NUMBER_TABLE](#)
- [TIME_TABLE](#)
- [TIME_WITH_TIME_ZONE_TABLE](#)
- [TIMESTAMP_TABLE](#)
- [TIMESTAMP_WITH_LTZ_TABLE](#)
- [UROWID_TABLE](#)
- [VARCHAR2_TABLE](#)

BFILE_TABLE

TYPE bfile_table IS TABLE OF BFILE INDEX BY BINARY_INTEGER;

BINARY_DOUBLE_TABLE

TYPE binary_double_table IS TABLE OF BINARY_DOUBLE INDEX BY BINARY_INTEGER;

BINARY_FLOAT_TABLE

TYPE binary_float_table IS TABLE OF BINARY_FLOAT INDEX BY BINARY_INTEGER;

BLOB_TABLE

TYPE blob_table IS TABLE OF BLOB INDEX BY BINARY_INTEGER;

CLOB_TABLE

TYPE clob_table IS TABLE OF CLOB INDEX BY BINARY_INTEGER;

DATE_TABLE

type date_table IS TABLE OF DATE INDEX BY BINARY_INTEGER;

INTERVAL_DAY_TO_SECOND_TABLE

```
TYPE interval_day_to_second_Table IS TABLE OF
    dsinterval_unconstrained INDEX BY binary_integer;
```

INTERVAL_YEAR_TO_MONTH_TABLE

```
TYPE interval_year_to_month_table IS TABLE OF yminterval_unconstrained INDEX BY
    BINARY_INTEGER;
```

DESC_REC, DESC_TAB

```
TYPE desc_rec IS RECORD (
    col_type          BINARY_INTEGER := 0,
    col_max_len       BINARY_INTEGER := 0,
    col_name          VARCHAR2(32)   := '',
    col_name_len      BINARY_INTEGER := 0,
    col_schema_name   VARCHAR2(32)   := '',
    col_schema_name_len BINARY_INTEGER := 0,
    col_precision     BINARY_INTEGER := 0,
    col_scale         BINARY_INTEGER := 0,
    col_charsetid     BINARY_INTEGER := 0,
    col_charsetform   BINARY_INTEGER := 0,
    col_null_ok       BOOLEAN        := TRUE);
TYPE desc_tab IS TABLE OF desc_rec INDEX BY BINARY_INTEGER;
```

NUMBER_TABLE

```
TYPE number_table IS TABLE OF NUMBER INDEX BY BINARY_INTEGER;
```

TIME_TABLE

```
TYPE time_table IS TABLE OF time_unconstrained INDEX BY BINARY_INTEGER;
```

TIME_WITH_TIME_ZONE_TABLE

```
TYPE time_with_time_zone_table IS TABLE OF TIME_TZ_UNCONSTRAINED INDEX
    BY BINARY_INTEGER;
```

TIMESTAMP_TABLE

```
TYPE timestamp_table IS TABLE OF timestamp_unconstrained INDEX BY BINARY_
    INTEGER;
```

TIMESTAMP_WITH_LTZ_TABLE

```
TYPE timestamp_with_ltz_table IS TABLE OF
```

```
TIMESTAMP_LTZ_UNCONSTRAINED INDEX BY binary_integer;
```

UROWID_TABLE

```
TYPE urowid_table IS TABLE OF UROWID INDEX BY BINARY_INTEGER;
```

VARCHAR2_TABLE

```
TYPE varchar2_table IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER;
```

VARCHAR2A, DESC_REC2

```
TYPE varchar2a IS TABLE OF VARCHAR2(32767) INDEX BY BINARY_INTEGER;
TYPE desc_rec2 IS RECORD (
    col_type          binary_integer := 0,
    col_max_len       binary_integer := 0,
    col_name          varchar2(32767) := '',
    col_name_len      binary_integer := 0,
    col_schema_name   varchar2(32)   := '',
    col_schema_name_len binary_integer := 0,
    col_precision     binary_integer := 0,
    col_scale         binary_integer := 0,
    col_charsetid     binary_integer := 0,
    col_charsetform   binary_integer := 0,
    col_null_ok       boolean        := TRUE);
TYPE desc_tab2 IS TABLE OF desc_rec2 INDEX BY BINARY_INTEGER;
```

VARCHAR2S

```
TYPE varchar2s IS TABLE OF VARCHAR2(256) INDEX BY BINARY_INTEGER;
```

Exceptions

```
inconsistent_type EXCEPTION;
pragma exception_init(inconsistent_type, -6562);
```

This exception is raised by the [COLUMN_VALUE Procedure](#) or the [VARIABLE_VALUE Procedures](#) when the type of the given OUT parameter (for where to put the requested value) is different from the type of the value.

Operational Notes

Execution Flow

OPEN_CURSOR

To process a SQL statement, you must have an open cursor. When you call the [OPEN_CURSOR Function](#) function, you receive a cursor ID number for the data structure representing a valid cursor maintained by Oracle. These cursors are distinct from cursors defined at the precompiler, OCI, or PL/SQL level, and are used only by the DBMS_SQL package.

PARSE


Every SQL statement must be parsed by calling the [PARSE Procedure](#). Parsing the statement checks the statement's syntax and associates it with the cursor in your program.

You can parse any DML or DDL statement. DDL statements are run on the parse, which performs the implied commit.

Note: When parsing a DDL statement to drop a package or a procedure, a deadlock can occur if you're still using a procedure in the package. After a call to a procedure, that procedure is considered to be in use until execution has returned to the user side. Any such deadlock timeouts after five minutes.

The execution flow of DBMS_SQL is shown in [Figure 90-1](#).

Figure 90-1 DBMS_SQL Execution Flow



BIND_VARIABLE or BIND_ARRAY

Many DML statements require that data in your program be input to Oracle. When you define a SQL statement that contains input data to be supplied at runtime, you must use placeholders in the SQL statement to mark where data must be supplied.

For each placeholder in the SQL statement, you must call one of the bind procedures, the [BIND_ARRAY Procedures](#) on page 90-27 or the [BIND_VARIABLE Procedures](#) on page 90-30, to supply the value of a variable in your program (or the values of an array) to the placeholder. When the SQL statement is subsequently run, Oracle uses the data that your program has placed in the output and input, or bind, variables.

DBMS_SQL can run a DML statement multiple times — each time with a different bind variable. The `BIND_ARRAY` procedure lets you bind a collection of scalars, each value of which is used as an input variable once for each `EXECUTE`. This is similar to the array interface supported by the OCI.

DEFINE_COLUMN, DEFINE_COLUMN_LONG, or DEFINE_ARRAY

The columns of the row being selected in a `SELECT` statement are identified by their relative positions as they appear in the select list, from left to right. For a query, you must call one of the define procedures (`DEFINE_COLUMN`, `DEFINE_COLUMN_LONG`, or `DEFINE_ARRAY`) to specify the variables that are to receive the `SELECT` values, much the way an `INTO` clause does for a static query.

Use the `DEFINE_COLUMN_LONG` procedure to define `LONG` columns, in the same way that `DEFINE_COLUMN` is used to define non-`LONG` columns. You must call `DEFINE_COLUMN_LONG` before using the `COLUMN_VALUE_LONG` procedure to fetch from the `LONG` column.

Use the `DEFINE_ARRAY` procedure to define a PL/SQL collection into which you want to fetch rows in a single `SELECT` statement. `DEFINE_ARRAY` provides an interface to fetch multiple rows at one fetch. You must call `DEFINE_ARRAY` before using the `COLUMN_VALUE` procedure to fetch the rows.

EXECUTE

Call the `EXECUTE` function to run your SQL statement.

FETCH_ROWS or EXECUTE_AND_FETCH

The `FETCH_ROWS` function retrieves the rows that satisfy the query. Each successive fetch retrieves another set of rows, until the fetch is unable to retrieve anymore rows. Instead of calling `EXECUTE` and then `FETCH_ROWS`, you may find it more efficient to call `EXECUTE_AND_FETCH` if you are calling `EXECUTE` for a single execution.

VARIABLE_VALUE, COLUMN_VALUE, or COLUMN_VALUE_LONG

For queries, call `COLUMN_VALUE` to determine the value of a column retrieved by the `FETCH_ROWS` call. For anonymous blocks containing calls to PL/SQL procedures or DML statements with `returning` clause, call `VARIABLE_VALUE` to retrieve the values assigned to the output variables when statements were run.

To fetch just part of a `LONG` database column (which can be up to two gigabytes in size), use the `COLUMN_VALUE_LONG` procedure. You can specify the offset (in bytes) into the column value, and the number of bytes to fetch.

CLOSE_CURSOR

When you no longer need a cursor for a session, close the cursor by calling `CLOSE_CURSOR`. If you are using an Oracle Open Gateway, then you may need to close cursors at other times as well. Consult your *Oracle Open Gateway* documentation for additional information.

If you neglect to close a cursor, then the memory used by that cursor remains allocated even though it is no longer needed.

Processing Queries

If you are using dynamic SQL to process a query, then you must perform the following steps:

1. Specify the variables that are to receive the values returned by the `SELECT` statement by calling the [DEFINE_COLUMN Procedure](#), the [DEFINE_COLUMN_LONG Procedure](#), or the [DEFINE_ARRAY Procedure](#).
2. Run your `SELECT` statement by calling the [EXECUTE Function](#).
3. Call the [FETCH_ROWS Function](#) (or `EXECUTE_AND_FETCH`) to retrieve the rows that satisfied your query.
4. Call [COLUMN_VALUE Procedure](#) or [COLUMN_VALUE_LONG Procedure](#) to determine the value of a column retrieved by the [FETCH_ROWS Function](#) for your query. If you used anonymous blocks containing calls to PL/SQL procedures, then you must call the [VARIABLE_VALUE Procedures](#) to retrieve the values assigned to the output variables of these procedures.

Processing Updates, Inserts, and Deletes

If you are using dynamic SQL to process an `INSERT`, `UPDATE`, or `DELETE`, then you must perform the following steps:

1. You must first run your `INSERT`, `UPDATE`, or `DELETE` statement by calling the [EXECUTE Function](#).

2. If statements have the `returning` clause, then you must call the [VARIABLE_VALUE Procedures](#) to retrieve the values assigned to the output variables.

Locating Errors

There are additional functions in the `DBMS_SQL` package for obtaining information about the last referenced cursor in the session. The values returned by these functions are only meaningful immediately after a SQL statement is run. In addition, some error-locating functions are only meaningful after certain `DBMS_SQL` calls. For example, you call the [LAST_ERROR_POSITION Function](#) immediately after a `PARSE`.

Examples

This section provides example procedures that make use of the `DBMS_SQL` package.

Example 1

This example does not require the use of dynamic SQL because the text of the statement is known at compile time., but it illustrates the basic concept underlying the package.

The `DEMO` procedure deletes all of the employees from the `EMP` table whose salaries are greater than the salary that you specify when you run `DEMO`.

```
CREATE OR REPLACE PROCEDURE demo(salary IN NUMBER) AS
    cursor_name INTEGER;
    rows_processed INTEGER;
BEGIN
    cursor_name := dbms_sql.open_cursor;
    DBMS_SQL.PARSE(cursor_name, 'DELETE FROM emp WHERE sal > :x',
                   dbms_sql.native);
    DBMS_SQL.BIND_VARIABLE(cursor_name, ':x', salary);
    rows_processed := dbms_sql.execute(cursor_name);
    DBMS_SQL.close_cursor(cursor_name);
EXCEPTION
WHEN OTHERS THEN
    DBMS_SQL.CLOSE_CURSOR(cursor_name);
END;
```

Example 2

The following sample procedure is passed a SQL statement, which it then parses and runs:

```
CREATE OR REPLACE PROCEDURE exec(STRING IN varchar2) AS
    cursor_name INTEGER;
    ret INTEGER;
BEGIN
    cursor_name := DBMS_SQL.OPEN_CURSOR;
```

DDL statements are run by the parse call, which performs the implied commit.

```
    DBMS_SQL.PARSE(cursor_name, string, DBMS_SQL.native);
    ret := DBMS_SQL.EXECUTE(cursor_name);
    DBMS_SQL.CLOSE_CURSOR(cursor_name);
END;
```

Creating such a procedure enables you to perform the following operations:

- The SQL statement can be dynamically generated at runtime by the calling program.
- The SQL statement can be a DDL statement or a DML without binds.

For example, after creating this procedure, you could make the following call:

```
exec('create table acct(c1 integer)');
```

You could even call this procedure remotely, as shown in the following example. This lets you perform remote DDL.

```
exec@hq.com('CREATE TABLE acct(c1 INTEGER)');
```

Example 3

The following sample procedure is passed the names of a source and a destination table, and copies the rows from the source table to the destination table. This sample procedure assumes that both the source and destination tables have the following columns:

```
id          of type NUMBER
name        of type VARCHAR2(30)
birthdate  of type DATE
```

This procedure does not specifically require the use of dynamic SQL; however, it illustrates the concepts of this package.

```
CREATE OR REPLACE PROCEDURE copy (
    source      IN VARCHAR2,
    destination IN VARCHAR2) IS
    id_var      NUMBER;
    name_var    VARCHAR2(30);
```

```
        birthdate_var      DATE;
        source_cursor      INTEGER;
        destination_cursor INTEGER;
        ignore             INTEGER;
BEGIN

-- Prepare a cursor to select from the source table:
source_cursor := dbms_sql.open_cursor;
DBMS_SQL.PARSE(source_cursor,
    'SELECT id, name, birthdate FROM ' || source,
    DBMS_SQL.native);
DBMS_SQL.DEFINE_COLUMN(source_cursor, 1, id_var);
DBMS_SQL.DEFINE_COLUMN(source_cursor, 2, name_var, 30);
DBMS_SQL.DEFINE_COLUMN(source_cursor, 3, birthdate_var);
ignore := DBMS_SQL.EXECUTE(source_cursor);

-- Prepare a cursor to insert into the destination table:
destination_cursor := DBMS_SQL.OPEN_CURSOR;
DBMS_SQL.PARSE(destination_cursor,
    'INSERT INTO ' || destination ||
    ' VALUES (:id_bind, :name_bind, :birthdate_bind)',
    DBMS_SQL.native);

-- Fetch a row from the source table and insert it into the destination table:
LOOP
    IF DBMS_SQL.FETCH_ROWS(source_cursor)>0 THEN
        -- get column values of the row
        DBMS_SQL.COLUMN_VALUE(source_cursor, 1, id_var);
        DBMS_SQL.COLUMN_VALUE(source_cursor, 2, name_var);
        DBMS_SQL.COLUMN_VALUE(source_cursor, 3, birthdate_var);

-- Bind the row into the cursor that inserts into the destination table. You
-- could alter this example to require the use of dynamic SQL by inserting an
-- if condition before the bind.
        DBMS_SQL.BIND_VARIABLE(destination_cursor, ':id_bind', id_var);
        DBMS_SQL.BIND_VARIABLE(destination_cursor, ':name_bind', name_var);
        DBMS_SQL.BIND_VARIABLE(destination_cursor, ':birthdate_bind',
birthdate_var);
        ignore := DBMS_SQL.EXECUTE(destination_cursor);
    ELSE

-- No more rows to copy:
        EXIT;
    END IF;
END LOOP;
```

```
-- Commit and close all cursors:
COMMIT;
DBMS_SQL.CLOSE_CURSOR(source_cursor);
DBMS_SQL.CLOSE_CURSOR(destination_cursor);
EXCEPTION
  WHEN OTHERS THEN
    IF DBMS_SQL.IS_OPEN(source_cursor) THEN
      DBMS_SQL.CLOSE_CURSOR(source_cursor);
    END IF;
    IF DBMS_SQL.IS_OPEN(destination_cursor) THEN
      DBMS_SQL.CLOSE_CURSOR(destination_cursor);
    END IF;
    RAISE;
END;
/
```

Examples 3, 4, and 5: Bulk DML

This series of examples shows how to use bulk array binds (table items) in the SQL DML statements DELETE, INSERT, and UPDATE.

In a DELETE statement, for example, you could bind in an array in the WHERE clause and have the statement be run for each element in the array:

```
declare
  stmt varchar2(200);
  dept_no_array dbms_sql.Number_Table;
  c number;
  dummy number;
begin
  dept_no_array(1) := 10; dept_no_array(2) := 20;
  dept_no_array(3) := 30; dept_no_array(4) := 40;
  dept_no_array(5) := 30; dept_no_array(6) := 40;
  stmt := 'delete from emp where deptno = :dept_array';
  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, stmt, dbms_sql.native);
  dbms_sql.bind_array(c, ':dept_array', dept_no_array, 1, 4);
  dummy := dbms_sql.execute(c);
  dbms_sql.close_cursor(c);

  exception when others then
    if dbms_sql.is_open(c) then
      dbms_sql.close_cursor(c);
    end if;
    raise;
end;
```

```
end;
/
```

In the preceding example, only elements 1 through 4 are used as specified by the `BIND_ARRAY` call. Each element of the array potentially deletes a large number of employees from the database.

Here is an example of a bulk `INSERT` statement:

```
declare
  stmt varchar2(200);
  empno_array dbms_sql.Number_Table;
  empname_array dbms_sql.Varchar2_Table;
  c number;
  dummy number;
begin
  for i in 0..9 loop
    empno_array(i) := 1000 + i;
    empname_array(i) := get_name(i);
  end loop;
  stmt := 'insert into emp values(:num_array, :name_array)';
  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, stmt, dbms_sql.native);
  dbms_sql.bind_array(c, ':num_array', empno_array);
  dbms_sql.bind_array(c, ':name_array', empname_array);
  dummy := dbms_sql.execute(c);
  dbms_sql.close_cursor(c);

  exception when others then
    if dbms_sql.is_open(c) then
      dbms_sql.close_cursor(c);
    end if;
    raise;
end;
/
```

When the execute takes place, all 10 of the employees are inserted into the table.

Finally, here is an example of an bulk `UPDATE` statement.

```
declare
  stmt varchar2(200);
  emp_no_array dbms_sql.Number_Table;
  emp_addr_array dbms_sql.Varchar2_Table;
  c number;
  dummy number;
```

```
begin
  for i in 0..9 loop
    emp_no_array(i) := 1000 + i;
    emp_addr_array(i) := get_new_addr(i);
  end loop;
  stmt := 'update emp set ename = :name_array
    where empno = :num_array';
  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, stmt, dbms_sql.native);
  dbms_sql.bind_array(c, ':num_array', empno_array);
  dbms_sql.bind_array(c, ':name_array', empname_array);
  dummy := dbms_sql.execute(c);
  dbms_sql.close_cursor(c);

  exception when others then
    if dbms_sql.is_open(c) then
      dbms_sql.close_cursor(c);
    end if;
    raise;
end;
/
```

When the [EXECUTE Function](#) call happens, the addresses of all employees are updated at once. The two collections are always stepped in unison. If the `WHERE` clause returns more than one row, then all those employees get the address the `addr_array` happens to be pointing to at that time.

Examples 6 and 7: Defining an Array

The following examples show how to use the `DEFINE_ARRAY` procedure:

```
declare
  c      number;
  d      number;
  n_tab  dbms_sql.Number_Table;
  indx   number := -10;
begin
  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, 'select n from t order by 1', dbms_sql);

  dbms_sql.define_array(c, 1, n_tab, 10, indx);

  d := dbms_sql.execute(c);
  loop
    d := dbms_sql.fetch_rows(c);
```

```

        dbms_sql.column_value(c, 1, n_tab);

        exit when d != 10;
    end loop;

    dbms_sql.close_cursor(c);

exception when others then
    if dbms_sql.is_open(c) then
        dbms_sql.close_cursor(c);
    end if;
    raise;
end;
/

```

Each time the preceding example does a [FETCH_ROWS Function](#) call, it fetches 10 rows that are kept in DBMS_SQL buffers. When the [COLUMN_VALUE Procedure](#) call is run, those rows move into the PL/SQL table specified (in this case `n_tab`), at positions -10 to -1, as specified in the `DEFINE` statements. When the second batch is fetched in the loop, the rows go to positions 0 to 9; and so on.

A current index into each array is maintained automatically. This index is initialized to "indx" at `EXECUTE` and keeps getting updated every time a `COLUMN_VALUE` call is made. If you reexecute at any point, then the current index for each `DEFINE` is re-initialized to "indx".

In this way the entire result of the query is fetched into the table. When `FETCH_ROWS` cannot fetch 10 rows, it returns the number of rows actually fetched (if no rows could be fetched, then it returns zero) and exits the loop.

Here is another example of using the `DEFINE_ARRAY` procedure:

Consider a table `MULTI_TAB` defined as:

```

create table multi_tab (num number,
                        dat1 date,
                        var varchar2(24),
                        dat2 date)

```

To select everything from this table and move it into four PL/SQL tables, you could use the following simple program:

```

declare
    c      number;
    d      number;

```

```
n_tab  dbms_sql.Number_Table;
d_tab1 dbms_sql.Date_Table;
v_tab  dbms_sql.Varchar2_Table;
d_tab2 dbms_sql.Date_Table;
indx number := 10;
begin

  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, 'select * from multi_tab order by 1', dbms_sql);

  dbms_sql.define_array(c, 1, n_tab, 5, indx);
  dbms_sql.define_array(c, 2, d_tab1, 5, indx);
  dbms_sql.define_array(c, 3, v_tab, 5, indx);
  dbms_sql.define_array(c, 4, d_tab2, 5, indx);

  d := dbms_sql.execute(c);

  loop
    d := dbms_sql.fetch_rows(c);

    dbms_sql.column_value(c, 1, n_tab);
    dbms_sql.column_value(c, 2, d_tab1);
    dbms_sql.column_value(c, 3, v_tab);
    dbms_sql.column_value(c, 4, d_tab2);

    exit when d != 5;
  end loop;

  dbms_sql.close_cursor(c);

/*

The four tables can be used for anything. One usage might be to use BIND_ARRAY to move the rows to another table by using a query such as 'INSERT into SOME_T values (:a, :b, :c, :d);

*/

exception when others then
  if dbms_sql.is_open(c) then
    dbms_sql.close_cursor(c);
  end if;
  raise;
end;
/
```


Example 8: Describe Columns

This can be used as a substitute to the SQL*Plus DESCRIBE call by using a SELECT * query on the table that you want to describe.

```

declare
  c number;
  d number;
  col_cnt integer;
  f boolean;
  rec_tab dbms_sql.desc_tab;
  col_num number;
  procedure print_rec(rec in dbms_sql.desc_rec) is
  begin
    dbms_output.new_line;
    dbms_output.put_line('col_type          = '
                          || rec.col_type);
    dbms_output.put_line('col_maxlen       = '
                          || rec.col_max_len);
    dbms_output.put_line('col_name        = '
                          || rec.col_name);
    dbms_output.put_line('col_name_len    = '
                          || rec.col_name_len);
    dbms_output.put_line('col_schema_name = '
                          || rec.col_schema_name);
    dbms_output.put_line('col_schema_name_len = '
                          || rec.col_schema_name_len);
    dbms_output.put_line('col_precision   = '
                          || rec.col_precision);
    dbms_output.put_line('col_scale       = '
                          || rec.col_scale);
    dbms_output.put('col_null_ok          = ');
    if (rec.col_null_ok) then
      dbms_output.put_line('true');
    else
      dbms_output.put_line('false');
    end if;
  end;
begin
  c := dbms_sql.open_cursor;

  dbms_sql.parse(c, 'select * from scott.bonus', dbms_sql);

  d := dbms_sql.execute(c);

  dbms_sql.describe_columns(c, col_cnt, rec_tab);

```

```
/*
 * Following loop could simply be for j in 1..col_cnt loop.
 * Here we are simply illustrating some of the PL/SQL table
 * features.
 */
col_num := rec_tab.first;
if (col_num is not null) then
  loop
    print_rec(rec_tab(col_num));
    col_num := rec_tab.next(col_num);
    exit when (col_num is null);
  end loop;
end if;

dbms_sql.close_cursor(c);
end;
/
```

Example 9: RETURNING clause The RETURNING clause was added to DML statements in an earlier Oracle database release. With this clause, INSERT, UPDATE, and DELETE statements can return values of expressions. These values are returned in bind variables.

DBMS_SQL.BIND_VARIABLE is used to bind these outbinds if a single row is inserted, updated, or deleted. If multiple rows are inserted, updated, or deleted, then DBMS_SQL.BIND_ARRAY is used. DBMS_SQL.VARIABLE_VALUE must be called to get the values in these bind variables.

Note: This is similar to DBMS_SQL.VARIABLE_VALUE, which must be called after running a PL/SQL block with an out-bind inside DBMS_SQL.

i) Single row insert

```
create or replace procedure single_Row_insert
  (c1 number, c2 number, r out number) is
  c number;
  n number;
begin
  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, 'insert into tab values (:bnd1, :bnd2) ' ||
    'returning c1*c2 into :bnd3', 2);
```

```

dbms_sql.bind_variable(c, 'bnd1', c1);
  dbms_sql.bind_variable(c, 'bnd2', c2);
  dbms_sql.bind_variable(c, 'bnd3', r);
  n := dbms_sql.execute(c);
  dbms_sql.variable_value(c, 'bnd3', r); -- get value of outbind variable
  dbms_sql.close_Cursor(c);
end;
/

```

ii) Single row update

```

create or replace procedure single_Row_update
  (c1 number, c2 number, r out number) is
c number;
n number;
begin
  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, 'update tab set c1 = :bnd1, c2 = :bnd2 ' ||
    'where rownum < 2' ||
    'returning c1*c2 into :bnd3', 2);
  dbms_sql.bind_variable(c, 'bnd1', c1);
  dbms_sql.bind_variable(c, 'bnd2', c2);
  dbms_sql.bind_variable(c, 'bnd3', r);
  n := dbms_sql.execute(c);
  dbms_sql.variable_value(c, 'bnd3', r);-- get value of outbind variable
  dbms_sql.close_Cursor(c);
end;
/

```

iii) Single row delete

```

create or replace procedure single_Row_Delete
  (c1 number, c2 number, r out number) is
c number;
n number;
begin
  c := dbms_sql.open_cursor;
  dbms_sql.parse(c, 'delete from tab ' ||
    'where rownum < 2 ' ||
    'returning c1*c2 into :bnd3', 2);
  dbms_sql.bind_variable(c, 'bnd1', c1);
  dbms_sql.bind_variable(c, 'bnd2', c2);
  dbms_sql.bind_variable(c, 'bnd3', r);
  n := dbms_sql.execute(c);
  dbms_sql.variable_value(c, 'bnd3', r);-- get value of outbind variable
  dbms_sql.close_Cursor(c);

```

```
end;  
/
```

iv) Multi-row insert

```
create or replace procedure multi_Row_insert  
  (c1 dbms_sql.number_table, c2 dbms_sql.number_table,  
   r out dbms_sql.number_table) is  
  c number;  
  n number;  
begin  
  c := dbms_sql.open_cursor;  
  dbms_sql.parse(c, 'insert into tab values (:bnd1, :bnd2) ' ||  
    'returning c1*c2 into :bnd3', 2);  
  dbms_sql.bind_array(c, 'bnd1', c1);  
  dbms_sql.bind_array(c, 'bnd2', c2);  
  dbms_sql.bind_array(c, 'bnd3', r);  
  n := dbms_sql.execute(c);  
  dbms_sql.variable_value(c, 'bnd3', r);-- get value of outbind variable  
  dbms_Sql.close_Cursor(c);  
end;  
/
```

v) Multi row Update.

```
create or replace procedure multi_Row_update  
  (c1 number, c2 number, r out dbms_Sql.number_table) is  
  c number;  
  n number;  
begin  
  c := dbms_sql.open_cursor;  
  dbms_sql.parse(c, 'update tab set c1 = :bnd1 where c2 = :bnd2 ' ||  
    'returning c1*c2 into :bnd3', 2);  
  dbms_sql.bind_variable(c, 'bnd1', c1);  
  dbms_sql.bind_variable(c, 'bnd2', c2);  
  dbms_sql.bind_array(c, 'bnd3', r);  
  n := dbms_sql.execute(c);  
  dbms_sql.variable_value(c, 'bnd3', r);-- get value of outbind variable  
  dbms_Sql.close_Cursor(c);  
end;  
/
```

Note: bnd1 and bnd2 can be array as well. The value of the expression for all the rows updated will be in bnd3. There is no way of differentiating which rows got updated of each value of bnd1 and bnd2.

vi) Multi-row delete

```

create or replace procedure multi_row_delete
    (c1 dbms_sql.number_table,
     r out dbms_sql.number_table) is
c number;
n number;
begin
    c := dbms_sql.open_cursor;
    dbms_sql.parse(c, 'delete from tab where c1 = :bnd1' ||
                  'returning c1*c2 into :bnd2', 2);
    dbms_sql.bind_array(c, 'bnd1', c1);
    dbms_sql.bind_array(c, 'bnd2', r);
    n := dbms_sql.execute(c);
    dbms_sql.variable_value(c, 'bnd2', r);-- get value of outbind variable
    dbms_sql.close_cursor(c);
end;
/

```

vii) Out-bind in bulk PL/SQL

```

create or replace procedure foo (n number, square out number) is
begin square := n * n; end;/

create or replace procedure bulk_plsql
    (n dbms_sql.number_table, square out dbms_sql.number_table) is
c number;
r number;
begin
    c := dbms_sql.open_cursor;
    dbms_sql.parse(c, 'begin foo(:bnd1, :bnd2); end;', 2);
    dbms_sql.bind_array(c, 'bnd1', n);
    dbms_sql.bind_array(c, 'bnd2', square);
    r := dbms_sql.execute(c);
    dbms_sql.variable_value(c, 'bnd2', square);
end;
/

```

Note: DBMS_SQL.BIND_ARRAY of number_Table internally binds a number. The number of times statement is run depends on the number of elements in an inbind array.

Summary of DBMS_SQL Subprograms

Table 90–1 DBMS_SQL Package Subprograms

Subprogram	Description
BIND_ARRAY Procedures on page 90-27	Binds a given value to a given collection
BIND_VARIABLE Procedures on page 90-30	Binds a given value to a given variable
CLOSE_CURSOR Procedure on page 90-35	Closes given cursor and frees memory
COLUMN_VALUE Procedure on page 90-36	Returns value of the cursor element for a given position in a cursor
COLUMN_VALUE_LONG Procedure on page 90-39	Returns a selected part of a LONG column, that has been defined using <code>DEFINE_COLUMN_LONG</code>
DEFINE_ARRAY Procedure on page 90-40	Defines a collection to be selected from the given cursor, used only with <code>SELECT</code> statements
DEFINE_COLUMN Procedure on page 90-43	Defines a column to be selected from the given cursor, used only with <code>SELECT</code> statements
DEFINE_COLUMN_LONG Procedure on page 90-45	Defines a LONG column to be selected from the given cursor, used only with <code>SELECT</code> statements
DESCRIBE_COLUMNS Procedure on page 90-46	Describes the columns for a cursor opened and parsed through <code>DBMS_SQL</code>
DESCRIBE_COLUMNS2 Procedure on page 90-47	Describes describes the specified column, an alternative to DESCRIBE_COLUMNS Procedure
EXECUTE Function on page 90-48	Executes a given cursor
EXECUTE_AND_FETCH Function on page 90-49	Executes a given cursor and fetch rows
FETCH_ROWS Function on page 90-50	Fetches a row from a given cursor
IS_OPEN Function on page 90-51	Returns <code>TRUE</code> if given cursor is open
LAST_ERROR_POSITION Function on page 90-52	Returns byte offset in the SQL statement text where the error occurred
LAST_ROW_COUNT Function on page 90-53	Returns cumulative count of the number of rows fetched

Table 90–1 (Cont.) DBMS_SQL Package Subprograms

Subprogram	Description
LAST_ROW_ID Function on page 90-54	Returns ROWID of last row processed
LAST_SQL_FUNCTION_CODE Function on page 90-55	Returns SQL function code for statement
OPEN_CURSOR Function on page 90-56	Returns cursor ID number of new cursor
PARSE Procedure on page 90-57	Parses given statement
VARIABLE_VALUE Procedures on page 90-60	Returns value of named variable for given cursor

BIND_ARRAY Procedures

This procedure binds a given value or set of values to a given variable in a cursor, based on the name of the variable in the statement.

Syntax

```
DBMS_SQL.BIND_ARRAY (
    c                IN INTEGER,
    name             IN VARCHAR2,
    <table_variable> IN <datatype>
    [,index1        IN INTEGER,
    index2          IN INTEGER]) );
```

Where the <table_variable> and its corresponding <datatype> can be any one of the following matching pairs:

```
<clob_tab>      Clob_Table
<bflt_tab>      Binary_Float_Table
<bdbl_tab>      Binary_Double_Table
<blob_tab>      Blob_Table
<bfile_tab>     Bfile_Table
<date_tab>      Date_Table
<num_tab>       Number_Table
<urowid_tab>    Urowid_Table
<vchr2_tab>     Varchar2_Table
```

Notice that the BIND_ARRAY procedure is overloaded to accept different datatypes.

Parameters

Table 90–2 BIND_ARRAY Procedure Parameters

Parameter	Description
c	ID number of the cursor to which you want to bind a value.
name	Name of the collection in the statement.
table_variable	Local variable that has been declared as <datatype>.
index1	Index for the table element that marks the lower bound of the range.
index2	Index for the table element that marks the upper bound of the range.

Usage Notes

The length of the bind variable name should be ≤ 30 bytes.

For binding a range, the table must contain the elements that specify the range — `tab(index1)` and `tab(index2)` — but the range does not have to be dense. `index1` must be less than or equal to `index2`. All elements between `tab(index1)` and `tab(index2)` are used in the bind.

If you do not specify indexes in the bind call, and two different binds in a statement specify tables that contain a different number of elements, then the number of elements actually used is the minimum number between all tables. This is also the case if you specify indexes — the minimum range is selected between the two indexes for all tables.

Not all bind variables in a query have to be array binds. Some can be regular binds and the same value are used for each element of the collections in expression evaluations (and so forth).

See Also: ["Examples 3, 4, and 5: Bulk DML"](#) on page 90-14 for examples of how to bind collections.

Bulk Array Binds

Bulk selects, inserts, updates, and deletes can enhance the performance of applications by bundling many calls into one. The `DBMS_SQL` package lets you work on collections of data using the PL/SQL table type.

Table items are unbounded homogeneous collections. In persistent storage, they are like other relational tables and have no intrinsic ordering. But when a table item is brought into the workspace (either by querying or by navigational access of persistent data), or when it is created as the value of a PL/SQL variable or parameter, its elements are given subscripts that can be used with array-style syntax to get and set the values of elements.

The subscripts of these elements need not be dense, and can be any number including negative numbers. For example, a table item can contain elements at locations -10, 2, and 7 only.

When a table item is moved from transient workspace to persistent storage, the subscripts are not stored; the table item is unordered in persistent storage.

At bind time the table is copied out from the PL/SQL buffers into local `DBMS_SQL` buffers (the same as for all scalar types) and then the table is manipulated from the local `DBMS_SQL` buffers. Therefore, if you change the table after the bind call, then that change does not affect the way the execute acts.

Types for Scalar and LOB Collections

You can declare a local variable as one of the following table-item types, which are defined as public types in DBMS_SQL.

```

TYPE binary_double_table
    IS TABLE OF BINARY_DOUBLE INDEX BY BINARY_INTEGER;
TYPE binary_float_table
    IS TABLE OF BINARY_FLOAT INDEX BY BINARY_INTEGER;
TYPE bfile_table IS TABLE OF BFILE INDEX BY BINARY_INTEGER;
TYPE blob_table IS TABLE OF BLOB INDEX BY BINARY_INTEGER;
TYPE clob_table IS TABLE OF CLOB INDEX BY BINARY_INTEGER;
TYPE date_table IS TABLE OF DATE INDEX BY BINARY_INTEGER;
TYPE interval_day_to_second_Table
    IS TABLE OF dsinterval_unconstrained
    INDEX BY BINARY_INTEGER;
TYPE interval_year_to_MONTH_Table
    IS TABLE OF yminterval_unconstrained
    INDEX BY BINARY_INTEGER;
TYPE number_table IS TABLE OF NUMBER INDEX BY BINARY_INTEGER;
TYPE time_table IS TABLE OF time_unconstrained
    INDEX BY BINARY_INTEGER;
TYPE time_with_time_zone_table
    IS TABLE OF time_tz_unconstrained
    INDEX BY BINARY_INTEGER;
TYPE timestamp_table
    IS TABLE OF timestamp_unconstrained
    INDEX BY BINARY_INTEGER;
TYPE timestamp_with_ltz_Table
    IS TABLE OF timestamp_ltz_unconstrained
    INDEX BY BINARY_INTEGER;
TYPE timestamp_with_time_zone_Table
    IS TABLE OF timestamp_tz_unconstrained
    INDEX BY BINARY_INTEGER;
TYPE urowid_table IS TABLE OF UROWID INDEX BY BINARY_INTEGER;
TYPE varchar2_table IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER;

<tm_tab> Time_Table
<ttz_tab> Time_With_Time_Zone_Table
<tms_tab> Timestamp_Table
<tstz_tab> Timestamp_With_ltz_Table;
<tstz_tab> Timestamp_With_Time_Zone_Table
<ids_tab> Interval_Day_To_Second_Table
<iym_tab> Interval_Year_To_Month_Table

```

BIND_VARIABLE Procedures

This procedure binds a given value or set of values to a given variable in a cursor, based on the name of the variable in the statement.

Syntax

```
DBMS_SQL.BIND_VARIABLE (
    c           IN INTEGER,
    name        IN VARCHAR2,
    value       IN <datatype>)
```

Where <datatype> can be any one of the following types:

```
BINARY_DOUBLE
BINARY_FLOAT
BFILE
BLOB
CLOB CHARACTER SET ANY_CS
DATE
DSINTERVAL_UNCONSTRAINED
NUMBER
TIME_UNCONSTRAINED
TIME_TZ_UNCONSTRAINED
TIMESTAMP_LTZ_UNCONSTRAINED
TIMESTAMP_TZ_UNCONSTRAINED
TIMESTAMP_UNCONSTRAINED
UROWID
VARCHAR2 CHARACTER SET ANY_CS
YMINTERVAL_UNCONSTRAINED
```

Notice that `BIND_VARIABLE` is overloaded to accept different datatypes.

The following syntax is also supported for `BIND_VARIABLE`. The square brackets [] indicate an optional parameter for the `BIND_VARIABLE` function.

```
DBMS_SQL.BIND_VARIABLE (
    c           IN INTEGER,
    name        IN VARCHAR2,
    value       IN VARCHAR2 CHARACTER SET ANY_CS [,out_value_size IN
INTEGER]);
```

To bind `CHAR`, `RAW`, and `ROWID` data, you can use the following variations on the syntax:

```
DBMS_SQL.BIND_VARIABLE_CHAR (
    c           IN INTEGER,
    name        IN VARCHAR2,
    value       IN CHAR CHARACTER SET ANY_CS [,out_value_size IN INTEGER]);
```

```
DBMS_SQL.BIND_VARIABLE_RAW (
    c           IN INTEGER,
    name        IN VARCHAR2,
    value       IN RAW [,out_value_size IN INTEGER]);
```

```
DBMS_SQL.BIND_VARIABLE_ROWID (
    c           IN INTEGER,
    name        IN VARCHAR2,
    value       IN ROWID);
```

See Also: *Oracle Database Application Developer's Guide - Large Objects*

Pragmas

```
pragma restrict_references(bind_variable,WNDS);
```

Parameters

Table 90–3 *BIND_VARIABLE Procedure Parameters*

Parameter	Description
c	ID number of the cursor to which you want to bind a value.
name	Name of the variable in the statement.
value	Value that you want to bind to the variable in the cursor. For IN and IN/OUT variables, the value has the same type as the type of the value being passed in for this parameter.
out_value_size	Maximum expected OUT value size, in bytes, for the VARCHAR2, RAW, CHAR OUT or IN/OUT variable. If no size is given, then the length of the current value is used. This parameter must be specified if the value parameter is not initialized.

Usage Notes

If the variable is an IN or IN/OUT variable or an IN collection, then the given bind value must be valid for the variable or array type. Bind values for OUT variables are ignored.

The bind variables or collections of a SQL statement are identified by their names. When binding a value to a bind variable or bind array, the string identifying it in the statement must contain a leading colon, as shown in the following example:

```
SELECT emp_name FROM emp WHERE SAL > :X;
```

For this example, the corresponding bind call would look similar to

```
BIND_VARIABLE(cursor_name, 'X', 3500);
```

or

```
BIND_VARIABLE (cursor_name, 'X', 3500);
```

The length of the bind variable name should be ≤ 30 bytes.

The length of the bind variable name should be ≤ 30 bytes.

For binding a range, the table must contain the elements that specify the range — `tab(index1)` and `tab(index2)` — but the range does not have to be dense. `index1` must be less than or equal to `index2`. All elements between `tab(index1)` and `tab(index2)` are used in the bind.

If you do not specify indexes in the bind call, and two different binds in a statement specify tables that contain a different number of elements, then the number of elements actually used is the minimum number between all tables. This is also the case if you specify indexes — the minimum range is selected between the two indexes for all tables.

Not all bind variables in a query have to be array binds. Some can be regular binds and the same value are used for each element of the collections in expression evaluations (and so forth).

See Also: ["Examples 3, 4, and 5: Bulk DML"](#) on page 90-14 for examples of how to bind collections.

Bulk Array Binds

Bulk selects, inserts, updates, and deletes can enhance the performance of applications by bundling many calls into one. The `DBMS_SQL` package lets you work on collections of data using the PL/SQL table type.

Table items are unbounded homogeneous collections. In persistent storage, they are like other relational tables and have no intrinsic ordering. But when a table item is brought into the workspace (either by querying or by navigational access of persistent data), or when it is created as the value of a PL/SQL variable or

parameter, its elements are given subscripts that can be used with array-style syntax to get and set the values of elements.

The subscripts of these elements need not be dense, and can be any number including negative numbers. For example, a table item can contain elements at locations -10, 2, and 7 only.

When a table item is moved from transient workspace to persistent storage, the subscripts are not stored; the table item is unordered in persistent storage.

At bind time the table is copied out from the PL/SQL buffers into local DBMS_SQL buffers (the same as for all scalar types) and then the table is manipulated from the local DBMS_SQL buffers. Therefore, if you change the table after the bind call, then that change does not affect the way the execute acts.

Types for Scalar and LOB Collections

You can declare a local variable as one of the following table-item types, which are defined as public types in DBMS_SQL.

```

TYPE binary_double_table
            IS TABLE OF BINARY_DOUBLE   INDEX BY BINARY_INTEGER;
TYPE binary_float_table
            IS TABLE OF BINARY_FLOAT    INDEX BY BINARY_INTEGER;
TYPE bfile_table
            IS TABLE OF BFILE           INDEX BY BINARY_INTEGER;
TYPE blob_table
            IS TABLE OF BLOB            INDEX BY BINARY_INTEGER;
TYPE clob_table
            IS TABLE OF CLOB            INDEX BY BINARY_INTEGER;
TYPE date_table
            IS TABLE OF DATE            INDEX BY BINARY_INTEGER;
TYPE interval_day_to_second_Table
            IS TABLE OF dsinterval_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE interval_year_to_MONTH_Table
            IS TABLE OF yminterval_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE number_table
            IS TABLE OF NUMBER          INDEX BY BINARY_INTEGER;
TYPE time_table
            IS TABLE OF time_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE time_with_time_zone_table
            IS TABLE OF time_tz_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE timestamp_table
            IS TABLE OF timestamp_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE timestamp_with_ltz_Table
            IS TABLE OF timestamp_ltz_unconstrained
                                   INDEX BY BINARY_INTEGER;

```

```
TYPE timestamp_with_time_zone_Table
      IS TABLE OF timestamp_tz_unconstrained
                                INDEX BY BINARY_INTEGER;
TYPE urowid_table IS TABLE OF UROWID      INDEX BY BINARY_INTEGER;
TYPE varchar2_table IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER;

<tm_tab>    Time_Table
<ttz_tab>   Time_With_Time_Zone_Table
<tms_tab>   Timestamp_Table
<tstz_tab>  Timestamp_With_ltz_Table;
<tstz_tab>  Timestamp_With_Time_Zone_Table
<ids_tab>   Interval_Day_To_Second_Table
<iym_tab>   Interval_Year_To_Month_Table
```


CLOSE_CURSOR Procedure

This procedure closes a given cursor.

Syntax

```
DBMS_SQL.CLOSE_CURSOR (  
    c      IN OUT INTEGER);
```

Pragmas

```
pragma restrict_references(close_cursor,RNDS,WNDS);
```

Parameters

Table 90–4 *CLOSE_CURSOR Procedure Parameters*

Parameter	Mode	Description
c	IN	ID number of the cursor that you want to close.
c	OUT	Cursor is set to null. After you call <code>CLOSE_CURSOR</code> , the memory allocated to the cursor is released and you can no longer fetch from that cursor.

COLUMN_VALUE Procedure

This procedure returns the value of the cursor element for a given position in a given cursor. This procedure is used to access the data fetched by calling `FETCH_ROWS`.

Syntax

```
DBMS_SQL.COLUMN_VALUE (  
    c                IN  INTEGER,  
    position         IN  INTEGER,  
    value            OUT <datatype>  
    [,column_error   OUT NUMBER]  
    [,actual_length  OUT INTEGER]);
```

Where <datatype> can be any one of the following types:

```
BINARY_DOUBLE  
BINARY_FLOAT  
BFILE  
BLOB  
CLOB CHARACTER SET ANY_CS  
DATE  
DSINTERVAL_UNCONSTRAINED  
NUMBER  
TIME_TZ_UNCONSTRAINED  
TIME_UNCONSTRAINED  
TIMESTAMP_LTZ_UNCONSTRAINED  
TIMESTAMP_TZ_UNCONSTRAINED  
TIMESTAMP_UNCONSTRAINED  
UROWID  
VARCHAR2 CHARACTER SET ANY_CS  
YMINTERVAL_UNCONSTRAINED  
  
<tm_tab>    Time_Table  
<tztz_tab>  Time_With_Time_Zone_Table  
<tms_tab>   Timestamp_Table  
<tstz_tab>  Timestamp_With_ltz_Table;  
<tstz_tab>  Timestamp_With_Time_Zone_Table  
<ids_tab>   Interval_Day_To_Second_Table  
<iym_tab>   Interval_Year_To_Month_Table
```

Note: The square brackets [] indicate optional parameters.

See Also: *Oracle Database Application Developer's Guide - Large Objects*

Pragmas

```
pragma restrict_references(column_value,RNDS,WNDS);
```

The following syntax is also supported for the COLUMN_VALUE procedure:

```
DBMS_SQL.COLUMN_VALUE(
    c                IN  INTEGER,
    position         IN  INTEGER,
    <table_variable> IN  <datatype>);
```

Where the <table_variable> and its corresponding <datatype> can be any one of these matching pairs:

<bdbl_tab>	Binary_Double_Table
<bflt_tab>	Binary_Float_Table
<bfile_tab>	Bfile_Table
<blob_tab>	Blob_Table
<clob_tab>	Clob_Table
<date_tab>	Date_Table
<ids_tab>	Interval_Day_To_Second_Table
<iym_tab>	Interval_Year_To_Month_Table
<num_tab>	Number_Table
<tm_tab>	Time_Table
<ttz_tab>	Time_With_Time_Zone_Table
<tms_tab>	Timestamp_Table
<tstz_tab>	Timestamp_With_ltz_Table;
<tstz_tab>	Timestamp_With_Time_Zone_Table
<urowid_tab>	Urowid_Table
<vchr2_tab>	Varchar2_Table

For columns containing CHAR, RAW, and ROWID data, you can use the following variations on the syntax:

```
DBMS_SQL.COLUMN_VALUE_CHAR (
    c                IN  INTEGER,
    position         IN  INTEGER,
    value            OUT CHAR CHARACTER SET ANY_CS
    [,column_error   OUT NUMBER]
    [,actual_length  OUT INTEGER]);
```

```
DBMS_SQL.COLUMN_VALUE_RAW (
    c                IN  INTEGER,
```

```

    position      IN  INTEGER,
    value         OUT RAW
  [,column_error OUT NUMBER]
  [,actual_length OUT INTEGER]);

```

```

DBMS_SQL.COLUMN_VALUE_ROWID (
  c           IN  INTEGER,
  position    IN  INTEGER,
  value       OUT ROWID
  [,column_error OUT NUMBER]
  [,actual_length OUT INTEGER]);

```

Parameters

Table 90–5 *COLUMN_VALUE Procedure Parameters*

Parameter	Description
<code>c</code>	ID number of the cursor from which you are fetching the values.
<code>position</code>	Relative position of the column in the cursor. The first column in a statement has position 1.
<code>value</code>	Returns the value at the specified column and row. If the row number specified is greater than the total number of rows fetched, then you receive an error message. Oracle raises exception <code>ORA-06562, inconsistent_type</code> , if the type of this output parameter differs from the actual type of the value, as defined by the call to <code>DEFINE_COLUMN</code> .
<code>table_variable</code>	Local variable that has been declared <code><datatype></code> .
<code>column_error</code>	Returns any error code for the specified column value.
<code>actual_length</code>	The actual length, before any truncation, of the value in the specified column.

Exceptions

`inconsistent_type` (ORA-06562) is raised if the type of the given OUT parameter value is different from the actual type of the value. This type was the given type when the column was defined by calling procedure `DEFINE_COLUMN`.

COLUMN_VALUE_LONG Procedure

This procedure gets part of the value of a long column.

Syntax

```
DBMS_SQL.COLUMN_VALUE_LONG (
    c           IN  INTEGER,
    position    IN  INTEGER,
    length      IN  INTEGER,
    offset      IN  INTEGER,
    value       OUT VARCHAR2,
    value_length OUT INTEGER);
```

Pragmas

```
pragma restrict_references(column_value_long,RNDS,WNDS);
```

Parameters

Table 90–6 *COLUMN_VALUE_LONG Procedure Parameters*

Parameter	Description
c	Cursor ID number of the cursor from which to get the value.
position	Position of the column of which to get the value.
length	Number of bytes of the long value to fetch.
offset	Offset into the long field for start of fetch.
value	Value of the column as a VARCHAR2.
value_length	Number of bytes actually returned in value.

DEFINE_ARRAY Procedure

This procedure defines the collection for column into which you want to fetch rows (with a `FETCH_ROWS` call). This procedure lets you do batch fetching of rows from a single `SELECT` statement. A single fetch call brings over a number of rows into the PL/SQL aggregate object.

When you fetch the rows, they are copied into `DBMS_SQL` buffers until you run a `COLUMN_VALUE` call, at which time the rows are copied into the table that was passed as an argument to the `COLUMN_VALUE` call.

Scalar and LOB Types for Collections

You can declare a local variable as one of the following table-item types, and then fetch any number of rows into it using `DBMS_SQL`. (These are the same types as you can specify for the `BIND_ARRAY` procedure.)

```

TYPE binary_double_table
           IS TABLE OF BINARY_DOUBLE INDEX BY BINARY_INTEGER;
TYPE binary_float_table
           IS TABLE OF BINARY_FLOAT INDEX BY BINARY_INTEGER;
TYPE bfile_table
           IS TABLE OF BFILE INDEX BY BINARY_INTEGER;
TYPE blob_table
           IS TABLE OF BLOB INDEX BY BINARY_INTEGER;
TYPE clob_table
           IS TABLE OF CLOB INDEX BY BINARY_INTEGER;
TYPE date_table
           IS TABLE OF DATE INDEX BY BINARY_INTEGER;
TYPE interval_day_to_second_Table
           IS TABLE OF dsinterval_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE interval_year_to_MONTH_Table
           IS TABLE OF yminterval_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE number_table
           IS TABLE OF NUMBER INDEX BY BINARY_INTEGER;
TYPE time_table
           IS TABLE OF time_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE time_with_time_zone_table
           IS TABLE OF time_tz_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE timestamp_table
           IS TABLE OF timestamp_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE timestamp_with_ltz_Table
           IS TABLE OF timestamp_ltz_unconstrained
                                   INDEX BY BINARY_INTEGER;
TYPE timestamp_with_time_zone_Table

```

```

                                IS TABLE OF timestamp_tz_unconstrained
                                INDEX BY BINARY_INTEGER;
TYPE urowid_table  IS TABLE OF UROWID          INDEX BY BINARY_INTEGER;
TYPE varchar2_table IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER;

<tm_tab>    Time_Table
<ttz_tab>   Time_With_Time_Zone_Table
<tms_tab>   Timestamp_Table
<tstz_tab>  Timestamp_With_ltz_Table;
<tstz_tab>  Timestamp_With_Time_Zone_Table
<ids_tab>   Interval_Day_To_Second_Table
<iym_tab>   Interval_Year_To_Month_Table

```

Syntax

```

DBMS_SQL.DEFINE_ARRAY (
    c           IN INTEGER,
    position    IN INTEGER,
    <table_variable>  IN <datatype>
    cnt         IN INTEGER,
    lower_bnd   IN INTEGER);

```

Where <table_variable> and its corresponding <datatype> can be any one of the following matching pairs:

```

<clob_tab>    Clob_Table
<bflt_tab>    Binary_Float_Table
<bdbl_tab>    Binary_Double_Table
<blob_tab>    Blob_Table
<bfile_tab>   Bfile_Table
<date_tab>    Date_Table
<num_tab>     Number_Table
<urowid_tab>  Urowid_Table
<vchr2_tab>   Vvarchar2_Table

```

Notice that DEFINE_ARRAY is overloaded to accept different datatypes.

Pragmas

```
pragma restrict_references(define_array,RNDS,WNDS);
```

The subsequent FETCH_ROWS call fetch "count" rows. When the COLUMN_VALUE call is made, these rows are placed in positions indx, indx+1, indx+2, and so on. While there are still rows coming, the user keeps issuing FETCH_ROWS/COLUMN_

VALUE calls. The rows keep accumulating in the table specified as an argument in the COLUMN_VALUE call.

Parameters

Table 90–7 *DEFINE_ARRAY Procedure Parameters*

Parameter	Description
<code>c</code>	ID number of the cursor to which you want to bind an array.
<code>position</code>	Relative position of the column in the array being defined. The first column in a statement has position 1.
<code>table_variable</code>	Local variable that has been declared as <datatype>.
<code>cnt</code>	Number of rows that must be fetched.
<code>lower_bnd</code>	Results are copied into the collection, starting at this lower bound index.

The count (`cnt`) must be an integer greater than zero; otherwise an exception is raised. The `indx` can be positive, negative, or zero. A query on which a `DEFINE_ARRAY` call was issued cannot contain array binds.

See Also: ["Examples 6 and 7: Defining an Array"](#) on page 90-16 for examples of how to define collections.

DEFINE_COLUMN Procedure

This procedure defines a column to be selected from the given cursor. This procedure is only used with `SELECT` cursors.

The column being defined is identified by its relative position in the `SELECT` list of the statement in the given cursor. The type of the `COLUMN` value determines the type of the column being defined.

Syntax

```
DBMS_SQL.DEFINE_COLUMN (
    c                IN INTEGER,
    position         IN INTEGER,
    column           IN <datatype>)
```

Where <datatype> can be any one of the following types:

```
BINARY_DOUBLE
BINARY_FLOAT
BFILE
BLOB
CLOB CHARACTER SET ANY_CS
DATE
DSINTERVAL_UNCONSTRAINED
NUMBER
TIME_UNCONSTRAINED
TIME_TZ_UNCONSTRAINED
TIMESTAMP_LTZ_UNCONSTRAINED
TIMESTAMP_TZ_UNCONSTRAINED
TIMESTAMP_UNCONSTRAINED
UROWID
VARCHAR2 CHARACTER SET ANY_CS
YMINTERVAL_UNCONSTRAINED
```

Notice that `DEFINE_COLUMN` is overloaded to accept different datatypes.

See Also: *Oracle Database Application Developer's Guide - Large Objects*

Pragmas

```
pragma restrict_references(define_column,RNDS,WNDS);
```

The following syntax is also supported for the DEFINE_COLUMN procedure:

```
DBMS_SQL.DEFINE_COLUMN (
    c           IN INTEGER,
    position    IN INTEGER,
    column      IN VARCHAR2 CHARACTER SET ANY_CS,
    column_size IN INTEGER),
    urowid      IN INTEGER;
```

To define columns with CHAR, RAW, and ROWID data, you can use the following variations on the procedure syntax:

```
DBMS_SQL.DEFINE_COLUMN_CHAR (
    c           IN INTEGER,
    position    IN INTEGER,
    column      IN CHAR CHARACTER SET ANY_CS,
    column_size IN INTEGER);
```

```
DBMS_SQL.DEFINE_COLUMN_RAW (
    c           IN INTEGER,
    position    IN INTEGER,
    column      IN RAW,
    column_size IN INTEGER);
```

```
DBMS_SQL.DEFINE_COLUMN_ROWID (
    c           IN INTEGER,
    position    IN INTEGER,
    column      IN ROWID);
```

Parameters

Table 90–8 DEFINE_COLUMN Procedure Parameters

Parameter	Description
c	ID number of the cursor for the row being defined to be selected.
position	Relative position of the column in the row being defined. The first column in a statement has position 1.
column	Value of the column being defined. The type of this value determines the type for the column being defined.
column_size	Maximum expected size of the column value, in bytes, for columns of type VARCHAR2, CHAR, and RAW.

DEFINE_COLUMN_LONG Procedure

This procedure defines a `LONG` column for a `SELECT` cursor. The column being defined is identified by its relative position in the `SELECT` list of the statement for the given cursor. The type of the `COLUMN` value determines the type of the column being defined.

Syntax

```
DBMS_SQL.DEFINE_COLUMN_LONG (  
    c           IN INTEGER,  
    position   IN INTEGER);
```

Parameters

Table 90–9 *DEFINE_COLUMN_LONG Procedure Parameters*

Parameter	Description
<code>c</code>	ID number of the cursor for the row being defined to be selected.
<code>position</code>	Relative position of the column in the row being defined. The first column in a statement has position 1.

DESCRIBE_COLUMNS Procedure

This procedure describes the columns for a cursor opened and parsed through DBMS_SQL.

Syntax

```
DBMS_SQL.DESCRIBE_COLUMNS (  
    c           IN  INTEGER,  
    col_cnt    OUT INTEGER,  
    desc_t     OUT DESC_TAB);
```

Parameters

Table 90–10 *DBMS_SQL.DESCRIBE_COLUMNS Procedure Parameters*

Parameter	Description
c	ID number of the cursor for the columns being described.
col_cnt	Number of columns in the select list of the query.
desc_t	Table of DESC_REC, each DESC_REC describing a column in the query.

See Also: ["Example 8: Describe Columns"](#) on page 90-19 illustrates how to use DESCRIBE_COLUMNS.

DESCRIBE_COLUMNS2 Procedure

This function describes the specified column. This is an alternative to [DESCRIBE_COLUMNS Procedure](#).

Syntax

```
DBMS_SQL.DESCRIBE_COLUMNS2 (  
    c           IN INTEGER,  
    col_cnt     OUT INTEGER,  
    desc_tab2   OUT DESC_TAB);
```

Pragmas

```
PRAGMA RESTRICT_REFERENCES(describe_columns2,WNDS);
```

Parameters

Table 90–11 *DBMS_SQL.DESCRIBE_COLUMNS2 Procedure Parameters*

Parameter	Description
c	ID number of the cursor for the columns being described.
col_cnt	Number of columns in the select list of the query.
desc_tab2	The describe table to fill in with the description of each of the columns of the query. This table is indexed from one to the number of elements in the select list of the query.

EXECUTE Function

This function executes a given cursor. This function accepts the ID number of the cursor and returns the number of rows processed. The return value is only valid for INSERT, UPDATE, and DELETE statements; for other types of statements, including DDL, the return value is undefined and should be ignored.

Syntax

```
DBMS_SQL.EXECUTE (  
    c    IN INTEGER)  
RETURN INTEGER;
```

Parameters

Table 90–12 EXECUTE Function Parameters

Parameter	Description
c	Cursor ID number of the cursor to execute.

EXECUTE_AND_FETCH Function

This function executes the given cursor and fetches rows. This function provides the same functionality as calling `EXECUTE` and then calling `FETCH_ROWS`. Calling `EXECUTE_AND_FETCH` instead, however, may reduce the number of network round-trips when used against a remote database.

The `EXECUTE_AND_FETCH` function returns the number of rows actually fetched.

Syntax

```
DBMS_SQL.EXECUTE_AND_FETCH (
    c           IN INTEGER,
    exact       IN BOOLEAN DEFAULT FALSE)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(execute_and_fetch,WNDS);
```

Parameters

Table 90–13 EXECUTE_AND_FETCH Function Parameters

Parameter	Description
<code>c</code>	ID number of the cursor to execute and fetch.
<code>exact</code>	Set to <code>TRUE</code> to raise an exception if the number of rows actually matching the query differs from one. Note: Oracle does not support the exact fetch <code>TRUE</code> option with <code>LONG</code> columns. Even if an exception is raised, the rows are still fetched and available.

FETCH_ROWS Function

This function fetches a row from a given cursor. You can call `FETCH_ROWS` repeatedly as long as there are rows remaining to be fetched. These rows are retrieved into a buffer, and must be read by calling `COLUMN_VALUE`, for each column, after each call to `FETCH_ROWS`.

The `FETCH_ROWS` function accepts the ID number of the cursor to fetch, and returns the number of rows actually fetched.

Syntax

```
DBMS_SQL.FETCH_ROWS (
    c          IN INTEGER)
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(fetch_rows,WNDS);
```

Parameters

Table 90–14 *FETCH_ROWS Function Parameters*

Parameter	Description
c	ID number.

IS_OPEN Function

This function checks to see if the given cursor is currently open.

Syntax

```
DBMS_SQL.IS_OPEN (  
    c           IN INTEGER)  
    RETURN BOOLEAN;
```

Pragmas

```
pragma restrict_references(is_open,RNDS,WNDS);
```

Parameters

Table 90–15 IS_OPEN Function Parameters

Parameter	Description
c	Cursor ID number of the cursor to check.

Return Values

Table 90–16 IS_OPEN Function Return Values

Return Value	Description
TRUE	Given cursor is currently open.
FALSE	Given cursor is currently not open.

LAST_ERROR_POSITION Function

This function returns the byte offset in the SQL statement text where the error occurred. The first character in the SQL statement is at position 0.

Syntax

```
DBMS_SQL.LAST_ERROR_POSITION  
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(last_error_position,RNDS,WNDS);
```

Usage Notes

Call this function after a `PARSE` call, before any other `DBMS_SQL` procedures or functions are called.

LAST_ROW_COUNT Function

This function returns the cumulative count of the number of rows fetched.

Syntax

```
DBMS_SQL.LAST_ROW_COUNT  
    RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(last_row_count,RNDS,WNDS);
```

Usage Notes

Call this function after a `FETCH_ROWS` or an `EXECUTE_AND_FETCH` call. If called after an `EXECUTE` call, then the value returned is zero.

LAST_ROW_ID Function

This function returns the ROWID of the last row processed.

Syntax

```
DBMS_SQL.LAST_ROW_ID  
RETURN ROWID;
```

Pragmas

```
pragma restrict_references(last_row_id,RNDS,WNDS);
```

Usage Notes

Call this function after a `FETCH_ROWS` or an `EXECUTE_AND_FETCH` call.

LAST_SQL_FUNCTION_CODE Function

This function returns the SQL function code for the statement. These codes are listed in the *Oracle Call Interface Programmer's Guide*.

Syntax

```
DBMS_SQL.LAST_SQL_FUNCTION_CODE  
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(last_sql_function_code,RNDS,WNDS);
```

Usage Notes

You should call this function immediately after the SQL statement is run; otherwise, the return value is undefined.

OPEN_CURSOR Function

This procedure opens a new cursor. When you no longer need this cursor, you must close it explicitly by calling `CLOSE_CURSOR`.

You can use cursors to run the same SQL statement repeatedly or to run a new SQL statement. When a cursor is reused, the contents of the corresponding cursor data area are reset when the new SQL statement is parsed. It is never necessary to close and reopen a cursor before reusing it.

Syntax

```
DBMS_SQL.OPEN_CURSOR  
RETURN INTEGER;
```

Pragmas

```
pragma restrict_references(open_cursor,RNDS,WNDS);
```

Return Values

This function returns the cursor ID number of the new cursor.

PARSE Procedure

This procedure parses the given statement in the given cursor. All statements are parsed immediately. In addition, DDL statements are run immediately when parsed.

There are two versions of the PARSE procedure: one uses a VARCHAR2 statement as an argument, and the other uses a VARCHAR2S (table of VARCHAR2) as an argument.

Syntax

```
DBMS_SQL.PARSE (
    c                IN    INTEGER,
    statement        IN    VARCHAR2,
    language_flag   IN    INTEGER);
```

```
DBMS_SQL.PARSE (
    c                IN    INTEGER,
    statement        IN    VARCHAR2A,
    lb              IN    INTEGER,
    ub              IN    INTEGER,
    lfflg          IN    BOOLEAN,
    language_flag   IN    INTEGER);
```

The PARSE procedure also supports the following syntax for large SQL statements:

```
DBMS_SQL.PARSE (
    c                IN    INTEGER,
    statement        IN    VARCHAR2S,
    lb              IN    INTEGER,
    ub              IN    INTEGER,
    lfflg          IN    BOOLEAN,
    language_flag   IN    INTEGER);
```

Note: The procedure concatenates elements of a PL/SQL table statement and parses the resulting string. You can use this procedure to parse a statement that is longer than the limit for a single VARCHAR2 variable by splitting up the statement.

Parameters

Table 90–17 *PARSE Procedure Parameters*

Parameter	Description
<code>c</code>	ID number of the cursor in which to parse the statement.
<code>statement</code>	SQL statement to be parsed. Unlike PL/SQL statements, your SQL statement should not include a final semicolon. For example: <code>DBMS_SQL.PARSE(cursor1, 'BEGIN proc; END;', 2);</code> <code>DBMS_SQL.PARSE(cursor1, 'INSERT INTO tab values(1)', 2);</code>
<code>lb</code>	Lower bound for elements in the statement.
<code>ub</code>	Upper bound for elements in the statement.
<code>lfflg</code>	If <code>TRUE</code> , then insert a linefeed after each element on concatenation.
<code>language_flag</code>	Determines how Oracle handles the SQL statement. The following options are recognized: <ul style="list-style-type: none"> ▪ <code>V6</code> (or <code>0</code>) specifies version 6 behavior. ▪ <code>NATIVE</code> (or <code>1</code>) specifies normal behavior for the database to which the program is connected. ▪ <code>V7</code> (or <code>2</code>) specifies Oracle database version 7 behavior.

Usage Notes

Note: Using `DBMS_SQL` to dynamically run DDL statements can result in the program hanging. For example, a call to a procedure in a package results in the package being locked until the execution returns to the user side. Any operation that results in a conflicting lock, such as dynamically trying to drop the package before the first lock is released, results in a hang.

The size limit for parsing SQL statements with the preceding syntax is 32KB.

Note: Because client-side code cannot reference remote package variables or constants, you must explicitly use the values of the constants.

For example, the following code does *not* compile on the client:

```
DBMS_SQL.PARSE(cur_hdl, stmt_str, dbms_sql.V7); -- uses constant
dbms_sql.V7
```

The following code works on the client, because the argument is explicitly provided:

```
DBMS_SQL.PARSE(cur_hdl, stmt_str, 2); -- compiles on the client
```

Examples

To parse SQL statements larger than 32 KB, DBMS_SQL makes use of PL/SQL tables to pass a table of strings to the PARSE procedure. These strings are concatenated and then passed on to the Oracle server.

You can declare a local variable as the VARCHAR2S table-item type, and then use the PARSE procedure to parse a large SQL statement as VARCHAR2S.

The definition of the VARCHAR2S datatype is:

```
TYPE varchar2s IS TABLE OF VARCHAR2(256) INDEX BY BINARY_INTEGER;
```

Exceptions

If you create a type/procedure/function/package using DBMS_SQL that has compilation warnings, an ORA-24344 exception is raised, and the procedure is still created.

VARIABLE_VALUE Procedures

This procedure returns the value of the named variable for a given cursor. It is used to return the values of bind variables inside PL/SQL blocks or DML statements with `returning` clause.

Syntax

```
DBMS_SQL.VARIABLE_VALUE (  
    c                IN  INTEGER,  
    name             IN  VARCHAR2,  
    value            OUT <datatype>);
```

Where <datatype> can be any one of the following types:

```
BINARY_DOUBLE  
BINARY_FLOAT  
BFILE  
BLOB  
CLOB CHARACTER SET ANY_CS  
DATE  
DSINTERVAL_UNCONSTRAINED  
NUMBER  
TIME_TZ_UNCONSTRAINED  
TIME_UNCONSTRAINED  
TIMESTAMP_LTZ_UNCONSTRAINED  
TIMESTAMP_TZ_UNCONSTRAINED  
TIMESTAMP_UNCONSTRAINED  
UROWID  
VARCHAR2 CHARACTER SET ANY_CS  
YMINTERVAL_UNCONSTRAINED
```

The following syntax is also supported for the `VARIABLE_VALUE` procedure:

```
DBMS_SQL.VARIABLE_VALUE (  
    c                IN  INTEGER,  
    name             IN  VARCHAR2,  
    <table_variable> IN  <datatype>);
```

Where the <table_variable> and its corresponding <datatype> can be any one of these matching pairs:

```
<bdbl_tab>      Binary_Double_Table  
<bflt_tab>      Binary_Float_Table  
<bfile_tab>     Bfile_Table
```

<blob_tab>	Blob_Table
<clob_tab>	Clob_Table
<date_tab>	Date_Table
<ids_tab>	Interval_Day_To_Second_Table
<iym_tab>	Interval_Year_To_Month_Table
<num_tab>	Number_Table
<tm_tab>	Time_Table
<ttz_tab>	Time_With_Time_Zone_Table
<tms_tab>	Timestamp_Table
<tstz_tab>	Timestamp_With_ltz_Table;
<tstz_tab>	Timestamp_With_Time_Zone_Table
<urowid_tab>	Urowid_Table
<vchr2_tab>	Varchar2_Table

For variables containing CHAR, RAW, and ROWID data, you can use the following variations on the syntax:

```
DBMS_SQL.VARIABLE_VALUE_CHAR (
  c           IN  INTEGER,
  name        IN  VARCHAR2,
  value       OUT CHAR CHARACTER SET ANY_CS);
```

```
DBMS_SQL.VARIABLE_VALUE_RAW (
  c           IN  INTEGER,
  name        IN  VARCHAR2,
  value       OUT RAW);
```

```
DBMS_SQL.VARIABLE_VALUE_ROWID (
  c           IN  INTEGER,
  name        IN  VARCHAR2,
  value       OUT ROWID);
```

Pragmas

```
pragma restrict_references(variable_value,RNDS,WNDS);
```

Parameters

Table 90–18 *VARIABLE_VALUE Procedure Parameters*

Parameter	Description
<code>c</code>	ID number of the cursor from which to get the values.
<code>name</code>	Name of the variable for which you are retrieving the value.
<code>value</code>	Returns the value of the variable for the specified position. Oracle raises exception <code>ORA-06562, inconsistent_type</code> , if the type of this output parameter differs from the actual type of the value, as defined by the call to <code>BIND_VARIABLE</code> .
<code>position</code>	Relative position of the column in the cursor. The first column in a statement has position 1.

The DBMS_SQLTUNE package provides the interface to tune SQL statements.

The chapter contains the following topics:

- [Using DBMS_SQLTUNE](#)
 - [Overview](#)
 - [Types](#)
 - [Operational Notes](#)
- [Summary of DBMS_SQLTUNE Subprograms](#)

Using DBMS_SQLTUNE

- [Overview](#)
- [Types](#)
- [Operational Notes](#)

Overview

SQL Tuning Sets is a new object for capturing SQL workload information. SQL Tuning Sets provide a common infrastructure for dealing with SQL workloads and simplify tuning of a large number of SQL statements.

SQL Tuning Sets store SQL statements along with

- The execution context, such as the parsing schema name and bind values.
- Execution statistics such as average elapsed time and execution count.

SQL Tuning Sets can be created by filtering or ranking SQL statements from several sources:

- The cursor cache.
- AWR selecting top SQL statements executed during some prior interval
- A user-defined workload.
- Other SQL Tuning Sets.

Types

- [SqlSet_cursor](#)

SqlSet_cursor

This defines a cursor type for SQL statements with their related data. This type is mainly used by the `LOAD_SQLSET` procedure as an argument to populate a `SqlSet` from a possible data source. See the [LOAD_SQLSET Procedure](#) on page 91-21 for more details.

It is important to keep in mind that this cursor is weakly defined.

Operational Notes

Under normal mode, the Cost Based Optimizer (CBO) produces the best possible execution plan with whatever information is currently available for the query. It does not have time to gather additional information that might improve the plan because the CBO has to generate an execution plan in a fraction of a second under normal mode. However, in the Plan Tuning Analysis mode, the CBO has time to gather additional information for the query, in the form of a SQL Profile, and this profile allows the generation of a superior execution plan that is well tuned.

In the Plan Tuning Analysis mode, the CBO collects the SQL Profile for the query automatically and the DBA can then decide whether to activate the profile or not. Once activated, the CBO uses the SQL Profile under normal mode to generate the well-tuned plan, that is superior to the original.

Note that SQL Profile is stored persistently in data dictionary, and hence this form of tuning does not require any application code changes.

Summary of DBMS_SQLTUNE Subprograms

Table 91–1 DBMS_SQLTUNE Package Subprograms

Subprogram	Description
ACCEPT_SQL_PROFILE Procedure on page 91-6	Create a SQL Profile for the specified tuning task
ADD_SQLSET_REFERENCE Function on page 91-8	Adds a new reference to an existing SqlSet to indicate its use by a client
ALTER_SQL_PROFILE Procedure on page 91-9	Alters specific attributes of an existing SQL Profile object
CANCEL_TUNING_TASK Procedure on page 91-10	Cancel the currently executing tuning task
CREATE_SQLSET Procedure on page 91-11	Creates a SqlSet object in the database
CREATE_TUNING_TASK Functions on page 91-12	Prepares the tuning of a single statement or SqlSet
DELETE_SQLSET Procedure on page 91-15	Deletes a set of SQL statements from a SqlSet
DROP_SQL_PROFILE Procedure on page 91-16	Drops the named SQL Profile from the database
DROP_SQLSET Procedure on page 91-17	Drops a SqlSet if it is not active
DROP_TUNING_TASK Procedure on page 91-18	Drops a SQL tuning task
EXECUTE_TUNING_TASK Procedure on page 91-19	Executes a previously created tuning task
INTERRUPT_TUNING_TASK Procedure on page 91-20	Interrupts the currently executing tuning task to allow access intermediate result data
LOAD_SQLSET Procedure on page 91-21	Populates the SqlSet with a set of selected SQL
REMOVE_SQLSET_REFERENCE Procedure on page 91-22	Deactivates a SqlSet to indicate it is no longer used by the client
REPORT_TUNING_TASK Function on page 91-23	Displays the results of a tuning task

Table 91–1 (Cont.) DBMS_SQLTUNE Package Subprograms (Cont.)

Subprogram	Description
RESET_TUNING_TASK Procedure on page 91-24	Resets the currently executing tuning task to its initial state
RESUME_TUNING_TASK Procedure on page 91-25	Resumes a previously interrupted tuning task
SELECT_SQLSET Function on page 91-26	Collects SQL statements from the cursor cache
SELECT_WORKLOAD_REPOSITORY Functions on page 91-27	Collects SQL statements from workload repository
UPDATE_SQLSET Procedures on page 91-29	Updates whether selected string fields for a SQL statement in a SqlSet or the set numerical attributes of a SQL in a SqlSet

ACCEPT_SQL_PROFILE Procedure

This procedure accepts a SQL Profile recommended by the SQL Tuning Advisor. The SQL text is normalized for matching purposes though it is stored in the data dictionary in de-normalized form for readability. SQL text is provided through a reference to the SQL Tuning task. If the referenced SQL statement doesn't exist, an error is reported.

Syntax

```
DBMS_SQLTUNE.ACCEPT_SQL_PROFILE (
    task_name      IN  VARCHAR2,
    object_id      IN  NUMBER    := NULL,
    name           IN  VARCHAR2  := NULL,
    description    IN  VARCHAR2  := NULL,
    category       IN  VARCHAR2  := NULL);
```

Parameters

Table 91–2 ACCEPT_SQL_PROFILE Procedure Parameters

Parameter	Description
task_name	The (mandatory) name of the SQL tuning task.
object_id	The (optional) identifier of the framework object representing the SQL statement associated with the tuning task.
name	The name of the SQL Profile. It cannot contain double quotation marks. The name is case sensitive. If not specified, the system will generate a unique name for the SQL Profile.
description	A user specified string describing the purpose of the SQL Profile. The maximum size is 500 characters.
category	This is the category name which must match the value of the SQLTUNE_CATEGORY parameter in a session for the session to use this SQL Profile. It defaults to the value "DEFAULT". This is also the default of the SQLTUNE_CATEGORY parameter. The category must be a valid Oracle identifier. The category name specified is always converted to upper case. The combination of the normalized SQL text and category name create a unique key for a SQL Profile. An ACCEPT_SQL_PROFILE will fail if this combination is duplicated.

Usage Notes

The "CREATE ANY SQL PROFILE" privilege is required.

ADD_SQLSET_REFERENCE Function

This procedure adds a new reference to an existing SqlSet to indicate its use by a client.

Syntax

```
DBMS_SQLTUNE.ADD_SQLSET_REFERENCE (  
    sqlset_name IN VARCHAR2,  
    description IN VARCHAR2 := NULL)  
RETURN NUMBER;
```

Parameters

Table 91–3 ADD_SQLSET_REFERENCE Function Parameters

Parameter	Description
sqlset_name	The SqlSet name.
description	The description of the usage of SqlSet.

Return Values

The identifier of the added reference.

ALTER_SQL_PROFILE Procedure

This procedure alters specific attributes of an existing SQL Profile object. The following attributes can be altered (using these attribute names):

- "STATUS" can be set to "ENABLED" or "DISABLED"
- "NAME" can be reset to a valid name which must be a valid Oracle identifier and must be unique.
- "DESCRIPTION" can be set to any string of size no more than 500 characters
- "CATEGORY" can be reset to a valid category name which must be a valid Oracle identifier and must be unique when combined with normalized SQL text)

Syntax

```
DBMS_SQLTUNE.ALTER_SQL_PROFILE (
  name           IN VARCHAR2,
  attribute_name IN VARCHAR2,
  value          IN VARCHAR2);
```

Parameters

Table 91–4 ALTER_SQL_PROFILE Procedure Parameters

Parameter	Description
name	The (mandatory) name of the existing SQL Profile to alter
attribute_name	The (mandatory) attribute name to alter (case insensitive) using valid attribute names.
value	The (mandatory) new value of the attribute using valid attribute values.

Usage Notes

Requires the "ALTER ANY SQL PROFILE" privilege.

CANCEL_TUNING_TASK Procedure

This procedure cancels the currently executing tuning task. All intermediate result data is deleted.

Syntax

```
DBMS_SQLTUNE.CANCEL_TUNING_TASK(  
    task_name          IN VARCHAR2);
```

Parameters

Table 91-5 *CANCEL_TUNING_TASK Procedure Parameters*

Parameter	Description
task_name	The identifier of the task to execute.

CREATE_SQLSET Procedure

This procedure creates a SqlSet object in the database.

Syntax

```
DBMS_SQLTUNE.CREATE_SQLSET (  
    sqlset_name IN VARCHAR2,  
    description IN VARCHAR2 := NULL);
```

Parameters

Table 91–6 CREATE_SQLSET Procedure Parameters

Parameter	Description
sqlset_name	The SqlSet name.
description	The description of the SqlSet.

CREATE_TUNING_TASK Functions

You can use different forms of this function to:

- Prepare the tuning of a single statement given its text.
- Prepare the tuning of a single statement from the Cursor Cache given its identifier.
- Prepare the tuning of a single statement from the workload repository given a range of snapshot identifiers.
- Prepare the tuning of a SqlSet.

In all cases, the function mainly creates an advisor task and sets its parameters.

Syntax

```
DBMS_SQLTUNE.CREATE_TUNING_TASK(  
  sql_text          IN CLOB,  
  bind_list         IN sql_binds := NULL,  
  user_name         IN VARCHAR2  := NULL,  
  scope             IN VARCHAR2  := SCOPE_COMPREHENSIVE,  
  time_limit        IN NUMBER     := TIME_LIMIT_DEFAULT,  
  task_name         IN VARCHAR2  := NULL,  
  description       IN VARCHAR2  := NULL)  
RETURN VARCHAR2;
```

```
DBMS_SQLTUNE.CREATE_TUNING_TASK(  
  sql_id            IN VARCHAR2,  
  plan_hash_value   IN NUMBER     := NULL,  
  scope             IN VARCHAR2  := SCOPE_COMPREHENSIVE,  
  time_limit        IN NUMBER     := TIME_LIMIT_DEFAULT,  
  task_name         IN VARCHAR2  := NULL,  
  description       IN VARCHAR2  := NULL)  
RETURN VARCHAR2;
```

```
DBMS_SQLTUNE.CREATE_TUNING_TASK(  
  begin_snap       IN NUMBER,  
  end_snap         IN NUMBER,  
  sql_id           IN VARCHAR2,  
  plan_hash_value  IN NUMBER     := NULL,  
  scope            IN VARCHAR2  := SCOPE_COMPREHENSIVE,  
  time_limit       IN NUMBER     := TIME_LIMIT_DEFAULT,  
  task_name        IN VARCHAR2  := NULL,  
  description      IN VARCHAR2  := NULL)
```



```

RETURN VARCHAR2;

DBMS_SQLTUNE.CREATE_TUNING_TASK(
  sqlset_name      IN VARCHAR2,
  basic_filter     IN VARCHAR2 := NULL,
  object_filter    IN VARCHAR2 := NULL,
  rank1            IN VARCHAR2 := NULL,
  rank2            IN VARCHAR2 := NULL,
  rank3            IN VARCHAR2 := NULL,
  result_percentage IN NUMBER   := NULL,
  result_limit     IN NUMBER   := NULL,
  scope            IN VARCHAR2 := SCOPE_COMPREHENSIVE,
  time_limit       IN NUMBER   := TIME_LIMIT_DEFAULT,
  task_name        IN VARCHAR2 := NULL,
  description      IN VARCHAR2 := NULL)
RETURN VARCHAR2;

```

Parameters

Table 91–7 CREATE_TUNING_TASK Function Parameters

Parameter	Description
sql_text	The text of a SQL statement.
begin_snap	Begin snapshot identifier.
end_snap	End snapshot identifier.
sql_id	The identifier of a SQL statement.
bind_list	A set of bind values.
plan_hash_value	The hash value of the SQL execution plan.
sqlset_name	The SqlSet name.
basic_filter	The SQL predicate to filter the SQL from the STS.
object_filter	The object filter.
rankn	An order-by clause on the selected SQL.
result_percentage	A percentage on the sum of a ranking measure
result_limit	The top L(imit) SQL from the (filtered/ranked) SQL.
user_name	The username for whom the statement or SQL set is to be tuned.
scope	Tuning scope (limited/comprehensive).

Table 91-7 (Cont.) CREATE_TUNING_TASK Function Parameters

Parameter	Description
<code>time_limit</code>	The maximum duration in seconds for the tuning session.
<code>task_name</code>	An optional tuning task name.
<code>description</code>	A description of the SQL tuning session to a maximum of 256 characters.

Return Values

A SQL tune task identifier.

DELETE_SQLSET Procedure

This procedure deletes a set of SQL statements from a SqlSet.

Syntax

```
DBMS_SQLTUNE.DELETE_SQLSET (  
    sqlset_name  IN  VARCHAR2,  
    basic_filter IN  VARCHAR2 := NULL);
```

Parameters

Table 91–8 *DELETE_SQLSET Procedure Parameters*

Parameter	Description
sqlset_name	The SqlSet name
basic_filter	The QL predicate to filter the SQL from the SqlSet. This basic filter is used as a where clause on the SqlSet content to select a desired subset of SQL from the Tuning Set.

DROP_SQL_PROFILE Procedure

This procedure drops the named SQL Profile from the database.

Syntax

```
DBMS_SQLTUNE.DROP_SQL_PROFILE (  
    name          IN VARCHAR2,  
    ignore        IN BOOLEAN := FALSE);
```

Parameters

Table 91–9 *DROP_SQL_PROFILE Procedure Parameters*

Parameter	Description
name	The (mandatory) name of SQL Profile to be dropped. The name is case sensitive.
ignore	Ignores errors due to object not existing.

Usage Notes

Requires the "DROP ANY SQL PROFILE" privilege.

DROP_SQLSET Procedure

This procedure drops a SqlSet if it is not active.

Syntax

```
DBMS_SQLTUNE.DROP_SQLSET (  
    sqlset_name IN VARCHAR2;
```

Parameters

Table 91–10 *DROP_SQLSET Procedure Parameters*

Parameter	Description
sqlset_name	The SqlSet name.

Usage Notes

You cannot drop a SqlSet when it is referenced by one or more clients (for example, SQL tune advisor).

DROP_TUNING_TASK Procedure

This procedure drops a SQL tuning task. The task and all its result data are deleted.

Syntax

```
DBMS_SQLTUNE.DROP_TUNING_TASK(  
    task_name          IN VARCHAR2);
```

Parameters

Table 91–11 *DROP_TUNING_TASK Procedure Parameters*

Parameter	Description
task_name	The identifier of the current task.

EXECUTE_TUNING_TASK Procedure

This procedure executes a previously created tuning task.

Syntax

```
DBMS_SQLTUNE.EXECUTE_TUNING_TASK(  
    task_name          IN VARCHAR2);
```

Parameters

Table 91–12 EXECUTE_TUNING_TASK Procedure Parameters

Parameter	Description
task_name	The identifier of the task to execute.

INTERRUPT_TUNING_TASK Procedure

This procedure interrupts the currently executing tuning task and access intermediate result data.

Syntax

```
DBMS_SQLTUNE.INTERRUPT_TUNING_TASK(  
    task_name          IN VARCHAR2);
```

Parameters

Table 91–13 *INTERRUPT_TUNING_TASK Procedure Parameters*

Parameter	Description
task_name	The identifier of the current task.

LOAD_SQLSET Procedure

This procedure populates the SqlSet with a set of selected SQL.

Syntax

```
DBMS_SQLTUNE.LOAD_SQLSET (  
    sqlset_name      IN  VARCHAR2,  
    populate_cursor  IN  SqlSet_cursor);
```

Parameters

Table 91–14 *LOAD_SQLSET Procedure Parameters*

Parameter	Description
sqlset_name	The SqlSet name.
populate_cursor	The cursor reference from which to populate.

Usage Notes

This procedure returns an error when `sqlset_name` is invalid, or a corresponding SqlSet does not exist, or the `populate_cursor` is incorrect and cannot be executed.

REMOVE_SQLSET_REFERENCE Procedure

This procedure deactivates a SqlSet to indicate it is no longer used by the client.

Syntax

```
DBMS_SQLTUNE.REMOVE_SQLSET_REFERENCE (  
    sqlset_name  IN VARCHAR2,  
    reference_id IN NUMBER);
```

Parameters

Table 91–15 REMOVE_SQLSET_REFERENCE Procedure Parameters

Parameter	Description
sqlset_name	The SqlSet name.
reference_id	The identifier of the reference to remove.

REPORT_TUNING_TASK Function

This procedure displays the results of a tuning task.

Syntax

```
DBMS_SQLTUNE.REPORT_TUNING_TASK(
  task_name      IN  VARCHAR2 := NULL,
  object_id      IN  NUMBER    := NULL,
  result_limit   IN  NUMBER    := NULL,
  plan_format    IN  VARCHAR2 := FORMAT_TYPICAL,
  rec_format     IN  VARCHAR2 := FORMAT_TYPICAL)
RETURN CLOB;
```

Parameters

Table 91–16 *REPORT_TUNING_TASK Function Parameters*

Parameter	Description
task_name	The identifier of the task to report. If the task ID is not given by the caller, the function will generate a report for the results of the last tuning task run by the user.
object_id	The identifier of the advisor framework object that represents a given statement in the SqlSet.
result_limit	The number of statements in a SqlSet for which a report is generated.
plan_format	The format of the explain plans displayed in the report. Possible values are TYPICAL, BASIC, ALL and SERIAL.
rec_format	The format of the recommendations displayed in the report. Possible values are TYPICAL and BASIC.

Return Values

A text report.

RESET_TUNING_TASK Procedure

This procedure resets the currently executing tuning task to its initial state. All intermediate result data is deleted.

Syntax

```
DBMS_SQLTUNE.RESET_TUNING_TASK(  
    task_name          IN VARCHAR2);
```

Parameters

Table 91–17 *RESET_TUNING_TASK Procedure Parameters*

Parameter	Description
task_name	The identifier of the current task.

RESUME_TUNING_TASK Procedure

This procedure resumes a previously interrupted tuning task.

Syntax

```
DBMS_SQLTUNE.RESUME_TUNING_TASK(  
    task_name          IN VARCHAR2);
```

Parameters

Table 91–18 *RESUME_TUNING_TASK Procedure Parameters*

Parameter	Description
task_name	The identifier of the current task.

SELECT_SQLSET Function

This function collects SQL statements from the cursor cache.

Syntax

```
DBMS_SQLTUNE.SELECT_SQLSET (
  sqlset_name      IN  VARCHAR2,
  basic_filter     IN  VARCHAR2 := NULL,
  object_filter    IN  VARCHAR2 := NULL,
  ranking_measure1 IN  VARCHAR2 := NULL,
  ranking_measure2 IN  VARCHAR2 := NULL,
  ranking_measure3 IN  VARCHAR2 := NULL,
  result_percentage IN NUMBER := 1,
  result_limit     IN  NUMBER := NULL)
RETURN sys.sqlset PIPELINED;
```

Parameters

Table 91–19 *SELECT_SQLSET Procedure Parameters*

Parameter	Description
<code>sqlset_name</code>	The SqlSet name.
<code>basic_filter</code>	The SQL predicate to filter the SQL from the cursor cache.
<code>object_filter</code>	Specifies the objects that should exist in the object list of selected SQL from the cursor cache.
<code>ranking_measure(n)</code>	An order-by clause on the selected SQL.
<code>result_percentage</code>	A percentage on the sum of a ranking measure.
<code>result_limit</code>	The top L(imit) SQL from the (filtered) source ranked by the ranking measure.

Return Values

This function returns a sqlset object.

SELECT_WORKLOAD_REPOSITORY Functions

This function collects SQL statements from the workload repository. The overloaded forms let you:

- Collect SQL statements from all snapshots between `begin_snap` and `end_snap`.
- Collect SQL statements from a workload repository baseline.

Syntax

```
DBMS_SQLTUNE.SELECT_WORKLAOD_REPOSITORY (
  begin_snap      IN NUMBER,
  end_snap        IN NUMBER,
  basic_filter    IN VARCHAR2 := NULL,
  object_filter   IN VARCHAR2 := NULL,
  ranking_measure1 IN VARCHAR2 := NULL,
  ranking_measure2 IN VARCHAR2 := NULL,
  ranking_measure3 IN VARCHAR2 := NULL,
  result_percentage IN NUMBER := 1,
  result_limit    IN NUMBER := NULL)
RETURN sys.sqlset PIPELINED;
```

```
DBMS_SQLTUNE.SELECT_WORKLAOD REPOSITORY (
  begin_snap      IN NUMBER,
  end_snap        IN NUMBER,
  basic_filter    IN VARCHAR2 := NULL,
  object_filter   IN VARCHAR2 := NULL,
  ranking_measure1 IN VARCHAR2 := NULL,
  ranking_measure2 IN VARCHAR2 := NULL,
  ranking_measure3 IN VARCHAR2 := NULL,
  result_percentage IN NUMBER := 1,
  result_limit    IN NUMBER := NULL)
RETURN sys.sqlset PIPELINED;
```

Parameters

Table 91–20 *SELECT_WORKLOAD_REPOSITORY Procedure Parameters*

Parameter	Description
<code>begin_snap</code>	Begin snapshot.
<code>end_snap</code>	End snapshot.

Table 91–20 (Cont.) SELECT_WORKLOAD_REPOSITORY Procedure Parameters

Parameter	Description
<code>baseline_name</code>	The name of the baseline period.
<code>basic_filter</code>	The SQL predicate to filter the SQL from the serf.
<code>object_filter</code>	Specifies the objects that should exist in the object list of selected SQL from the swrf.
<code>ranking_measure(n)</code>	An order-by clause on the selected SQL.
<code>result_percentage</code>	A percentage on the sum of a ranking measure.
<code>result_limit</code>	The top L(limit) SQL from the (filtered) source ranked by the ranking measure.

Return Values

This function returns a sqlset object.

UPDATE_SQLSET Procedures

There are two forms of this procedure:

- You use the first form of the procedure to update selected string fields for a SQL statement in a SqlSet, specifically to update the `MODULE` and `ACTION` fields.
- You use the second form of the procedure to update the set numerical attributes of a SQL in a SqlSet, specifically `PRIORITY` and `PARSING_SCHEMA_ID`.

Syntax

```
DBMS_SQLTUNE.UPDATE_SQLSET (
  sqlset_name      IN VARCHAR2,
  sql_id           IN VARCHAR2,
  attribute_name   IN VARCHAR2,
  attribute_value  IN VARCHAR2 := NULL);
```

```
DBMS_SQLTUNE.UPDATE_SQLSET (
  sqlset_name      IN VARCHAR2,
  sql_id           IN VARCHAR2,
  attribute_name   IN VARCHAR2,
  attribute_value  IN NUMBER := NULL);
```

Parameters

Table 91–21 UPDATE_SQLSET Function Parameters

Parameter	Description
<code>sqlset_name</code>	The SqlSet name.
<code>sql_id</code>	The identifier of the statement to update.
<code>attribute_name</code>	The name of the attribute to modify.
<code>attribute_value</code>	The new value of the attribute.

DBMS_STAT_FUNCS

The DBMS_STAT_FUNCS package provides statistical functions.

This chapter contains the following topic:

- [Summary of DBMS_STAT_FUNCS Subprograms](#)

Summary of DBMS_STAT_FUNCS Subprograms

Table 92–1 *DBMS_STAT_FUNCS Package Subprograms*

Subprogram	Description
EXPONENTIAL_DIST_FIT Procedure on page 92-3	Tests how well a sample of values fits an exponential distribution
NORMAL_DIST_FIT Procedure on page 92-4	Tests how well a sample of values fits a normal distribution
POISSON_DIST_FIT Procedure on page 92-5	Tests how well a sample of values fits a Poisson distribution
SUMMARY Procedure on page 92-6	Summarizes a numerical column of a table
UNIFORM_DIST_FIT Procedure on page 92-8	Tests how well a sample of values fits a uniform distribution
WEIBULL_DIST_FIT Procedure on page 92-9	Tests how well a sample of values fits a Weibull distribution

EXPONENTIAL_DIST_FIT Procedure

This procedure tests how well a sample of values fits an exponential distribution.

Syntax

```
DBMS_STAT_FUNCS.EXPONENTIAL_DIST_FIT (
  ownername      IN   VARCHAR2,
  tablename      IN   VARCHAR2,
  columnname     IN   VARCHAR2,
  test_type      IN   VARCHAR2 DEFAULT 'KOLMOGOROV_SMIRNOV',
  lambda         IN   NUMBER,
  mu             IN   NUMBER,
  sig            OUT  NUMBER);
```

Parameters

Table 92–2 *EXPONENTIAL_DIST_FIT Procedure Parameters*

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
lambda	The scale parameter.
mu	The location parameter.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the exponential distribution. A number close to 1 indicates a close match.

NORMAL_DIST_FIT Procedure

This procedure tests how well a sample of values fits a normal distribution.

Syntax

```
DBMS_STAT_FUNCS.NORMAL_DIST_FIT (  
    ownername    IN    VARCHAR2,  
    tablename    IN    VARCHAR2,  
    columnname   IN    VARCHAR2,  
    test_type    IN    VARCHAR2 DEFAULT 'SHAPIRO_WILKS',  
    mean         IN    NUMBER,  
    stdev        IN    NUMBER,  
    sig          OUT   NUMBER);
```

Parameters

Table 92–3 *NORMAL_DIST_FIT Procedure Parameters*

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV', 'ANDERSON_DARLING' or 'SHAPIRO_WILKS'.
mean	The mean of the distribution against which to compare.
stdev	The standard deviation of the distribution against which to compare.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the normal distribution. A number close to 1 indicates a close match.

POISSON_DIST_FIT Procedure

This procedure tests how well a sample of values fits a Poisson distribution.

Syntax

```
DBMS_STAT_FUNCS.POISSON_DIST_FIT (
  ownername      IN   VARCHAR2,
  tablename      IN   VARCHAR2,
  columnname     IN   VARCHAR2,
  test_type      IN   VARCHAR2 DEFAULT 'KOLMOGOROV_SMIRNOV',
  lambda         IN   NUMBER,
  sig            OUT  NUMBER);
```

Parameters

Table 92–4 POISSON_DIST_FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
test_type	The type of test to use: 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
lambda	The lambda parameter is the shape parameter.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the Poisson distribution. A number close to 1 indicates a close match.

SUMMARY Procedure

This procedure summarizes the numerical column specified in the `columnname` of `tablename`. The summary is returned as a Summary Type. Note that most of the output of `SUMMARY` can be obtained with currently available SQL.

Syntax

```
DBMS_STAT_FUNCS.SUMMARY (  
    ownername    IN    VARCHAR2,  
    tablename    IN    VARCHAR2,  
    columnname   IN    VARCHAR2,  
    sigma_value  IN    NUMBER DEFAULT 3,  
    s            OUT   SummaryType);
```

Parameters

Table 92–5 *SUMMARY Procedure Parameters*

Parameter	Description
<code>ownername</code>	The schema where the table resides.
<code>tablename</code>	The table where the column resides.
<code>columnname</code>	The column of the table to be summarized.
<code>sigma_value</code>	The number of sigmas for the set of extreme values, defaults to 3.
<code>s</code>	The Record containing summary information about given column.

Definition of SummaryType

```
TYPE n_arr IS VARRAY(5) of NUMBER;  
TYPE num_table IS TABLE of NUMBER;  
TYPE summaryType IS RECORD (  
    count        NUMBER,  
    min          NUMBER,  
    max          NUMBER,  
    range        NUMBER,  
    mean         NUMBER,  
    cmode        num_table,  
    variance     NUMBER,  
    stddev       NUMBER,
```


quantile_5	NUMBER,
quantile_25	NUMBER,
median	NUMBER,
quantile_75	NUMBER,
quantile_95	NUMBER,
plus_x_sigma	NUMBER,
minus_x_sigma	NUMBER,
extreme_values	num_table,
top_5_values	n_arr,
bottom_5_values	n_arr);

UNIFORM_DIST_FIT Procedure

This procedure tests well a sample of values fits a uniform distribution.

Syntax

```
DBMS_STAT_FUNCS.UNIFORM_DIST_FIT (  
    ownername    IN    VARCHAR2,  
    tablename    IN    VARCHAR2,  
    columnname   IN    VARCHAR2,  
    var_type     IN    VARCHAR2 DEFAULT 'CONTINUOUS',  
    test_type    IN    VARCHAR2 DEFAULT 'KOLMOGOROV_SMIRNOV',  
    paramA       IN    NUMBER,  
    paramB       IN    NUMBER,  
    sig          OUT   NUMBER);
```

Parameters

Table 92–6 UNIFORM_DIST_FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
var_type	The type of distribution: 'CONTINUOUS' (the default) or 'DISCRETE'
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
paramA	Parameter A estimated from the sample (the location parameter).
paramB	Parameter B estimated from the sample (the scale parameter).
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the uniform distribution. A number close to 1 indicates a close match.

WEIBULL_DIST_FIT Procedure

This procedure tests how well a sample of values fits a Weibull distribution.

Syntax

```
DBMS_STAT_FUNCS.WEIBULL_DIST_FIT (
  ownername      IN   VARCHAR2,
  tablename      IN   VARCHAR2,
  columnname     IN   VARCHAR2,
  test_type      IN   VARCHAR2 DEFAULT 'KOLMOGOROV_SMIRNOV',
  alpha          IN   NUMBER,
  mu             IN   NUMBER,
  beta           IN   NUMBER,
  sig            OUT  NUMBER);
```

Parameters

Table 92–7 WEIBULL_DIST_FIT Procedure Parameters

Parameter	Description
ownername	The schema where the table resides.
tablename	The table where the column resides.
columnname	The column of the table against which to run the test.
test_type	The type of test to use: 'CHI_SQUARED', 'KOLMOGOROV_SMIRNOV' or 'ANDERSON_DARLING'.
alpha	The scale parameter.
mu	The location parameter.
beta	The slope/shape parameter.
sig	The goodness of fit value, based on test type. A small value indicates a significant difference between the sample and the Weibull distribution. A number close to 1 indicates a close match.

With the `DBMS_STATS` package you can view and modify optimizer statistics gathered for database objects.

This chapter contains the following topics:

- [Using DBMS_STATS](#)
 - [Overview](#)
 - [Types](#)
 - [Constants](#)
 - [Operational Notes](#)
 - [Deprecated Subprograms](#)
 - [Examples](#)
- [Summary of DBMS_STATS Subprograms](#)

Using DBMS_STATS

- [Overview](#)
- [Types](#)
- [Constants](#)
- [Operational Notes](#)
- [Deprecated Subprograms](#)
- [Examples](#)

Overview

The statistics to be viewed or modified can reside in the dictionary or in a table created in the user's schema for this purpose. You can also collect and manage user-defined statistics for tables and domain indexes using this package. For example, if the `DELETE_COLUMN_STATS` procedure is invoked on a column for which an association is defined, user-defined statistics for that column are deleted in addition to deletion of the standard statistics.

Only statistics stored in the dictionary have an impact on the cost-based optimizer. You can also use `DBMS_STATS` to gather statistics in parallel

Types

Types for the minimum and maximum values and histogram endpoints include:

```
TYPE numarray IS VARRAY(256) OF NUMBER;
TYPE datearray IS VARRAY(256) OF DATE;
TYPE chararray IS VARRAY(256) OF VARCHAR2(4000);
TYPE rawarray IS VARRAY(256) OF RAW(2000);
TYPE fltarray IS VARRAY(256) OF BINARY_FLOAT;
TYPE dblarray IS VARRAY(256) OF BINARY_DOUBLE;
```

```
TYPE StatRec IS RECORD (
    epc NUMBER,
    minval RAW(2000),
    maxval RAW(2000),
    bkvals NUMARRAY,
    novals NUMARRAY);
```

Types for listing stale tables include:

```
TYPE ObjectElem IS RECORD (
  ownname      VARCHAR2(30),      -- owner
  objtype      VARCHAR2(6),      -- 'TABLE' or 'INDEX'
  objname      VARCHAR2(30),      -- table/index
  partname     VARCHAR2(30),      -- partition
  subpartname  VARCHAR2(30),      -- subpartition
  confidence   NUMBER);          -- not used
type ObjectTab is TABLE of ObjectElem;
```

Constants

Use the following constant to indicate that auto-sample size algorithms should be used:

```
AUTO_SAMPLE_SIZE CONSTANT NUMBER;
```

The constant used to determine the system default degree of parallelism, based on the initialization parameters, is:

```
DEFAULT_DEGREE CONSTANT NUMBER;
```

Use the following constant to let Oracle select the degree of parallelism based on size of the object, number of CPUs and initialization parameters:

```
AUTO_DEGREE CONSTANT NUMBER;
```

Use the following constant to let Oracle decide whether to collect statistics for indexes or not:

```
AUTO_CASCADE CONSTANT BOOLEAN;
```

Use the following constant to let oracle decide when to invalidate dependent cursors.

```
AUTO_INVALIDATE CONSTANT BOOLEAN
```

Operational Notes

The DBMS_STATS subprograms perform the following general operations:

- [Setting, Getting or Deleting Statistics](#)

- [Deleting Statistics](#)
- [Transferring Statistics](#)
- [Gathering Optimizer Statistics](#)
- [Locking or Unlocking Statistics](#)
- [Restoring and Purging Statistics History](#)
- [Setting, Getting or Deleting Statistics](#)

Most of the `DBMS_STATS` procedures include the three parameters `statown`, `stattab`, and `statid`. These parameters allow you to store statistics in your own tables (outside of the dictionary), which does not affect the optimizer. Therefore, you can maintain and experiment with *sets* of statistics.

The `stattab` parameter specifies the name of a table in which to hold statistics, and it is assumed that it resides in the same schema as the object for which statistics are collected (unless the `statown` parameter is specified). You can create multiple tables with different `stattab` identifiers to hold separate sets of statistics.

Additionally, you can maintain different sets of statistics within a single `stattab` by using the `statid` parameter, which avoids cluttering the user's schema.

For the `SET` and `GET` procedures, if `stattab` is not provided (that is, `NULL`), then the operation works directly on the dictionary statistics; therefore, you do not need to create these statistics tables if they only plan to modify the dictionary directly. However, if `stattab` is not `NULL`, then the `SET` or `GET` operation works on the specified user statistics table, and not the dictionary.

You can change the default values of some of the parameters of `DBMS_STATS` procedures using the [SET_PARAM Procedure](#).

Most of the procedures in this package commit the current transaction, perform the operation, and then commit again.

Setting, Getting or Deleting Statistics

When a `DBMS_STATS` subprogram modifies or deletes the statistics for an object, all the dependent cursors are invalidated by default and corresponding statements are subject to recompilation next time so that the new statistics have immediate effects. This behavior can be altered with the `no_invalidate` argument.

Use the following procedures to store and retrieve individual column-related, index-related, and table-related statistics:

```
PREPARE_COLUMN_VALUES
```



```

SET_COLUMN_STATS
SET_INDEX_STATS
SET_SYSTEM_STATS
SET_TABLE_STATS

```

In the special versions of the SET_*_STATS procedures for setting user-defined statistics, the following, if provided, are stored in the dictionary or external statistics table:

- User-defined statistics (*extstats*)
- The statistics type schema name (*statsschema*)
- The statistics type name (*statsname*)

The user-defined statistics and the corresponding statistics type are inserted into the USTATS\$ dictionary table. You can specify user-defined statistics without specifying the statistics type name.

```

CONVERT_RAW_VALUE
GET_COLUMN_STATS
GET_INDEX_STATS
GET_SYSTEM_STATS
GET_TABLE_STATS

```

The special versions of the GET_*_STATS procedures return user-defined statistics and the statistics type owner and name as OUT arguments corresponding to the schema object specified. If user-defined statistics are not collected, NULL values are returned.

Deleting Statistics

The DELETE_* procedures delete both user-defined statistics and the standard statistics for the given schema object.

```

DELETE_COLUMN_STATS
DELETE_DATABASE_STATS
DELETE_DICTIONARY_STATS
DELETE_FIXED_OBJECTS_STATS
DELETE_INDEX_STATS
DELETE_SCHEMA_STATS
DELETE_SYSTEM_STATS
DELETE_TABLE_STATS

```

Transferring Statistics

Use the following procedures to transfer statistics from the dictionary to a user statistics table (`export_*`) and from a user statistics table to the dictionary (`import_*`):

```
CREATE_STAT_TABLE  
DROP_STAT_TABLE
```

`CREATE_STAT_TABLE` can hold user-defined statistics and the statistics type object number.

```
EXPORT_COLUMN_STATS  
EXPORT_DATABASE_STATS  
EXPORT_DICTIONARY_STATS  
EXPORT_FIXED_OBJECTS_STATS  
EXPORT_INDEX_STATS  
EXPORT_SCHEMA_STATS  
EXPORT_SYSTEM_STATS  
EXPORT_TABLE_STATS
```

```
IMPORT_COLUMN_STATS  
IMPORT_DICTIONARY_STATS  
IMPORT_FIXED_OBJECTS_STATS  
IMPORT_INDEX_STATS  
IMPORT_SCHEMA_STATS  
IMPORT_SYSTEM_STATS  
IMPORT_TABLE_STATS
```

The `IMPORT_*` procedures retrieve statistics, including user-defined statistics, from the `stattab` table and store them in the dictionary. Because the `SET_*_STATS` and `GET_*_STATS` interfaces are supported for user-defined statistics, user-defined statistics can be copied to another database using this interface.

Gathering Optimizer Statistics

Use the following procedures to gather certain classes of optimizer statistics, with possible performance improvements over the `ANALYZE` command:

```
GATHER_DATABASE_STATS  
GATHER_DICTIONARY_STATS  
GATHER_FIXED_OBJECTS_STATS  
GATHER_INDEX_STATS  
GATHER_SCHEMA_STATS  
GATHER_SYSTEM_STATS  
GATHER_TABLE_STATS
```

The `GATHER_*` procedures also collect user-defined statistics for columns and domain indexes.

The `statown`, `stattab`, and `statid` parameters instruct the package to back up current statistics in the specified table before gathering new statistics.

Oracle also provides the following procedure for generating statistics for derived objects when you have sufficient statistics on related objects:

```
GENERATE_STATS
```

Locking or Unlocking Statistics

Use the following procedures to lock and unlock statistics on objects.

```
LOCK_TABLE_STATS
```

```
LOCK_SCHEMA_STATS
```

```
UNLOCK_TABLE_STATS
```

```
UNLOCK_SCHEMA_STATS
```

The `LOCK*` procedures either freeze the current set of the statistics or to keep the statistics empty (uncollected). When statistics on a table are locked, all the statistics depending on the table, including table statistics, column statistics, histograms and statistics on all dependent indexes, are considered to be locked.

Restoring and Purging Statistics History

Use the following procedures to restore statistics as of a specified timestamp. This is useful in case newly collected statistics leads to some sub-optimal execution plans and the administrator wants to revert to the previous set of statistics.

```
RESTORE_TABLE_STATS
```

```
RESTORE_SCHEMA_STATS
```

```
RESTORE_DATABASE_STATS
```

```
RESTORE_FIXED_OBJECTS_STATS
```

```
RESTORE_DICTIONARY_STATS
```

```
RESTORE_SYSTEM_STATS
```

Whenever statistics in dictionary are modified, old versions of statistics are saved automatically for future restoring. The old statistics are purged automatically at regular intervals based on the statistics history retention setting and the time of the recent analysis of the system. Retention is configurable using the `ALTER_STATS_HISTORY_RETENTION` procedure.

The other `DBMS_STATS` procedures related to restoring statistics are:

- `PURGE_STATS`: This procedure lets you manually purge old versions beyond a time stamp.
- `GET_STATS_HISTORY_RETENTION`: This function gets the current statistics history retention value.
- `GET_STATS_HISTORY_AVAILABILITY`: This function gets the oldest time stamp where statistics history is available. Users cannot restore statistics to a time stamp older than the oldest time stamp.

User-Defined Statistics

`DBMS_STATS` supports operations on user-defined statistics. When a domain index or column is associated with a statistics type (using the `associate` statement), operations on the index or column manipulate user-defined statistics. For example, gathering statistics for a domain index (for which an association with a statistics type exists) using the `GATHER_INDEX_STATS` interface invokes the user-defined statistics collection method of the associated statistics type. Similarly, delete, transfer, import, and export operations manipulate user-defined statistics.

`SET` and `GET` operations for user-defined statistics are also supported using a special version of the `SET` and `GET` interfaces for columns and indexes.

Deprecated Subprograms

The following subprograms are obsolete with Release 10g:

- [ALTER_DATABASE_TAB_MONITORING Procedure](#)
- [ALTER_SCHEMA_TAB_MONITORING Procedure](#)

In earlier releases, you could use these subprograms to operate on statistics. These subprograms are now non-operational because Oracle performs their functions automatically.

Examples

- [Saving Original Statistics and Gathering New Statistics](#)
- [Gathering Daytime System Statistics](#)

Saving Original Statistics and Gathering New Statistics

Assume many modifications have been made to the `employees` table since the last time statistics were gathered. To ensure that the cost-based optimizer is still picking the best plan, statistics should be gathered once again; however, the user is concerned that new statistics will cause the optimizer to choose bad plans when the current ones are acceptable. The user can do the following:

```
BEGIN
  DBMS_STATS.CREATE_STAT_TABLE ('hr', 'savestats');
  DBMS_STATS.GATHER_TABLE_STATS ('hr', 'employees', stattab => 'savestats');
END;
```

This operation gathers new statistics on the `employees` table, but first saves the original statistics in a user statistics table: `hr.savestats`.

If the user believes that the new statistics are causing the optimizer to generate poor plans, then the original statistics can be restored as follows:

```
BEGIN
  DBMS_STATS.DELETE_TABLE_STATS ('hr', 'employees');
  DBMS_STATS.IMPORT_TABLE_STATS ('hr', 'employees', stattab => 'savestats');
END;
```

Gathering Daytime System Statistics

Assume that you want to perform database application processing OLTP transactions during the day and run reports at night.

To collect daytime system statistics, gather statistics for 720 minutes. Store the statistics in the `MYSTATS` table.

```
BEGIN
  DBMS_STATS.GATHER_SYSTEM_STATS (
    interval => 720,
    stattab  => 'mystats',
    statid   => 'OLTP');
END;
```

To collect nighttime system statistics, gather statistics for 720 minutes. Store the statistics in the `MYSTATS` table.

```
BEGIN
  DBMS_STATS.GATHER_SYSTEM_STATS (
    interval => 720,
    stattab  => 'mystats',
    statid   => 'OLAP');
END;
```

```
END;
```

Update the dictionary with the gathered statistics.

```
VARIABLE jobno number;
BEGIN
    DBMS_JOB.SUBMIT (:jobno, 'DBMS_STATS.IMPORT_SYSTEM_STATS
        (''mystats'', ''OLTP'');'
        sysdate, 'sysdate + 1');
    COMMIT;
END;

BEGIN
    DBMS_JOB.SUBMIT (:jobno, 'DBMS_STATS.IMPORT_SYSTEM_STATS
        (''mystats'', ''OLAP'');'
        sysdate + 0.5, 'sysdate + 1');
    COMMIT;
END;
```

Summary of DBMS_STATS Subprograms

Table 93–1 DBMS_STATS Package Subprograms

Subprogram	Description
ALTER_DATABASE_TAB_MONITORING Procedure on page 93-16	Enables or disables the DML monitoring feature of all tables in the database, except for snapshot logs and the tables, which monitoring does not support [See Deprecated Subprograms on page 93-8]
ALTER_SCHEMA_TAB_MONITORING Procedure on page 93-17	Enables or disables the DML monitoring feature of all tables in the schema, except for snapshot logs and the tables, which monitoring does not support [See Deprecated Subprograms on page 93-8]
ALTER_STATS_HISTORY_RETENTION Procedure on page 93-18	Changes the statistics history retention value
CONVERT_RAW_VALUE Procedures on page 93-19	Convert the internal representation of a minimum or maximum value into a datatype-specific value
CONVERT_RAW_VALUE_NVARCHAR Procedure on page 93-20	Convert the internal representation of a minimum or maximum value into a datatype-specific value
CONVERT_RAW_VALUE_ROWID Procedure on page 93-21	Convert the internal representation of a minimum or maximum value into a datatype-specific value
CREATE_STAT_TABLE Procedure on page 93-22	Creates a table with name <code>stattab</code> in ownname's schema which is capable of holding statistics
DELETE_COLUMN_STATS Procedure on page 93-23	Deletes column-related statistics
DELETE_DATABASE_STATS Procedure on page 93-25	Deletes statistics for the entire database
DELETE_DICTIONARY_STATS Procedure on page 93-26	Deletes statistics for all dictionary schemas ('SYS', 'SYSTEM' and RDBMS component schemas)
DELETE_FIXED_OBJECTS_STATS Procedure on page 93-25	Deletes statistics of all fixed tables
DELETE_INDEX_STATS Procedure on page 93-29	Deletes index-related statistics
DELETE_SCHEMA_STATS Procedure on page 93-31	Deletes schema-related statistics

Table 93–1 (Cont.) DBMS_STATS Package Subprograms

Subprogram	Description
DELETE_SYSTEM_STATS Procedure on page 93-32	Deletes system statistics
DELETE_TABLE_STATS Procedure on page 93-33	Deletes table-related statistics
DROP_STAT_TABLE Procedure on page 93-35	Drops a user statistics table created by <code>CREATE_STAT_TABLE</code>
EXPORT_COLUMN_STATS Procedure on page 93-36	Retrieves statistics for a particular column and stores them in the user statistics table identified by <code>stattab</code>
EXPORT_DATABASE_STATS Procedure on page 93-37	Retrieves statistics for all objects in the database and stores them in the user statistics table identified by <code>statown.stattab</code>
EXPORT_DICTIONARY_STATS Procedure on page 93-38	Retrieves statistics for all dictionary schemas ('SYS', 'SYSTEM' and RDBMS component schemas) and stores them in the user statistics table identified by <code>stattab</code>
EXPORT_FIXED_OBJECTS_STATS Procedure on page 93-39	Retrieves statistics for fixed tables and stores them in the user statistics table identified by <code>stattab</code>
EXPORT_INDEX_STATS Procedure on page 93-40	Retrieves statistics for a particular index and stores them in the user statistics table identified by <code>stattab</code>
EXPORT_SCHEMA_STATS Procedure on page 93-41	Retrieves statistics for all objects in the schema identified by <code>ownname</code> and stores them in the user statistics table identified by <code>stattab</code>
EXPORT_SYSTEM_STATS Procedure on page 93-42	Retrieves system statistics and stores them in the user statistics table
EXPORT_TABLE_STATS Procedure on page 93-43	Retrieves statistics for a particular table and stores them in the user statistics table
FLUSH_DATABASE_MONITORING_INFO Procedure on page 93-44	Flushes in-memory monitoring information for all the tables to the dictionary
GATHER_DATABASE_STATS Procedures on page 93-45	Gathers statistics for all objects in the database
GATHER_DICTIONARY_STATS Procedure on page 93-45	Gathers statistics for dictionary schemas 'SYS', 'SYSTEM' and schemas of RDBMS components
GATHER_FIXED_OBJECTS_STATS Procedure on page 93-55	Gathers statistics of fixed objects

Table 93–1 (Cont.) DBMS_STATS Package Subprograms

Subprogram	Description
GATHER_INDEX_STATS Procedure on page 93-56	Gathers index statistics
GATHER_SCHEMA_STATS Procedures on page 93-59	Gathers statistics for all objects in a schema
GATHER_SYSTEM_STATS Procedure on page 93-64	Gathers system statistics
GATHER_TABLE_STATS Procedure on page 93-67	Gathers table and column (and index) statistics
GENERATE_STATS Procedure on page 93-71	Generates object statistics from previously collected statistics of related objects
GET_COLUMN_STATS Procedures on page 93-72	Gets all column-related information
GET_INDEX_STATS Procedures on page 93-74	Gets all index-related information
GET_PARAM Function on page 93-78	Gets the default value of parameters of DBMS_STATS procedures
GET_STATS_HISTORY_AVAILABILITY Function on page 93-79	Gets the oldest timestamp where statistics history is available
GET_STATS_HISTORY_RETENTION Function on page 93-80	Returns the current retention value
GET_SYSTEM_STATS Procedure on page 93-81	Gets system statistics from statab, or from the dictionary if statab is NULL
GET_TABLE_STATS Procedure on page 93-84	Gets all table-related information
IMPORT_COLUMN_STATS Procedure on page 93-86	Retrieves statistics for a particular column from the user statistics table identified by statab and stores them in the dictionary
"IMPORT_DATABASE_STATS Procedure" on page 93-88	Retrieves statistics for all objects in the database from the user statistics table and stores them in the dictionary
"IMPORT_DICTIONARY_STATS Procedure" on page 93-90	Retrieves statistics for all dictionary schemas ('SYS', 'SYSTEM' and RDBMS component schemas) from the user statistics table and stores them in the dictionary

Table 93–1 (Cont.) DBMS_STATS Package Subprograms

Subprogram	Description
IMPORT_FIXED_OBJECTS_STATS Procedure on page 93-92	Retrieves statistics for fixed tables from the user statistics table identified by <code>stattab</code> and stores them in the dictionary
IMPORT_INDEX_STATS Procedure on page 93-94	Retrieves statistics for a particular index from the user statistics table identified by <code>stattab</code> and stores them in the dictionary
IMPORT_SCHEMA_STATS Procedure on page 93-96	Retrieves statistics for all objects in the schema identified by <code>ownname</code> from the user statistics table and stores them in the dictionary
IMPORT_SYSTEM_STATS Procedure on page 93-98	Retrieves system statistics from the user statistics table and stores them in the dictionary
IMPORT_TABLE_STATS Procedure on page 93-99	Retrieves statistics for a particular table from the user statistics table identified by <code>stattab</code> and stores them in the dictionary
LOCK_SCHEMA_STATS Procedure on page 93-101	Locks the statistics of all tables of a schema
LOCK_TABLE_STATS Procedure on page 93-102	Locks the statistics on the table
PREPARE_COLUMN_VALUES Procedures on page 93-103	Converts user-specified minimum, maximum, and histogram endpoint datatype-specific values into Oracle's internal representation for future storage using the SET_COLUMN_STATS Procedures
PREPARE_COLUMN_VALUES_NVARCHAR2 Procedure on page 93-106	Converts user-specified minimum, maximum, and histogram endpoint datatype-specific values into Oracle's internal representation for future storage using the SET_COLUMN_STATS Procedures
PREPARE_COLUMN_VALUES_ROWID Procedure on page 93-108	Converts user-specified minimum, maximum, and histogram endpoint datatype-specific values into Oracle's internal representation for future storage using the SET_COLUMN_STATS Procedures
PURGE_STATS Procedure on page 93-110	Purges old versions of statistics saved in the dictionary
RESTORE_DATABASE_STATS Procedure on page 93-111	Restores statistics of all tables of the database as of a specified timestamp
RESTORE_DICTIONARY_STATS Procedure on page 93-112	Restores statistics of all dictionary tables (tables of 'SYS', 'SYSTEM' and RDBMS component schemas) as of a specified timestamp

Table 93–1 (Cont.) DBMS_STATS Package Subprograms

Subprogram	Description
RESTORE_FIXED_OBJECTS_STATS Procedure on page 93-113	Restores statistics of all fixed tables as of a specified timestamp
RESTORE_SCHEMA_STATS Procedure on page 93-114	Restores statistics of all tables of a schema as of a specified timestamp
RESTORE_SYSTEM_STATS Procedure on page 93-115	Restores statistics of all tables of a schema as of a specified timestamp
RESTORE_TABLE_STATS Procedure on page 93-116	Restores statistics of a table as of a specified timestamp (as_of_timestamp), as well as statistics of associated indexes and columns
SET_COLUMN_STATS Procedures on page 93-117	Sets column-related information
SET_INDEX_STATS Procedures on page 93-120	Sets index-related information
SET_PARAM Procedure on page 93-124	Sets default values for parameters of DBMS_STATS procedures
SET_SYSTEM_STATS Procedure on page 93-126	Sets system statistics
SET_TABLE_STATS Procedure on page 93-129	Sets table-related information
UNLOCK_SCHEMA_STATS Procedure on page 93-132	Unlocks the statistics on all the table in a schema
UNLOCK_TABLE_STATS Procedure on page 93-133	Unlocks the statistics on the table
UPGRADE_STAT_TABLE Procedure on page 93-134	Upgrades user statistics on an older table

ALTER_DATABASE_TAB_MONITORING Procedure

Note: See [Deprecated Subprograms](#) on page 93-8.

This procedure enables or disables the DML monitoring feature of all the tables in the schema, except for snapshot logs and the tables, which monitoring does not support. Using this procedure is equivalent to issuing ALTER TABLE . . . MONITORING (or NOMONITORING) individually.

Syntax

```
DBMS_STATS.ALTER_DATABASE_TAB_MONITORING (  
    monitoring BOOLEAN DEFAULT TRUE,  
    sysobjs     BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–2 ALTER_DATABASE_TAB_MONITORING Procedure Parameters

Parameter	Description
monitoring	Enables monitoring if true, and disables monitoring if false.
sysobjs	If true, changes monitoring on the dictionary objects.

Usage Notes

Exceptions

ORA-20000: Insufficient privileges.

ALTER_SCHEMA_TAB_MONITORING Procedure

Note: See [Deprecated Subprograms](#) on page 93-8.

This procedure enables or disables the DML monitoring feature of all the tables in the schema, except for snapshot logs and the tables, which monitoring does not support. Using this procedure is equivalent to issuing ALTER TABLE . . . MONITORING (or NOMONITORING) individually.

Syntax

```
DBMS_STATS.ALTER_SCHEMA_TAB_MONITORING (
    ownname      VARCHAR2 DEFAULT NULL,
    monitoring   BOOLEAN DEFAULT TRUE);
```

Parameters

Table 93–3 ALTER_SCHEMA_TAB_MONITORING Procedure Parameters

Parameter	Description
ownname	The name of the schema. (NULL means the current schema.)
monitoring	Enables monitoring if true, and disables monitoring if false.

Usage Notes

You should enable monitoring if you use GATHER_DATABASE_STATS or GATHER_SCHEMA_STATS with the GATHER AUTO or GATHER STALE options.

Exceptions

ORA-20000: Insufficient privileges.

ALTER_STATS_HISTORY_RETENTION Procedure

This procedure changes the statistics history retention value. Statistics history retention is used by both the automatic purge and [PURGE_STATS Procedure](#).

Syntax

```
DBMS_STATS.ALTER_STATS_HISTORY_RETENTION (  
    retention          IN          NUMBER);
```

Parameters

Table 93–4 ALTER_STATS_HISTORY_RETENTION Procedure Parameters

Parameter	Description
retention	<p>The retention time in days. The statistics history will be retained for at least these many number of days. The valid range is [1,365000]. Also you can use the following values for special purposes:</p> <ul style="list-style-type: none">■ 0 - old statistics are never saved. The automatic purge will delete all statistics history■ 1 - statistics history is never purged by automatic purge.■ NULL - change statistics history retention to default value

Usage Notes

To run this procedure, you must have the SYSDBA or both ANALYZE ANY DICTIONARY and ANALYZE ANY system privilege.

Exceptions

ORA-20000: Insufficient privileges.

CONVERT_RAW_VALUE Procedures

This procedure converts the internal representation of a minimum or maximum value into a datatype-specific value. The `minval` and `maxval` fields of the `StatRec` structure as filled in by `GET_COLUMN_STATS` or `PREPARE_COLUMN_VALUES` are appropriate values for input.

Syntax

```
DBMS_STATS.CONVERT_RAW_VALUE (
    rawval    RAW,
    resval OUT BINARY_FLOAT);
```

```
DBMS_STATS.CONVERT_RAW_VALUE (
    rawval    RAW,
    resval OUT BINARY_DOUBLE);
```

```
DBMS_STATS.CONVERT_RAW_VALUE (
    rawval    RAW,
    resval OUT DATE);
```

```
DBMS_STATS.CONVERT_RAW_VALUE (
    rawval    RAW,
    resval OUT NUMBER);
```

```
DBMS_STATS.CONVERT_RAW_VALUE (
    rawval    RAW,
    resval OUT VARCHAR2);
```

Pragmas

```
pragma restrict_references(convert_raw_value, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 93–5 *CONVERT_RAW_VALUE Procedure Parameters*

Parameter	Description
<code>rawval</code>	The raw representation of a column minimum or maximum datatype-specific output parameters.
<code>resval</code>	The converted, type-specific value.

CONVERT_RAW_VALUE_NVARCHAR Procedure

This procedure converts the internal representation of a minimum or maximum value into a datatype-specific value. The `minval` and `maxval` fields of the `StatRec` structure as filled in by `GET_COLUMN_STATS` or `PREPARE_COLUMN_VALUES` are appropriate values for input.

Syntax

```
DBMS_STATS.CONVERT_RAW_VALUE_NVARCHAR (
    rawval      RAW,
    resval OUT NVARCHAR2);
```

Pragmas

```
pragma restrict_references(convert_raw_value_nvarchar, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 93–6 *CONVERT_RAW_VALUE_NVARCHAR Procedure Parameters*

Parameter	Description
<code>rawval</code>	The raw representation of a column minimum or maximum datatype-specific output parameters.
<code>resval</code>	The converted, type-specific value.

CONVERT_RAW_VALUE_ROWID Procedure

This procedure converts the internal representation of a minimum or maximum value into a datatype-specific value. The `minval` and `maxval` fields of the `StatRec` structure as filled in by `GET_COLUMN_STATS` or `PREPARE_COLUMN_VALUES` are appropriate values for input.

Syntax

```
DBMS_STATS.CONVERT_RAW_VALUE_ROWID (
    rawval      RAW,
    resval OUT ROWID);
```

Pragmas

```
pragma restrict_references(convert_raw_value_rowid, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 93–7 *CONVERT_RAW_VALUE_ROWID Procedure Parameters*

Parameter	Description
<code>rawval</code>	The raw representation of a column minimum or maximum datatype-specific output parameters.
<code>resval</code>	The converted, type-specific value.

CREATE_STAT_TABLE Procedure

This procedure creates a table with name `stattab` in `ownname`'s schema which is capable of holding statistics. The columns and types that compose this table are not relevant as it should be accessed solely through the procedures in this package.

Syntax

```
DBMS_STATS.CREATE_STAT_TABLE (  
    ownname VARCHAR2,  
    stattab VARCHAR2,  
    tblspace VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–8 CREATE_STAT_TABLE Procedure Parameters

Parameter	Description
<code>ownname</code>	Name of the schema.
<code>stattab</code>	Name of the table to create. This value should be passed as the <code>stattab</code> parameter to other procedures when the user does not want to modify the dictionary statistics directly.
<code>tblspace</code>	Tablespace in which to create the statistics tables. If none is specified, then they are created in the user's default tablespace.

Exceptions

ORA-20000: Table already exists or insufficient privileges.

ORA-20001: Tablespace does not exist.

DELETE_COLUMN_STATS Procedure

This procedure deletes column-related statistics.

Syntax

```
DBMS_STATS.DELETE_COLUMN_STATS (
  ownname      VARCHAR2,
  tabname      VARCHAR2,
  colname      VARCHAR2,
  partname     VARCHAR2 DEFAULT NULL,
  statab       VARCHAR2 DEFAULT NULL,
  statid       VARCHAR2 DEFAULT NULL,
  cascade_parts BOOLEAN  DEFAULT TRUE,
  statown      VARCHAR2 DEFAULT NULL,
  no_invalidate BOOLEAN  DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')),
  force        BOOLEAN  DEFAULT FALSE);
```

Parameters

Table 93-9 *DELETE_COLUMN_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
tabname	Name of the table to which this column belongs.
colname	Name of the column.
partname	Name of the table partition for which to delete the statistics. If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then global column statistics are deleted.
statab	User statistics table identifier describing from where to delete the statistics. If <code>statab</code> is <code>NULL</code> , then the statistics are deleted directly from the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>statab</code> (Only pertinent if <code>statab</code> is not <code>NULL</code>).
cascade_parts	If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then setting this to true causes the deletion of statistics for this column for all underlying partitions as well.
statown	Schema containing <code>statab</code> (if different than <code>ownname</code>).

Table 93–9 (Cont.) DELETE_COLUMN_STATS Procedure Parameters

Parameter	Description
<code>no_invalidate</code>	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
<code>force</code>	When value of this argument is <code>TRUE</code> , deletes column statistics even if locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20005: Object statistics are locked.

DELETE_DATABASE_STATS Procedure

This procedure deletes statistics for all the tables in a database.

Syntax

```
DBMS_STATS.DELETE_DATABASE_STATS (
  statab          VARCHAR2 DEFAULT NULL,
  statid          VARCHAR2 DEFAULT NULL,
  statown         VARCHAR2 DEFAULT NULL,
  no_invalidate  BOOLEAN   DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')),
  force           BOOLEAN   DEFAULT FALSE);
```

Parameters

Table 93–10 *DELETE_DATABASE_STATS Procedure Parameters*

Parameter	Description
statab	User statistics table identifier describing from where to delete the statistics. If <code>statab</code> is <code>NULL</code> , then the statistics are deleted directly in the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>statab</code> (Only pertinent if <code>statab</code> is not <code>NULL</code>).
statown	Schema containing <code>statab</code> . If <code>statab</code> is not <code>NULL</code> and if <code>statown</code> is <code>NULL</code> , then it is assumed that every schema in the database contains a user statistics table with the name <code>statab</code> .
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	When the value of this argument is <code>TRUE</code> , deletes statistics of tables in a database even if they are locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

DELETE_DICTIONARY_STATS Procedure

This procedure deletes statistics for all dictionary schemas ('SYS', 'SYSTEM' and RDBMS component schemas).

Syntax

```
DBMS_STATS.DELETE_DICTIONARY_STATS (  
    statab          VARCHAR2 DEFAULT NULL,  
    statid          VARCHAR2 DEFAULT NULL,  
    statown        VARCHAR2 DEFAULT NULL,  
    no_invalidate  BOOLEAN   DEFAULT to_no_invalidate_type (  
                                                get_param('NO_INVALIDATE')),  
    force          BOOLEAN   DEFAULT FALSE);
```

Parameters

Table 93–11 *DELETE_DICTIONARY_STATS Procedure Parameters*

Parameter	Description
statab	User statistics table identifier describing from where to delete the statistics. If <code>statab</code> is <code>NULL</code> , then the statistics are deleted directly in the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>statab</code> (Only pertinent if <code>statab</code> is not <code>NULL</code>).
statown	Schema containing <code>statab</code> . If <code>statab</code> is not <code>NULL</code> and if <code>statown</code> is <code>NULL</code> , then it is assumed that every schema in the database contains a user statistics table with the name <code>statab</code> .
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	When the value of this argument is <code>TRUE</code> , deletes statistics of tables in a database even if they are locked.

Usage Notes

You must have the SYSDBA or both ANALYZE ANY DICTIONARY and ANALYZE ANY system privilege to execute this procedure.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20002: Bad user statistics table, may need to upgrade it.

DELETE_FIXED_OBJECTS_STATS Procedure

This procedure deletes statistics of all fixed tables.

Syntax

```
DBMS_STATS.DELETE_FIXED_OBJECTS_STATS (
  statab      VARCHAR2 DEFAULT NULL,
  statid      VARCHAR2 DEFAULT NULL,
  statown     VARCHAR2 DEFAULT NULL,
  no_invalidate BOOLEAN DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')),
  force       BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–12 *DELETE_FIXED_OBJECTS_STATS Procedure Parameters*

Parameter	Description
statab	The user statistics table identifier describing from where to delete the current statistics. If <code>statab</code> is <code>NULL</code> , the statistics will be deleted directly in the dictionary.
statid	The (optional) identifier to associate with these statistics within <code>statab</code> . This only applies if <code>statab</code> is not <code>NULL</code> .
statown	The schema containing <code>statab</code> (if different from <code>ownname</code>).
no_invalidate	Does not invalidate the dependent cursors if set to <code>TRUE</code> . Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	Ignores the statistics lock on objects and deletes the statistics if set to <code>TRUE</code> .

Usage Notes

You must have the `SYSDBA` or `ANALYZE ANY DICTIONARY` system privilege to execute this procedure.

Exceptions

ORA-20000: Insufficient privileges.

ORA-20002: Bad user statistics table, may need to upgrade it.

DELETE_INDEX_STATS Procedure

This procedure deletes index-related statistics.

Syntax

```
DBMS_STATS.DELETE_INDEX_STATS (
    ownname          VARCHAR2,
    indname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    statab           VARCHAR2 DEFAULT NULL,
    statid           VARCHAR2 DEFAULT NULL,
    cascade_parts    BOOLEAN  DEFAULT TRUE,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate    BOOLEAN  DEFAULT to_no_invalidate_type (
                                get_param('NO_INVALIDATE')),
    force            BOOLEAN  DEFAULT FALSE);
```

Parameters

Table 93–13 *DELETE_INDEX_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
indname	Name of the index.
partname	Name of the index partition for which to delete the statistics. If the index is partitioned and if <code>partname</code> is <code>NULL</code> , then index statistics are deleted at the global level.
statab	User statistics table identifier describing from where to delete the statistics. If <code>statab</code> is <code>NULL</code> , then the statistics are deleted directly from the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>statab</code> (Only pertinent if <code>statab</code> is not <code>NULL</code>).
cascade_parts	If the index is partitioned and if <code>partname</code> is <code>NULL</code> , then setting this to <code>TRUE</code> causes the deletion of statistics for this index for all underlying partitions as well.
statown	Schema containing <code>statab</code> (if different than <code>ownname</code>).

Table 93–13 (Cont.) DELETE_INDEX_STATS Procedure Parameters

Parameter	Description
<code>no_invalidate</code>	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
<code>force</code>	When value of this argument is <code>TRUE</code> , deletes index statistics even if locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20005: Object statistics are locked.

DELETE_SCHEMA_STATS Procedure

This procedure deletes statistics for an entire schema.

Syntax

```
DBMS_STATS.DELETE_SCHEMA_STATS (
  ownname          VARCHAR2,
  stattab          VARCHAR2 DEFAULT NULL,
  statid          VARCHAR2 DEFAULT NULL,
  statown         VARCHAR2 DEFAULT NULL,
  no_invalidate   BOOLEAN DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')),
  force           BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–14 *DELETE_SCHEMA_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
stattab	User statistics table identifier describing from where to delete the statistics. If <code>stattab</code> is <code>NULL</code> , then the statistics are deleted directly in the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> (Only pertinent if <code>stattab</code> is not <code>NULL</code>).
statown	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	When value of this argument is <code>TRUE</code> , deletes statistics of tables in a schema even if locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges

DELETE_SYSTEM_STATS Procedure

This procedure deletes workload statistics (collected using the 'INTERVAL' or 'START' and 'STOP' options) and resets the default to `noworkload` statistics (collected using 'NOWORKLOAD' option) if `stattab` is not specified. If `stattab` is specified, the subprogram deletes all system statistics with the associated `statid` from the `stattab`.

Syntax

```
DBMS_STATS.DELETE_SYSTEM_STATS (  
    stattab      VARCHAR2 DEFAULT NULL,  
    statid       VARCHAR2 DEFAULT NULL,  
    statown     VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–15 *DELETE_SYSTEM_STATS Procedure Parameters*

Parameter	Description
<code>stattab</code>	Identifier of the user statistics table where the statistics will be saved.
<code>statid</code>	Optional identifier associated with the statistics saved in the <code>stattab</code> .
<code>statown</code>	The schema containing <code>stattab</code> , if different from the user's schema.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20002: Bad user statistics table; may need to be upgraded.

DELETE_TABLE_STATS Procedure

This procedure deletes table-related statistics.

Syntax

```
DBMS_STATS.DELETE_TABLE_STATS (
    ownname          VARCHAR2,
    tabname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    statab           VARCHAR2 DEFAULT NULL,
    statid           VARCHAR2 DEFAULT NULL,
    cascade_parts    BOOLEAN  DEFAULT TRUE,
    cascade_columns  BOOLEAN  DEFAULT TRUE,
    cascade_indexes  BOOLEAN  DEFAULT TRUE,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate    BOOLEAN  DEFAULT to_no_invalidate_type (
                                get_param('NO_INVALIDATE')),
    force            BOOLEAN  DEFAULT FALSE);
```

Parameters

Table 93–16 *DELETE_TABLE_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
tabname	Name of the table to which this column belongs.
partname	Name of the table partition from which to get the statistics. If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then the statistics are retrieved from the global table level.
statab	User statistics table identifier describing from where to retrieve the statistics. If <code>statab</code> is <code>NULL</code> , then the statistics are retrieved directly from the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>statab</code> (Only pertinent if <code>statab</code> is not <code>NULL</code>).
cascade_parts	If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then setting this to <code>TRUE</code> causes the deletion of statistics for this table for all underlying partitions as well.
cascade_columns	Indicates that <code>DELETE_COLUMN_STATS</code> should be called for all underlying columns (passing the <code>cascade_parts</code> parameter).

Table 93–16 (Cont.) DELETE_TABLE_STATS Procedure Parameters

Parameter	Description
<code>cascade_indexes</code>	Indicates that <code>DELETE_INDEX_STATS</code> should be called for all underlying indexes (passing the <code>cascade_parts</code> parameter).
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
<code>no_invalidate</code>	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
<code>force</code>	When value of this argument is <code>TRUE</code> , deletes table statistics even if locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20005: Object statistics are locked.

DROP_STAT_TABLE Procedure

This procedure drops a user statistics table.

Syntax

```
DBMS_STATS.DROP_STAT_TABLE (  
    ownname VARCHAR2,  
    stattab VARCHAR2);
```

Parameters

Table 93–17 DROP_STAT_TABLE Procedure Parameters

Parameter	Description
ownname	Name of the schema.
stattab	User statistics table identifier.

Exceptions

ORA-20000: Table does not exists or insufficient privileges.

EXPORT_COLUMN_STATS Procedure

This procedure retrieves statistics for a particular column and stores them in the user statistics table identified by `stattab`.

Syntax

```
DBMS_STATS.EXPORT_COLUMN_STATS (  
    ownname  VARCHAR2,  
    tabname  VARCHAR2,  
    colname  VARCHAR2,  
    partname VARCHAR2 DEFAULT NULL,  
    stattab  VARCHAR2,  
    statid   VARCHAR2 DEFAULT NULL,  
    statown  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–18 EXPORT_COLUMN_STATS Procedure Parameters

Parameter	Description
<code>ownname</code>	Name of the schema.
<code>tabname</code>	Name of the table to which this column belongs.
<code>colname</code>	Name of the column.
<code>partname</code>	Name of the table partition. If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then global and partition column statistics are exported.
<code>stattab</code>	User statistics table identifier describing where to store the statistics.
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code> .
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

EXPORT_DATABASE_STATS Procedure

This procedure retrieves statistics for all objects in the database and stores them in the user statistics tables identified by `statown.stattab`.

Syntax

```
DBMS_STATS.EXPORT_DATABASE_STATS (
  stattab VARCHAR2,
  statid  VARCHAR2 DEFAULT NULL,
  statown VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–19 EXPORT_DATABASE_STATS Procedure Parameters

Parameter	Description
<code>stattab</code>	User statistics table identifier describing where to store the statistics
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code>
<code>statown</code>	Schema containing <code>stattab</code> . If <code>statown</code> is <code>NULL</code> , then it is assumed that every schema in the database contains a user statistics table with the name <code>stattab</code> .

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

EXPORT_DICTIONARY_STATS Procedure

This procedure retrieves statistics for all dictionary schemas ('SYS', 'SYSTEM' and RDBMS component schemas) and stores them in the user statistics table identified by `stattab`.

Syntax

```
DBMS_STATS.EXPORT_DICTIONARY_STATS (  
    stattab VARCHAR2,  
    statid  VARCHAR2 DEFAULT NULL,  
    statown VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–20 EXPORT_DICTIONARY_STATS Procedure Parameters

Parameter	Description
<code>stattab</code>	User statistics table identifier describing where to store the statistics
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code>
<code>statown</code>	Schema containing <code>stattab</code> . If <code>statown</code> is <code>NULL</code> , then it is assumed that every schema in the database contains a user statistics table with the name <code>stattab</code> .

Usage Notes

You must have the `SYSDBA` or `ANALYZE ANY DICTIONARY` and `ANALYZE ANY SYSTEM` privilege to execute this procedure.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20002: Bad user statistics table, may need to upgrade it.

EXPORT_FIXED_OBJECTS_STATS Procedure

This procedure retrieves statistics for fixed tables and stores them in the user statistics table identified by `stattab`.

Syntax

```
DBMS_STATS.EXPORT_FIXED_OBJECTS_STATS (
  stattab VARCHAR2,
  statid  VARCHAR2 DEFAULT NULL,
  statown VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–21 EXPORT_FIXED_OBJECTS_STATS Procedure Parameters

Parameter	Description
<code>stattab</code>	User statistics table identifier describing where to store the statistics.
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code> .
<code>statown</code>	Schema containing <code>stattab</code> (if different from <code>ownname</code>).

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20002: Bad user statistics table, may need to upgrade it.

EXPORT_INDEX_STATS Procedure

This procedure retrieves statistics for a particular index and stores them in the user statistics table identified by `stattab`.

Syntax

```
DBMS_STATS.EXPORT_INDEX_STATS (  
    ownname  VARCHAR2,  
    indname  VARCHAR2,  
    partname VARCHAR2 DEFAULT NULL,  
    stattab  VARCHAR2,  
    statid   VARCHAR2 DEFAULT NULL,  
    statown  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–22 EXPORT_INDEX_STATS Procedure Parameters

Parameter	Description
<code>ownname</code>	Name of the schema.
<code>indname</code>	Name of the index.
<code>partname</code>	Name of the index partition. If the index is partitioned and if <code>partname</code> is <code>NULL</code> , then global and partition index statistics are exported.
<code>stattab</code>	User statistics table identifier describing where to store the statistics.
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code> .
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

EXPORT_SCHEMA_STATS Procedure

This procedure retrieves statistics for all objects in the schema identified by `ownname` and stores them in the user statistics tables identified by `stattab`.

Syntax

```
DBMS_STATS.EXPORT_SCHEMA_STATS (
    ownname VARCHAR2,
    stattab VARCHAR2,
    statid  VARCHAR2 DEFAULT NULL,
    statown VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–23 EXPORT_SCHEMA_STATS Procedure Parameters

Parameter	Description
<code>ownname</code>	Name of the schema.
<code>stattab</code>	User statistics table identifier describing where to store the statistics.
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code> .
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

EXPORT_SYSTEM_STATS Procedure

This procedure retrieves system statistics and stores them in the user statistics table, identified by `stattab`.

Syntax

```
DBMS_STATS.EXPORT_SYSTEM_STATS (  
    stattab      VARCHAR2,  
    statid       VARCHAR2 DEFAULT NULL,  
    statown      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93-24 EXPORT_SYSTEM_STATS Procedure Parameters

Parameter	Description
<code>stattab</code>	Identifier of the user statistics table that describes where the statistics will be stored.
<code>statid</code>	Optional identifier associated with the statistics stored from the <code>stattab</code> .
<code>statown</code>	The schema containing <code>stattab</code> , if different from the user's schema.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20002: Bad user statistics table; may need to be upgraded.

ORA-20003: Unable to export system statistics.

EXPORT_TABLE_STATS Procedure

This procedure retrieves statistics for a particular table and stores them in the user statistics table. Cascade results in all index and column statistics associated with the specified table being exported as well.

Syntax

```
DBMS_STATS.EXPORT_TABLE_STATS (
  ownname  VARCHAR2,
  tabname  VARCHAR2,
  partname VARCHAR2 DEFAULT NULL,
  stattab  VARCHAR2,
  statid   VARCHAR2 DEFAULT NULL,
  cascade  BOOLEAN   DEFAULT TRUE,
  statown  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–25 EXPORT_TABLE_STATS Procedure Parameters

Parameter	Description
ownname	Name of the schema.
tabname	Name of the table.
partname	Name of the table partition. If the table is partitioned and if partname is NULL, then global and partition table statistics are exported.
stattab	User statistics table identifier describing where to store the statistics.
statid	Identifier (optional) to associate with these statistics within stattab.
cascade	If true, then column and index statistics for this table are also exported.
statown	Schema containing stattab (if different than ownname).

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

FLUSH_DATABASE_MONITORING_INFO Procedure

This procedure flushes in-memory monitoring information for all tables in the dictionary. Corresponding entries in the *_TAB_MODIFICATIONS views are updated immediately, without waiting for the Oracle database to flush them periodically. This procedure is useful when you need up-to-date information in those views. Because the GATHER_*_STATS procedures internally flush monitoring information, it is not necessary to run this procedure before gathering the statistics.

Syntax

```
DBMS_STATS.FLUSH_DATABASE_MONITORING_INFO;
```

Exceptions

ORA-20000: Insufficient privileges.

GATHER_DATABASE_STATS Procedures

This procedure gathers statistics for all objects in the database.

Syntax

```
DBMS_STATS.GATHER_DATABASE_STATS (
    estimate_percent NUMBER    DEFAULT to_estimate_percent_type
                                (get_param('ESTIMATE_PERCENT')),
    block_sample      BOOLEAN  DEFAULT FALSE,
    method_opt        VARCHAR2 DEFAULT get_param('METHOD_OPT'),
    degree            NUMBER   DEFAULT to_degree_type(get_param('DEGREE')),
    granularity       VARCHAR2 DEFAULT 'AUTO',
    cascade           BOOLEAN  DEFAULT to_cascade_type(get_param('CASCADE')),
    stattab          VARCHAR2  DEFAULT NULL,
    statid           VARCHAR2  DEFAULT NULL,
    options           VARCHAR2  DEFAULT 'GATHER',
    objlist           OUT      ObjectTab,
    statown          VARCHAR2  DEFAULT NULL,
    gather_sys        BOOLEAN  DEFAULT FALSE,
    no_invalidate     BOOLEAN  DEFAULT to_no_invalidate_type (
                                get_param('NO_INVALIDATE')));
```

```
DBMS_STATS.GATHER_DATABASE_STATS (
    estimate_percent NUMBER    DEFAULT to_estimate_percent_type
                                (get_param('ESTIMATE_PERCENT')),
    block_sample      BOOLEAN  DEFAULT FALSE,
    method_opt        VARCHAR2 DEFAULT get_param('METHOD_OPT'),
    degree            NUMBER   DEFAULT to_degree_type(get_param('DEGREE')),
    granularity       VARCHAR2 DEFAULT 'AUTO',
    cascade           BOOLEAN  DEFAULT to_cascade_type(get_param('CASCADE')),
    stattab          VARCHAR2  DEFAULT NULL,
    statid           VARCHAR2  DEFAULT NULL,
    options           VARCHAR2  DEFAULT 'GATHER',
    statown          VARCHAR2  DEFAULT NULL,
    gather_sys        BOOLEAN  DEFAULT FALSE,
    no_invalidate     BOOLEAN  DEFAULT to_no_invalidate_type (
                                get_param('NO_INVALIDATE')));
```

Parameters

Table 93–26 *GATHER_DATABASE_STATS Procedure Parameters*

Parameter	Description
<code>estimate_percent</code>	Percentage of rows to estimate (NULL means compute): The valid range is [0.000001,100]. Use the constant <code>DBMS_STATS.AUTO_SAMPLE_SIZE</code> to have Oracle determine the appropriate sample size for good statistics. This is the default. The default value can be changed using the SET_PARAM Procedure ...
<code>block_sample</code>	Whether or not to use random block sampling instead of random row sampling. Random block sampling is more efficient, but if the data is not randomly distributed on disk, then the sample values may be somewhat correlated. Only pertinent when doing an estimate statistics.
<code>method_opt</code>	<p>Accepts:</p> <ul style="list-style-type: none"> ■ <code>FOR ALL [INDEXED HIDDEN] COLUMNS [size_clause]</code> ■ <code>FOR COLUMNS [size_clause] column attribute [size_clause] [,column attribute [size_clause]...]</code>, where <code>size_clause</code> is defined as <code>size_clause := SIZE {integer REPEAT AUTO SKEWONLY}</code> ■ <code>integer</code>—Number of histogram buckets. Must be in the range [1,254]. ■ <code>REPEAT</code>—Collects histograms only on the columns that already have histograms. ■ <code>AUTO</code>—Oracle determines the columns to collect histograms based on data distribution and the workload of the columns. ■ <code>SKEWONLY</code>—Oracle determines the columns to collect histograms based on the data distribution of the columns. <p>The default is <code>FOR ALL COLUMNS SIZE AUTO</code>. The default value can be changed using the SET_PARAM Procedure.</p>

Table 93–26 (Cont.) GATHER_DATABASE_STATS Procedure Parameters

Parameter	Description
degree	Degree of parallelism. The default for degree is NULL. The default value can be changed using the SET_PARAM Procedure . NULL means use the table default value specified by the DEGREE clause in the CREATE TABLE or ALTER TABLE statement. Use the constant DBMS_STATS.DEFAULT_DEGREE to specify the default value based on the initialization parameters. The AUTO_DEGREE value determines the degree of parallelism automatically. This is either 1 (serial execution) or DEFAULT_DEGREE (the system default value based on number of CPUs and initialization parameters) according to size of the object.
granularity	Granularity of statistics to collect (only pertinent if the table is partitioned). <p>'ALL' - gathers all (subpartition, partition, and global) statistics</p> <p>'AUTO' - determines the granularity based on the partitioning type, and collects the global, partition level and subpartition level statistics if the subpartitioning method is LIST, and the global and partition level only otherwise. This is the default value.</p> <p>'DEFAULT' - gathers global and partition-level statistics. This option is obsolete, and while currently supported, it is included in the documentation for legacy reasons only. You should use the 'GLOBAL AND PARTITION' for this functionality. Note that the default value is now 'AUTO'.</p> <p>'GLOBAL' - gathers global statistics</p> <p>'GLOBAL AND PARTITION' - gathers the global and partition level statistics. No subpartition level statistics are gathered even if it is a composite partitioned object.</p> <p>'PARTITION' - gathers partition-level statistics</p> <p>'SUBPARTITION' - gathers subpartition-level statistics.</p>
cascade	Gather statistics on the indexes as well. Index statistics gathering is not parallelized. Using this option is equivalent to running the GATHER_INDEX_STATS Procedure on each of the indexes in the database in addition to gathering table and column statistics. Use the constant DBMS_STATS.AUTO_CASCADE to have Oracle determine whether index statistics to be collected or not. This is the default. The default value can be changed using the SET_PARAM Procedure .

Table 93–26 (Cont.) GATHER_DATABASE_STATS Procedure Parameters

Parameter	Description
stattab	User statistics table identifier describing where to save the current statistics. The statistics table is assumed to reside in the same schema as the object being analyzed, so there must be one such table in each schema to use this option.
statid	Identifier (optional) to associate with these statistics within stattab.
options	Further specification of which objects to gather statistics for: GATHER: Gathers statistics on all objects in the schema. GATHER AUTO: Gathers all necessary statistics automatically. Oracle implicitly determines which objects need new statistics, and determines how to gather those statistics. When GATHER AUTO is specified, the only additional valid parameters are stattab, statid, objlist and statown; all other parameter settings are ignored. Returns a list of processed objects. GATHER STALE: Gathers statistics on stale objects as determined by looking at the *_tab_modifications views. Also, return a list of objects found to be stale. GATHER EMPTY: Gathers statistics on objects which currently have no statistics. Return a list of objects found to have no statistics. LIST AUTO: Returns a list of objects to be processed with GATHER AUTO. LIST STALE: Returns a list of stale objects as determined by looking at the *_tab_modifications views. LIST EMPTY: Returns a list of objects which currently have no statistics.
objlist	List of objects found to be stale or empty.
statown	Schema containing stattab (if different than ownname).
gather_sys	Gathers statistics on the objects owned by the 'SYS' user.

Table 93–26 (Cont.) GATHER_DATABASE_STATS Procedure Parameters

Parameter	Description
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the objects for which statistics are being gathered. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Cannot be used with the <code>cascade</code> option. This option has no effect when an index is picked up as a target because <code>GATHER_INDEX_STATS</code> does not support this option. Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .

Usage Notes

Statistics for external tables are not collected by this procedure.

Exceptions

ORA-20000: Insufficient privileges.

ORA-20001: Bad input value.

GATHER_DICTIONARY_STATS Procedure

This procedure gathers statistics for dictionary schemas 'SYS', 'SYSTEM' and schemas of RDBMS components.

Syntax

```
DBMS_STATS.GATHER_DICTIONARY_STATS (
  comp_id          VARCHAR2 DEFAULT NULL,
  estimate_percent NUMBER   DEFAULT to_estimate_percent_type
                                     (get_param('ESTIMATE_PERCENT')),
  block_sample     BOOLEAN   DEFAULT FALSE,
  method_opt       VARCHAR2 DEFAULT get_param('METHOD_OPT'),
  degree           NUMBER   DEFAULT to_degree_type(get_param('DEGREE')),
  granularity      VARCHAR2 DEFAULT 'AUTO',
  cascade          BOOLEAN   DEFAULT to_cascade_type(get_param('CASCADE')),
  stattab          VARCHAR2 DEFAULT NULL,
  statid           VARCHAR2 DEFAULT NULL,
  options          VARCHAR2 DEFAULT 'GATHER AUTO',
  objlist          OUT      ObjectTab,
  statown          VARCHAR2 DEFAULT NULL,
  no_invalidate    BOOLEAN   DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')));
```

Parameters

Table 93–27 GATHER_DICTIONARY_STATS Procedure Parameters

Parameter	Description
comp_id	The component id of the schema to analyze (NULL will result in analyzing schemas of all RDBMS components). Please refer to comp_id column of DBA_REGISTRY view. The procedure always gather statistics on 'SYS' and 'SYSTEM' schemas regardless of this argument.
estimate_percent	Percentage of rows to estimate (NULL means compute). The valid range is [0.000001, 100]. Use the constant DBMS_STATS.AUTO_SAMPLE_SIZE to have Oracle determine the appropriate sample size for good statistics. This is the default. The default value can be changed using the SET_PARAM Procedure .

Table 93–27 (Cont.) GATHER_DICTIONARY_STATS Procedure Parameters

Parameter	Description
block_sample	Determines whether or not to use random block sampling instead of random row sampling. Random block sampling is more efficient, but if the data is not randomly distributed on disk then the sample values may be somewhat correlated. Only pertinent when performing estimate statistics.
method_opt	The method options of the following format: <pre>size_clause := SIZE [integer auto skewonly repeat]</pre> <p>where integer is between 1 and 254 FOR ALL [INDEXED HIDDEN] COLUMNS [size_clause]. This value will be passed to all of the individual tables. The default is FOR ALL COLUMNS SIZE AUTO. The default value can be changed using the SET_PARAM Procedure.</p>
degree	Degree of parallelism. The default for degree is NULL. The default value can be changed using the SET_PARAM Procedure . NULL means use of table default value that was specified by the DEGREE clause in the CREATE or ALTER INDEX statement. Use the constant DBMS_STATS.DEFAULT_DEGREE for the default value based on the initialization parameters. The AUTO_DEGREE value determines the degree of parallelism automatically. This is either 1 (serial execution) or DEFAULT_DEGREE (the system default value based on number of CPUs and initialization parameters) according to size of the object.

Table 93–27 (Cont.) GATHER_DICTIONARY_STATS Procedure Parameters

Parameter	Description
granularity	<p>Granularity of statistics to collect (only pertinent if the table is partitioned).</p> <p>'ALL' - gathers all (subpartition, partition, and global) statistics</p> <p>'AUTO' - determines the granularity based on the partitioning type, and collects the global, partition level and subpartition level statistics if the subpartitioning method is <code>LIST</code>, and the global and partition level only otherwise. This is the default value.</p> <p>'DEFAULT' - gathers global and partition-level statistics. This option is obsolete, and while currently supported, it is included in the documentation for legacy reasons only. You should use the 'GLOBAL AND PARTITION' for this functionality. Note that the default value is now 'AUTO'.</p> <p>'GLOBAL' - gathers global statistics</p> <p>'GLOBAL AND PARTITION' - gathers the global and partition level statistics. No subpartition level statistics are gathered even if it is a composite partitioned object.</p> <p>'PARTITION' - gathers partition-level statistics</p> <p>'SUBPARTITION' - gathers subpartition-level statistics.</p>
cascade	<p>Gathers statistics on indexes also. Index statistics gathering will not be parallelized. Using this option is equivalent to running the GATHER_INDEX_STATS Procedure on each of the indexes in the schema in addition to gathering table and column statistics. Use the constant <code>DBMS_STATS.AUTO_CASCADE</code> to have Oracle determine whether index statistics to be collected or not. This is the default. The default value can be changed using the SET_PARAM Procedure.</p>
stattab	<p>User statistics table identifier describing where to save the current statistics.</p>
statid	<p>The (optional) identifier to associate with these statistics within <code>stattab</code>.</p>

Table 93–27 (Cont.) GATHER_DICTIONARY_STATS Procedure Parameters

Parameter	Description
options	<p>Further specification of objects for which to gather statistics:</p> <ul style="list-style-type: none"> ■ 'GATHER' - gathers statistics on all objects in the schema ■ 'GATHER AUTO' - gathers all necessary statistics automatically. Oracle implicitly determines which objects need new statistics and determines how to gather those statistics. When 'GATHER AUTO' is specified, the only additional valid parameters are <code>comp_id</code>, <code>stattab</code>, <code>statid</code> and <code>statown</code>; all other parameter settings will be ignored. Also, returns a list of objects processed. ■ 'GATHER STALE' - gathers statistics on stale objects as determined by looking at the <code>*_tab_modifications</code> views. Also, returns a list of objects found to be stale. ■ 'GATHER EMPTY' - gathers statistics on objects which currently have no statistics. Also, returns a list of objects found to have no statistics. ■ 'LIST AUTO' - returns list of objects to be processed with 'GATHER AUTO' ■ 'LIST STALE' - returns list of stale objects as determined by looking at the <code>*_tab_modifications</code> views ■ 'LIST EMPTY' - returns list of objects which currently have no statistics
objlist	The list of objects found to be stale or empty.
statown	The schema containing <code>stattab</code> (if different than <code>ownname</code>).
no_invalidate	Dependent cursors are not invalidated if this parameter is set to <code>TRUE</code> . When 'CASCADE' option is specified, this does not apply to certain types of indexes described with regard to the GATHER_INDEX_STATS Procedure . Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .

Usage Notes

You must have the `SYSDBA` or both `ANALYZE ANY DICTIONARY` and `ANALYZE ANY SYSTEM` privilege to execute this procedure.

Exceptions

ORA-20000: Index does not exist or insufficient privileges.

ORA-20001: Bad input value.

ORA-20002: Bad user statistics table, may need to upgrade it.

GATHER_FIXED_OBJECTS_STATS Procedure

This procedure gathers statistics for all fixed objects (dynamic performance tables).

Syntax

```
DBMS_STATS.GATHER_FIXED_OBJECTS_STATS (
  statab      VARCHAR2 DEFAULT NULL,
  statid      VARCHAR2 DEFAULT NULL,
  statown     VARCHAR2 DEFAULT NULL,
  no_invalidate BOOLEAN DEFAULT to_no_invalidate_type (
    get_param('NO_INVALIDATE')));
```

Parameters

Table 93–28 *GATHER_FIXED_OBJECTS_STATS Procedure Parameters*

Parameter	Description
statab	The user statistics table identifier describing where to save the current statistics.
statid	The (optional) identifier to associate with these statistics within statab.
statown	The schema containing statab (if different from ownname).
no_invalidate	Does not invalidate the dependent cursors if set to TRUE. Use DBMS_STATS.AUTO_INVALIDATE to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .

Usage Notes

You must have the SYSDBA or ANALYZE ANY DICTIONARY system privilege to execute this procedure.

Exceptions

ORA-20000: Insufficient privileges.

ORA-20001: Bad input value.

ORA-20002: Bad user statistics table, may need to upgrade it.

GATHER_INDEX_STATS Procedure

This procedure gathers index statistics. It attempts to parallelize as much of the work as possible. Restrictions are described in the individual parameters. This operation will not parallelize with certain types of indexes, including cluster indexes, domain indexes, and bitmap join indexes. The `granularity` and `no_invalidate` arguments are not relevant to these types of indexes.

Syntax

```
DBMS_STATS.GATHER_INDEX_STATS (
  ownname          VARCHAR2,
  indname          VARCHAR2,
  partname         VARCHAR2 DEFAULT NULL,
  estimate_percent NUMBER   DEFAULT to_estimate_percent_type
                                     (get_param('ESTIMATE_PERCENT')),
  stattab          VARCHAR2 DEFAULT NULL,
  statid           VARCHAR2 DEFAULT NULL,
  statown          VARCHAR2 DEFAULT NULL,
  degree           NUMBER   DEFAULT to_degree_type(get_param('DEGREE')),
  granularity      VARCHAR2 DEFAULT 'AUTO',
  no_invalidate    BOOLEAN  DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')));
```

Parameters

Table 93–29 *GATHER_INDEX_STATS Procedure Parameters*

Parameter	Description
<code>ownname</code>	Schema of index to analyze.
<code>indname</code>	Name of index.
<code>partname</code>	Name of partition.
<code>estimate_percent</code>	Percentage of rows to estimate (NULL means compute). The valid range is [0.000001, 100]. Use the constant <code>DBMS_STATS.AUTO_SAMPLE_SIZE</code> to have Oracle determine the appropriate sample size for good statistics. This is the default. The default value can be changed using the SET_PARAM Procedure .
<code>stattab</code>	User statistics table identifier describing where to save the current statistics.

Table 93–29 (Cont.) GATHER_INDEX_STATS Procedure Parameters

Parameter	Description
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> .
statown	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
degree	Degree of parallelism. The default for <code>degree</code> is <code>NULL</code> . The default value can be changed using the SET_PARAM Procedure . <code>NULL</code> means use of table default value that was specified by the <code>DEGREE</code> clause in the <code>CREATE/ALTER INDEX</code> statement. Use the constant <code>DBMS_STATS.DEFAULT_DEGREE</code> for the default value based on the initialization parameters. The <code>AUTO_DEGREE</code> value determines the degree of parallelism automatically. This is either 1 (serial execution) or <code>DEFAULT_DEGREE</code> (the system default value based on number of CPUs and initialization parameters) according to size of the object.
granularity	Granularity of statistics to collect (only pertinent if the table is partitioned). <p>'ALL' - gathers all (subpartition, partition, and global) statistics</p> <p>'AUTO' - determines the granularity based on the partitioning type, and collects the global, partition level and subpartition level statistics if the subpartitioning method is <code>LIST</code>, and the global and partition level only otherwise. This is the default value.</p> <p>'DEFAULT' - gathers global and partition-level statistics. This option is obsolete, and while currently supported, it is included in the documentation for legacy reasons only. You should use the 'GLOBAL AND PARTITION' for this functionality. Note that the default value is now 'AUTO'.</p> <p>'GLOBAL' - gathers global statistics</p> <p>'GLOBAL AND PARTITION' - gathers the global and partition level statistics. No subpartition level statistics are gathered even if it is a composite partitioned object.</p> <p>'PARTITION' - gathers partition-level statistics</p> <p>'SUBPARTITION' - gathers subpartition-level statistics.</p>
no_invalidate	Dependent cursors are not invalidated if this parameter is set to <code>TRUE</code> . Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .

Exceptions

ORA-20000: Index does not exist or insufficient privileges.

ORA-20001: Bad input value.

GATHER_SCHEMA_STATS Procedures

This procedure gathers statistics for all objects in a schema.

Syntax

```
DBMS_STATS.GATHER_SCHEMA_STATS (
  ownname          VARCHAR2,
  estimate_percent NUMBER   DEFAULT to_estimate_percent_type
                                     (get_param('ESTIMATE_PERCENT')),
  block_sample     BOOLEAN  DEFAULT FALSE,
  method_opt       VARCHAR2 DEFAULT get_param('METHOD_OPT'),
  degree           NUMBER   DEFAULT to_degree_type(get_param('DEGREE')),
  granularity       VARCHAR2 DEFAULT 'AUTO',
  cascade          BOOLEAN  DEFAULT to_cascade_type(get_param('CASCADE')),
  statab           VARCHAR2 DEFAULT NULL,
  statid           VARCHAR2 DEFAULT NULL,
  options          VARCHAR2 DEFAULT 'GATHER',
  statown          VARCHAR2 DEFAULT NULL,
  no_invalidate    BOOLEAN  DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')));
```

```
DBMS_STATS.GATHER_SCHEMA_STATS (
  ownname          VARCHAR2,
  estimate_percent NUMBER   DEFAULT to_estimate_percent_type
                                     (get_param('ESTIMATE_PERCENT')),
  block_sample     BOOLEAN  DEFAULT FALSE,
  method_opt       VARCHAR2 DEFAULT get_param('METHOD_OPT'),
  degree           NUMBER   DEFAULT to_degree_type(get_param('DEGREE')),
  granularity       VARCHAR2 DEFAULT 'AUTO',
  cascade          BOOLEAN  DEFAULT to_cascade_type(get_param('CASCADE')),
  statab           VARCHAR2 DEFAULT NULL,
  statid           VARCHAR2 DEFAULT NULL,
  options          VARCHAR2 DEFAULT 'GATHER',
  statown          VARCHAR2 DEFAULT NULL,
  no_invalidate    BOOLEAN  DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')));
```

Parameters

Table 93–30 *GATHER_SCHEMA_STATS Procedure Parameters*

Parameter	Description
ownname	Schema to analyze (NULL means current schema).
estimate_percent	Percentage of rows to estimate (NULL means compute): The valid range is [0.000001,100]. Use the constant DBMS_STATS.AUTO_SAMPLE_SIZE to have Oracle determine the appropriate sample size for good statistics. This is the default. The default value can be changed using the SET_PARAM Procedure .
block_sample	Whether or not to use random block sampling instead of random row sampling. Random block sampling is more efficient, but if the data is not randomly distributed on disk, then the sample values may be somewhat correlated. Only pertinent when doing an estimate statistics.
method_opt	<p>Accepts:</p> <ul style="list-style-type: none"> ■ FOR ALL [INDEXED HIDDEN] COLUMNS [size_clause] ■ FOR COLUMNS [size_clause] column attribute [size_clause] [,column attribute [size_clause]...], where size_clause is defined as size_clause := SIZE {integer REPEAT AUTO SKEWONLY} ■ integer—Number of histogram buckets. Must be in the range [1,254]. ■ REPEAT—Collects histograms only on the columns that already have histograms. ■ AUTO—Oracle determines the columns to collect histograms based on data distribution and the workload of the columns. ■ SKEWONLY—Oracle determines the columns to collect histograms based on the data distribution of the columns. <p>The default is FOR ALL COLUMNS SIZE AUTO. The default value can be changed using the SET_PARAM Procedure.</p>

Table 93–30 (Cont.) GATHER_SCHEMA_STATS Procedure Parameters

Parameter	Description
degree	Degree of parallelism. The default for degree is NULL. The default value can be changed using the SET_PARAM Procedure . NULL means use the table default value specified by the DEGREE clause in the CREATE TABLE or ALTER TABLE statement. Use the constant DBMS_STATS.DEFAULT_DEGREE to specify the default value based on the initialization parameters. The AUTO_DEGREE value determines the degree of parallelism automatically. This is either 1 (serial execution) or DEFAULT_DEGREE (the system default value based on number of CPUs and initialization parameters) according to size of the object.
granularity	Granularity of statistics to collect (only pertinent if the table is partitioned). <p>'ALL' - gathers all (subpartition, partition, and global) statistics</p> <p>'AUTO' - determines the granularity based on the partitioning type, and collects the global, partition level and subpartition level statistics if the subpartitioning method is LIST, and the global and partition level only otherwise. This is the default value.</p> <p>'DEFAULT' - gathers global and partition-level statistics. This option is obsolete, and while currently supported, it is included in the documentation for legacy reasons only. You should use the 'GLOBAL AND PARTITION' for this functionality. Note that the default value is now 'AUTO'.</p> <p>'GLOBAL' - gathers global statistics</p> <p>'GLOBAL AND PARTITION' - gathers the global and partition level statistics. No subpartition level statistics are gathered even if it is a composite partitioned object.</p> <p>'PARTITION' - gathers partition-level statistics</p> <p>'SUBPARTITION' - gathers subpartition-level statistics.</p>
cascade	Gather statistics on the indexes as well. Index statistics gathering is not parallelized. Using this option is equivalent to running the GATHER_INDEX_STATS Procedure on each of the indexes in the schema in addition to gathering table and column statistics. Use the constant DBMS_STATS.AUTO_CASCADE to have Oracle determine whether index statistics to be collected or not. This is the default. The default value can be changed using the SET_PARAM Procedure .

Table 93–30 (Cont.) GATHER_SCHEMA_STATS Procedure Parameters

Parameter	Description
stattab	User statistics table identifier describing where to save the current statistics.
statid	Identifier (optional) to associate with these statistics within stattab.
options	<p>Further specification of which objects to gather statistics for:</p> <p>GATHER: Gathers statistics on all objects in the schema.</p> <p>GATHER AUTO: Gathers all necessary statistics automatically. Oracle implicitly determines which objects need new statistics, and determines how to gather those statistics. When GATHER AUTO is specified, the only additional valid parameters are ownname, stattab, statid, objlist and statown; all other parameter settings are ignored. Returns a list of processed objects.</p> <p>GATHER STALE: Gathers statistics on stale objects as determined by looking at the *_tab_modifications views. Also, return a list of objects found to be stale.</p> <p>GATHER EMPTY: Gathers statistics on objects which currently have no statistics. also, return a list of objects found to have no statistics.</p> <p>LIST AUTO: Returns a list of objects to be processed with GATHER AUTO.</p> <p>LIST STALE: Returns list of stale objects as determined by looking at the *_tab_modifications views.</p> <p>LIST EMPTY: Returns list of objects which currently have no statistics.</p>
statown	Schema containing stattab (if different than ownname).
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the objects for which statistics are being gathered. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Cannot be used with the cascade option because GATHER_INDEX_STATS does not support the cascade option. This option has no effect when an index is picked up as a target because GATHER_INDEX_STATS does not support this option. Use DBMS_STATS.AUTO_INVALIDATE . to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .

Usage Notes

DBMS_STATS.GATHER_SCHEMA_STATS generates differing sampling rates on partitioned tables when you use the `auto_sample_size` constant. DBMS_STATS tries to determine an adequate sample size for each type of statistic, which is different for each table or column (and each partition, if partitioned). It starts with a sampling rate to get approximately 5000 rows and examines the result based on statistical equations. This process is repeated with increased sampling rate for unsatisfactory results.

In general, the number of distinct values column statistics requires the highest sampling rate among the others, especially when each distinct value repeats a small number of times.

When you use a specific value for the sampling percentage, DBMS_STATS honors it except for when:

- The result is less than 2500 rows (too small a sample) and
- The specified percentage is more than the certain percentage.

Statistics for external tables are not collected by this procedure.

Exceptions

ORA-20000: Schema does not exist or insufficient privileges.

ORA-20001: Bad input value.

GATHER_SYSTEM_STATS Procedure

This procedure gathers system statistics.

Syntax

```
DBMS_STATS.GATHER_SYSTEM_STATS (  
    gathering_mode    VARCHAR2 DEFAULT 'NOWORKLOAD',  
    interval          INTEGER   DEFAULT NULL,  
    stattab           VARCHAR2  DEFAULT NULL,  
    statid            VARCHAR2  DEFAULT NULL,  
    statown           VARCHAR2  DEFAULT NULL);
```

Parameters

Table 93–31 GATHER_SYSTEM_STATS Procedure Parameters

Parameter	Description
gathering_mode	<p>Mode values are:</p> <p>NOWORKLOAD: Will capture characteristics of the I/O system. Gathering may take a few minutes and depends on the size of the database. During this period Oracle will estimate the average read seek time and transfer speed for the I/O system. This mode is suitable for the all workloads. Oracle recommends to run <code>GATHER_SYSTEM_STATS ('noworkload')</code> after creation of the database and tablespaces. To fine tune system statistics for the workload use 'START' and 'STOP' or 'INTERVAL' options. If you gather both 'NOWORKLOAD' and workload specific (statistics collected using 'INTERVAL' or 'START' and 'STOP'), the workload statistics will be used by optimizer. Collected components: <code>cpuspeednw</code>, <code>ioseektim</code>, <code>iotfrspeed</code>.</p> <p>INTERVAL: Captures system activity during a specified interval. This works in combination with the <code>interval</code> parameter. You should provide an interval value in minutes, after which system statistics are created or updated in the dictionary or <code>stattab</code>. You can use <code>GATHER_SYSTEM_STATS (gathering_mode=> 'STOP')</code> to stop gathering earlier than scheduled. Collected components: <code>maxthr</code>, <code>slavethr</code>, <code>cpuspeed</code>, <code>sreadtim</code>, <code>mreadtim</code>, <code>mbrc</code>.</p> <p>START STOP: Captures system activity during specified start and stop times and refreshes the dictionary or <code>stattab</code> with statistics for the elapsed period. Interval value is ignored. Collected components: <code>maxthr</code>, <code>slavethr</code>, <code>cpuspeed</code>, <code>sreadtim</code>, <code>mreadtim</code>, <code>mbrc</code>.</p>
interval	Time, in minutes, to gather statistics. This parameter applies only when <code>gathering_mode= 'INTERVAL'</code> .
stattab	Identifier of the user statistics table where the statistics will be saved.
statid	Optional identifier associated with the statistics saved in the <code>stattab</code> .
statown	The schema containing <code>stattab</code> , if different from the user's schema.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid input value.

ORA-20002: Bad user statistics table; may need to be upgraded.

ORA-20003: Unable to gather system statistics.

ORA-20004: Error in the INTERVAL mode: system parameter job_queue_processes must be >0.

GATHER_TABLE_STATS Procedure

This procedure gathers table and column (and index) statistics. It attempts to parallelize as much of the work as possible, but there are some restrictions as described in the individual parameters.

Syntax

```
DBMS_STATS.GATHER_TABLE_STATS (
  ownname          VARCHAR2,
  tabname          VARCHAR2,
  partname         VARCHAR2 DEFAULT NULL,
  estimate_percent NUMBER   DEFAULT to_estimate_percent_type
                                     (get_param('ESTIMATE_PERCENT')),
  block_sample     BOOLEAN   DEFAULT FALSE,
  method_opt       VARCHAR2 DEFAULT get_param('METHOD_OPT'),
  degree           NUMBER   DEFAULT to_degree_type(get_param('DEGREE')),
  granularity      VARCHAR2 DEFAULT 'AUTO',
  cascade          BOOLEAN   DEFAULT to_cascade_type(get_param('CASCADE')),
  statstab         VARCHAR2 DEFAULT NULL,
  statid           VARCHAR2 DEFAULT NULL,
  statown          VARCHAR2 DEFAULT NULL,
  no_invalidate    BOOLEAN   DEFAULT to_no_invalidate_type (
                                     get_param('NO_INVALIDATE')));
```

Parameters

Table 93–32 *GATHER_TABLE_STATS Procedure Parameters*

Parameter	Description
ownname	Schema of table to analyze.
tabname	Name of table.
partname	Name of partition.
estimate_percent	Percentage of rows to estimate (NULL means compute) The valid range is [0.000001,100]. Use the constant DBMS_STATS.AUTO_SAMPLE_SIZE to have Oracle determine the appropriate sample size for good statistics. This is the default. The default value can be changed using the SET_PARAM Procedure .

Table 93–32 (Cont.) GATHER_TABLE_STATS Procedure Parameters

Parameter	Description
block_sample	Whether or not to use random block sampling instead of random row sampling. Random block sampling is more efficient, but if the data is not randomly distributed on disk, then the sample values may be somewhat correlated. Only pertinent when doing an estimate statistics.
method_opt	<p>Accepts:</p> <ul style="list-style-type: none"> ■ FOR ALL [INDEXED HIDDEN] COLUMNS [size_clause] ■ FOR COLUMNS [size clause] column attribute [size_clause] [,column attribute [size_clause]...], where size_clause is defined as: size_clause := SIZE {integer REPEAT AUTO SKEWONLY} ■ integer—Number of histogram buckets. Must be in the range [1,254]. ■ REPEAT—Collects histograms only on the columns that already have histograms. ■ AUTO—Oracle determines the columns to collect histograms based on data distribution and the workload of the columns. ■ SKEWONLY—Oracle determines the columns to collect histograms based on the data distribution of the columns. <p>The default is FOR ALL COLUMNS SIZE AUTO. The default value can be changed using the SET_PARAM Procedure.</p>
degree	<p>Degree of parallelism. The default for degree is NULL. The default value can be changed using the SET_PARAM Procedure NULL means use the table default value specified by the DEGREE clause in the CREATE TABLE or ALTER TABLE statement. Use the constant DBMS_STATS.DEFAULT_DEGREE to specify the default value based on the initialization parameters. The AUTO_DEGREE value determines the degree of parallelism automatically. This is either 1 (serial execution) or DEFAULT_DEGREE (the system default value based on number of CPUs and initialization parameters) according to size of the object.</p>

Table 93–32 (Cont.) GATHER_TABLE_STATS Procedure Parameters

Parameter	Description
granularity	<p>Granularity of statistics to collect (only pertinent if the table is partitioned).</p> <p>'ALL' - gathers all (subpartition, partition, and global) statistics</p> <p>'AUTO' - determines the granularity based on the partitioning type, and collects the global, partition level and subpartition level statistics if the subpartitioning method is LIST, and the global and partition level only otherwise. This is the default value.</p> <p>'DEFAULT' - gathers global and partition-level statistics. This option is obsolete, and while currently supported, it is included in the documentation for legacy reasons only. You should use the 'GLOBAL AND PARTITION' for this functionality. Note that the default value is now 'AUTO'.</p> <p>'GLOBAL' - gathers global statistics</p> <p>'GLOBAL AND PARTITION' - gathers the global and partition level statistics. No subpartition level statistics are gathered even if it is a composite partitioned object.</p> <p>'PARTITION' - gathers partition-level statistics</p> <p>'SUBPARTITION' - gathers subpartition-level statistics.</p>
cascade	<p>Gather statistics on the indexes for this table. Index statistics gathering is not parallelized. Using this option is equivalent to running the GATHER_INDEX_STATS Procedure on each of the table's indexes. Use the constant <code>DBMS_STATS.AUTO_CASCADE</code> to have Oracle determine whether index statistics to be collected or not. This is the default. The default value can be changed using the SET_PARAM Procedure.</p>
stattab	User statistics table identifier describing where to save the current statistics.
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> .
statown	Schema containing <code>stattab</code> (if different than <code>ownname</code>).

Table 93–32 (Cont.) GATHER_TABLE_STATS Procedure Parameters

Parameter	Description
<code>no_invalidate</code>	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Cannot be used with the <code>cascade</code> option because <code>GATHER_INDEX_STATS</code> does not support the <code>cascade</code> option. Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .

Usage Notes

This operation does not parallelize if the user does not have select privilege on the table being analyzed.

Exceptions

ORA-20000: Table does not exist or insufficient privileges.

ORA-20001: Bad input value.

GENERATE_STATS Procedure

This procedure generates object statistics from previously collected statistics of related objects. The currently supported objects are b-tree and bitmap indexes.

Syntax

```
DBMS_STATS.GENERATE_STATS (
  ownname  VARCHAR2,
  objname  VARCHAR2,
  organized NUMBER DEFAULT 7);
```

Parameters

Table 93–33 *GENERATE_STATS Procedure Parameters*

Parameter	Description
ownname	Schema of object.
objname	Name of object.
organized	Amount of ordering associated between the index and its underlying table. A heavily organized index would have consecutive index keys referring to consecutive rows on disk for the table (the same block). A heavily disorganized index would have consecutive keys referencing different table blocks on disk. This parameter is only used for b-tree indexes. The number can be in the range of 0-10, with 0 representing a completely organized index and 10 a completely disorganized one.

Usage Notes

For fully populated schemas, the gather procedures should be used instead when more accurate statistics are desired.

Exceptions

ORA-20000: Unsupported object type of object does not exist.

ORA-20001: Invalid option or invalid statistics.

GET_COLUMN_STATS Procedures

These procedures gets all column-related information. In the form of this procedure that deals with user-defined statistics, the statistics type returned is the type stored, in addition to the user-defined statistics.

Syntax

```
DBMS_STATS.GET_COLUMN_STATS (
    ownname      VARCHAR2,
    tabname      VARCHAR2,
    colname      VARCHAR2,
    partname     VARCHAR2 DEFAULT NULL,
    stattab      VARCHAR2 DEFAULT NULL,
    statid       VARCHAR2 DEFAULT NULL,
    distcnt OUT  NUMBER,
    density OUT  NUMBER,
    nullcnt OUT  NUMBER,
    srec        OUT StatRec,
    avgclen OUT  NUMBER,
    statown     VARCHAR2 DEFAULT NULL);
```

Use the following for user-defined statistics:

```
DBMS_STATS.GET_COLUMN_STATS (
    ownname      VARCHAR2,
    tabname      VARCHAR2,
    colname      VARCHAR2,
    partname     VARCHAR2 DEFAULT NULL,
    stattab      VARCHAR2 DEFAULT NULL,
    statid       VARCHAR2 DEFAULT NULL,
    ext_stats    OUT RAW,
    statypown    OUT VARCHAR2 DEFAULT NULL,
    statypname   OUT VARCHAR2 DEFAULT NULL,
    statown     VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–34 *GET_COLUMN_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
tabname	Name of the table to which this column belongs.

Table 93–34 (Cont.) GET_COLUMN_STATS Procedure Parameters

Parameter	Description
colname	Name of the column.
partname	Name of the table partition from which to get the statistics. If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then the statistics are retrieved from the global table level.
stattab	User statistics table identifier describing from where to retrieve the statistics. If <code>stattab</code> is <code>NULL</code> , then the statistics are retrieved directly from the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> (Only pertinent if <code>stattab</code> is not <code>NULL</code>).
ext_stats	The user-defined statistics.
stattypown	Schema of the statistics type.
stattypname	Name of the statistics type.
distcnt	Number of distinct values.
density	Column density.
nullcnt	Number of <code>NULL</code> s .
srec	Structure holding internal representation of column minimum, maximum, and histogram values.
avgclen	Average length of the column (in bytes).
statown	Schema containing <code>stattab</code> (if different than <code>ownname</code>).

Exceptions

ORA-20000: Object does not exist or insufficient privileges or no statistics have been stored for requested object.

GET_INDEX_STATS Procedures

These procedures get all index-related information. In the form of this procedure that deals with user-defined statistics, the statistics type returned is the type stored, in addition to the user-defined statistics.

Syntax

```
DBMS_STATS.GET_INDEX_STATS (  
    ownname          VARCHAR2,  
    indname          VARCHAR2,  
    partname         VARCHAR2 DEFAULT NULL,  
    stattab          VARCHAR2 DEFAULT NULL,  
    statid           VARCHAR2 DEFAULT NULL,  
    numrows          OUT NUMBER,  
    numlblks         OUT NUMBER,  
    numdist          OUT NUMBER,  
    avglblk          OUT NUMBER,  
    avgdblk          OUT NUMBER,  
    clstfct          OUT NUMBER,  
    indlevel         OUT NUMBER,  
    statown          VARCHAR2 DEFAULT NULL,  
    cachedblk       OUT NUMBER,  
    cachehit        OUT NUMBER);
```

```
DBMS_STATS.GET_INDEX_STATS (  
    ownname          VARCHAR2,  
    indname          VARCHAR2,  
    partname         VARCHAR2 DEFAULT NULL,  
    stattab          VARCHAR2 DEFAULT NULL,  
    statid           VARCHAR2 DEFAULT NULL,  
    numrows          OUT NUMBER,  
    numlblks         OUT NUMBER,  
    numdist          OUT NUMBER,  
    avglblk          OUT NUMBER,  
    avgdblk          OUT NUMBER,  
    clstfct          OUT NUMBER,  
    indlevel         OUT NUMBER,  
    statown          VARCHAR2 DEFAULT NULL,  
    guessq           OUT NUMBER,  
    cachedblk       OUT NUMBER,  
    cachehit        OUT NUMBER);
```

Use the following for user-defined statistics:

```

DBMS_STATS.GET_INDEX_STATS (
  ownname          VARCHAR2,
  indname          VARCHAR2,
  partname         VARCHAR2 DEFAULT NULL,
  stattab          VARCHAR2 DEFAULT NULL,
  statid           VARCHAR2 DEFAULT NULL,
  ext_stats        OUT RAW,
  stattydown       OUT VARCHAR2 DEFAULT NULL,
  stattyname       OUT VARCHAR2 DEFAULT NULL,
  statown          VARCHAR2 DEFAULT NULL,
  cachedblk        OUT NUMBER,
  cachehit         OUT NUMBER);

```

Parameters

Table 93–35 *GET_INDEX_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
indname	Name of the index.
partname	Name of the index partition for which to get the statistics. If the index is partitioned and if <code>partname</code> is <code>NULL</code> , then the statistics are retrieved for the global index level.
stattab	User statistics table identifier describing from where to retrieve the statistics. If <code>stattab</code> is <code>NULL</code> , then the statistics are retrieved directly from the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> (Only pertinent if <code>stattab</code> is not <code>NULL</code>).
ext_stats	The user-defined statistics.
stattydown	Schema of the statistics type.
stattyname	Name of the statistics type.
numrows	Number of rows in the index (partition).
numlblks	Number of leaf blocks in the index (partition).
numdist	Number of distinct keys in the index (partition).
avglblk	Average integral number of leaf blocks in which each distinct key appears for this index (partition).
avgdblks	Average integral number of data blocks in the table pointed to by a distinct key for this index (partition).

Table 93–35 (Cont.) GET_INDEX_STATS Procedure Parameters

Parameter	Description
<code>clstfct</code>	Clustering factor for the index (partition).
<code>indlevel</code>	Height of the index (partition).
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
<code>guessq</code>	Guess quality for the index (partition).
<code>cachedblk</code>	The average number of blocks in the buffer cache for the segment (index/table/index partition/table partition).
<code>cachehit</code>	The average cache hit ratio for the segment (index/table/index partition/table partition).

Usage Notes

- The Optimizer uses the cached data to estimate number of cached blocks for index or statistics table access. The total cost of the operation will be combined from the I/O cost of reading not cached blocks from disk, the CPU cost of getting cached blocks from the buffer cache, and the CPU cost of processing the data.
- Oracle maintains `cachedblk` and `cachehit` at all times but uses correspondent caching statistics for optimization as part of the table and index statistics only when the user calls `DBMS_STATS.GATHER_[TABLE/INDEX/SCHEMA/DATABASE]_STATS` procedure for auto mode or `DBMS_STATS.GATHER_SYSTEM_STATS` for manual mode. In order to prevent the user from utilizing inaccurate and unreliable data, the optimizer will compute a 'confidence factor' for each `cachehit` and a `cachedblk` for each object. If the 'confidence factor' for the value meets confidence criteria, this value will be used, otherwise the defaults will be used.
- The automatic maintenance algorithm for object caching statistics assumes that there is only one major workload for the system and adjusts statistics to this workload, ignoring other "minor" workloads. If this is not the case, you must use manual mode for maintaining object caching statistics.
- The object caching statistics maintenance algorithm for auto mode prevents you from using statistics in the following situations
 - When not enough data has been analyzed, such as when an object has been recently create

- When the system does not have one major workload resulting in averages not corresponding to real values.

Exceptions

ORA-20000: Object does not exist or insufficient privileges or no statistics have been stored for requested object.

GET_PARAM Function

This function returns the default value of parameters of DBMS_STATS procedures.

Syntax

```
DBMS_STATS.GET_PARAM (  
    pname      IN  VARCHAR2)  
RETURN VARCHAR2;
```

Parameters

Table 93–36 *GET_PARAM Function Parameters*

Parameter	Description
pname	The parameter name.

Exceptions

ORA-20001: Invalid input values

GET_STATS_HISTORY_AVAILABILITY Function

This function returns oldest timestamp where statistics history is available. Users cannot restore statistics to a timestamp older than this one.

Syntax

```
DBMS_STATS.GET_STATS_HISTORY_AVAILABILITY  
RETURN TIMESTAMP WITH TIMEZONE;
```

GET_STATS_HISTORY_RETENTION Function

This function returns the current retention value.

Syntax

```
DBMS_STATS.GET_STATS_HISTORY_RETENTION  
RETURN NUMBER;
```

GET_SYSTEM_STATS Procedure

This procedure gets system statistics from `stattab`, or from the dictionary if `stattab` is `NULL`.

Syntax

```
DBMS_STATS.GET_SYSTEM_STATS (
  status      OUT  VARCHAR2,
  dstart      OUT  DATE,
  dstop       OUT  DATE,
  pname       VARCHAR2,
  pvalue      OUT  NUMBER,
  stattab     IN   VARCHAR2 DEFAULT NULL,
  statid      IN   VARCHAR2 DEFAULT NULL,
  statown     IN   VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–37 *GET_SYSTEM_STATS Procedure Parameters*

Parameter	Description
<code>status</code>	Output is one of the following: COMPLETED: AUTOGATHERING: MANUALGATHERING: BADSTATS:
<code>dstart</code>	Date when statistics gathering started. If <code>status = MANUALGATHERING</code> , the start date is returned.
<code>dstop</code>	Date when statistics gathering stopped. <ul style="list-style-type: none"> ■ If <code>status = COMPLETE</code>, the finish date is returned. ■ If <code>status = AUTOGATHERING</code>, the future finish date is returned. ■ If <code>status = BADSTATS</code>, the must-finished-by date is returned.

Table 93–37 (Cont.) GET_SYSTEM_STATS Procedure Parameters

Parameter	Description
pname	<p>The parameter name to get, which can have one of the following values:</p> <ul style="list-style-type: none"> ■ <code>iotfrspeed</code> - I/O transfer speed in bytes for each millisecond ■ <code>ioseektim</code> - seek time + latency time + operating system overhead time, in milliseconds ■ <code>sreadtim</code> - average time to read single block (random read), in milliseconds ■ <code>mreadtim</code> - average time to read an mbrc block at once (sequential read), in milliseconds ■ <code>cpuspeed</code> - average number of CPU cycles for each second, in millions, captured for the workload (statistics collected using 'INTERVAL' or 'START' and 'STOP' options) ■ <code>cpuspeednw</code> - average number of CPU cycles for each second, in millions, captured for the noworkload (statistics collected using 'NOWORKLOAD' option. ■ <code>mbrc</code> - average multiblock read count for sequential read, in blocks ■ <code>maxthr</code> - maximum I/O system throughput, in bytes/second ■ <code>slavethr</code> - average slave I/O throughput, in bytes/second
pvalue	The parameter value to get.
stattab	Identifier of the user statistics table where the statistics will be obtained. If stattab is null, the statistics will be obtained from the dictionary.
statid	Optional identifier associated with the statistics saved in the stattab.
statown	The schema containing stattab, if different from the user's schema.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20002: Bad user statistics table; may need to be upgraded.

ORA-20003: Unable to gather system statistics.

ORA-20004: Parameter does not exist.

GET_TABLE_STATS Procedure

This procedure gets all table-related information.

Syntax

```
DBMS_STATS.GET_TABLE_STATS (
    ownname          VARCHAR2,
    tabname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    stattab          VARCHAR2 DEFAULT NULL,
    statid           VARCHAR2 DEFAULT NULL,
    numRows          OUT NUMBER,
    numblks          OUT NUMBER,
    avgrlen          OUT NUMBER,
    statown          VARCHAR2 DEFAULT NULL,
    cachedblk       OUT NUMBER,
    cachehit         OUT NUMBER);
```

Parameters

Table 93–38 *GET_TABLE_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
tabname	Name of the table to which this column belongs.
partname	Name of the table partition from which to get the statistics. If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then the statistics are retrieved from the global table level.
stattab	User statistics table identifier describing from where to retrieve the statistics. If <code>stattab</code> is <code>NULL</code> , then the statistics are retrieved directly from the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> (Only pertinent if <code>stattab</code> is not <code>NULL</code>).
numrows	Number of rows in the table (partition).
numblks	Number of blocks the table (partition) occupies.
avgrlen	Average row length for the table (partition).
statown	Schema containing <code>stattab</code> (if different than <code>ownname</code>).

Table 93–38 (Cont.) GET_TABLE_STATS Procedure Parameters

Parameter	Description
cachedblk	
cachehit	

Usage Notes

- The Optimizer uses the cached data to estimate number of cached blocks for index or statistics table access. The total cost of the operation will be combined from the I/O cost of reading not cached blocks from disk, the CPU cost of getting cached blocks from the buffer cache, and the CPU cost of processing the data.
- Oracle maintains `cachedblk` and `cachehit` at all times but uses correspondent caching statistics for optimization as part of the table and index statistics only when the user calls `DBMS_STATS.GATHER_[TABLE/INDEX/SCHEMA/DATABASE]_STATS` procedure for auto mode or `DBMS_STATS.GATHER_SYSTEM_STATS` for manual mode. In order to prevent the user from utilizing inaccurate and unreliable data, the optimizer will compute a 'confidence factor' for each `cachehit` and a `cachedblk` for each object. If the 'confidence factor' for the value meets confidence criteria, this value will be used, otherwise the defaults will be used.
- The automatic maintenance algorithm for object caching statistics assumes that there is only one major workload for the system and adjusts statistics to this workload, ignoring other "minor" workloads. If this is not the case, you must use manual mode for maintaining object caching statistics.
- The object caching statistics maintenance algorithm for auto mode prevents you from using statistics in the following situations
 - When not enough data has been analyzed, such as when an object has been recently create
 - When the system does not have one major workload resulting in averages not corresponding to real values.

Exceptions

ORA-20000: Object does not exist or insufficient privileges or no statistics have been stored for requested object

IMPORT_COLUMN_STATS Procedure

This procedure retrieves statistics for a particular column from the user statistics table identified by `stattab` and stores them in the dictionary.

Syntax

```
DBMS_STATS.IMPORT_COLUMN_STATS (
    ownname          VARCHAR2,
    tabname          VARCHAR2,
    colname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    stattab          VARCHAR2,
    statid           VARCHAR2 DEFAULT NULL,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate   BOOLEAN DEFAULT to_no_invalidate_type (
                                get_param('NO_INVALIDATE')),
    force            BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–39 *IMPORT_COLUMN_STATS Procedure Parameters*

Parameter	Description
<code>ownname</code>	The name of the schema.
<code>tabname</code>	The name of the table to which this column belongs.
<code>colname</code>	The name of the column.
<code>partname</code>	The name of the table partition. If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then global and partition column statistics are imported.
<code>stattab</code>	The user statistics table identifier describing from where to retrieve the statistics.
<code>statid</code>	The (optional) identifier to associate with these statistics within <code>stattab</code> .
<code>statown</code>	The schema containing <code>stattab</code> (if different than <code>ownname</code>).

Table 93–39 (Cont.) IMPORT_COLUMN_STATS Procedure Parameters

Parameter	Description
no_invalidate	If set to FALSE, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they expire or are invalidated.) Use DBMS_STATS.AUTO_INVALIDATE to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	If set to TRUE, imports statistics even if statistics are locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

ORA-20005: Object statistics are locked.

IMPORT_DATABASE_STATS Procedure

This procedure retrieves statistics for all objects in the database from the user statistics table(s) and stores them in the dictionary.

Syntax

```
DBMS_STATS.IMPORT_DATABASE_STATS (
    statab          VARCHAR2,
    statid          VARCHAR2 DEFAULT NULL,
    statown         VARCHAR2 DEFAULT NULL,
    no_invalidate  BOOLEAN DEFAULT to_no_invalidate_type(
                                get_param('NO_INVALIDATE')),
    force           BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–40 *IMPORT_DATABASE_STATS Procedure Parameters*

Parameter	Description
statab	User statistics table identifier describing from where to retrieve the statistics.
statid	Identifier (optional) to associate with these statistics within statab.
statown	Schema containing statab. If statown is NULL, then it is assumed that every schema in the database contains a user statistics table with the name statab.
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the objects to which the statistics are being imported. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	Overrides statistics locked at the object (table) level: <ul style="list-style-type: none"> ■ TRUE - Ignores the statistics lock and imports the statistics. ■ FALSE - The statistics will be imported only if they are not locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

IMPORT_DICTIONARY_STATS Procedure

This procedure retrieves statistics for all dictionary schemas ('SYS', 'SYSTEM' and RDBMS component schemas) from the user statistics table and stores them in the dictionary.

Syntax

```
DBMS_STATS.IMPORT_DICTIONARY_STATS (
    statab          VARCHAR2,
    statid          VARCHAR2 DEFAULT NULL,
    statown         VARCHAR2 DEFAULT NULL,
    no_invalidate  BOOLEAN DEFAULT to_no_invalidate_type(
                                get_param('NO_INVALIDATE')),
    force           BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–41 *IMPORT_DICTIONARY_STATS Procedure Parameters*

Parameter	Description
statab	User statistics table identifier describing from where to retrieve the statistics.
statid	The (optional) identifier to associate with these statistics within statab.
statown	The schema containing statab (if different from current schema).
no_invalidate	Do not invalidate the dependent cursors if set to TRUE. Use DBMS_STATS.AUTO_INVALIDATE to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	Overrides statistics locked at the object (table) level: <ul style="list-style-type: none"> ■ TRUE - Ignores the statistics lock and imports the statistics. ■ FALSE - The statistics will be imported only if there is no lock.

Usage Notes

You must have the SYSDBA or both ANALYZE ANY DICTIONARY and ANALYZE ANY system privilege to execute this procedure.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

ORA-20002: Bad user statistics table, may need to upgrade it.

IMPORT_FIXED_OBJECTS_STATS Procedure

This procedure retrieves statistics for fixed tables from the user statistics table(s) and stores them in the dictionary.

Syntax

```
DBMS_STATS.IMPORT_FIXED_OBJECTS_STATS (
  statab          VARCHAR2,
  statid          VARCHAR2 DEFAULT NULL,
  statown        VARCHAR2 DEFAULT NULL,
  no_invalidate  BOOLEAN DEFAULT to_no_invalidate_type(
                                     get_param('NO_INVALIDATE')),
  force          BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–42 *IMPORT_FIXED_OBJECTS_STATS Procedure Parameters*

Parameter	Description
statab	User statistics table identifier describing from where to retrieve the statistics.
statid	Identifier (optional) to associate with these statistics within statab.
statown	Schema containing statab. If statown is NULL, then it is assumed that every schema in the database contains a user statistics table with the name statab.
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the objects to which the statistics are being imported. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	Overrides statistics lock: <ul style="list-style-type: none"> ■ TRUE - Ignores the statistics lock and imports the statistics ■ FALSE - The statistics will be imported only if there is no lock

Usage Notes

You must have the `SYSDBA` or `ANALYZE ANY DICTIONARY` system privilege to execute this procedure.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

ORA-20002: Bad user statistics table, may need to upgrade it.

IMPORT_INDEX_STATS Procedure

This procedure retrieves statistics for a particular index from the user statistics table identified by `stattab` and stores them in the dictionary.

Syntax

```
DBMS_STATS.IMPORT_INDEX_STATS (
    ownname          VARCHAR2,
    indname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    stattab          VARCHAR2,
    statid           VARCHAR2 DEFAULT NULL,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate    BOOLEAN DEFAULT to_no_invalidate_type(
                                get_param('NO_INVALIDATE')),
    force            BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–43 *IMPORT_INDEX_STATS Procedure Parameters*

Parameter	Description
<code>ownname</code>	Name of the schema.
<code>indname</code>	Name of the index.
<code>partname</code>	Name of the index partition. If the index is partitioned and if <code>partname</code> is <code>NULL</code> , then global and partition index statistics are imported.
<code>stattab</code>	User statistics table identifier describing from where to retrieve the statistics.
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code> .
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
<code>no_invalidate</code>	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> . to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .

Table 93–43 (Cont.) IMPORT_INDEX_STATS Procedure Parameters

Parameter	Description
<code>force</code>	Imports statistics even if index statistics are locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

ORA-20005: Object statistics are locked.

IMPORT_SCHEMA_STATS Procedure

This procedure retrieves statistics for all objects in the schema identified by `ownname` from the user statistics table and stores them in the dictionary.

Syntax

```
DBMS_STATS.IMPORT_SCHEMA_STATS (
    ownname          VARCHAR2,
    stattab          VARCHAR2,
    statid           VARCHAR2 DEFAULT NULL,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate    BOOLEAN DEFAULT to_no_invalidate_type(
                    get_param('NO_INVALIDATE')),
    force            BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–44 *IMPORT_SCHEMA_STATS Procedure Parameters*

Parameter	Description
<code>ownname</code>	Name of the schema.
<code>stattab</code>	User statistics table identifier describing from where to retrieve the statistics.
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code> .
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
<code>no_invalidate</code>	If set to the default, does not invalidate the shared cursors dependent on the objects to which the statistics are being imported. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
<code>force</code>	Overrides statistics locked at the object (table) level: <ul style="list-style-type: none"> ■ TRUE - Ignores the statistics lock and imports the statistics. ■ FALSE - The statistics will be imported only if there is no lock.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

IMPORT_SYSTEM_STATS Procedure

This procedure retrieves system statistics from the user statistics table, identified by `stattab`, and stores the statistics in the dictionary.

Syntax

```
DBMS_STATS.IMPORT_SYSTEM_STATS (  
    stattab      VARCHAR2,  
    statid       VARCHAR2 DEFAULT NULL,  
    statown      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–45 *IMPORT_SYSTEM_STATS Procedure Parameters*

Parameter	Description
<code>stattab</code>	Identifier of the user statistics table where the statistics will be retrieved.
<code>statid</code>	Optional identifier associated with the statistics retrieved from the <code>stattab</code> .
<code>statown</code>	The schema containing <code>stattab</code> , if different from the user's schema.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

ORA-20002: Bad user statistics table; may need to be upgraded.

ORA-20003: Unable to import system statistics.

IMPORT_TABLE_STATS Procedure

This procedure retrieves statistics for a particular table from the user statistics table identified by `stattab` and stores them in the dictionary. Cascade results in all index and column statistics associated with the specified table being imported as well.

Syntax

```
DBMS_STATS.IMPORT_TABLE_STATS (
    ownname          VARCHAR2,
    tabname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    stattab          VARCHAR2,
    statid           VARCHAR2 DEFAULT NULL,
    cascade          BOOLEAN  DEFAULT TRUE,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate   BOOLEAN  DEFAULT to_no_invalidate_type(
                                get_param('NO_INVALIDATE')),
    force            BOOLEAN  DEFAULT FALSE);
```

Parameters

Table 93–46 *IMPORT_TABLE_STATS Procedure Parameters*

Parameter	Description
<code>ownname</code>	Name of the schema.
<code>tabname</code>	Name of the table.
<code>partname</code>	Name of the table partition. If the table is partitioned and if <code>partname</code> is <code>NULL</code> , then global and partition table statistics are imported.
<code>stattab</code>	User statistics table identifier describing from where to retrieve the statistics.
<code>statid</code>	Identifier (optional) to associate with these statistics within <code>stattab</code> .
<code>cascade</code>	If true, then column and index statistics for this table are also imported.
<code>statown</code>	Schema containing <code>stattab</code> (if different than <code>ownname</code>).

Table 93–46 (Cont.) IMPORT_TABLE_STATS Procedure Parameters

Parameter	Description
<code>no_invalidate</code>	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
<code>force</code>	Imports statistics even if table statistics are locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values in the user statistics table.

LOCK_SCHEMA_STATS Procedure

This procedure locks the statistics of all tables of a schema.

Syntax

```
DBMS_STATS.LOCK_SCHEMA_STATS (  
    ownname    VARCHAR2);
```

Parameters

Table 93–47 LOCK_SCHEMA_STATS Procedure Parameters

Parameter	Description
ownname	The name of the schema to lock.

Usage Notes

See "Usage Notes" for [LOCK_TABLE_STATS Procedure](#).

LOCK_TABLE_STATS Procedure

This procedure locks the statistics on the table.

Syntax

```
DBMS_STATS.LOCK_TABLE_STATS (  
    ownname    VARCHAR2,  
    tabname    VARCHAR2);
```

Parameters

Table 93–48 LOCK_TABLE_STATS Procedure Parameters

Parameter	Description
ownname	The name of the schema.
tabname	The name of the table.

Usage Notes

- When statistics on a table are locked, all the statistics depending on the table, including table statistics, column statistics, histograms and statistics on all dependent indexes, are considered to be locked.
- The SET_*, DELETE_*, IMPORT_*, GATHER_* procedures that modify statistics in the dictionary of an individual table, index or column will raise an error if statistics of the object is locked.
- Procedures that operates on multiple objects (such as GATHER_SCHEMA_STATS) will skip modifying the statistics of an object if it is locked. Many procedures have force argument to override the lock.
- This procedure either freezes the current set of the statistics keeps the statistics empty (uncollected) to use Dynamic Sampling.
- The locked or unlocked state is not exported along with the table statistics when using EXPORT_*_STATS procedures.

PREPARE_COLUMN_VALUES Procedures

These procedures convert user-specified minimum, maximum, and histogram endpoint datatype-specific values into Oracle's internal representation for future storage using SET_COLUMN_STATS.

Syntax

```
DBMS_STATS.PREPARE_COLUMN_VALUES (
  srec      IN OUT StatRec,
  charvals  CHARARRAY);
```

```
DBMS_STATS.PREPARE_COLUMN_VALUES (
  srec      IN OUT StatRec,
  datevals  DATEARRAY);
```

```
DBMS_STATS.PREPARE_COLUMN_VALUES (
  srec      IN OUT StatRec,
  dblvals   DBLARRAY);
```

```
DBMS_STATS.PREPARE_COLUMN_VALUES (
  srec      IN OUT StatRec,
  fltvals   FLTARRAY);
```

```
DBMS_STATS.PREPARE_COLUMN_VALUES (
  srec      IN OUT StatRec,
  numvals   NUMARRAY);
```

```
DBMS_STATS.PREPARE_COLUMN_VALUES (
  srec      IN OUT StatRec,
  rawvals   RAWARRAY);
```

Pragmas

```
pragma restrict_references(prepare_column_values, WNDS, RNDS, WNPS, RNPS);
pragma restrict_references(prepare_column_values_nvarchar, WNDS, RNDS, WNPS,
RNPS);
pragma restrict_references(prepare_column_values_rowid, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 93–49 *PREPARE_COLUMN_VALUES Procedure Parameters*

Parameter	Description
<code>srec.epc</code>	<p>Number of values specified in <code>charvals</code>, <code>datevals</code>, <code>dblvals</code>, <code>fltvals</code>, <code>numvals</code>, or <code>rawvals</code>. This value must be between 2 and 256, inclusive, and it should be set to 2 for procedures which do not allow histogram information (<code>nvarchar</code> and <code>rowid</code>).</p> <p>The first corresponding array entry should hold the minimum value for the column, and the last entry should hold the maximum. If there are more than two entries, then all the others hold the remaining height-balanced or frequency histogram endpoint values (with in-between values ordered from next-smallest to next-largest). This value may be adjusted to account for compression, so the returned value should be left as is for a call to <code>SET_COLUMN_STATS</code>.</p>
<code>srec.bkvals</code>	<p>If you want a frequency distribution, then this array contains the number of occurrences of each distinct value specified in <code>charvals</code>, <code>datevals</code>, <code>dblvals</code>, <code>fltvals</code>, <code>numvals</code>, or <code>rawvals</code>. Otherwise, it is merely an output parameter, and it must be set to <code>NULL</code> when this procedure is called.</p>

Datatype-specific input parameters (use one) are shown in [Table 93–50](#).

Table 93–50 *Datatype-Specific Input Parameters*

Type	Description
<code>charvals</code>	The array of values when the column type is character-based. Up to the first 32 bytes of each string should be provided. Arrays must have between 2 and 256 entries, inclusive. If the datatype is fixed <code>CHAR</code> , the strings must be space-padded to 15 characters for correct normalization.
<code>datevals</code>	The array of values when the column type is date-based.
<code>dblvals</code>	The array of values when the column type is double-based.
<code>fltvals</code>	The array of values when the column type is float-based.
<code>numvals</code>	The array of values when the column type is numeric-based.

Table 93–50 (Cont.) Datatype-Specific Input Parameters

Type	Description
<code>rawvals</code>	The array of values when the column type is RAW. Up to the first 32 bytes of each strings should be provided.
<code>nvmin, nvmax</code>	The minimum and maximum values when the column type is national character set based. No histogram information can be provided for a column of this type. If the datatype is fixed CHAR, the strings must be space-padded to 15 characters for correct normalization.
<code>rwmin, rwmax</code>	The minimum and maximum values when the column type is rowid. No histogram information is provided for a column of this type.

Output Parameters

Table 93–51 PREPARE_COLUMN_VALUES Procedure Output Parameters

Parameter	Description
<code>srec.minval</code>	Internal representation of the minimum suitable for use in a call to SET_COLUMN_STATS.
<code>srec.maxval</code>	Internal representation of the maximum suitable for use in a call to SET_COLUMN_STATS.
<code>srec.bkvals</code>	Array suitable for use in a call to SET_COLUMN_STATS.
<code>srec.novals</code>	Array suitable for use in a call to SET_COLUMN_STATS.

Exceptions

ORA-20001: Invalid or inconsistent input values.

PREPARE_COLUMN_VALUES_NVARCHAR2 Procedure

This procedure converts user-specified minimum, maximum, and histogram endpoint datatype-specific values into Oracle's internal representation for future storage using `SET_COLUMN_STATS`.

Syntax

```
DBMS_STATS.PREPARE_COLUMN_VALUES_NVARCHAR2 (
    srec      IN OUT StatRec,
    nvmin     NVARCHAR2,
    nvmax     NVARCHAR2);
```

Pragmas

```
pragma restrict_references(prepare_column_values_nvarchar, WNDS, RNDS, WNPS,
RNPS);
```

Parameters

Table 93–52 *PREPARE_COLUMN_VALUES_NVARCHAR2 Procedure Parameters*

Parameter	Description
<code>srec.epc</code>	<p>Number of values specified in <code>charvals</code>, <code>datevals</code>, <code>dblvals</code>, <code>fltvals</code>, <code>numvals</code>, or <code>rawvals</code>. This value must be between 2 and 256, inclusive, and it should be set to 2 for procedures which do not allow histogram information (<code>nvarchar</code> and <code>rowid</code>).</p> <p>The first corresponding array entry should hold the minimum value for the column, and the last entry should hold the maximum. If there are more than two entries, then all the others hold the remaining height-balanced or frequency histogram endpoint values (with in-between values ordered from next-smallest to next-largest). This value may be adjusted to account for compression, so the returned value should be left as is for a call to <code>SET_COLUMN_STATS</code>.</p>
<code>srec.bkvals</code>	<p>If you want a frequency distribution, then this array contains the number of occurrences of each distinct value specified in <code>charvals</code>, <code>datevals</code>, <code>dblvals</code>, <code>fltvals</code>, <code>numvals</code>, or <code>rawvals</code>. Otherwise, it is merely an output parameter, and it must be set to <code>NULL</code> when this procedure is called.</p>

Datatype-specific input parameters (use one) are shown in [Table 93–50](#).

Table 93–53 Datatype-Specific Input Parameters

Type	Description
<code>nvmin, nvmax</code>	The minimum and maximum values when the column type is national character set based. No histogram information can be provided for a column of this type. If the datatype is fixed <code>CHAR</code> , the strings must be space-padded to 15 characters for correct normalization.

Output Parameters

Table 93–54 PREPARE_COLUMN_VALUES Procedure Output Parameters

Parameter	Description
<code>srec.minval</code>	Internal representation of the minimum suitable for use in a call to <code>SET_COLUMN_STATS</code> .
<code>srec.maxval</code>	Internal representation of the maximum suitable for use in a call to <code>SET_COLUMN_STATS</code> .
<code>srec.bkvals</code>	Array suitable for use in a call to <code>SET_COLUMN_STATS</code> .
<code>srec.novals</code>	Array suitable for use in a call to <code>SET_COLUMN_STATS</code> .

Exceptions

ORA-20001: Invalid or inconsistent input values.

PREPARE_COLUMN_VALUES_ROWID Procedure

This procedure converts user-specified minimum, maximum, and histogram endpoint datatype-specific values into Oracle's internal representation for future storage using `SET_COLUMN_STATS`.

Syntax

```
DBMS_STATS.PREPARE_COLUMN_VALUES_ROWID (
    srec  IN OUT StatRec,
    rwmn      ROWID,
    rwmax      ROWID);
```

Pragmas

```
pragma restrict_references(prepare_column_values_rowid, WNDS, RNDS, WNPS, RNPS);
```

Parameters

Table 93–55 *PREPARE_COLUMN_VALUES_ROWID Procedure Parameters*

Parameter	Description
<code>srec.epc</code>	<p>Number of values specified in <code>charvals</code>, <code>datevals</code>, <code>dblvals</code>, <code>fltvals</code>, <code>numvals</code>, or <code>rawvals</code>. This value must be between 2 and 256, inclusive, and it should be set to 2 for procedures which do not allow histogram information (<code>nvarchar</code> and <code>rowid</code>).</p> <p>The first corresponding array entry should hold the minimum value for the column, and the last entry should hold the maximum. If there are more than two entries, then all the others hold the remaining height-balanced or frequency histogram endpoint values (with in-between values ordered from next-smallest to next-largest). This value may be adjusted to account for compression, so the returned value should be left as is for a call to <code>SET_COLUMN_STATS</code>.</p>
<code>srec.bkvals</code>	<p>If you want a frequency distribution, then this array contains the number of occurrences of each distinct value specified in <code>charvals</code>, <code>datevals</code>, <code>dblvals</code>, <code>fltvals</code>, <code>numvals</code>, or <code>rawvals</code>. Otherwise, it is merely an output parameter, and it must be set to <code>NULL</code> when this procedure is called.</p>

Datatype-specific input parameters (use one) are shown in [Table 93–50](#).

Table 93–56 Datatype-Specific Input Parameters

Type	Description
<code>rwmin, rwmax</code>	The minimum and maximum values when the column type is <code>rowid</code> . No histogram information is provided for a column of this type.

Output Parameters

Table 93–57 PREPARE_COLUMN_VALUES Procedure Output Parameters

Parameter	Description
<code>srec.minval</code>	Internal representation of the minimum suitable for use in a call to <code>SET_COLUMN_STATS</code> .
<code>srec.maxval</code>	Internal representation of the maximum suitable for use in a call to <code>SET_COLUMN_STATS</code> .
<code>srec.bkvals</code>	Array suitable for use in a call to <code>SET_COLUMN_STATS</code> .
<code>srec.novals</code>	Array suitable for use in a call to <code>SET_COLUMN_STATS</code> .

Exceptions

ORA-20001: Invalid or inconsistent input values.

PURGE_STATS Procedure

This procedure purges old versions of statistics saved in the dictionary. To run this procedure, you must have the SYSDBA or both ANALYZE ANY DICTIONARY and ANALYZE ANY system privilege.

Syntax

```
DBMS_STATS.PURGE_STATS(  
    before_timestamp          TIMESTAMP WITH TIME ZONE);
```

Parameters

Table 93–58 *PURGE_STATS Procedure Parameters*

Parameter	Description
before_timestamp	Versions of statistics saved before this timestamp are purged. If NULL, it uses the purging policy used by automatic purge. The automatic purge deletes all history older than the older of (current time - statistics history retention) and (time of recent analyze in the system - 1). The statistics history retention value can be changed using ALTER_STATS_HISTORY_RETENTION Procedure. The default is 31 days.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values.

RESTORE_DATABASE_STATS Procedure

This procedure restores statistics of all tables of the database as of a specified timestamp (`as_of_timestamp`).

Syntax

```
DBMS_STATS.RESTORE_DATABASE_STATS(
  as_of_timestamp    TIMESTAMP WITH TIME ZONE,
  force              BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–59 *RESTORE_DATABASE_STATS Procedure Parameters*

Parameter	Description
<code>as_of_timestamp</code>	The timestamp to which to restore statistics.
<code>force</code>	Restores statistics even if their statistics are locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values.

ORA-20006: Unable to restore statistics, statistics history not available.

RESTORE_DICTIONARY_STATS Procedure

This procedure restores statistics of all dictionary tables (tables of 'SYS', 'SYSTEM' and RDBMS component schemas) as of a specified timestamp (`as_of_timestamp`).

Syntax

```
DBMS_STATS.RESTORE_DICTIONARY_STATS(  
    as_of_timestamp    TIMESTAMP WITH TIME ZONE,  
    force              BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–60 *RESTORE_DICTIONARY_STATS Procedure Parameters*

Parameter	Description
<code>as_of_timestamp</code>	The timestamp to which to restore statistics.
<code>force</code>	Restores statistics even if their statistics are locked.

Usage Notes

To run this procedure, you must have the SYSDBA or both ANALYZE ANY DICTIONARY and ANALYZE ANY system privilege.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values.

ORA-20006: Unable to restore statistics, statistics history not available.

RESTORE_FIXED_OBJECTS_STATS Procedure

This procedure restores statistics of all fixed tables as of a specified timestamp (`as_of_timestamp`).

Syntax

```
DBMS_STATS.RESTORE_FIXED_OBJECTS_STATS(
  as_of_timestamp    TIMESTAMP WITH TIME ZONE,
  force              BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–61 *RESTORE_FIXED_OBJECTS_STATS Procedure Parameters*

Parameter	Description
<code>as_of_timestamp</code>	The timestamp to which to restore statistics.
<code>force</code>	Restores statistics even if their statistics are locked.

Usage Notes

To run this procedure, you must have the `SYSDBA` or `ANALYZE ANY DICTIONARY` system privilege.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values.

ORA-20006: Unable to restore statistics, statistics history not available.

RESTORE_SCHEMA_STATS Procedure

This procedure restores statistics of all tables of a schema as of a specified timestamp (`as_of_timestamp`).

Syntax

```
DBMS_STATS.RESTORE_SCHEMA_STATS(  
    ownname          VARCHAR2,  
    as_of_timestamp  TIMESTAMP WITH TIME ZONE,  
    force            BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93-62 *RESTORE_SCHEMA_STATS Procedure Parameters*

Parameter	Description
<code>ownname</code>	The schema of the tables for which the statistics are to be restored.
<code>as_of_timestamp</code>	The timestamp to which to restore statistics.
<code>force</code>	Restores statistics even if their statistics are locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values.

ORA-20006: Unable to restore statistics, statistics history not available.

RESTORE_SYSTEM_STATS Procedure

This procedure restores system statistics as of a specified timestamp (`as_of_timestamp`).

Syntax

```
DBMS_STATS.RESTORE_SCHEMA_STATS(  
    as_of_timestamp          TIMESTAMP WITH TIME ZONE);
```

Parameters

Table 93–63 *RESTORE_SYSTEM_STATS Procedure Parameters*

Parameter	Description
<code>as_of_timestamp</code>	The timestamp to which to restore statistics.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values.

ORA-20006: Unable to restore statistics, statistics history not available.

RESTORE_TABLE_STATS Procedure

This procedure restores statistics of a table as of a specified timestamp (`as_of_timestamp`). The procedure will restore statistics of associated indexes and columns as well. If the table statistics were locked at the specified timestamp the procedure will lock the statistics. The procedure will not restore user defined statistics.

Syntax

```
DBMS_STATS.RESTORE_TABLE_STATS (  
    ownname          VARCHAR2,  
    tabname          VARCHAR2,  
    as_of_timestamp  TIMESTAMP WITH TIME ZONE,  
    restore_cluster_index  BOOLEAN DEFAULT FALSE,  
    force            BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–64 *RESTORE_TABLE_STATS Procedure Parameters*

Parameter	Description
<code>ownname</code>	The schema of the table for which the statistics are to be restored.
<code>tabname</code>	The table name.
<code>as_of_timestamp</code>	The timestamp to which to restore statistics.
<code>restore_cluster_index</code>	If the table is part of a cluster, restore statistics of the cluster index if set to <code>TRUE</code> .
<code>force</code>	Restores statistics even if the table statistics are locked. If the table statistics were not locked at the specified timestamp, it unlocks the statistics.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent values.

ORA-20006: Unable to restore statistics, statistics history not available.

SET_COLUMN_STATS Procedures

This procedure sets column-related information. In the version of this procedure that deals with user-defined statistics, the statistics type specified is the type to store in the dictionary, in addition to the actual user-defined statistics. If this statistics type is NULL, the statistics type associated with the index or column is stored.

Syntax

```
DBMS_STATS.SET_COLUMN_STATS (
  ownname          VARCHAR2,
  tabname          VARCHAR2,
  colname          VARCHAR2,
  partname         VARCHAR2 DEFAULT NULL,
  stattab         VARCHAR2 DEFAULT NULL,
  statid          VARCHAR2 DEFAULT NULL,
  distcnt         NUMBER DEFAULT NULL,
  density         NUMBER DEFAULT NULL,
  nullcnt         NUMBER DEFAULT NULL,
  srec            StatRec DEFAULT NULL,
  avgclen         NUMBER DEFAULT NULL,
  flags           NUMBER DEFAULT NULL,
  statown         VARCHAR2 DEFAULT NULL,
  no_invalidate   BOOLEAN DEFAULT to_no_invalidate_type(
                                     get_param('NO_INVALIDATE')),
  force           BOOLEAN DEFAULT FALSE);
```

Use the following for user-defined statistics:

```
DBMS_STATS.SET_COLUMN_STATS (
  ownname          VARCHAR2,
  tabname          VARCHAR2,
  colname          VARCHAR2,
  partname         VARCHAR2 DEFAULT NULL,
  stattab         VARCHAR2 DEFAULT NULL,
  statid          VARCHAR2 DEFAULT NULL,
  ext_stats        RAW,
  stattypown      VARCHAR2 DEFAULT NULL,
  stattypename    VARCHAR2 DEFAULT NULL,
  statown         VARCHAR2 DEFAULT NULL,
  no_invalidate   BOOLEAN DEFAULT to_no_invalidate_type(
                                     get_param('NO_INVALIDATE')),
  force           BOOLEAN DEFAULT FALSE);
```

Parameters

Table 93–65 SET_COLUMN_STATS Procedure Parameters

Parameter	Description
ownname	Name of the schema.
tabname	Name of the table to which this column belongs.
colname	Name of the column.
partname	Name of the table partition in which to store the statistics. If the table is partitioned and <code>partname</code> is <code>NULL</code> , then the statistics are stored at the global table level.
stattab	User statistics table identifier describing where to store the statistics. If <code>stattab</code> is <code>NULL</code> , then the statistics are stored directly in the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> (Only pertinent if <code>stattab</code> is not <code>NULL</code>).
ext_stats	The user-defined statistics.
stattypown	Schema of the statistics type.
stattypname	Name of the statistics type.
distcnt	Number of distinct values.
density	Column density. If this value is <code>NULL</code> and if <code>distcnt</code> is not <code>NULL</code> , then <code>density</code> is derived from <code>distcnt</code> .
nullcnt	Number of <code>NULL</code> s .
srec	<code>StatRec</code> structure filled in by a call to <code>PREPARE_COLUMN_VALUES</code> or <code>GET_COLUMN_STATS</code> .
avgclen	Average length for the column (in bytes).
flags	For internal Oracle use (should be left as <code>NULL</code>).
statown	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
force	Sets the values even if statistics of the column are locked.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or inconsistent input values.

ORA-20005: Object statistics are locked.

SET_INDEX_STATS Procedures

These procedures set index-related information. In the version of this procedure that deals with user-defined statistics, the statistics type specified is the type to store in the dictionary, in addition to the actual user-defined statistics. If this statistics type is NULL, the statistics type associated with the index or column is stored.

Syntax

```
DBMS_STATS.SET_INDEX_STATS (
    ownname          VARCHAR2,
    indname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    statab           VARCHAR2 DEFAULT NULL,
    statid           VARCHAR2 DEFAULT NULL,
    numrows          NUMBER   DEFAULT NULL,
    numblks         NUMBER   DEFAULT NULL,
    numdist          NUMBER   DEFAULT NULL,
    avglblk          NUMBER   DEFAULT NULL,
    avgdblks        NUMBER   DEFAULT NULL,
    clstfct          NUMBER   DEFAULT NULL,
    indlevel         NUMBER   DEFAULT NULL,
    flags            NUMBER   DEFAULT NULL,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate    BOOLEAN   DEFAULT to_no_invalidate_type(
                                get_param('NO_INVALIDATE')),
    guesssq          NUMBER   DEFAULT NULL,
    cachedblk       NUMBER   DEFAULT NULL,
    cachehit         NUMBER   DEFAULT NULL,
    force            BOOLEAN   DEFAULT FALSE);
```

Use the following for user-defined statistics:

```
DBMS_STATS.SET_INDEX_STATS (
    ownname          VARCHAR2,
    indname          VARCHAR2,
    partname         VARCHAR2 DEFAULT NULL,
    statab           VARCHAR2 DEFAULT NULL,
    statid           VARCHAR2 DEFAULT NULL,
    ext_stats        RAW,
    statypown        VARCHAR2 DEFAULT NULL,
    statypname       VARCHAR2 DEFAULT NULL,
    statown          VARCHAR2 DEFAULT NULL,
    no_invalidate    BOOLEAN DEFAULT to_no_invalidate_type(
```

```

                                get_param('NO_INVALIDATE')),
cachedblk    NUMBER    DEFAULT NULL,
cachehit    NUMBER    DEFAULT NULL,
force       BOOLEAN   DEFAULT FALSE);

```

Parameters

Table 93–66 *SET_INDEX_STATS Procedure Parameters*

Parameter	Description
ownname	Name of the schema.
indname	Name of the index.
partname	Name of the index partition in which to store the statistics. If the index is partitioned and if <code>partname</code> is <code>NULL</code> , then the statistics are stored at the global index level.
stattab	User statistics table identifier describing where to store the statistics. If <code>stattab</code> is <code>NULL</code> , then the statistics are stored directly in the dictionary.
statid	Identifier (optional) to associate with these statistics within <code>stattab</code> (Only pertinent if <code>stattab</code> is not <code>NULL</code>).
ext_stats	The user-defined statistics.
stattypown	Schema of the statistics type.
stattypname	Name of the statistics type.
numrows	Number of rows in the index (partition).
numlblks	Number of leaf blocks in the index (partition).
numdist	Number of distinct keys in the index (partition).
avglblk	Average integral number of leaf blocks in which each distinct key appears for this index (partition). If not provided, then this value is derived from <code>numlblks</code> and <code>numdist</code> .
avgdblk	Average integral number of data blocks in the table pointed to by a distinct key for this index (partition). If not provided, then this value is derived from <code>clstfct</code> and <code>numdist</code> .
clstfct	See <code>clustering_factor</code> column of the <code>all_indexes</code> view for a description.
indlevel	Height of the index (partition).
flags	For internal Oracle use (should be left as <code>NULL</code>).

Table 93–66 (Cont.) SET_INDEX_STATS Procedure Parameters

Parameter	Description
statown	Schema containing statab (if different than ownname).
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
guessq	Guess quality. See the <code>pct_direct_access</code> column of the <code>all_indexes</code> view for a description.
cachedblk	The average number of blocks in the buffer cache for the segment (index/table/index partition/table partition).
cachehit	The average cache hit ratio for the segment (index/table/index partition/table partition).
force	Sets the values even if statistics of the index are locked.

Usage Notes

- The Optimizer uses the cached data to estimate number of cached blocks for index or statistics table access. The total cost of the operation will be combined from the I/O cost of reading not cached blocks from disk, the CPU cost of getting cached blocks from the buffer cache, and the CPU cost of processing the data.
- Oracle maintains `cachedblk` and `cachehit` at all times but uses correspondent caching statistics for optimization as part of the table and index statistics only when the user calls `DBMS_STATS.GATHER_[TABLE/INDEX/SCHEMA/DATABASE]_STATS` procedure for auto mode or `DBMS_STATS.GATHER_SYSTEM_STATS` for manual mode. In order to prevent the user from utilizing inaccurate and unreliable data, the optimizer will compute a 'confidence factor' for each `cachehit` and a `cachedblk` for each object. If the 'confidence factor' for the value meets confidence criteria, this value will be used, otherwise the defaults will be used.
- The automatic maintenance algorithm for object caching statistics assumes that there is only one major workload for the system and adjusts statistics to this workload, ignoring other "minor" workloads. If this is not the case, you must use manual mode for maintaining object caching statistics.

- The object caching statistics maintenance algorithm for auto mode prevents you from using statistics in the following situations
 - When not enough data has been analyzed, such as when an object has been recently create
 - When the system does not have one major workload resulting in averages not corresponding to real values.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid input value.

ORA-20005: Object statistics are locked.

SET_PARAM Procedure

This procedure sets default values for parameters of DBMS_STATS procedures. You can use the GET_PARAM Function to get the current default value of a parameter.

Syntax

```
DBMS_STATS.SET_PARAM (  
    pname      IN    VARCHAR2,  
    pval       IN    VARCHAR2);
```

Parameters

Table 93–67 SET_PARAM Procedure Parameters

Parameter	Description
pname	The parameter name The default value for following parameters can be set. <ul style="list-style-type: none">■ CASCADE - The default value for CASCADE set by SET_PARAM is not used by export/import procedures.It is used only by gather procedures.■ DEGREE■ ESTIMATE_PERCENT■ METHOD_OPT■ NO_INVALIDATE
pval	The parameter value. If NULL is specified, it will set the oracle default value.

Usage Notes

To run this procedure, you must have the SYSDBA or both the ANALYZE ANY DICTIONARY and ANALYZE ANY system privileges.

Note that both arguments are of type VARCHAR2 and the values need to be enclosed in quotes.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid or illegal input value.

Examples

```
dbms_stats.set_param('CASCADE', 'DBMS_STATS.AUTO_CASCADE');  
dbms_stats.set_param('ESTIMATE_PERCENT', '5');  
dbms_stats.set_param('DEGREE', 'NULL');
```

SET_SYSTEM_STATS Procedure

This procedure sets systems statistics.

Syntax

```
DBMS_STATS.SET_SYSTEM_STATS (
  pname          VARCHAR2,
  pvalue         NUMBER,
  stattab       IN   VARCHAR2 DEFAULT NULL,
  statid        IN   VARCHAR2 DEFAULT NULL,
  statown       IN   VARCHAR2 DEFAULT NULL);
```

Parameters

Table 93–68 SET_SYSTEM_STATS Procedure Parameters

Parameter	Description
pname	<p>The parameter name to get, which can have one of the following values:</p> <ul style="list-style-type: none"> ■ <code>iotfrspeed</code>—I/O transfer speed in bytes for each millisecond ■ <code>ioseektim</code> - seek time + latency time + operating system overhead time, in milliseconds ■ <code>sreadtim</code> - average time to read single block (random read), in milliseconds ■ <code>mreadtim</code> - average time to read an mbrc block at once (sequential read), in milliseconds ■ <code>cpuspeed</code> - average number of CPU cycles for each second, in millions, captured for the workload (statistics collected using 'INTERVAL' or 'START' and 'STOP' options) ■ <code>cpuspeednw</code> - average number of CPU cycles for each second, in millions, captured for the noworkload (statistics collected using 'NOWORKLOAD' option. ■ <code>mbrc</code> - average multiblock read count for sequential read, in blocks ■ <code>maxthr</code> - maximum I/O system throughput, in bytes/second ■ <code>slavethr</code> - average slave I/O throughput, in bytes/second

Table 93–68 (Cont.) SET_SYSTEM_STATS Procedure Parameters

Parameter	Description
pvalue	Parameter value to get.
stattab	Identifier of the user statistics table where the statistics will be obtained. If stattab is null, the statistics will be obtained from the dictionary.
statid	Optional identifier associated with the statistics saved in the stattab.
statown	The schema containing stattab, if different from the user's schema.
cachedblk	The average number of blocks in the buffer cache for the segment (index/table/index partition/table partition).
cachehit	The average cache hit ratio for the segment (index/table/index partition/table partition).

Usage Notes

- The Optimizer uses the cached data to estimate number of cached blocks for index or statistics table access. The total cost of the operation will be combined from the I/O cost of reading not cached blocks from disk, the CPU cost of getting cached blocks from the buffer cache, and the CPU cost of processing the data.
- Oracle maintains `cachedblk` and `cachehit` at all times but uses correspondent caching statistics for optimization as part of the table and index statistics only when the user calls `DBMS_STATS.GATHER_[TABLE/INDEX/SCHEMA/DATABASE]_STATS` procedure for auto mode or `DBMS_STATS.GATHER_SYSTEM_STATS` for manual mode. In order to prevent the user from utilizing inaccurate and unreliable data, the optimizer will compute a 'confidence factor' for each `cachehit` and a `cachedblk` for each object. If the 'confidence factor' for the value meets confidence criteria, this value will be used, otherwise the defaults will be used.
- The automatic maintenance algorithm for object caching statistics assumes that there is only one major workload for the system and adjusts statistics to this workload, ignoring other "minor" workloads. If this is not the case, you must use manual mode for maintaining object caching statistics.
- The object caching statistics maintenance algorithm for auto mode prevents you from using statistics in the following situations

- When not enough data has been analyzed, such as when an object has been recently create
- When the system does not have one major workload resulting in averages not corresponding to real values.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid input value.

ORA-20002: Bad user statistics table; may need to be upgraded.

ORA-20003: Unable to set system statistics.

ORA-20004: Parameter does not exist.

SET_TABLE_STATS Procedure

This procedure sets table-related information.

Syntax

```
DBMS_STATS.SET_TABLE_STATS (
  ownname          VARCHAR2,
  tabname          VARCHAR2,
  partname         VARCHAR2 DEFAULT NULL,
  stattab          VARCHAR2 DEFAULT NULL,
  statid           VARCHAR2 DEFAULT NULL,
  numrows         NUMBER   DEFAULT NULL,
  numblks         NUMBER   DEFAULT NULL,
  avgrlen         NUMBER   DEFAULT NULL,
  flags           NUMBER   DEFAULT NULL,
  statown         VARCHAR2 DEFAULT NULL,
  no_invalidate   BOOLEAN   DEFAULT to_no_invalidate_type (
                                get_param('NO_INVALIDATE')),
  cachedblk       NUMBER   DEFAULT NULL,
  cachehit        NUMBER   DEFAULT NULL,
  force           BOOLEAN   DEFAULT FALSE);
```

Parameters

Table 93–69 SET_TABLE_STATS Procedure Parameters

Parameter	Description
ownname	Name of the schema.
tabname	Name of the table.
partname	Name of the table partition in which to store the statistics. If the table is partitioned and partname is NULL, then the statistics are stored at the global table level.
stattab	User statistics table identifier describing where to store the statistics. If stattab is NULL, then the statistics are stored directly in the dictionary.
statid	Identifier (optional) to associate with these statistics within stattab (Only pertinent if stattab is not NULL).
numrows	Number of rows in the table (partition).
numblks	Number of blocks the table (partition) occupies.

Table 93–69 (Cont.) SET_TABLE_STATS Procedure Parameters

Parameter	Description
avgrlen	Average row length for the table (partition).
flags	For internal Oracle use (should be left as NULL).
statown	Schema containing <code>stattab</code> (if different than <code>ownname</code>).
no_invalidate	If set to the default, does not invalidate the shared cursors dependent on the table. (The statements corresponding to those cursors are not recompiled until they are gone or invalidated.) Use <code>DBMS_STATS.AUTO_INVALIDATE</code> to have Oracle decide when to invalidate dependent cursors. This is the default. The default can be changed using the SET_PARAM Procedure .
cachedblk	The average number of blocks in the buffer cache for the segment (index/table/index partition/table partition).
cachehit	The average cache hit ratio for the segment (index/table/index partition/table partition).
force	Sets the values even if statistics of the table are locked.

Usage Notes

- The Optimizer uses the cached data to estimate number of cached blocks for index or statistics table access. The total cost of the operation will be combined from the I/O cost of reading not cached blocks from disk, the CPU cost of getting cached blocks from the buffer cache, and the CPU cost of processing the data.
- Oracle maintains `cachedblk` and `cachehit` at all times but uses correspondent caching statistics for optimization as part of the table and index statistics only when the user calls `DBMS_STATS.GATHER_[TABLE/INDEX/SCHEMA/DATABASE]_STATS` procedure for auto mode or `DBMS_STATS.GATHER_SYSTEM_STATS` for manual mode. In order to prevent the user from utilizing inaccurate and unreliable data, the optimizer will compute a 'confidence factor' for each `cachehit` and a `cachedblk` for each object. If the 'confidence factor' for the value meets confidence criteria, this value will be used, otherwise the defaults will be used.
- The automatic maintenance algorithm for object caching statistics assumes that there is only one major workload for the system and adjusts statistics to this workload, ignoring other "minor" workloads. If this is not the case, you must use manual mode for maintaining object caching statistics.

- The object caching statistics maintenance algorithm for auto mode prevents you from using statistics in the following situations
 - When not enough data has been analyzed, such as when an object has been recently create
 - When the system does not have one major workload resulting in averages not corresponding to real values.

Exceptions

ORA-20000: Object does not exist or insufficient privileges.

ORA-20001: Invalid input value.

ORA-20005: Object statistics are locked.

UNLOCK_SCHEMA_STATS Procedure

This procedure unlocks the statistics on all the tables in schema.

Syntax

```
DBMS_STATS.UNLOCK_SCHEMA_STATS (  
    ownname    VARCHAR2);
```

Parameters

Table 93–70 UNLOCK_SCHEMA_STATS Procedure Parameters

Parameter	Description
ownname	The name of the schema.

Usage Notes

- When statistics on a table is locked, all the statistics depending on the table, including table statistics, column statistics, histograms and statistics on all dependent indexes, are considered to be locked.
- The `SET_*`, `DELETE_*`, `IMPORT_*`, `GATHER_*` procedures that modify statistics in the dictionary of an individual table, index or column will raise an error if statistics of the object is locked.
- Procedures that operates on multiple objects (such as `GATHER_SCHEMA_STATS`) will skip modifying the statistics of an object if it is locked. Many procedures have force argument to override the lock.

UNLOCK_TABLE_STATS Procedure

This procedure unlocks the statistics on the table.

Syntax

```
DBMS_STATS.UNLOCK_TABLE_STATS (
    ownname    VARCHAR2,
    tabname    VARCHAR2);
```

Parameters

Table 93–71 UNLOCK_TABLE_STATS Procedure Parameters

Parameter	Description
ownname	The name of the schema.
tabname	The name of the table.

Usage Notes

- When statistics on a table is locked, all the statistics depending on the table, including table statistics, column statistics, histograms and statistics on all dependent indexes, are considered to be locked.
- The SET_*, DELETE_*, IMPORT_*, GATHER_* procedures that modify statistics in the dictionary of an individual table, index or column will raise an error if statistics of the object is locked.
- Procedures that operates on multiple objects (such as GATHER_SCHEMA_STATS) will skip modifying the statistics of an object if it is locked. Many procedures have force argument to override the lock.

UPGRADE_STAT_TABLE Procedure

This procedure upgrades a user statistics table from an older version.

Syntax

```
DBMS_STATS.UPGRADE_STAT_TABLE (  
    ownname    VARCHAR2,  
    stattab    VARCHAR2);
```

Parameters

Table 93–72 UPGRADE_STAT_TABLE Procedure Parameters

Parameter	Description
ownname	Name of the schema.
stattab	Name of the table.

Exceptions

ORA-20000: Unable to upgrade table.

DBMS_STORAGE_MAP

With the `DBMS_STORAGE_MAP` package, you can communicate with the Oracle background process `FMON` to invoke mapping operations that populate mapping views. `FMON` communicates with operating and storage system vendor-supplied mapping libraries.

This chapter contains the following topics:

- [Using DBMS_STORAGE_MAP](#)
 - [Overview](#)
 - [Operational Notes](#)
- [Summary of DBMS_STORAGE_MAP Subprograms](#)

Using DBMS_STORAGE_MAP

- [Overview](#)
- [Operational Notes](#)

Overview

The following terminology and descriptions will help you understand the DBMS_STORAGE_MAP API:

- **Mapping libraries**

Mapping libraries help you map the components of I/O processing stack elements. Examples of I/O processing components include files, logical volumes, and storage array I/O targets. The mapping libraries are identified in `filemap.ora`.
- **Mapping files**

A mapping file is a mapping structure that describes a file. It provides a set of attributes, including file size, number of extents that the file is composed of, and file type.
- **Mapping elements and sub-elements**

A mapping element is the abstract mapping structure that describes a storage component within the I/O stack. Examples of elements include mirrors, stripes, partitions, raid5, concatenated elements, and disks—structures that are the mapping building blocks. A mapping sub-element describes the link between an element and the next elements in the I/O mapping stack
- **Mapping file extents**

A mapping file extent describes a contiguous chunk of blocks residing on one element. This includes the device offset, the extent size, the file offset, the type (data or parity), and the name of the element where the extent resides. In the case of a raw device or volume, the file is composed of only one file extent component. A mapping file extent is different from Oracle extents.

See Also:

- *Oracle Database Administrator's Guide* for more information
- *Oracle Database Reference* for V\$MAP views, including V\$MAP_FILE, V\$MAP_ELEMENT, V\$MAP_SUBELEMENT, V\$MAP_FILE_EXTENT

Operational Notes

For MAP_ELEMENT, MAP_FILE, and MAP_ALL: Invoking these functions when mapping information already exists will refresh the mapping if configuration IDs are supported. If configuration IDs are not supported, then invoking these functions again will rebuild the mapping.

See Also: *Oracle Database Administrator's Guide* for a discussion of the configuration ID, an attribute of the element or file that is changed.

Summary of DBMS_STORAGE_MAP Subprograms

Table 94-1 *DBMS_STORAGE_MAP Package Subprograms*

Subprogram	Description
DROP_ALL Function on page 94-5	Drops all mapping information in the shared memory of the instance
DROP_ELEMENT Function on page 94-6	Drops the mapping information for the element defined by <code>elemname</code>
DROP_FILE Function on page 94-7	Drops the file mapping information defined by <code>filename</code>
LOCK_MAP Procedure on page 94-8	Locks the mapping information in the shared memory of the instance
MAP_ALL Function on page 94-9	Builds the entire mapping information for all types of Oracle files (except archive logs), including all directed acyclic graph (DAG) elements
MAP_ELEMENT Function on page 94-10	Builds mapping information for the element identified by <code>elemname</code>
MAP_FILE Function on page 94-11	Builds mapping information for the file identified by <code>filename</code>
MAP_OBJECT Function on page 94-13	Builds the mapping information for the Oracle object identified by the object name, owner, and type
RESTORE Function on page 94-14	Loads the entire mapping information from the data dictionary into the shared memory of the instance
SAVE Function on page 94-15	Saves information needed to regenerate the entire mapping into the data dictionary
UNLOCK_MAP Procedure on page 94-16	Unlocks the mapping information in the shared memory of the instance.

DROP_ALL Function

This function drops all mapping information in the shared memory of the instance.

Syntax

```
DBMS_STORAGE_MAP.DROP_ALL(  
    dictionary_update IN BOOLEAN DEFAULT TRUE);
```

Parameters

Table 94–2 *DROP_ALL Function Parameters*

Parameter	Description
dictionary_update	If TRUE, mapping information in the data dictionary is updated to reflect the changes. The default value is TRUE; dictionary_update is an overloaded argument.

DROP_ELEMENT Function

This function drops the mapping information for the element defined by `elemname`.

Syntax

```
DBMS_STORAGE_MAP.DROP_ELEMENT(  
    elemname          IN VARCHAR2,  
    cascade           IN BOOLEAN,  
    dictionary_update IN BOOLEAN DEFAULT TRUE);
```

Parameters

Table 94–3 *DROP_ELEMENT Function Parameters*

Parameter	Description
<code>elemname</code>	The element for which mapping information is dropped.
<code>cascade</code>	If <code>TRUE</code> , then <code>DROP_ELEMENT</code> is invoked recursively on all elements of the DAG defined by <code>elemname</code> , if possible.
<code>dictionary_update</code>	If <code>TRUE</code> , mapping information in the data dictionary is updated to reflect the changes. The default value is <code>TRUE</code> ; <code>dictionary_update</code> is an overloaded argument.

DROP_FILE Function

This function drops the file mapping information defined by `filename`.

Syntax

```
DBMS_STORAGE_MAP.DROP_FILE(  
    filename          IN VARCHAR2,  
    cascade           IN BOOLEAN,  
    dictionary_update IN BOOLEAN DEFAULT TRUE);
```

Parameters

Table 94–4 *DROP_FILE Function Parameters*

Parameter	Description
<code>filename</code>	The file for which file mapping information is dropped.
<code>cascade</code>	If <code>TRUE</code> , then the mapping DAGs for the elements where the file resides are also dropped, if possible.
<code>dictionary_update</code>	If <code>TRUE</code> , mapping information in the data dictionary is updated to reflect the changes. The default value is <code>TRUE</code> ; <code>dictionary_update</code> is an overloaded argument.

LOCK_MAP Procedure

This procedure locks the mapping information in the shared memory of the instance. This is useful when you need a consistent snapshot of the V\$MAP tables. Without locking the mapping information, V\$MAP_ELEMENT and V\$MAP_SUBELEMENT, for example, may be inconsistent.

Syntax

```
DBMS_STORAGE_MAP.LOCK_MAP;
```

MAP_ALL Function

This function builds the entire mapping information for all types of Oracle files (except archive logs), including all directed acyclic graph (DAG) elements. It obtains the latest mapping information because it explicitly synchronizes all mapping libraries.

Syntax

```
DBMS_STORAGE_MAP.MAP_ALL(
    max_num_fileext    IN NUMBER DEFAULT 100,
    dictionary_update  IN BOOLEAN DEFAULT TRUE);
```

Parameters

Table 94–5 *MAP_ALL Function Parameters*

Parameter	Description
max_num_fileext	Defines the maximum number of file extents to be mapped. This limits the amount of memory used when mapping file extents. The default value is 100; max_num_fileextent is an overloaded argument.
dictionary_update	If TRUE, mapping information in the data dictionary is updated to reflect the changes. The default value is TRUE; dictionary_update is an overloaded argument.

Usage Notes

You must explicitly call MAP_ALL in a cold startup scenario.

MAP_ELEMENT Function

This function builds mapping information for the element identified by `elemname`. It may not obtain the latest mapping information if the element being mapped, or any one of the elements within its I/O stack (if `cascade` is `TRUE`), is owned by a library that must be explicitly synchronized.

Syntax

```
DBMS_STORAGE_MAP.MAP_ELEMENT(  
    elemname          IN VARCHAR2,  
    cascade           IN BOOLEAN,  
    dictionary_update IN BOOLEAN DEFAULT TRUE);
```

Parameters

Table 94–6 MAP_ELEMENT Function Parameters

Parameter	Description
<code>elemname</code>	The element for which mapping information is built.
<code>cascade</code>	If <code>TRUE</code> , all elements within the <code>elemname</code> I/O stack DAG are mapped.
<code>dictionary_update</code>	If <code>TRUE</code> , mapping information in the data dictionary is updated to reflect the changes. The default value is <code>TRUE</code> ; <code>dictionary_update</code> is an overloaded argument.

MAP_FILE Function

This function builds mapping information for the file identified by `filename`. Use this function if the mapping of one particular file has changed. The Oracle database server does not have to rebuild the entire mapping.

Syntax

```
DBMS_STORAGE_MAP.MAP_FILE(
  filename          IN VARCHAR2,
  filetype          IN VARCHAR2,
  cascade           IN BOOLEAN,
  max_num_fileextent IN NUMBER DEFAULT 100,
  dictionary_update IN BOOLEAN DEFAULT TRUE);
```

Parameters

Table 94-7 *MAP_FILE Function Parameters*

Parameter	Description
<code>filename</code>	The file for which mapping information is built.
<code>filetype</code>	Defines the type of the file to be mapped. It can be "DATAFILE", "SPFILE", "TEMPFILE", "CONTROLFILE", "LOGFILE", or "ARCHIVEFILE".
<code>cascade</code>	Should be <code>TRUE</code> only if a storage reconfiguration occurred. For all other instances, such as file resizing (either through an <code>ALTER SYSTEM</code> command or DML operations on extended files), <code>cascade</code> can be set to <code>FALSE</code> because the mapping changes are limited to the file extents only. If <code>TRUE</code> , mapping DAGs are also built for the elements where the file resides.
<code>max_num_fileextent</code>	Defines the maximum number of file extents to be mapped. This limits the amount of memory used when mapping file extents. The default value is 100; <code>max_num_fileextent</code> is an overloaded argument.
<code>dictionary_update</code>	If <code>TRUE</code> , mapping information in the data dictionary is updated to reflect the changes. The default value is <code>TRUE</code> ; <code>dictionary_update</code> is an overloaded argument.

Usage Notes

This function may not obtain the latest mapping information if the file being mapped, or any one of the elements within its I/O stack (if `cascade` is `TRUE`), is owned by a library that must be explicitly synchronized.

MAP_OBJECT Function

This function builds the mapping information for the Oracle object identified by the object name, owner, and type.

Syntax

```
DBMS_STORAGE_MAP.MAP_OBJECT(  
    objname IN VARCHAR2,  
    owner   IN VARCHAR2,  
    objtype IN VARCHAR2);
```

Parameters

Table 94–8 *MAP_OBJECT Function Parameters*

Parameter	Description
objname	The name of the object.
owner	The owner of the object.
objtype	The type of the object.

RESTORE Function

This function loads the entire mapping information from the data dictionary into the shared memory of the instance. You can invoke `RESTORE` only after a `SAVE` operation. You must explicitly call `RESTORE` in a warm startup scenario.

Syntax

```
DBMS_STORAGE_MAP.RESTORE;
```


SAVE Function

This function saves information needed to regenerate the entire mapping into the data dictionary.

Syntax

```
DBMS_STORAGE_MAP.SAVE;
```

UNLOCK_MAP Procedure

This procedure unlocks the mapping information in the shared memory of the instance.

Syntax

```
DBMS_STORAGE_MAP.UNLOCK_MAP;
```

DBMS_STREAMS

The `DBMS_STREAMS` package, one of a set of Streams packages, provides interfaces to convert `SYS.AnyData` objects into logical change record (LCR) objects, to return information about Streams attributes and Streams clients, and to annotate redo entries generated by a session with a binary tag. This tag affects the behavior of a capture process, a propagation, or an apply process whose rules include specifications for these binary tags in redo entries or LCRs.

See Also: *Oracle Streams Concepts and Administration* and *Oracle Streams Replication Administrator's Guide* for more information about this package and Streams

This chapter contains the following topics:

- [Using DBMS_STREAMS](#)
 - [Security Model](#)
- [Summary of DBMS_STREAMS Subprograms](#)

Using DBMS_STREAMS

- [Security Model](#)

Security Model

PUBLIC is granted EXECUTE privilege on this package.

Summary of DBMS_STREAMS Subprograms

Table 95–1 DBMS_STREAMS Package Subprograms

Subprogram	Description
COMPATIBLE_10_1 Function on page 95-4	Returns the DBMS_STREAMS.COMPATIBLE_10_1 constant
COMPATIBLE_9_2 Function on page 95-5	Returns the DBMS_STREAMS.COMPATIBLE_9_2 constant
CONVERT_ANYDATA_TO_LCR_DDL Function on page 95-6	Converts a SYS.AnyData object to a SYS.LCR\$_DDL_RECORD object
CONVERT_ANYDATA_TO_LCR_ROW Function on page 95-7	Converts a SYS.AnyData object to a SYS.LCR\$_ROW_RECORD object
GET_INFORMATION Function on page 95-8	Returns information about various Streams attributes
GET_STREAMS_NAME Function on page 95-9	Returns the name of the invoker
GET_STREAMS_TYPE Function on page 95-10	Returns the type of the invoker
GET_TAG Function on page 95-11	Gets the binary tag for all redo entries generated by the current session
SET_TAG Procedure on page 95-12	Sets the binary tag for all redo entries subsequently generated by the current session

COMPATIBLE_10_1 Function

This function returns the `DBMS_STREAMS.COMPATIBLE_10_1` constant.

Syntax

```
DBMS_STREAMS.COMPATIBLE_10_1  
RETURN INTEGER;
```

Usage Notes

You can use this function with the `GET_COMPATIBLE` member function for LCRs to specify behavior based on compatibility.

The constant value returned by this function corresponds to 10.1.0 compatibility in a database. You control the compatibility of an Oracle database using the `COMPATIBLE` initialization parameter.

See Also:

- ["GET_COMPATIBLE Member Function"](#) on page 174-35
- *Oracle Streams Concepts and Administration* for information about creating rules that discard changes that are not supported by Streams
- *Oracle Database Reference* and *Oracle Database Upgrade Guide* for more information about the `COMPATIBLE` initialization parameter

COMPATIBLE_9_2 Function

This function returns the `DBMS_STREAMS.COMPATIBLE_9_2` constant.

Syntax

```
DBMS_STREAMS.COMPATIBLE_9_2  
RETURN INTEGER;
```

Usage Notes

You may use this function with the `GET_COMPATIBLE` member function for LCRs to specify behavior based on compatibility.

The constant value returned by this function corresponds to 9.2.0 compatibility in a database. You control the compatibility of an Oracle database using the `COMPATIBLE` initialization parameter.

See Also:

- ["GET_COMPATIBLE Member Function"](#) on page 174-35
- *Oracle Streams Concepts and Administration* for information about creating rules that discard changes that are not supported by Streams
- *Oracle Database Reference* and *Oracle Database Upgrade Guide* for more information about the `COMPATIBLE` initialization parameter

CONVERT_ANYDATA_TO_LCR_DDL Function

This function converts a `SYS.AnyData` object into a `SYS.LCR$_DDL_RECORD` object.

Syntax

```
DBMS_STREAMS.CONVERT_ANYDATA_TO_LCR_DDL(
    source IN SYS.AnyData)
RETURN SYS.LCR$_DDL_RECORD;
```

Parameters

Table 95–2 *CONVERT_ANYDATA_TO_LCR_DDL Function Parameter*

Parameter	Description
source	The <code>SYS.AnyData</code> object to be converted. If this object is not a DDL LCR, then an exception is raised.

Usage Notes

You can use this function in a transformation created by the `CREATE_TRANSFORMATION` procedure in the `DBMS_TRANSFORM` package. Use the transformation you create when you add a subscriber for propagation of DDL LCRs from a `SYS.AnyData` queue to a `SYS.LCR$_DDL_RECORD` typed queue.

See Also: *Oracle Streams Concepts and Administration* for more information about this function

CONVERT_ANYDATA_TO_LCR_ROW Function

This function converts a `SYS.AnyData` object into a `SYS.LCR$_ROW_RECORD` object.

Syntax

```
DBMS_STREAMS.CONVERT_ANYDATA_TO_LCR_ROW(
    source IN SYS.AnyData)
RETURN SYS.LCR$_ROW_RECORD;
```

Parameters

Table 95–3 *CONVERT_ANYDATA_TO_LCR_ROW Function Parameter*

Parameter	Description
source	The <code>SYS.AnyData</code> object to be converted. If this object is not a row LCR, then an exception is raised.

Usage Notes

You can use this function in a transformation created by the `CREATE_TRANSFORMATION` procedure in the `DBMS_TRANSFORM` package. Use the transformation you create when you add a subscriber for propagation of row LCRs from a `SYS.AnyData` queue to a `SYS.LCR$_ROW_RECORD` typed queue.

See Also: *Oracle Streams Concepts and Administration* for more information about this function

GET_INFORMATION Function

This function returns information about various Streams attributes.

Syntax

```
DBMS_STREAMS.GET_INFORMATION(  
    name IN VARCHAR2)  
RETURN SYS.AnyData;
```

Parameters

Table 95–4 *GET_INFORMATION Function Parameter*

Parameter	Description
name	<p>The type of information you want to retrieve. Currently, the following names are available:</p> <ul style="list-style-type: none">▪ SENDER: Returns the name of the sender for the current LCR (from its AQ message properties). This function is called inside an apply handler. An apply handler is a DML handler, a DDL handler, an error handler, or a message handler. Returns <code>NULL</code> if called outside of an apply handler. The return value is to be interpreted as a <code>VARCHAR2</code>.▪ CONSTRAINT_NAME: Returns the name of the constraint that was violated for an LCR that raised an error. This function is called inside a DML handler or error handler for an apply process. Returns <code>NULL</code> if called outside of a DML handler or error handler. The return value is to be interpreted as a <code>VARCHAR2</code>.

GET_STREAMS_NAME Function

This function gets the Streams name of the invoker if the invoker is one of the following Streams types:

- CAPTURE
- APPLY
- ERROR_EXECUTION

If the invoker is not one of these types, then this function returns a NULL.

Syntax

```
DBMS_STREAMS.GET_STREAMS_NAME  
RETURN VARCHAR2;
```

Usage Notes

You can use this function in rule conditions, rule-based transformations, apply handlers, and error handlers. For example, if you use one error handler for multiple apply processes, then you can use the `GET_STREAMS_NAME` function to determine the name of the apply process that raised the error.

GET_STREAMS_TYPE Function

This function gets the Streams type of the invoker and returns one of the following types:

- CAPTURE
- APPLY
- ERROR_EXECUTION

If the invoker is not one of these types, then this function returns a `NULL`.

Syntax

```
DBMS_STREAMS.GET_STREAMS_TYPE  
RETURN VARCHAR2;
```

Usage Notes

This function can be used in rule conditions, rule-based transformations, apply handlers, and error handlers. For example, you can use the `GET_STREAMS_TYPE` function to instruct a DML handler to operate differently if it is processing events from the error queue (`ERROR_EXECUTION` type) instead of the apply process queue (`APPLY` type).

GET_TAG Function

This function gets the binary tag for all redo entries generated by the current session.

See Also: *Oracle Streams Replication Administrator's Guide* for more information about tags

Syntax

```
DBMS_STREAMS.GET_TAG()  
RETURN RAW;
```

Examples

The following example illustrates how to display the current LCR tag as output:

```
SET SERVEROUTPUT ON  
DECLARE  
    raw_tag RAW(2000);  
BEGIN  
    raw_tag := DBMS_STREAMS.GET_TAG();  
    DBMS_OUTPUT.PUT_LINE('Tag Value = ' || RAWTOHEX(raw_tag));  
END;  
/
```

You can also display the value by querying the DUAL view:

```
SELECT DBMS_STREAMS.GET_TAG FROM DUAL;
```

SET_TAG Procedure

This procedure sets the binary tag for all redo entries subsequently generated by the current session. Each redo entry generated by DML or DDL statements in the current session will have this tag. This procedure affects only the current session.

Note: This procedure is not transactional. That is, the effects of SET_TAG cannot be rolled back.

See Also: *Oracle Streams Replication Administrator's Guide* for more information about tags

Syntax

```
DBMS_STREAMS.SET_TAG(  
    tag IN RAW DEFAULT NULL);
```

Parameter

Table 95–5 SET_TAG Procedure Parameter

Parameter	Description
tag	The binary tag for all subsequent redo entries generated by the current session. A raw value is a sequence of bytes, and a byte is a sequence of bits. By default, the tag for a session is NULL. The size limit for a tag value is 2000 bytes.

Usage Notes

To set the tag to the hexadecimal value of '17' in the current session, run the following procedure:

```
EXEC DBMS_STREAMS.SET_TAG(tag => HEXTORAW('17'));
```

DBMS_STREAMS_ADM

The `DBMS_STREAMS_ADM` package, one of a set of Streams packages, provides administrative interfaces for adding and removing simple rules for capture, propagation, apply, and dequeue at the table, schema, and database level.

See Also:

- *Oracle Streams Concepts and Administration* and *Oracle Streams Replication Administrator's Guide* for more information about this package and Streams
- [Chapter 82, "DBMS_RULE_ADM"](#)

This chapter contains the following topics:

- [Using DBMS_STREAMS_ADM](#)
 - [Overview](#)
 - [Rules](#)
 - [Users](#)
- [Summary of DBMS_STREAMS_ADM Subprograms](#)

Using DBMS_STREAMS_ADM

- [Overview](#)
- [Rules](#)
- [Users](#)

Overview

The `DBMS_STREAMS_ADM` package, one of a set of Streams packages, provides administrative interfaces for adding and removing simple rules for capture, propagation, apply, and dequeue at the table, schema, and database level. These rules support logical change records (LCRs), which include row LCRs and data definition language (DDL) LCRs. This package also contains subprograms for creating message rules for specific message types. This package also contains subprograms for creating queues and for managing Streams metadata, such as data dictionary information.

If you require more sophisticated rules, then you can use the [DBMS_RULE_ADM](#) package.

Rules

Streams clients include capture processes, propagations, apply processes, and messaging clients. Some of the procedures in the `DBMS_STREAMS_ADM` package add rules to the rule sets of Streams clients. The rules may pertain to changes in the redo log, to logical change records (LCRs), or to user messages.

An LCR represents either a row change that results from a data manipulation language (DML) change or a data definition language (DDL) change. An LCR that represents a row change is a row LCR, and an LCR that represents a DDL change is a DDL LCR. LCRs either may represent changes in the redo record that were captured by a capture process, or they may represent changes created by a user or application. User messages are custom messages that are based on a user-defined types and created by users or applications.

For all of the procedures except the ones that create subset rules, you use the `inclusion_rule` parameter to specify the type of rule set (either positive or negative) for the created rules. If the Streams client does not have a rule set of the

specified type, then a rule set is created automatically, and the rules are added to the rule set. Other rules in an existing rule set for the Streams client are not affected. Additional rules can be added to a rule set using either the `DBMS_STREAMS_ADM` package or the `DBMS_RULE_ADM` package. If a Streams client has both a positive and a negative rule set, then the negative rule set is always evaluated first.

The following sections describe each type of rule in detail:

- [Capture Process Rules for Changes in the Redo Log](#)
- [Propagation Rules for LCRs](#)
- [Propagation Rules for User Messages](#)
- [Apply Process Rules for LCRs](#)
- [Apply Process Rules for User Messages](#)
- [Messaging Client Rules for LCRs](#)
- [Messaging Client Rules for User Messages](#)

See Also: *Oracle Streams Concepts and Administration* for more information about how rules are used in Streams

Capture Process Rules for Changes in the Redo Log

The following procedures add rules to a rule set of a capture process when you specify `capture` for the `streams_type` parameter:

- The `ADD_GLOBAL_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for all changes made to a source database. See "[ADD_GLOBAL_RULES Procedures](#)" on page 96-19.
- The `ADD_SCHEMA_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for changes made to a specified schema. See "[ADD_SCHEMA_RULES Procedures](#)" on page 96-39.
- The `ADD_SUBSET_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for DML changes made to a subset of rows in a specified table. See "[ADD_SUBSET_RULES Procedures](#)" on page 96-52.
- The `ADD_TABLE_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for changes made to a specified table. See "[ADD_TABLE_RULES Procedures](#)" on page 96-63.

If one of these procedures adds rules to the positive rule set for a capture process, then the capture process captures row changes resulting from DML changes, or

DDL changes, or both from a source database and enqueues these changes into the specified queue. If one of these procedures adds rules to the negative rule set for a capture process, then the capture process discards row changes, or DDL changes, or both from a source database.

A capture process can capture changes locally at a source database or remotely at a downstream database. Therefore, for capture process rules, you should execute this procedure either at the source database or at a downstream database.

If the capture process is a local capture process, or if the capture process is a downstream capture process that uses a database link to the source database, then these procedures automatically prepare the appropriate database objects for instantiation:

- `ADD_GLOBAL_RULES` invokes the `PREPARE_GLOBAL_INSTANTIATION` procedure in the `DBMS_CAPTURE_ADM` package at the source database.
- `ADD_SCHEMA_RULES` invokes the `PREPARE_SCHEMA_INSTANTIATION` procedure in the `DBMS_CAPTURE_ADM` package at the source database.
- `ADD_SUBSET_RULES` and `ADD_TABLE_RULES` invoke the `PREPARE_TABLE_INSTANTIATION` procedure in the `DBMS_CAPTURE_ADM` package at the source database.

If the capture process is a downstream capture process that does not use a database link to the source database, then you must prepare the appropriate objects for instantiation manually at the source database.

If one of these procedures is executed at a downstream database, then you specify the source database using the `source_database` parameter, and the specified capture process must exist. The procedure cannot create a capture process if it is run at a downstream database. You can create a capture process at a downstream database using the `CREATE_CAPTURE` procedure in the `DBMS_CAPTURE_ADM` package.

See Also: ["Summary of DBMS_CAPTURE_ADM Subprograms"](#) on page 19-2 for more information about the `CREATE_CAPTURE` procedure and the procedures that prepare database objects for instantiation

Propagation Rules for LCRs

The following procedures add propagation rules to a rule set of a propagation:

- The `ADD_GLOBAL_PROPAGATION_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for all LCRs in a source queue. See "[ADD_GLOBAL_PROPAGATION_RULES Procedures](#)" on page 96-14.
- The `ADD_SCHEMA_PROPAGATION_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for LCRs in a source queue containing changes made to a specified schema. See "[ADD_SCHEMA_PROPAGATION_RULES Procedures](#)" on page 96-34.
- The `ADD_SUBSET_PROPAGATION_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for row LCRs in a source queue containing the results of DML changes made to a subset of rows in a specified table. See "[ADD_SUBSET_PROPAGATION_RULES Procedures](#)" on page 96-46.
- The `ADD_TABLE_PROPAGATION_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for LCRs in a source queue containing changes made to a specified table. See "[ADD_TABLE_PROPAGATION_RULES Procedure](#)" on page 96-58.

If one of these procedures adds rules to the positive rule set for the propagation, then the rules specify that the propagation propagates LCRs in a source queue to a destination queue. If one of these procedures adds rules to the negative rule set for the propagation, then the rules specify that the propagation discards LCRs in a source queue. When you create rules with one of these procedures, and you specify a value for the `source_database` parameter, then the rules include conditions for the specified source database.

Propagation Rules for User Messages

The `ADD_MESSAGE_PROPAGATION_RULE` procedure adds a message rule to a rule set of a propagation. If this procedure adds a rule to the positive rule set for the propagation, then the rule specifies that the propagation propagates the user-enqueued messages of a specific message type that evaluate to `TRUE` for the rule condition in a source queue to a destination queue. If this procedure adds a rule to the negative rule set for the propagation, then the rule specifies that the propagation discards the user-enqueued messages of a specific message type that evaluate to `TRUE` for the rule condition in a source queue. This procedure generates a rule name for the rule.

See Also: "[ADD_MESSAGE_PROPAGATION_RULE Procedures](#)" on page 96-26

Apply Process Rules for LCRs

The following procedures add rules to a rule set of an apply process when you specify `apply` for the `streams_type` parameter:

- The `ADD_GLOBAL_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for all LCRs in the apply process queue. See "[ADD_GLOBAL_RULES Procedures](#)" on page 96-19.
- The `ADD_SCHEMA_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for LCRs in the apply process queue containing changes made to a specified schema. See "[ADD_SCHEMA_RULES Procedures](#)" on page 96-39.
- The `ADD_SUBSET_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for row LCRs in the apply process queue containing the results of DML changes made to a subset of rows in a specified table. See "[ADD_SUBSET_RULES Procedures](#)" on page 96-52.
- The `ADD_TABLE_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for LCRs in the apply process queue containing changes made to a specified table. See "[ADD_TABLE_RULES Procedures](#)" on page 96-63.

If one of these procedures adds rules to the positive rule set for the apply process, then the rules specify that the apply process applies LCRs in its queue. If one of these procedures adds rules to the negative rule set for the apply process, then the rules specify that the apply process discards LCRs in its queue. For apply process rules, you should execute these procedures at the destination database.

An apply process can apply captured LCRs from only one source database. If one of these procedures creates an apply process, then specify the source database for the apply process using the `source_database` parameter. If the `source_database` parameter is `NULL`, and one of these procedures creates an apply process, then the source database name of the first LCR received by the apply process is used for the source database.

The rules in the apply process rule sets determine which events are dequeued by the apply process. When you create rules with one of these procedures, and you specify a value for the `source_database` parameter, then the rules include conditions for the specified source database. If the apply process dequeues an LCR with a source database that is different than the source database for the apply process, then an error is raised. In addition, when adding rules to an existing apply process, the database specified in the `source_database` parameter cannot be different than the source database for the apply process. You can determine the source database for an apply process by querying the `DBA_APPLY_PROGRESS` data dictionary view.

Changes applied by an apply process created by one of these procedures generate tags in the redo log at the destination database with a value of '00' (double zero). You can use the `ALTER_APPLY` procedure in the `DBMS_APPLY_ADM` package to alter the tag value after the apply process is created, if necessary.

An apply process created by one of these procedures can apply events only at the local database and can apply only captured events. To create an apply process that applies events at a remote database or an apply process that applies user-enqueued events, use the `CREATE_APPLY` procedure in the `DBMS_APPLY_ADM` package.

You also can use the `DBMS_APPLY_ADM.CREATE_APPLY` procedure to specify nondefault values for the `apply_captured`, `apply_user`, `apply_database_link`, and `apply_tag` parameters when you run that procedure. You can use one of the procedures in the `DBMS_STREAMS_ADM` package to add rules to a rule set used by the apply process after you create it.

See Also: ["ALTER_APPLY Procedure"](#) on page 15-4 and ["CREATE_APPLY Procedure"](#) on page 15-14

Apply Process Rules for User Messages

The `ADD_MESSAGE_RULE` procedure adds a message rule to a rule set of an apply process when you specify `apply` for the `streams_type` parameter. For an apply process rule, you should execute this procedure at the destination database.

If this procedure adds a rule to the positive rule set for an apply process, then the apply process dequeues user-enqueued messages of a specific message type that satisfy the apply process rule and sends these messages to its message handler. If no message handler is specified for the apply process, then use the `ALTER_APPLY` procedure in the `DBMS_APPLY_ADM` package to set the message handler. If this procedure adds a rule to the negative rule set for an apply process, then the apply process discards user-enqueued messages of a specific message type that satisfy the apply process rule.

See Also:

- ["ADD_MESSAGE_RULE Procedures"](#) on page 96-30
- ["ALTER_APPLY Procedure"](#) on page 15-4

Messaging Client Rules for LCRs

The following procedures add rules to a rule set of a messaging client when you specify `dequeue` for the `streams_type` parameter:

- The `ADD_GLOBAL_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for all LCRs in the messaging client queue. See "[ADD_GLOBAL_RULES Procedures](#)" on page 96-19.
- The `ADD_SCHEMA_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for LCRs in the messaging client queue containing changes made to a specified schema. See "[ADD_SCHEMA_RULES Procedures](#)" on page 96-39.
- The `ADD_SUBSET_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for row LCRs in the messaging client queue containing the results of DML changes made to a subset of rows in a specified table. See "[ADD_SUBSET_RULES Procedures](#)" on page 96-52.
- The `ADD_TABLE_RULES` procedure adds rules whose rule condition evaluates to `TRUE` for LCRs in the messaging client queue containing changes made to a specified table. See "[ADD_TABLE_RULES Procedures](#)" on page 96-63.

If one of these procedures adds rules to the positive rule set for a messaging client, then the messaging client can dequeue user-enqueued row LCRs, or DDL LCRs, or both that originated at the source database matching the `source_database` parameter. If one of these procedures adds rules to the negative rule set for a messaging client, then the messaging client discards user-enqueued row LCRs, or DDL LCRs, or both that originated at the source database matching the `source_database` parameter. You should execute these procedures at the database where you want to dequeue the events with the messaging client.

Messaging Client Rules for User Messages

The `ADD_MESSAGE_RULE` procedure adds a message rule to a rule set of a messaging client when you specify `dequeue` for the `streams_type` parameter. You should execute this procedure at the database that will dequeue messages.

If this procedure adds a rule to the positive rule set for a messaging client, then the messaging client dequeues user-enqueued messages of a specific message type that satisfy the message rule. If this procedure adds a rule to the negative rule set for a messaging client, then the messaging client discards user-enqueued messages of a specific message type that satisfy the message rule.

See Also: "[ADD_MESSAGE_RULE Procedures](#)" on page 96-30

Users

A user is associated with each Streams client. The following sections describe these users.

Capture User

The following procedures can create a capture process:

- [ADD_GLOBAL_RULES Procedures](#)
- [ADD_SCHEMA_RULES Procedures](#)
- [ADD_SUBSET_RULES Procedures](#)
- [ADD_TABLE_RULES Procedures](#)

If one of these procedures creates a capture process, then it configures the current user as the `capture_user`. This user captures changes that satisfy the capture process rule sets. This user must have the necessary privileges to capture changes. The procedure grants the capture user enqueue privilege on the queue used by the capture process and configures the user as a secure queue user of the queue.

See Also: ["CREATE_CAPTURE Procedure"](#) on page 19-16 for information about the privileges required to capture changes

Propagation User

The following procedures can create a propagation:

- [ADD_GLOBAL_PROPAGATION_RULES Procedures](#)
- [ADD_MESSAGE_PROPAGATION_RULE Procedures](#)
- [ADD_SCHEMA_PROPAGATION_RULES Procedures](#)
- [ADD_SUBSET_PROPAGATION_RULES Procedures](#)
- [ADD_TABLE_PROPAGATION_RULES Procedure](#)

When a propagation is created, a propagation job is created also if one does not exist for the database link used by the propagation. If a propagation job is created when one of these procedures is run, then the user who runs the procedure owns the propagation job.

Note: The source queue owner performs the propagation, but the propagation job is owned by the user who creates it. These two users may or may not be the same.

See Also: ["CREATE_PROPAGATION Procedure"](#) on page 65-6 for more information about the required privileges

Apply User

The following procedures can create an apply process:

- [ADD_GLOBAL_RULES Procedures](#)
- [ADD_MESSAGE_RULE Procedures](#)
- [ADD_SCHEMA_RULES Procedures](#)
- [ADD_SUBSET_RULES Procedures](#)
- [ADD_TABLE_RULES Procedures](#)

If one of these procedures creates an apply process, then it configures the current user as the `apply_user`. This user applies changes that satisfy the apply process rule sets and runs user-defined apply handlers. This user must have the necessary privileges to apply changes. The procedure grants the apply user dequeue privilege on the queue used by the apply process and configures the user as a secure queue user of the queue.

See Also: ["CREATE_APPLY Procedure"](#) on page 15-14 for information about the privileges required to apply changes (refer to the `apply_user` parameter)

Messaging Client User

The following procedures can create a messaging client:

- [ADD_GLOBAL_RULES Procedures](#)
- [ADD_MESSAGE_RULE Procedures](#)
- [ADD_SCHEMA_RULES Procedures](#)
- [ADD_SUBSET_RULES Procedures](#)
- [ADD_TABLE_RULES Procedures](#)

If one of these procedures creates a messaging client, then the user who runs this procedure is granted the privileges to dequeue from the queue using the messaging client. The procedure configures this user as a secure queue user of the queue, and only this user can use the messaging client.

Summary of DBMS_STREAMS_ADM Subprograms

Table 96–1 DBMS_STREAMS_ADM Package Subprograms

Subprogram	Description
ADD_GLOBAL_PROPAGATION_RULES Procedures on page 96-14	Either adds global rules to the positive rule set for a propagation, or adds global rules to the negative rule set for a propagation, and creates the specified propagation if it does not exist
ADD_GLOBAL_RULES Procedures on page 96-19	Adds global rules to either the positive or negative rule set of a capture process, apply process, or messaging client, and creates the specified capture process, apply process, or messaging client if it does not exist
ADD_MESSAGE_PROPAGATION_RULE Procedures on page 96-26	Either adds a message rule to the positive rule set for a propagation, or adds a message rule to the negative rule set for a propagation, and creates the specified propagation if it does not exist
ADD_MESSAGE_RULE Procedures on page 96-30	Adds a message rule to either the positive or negative rule set of an apply process or messaging client, and creates the specified apply process or messaging client if it does not exist
ADD_SCHEMA_PROPAGATION_RULES Procedures on page 96-34	Either adds schema rules to the positive rule set for a propagation, or adds schema rules to the negative rule set for a propagation, and creates the specified propagation if it does not exist
ADD_SCHEMA_RULES Procedures on page 96-39	Adds schema rules to either the positive or negative rule set of a capture process, apply process, or messaging client, and creates the specified capture process, apply process, or messaging client if it does not exist
ADD_SUBSET_PROPAGATION_RULES Procedures on page 96-46	Adds subset rules to the positive rule set for a propagation, and creates the specified propagation if it does not exist

Table 96–1 (Cont.) DBMS_STREAMS_ADM Package Subprograms

Subprogram	Description
ADD_SUBSET_RULES Procedures on page 96-52	Adds subset rules to the positive rule set of a capture process, apply process, or messaging client, and creates the specified capture process, apply process, or messaging client if it does not exist
ADD_TABLE_PROPAGATION_RULES Procedure on page 96-58	Either adds table rules to the positive rule set for a propagation, or adds table rules to the negative rule set for a propagation, and creates the specified propagation if it does not exist
ADD_TABLE_RULES Procedures on page 96-63	Adds table rules to either the positive or negative rule set of a capture process, apply process, or messaging client, and creates the specified capture process, apply process, or messaging client if it does not exist
GET_SCN_MAPPING Procedure on page 96-70	Gets information about the system change number (SCN) values to use for Streams capture and apply processes in a Streams replication environment
MAINTAIN_SIMPLE_TABLESPACE Procedure on page 96-72	Clones a simple tablespace from a source database at a destination database and uses Streams to maintain this tablespace at both databases
MAINTAIN_TABLESPACES Procedure on page 96-78	Clones a set of tablespaces from a source database at a destination database and uses Streams to maintain these tablespaces at both databases
PURGE_SOURCE_CATALOG Procedure on page 96-92	Removes all Streams data dictionary information at the local database for the specified object
REMOVE_QUEUE Procedure on page 96-94	Removes the specified SYS.AnyData queue
REMOVE_RULE Procedure on page 96-96	Removes the specified rule or all rules from the rule set associated with the specified capture process, apply process, or propagation
REMOVE_STREAMS_CONFIGURATION Procedure on page 96-98	Removes the Streams configuration at the local database.

Table 96–1 (Cont.) DBMS_STREAMS_ADM Package Subprograms

Subprogram	Description
SET_MESSAGE_NOTIFICATION Procedure on page 96-100	Sets a notification for messages that can be dequeued by a specified Streams messaging client from a specified queue
SET_RULE_TRANSFORM_FUNCTION Procedure on page 96-105	Sets or removes the transformation function name for a rule-based transformation
SET_UP_QUEUE Procedure on page 96-107	Creates a queue table and a queue for use with the capture, propagate, and apply functionality of Streams

Note: All procedures commit unless specified otherwise.

ADD_GLOBAL_PROPAGATION_RULES Procedures

These procedures either add global rules to the positive rule set for a propagation, or add global rules to the negative rule set for a propagation, and create the specified propagation if it does not exist.

Note: This procedure is overloaded. One version of this procedure contains two OUT parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_GLOBAL_PROPAGATION_RULES(
    streams_name          IN   VARCHAR2  DEFAULT NULL,
    source_queue_name     IN   VARCHAR2,
    destination_queue_name IN  VARCHAR2,
    include_dml           IN   BOOLEAN   DEFAULT true,
    include_ddl           IN   BOOLEAN   DEFAULT false,
    include_tagged_lcr    IN   BOOLEAN   DEFAULT false,
    source_database       IN   VARCHAR2  DEFAULT NULL,
    dml_rule_name         OUT  VARCHAR2,
    ddl_rule_name         OUT  VARCHAR2,
    inclusion_rule        IN   BOOLEAN   DEFAULT true,
    and_condition         IN   VARCHAR2  DEFAULT NULL);
```

Parameters

Table 96–2 ADD_GLOBAL_PROPAGATION_RULES Procedure Parameters

Parameter	Description
streams_name	The name of the propagation. Do not specify an owner. If the specified propagation does not exist, then it is created automatically. If NULL and a propagation exists for the same source queue and destination queue (including database link), then this propagation is used. If NULL and no propagation exists for the same source queue and destination queue (including database link), then a propagation is created automatically with a system-generated name.

Table 96–2 (Cont.) ADD_GLOBAL_PROPAGATION_RULES Procedure Parameters

Parameter	Description
source_queue_name	<p>The name of the source queue, specified as [<i>schema_name</i>.]<i>queue_name</i>. The current database must contain the source queue, and the queue must be SYS.AnyData type.</p> <p>For example, to specify a source queue named <i>streams_queue</i> in the <i>strmadmin</i> schema, enter <i>strmadmin.streams_queue</i> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p>
destination_queue_name	<p>The name of the destination queue, including a database link, specified as [<i>schema_name</i>.]<i>queue_name</i>[<i>@dblink_name</i>], if the destination queue is in a remote database. The queue must be SYS.AnyData type.</p> <p>For example, to specify a destination queue named <i>streams_queue</i> in the <i>strmadmin</i> schema and use a database link named <i>dbs2.net</i>, enter <i>strmadmin.streams_queue@dbs2.net</i> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p> <p>If the database link is omitted, then the global name of the current database is used, and the source queue and destination queue must be in the same database.</p> <p>Note: Connection qualifiers are not allowed.</p>
include_dml	<p>If <i>true</i>, then creates a rule for DML changes. If <i>false</i>, then does not create a DML rule. NULL is not permitted.</p>
include_ddl	<p>If <i>true</i>, then creates a rule for DDL changes. If <i>false</i>, then does not create a DDL rule. NULL is not permitted.</p>

Table 96–2 (Cont.) ADD_GLOBAL_PROPAGATION_RULES Procedure Parameters

Parameter	Description
<code>include_tagged_lcr</code>	<p>If <code>true</code>, then no condition regarding Streams tags is added to the generated rules. Therefore, these rules can evaluate to <code>TRUE</code> regardless of whether an LCR has a non-<code>NULL</code> tag. If the rules are added to the positive rule set for the propagation, then an LCR is always considered for propagation, regardless of whether it has a non-<code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>true</code> is appropriate for a full (for example, standby) copy of a database. If the rules are added to the negative rule set for the propagation, then whether an LCR is discarded does not depend on the LCR's tag.</p> <p>If <code>false</code>, then adds a condition to each generated rule that causes the rule to evaluate to <code>TRUE</code> only if an LCR has a <code>NULL</code> Streams tag. If the rules are added to the positive rule set for the propagation, then an LCR is considered for propagation only when the LCR contains a <code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>false</code> may be appropriate in update-anywhere configurations to avoid sending a change back to its source database. If the rules are added to the negative rule set for the propagation, then an LCR can be discarded only if it has a <code>NULL</code> tag.</p> <p>In most cases, specify <code>true</code> for this parameter if the <code>inclusion_rule</code> parameter is set to <code>false</code>.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>
<code>source_database</code>	<p>The global name of the source database. The source database is where the changes originated. If <code>NULL</code>, then no condition regarding the source database is added to the generated rules.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p> <p>Oracle recommends that you specify a source database for propagation rules.</p>
<code>dml_rule_name</code>	<p>If <code>include_dml</code> is <code>true</code>, then contains the DML rule name.</p> <p>If <code>include_dml</code> is <code>false</code>, then contains a <code>NULL</code>.</p>

Table 96–2 (Cont.) ADD_GLOBAL_PROPAGATION_RULES Procedure Parameters

Parameter	Description
ddl_rule_name	If <code>include_ddl</code> is true, then contains the DDL rule name. If <code>include_ddl</code> is false, then contains a NULL.
inclusion_rule	If <code>inclusion_rule</code> is true, then the rules are added to the positive rule set for the propagation. If <code>inclusion_rule</code> is false, then the rules are added to the negative rule set for the propagation. In either case, the system creates the rule set if it does not exist.
and_condition	If non-NULL, appends the specified condition to the system-generated rule condition using an AND clause in the following way: <pre>(system_condition) AND (and_condition)</pre> <p>The variable in the specified condition must be <code>:lcr</code>. For example, to specify that the global rules generated by the procedure evaluate to true only if the Streams tag is the hexadecimal equivalent of '02', specify the following condition:</p> <pre>:lcr.get_tag() = HEXTORAW('02')</pre> <p>The <code>:lcr</code> in the specified condition is converted to <code>:dml</code> or <code>:ddl</code>, depending on the rule that is being generated. If you are specifying an LCR member subprogram that is dependent on the LCR type (row or DDL), then make sure this procedure only generates the appropriate rule.</p> <p>Specifically, if you specify an LCR member subprogram that is valid only for row LCRs, then specify true for the <code>include_dml</code> parameter and false for the <code>include_ddl</code> parameter. If you specify an LCR member subprogram that is valid only for DDL LCRs, then specify false for the <code>include_dml</code> parameter and true for the <code>include_ddl</code> parameter.</p> <p>See Also: Chapter 174, "Logical Change Record TYPES"</p>

Usage Notes

This procedure creates DML and DDL rules automatically based on `include_dml` and `include_ddl` parameter values, respectively. A system-generated rule name is

the database name with a sequence number appended to it. The sequence number is used to avoid naming conflicts. If the database name plus the sequence number is too long, then the database name is truncated. The overloaded `ADD_GLOBAL_PROPAGATION_RULES` procedure generates the rule names for DML and DDL changes. A propagation uses the rules created for filtering.

If no propagation job exists for the database link specified in the `destination_queue_name` parameter when this procedure is run, then a propagation job is created for use by the propagation. If a propagation job already exists for the specified database link, then the propagation uses the existing propagation job.

This procedure also configures propagation using the current user, and establish a default propagation schedule. Only one propagation is allowed between the source queue and destination queue.

Note:

- Currently, a single propagation job propagates all events that use a particular database link, even if the database link is used by multiple propagations to propagate events to multiple destination queues.
 - For a propagation to work properly, the owner of the source queue must have the necessary privileges to propagate events.
-
-

See Also:

- ["Rules"](#) on page 96-2 and ["Propagation Rules for LCRs"](#) on page 96-4 for more information about the rules created by this procedure
- ["Propagation User"](#) on page 96-9

Examples

The following is an example of a global rule condition that may be created for DML changes:

```
:dml.get_source_database_name() = 'DBS1.NET' AND :dml.is_null_tag() = 'Y'
```


ADD_GLOBAL_RULES Procedures

These procedures add rules to a rule set of one of the following types of Streams clients:

- Capture process rules for capturing changes to an entire database when the `streams_type` parameter is set to `capture`. See ["Capture Process Rules for Changes in the Redo Log"](#) on page 96-3 for more information about these rules.
- Apply process rules for applying all logical change records (LCRs) in a queue when the `streams_type` parameter is set to `apply`. The rules may specify that the LCRs must be from a particular source database. See ["Apply Process Rules for LCRs"](#) on page 96-6 for more information about these rules.
- Messaging client rules for dequeuing all user-enqueued LCRs from a queue when the `streams_type` parameter is set to `dequeue`. The rules may specify that the LCRs must be from a particular source database. See ["Messaging Client Rules for LCRs"](#) on page 96-7 for more information about these rules.

Note: This procedure is overloaded. One version of this procedure contains two OUT parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_GLOBAL_RULES (
  streams_type      IN  VARCHAR2,
  streams_name     IN  VARCHAR2  DEFAULT NULL,
  queue_name       IN  VARCHAR2  DEFAULT 'streams_queue',
  include_dml      IN  BOOLEAN   DEFAULT true,
  include_ddl     IN  BOOLEAN   DEFAULT false,
  include_tagged_lcr IN  BOOLEAN   DEFAULT false,
  source_database  IN  VARCHAR2  DEFAULT NULL,
  dml_rule_name    OUT VARCHAR2,
  ddl_rule_name    OUT VARCHAR2,
  inclusion_rule   IN  BOOLEAN   DEFAULT true,
  and_condition    IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 96–3 ADD_GLOBAL_RULES Procedure Parameters

Parameter	Description
<code>streams_type</code>	<p>The type of Streams client:</p> <ul style="list-style-type: none"> ■ Specify <code>capture</code> for a capture process. ■ Specify <code>apply</code> for an apply process. ■ Specify <code>dequeue</code> for a messaging client.
<code>streams_name</code>	<p>The name of the capture process, apply process, or messaging client. Do not specify an owner.</p> <p>If the specified Streams client does not exist, then it is created automatically.</p> <p>If <code>NULL</code>, if <code>streams_type</code> is <code>capture</code> or <code>dequeue</code>, and if one relevant capture process or messaging client for the queue exists, then the relevant Streams client is used. If no relevant Streams client exists for the queue, then a Streams client is created automatically with a system-generated name. If <code>NULL</code> and multiple Streams clients of the specified <code>streams_type</code> for the queue exist, then an error is raised.</p> <p>If <code>NULL</code>, if <code>streams_type</code> is <code>apply</code>, and if one relevant apply process exists, then the relevant apply process is used. The relevant apply process is identified in one of the following ways:</p> <ul style="list-style-type: none"> ■ If one existing apply process has the source database specified in <code>source_database</code> and uses the queue specified in <code>queue_name</code>, then this apply process is used. ■ If <code>source_database</code> is <code>NULL</code> and one existing apply process is using the queue specified in <code>queue_name</code>, then this apply process is used. <p>If <code>NULL</code> and no relevant apply process exists, then an apply process is created automatically with a system-generated name. If <code>NULL</code> and multiple relevant apply processes exist, then an error is raised.</p> <p>An apply process and a messaging client cannot have the same name.</p>

Table 96–3 (Cont.) ADD_GLOBAL_RULES Procedure Parameters

Parameter	Description
queue_name	<p>The name of the local queue, specified as [<i>schema_name</i>.]<i>queue_name</i>. The current database must contain the queue, and the queue must be SYS.AnyData type.</p> <p>For example, to specify a queue named <i>streams_queue</i> in the <i>strmadmin</i> schema, enter <i>strmadmin.streams_queue</i> for this parameter. If the schema is not specified, then the current user is the default.</p> <p>For capture process rules, this is the queue into which a capture process enqueues events. For apply process rules, this is the queue from which an apply process dequeues events. For messaging client rules, this is the queue from which a messaging client dequeues events.</p>
include_dml	If <i>true</i> , then creates a rule for DML changes. If <i>false</i> , then does not create a DML rule. NULL is not permitted.
include_ddl	If <i>true</i> , then creates a rule for DDL changes. If <i>false</i> , then does not create a DDL rule. NULL is not permitted.

Table 96–3 (Cont.) ADD_GLOBAL_RULES Procedure Parameters

Parameter	Description
<code>include_tagged_lcr</code>	<p>If <code>true</code>, then no condition regarding Streams tags is added to the generated rules. Therefore, these rules can evaluate to <code>TRUE</code> regardless of whether a redo entry or LCR has a non-<code>NULL</code> tag. If the rules are added to the positive rule set for the process, then a redo entry is always considered for capture, and an LCR is always considered for apply, regardless of whether the redo entry or LCR has a non-<code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>true</code> is appropriate for a full (for example, standby) copy of a database. If the rules are added to the negative rule set for the process, then whether a redo entry or LCR is discarded does not depend on the tag.</p> <p>If <code>false</code>, then adds a condition to each generated rule that causes the rule to evaluate to <code>TRUE</code> only if a redo entry or LCR has a <code>NULL</code> Streams tag. If the rules are added to the positive rule set for the process, then a redo entry is considered for capture, and an LCR is considered for apply, only when the redo entry or LCR contains a <code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>false</code> may be appropriate in update-anywhere configurations to avoid sending a change back to its source database. If the rules are added to the negative rule set for the process, then a redo entry or LCR can be discarded only if it has a <code>NULL</code> tag.</p> <p>In most cases, specify <code>true</code> for this parameter if the <code>inclusion_rule</code> parameter is set to <code>false</code>.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>

Table 96–3 (Cont.) ADD_GLOBAL_RULES Procedure Parameters

Parameter	Description
source_database	<p>The global name of the source database. If <code>NULL</code>, then no condition regarding the source database is added to the generated rules.</p> <p>For capture process rules, specify <code>NULL</code> or the global name of the local database if you are creating a capture process locally at the source database. If you are creating a capture process at a downstream database, then specify the source database of the changes that will be captured.</p> <p>For apply process rules, specify the source database of the changes that will be applied by the apply process. The source database is the database where the changes originated. If an apply process applies captured events, then the apply process can apply events from only one capture process at one source database.</p> <p>For messaging client rules, specify <code>NULL</code> if you do not want the rules created by this procedure to have a condition for the source database. Specify a source database if you want the rules created by this procedure to have a condition for the source database. The source database is part of the information in an LCR, and user-constructed LCRs may or may not have this information.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p>
dml_rule_name	<p>If <code>include_dml</code> is <code>true</code>, then contains the DML rule name.</p> <p>If <code>include_dml</code> is <code>false</code>, then contains a <code>NULL</code>.</p>
ddl_rule_name	<p>If <code>include_ddl</code> is <code>true</code>, then contains the DDL rule name.</p> <p>If <code>include_ddl</code> is <code>false</code>, then contains a <code>NULL</code>.</p>
inclusion_rule	<p>If <code>inclusion_rule</code> is <code>true</code>, then the rules are added to the positive rule set for the Streams client.</p> <p>If <code>inclusion_rule</code> is <code>false</code>, then the rules are added to the negative rule set for the Streams client.</p> <p>In either case, the system creates the rule set if it does not exist.</p>

Table 96–3 (Cont.) ADD_GLOBAL_RULES Procedure Parameters

Parameter	Description
<code>and_condition</code>	<p>If non-NULL, appends the specified condition to the system-generated rule condition using an AND clause in the following way:</p> <pre>(system_condition) AND (and_condition)</pre> <p>The variable in the specified condition must be <code>:lcr</code>. For example, to specify that the global rules generated by the procedure evaluate to <code>true</code> only if the Streams tag is the hexadecimal equivalent of '02', specify the following condition:</p> <pre>:lcr.get_tag() = HEXTORAW('02')</pre> <p>The <code>:lcr</code> in the specified condition is converted to <code>:dml</code> or <code>:ddl</code>, depending on the rule that is being generated. If you are specifying an LCR member subprogram that is dependent on the LCR type (row or DDL), then make sure this procedure only generates the appropriate rule.</p> <p>Specifically, if you specify an LCR member subprogram that is valid only for row LCRs, then specify <code>true</code> for the <code>include_dml</code> parameter and <code>false</code> for the <code>include_ddl</code> parameter. If you specify an LCR member subprogram that is valid only for DDL LCRs, then specify <code>false</code> for the <code>include_dml</code> parameter and <code>true</code> for the <code>include_ddl</code> parameter.</p> <p>See Also: Chapter 174, "Logical Change Record TYPES"</p>

Usage Notes

This procedure creates the specified capture process, apply process, or messaging client if it does not exist.

This procedure creates DML and DDL rules automatically based on `include_dml` and `include_ddl` parameter values, respectively. A system-generated rule name is the database name with a sequence number appended to it. The sequence number is used to avoid naming conflicts. If the database name plus the sequence number is too long, then the database name is truncated. The overloaded `ADD_GLOBAL_RULES` procedure generates the rule names for DML and DDL changes. A capture process, apply process, or messaging client uses the rules created for filtering.

See Also:

- ["Rules"](#) on page 96-2
- ["Users"](#) on page 96-8

Examples

The following is an example of a global rule condition that may be created for DML changes:

```
:dml.get_source_database_name() = 'DBS1.NET' AND :dml.is_null_tag() = 'Y'
```

ADD_MESSAGE_PROPAGATION_RULE Procedures

These procedures add a message rule to the positive rule set for a propagation, or add a message rule to the negative rule set for a propagation, and create the specified propagation if it does not exist.

Note: This procedure is overloaded. One version of this procedure contains the OUT parameter `rule_name`, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_MESSAGE_PROPAGATION_RULE(
  message_type          IN  VARCHAR2,
  rule_condition        IN  VARCHAR2,
  streams_name         IN  VARCHAR2 DEFAULT NULL,
  source_queue_name    IN  VARCHAR2,
  destination_queue_name IN VARCHAR2,
  inclusion_rule       IN  BOOLEAN  DEFAULT true,
  rule_name            OUT  VARCHAR2);
```

Parameters

Table 96–4 ADD_MESSAGE_PROPAGATION_RULE Procedure Parameters

Parameter	Description
<code>message_type</code>	The type of the message. If the type is not an Oracle built-in type, then specified as [<i>schema_name</i> .] <i>type_name</i> . If the schema is not specified, then the current user is the default. For example, to specify a type named <code>usr_msg</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.usr_msg</code> for this parameter.
<code>rule_condition</code>	The rule condition for this message type. The rule variable name specified in the rule condition must be the following: :msg

Table 96–4 (Cont.) ADD_MESSAGE_PROPAGATION_RULE Procedure Parameters

Parameter	Description
streams_name	<p>The name of the propagation. Do not specify an owner.</p> <p>If the specified propagation does not exist, then it is created automatically.</p> <p>If NULL and a propagation exists for the same source queue and destination queue (including database link), then this propagation is used.</p> <p>If NULL and no propagation exists for the same source queue and destination queue (including database link), then a propagation is created automatically with a system-generated name.</p>
source_queue_name	<p>The name of the source queue, specified as [<i>schema_name</i>.] <i>queue_name</i>. The current database must contain the source queue, and the queue must be SYS.AnyData type.</p> <p>For example, to specify a source queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p>
destination_queue_name	<p>The name of the destination queue, including a database link, specified as [<i>schema_name</i>.] <i>queue_name</i> [<i>@dblink_name</i>], if the destination queue is in a remote database. The queue must be SYS.AnyData type.</p> <p>For example, to specify a destination queue named <code>streams_queue</code> in the <code>strmadmin</code> schema and use a database link named <code>db2.net</code>, enter <code>strmadmin.streams_queue@db2.net</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p> <p>If the database link is omitted, then the global name of the current database is used, and the source queue and destination queue must be in the same database.</p> <p>Note: Connection qualifiers are not allowed.</p>

Table 96–4 (Cont.) ADD_MESSAGE_PROPAGATION_RULE Procedure Parameters

Parameter	Description
<code>inclusion_rule</code>	<p>If <code>inclusion_rule</code> is <code>true</code>, then the rule is added to the positive rule set for the propagation.</p> <p>If <code>inclusion_rule</code> is <code>false</code>, then the rule is added to the negative rule set for the propagation.</p> <p>In either case, the system creates the rule set if it does not exist.</p>
<code>rule_name</code>	Contains the rule name

Usage Notes

When you use this procedure to create a rule set for a message rule, the new rule set does not have an evaluation context. If no evaluation context exists for the specified message type, then this procedure creates a new evaluation context and associates it with the new rule. The evaluation context also has a system-generated name. If you create new rules that use an existing message type, then the new rules use the existing evaluation context for the message type.

If no propagation job exists for the database link specified in the `destination_queue_name` parameter when this procedure is run, then a propagation job is created for use by the propagation. If a propagation job already exists for the specified database link, then the propagation uses the existing propagation job.

This procedure also configures propagation using the current user, and establishes a default propagation schedule. Only one propagation is allowed between the source queue and destination queue.

Note:

- Currently, a single propagation job propagates all events that use a particular database link, even if the database link is used by multiple propagations to propagate events to multiple destination queues.
 - For a propagation to work properly, the owner of the source queue must have the necessary privileges to propagate events.
-
-

See Also:

- ["Rules"](#) on page 96-2 and ["Propagation Rules for User Messages"](#) on page 96-5 for more information about the rules created by this procedure
- ["Propagation User"](#) on page 96-9

Examples

Suppose the message type is `usr_msg`, and that this type has the following attributes: `source_dbname`, `owner`, `name`, and `message`. Given this type, the following rule condition may be specified:

```
':msg.source_dbname = 'DBS1.NET' AND ' || ':msg.owner = 'HR' AND ' ||  
' :msg.name = 'EMPLOYEES''
```

Note: The quotation marks in the preceding example are all single quotation marks.

This rule condition evaluates to `TRUE` if a user-enqueued message of type `usr_msg` has `dbs1.net` for its `source_dbname` attribute, `hr` for its `owner` attribute, and `employees` for its `name` attribute.

ADD_MESSAGE_RULE Procedures

These procedures add a message rule to a rule set of one of the following types of Streams clients:

- Apply process rule for dequeuing user-enqueued messages of a specific message type from a queue when the `streams_type` parameter is set to `apply`. See ["Apply Process Rules for User Messages"](#) on page 96-7 for more information about such rules.
- Messaging client rule dequeuing user-enqueued messages of a specific message type from a queue when the `streams_type` parameter is set to `dequeue`. See ["Messaging Client Rules for User Messages"](#) on page 96-8 for more information about such rules.

Note: This procedure is overloaded. One version of this procedure contains the `OUT` parameter `rule_name`, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_MESSAGE_RULE(  
  message_type    IN    VARCHAR2,  
  rule_condition  IN    VARCHAR2,  
  streams_type    IN    VARCHAR2,  
  streams_name    IN    VARCHAR2 DEFAULT NULL,  
  queue_name      IN    VARCHAR2 DEFAULT 'streams_queue',  
  inclusion_rule  IN    BOOLEAN  DEFAULT true,  
  rule_name       OUT   VARCHAR2);
```

Parameters

Table 96–5 *ADD_MESSAGE_RULE Procedure Parameters*

Parameter	Description
<code>message_type</code>	<p>The type of the message. If the type is not an Oracle built-in type, then specified as [<i>schema_name</i>.]<i>type_name</i>. If the schema is not specified, then the current user is the default.</p> <p>For example, to specify a type named <code>usr_msg</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.usr_msg</code> for this parameter.</p>
<code>rule_condition</code>	<p>The rule condition for the message type. The rule variable name specified in the rule condition must be the following:</p> <p style="padding-left: 40px;"><code>:msg</code></p>
<code>streams_type</code>	<p>The type of message consumer, either <code>apply</code> for apply process or <code>dequeue</code> for messaging client</p>
<code>streams_name</code>	<p>The name of the Streams apply process or messaging client.</p> <p>If the specified <code>streams_type</code> is <code>apply</code>, then specify the name of the apply process. Do not specify an owner. If the specified apply process does not exist, then it is created automatically with a system-generated name.</p> <p>If the specified <code>streams_type</code> is <code>dequeue</code>, then specify the messaging client. For example, if the user <code>strmadmin</code> is the messaging client, then specify <code>strmadmin</code>.</p> <p>If <code>NULL</code> and a relevant apply process or messaging client for the queue exists, then the relevant apply process or messaging client is used. If <code>NULL</code> and multiple relevant apply processes or messaging clients for the queue exist, then an error is raised.</p> <p>If <code>NULL</code> and no Streams client of the specified <code>streams_type</code> exists for the queue, then an apply process or messaging client is created automatically with a system-generated name.</p> <p>An apply process and a messaging client cannot have the same name.</p>

Table 96–5 (Cont.) ADD_MESSAGE_RULE Procedure Parameters

Parameter	Description
queue_name	The name of the local queue from which messages will be dequeued, specified as [<i>schema_name</i> .] <i>queue_name</i> . The current database must contain the queue, and the queue must be SYS.AnyData type. For example, to specify a queue named <i>streams_queue</i> in the <i>strmadmin</i> schema, enter <i>strmadmin.streams_queue</i> for this parameter. If the schema is not specified, then the current user is the default.
inclusion_rule	If <i>inclusion_rule</i> is true, then the rule is added to the positive rule set for the apply process or messaging client. If <i>inclusion_rule</i> is false, then the rule is added to the negative rule set for the apply process or messaging client. In either case, the system creates the rule set if it does not exist.
rule_name	Contains the rule name

Usage Notes

If an apply process rule is added, then this procedure creates the apply process if it does not exist. An apply process created by this procedure can apply only user-enqueued messages, and dequeued messages are sent to the message handler for the apply process. If a messaging client rule is added, then this procedure creates a messaging client if it does not exist.

When you use this procedure to create a rule set for a message rule, the new rule set does not have an evaluation context. If no evaluation context exists for the specified message type, then this procedure creates a new evaluation context and associates it with the new rule. The evaluation context also has a system-generated name. If you create new rules that use an existing message type, then the new rules use the existing evaluation context for the message type.

See Also:

- ["Rules"](#) on page 96-2
- ["Users"](#) on page 96-8
- ["ALTER_APPLY Procedure"](#) on page 15-4 for more information about setting a message handler for an apply process

Examples

You specify the condition for this rule using the `rule_condition` parameter. For example, suppose the message type is `usr_msg`, and that this type has the following attributes: `source_dbname`, `owner`, `name`, and `message`. Given this type, the following rule condition may be specified:

```
':msg.source_dbname = 'DBS1.NET' AND ' || ':msg.owner = 'HR' AND ' ||  
':msg.name = 'EMPLOYEES'''
```

Note: The quotation marks in the preceding example are all single quotation marks.

ADD_SCHEMA_PROPAGATION_RULES Procedures

These procedures either add schema rules to the positive rule set for a propagation, or add schema rules to the negative rule set for a propagation, and create the specified propagation if it does not exist.

Note: This procedure is overloaded. One version of this procedure contains two OUT parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_SCHEMA_PROPAGATION_RULES(
  schema_name          IN   VARCHAR2,
  streams_name         IN   VARCHAR2 DEFAULT NULL,
  source_queue_name    IN   VARCHAR2,
  destination_queue_name IN VARCHAR2,
  include_dml          IN   BOOLEAN DEFAULT true,
  include_ddl          IN   BOOLEAN DEFAULT false,
  include_tagged_lcr   IN   BOOLEAN DEFAULT false,
  source_database      IN   VARCHAR2 DEFAULT NULL,
  dml_rule_name        OUT  VARCHAR2,
  ddl_rule_name        OUT  VARCHAR2,
  inclusion_rule       IN   BOOLEAN DEFAULT true,
  and_condition        IN   VARCHAR2 DEFAULT NULL);
```

Parameters

Table 96–6 ADD_SCHEMA_PROPAGATION_RULES Procedure Parameters

Parameter	Description
schema_name	The name of the schema. For example, hr.

Table 96–6 (Cont.) ADD_SCHEMA_PROPAGATION_RULES Procedure Parameters

Parameter	Description
streams_name	<p>The name of the propagation. Do not specify an owner.</p> <p>If the specified propagation does not exist, then it is created automatically.</p> <p>If <code>NULL</code> and a propagation exists for the same source queue and destination queue (including database link), then this propagation is used.</p> <p>If <code>NULL</code> and no propagation exists for the same source queue and destination queue (including database link), then a propagation is created automatically with a system-generated name.</p>
source_queue_name	<p>The name of the source queue, specified as <code>[schema_name.]queue_name</code>. The current database must contain the source queue, and the queue must be <code>SYS.AnyData</code> type.</p> <p>For example, to specify a source queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p>
destination_queue_name	<p>The name of the destination queue, including a database link, specified as <code>[schema_name.]queue_name[@dblink_name]</code>, if the destination queue is in a remote database. The queue must be <code>SYS.AnyData</code> type.</p> <p>For example, to specify a destination queue named <code>streams_queue</code> in the <code>strmadmin</code> schema and use a database link named <code>dbs2.net</code>, enter <code>strmadmin.streams_queue@dbs2.net</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p> <p>If the database link is omitted, then the global name of the current database is used, and the source queue and destination queue must be in the same database.</p> <p>Note: Connection qualifiers are not allowed.</p>
include_dml	<p>If <code>true</code>, then creates a rule for DML changes. If <code>false</code>, then does not create a DML rule. <code>NULL</code> is not permitted.</p>
include_ddl	<p>If <code>true</code>, then creates a rule for DDL changes. If <code>false</code>, then does not create a DDL rule. <code>NULL</code> is not permitted.</p>

Table 96–6 (Cont.) ADD_SCHEMA_PROPAGATION_RULES Procedure Parameters

Parameter	Description
<code>include_tagged_lcr</code>	<p>If <code>true</code>, then no condition regarding Streams tags is added to the generated rules. Therefore, these rules can evaluate to <code>TRUE</code> regardless of whether an LCR has a non-<code>NULL</code> tag. If the rules are added to the positive rule set for the propagation, then an LCR is always considered for propagation, regardless of whether it has a non-<code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>true</code> is appropriate for a full (for example, standby) copy of a database. If the rules are added to the negative rule set for the propagation, then whether an LCR is discarded does not depend on the LCR's tag.</p> <p>If <code>false</code>, then adds a condition to each generated rule that causes the rule to evaluate to <code>TRUE</code> only if an LCR has a <code>NULL</code> Streams tag. If the rules are added to the positive rule set for the propagation, then an LCR is considered for propagation only when the LCR contains a <code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>false</code> may be appropriate in update-anywhere configurations to avoid sending a change back to its source database. If the rules are added to the negative rule set for the propagation, then an LCR can be discarded only if it has a <code>NULL</code> tag.</p> <p>In most cases, specify <code>true</code> for this parameter if the <code>inclusion_rule</code> parameter is set to <code>false</code>.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>
<code>source_database</code>	<p>The global name of the source database. The source database is where the change originated. If <code>NULL</code>, then no condition regarding the source database is added to the generated rules.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p> <p>Oracle recommends that you specify a source database for propagation rules.</p>
<code>dml_rule_name</code>	<p>If <code>include_dml</code> is <code>true</code>, then contains the DML rule name.</p> <p>If <code>include_dml</code> is <code>false</code>, then contains a <code>NULL</code>.</p>

Table 96–6 (Cont.) ADD_SCHEMA_PROPAGATION_RULES Procedure Parameters

Parameter	Description
ddl_rule_name	If <code>include_ddl</code> is true, then contains the DDL rule name. If <code>include_ddl</code> is false, then contains a NULL.
inclusion_rule	If <code>inclusion_rule</code> is true, then the rules are added to the positive rule set for the propagation. If <code>inclusion_rule</code> is false, then the rules are added to the negative rule set for the propagation. In either case, the system creates the rule set if it does not exist.
and_condition	If non-NULL, appends the specified condition to the system-generated rule condition using an AND clause in the following way: <pre>(system_condition) AND (and_condition)</pre> <p>The variable in the specified condition must be <code>:lcr</code>. For example, to specify that the schema rules generated by the procedure evaluate to true only if the Streams tag is the hexadecimal equivalent of '02', specify the following condition:</p> <pre>:lcr.get_tag() = HEXTORAW('02')</pre> <p>The <code>:lcr</code> in the specified condition is converted to <code>:dml</code> or <code>:ddl</code>, depending on the rule that is being generated. If you are specifying an LCR member subprogram that is dependent on the LCR type (row or DDL), then make sure this procedure only generates the appropriate rule.</p> <p>Specifically, if you specify an LCR member subprogram that is valid only for row LCRs, then specify true for the <code>include_dml</code> parameter and false for the <code>include_ddl</code> parameter. If you specify an LCR member subprogram that is valid only for DDL LCRs, then specify false for the <code>include_dml</code> parameter and true for the <code>include_ddl</code> parameter.</p> <p>See Also: Chapter 174, "Logical Change Record TYPES"</p>

Usage Notes

This procedure creates DML and DDL rules automatically based on `include_dml` and `include_ddl` parameter values, respectively. A system-generated rule name is the schema name with a sequence number appended to it. The sequence number is

used to avoid naming conflicts. If the schema name plus the sequence number is too long, then the schema name is truncated. For the overloaded `ADD_SCHEMA_PROPAGATION_RULES` procedure this generates the rule names for DML and DDL changes. A propagation uses the rules created for filtering.

If no propagation job exists for the database link specified in the `destination_queue_name` parameter when this procedure is run, then a propagation job is created for use by the propagation. If a propagation job already exists for the specified database link, then the propagation uses the existing propagation job.

This procedure also configures propagation using the current user, and establishes a default propagation schedule. Only one propagation is allowed between the source queue and the destination queue.

Note:

- Currently, a single propagation job propagates all events that use a particular database link, even if the database link is used by multiple propagations to propagate events to multiple destination queues.
 - For a propagation to work properly, the owner of the source queue must have the necessary privileges to propagate events.
-
-

See Also:

- ["Rules"](#) on page 96-2 and ["Propagation Rules for LCRs"](#) on page 96-4 for more information about the rules created by this procedure
- ["Propagation User"](#) on page 96-9

Examples

The following is an example of a schema rule condition that may be created for DML changes:

```
:dml.get_object_owner() = 'HR' AND :dml.is_null_tag() = 'Y'  
AND :dml.get_source_database_name() = 'DBS1.NET'
```

ADD_SCHEMA_RULES Procedures

These procedures add rules to a rule set of one of the following types of Streams clients:

- Capture process rules for capturing changes to a specified schema when the `streams_type` parameter is set to `capture`. See ["Capture Process Rules for Changes in the Redo Log"](#) on page 96-3 for more information about these rules.
- Apply process rules for applying logical change records (LCRs) in a queue that contain changes to a specified schema when the `streams_type` parameter is set to `apply`. The rules may specify that the LCRs must be from a particular source database. See ["Apply Process Rules for LCRs"](#) on page 96-6 for more information about these rules.
- Messaging client rules for dequeuing user-enqueued LCRs from a queue that contain changes to a specified schema when the `streams_type` parameter is set to `dequeue`. The rules may specify that the LCRs must be from a particular source database. See ["Messaging Client Rules for LCRs"](#) on page 96-7 for more information about these rules.

Note: This procedure is overloaded. One version of this procedure contains two OUT parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_SCHEMA_RULES(
  schema_name      IN  VARCHAR2,
  streams_type     IN  VARCHAR2,
  streams_name     IN  VARCHAR2 DEFAULT NULL,
  queue_name       IN  VARCHAR2 DEFAULT 'streams_queue',
  include_dml      IN  BOOLEAN  DEFAULT true,
  include_ddl      IN  BOOLEAN  DEFAULT false,
  include_tagged_lcr IN  BOOLEAN  DEFAULT false,
  source_database  IN  VARCHAR2 DEFAULT NULL,
  dml_rule_name    OUT VARCHAR2,
  ddl_rule_name    OUT VARCHAR2,
  inclusion_rule   IN  BOOLEAN  DEFAULT true,
  and_condition    IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 96–7 ADD_SCHEMA_RULES Procedure Parameters

Parameter	Description
<code>schema_name</code>	<p>The name of the schema. For example, <code>hr</code>.</p> <p>You can specify a schema that does not yet exist, because Streams does not validate the existence of the schema.</p>
<code>streams_type</code>	<p>The type of Streams client:</p> <ul style="list-style-type: none"> ■ Specify <code>capture</code> for a capture process. ■ Specify <code>apply</code> for an apply process. ■ Specify <code>dequeue</code> for a messaging client.
<code>streams_name</code>	<p>The name of the capture process, apply process, or messaging client. Do not specify an owner.</p> <p>If the specified Streams client does not exist, then it is created automatically.</p> <p>If <code>NULL</code>, if <code>streams_type</code> is <code>capture</code> or <code>dequeue</code>, and if one relevant capture process or messaging client for the queue exists, then the relevant Streams client is used. If no relevant Streams client exists for the queue, then a Streams client is created automatically with a system-generated name. If <code>NULL</code> and multiple Streams clients of the specified <code>streams_type</code> for the queue exist, then an error is raised.</p> <p>If <code>NULL</code>, if <code>streams_type</code> is <code>apply</code>, and if one relevant apply process exists, then the relevant apply process is used. The relevant apply process is identified in one of the following ways:</p> <ul style="list-style-type: none"> ■ If one existing apply process has the source database specified in <code>source_database</code> and uses the queue specified in <code>queue_name</code>, then this apply process is used. ■ If <code>source_database</code> is <code>NULL</code> and one existing apply process is using the queue specified in <code>queue_name</code>, then this apply process is used. <p>If <code>NULL</code> and no relevant apply process exists, then an apply process is created automatically with a system-generated name. If <code>NULL</code> and multiple relevant apply processes exist, then an error is raised.</p> <p>An apply process and a messaging client cannot have the same name.</p>

Table 96–7 (Cont.) ADD_SCHEMA_RULES Procedure Parameters

Parameter	Description
queue_name	<p>The name of the local queue, specified as [<i>schema_name</i>.]<i>queue_name</i>. The current database must contain the queue, and the queue must be SYS.AnyData type.</p> <p>For example, to specify a queue named <i>streams_queue</i> in the <i>strmadmin</i> schema, enter <i>strmadmin.streams_queue</i> for this parameter. If the schema is not specified, then the current user is the default.</p> <p>For capture process rules, this is the queue into which a capture process enqueues events. For apply process rules, this is the queue from which an apply process dequeues events. For messaging client rules, this is the queue from which a messaging client dequeues events.</p>
include_dml	If <i>true</i> , then creates a rule for DML changes. If <i>false</i> , then does not create a DML rule. <i>NULL</i> is not permitted.
include_ddl	If <i>true</i> , then creates a rule for DDL changes. If <i>false</i> , then does not create a DDL rule. <i>NULL</i> is not permitted.

Table 96–7 (Cont.) ADD_SCHEMA_RULES Procedure Parameters

Parameter	Description
<code>include_tagged_lcr</code>	<p>If <code>true</code>, then no condition regarding Streams tags is added to the generated rules. Therefore, these rules can evaluate to <code>TRUE</code> regardless of whether a redo entry or LCR has a non-<code>NULL</code> tag. If the rules are added to the positive rule set for the process, then a redo entry is always considered for capture, and an LCR is always considered for apply, regardless of whether the redo entry or LCR has a non-<code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>true</code> is appropriate for a full (for example, standby) copy of a database. If the rules are added to the negative rule set for the process, then whether a redo entry or LCR is discarded does not depend on the tag.</p> <p>If <code>false</code>, then adds a condition to each generated rule that causes the rule to evaluate to <code>TRUE</code> only if a redo entry or LCR has a <code>NULL</code> Streams tag. If the rules are added to the positive rule set for the process, then a redo entry is considered for capture, and an LCR is considered for apply, only when the redo entry or LCR contains a <code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>false</code> may be appropriate in update-anywhere configurations to avoid sending a change back to its source database. If the rules are added to the negative rule set for the process, then a redo entry or LCR can be discarded only if it has a <code>NULL</code> tag.</p> <p>In most cases, specify <code>true</code> for this parameter if the <code>inclusion_rule</code> parameter is set to <code>false</code>.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>

Table 96–7 (Cont.) ADD_SCHEMA_RULES Procedure Parameters

Parameter	Description
source_database	<p>The global name of the source database. If <code>NULL</code>, then no condition regarding the source database is added to the generated rules.</p> <p>For capture process rules, specify <code>NULL</code> or the global name of the local database if you are creating a capture process locally at the source database. If you are creating a capture process at a downstream database, then specify the source database of the changes that will be captured.</p> <p>For apply process rules, specify the source database of the changes that will be applied by the apply process. The source database is the database where the changes originated. If an apply process applies captured events, then the apply process can apply events from only one capture process at one source database.</p> <p>For messaging client rules, specify <code>NULL</code> if you do not want the rules created by this procedure to have a condition for the source database. Specify a source database if you want the rules created by this procedure to have a condition for the source database. The source database is part of the information in an LCR, and user-constructed LCRs may or may not have this information.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p>
dml_rule_name	<p>If <code>include_dml</code> is <code>true</code>, then contains the DML rule name.</p> <p>If <code>include_dml</code> is <code>false</code>, then contains a <code>NULL</code>.</p>
ddl_rule_name	<p>If <code>include_ddl</code> is <code>true</code>, then contains the DDL rule name.</p> <p>If <code>include_ddl</code> is <code>false</code>, then contains a <code>NULL</code>.</p>
inclusion_rule	<p>If <code>inclusion_rule</code> is <code>true</code>, then the rules are added to the positive rule set for the Streams client.</p> <p>If <code>inclusion_rule</code> is <code>false</code>, then the rules are added to the negative rule set for the Streams client.</p> <p>In either case, the system creates the rule set if it does not exist.</p>

Table 96–7 (Cont.) ADD_SCHEMA_RULES Procedure Parameters

Parameter	Description
<code>and_condition</code>	<p>If non-NULL, appends the specified condition to the system-generated rule condition using an AND clause in the following way:</p> <pre>(system_condition) AND (and_condition)</pre> <p>The variable in the specified condition must be <code>:lcr</code>. For example, to specify that the schema rules generated by the procedure evaluate to <code>true</code> only if the Streams tag is the hexadecimal equivalent of '02', specify the following condition:</p> <pre>:lcr.get_tag() = HEXTORAW('02')</pre> <p>The <code>:lcr</code> in the specified condition is converted to <code>:dml</code> or <code>:ddl</code>, depending on the rule that is being generated. If you are specifying an LCR member subprogram that is dependent on the LCR type (row or DDL), then make sure this procedure only generates the appropriate rule.</p> <p>Specifically, if you specify an LCR member subprogram that is valid only for row LCRs, then specify <code>true</code> for the <code>include_dml</code> parameter and <code>false</code> for the <code>include_ddl</code> parameter. If you specify an LCR member subprogram that is valid only for DDL LCRs, then specify <code>false</code> for the <code>include_dml</code> parameter and <code>true</code> for the <code>include_ddl</code> parameter.</p> <p>See Also: Chapter 174, "Logical Change Record TYPES"</p>

Usage Notes

This procedure creates the specified capture process, apply process, or messaging client if it does not exist.

This procedure creates DML and DDL rules automatically based on `include_dml` and `include_ddl` parameter values, respectively. A system-generated rule name is the schema name with a sequence number appended to it. The sequence number is used to avoid naming conflicts. If the schema name plus the sequence number is too long, then the schema name is truncated. The overloaded `ADD_SCHEMA_RULES` procedure generates the rule names for DML and DDL changes. A capture process, apply process, or messaging client uses the rules created for filtering.

See Also:

- ["Rules"](#) on page 96-2
- ["Users"](#) on page 96-8

Examples

The following is an example of a schema rule condition that may be created for DML changes:

```
:dml.get_object_owner() = 'HR' AND :dml.is_null_tag() = 'Y'
```

ADD_SUBSET_PROPAGATION_RULES Procedures

These procedures add propagation rules that propagate the logical change records (LCRs) related to a subset of the rows in the specified table in a source queue to a destination queue, and creates the specified propagation if it does not exist. They also configure propagation using the current user and establishes a default propagation schedule. The procedures enables propagation of LCRs for the specified table, subject to filtering conditions.

Note: This procedure is overloaded. One version of this procedure contains three OUT parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_SUBSET_PROPAGATION_RULES(
    table_name           IN   VARCHAR2,
    dml_condition        IN   VARCHAR2,
    streams_name         IN   VARCHAR2 DEFAULT NULL,
    source_queue_name    IN   VARCHAR2,
    destination_queue_name IN VARCHAR2,
    include_tagged_lcr   IN   BOOLEAN DEFAULT false,
    source_database      IN   VARCHAR2 DEFAULT NULL,
    insert_rule_name     OUT  VARCHAR2,
    update_rule_name     OUT  VARCHAR2,
    delete_rule_name    OUT  VARCHAR2);
```

Parameters

Table 96–8 ADD_SUBSET_PROPAGATION_RULES Procedure Parameters

Parameter	Description
table_name	The name of the table specified as [<i>schema_name</i> .] <i>object_name</i> . For example, hr.employees. If the schema is not specified, then the current user is the default. The specified table must exist in the same database as the propagation. Also, the specified table cannot have any LOB, LONG, or LONG RAW columns currently or in the future.

Table 96–8 (Cont.) ADD_SUBSET_PROPAGATION_RULES Procedure Parameters

Parameter	Description
dml_condition	<p>The subset condition. You specify this condition similar to the way you specify conditions in a <code>WHERE</code> clause in SQL.</p> <p>For example, to specify rows in the <code>hr.employees</code> table where the <code>salary</code> is greater than 4000 and the <code>job_id</code> is <code>SA_MAN</code>, enter the following as the condition:</p> <pre>' salary > 4000 and job_id = 'SA_MAN' '</pre> <p>Note: The quotation marks in the preceding example are all single quotation marks.</p>
streams_name	<p>The name of the propagation. Do not specify an owner.</p> <p>If the specified propagation does not exist, then it is created automatically.</p> <p>If <code>NULL</code> and a propagation exists for the same source queue and destination queue (including database link), then this propagation is used.</p> <p>If <code>NULL</code> and no propagation exists for the same source queue and destination queue (including database link), then a propagation is created automatically with a system-generated name.</p>
source_queue_name	<p>The name of the source queue, specified as [<code>schema_name.</code>] <code>queue_name</code>. The current database must contain the source queue, and the queue must be <code>SYS.AnyData</code> type.</p> <p>For example, to specify a source queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p>

Table 96–8 (Cont.) ADD_SUBSET_PROPAGATION_RULES Procedure Parameters

Parameter	Description
<code>destination_queue_name</code>	<p>The name of the destination queue, including a database link, specified as <code>[schema_name.]queue_name[@dblink_name]</code>, if the destination queue is in a remote database. The queue must be <code>SYS.AnyData</code> type.</p> <p>For example, to specify a destination queue named <code>streams_queue</code> in the <code>strmadmin</code> schema and use a database link named <code>db2.net</code>, enter <code>strmadmin.streams_queue@db2.net</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p> <p>If the database link is omitted, then the global name of the current database is used, and the source queue and destination queue must be in the same database.</p> <p>Note: Connection qualifiers are not allowed.</p>
<code>include_tagged_lcr</code>	<p>If <code>true</code>, then an LCR is always considered for propagation, regardless of whether it has a non-NULL tag. This setting is appropriate for a full (for example, standby) copy of a database.</p> <p>If <code>false</code>, then an LCR is considered for propagation only when the LCR contains a NULL tag. A setting of <code>false</code> is often specified in update-anywhere configurations to avoid sending a change back to its source database.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>
<code>source_database</code>	<p>The global name of the source database. The source database is where the change originated. If NULL, then no condition regarding the source database is added to the generated rules.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p> <p>Oracle recommends that you specify a source database for propagation rules.</p>
<code>insert_rule_name</code>	<p>Contains the system-generated INSERT rule name. This rule handles inserts, as well as updates that must be converted into inserts.</p>

Table 96–8 (Cont.) ADD_SUBSET_PROPAGATION_RULES Procedure Parameters

Parameter	Description
update_rule_name	Contains the system-generated UPDATE rule name. This rule handles updates that remain updates.
delete_rule_name	Contains the system-generated DELETE rule name. This rule handles deletes, as well as updates that must be converted into deletes

Usage Notes

Only one propagation is allowed between the source queue and the destination queue.

Running this procedure generates three rules for the specified propagation: one for INSERT statements, one for UPDATE statements, and one for DELETE statements. For INSERT and DELETE statements, only row LCRs that satisfy the condition specified for the `dml_condition` parameter are propagated. For UPDATE statements, the following variations are possible:

- If both the new and old values in a row LCR satisfy the specified `dml_condition`, then the row LCR is propagated without any changes.
- If neither the new or old values in a row LCR satisfy the specified `dml_condition`, then the row LCR is not propagated.
- If the old values for a row LCR satisfy the specified `dml_condition`, but the new values do not, then the update row LCR is converted into a delete row LCR.
- If the new values for a row LCR satisfy the specified `dml_condition`, but the old values do not, then the update row LCR is converted to an insert row LCR.

When an update is converted into an insert or a delete, it is called row migration.

A propagation uses the rules created for filtering. If the propagation does not have a positive rule set, then a positive rule set is created automatically, and the rules for propagating changes to the table are added to the positive rule set. A subset rule can be added to positive rule set only, not to a negative rule set. Other rules in an existing positive rule set for the propagation are not affected. Additional rules can be added using either the `DBMS_STREAMS_ADM` package or the `DBMS_RULE_ADM` package.

Rules for INSERT, UPDATE, and DELETE statements are created automatically when you run this procedure, and these rules are given a system-generated rule name.

The system-generated rule name is the table name with a sequence number appended to it. The sequence number is used to avoid naming conflicts. If the table name plus the sequence number is too long, then the table name is truncated. The `ADD_SUBSET_RULES` procedure is overloaded, and the system-generated rule names for `INSERT`, `UPDATE`, and `DELETE` statements are returned.

When you create propagation subset rules for a table, you should create an unconditional supplemental log group at the source database with all the columns in the table. Supplemental logging is required if an update must be converted to an insert. The propagation rule must have all the column values to be able to perform this conversion correctly.

For a propagation to work properly, the owner of the source queue must have the necessary privileges to propagate events.

If no propagation job exists for the database link specified in the `destination_queue_name` parameter when this procedure is run, then a propagation job is created for use by the propagation. If a propagation job already exists for the specified database link, then the propagation uses the existing propagation job.

Attention: Subset rules should only reside in positive rule sets. You should not add subset rules to negative rule sets. Doing so may have unpredictable results because row migration would not be performed on LCRs that are not discarded by the negative rule set.

Note: Currently, a single propagation job propagates all events that use a particular database link, even if the database link is used by multiple propagations to propagate events to multiple destination queues.

See Also:

- ["Rules"](#) on page 96-2 and ["Propagation Rules for LCRs"](#) on page 96-4 for more information about the rules created by this procedure
- ["Propagation User"](#) on page 96-9

Examples

The following is an example of a rule condition that may be created for filtering a row LCR containing an update operation when the `dml_condition` is `region_id = 2` and the `table_name` is `hr.regions`:

```
:dml.get_object_owner() = 'HR' AND :dml.get_object_name() = 'REGIONS' AND  
:dml.is_null_tag() = 'Y' AND :dml.get_command_type() = 'UPDATE' AND (:dml.get_  
value('NEW', 'REGION_ID') IS NOT NULL) AND (:dml.get_value('OLD', 'REGION_ID')  
IS NOT NULL) AND (:dml.get_value('OLD', 'REGION_ID').AccessNumber()=2) AND  
(:dml.get_value('NEW', 'REGION_ID').AccessNumber()=2)
```

ADD_SUBSET_RULES Procedures

These procedures add rules to a rule set of one of the following types of Streams clients:

- Capture process rules for capturing changes to a subset of rows in a specified table when the `streams_type` parameter is set to `capture`. See ["Capture Process Rules for Changes in the Redo Log"](#) on page 96-3 for more information about these rules.
- Apply process rules for applying logical change records (LCRs) in a queue that contain changes to a subset of rows in a specified table when the `streams_type` parameter is set to `apply`. The rules may specify that the LCRs must be from a particular source database. See ["Apply Process Rules for LCRs"](#) on page 96-6 for more information about these rules.
- Messaging client rules for dequeuing user-enqueued LCRs from a queue that contain changes to a subset of rows in a specified table when the `streams_type` parameter is set to `dequeue`. The rules may specify that the LCRs must be from a particular source database. See ["Messaging Client Rules for LCRs"](#) on page 96-7 for more information about these rules.

Note: This procedure is overloaded. One version of this procedure contains three `OUT` parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_SUBSET_RULES(  
    table_name          IN    VARCHAR2,  
    dml_condition       IN    VARCHAR2,  
    streams_type        IN    VARCHAR2 DEFAULT 'apply',  
    streams_name        IN    VARCHAR2 DEFAULT NULL,  
    queue_name          IN    VARCHAR2 DEFAULT 'streams_queue',  
    include_tagged_lcr  IN    BOOLEAN  DEFAULT false,  
    source_database     IN    VARCHAR2 DEFAULT NULL,  
    insert_rule_name    OUT   VARCHAR2,  
    update_rule_name    OUT   VARCHAR2,  
    delete_rule_name   OUT   VARCHAR2);
```

Parameters

Table 96–9 *ADD_SUBSET_RULES Procedure Parameters*

Parameter	Description
table_name	<p>The name of the table specified as [<i>schema_name</i>.]<i>object_name</i>. For example, <i>hr.employees</i>. If the schema is not specified, then the current user is the default.</p> <p>The specified table must exist in the same database as the capture process, apply process, or messaging client. Also, the specified table cannot have any LOB, LONG, or LONG RAW columns currently or in the future.</p>
dml_condition	<p>The subset condition. You specify this condition similar to the way you specify conditions in a <i>WHERE</i> clause in SQL.</p> <p>For example, to specify rows in the <i>hr.employees</i> table where the <i>salary</i> is greater than 4000 and the <i>job_id</i> is <i>SA_MAN</i>, enter the following as the condition:</p> <pre>' salary > 4000 and job_id = 'SA_MAN' '</pre> <p>Note: The quotation marks in the preceding example are all single quotation marks.</p>
streams_type	<p>The type of Streams client:</p> <ul style="list-style-type: none"> ■ Specify <i>capture</i> for a capture process. ■ Specify <i>apply</i> for an apply process. ■ Specify <i>dequeue</i> for a messaging client.

Table 96–9 (Cont.) ADD_SUBSET_RULES Procedure Parameters

Parameter	Description
<code>streams_name</code>	<p>The name of the capture process, apply process, or messaging client. Do not specify an owner.</p> <p>If the specified Streams client does not exist, then it is created automatically.</p> <p>If <code>NULL</code>, if <code>streams_type</code> is <code>capture</code> or <code>dequeue</code>, and if one relevant capture process or messaging client for the queue exists, then the relevant Streams client is used. If no relevant Streams client exists for the queue, then a Streams client is created automatically with a system-generated name. If <code>NULL</code> and multiple Streams clients of the specified <code>streams_type</code> for the queue exist, then an error is raised.</p> <p>If <code>NULL</code>, if <code>streams_type</code> is <code>apply</code>, and if one relevant apply process exists, then the relevant apply process is used. The relevant apply process is identified in one of the following ways:</p> <ul style="list-style-type: none"> ▪ If one existing apply process has the source database specified in <code>source_database</code> and uses the queue specified in <code>queue_name</code>, then this apply process is used. ▪ If <code>source_database</code> is <code>NULL</code> and one existing apply process is using the queue specified in <code>queue_name</code>, then this apply process is used. <p>If <code>NULL</code> and no relevant apply process exists, then an apply process is created automatically with a system-generated name. If <code>NULL</code> and multiple relevant apply processes exist, then an error is raised.</p> <p>An apply process and a messaging client cannot have the same name.</p>
<code>queue_name</code>	<p>The name of the local queue, specified as [<code>schema_name</code> .]<code>queue_name</code>. The current database must contain the queue, and the queue must be <code>SYS.AnyData</code> type.</p> <p>For example, to specify a queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter. If the schema is not specified, then the current user is the default.</p> <p>For capture process rules, this is the queue into which a capture process enqueues events. For apply process rules, this is the queue from which an apply process dequeues events. For messaging client rules, this is the queue from which a messaging client dequeues events.</p>

Table 96–9 (Cont.) ADD_SUBSET_RULES Procedure Parameters

Parameter	Description
<code>include_tagged_lcr</code>	<p>If <code>true</code>, then a redo entry is always considered for capture and an LCR is always considered for apply or dequeue, regardless of whether redo entry or LCR has a non-NULL tag. This setting is appropriate for a full (for example, standby) copy of a database.</p> <p>If <code>false</code>, then a redo entry is considered for capture and an LCR is considered for apply or dequeue only when the redo entry or the LCR contains a NULL tag. A setting of <code>false</code> is often specified in update-anywhere configurations to avoid sending a change back to its source database.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>
<code>source_database</code>	<p>The global name of the source database. If NULL, then no condition regarding the source database is added to the generated rules.</p> <p>For capture process rules, specify NULL or the global name of the local database if you are creating a capture process locally at the source database. If you are creating a capture process at a downstream database, then specify the source database of the changes that will be captured.</p> <p>For apply process rules, specify the source database of the changes that will be applied by the apply process. The source database is the database where the changes originated. If an apply process applies captured events, then the apply process can apply events from only one capture process at one source database.</p> <p>For messaging client rules, specify NULL if you do not want the rules created by this procedure to have a condition for the source database. Specify a source database if you want the rules created by this procedure to have a condition for the source database. The source database is part of the information in an LCR, and user-constructed LCRs may or may not have this information.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p>
<code>insert_rule_name</code>	<p>Contains the system-generated INSERT rule name. This rule handles inserts, as well as updates that must be converted into inserts.</p>

Table 96–9 (Cont.) ADD_SUBSET_RULES Procedure Parameters

Parameter	Description
update_rule_name	Contains the system-generated UPDATE rule name. This rule handles updates that remain updates.
delete_rule_name	Contains the system-generated DELETE rule name. This rule handles deletes, as well as updates that must be converted into deletes

Usage Notes

This procedure creates the specified capture process, apply process, or messaging client if it does not exist.

Running this procedure generates three rules for the specified capture process, apply process, or messaging client: one for INSERT statements, one for UPDATE statements, and one for DELETE statements. For INSERT and DELETE statements, only DML changes that satisfy the condition specified for the `dml_condition` parameter are captured, applied, or dequeued. For UPDATE statements, the following variations are possible:

- If both the new and old values in a DML change satisfy the specified `dml_condition`, then the DML change is captured, applied, or dequeued without any changes.
- If neither the new or old values in a DML change satisfy the specified `dml_condition`, then the DML change is not captured, applied, or dequeued.
- If the old values for a DML change satisfy the specified `dml_condition`, but the new values do not, then the DML change is converted into a delete.
- If the new values for a DML change satisfy the specified `dml_condition`, but the old values do not, then the DML change is converted to an insert.

When an update is converted into an insert or a delete, it is called row migration.

A capture process, apply process, or messaging client uses the rules created for filtering. If the Streams client does not have a positive rule set, then a positive rule set is created automatically, and the rules for the table are added to the positive rule set. A subset rule can be added to positive rule set only, not to a negative rule set. Other rules in an existing rule set for the process are not affected. Additional rules can be added using either the `DBMS_STREAMS_ADM` package or the `DBMS_RULE_ADM` package.

Rules for INSERT, UPDATE, and DELETE statements are created automatically when you run this procedure, and these rules are given a system-generated rule name.

The system-generated rule name is the table name with a sequence number appended to it. The sequence number is used to avoid naming conflicts. If the table name plus the sequence number is too long, then the table name is truncated. The `ADD_SUBSET_RULES` procedure is overloaded, and the system-generated rule names for `INSERT`, `UPDATE`, and `DELETE` statements are returned.

Attention: Subset rules should only reside in positive rule sets. You should not add subset rules to negative rule sets. Doing so may have unpredictable results because row migration would not be performed on LCRs that are not discarded by the negative rule set.

See Also:

- ["Rules"](#) on page 96-2
- ["Users"](#) on page 96-8

Examples

The following is an example of a rule condition that may be created for filtering DML changes containing an update operation when the `dml_condition` is `region_id = 2` and the `table_name` is `hr.regions`:

```
:dml.get_object_owner() = 'HR' AND :dml.get_object_name() = 'REGIONS' AND  
:dml.is_null_tag() = 'Y' AND :dml.get_command_type() = 'UPDATE' AND (:dml.get_  
value('NEW', 'REGION_ID') IS NOT NULL) AND (:dml.get_value('OLD', 'REGION_ID')  
IS NOT NULL) AND (:dml.get_value('OLD', 'REGION_ID').AccessNumber()=2) AND  
(:dml.get_value('NEW', 'REGION_ID').AccessNumber()=2)
```

ADD_TABLE_PROPAGATION_RULES Procedure

These procedures add table rules to the positive rule set for a propagation, or add table rules to the negative rule set for a propagation, and create the specified propagation if it does not exist.

Note: This procedure is overloaded. One version of this procedure contains two OUT parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_TABLE_PROPAGATION_RULES(
    table_name           IN   VARCHAR2,
    streams_name        IN   VARCHAR2 DEFAULT NULL,
    source_queue_name   IN   VARCHAR2,
    destination_queue_name IN VARCHAR2,
    include_dml         IN   BOOLEAN DEFAULT true,
    include_ddl         IN   BOOLEAN DEFAULT false,
    include_tagged_lcr  IN   BOOLEAN DEFAULT false,
    source_database     IN   VARCHAR2 DEFAULT NULL,
    dml_rule_name       OUT  VARCHAR2,
    ddl_rule_name       OUT  VARCHAR2,
    inclusion_rule      IN   BOOLEAN DEFAULT true,
    and_condition       IN   VARCHAR2 DEFAULT NULL);
```

Parameters

Table 96–10 ADD_TABLE_PROPAGATION_RULES Procedure Parameters

Parameter	Description
table_name	The name of the table specified as [<i>schema_name</i> .] <i>object_name</i> . For example, hr.employees. If the schema is not specified, then the current user is the default.

Table 96–10 (Cont.) ADD_TABLE_PROPAGATION_RULES Procedure Parameters

Parameter	Description
streams_name	<p>The name of the propagation. Do not specify an owner.</p> <p>If the specified propagation does not exist, then it is created automatically.</p> <p>If <code>NULL</code> and a propagation exists for the same source queue and destination queue (including database link), then this propagation is used.</p> <p>If <code>NULL</code> and no propagation exists for the same source queue and destination queue (including database link), then a propagation is created automatically with a system-generated name.</p>
source_queue_name	<p>The name of the source queue, specified as <code>[schema_name .] queue_name</code>. The current database must contain the source queue, and the queue must be <code>SYS.AnyData</code> type.</p> <p>For example, to specify a source queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p>
destination_queue_name	<p>The name of the destination queue, including a database link, specified as <code>[schema_name .] queue_name [@dblink_name]</code>, if the destination queue is in a remote database. The queue must be <code>SYS.AnyData</code> type.</p> <p>For example, to specify a destination queue named <code>streams_queue</code> in the <code>strmadmin</code> schema and use a database link named <code>dbs2.net</code>, enter <code>strmadmin.streams_queue@dbs2.net</code> for this parameter.</p> <p>If the schema is not specified, then the current user is the default.</p> <p>If the database link is omitted, then the global name of the current database is used, and the source queue and destination queue must be in the same database.</p> <p>Note: Connection qualifiers are not allowed.</p>
include_dml	<p>If <code>true</code>, then creates a rule for DML changes. If <code>false</code>, then does not create a DML rule. <code>NULL</code> is not permitted.</p>
include_ddl	<p>If <code>true</code>, then creates a rule for DDL changes. If <code>false</code>, then does not create a DDL rule. <code>NULL</code> is not permitted.</p>

Table 96–10 (Cont.) ADD_TABLE_PROPAGATION_RULES Procedure Parameters

Parameter	Description
<code>include_tagged_lcr</code>	<p>If <code>true</code>, then no condition regarding Streams tags is added to the generated rules. Therefore, these rules can evaluate to <code>TRUE</code> regardless of whether an LCR has a non-<code>NULL</code> tag. If the rules are added to the positive rule set for the propagation, then an LCR is always considered for propagation, regardless of whether it has a non-<code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>true</code> is appropriate for a full (for example, standby) copy of a database. If the rules are added to the negative rule set for the propagation, then whether an LCR is discarded does not depend on the LCR's tag.</p> <p>If <code>false</code>, then adds a condition to each generated rule that causes the rule to evaluate to <code>TRUE</code> only if an LCR has a <code>NULL</code> Streams tag. If the rules are added to the positive rule set for the propagation, then an LCR is considered for propagation only when the LCR contains a <code>NULL</code> tag. If the rules are added to a positive rule set, then setting this parameter to <code>false</code> may be appropriate in update-anywhere configurations to avoid sending a change back to its source database. If the rules are added to the negative rule set for the propagation, then an LCR can be discarded only if it has a <code>NULL</code> tag.</p> <p>In most cases, specify <code>true</code> for this parameter if the <code>inclusion_rule</code> parameter is set to <code>false</code>.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>
<code>source_database</code>	<p>The global name of the source database. The source database is where the change originated. If <code>NULL</code>, then no condition regarding the source database is added to the generated rules.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p> <p>Oracle recommends that you specify a source database for propagation rules.</p>
<code>dml_rule_name</code>	<p>If <code>include_dml</code> is <code>true</code>, then contains the DML rule name.</p> <p>If <code>include_dml</code> is <code>false</code>, then contains a <code>NULL</code>.</p>

Table 96–10 (Cont.) ADD_TABLE_PROPAGATION_RULES Procedure Parameters

Parameter	Description
ddl_rule_name	If <code>include_ddl</code> is true, then contains the DDL rule name. If <code>include_ddl</code> is false, then contains a NULL.
inclusion_rule	If <code>inclusion_rule</code> is true, then the rules are added to the positive rule set for the propagation. If <code>inclusion_rule</code> is false, then the rules are added to the negative rule set for the propagation. In either case, the system creates the rule set if it does not exist.
and_condition	If non-NULL, appends the specified condition to the system-generated rule condition using an AND clause in the following way: <pre>(system_condition) AND (and_condition)</pre> <p>The variable in the specified condition must be <code>:lcr</code>. For example, to specify that the table rules generated by the procedure evaluate to true only if the Streams tag is the hexadecimal equivalent of '02', specify the following condition:</p> <pre>:lcr.get_tag() = HEXTORAW('02')</pre> <p>The <code>:lcr</code> in the specified condition is converted to <code>:dml</code> or <code>:ddl</code>, depending on the rule that is being generated. If you are specifying an LCR member subprogram that is dependent on the LCR type (row or DDL), then make sure this procedure only generates the appropriate rule.</p> <p>Specifically, if you specify an LCR member subprogram that is valid only for row LCRs, then specify true for the <code>include_dml</code> parameter and false for the <code>include_ddl</code> parameter. If you specify an LCR member subprogram that is valid only for DDL LCRs, then specify false for the <code>include_dml</code> parameter and true for the <code>include_ddl</code> parameter.</p> <p>See Also: Chapter 174, "Logical Change Record TYPES"</p>

Usage Notes

This procedure creates DML and DDL rules automatically based on `include_dml` and `include_ddl` parameter values, respectively. A system-generated rule name is the table name with a sequence number appended to it. The sequence number is

used to avoid naming conflicts. If the table name plus the sequence number is too long, then the table name is truncated. The overloaded `ADD_TABLE_PROPAGATION_RULES` procedure generates the rule names for DML and DDL changes. A propagation uses the rules created for filtering.

If no propagation job exists for the database link specified in the `destination_queue_name` parameter when this procedure is run, then a propagation job is created for use by the propagation. If a propagation job already exists for the specified database link, then the propagation uses the existing propagation job.

This procedure also configures propagation using the current user, and establishes a default propagation schedule. Only one propagation is allowed between the source queue and the destination queue.

Note:

- Currently, a single propagation job propagates all events that use a particular database link, even if the database link is used by multiple propagations to propagate events to multiple destination queues.
 - For a propagation to work properly, the owner of the source queue must have the necessary privileges to propagate events.
-
-

See Also:

- ["Rules"](#) on page 96-2 and ["Propagation Rules for LCRs"](#) on page 96-4 for more information about the rules created by this procedure
- ["Users"](#) on page 96-8

Examples

The following is an example of a table rule condition that may be created for filtering DML statements:

```
:dml.get_object_owner() = 'HR' AND :dml.get_object_name() = 'LOCATIONS'  
AND :dml.is_null_tag() = 'Y' AND :dml.get_source_database_name() = 'DBS1.NET'
```

ADD_TABLE_RULES Procedures

These procedures add rules to a rule set of one of the following types of Streams clients:

- Capture process rules for capturing changes to a specified table when the `streams_type` parameter is set to `capture`. See ["Capture Process Rules for Changes in the Redo Log"](#) on page 96-3 for more information about these rules.
- Apply process rules for applying logical change records (LCRs) in a queue that contain changes to a specified table when the `streams_type` parameter is set to `apply`. The rules may specify that the LCRs must be from a particular source database. See ["Apply Process Rules for LCRs"](#) on page 96-6 for more information about these rules.
- Messaging client rules for dequeuing user-enqueued LCRs from a queue that contain changes to a specified table when the `streams_type` parameter is set to `dequeue`. The rules may specify that the LCRs must be from a particular source database. See ["Messaging Client Rules for LCRs"](#) on page 96-7 for more information about these rules.

Note: This procedure is overloaded. One version of this procedure contains two `OUT` parameters, and the other does not.

Syntax

```
DBMS_STREAMS_ADM.ADD_TABLE_RULES(
  table_name          IN  VARCHAR2,
  streams_type        IN  VARCHAR2,
  streams_name        IN  VARCHAR2 DEFAULT NULL,
  queue_name          IN  VARCHAR2 DEFAULT 'streams_queue',
  include_dml         IN  BOOLEAN  DEFAULT true,
  include_ddl         IN  BOOLEAN  DEFAULT false,
  include_tagged_lcr  IN  BOOLEAN  DEFAULT false,
  source_database     IN  VARCHAR2 DEFAULT NULL,
  dml_rule_name       OUT VARCHAR2,
  ddl_rule_name       OUT VARCHAR2,
  inclusion_rule      IN  BOOLEAN  DEFAULT true,
  and_condition       IN  VARCHAR2 DEFAULT NULL);
```

Parameters

Table 96–11 ADD_TABLE_RULES Procedure Parameters

Parameter	Description
table_name	<p>The name of the table specified as [<i>schema_name</i>.]<i>object_name</i>. For example, <i>hr.employees</i>. If the schema is not specified, then the current user is the default.</p> <p>You can specify a table that does not yet exist, because Streams does not validate the existence of the table.</p>
streams_type	<p>The type of Streams client:</p> <ul style="list-style-type: none"> ■ Specify <i>capture</i> for a capture process. ■ Specify <i>apply</i> for an apply process. ■ Specify <i>dequeue</i> for a messaging client.
streams_name	<p>The name of the capture process, apply process, or messaging client. Do not specify an owner.</p> <p>If the specified Streams client does not exist, then it is created automatically.</p> <p>If <i>NULL</i>, if <i>streams_type</i> is <i>capture</i> or <i>dequeue</i>, and if one relevant capture process or messaging client for the queue exists, then the relevant Streams client is used. If no relevant Streams client exists for the queue, then a Streams client is created automatically with a system-generated name. If <i>NULL</i> and multiple Streams clients of the specified <i>streams_type</i> for the queue exist, then an error is raised.</p> <p>If <i>NULL</i>, if <i>streams_type</i> is <i>apply</i>, and if one relevant apply process exists, then the relevant apply process is used. The relevant apply process is identified in one of the following ways:</p> <ul style="list-style-type: none"> ■ If one existing apply process has the source database specified in <i>source_database</i> and uses the queue specified in <i>queue_name</i>, then this apply process is used. ■ If <i>source_database</i> is <i>NULL</i> and one existing apply process is using the queue specified in <i>queue_name</i>, then this apply process is used. <p>If <i>NULL</i> and no relevant apply process exists, then an apply process is created automatically with a system-generated name. If <i>NULL</i> and multiple relevant apply processes exist, then an error is raised.</p> <p>An apply process and a messaging client cannot have the same name.</p>

Table 96–11 (Cont.) ADD_TABLE_RULES Procedure Parameters

Parameter	Description
queue_name	<p>The name of the local queue, specified as [<i>schema_name</i>.]<i>queue_name</i>. The current database must contain the queue, and the queue must be SYS.AnyData type.</p> <p>For example, to specify a queue named <i>streams_queue</i> in the <i>strmadmin</i> schema, enter <i>strmadmin.streams_queue</i> for this parameter. If the schema is not specified, then the current user is the default.</p> <p>For capture process rules, this is the queue into which a capture process enqueues events. For apply process rules, this is the queue from which an apply process dequeues events. For messaging client rules, this is the queue from which a messaging client dequeues events.</p>
include_dml	If <i>true</i> , then creates a DML rule for DML changes. If <i>false</i> , then does not create a DML rule. NULL is not permitted.
include_ddl	If <i>true</i> , then creates a DDL rule for DDL changes. If <i>false</i> , then does not create a DDL rule. NULL is not permitted.

Table 96–11 (Cont.) ADD_TABLE_RULES Procedure Parameters

Parameter	Description
include_tagged_lcr	<p>If <code>true</code>, then no condition regarding Streams tags is added to the generated rules. Therefore, these rules can evaluate to <code>TRUE</code> regardless of whether a redo entry or LCR has a non-NULL tag. If the rules are added to the positive rule set for the process, then a redo entry is always considered for capture, and an LCR is always considered for apply, regardless of whether the redo entry or LCR has a non-NULL tag. If the rules are added to a positive rule set, then setting this parameter to <code>true</code> is appropriate for a full (for example, standby) copy of a database. If the rules are added to the negative rule set for the process, then whether a redo entry or LCR is discarded does not depend on the tag.</p> <p>If <code>false</code>, then adds a condition to each generated rule that causes the rule to evaluate to <code>TRUE</code> only if a redo entry or LCR has a NULL Streams tag. If the rules are added to the positive rule set for the process, then a redo entry is considered for capture, and an LCR is considered for apply, only when the redo entry or LCR contains a NULL tag. If the rules are added to a positive rule set, then setting this parameter to <code>false</code> may be appropriate in update-anywhere configurations to avoid sending a change back to its source database. If the rules are added to the negative rule set for the process, then a redo entry or LCR can be discarded only if it has a NULL tag.</p> <p>In most cases, specify <code>true</code> for this parameter if the <code>inclusion_rule</code> parameter is set to <code>false</code>.</p> <p>See Also: <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>

Table 96–11 (Cont.) ADD_TABLE_RULES Procedure Parameters

Parameter	Description
source_database	<p>The global name of the source database. If <code>NULL</code>, then no condition regarding the source database is added to the generated rules.</p> <p>For capture process rules, specify <code>NULL</code> or the global name of the local database if you are creating a capture process locally at the source database. If you are creating a capture process at a downstream database, then specify the source database of the changes that will be captured.</p> <p>For apply process rules, specify the source database of the changes that will be applied by the apply process. The source database is the database where the changes originated. If an apply process applies captured events, then the apply process can apply events from only one capture process at one source database.</p> <p>For messaging client rules, specify <code>NULL</code> if you do not want the rules created by this procedure to have a condition for the source database. Specify a source database if you want the rules created by this procedure to have a condition for the source database. The source database is part of the information in an LCR, and user-constructed LCRs may or may not have this information.</p> <p>If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify <code>DBS1</code> and the domain is <code>.NET</code>, then <code>DBS1.NET</code> is specified automatically.</p>
dml_rule_name	<p>If <code>include_dml</code> is <code>true</code>, then contains the DML rule name.</p> <p>If <code>include_dml</code> is <code>false</code>, then contains a <code>NULL</code>.</p>
ddl_rule_name	<p>If <code>include_ddl</code> is <code>true</code>, then contains the DDL rule name.</p> <p>If <code>include_ddl</code> is <code>false</code>, then contains a <code>NULL</code>.</p>
inclusion_rule	<p>If <code>inclusion_rule</code> is <code>true</code>, then the rules are added to the positive rule set for the Streams client.</p> <p>If <code>inclusion_rule</code> is <code>false</code>, then the rules are added to the negative rule set for the Streams client.</p> <p>In either case, the system creates the rule set if it does not exist.</p>

Table 96–11 (Cont.) ADD_TABLE_RULES Procedure Parameters

Parameter	Description
<code>and_condition</code>	<p>If non-NULL, appends the specified condition to the system-generated rule condition using an AND clause in the following way:</p> <pre>(system_condition) AND (and_condition)</pre> <p>The variable in the specified condition must be <code>:lcr</code>. For example, to specify that the table rules generated by the procedure evaluate to <code>true</code> only if the Streams tag is the hexadecimal equivalent of '02', specify the following condition:</p> <pre>:lcr.get_tag() = HEXTORAW('02')</pre> <p>The <code>:lcr</code> in the specified condition is converted to <code>:dml</code> or <code>:ddl</code>, depending on the rule that is being generated. If you are specifying an LCR member subprogram that is dependent on the LCR type (row or DDL), then make sure this procedure only generates the appropriate rule.</p> <p>Specifically, if you specify an LCR member subprogram that is valid only for row LCRs, then specify <code>true</code> for the <code>include_dml</code> parameter and <code>false</code> for the <code>include_ddl</code> parameter. If you specify an LCR member subprogram that is valid only for DDL LCRs, then specify <code>false</code> for the <code>include_dml</code> parameter and <code>true</code> for the <code>include_ddl</code> parameter.</p> <p>See Also: Chapter 174, "Logical Change Record TYPES"</p>

Usage Notes

This procedure creates the specified capture process, apply process, or messaging client if it does not exist.

This procedure creates DML and DDL rules automatically based on `include_dml` and `include_ddl` parameter values, respectively. A system-generated rule name is the table name with a sequence number appended to it. The sequence number is used to avoid naming conflicts. If the table name plus the sequence number is too long, then the table name is truncated. The overloaded `ADD_TABLE_RULES` procedure generates the rule names for DML and DDL changes. A capture process, apply process, or messaging client uses the rules created for filtering.

See Also:

- ["Rules"](#) on page 96-2
- ["Users"](#) on page 96-8

Examples

The following is an example of a table rule condition that may be created for DML changes:

```
:dml.get_object_owner() = 'HR' and :dml.get_object_name() = 'EMPLOYEES'  
AND :dml.is_null_tag() = 'Y' AND :dml.get_source_database_name() = 'DBS1.NET'
```

GET_SCN_MAPPING Procedure

This procedure gets information about the system change number (SCN) values to use for Streams capture and apply processes in a Streams replication environment. This information can be used for the following purposes:

- To recover transactions after point-in-time recovery is performed on a source database in a multiple source Streams environment
- To run flashback queries for the corresponding SCN at a source database and destination database in a Streams single source replication environment

See Also: *Oracle Streams Replication Administrator's Guide* for information about point-in-time recovery and flashback queries in a Streams replication environment

Syntax

```
DBMS_STREAMS_ADM.GET_SCN_MAPPING(
  apply_name          IN  VARCHAR2,
  src_pit_scn         IN  NUMBER,
  dest_instantiation_scn OUT NUMBER,
  dest_start_scn      OUT NUMBER,
  dest_skip_txn_ids   OUT DBMS_UTILITY.NAME_ARRAY);
```

Parameters

Table 96–12 *GET_SCN_MAPPING Procedure Parameters*

Parameter	Description
apply_name	Name of the apply process which applies LCRs from the source database. An error is raised if the specified apply process does not exist.
src_pit_scn	The SCN at the source database. For point-in-time recovery, specify the point-in-time recovery SCN at the source database. If the specified SCN is greater than the source commit SCN of the last applied transaction, then NULL is returned for both <code>dest_start_scn</code> and <code>dest_instantiation_scn</code> . In this case, no values can be returned for these parameters because the corresponding transaction has not been applied at the destination database yet.

Table 96–12 (Cont.) GET_SCN_MAPPING Procedure Parameters

Parameter	Description
<code>dest_instantiation_scn</code>	<p>The SCN at the destination database that corresponds to the specified <code>src_pit_scn</code> at the source database.</p> <p>For point-in-time recovery, use this value for the instantiation SCNs at the source database during recovery.</p>
<code>dest_start_scn</code>	<p>For point in time recovery, the SCN to use for the <code>start_scn</code> parameter for the recovery capture process.</p>
<code>dest_skip_txn_ids</code>	<p>Transaction IDs of transactions that were skipped at the <code>dest_instantiation_scn</code> because the apply process was applying non-dependent transactions out of order.</p> <p>For point in time recovery, these transaction IDs should be ignored by the recovery apply process.</p> <p>This parameter is relevant only if the <code>commit_serialization</code> for the apply process that applied these transactions was set to <code>none</code>, and the transactions were applied out of order.</p>

MAINTAIN_SIMPLE_TABLESPACE Procedure

This procedure clones a simple tablespace from a source database at a destination database and uses Streams to maintain this tablespace at both databases. This procedure either can perform these actions directly, or it can generate a script that performs these actions.

Syntax

```
DBMS_STREAMS_ADM.MAINTAIN_SIMPLE_TABLESPACE(
    tablespace_name          IN VARCHAR2,
    source_directory_object  IN VARCHAR2,
    destination_directory_object IN VARCHAR2,
    destination_database     IN VARCHAR2,
    setup_streams           IN BOOLEAN   DEFAULT true,
    script_name             IN VARCHAR2  DEFAULT NULL,
    script_directory_object IN VARCHAR2  DEFAULT NULL,
    bi_directional          IN BOOLEAN   DEFAULT false);
```

Parameters

Table 96–13 MAINTAIN_SIMPLE_TABLESPACE Procedure Parameters

Parameter	Description
tablespace_name	<p>The local simple tablespace to be cloned at the destination database and maintained by Streams.</p> <p>A directory object must exist for the directory that contains the datafile for the tablespace. The user who invokes this procedure must have <code>READ</code> privilege on this directory object.</p> <p>If <code>NULL</code>, then an error is raised.</p>
source_directory_object	<p>The directory on the computer system running the source database into which the generated Data Pump export dump file and the datafile for the cloned tablespace are placed. These files remain in this directory after the procedure completes.</p> <p>If <code>NULL</code>, then an error is raised.</p>

Table 96–13 (Cont.) MAINTAIN_SIMPLE_TABLESPACE Procedure Parameters

Parameter	Description
<code>destination_directory_object</code>	<p>The directory on the computer system running the destination database into which the generated Data Pump dump file and the datafile for the cloned tablespace are transferred.</p> <p>If <code>NULL</code>, then an error is raised.</p>
<code>destination_database</code>	<p>The global name of the destination database. A database link from the source database to the destination database with the same name must exist.</p> <p>If <code>NULL</code>, then an error is raised.</p>
<code>setup_streams</code>	<p>If <code>true</code>, then the <code>MAINTAIN_SIMPLE_TABLESPACE</code> procedure performs the necessary actions to maintain the tablespace directly.</p> <p>If <code>false</code>, then the <code>MAINTAIN_SIMPLE_TABLESPACE</code> procedure does not perform the necessary actions to maintain the tablespace directly.</p> <p>You specify <code>false</code> when this procedure is generating a file that you will edit and then run. An error is raised if you specify <code>false</code> and either of the following parameters is <code>NULL</code>:</p> <ul style="list-style-type: none"> ■ <code>script_name</code> ■ <code>script_directory_object</code>

Table 96–13 (Cont.) MAINTAIN_SIMPLE_TABLESPACE Procedure Parameters

Parameter	Description
<code>script_name</code>	<p>If non-NULL and the <code>setup_streams</code> parameter is <code>false</code>, then the name of the script generated by this procedure. The script contains all of the statements used to maintain the specified tablespace. If a file with the specified file name exists in the specified directory for the <code>script_directory_object</code> parameter, then the statements are appended to the existing file.</p> <p>If non-NULL and the <code>setup_streams</code> parameter is <code>true</code>, then this procedure generates the specified script and performs the actions to maintain the specified tablespace directly.</p> <p>If NULL and the <code>setup_streams</code> parameter is <code>true</code>, then this procedure does not generate a file and performs the actions to maintain the specified tablespace directly. If NULL and the <code>setup_streams</code> parameter is <code>false</code>, then an error is raised.</p>
<code>script_directory_object</code>	<p>The directory on the local computer system into which the generated script is placed.</p> <p>If the <code>script_name</code> parameter is NULL, then this parameter is ignored, and this procedure does not generate a file.</p> <p>If NULL and the <code>script_name</code> parameter is non-NULL, then an error is raised.</p>
<code>bi_directional</code>	<p>Specify <code>true</code> to configure bi-directional replication between the current database and the database specified in <code>destination_database</code>. Both databases are configured as source and destination databases, and propagations are configured between the databases to propagate events.</p> <p>Specify <code>false</code> to configure one way replication from the current database to the database specified in <code>destination_database</code>. A capture process is configured at the current database, a propagation is configured to propagate events from the current database to the destination database, and an apply process is configured at the destination database.</p>

Usage Notes

Single Source and Bi-Directional Configurations

This procedure either sets up a single source Streams configuration with the local database as the source database, or it sets up a bi-directional Streams configuration with both databases acting as source and destination databases. The `bi_directional` parameter controls whether the Streams configuration is single source or bi-directional. The information about single source, bi-directional, and multi-directional Streams environments in the description for the `MAINTAIN_TABLESPACES` procedure also applies to this procedure.

Change Cycling and the `MAINTAIN_SIMPLE_TABLESPACE` Procedure

If the `bi_directional` is set to `true`, then this procedure configures bi-directional replication, but this procedure cannot be used to configure multi-directional replication where changes may be cycled back to a source database by a third database in the environment. The information about change cycling in the description for the `MAINTAIN_TABLESPACES` procedure also applies to this procedure.

DDL Changes Not Maintained

This procedure does not configure the Streams environment to maintain DDL changes to the tablespace nor to the database objects in the tablespace. For example, the Streams environment is not configured to replicate `ALTER TABLESPACE` statements on the tablespace, nor is it configured to replicate `ALTER TABLE` statements on tables in the tablespace. You may configure the Streams environment to maintain DDL changes manually or modify generated scripts to achieve this.

Privileges and Database Links Required by the `MAINTAIN_SIMPLE_TABLESPACE` Procedure

The user who runs the `MAINTAIN_SIMPLE_TABLESPACE` procedure should have DBA role. This user must have the necessary privileges to complete the following actions:

- Create `SYS.AnyData` queues, capture processes, propagations, and apply processes.
- Specify supplemental logging
- Run subprograms in the `DBMS_STREAMS_ADM`, `DBMS_STREAMS_TABLESPACES_ADM`, `DBMS_FILE_TRANSFER`, and `DBMS_AQADM` packages

- The necessary privileges to run the `CLONE_SIMPLE_TABLESPACE` procedure in the `DBMS_STREAMS_TABLESPACES_ADM` package at the source database. See [CLONE_SIMPLE_TABLESPACE Procedure](#) on page 99-11 for the list of required privileges.
- The necessary privileges to run the `ATTACH_SIMPLE_TABLESPACE` procedure in the `DBMS_STREAMS_TABLESPACES_ADM` package at the destination database. See [ATTACH_SIMPLE_TABLESPACE Procedure](#) on page 99-6 for the list of required privileges.
- Access the database specified in the `destination_database` parameter through a database link. This database link should have the same name as the global name of the destination database.

In addition, if the `bi_directional` parameter is set to `true`, then the corresponding user at the destination database must be able to use a database link to access the source database. This database link should have the same name as the global name of the source database.

To ensure that the user who runs this procedure has the necessary privileges, Oracle recommends that you configure a Streams administrator at each database. In this case, each database link should be created in the Streams administrator's schema.

See Also: *Oracle Streams Concepts and Administration* for information about configuring a Streams administrator

Actions Performed by the MAINTAIN_SIMPLE_TABLESPACE Procedure

The actions performed by this procedure are the same as the actions performed by the `MAINTAIN_TABLESPACES` procedure, except that this procedure only can be used for a simple tablespace. A simple tablespace is a single, self-contained tablespace that uses only one datafile. This procedure cannot be used for a non simple tablespace or a set of tablespaces.

This procedure uses the default values for the parameters in the `MAINTAIN_TABLESPACES` procedure that do not exist in the `MAINTAIN_SIMPLE_TABLESPACES` procedure. For example, this procedure creates a capture process at the source database named `capture`, because that is the default value for the `capture_name` parameter in the `MAINTAIN_TABLESPACES` procedure.

Note:

- To view all of the statements run by this procedure in detail, you can use the procedure to generate a script and then view the script in a text editor.
 - Each specified directory object must be created using the SQL statement `CREATE DIRECTORY`, and the user who invokes the `MAINTAIN_SIMPLE_TABLESPACE` procedure must have `READ` and `WRITE` privilege on each one.
 - If the source and destination databases are running on different platforms, then this procedure, or the script generated by this procedure, converts transferred datafile to the appropriate platform automatically.
-

See Also:

- [MAINTAIN_TABLESPACES Procedure](#) on page 96-78
- [Using DBMS_STREAMS_TABLESPACE_ADM](#) on page 99-2 and *Oracle Database Administrator's Guide* for more information about simple tablespaces and self-contained tablespace sets
- *Oracle Streams Concepts and Administration* for information about configuring a Streams administrator

MAINTAIN_TABLESPACES Procedure

This procedure clones a set of tablespaces from a source database at a destination database and uses Streams to maintain these tablespaces at both databases. This procedure either can perform these actions directly, or it can generate a script that performs these actions.

Syntax

```

DBMS_STREAMS_ADM.MAINTAIN_TABLESPACES(
    tablespace_names          IN DBMS_STREAMS_TABLESPACE_ADM.TABLESPACE_SET,
    source_directory_object   IN VARCHAR2,
    destination_directory_object IN VARCHAR2,
    destination_database      IN VARCHAR2,
    setup_streams             IN BOOLEAN   DEFAULT true,
    script_name               IN VARCHAR2  DEFAULT NULL,
    script_directory_object   IN VARCHAR2  DEFAULT NULL,
    dump_file_name           IN VARCHAR2  DEFAULT NULL,
    source_queue_table        IN VARCHAR2  DEFAULT 'streams_queue_table',
    source_queue_name         IN VARCHAR2  DEFAULT 'streams_queue',
    source_queue_user         IN VARCHAR2  DEFAULT NULL,
    destination_queue_table   IN VARCHAR2  DEFAULT 'streams_queue_table',
    destination_queue_name    IN VARCHAR2  DEFAULT 'streams_queue',
    destination_queue_user    IN VARCHAR2  DEFAULT NULL,
    capture_name              IN VARCHAR2  DEFAULT 'capture',
    propagation_name         IN VARCHAR2  DEFAULT NULL,
    apply_name                IN VARCHAR2  DEFAULT NULL,
    log_file                  IN VARCHAR2  DEFAULT NULL,
    bi_directional            IN BOOLEAN   DEFAULT false);
    
```

Parameters

Table 96–14 *MAINTAIN_TABLESPACES Procedure Parameters*

Parameter	Description
tablespace_names	<p>The local tablespace set to be cloned at the destination database and maintained by Streams.</p> <p>A directory object must exist for each directory that contains the datafiles for the tablespace set. The user who invokes this procedure must have READ privilege on these directory objects.</p> <p>If NULL, then an error is raised.</p> <p>See Also: TABLESPACE_SET Type on page 99-4</p>
source_directory_object	<p>The directory on the computer system running the source database into which the generated Data Pump export dump file and the datafiles that comprise the cloned tablespace set are placed. These files remain in this directory after the procedure completes.</p> <p>If NULL, then an error is raised.</p>
destination_directory_object	<p>The directory on the computer system running the destination database into which the generated Data Pump dump file and the datafiles that comprise the cloned tablespace set are transferred.</p> <p>If NULL, then an error is raised.</p>
destination_database	<p>The global name of the destination database. A database link from the source database to the destination database with the same name must exist and must be accessible to the user who runs the procedure.</p> <p>If NULL, then an error is raised.</p>

Table 96–14 (Cont.) MAINTAIN_TABLESPACES Procedure Parameters

Parameter	Description
setup_streams	<p>If <code>true</code>, then the <code>MAINTAIN_TABLESPACES</code> procedure performs the necessary actions to maintain the tablespaces directly.</p> <p>If <code>false</code>, then the <code>MAINTAIN_TABLESPACES</code> procedure does not perform the necessary actions to maintain the tablespaces directly.</p> <p>You specify <code>false</code> when this procedure is generating a file that you will edit and then run. An error is raised if you specify <code>false</code> and either of the following parameters is <code>NULL</code>:</p> <ul style="list-style-type: none"> ■ <code>script_name</code> ■ <code>script_directory_object</code>
script_name	<p>If non-<code>NULL</code> and the <code>setup_streams</code> parameter is <code>false</code>, then the name of the script generated by this procedure. The script contains all of the statements used to maintain the specified tablespace set. If a file with the specified file name exists in the specified directory for the <code>script_directory_object</code> parameter, then the statements are appended to the existing file.</p> <p>If non-<code>NULL</code> and the <code>setup_streams</code> parameter is <code>true</code>, then this procedure generates the specified script and performs the actions to maintain the specified tablespace directly.</p> <p>If <code>NULL</code> and the <code>setup_streams</code> parameter is <code>true</code>, then this procedure does not generate a file and performs the actions to maintain the specified tablespace set directly. If <code>NULL</code> and the <code>setup_streams</code> parameter is <code>false</code>, then an error is raised.</p>
script_directory_object	<p>The directory on the local computer system into which the generated script is placed.</p> <p>If the <code>script_name</code> parameter is <code>NULL</code>, then this parameter is ignored, and this procedure does not generate a file.</p> <p>If <code>NULL</code> and the <code>script_name</code> parameter is non-<code>NULL</code>, then an error is raised.</p>

Table 96–14 (Cont.) MAINTAIN_TABLESPACES Procedure Parameters

Parameter	Description
dump_file_name	<p>The name of the Data Pump dump file that contains the specified tablespace set. If a file with the specified file name exists in the specified directory for the <code>source_directory_object</code> or <code>destination_directory_object</code> parameter, then an error is raised.</p> <p>If NULL, then the dump file name is generated by the system. In this case, the dump file name is <code>expatnn.dmp</code>, where <code>nn</code> is a sequence number. The sequence number is incremented to produce a dump file with a unique name in the source directory.</p>
source_queue_table	<p>The name of the queue table for the queue at the source database, specified as [<code>schema_name</code>].<code>queue_table_name</code>. For example, <code>strmadmin.streams_queue_table</code>. If the schema is not specified, then the current user is the default.</p> <p>If the queue table owner is not specified, then the user who runs this procedure is automatically specified as the queue table owner.</p>
source_queue_name	<p>The name of the queue at the source database that will function as the <code>SYS.AnyData</code> queue, specified as [<code>schema_name</code>].<code>queue_name</code>. For example, <code>strmadmin.streams_queue</code>.</p> <p>If the schema is not specified, then it defaults to the queue table owner. The queue owner automatically has privileges to perform all queue operations on the queue.</p>
source_queue_user	<p>The name of the user who requires <code>ENQUEUE</code> and <code>DEQUEUE</code> privileges for the queue at the source database. This user is also configured as a secure queue user of the queue. The queue user cannot grant these privileges to other users because they are not granted with the <code>GRANT</code> option.</p> <p>If NULL, then no privileges are granted. You can also grant queue privileges to the appropriate users using the <code>DBMS_AQADM</code> package.</p>

Table 96–14 (Cont.) MAINTAIN_TABLESPACES Procedure Parameters

Parameter	Description
destination_queue_table	<p>The name of the queue table for the queue at the destination database, specified as [<i>schema_name</i>.]<i>queue_table_name</i>. For example, <i>strmadmin.streams_queue_table</i>. If the schema is not specified, then the current user is the default.</p> <p>If the queue table owner is not specified, then the user who runs this procedure is automatically specified as the queue table owner.</p>
destination_queue_name	<p>The name of the queue at the destination database that will function as the <i>SYS.AnyData</i> queue, specified as [<i>schema_name</i>.]<i>queue_name</i>. For example, <i>strmadmin.streams_queue</i>.</p> <p>If the schema is not specified, then it defaults to the queue table owner. The owner of the queue table must also be the owner of the queue. The queue owner automatically has privileges to perform all queue operations on the queue.</p> <p>If the schema is not specified for this parameter, and the queue table owner is not specified in <i>destination_queue_table</i>, then the current user is the default.</p>
destination_queue_user	<p>The name of the user who requires <i>ENQUEUE</i> and <i>DEQUEUE</i> privileges for the queue at the destination database. This user is also configured as a secure queue user of the queue. The queue user cannot grant these privileges to other users because they are not granted with the <i>GRANT</i> option.</p> <p>If <i>NULL</i>, then no privileges are granted. You can also grant queue privileges to the appropriate users using the <i>DBMS_AQADM</i> package.</p>

Table 96–14 (Cont.) MAINTAIN_TABLESPACES Procedure Parameters

Parameter	Description
capture_name	<p>The name of the capture process configured to capture DML changes to the tables in the tablespace set at the source database. Do not specify an owner.</p> <p>If the specified name matches the name of an existing capture process at the source database, then the existing capture process is used, and the rules for DML changes to the tables in the tablespaces are added to the positive capture process rule set.</p> <p>Note: The capture_name setting cannot be altered after the capture process is created.</p>
propagation_name	<p>The name of the propagation configured to propagate DML changes to the tables in the tablespace set. Do not specify an owner.</p> <p>If the specified name matches the name of an existing propagation at the source database, then the existing propagation is used, and the rules for DML changes to the tables in the tablespaces are added to the positive propagation rule set.</p> <p>If NULL, then the system generates a name for each propagation it creates.</p> <p>Note: The propagation_name setting cannot be altered after the propagation is created.</p>
apply_name	<p>The name of the apply process configured to apply DML changes to the tables in the tablespace set at the destination database. Do not specify an owner.</p> <p>If the specified name matches the name of an existing apply process at the destination database, then the existing apply process is used, and the for DML changes to the tables in the tablespaces are added to the positive apply process rule set.</p> <p>The specified name must not match the name of an existing messaging client at the destination database.</p> <p>If NULL, then the system generates a name for each apply process it creates.</p> <p>Note: The apply_name setting cannot be altered after the apply process is created.</p>

Table 96–14 (Cont.) MAINTAIN_TABLESPACES Procedure Parameters

Parameter	Description
<code>log_file</code>	<p>The name of the Data Pump export log file. This log file is placed in the same directory as the Data Pump export dump file.</p> <p>If <code>NULL</code>, then the log file name is the same name as the export dump file name with an extension of <code>.clg</code>.</p>
<code>bi_directional</code>	<p>Specify <code>true</code> to configure bi-directional replication between the current database and the database specified in <code>destination_database</code>. Both databases are configured as source and destination databases, and propagations are configured between the databases to propagate events.</p> <p>Specify <code>false</code> to configure one way replication from the current database to the database specified in <code>destination_database</code>. A capture process is configured at the current database, a propagation is configured to propagate events from the current database to the destination database, and an apply process is configured at the destination database.</p>

Usage Notes

The specified set of tablespaces must be self-contained. In this context "self-contained" means that there are no references from inside the set of tablespaces pointing outside of the set of tablespaces. For example, if a partitioned table is partially contained in the set of tablespaces, then the set of tablespaces is not self-contained.

Single Source and Bi-Directional Configurations

This procedure either sets up a single source Streams configuration with the local database as the source database, or it sets up a bi-directional Streams configuration with both databases acting as source and destination databases. The `bi_directional` parameter controls whether the Streams configuration is single source or bi-directional. If `bi_directional` is `false`, then a capture process at the local database captures DML changes to the tables in the specified tablespace set, a propagation propagates these changes to the destination database, and an apply process at the destination database applies these changes. If `bi_directional` is `true`, then each database captures changes and propagates them to the other database, and each database applies changes from the other database.

If `bi_directional` is set to `false`, then this procedure does not configure bi-directional information sharing. Therefore, changes made to the tables in the tablespace set at the destination database are not shared with the source database, and the tablespaces are not kept in sync at the two databases, unless no changes are made to the tablespace objects at the destination database. However, if `bi_directional` is set to `true`, then Streams is configured to keep the tablespaces in sync at the two databases, even if both databases allow DML changes to the tablespace objects.

Both databases must be open when the actions are performed. Meet the following requirements when you use this procedure:

- Run this procedure at the intended source database. If `bi_directional` is set to `true`, then run this procedure at the database that contains the tablespace set to be cloned.
- If this procedure is generating a script only, then the database specified in the `destination_database` parameter does not need to be open when you run this procedure, but both databases must be open when you run the generated script.

Note: You may need to configure conflict resolution if this procedure configures bi-directional replication.

See Also:

- [SET_UPDATE_CONFLICT_HANDLER Procedure](#) on page 15-54
- *Oracle Streams Replication Administrator's Guide* for more information about conflict resolution

Change Cycling and the MAINTAIN_TABLESPACES Procedure

If the `bi_directional` is set to `true`, then this procedure configures bi-directional replication, but this procedure cannot be used to configure multi-directional replication where changes may be cycled back to a source database by a third database in the environment. For example, this procedure cannot be used to configure a Streams replication environment with three databases where each database shares changes with the other two databases in the environment. If this procedure is used to configure a three way replication environment such as this, then changes made at a source database would be cycled

back to the same source database. In a valid three way replication environment, a particular change is made only once at each database.

To prevent change cycling in a bi-directional Streams replication environment, this procedure configures the environment in the following way:

- The apply process at each database applies changes with an apply tag that is unique to the environment. An apply tag is a Streams tag that is part of each redo record created by the apply process. For example, if this procedure configures databases `sfdb.net` and `nydb.net` for bi-directional replication, then assume that the apply tag for the apply process at `sfdb.net` is the hexadecimal equivalent of '1', and assume that the apply tag for the apply process at `nydb.net` is the hexadecimal equivalent of '2'.
- The capture process at each database captures all DML changes to the supported tables in the tablespace set, regardless of tags in the redo records for the changes.
- Each propagation propagates all DML changes to the supported tablespace set to the other database in the bi-directional replication environment, except for changes that originated at the other database. Continuing the example, the propagation at `sfdb.net` propagates all changes to `nydb.net`, except for changes with a tag value that is the hexadecimal equivalent of '1', because these changes originated at `nydb.net`. Similarly, the propagation at `nydb.net` propagates all changes to `sfdb.net`, except for changes with a tag value that is the hexadecimal equivalent of '2'.

This procedure can be used to configure a Streams replication environment that includes more than two databases, as long as changes made at a source database cannot cycle back to the same source database. For example, this procedure can be run multiple times to configure an environment in which a primary database shares changes with multiple secondary databases. Such an environment is sometimes called a "hub and spoke" environment.

You may configure the Streams environment manually to replicate changes in a multiple source environment where each source database shares changes with the other source databases, or you may modify generated scripts to achieve this.

See Also: *Oracle Streams Replication Administrator's Guide* for an example of a hub and spoke environment and for information about configuring a multiple source environment manually

DDL Changes Not Maintained

This procedure does not configure the Streams environment to maintain DDL changes to the tablespace set nor to the database objects in the tablespace set. For example, the Streams environment is not configured to replicate `ALTER TABLESPACE` statements on the tablespace, nor is it configured to replicate `ALTER TABLE` statements on tables in the tablespace. You may configure the Streams environment to maintain DDL changes manually or modify generated scripts to achieve this.

Privileges and Database Links Required by the MAINTAIN_TABLESPACES Procedure

The user who runs the `MAINTAIN_TABLESPACES` procedure should have `DBA` role. This user must have the necessary privileges to complete the following actions:

- Create `SYS.AnyData` queues, capture processes, propagations, and apply processes.
- Specify supplemental logging
- Run subprograms in the `DBMS_STREAMS_ADM`, `DBMS_STREAMS_TABLESPACES_ADM`, `DBMS_FILE_TRANSFER`, and `DBMS_AQADM` packages
- The necessary privileges to run the `CLONE_TABLESPACES` procedure in the `DBMS_STREAMS_TABLESPACES_ADM` package at the source database. See [CLONE_TABLESPACES Procedure](#) on page 99-14 for the list of required privileges.
- The necessary privileges to run the `ATTACH_TABLESPACES` procedure in the `DBMS_STREAMS_TABLESPACES_ADM` package at the destination database. See [ATTACH_TABLESPACES Procedure](#) on page 99-8 for the list of required privileges.
- Access the database specified in the `destination_database` parameter through a database link. This database link should have the same name as the global name of the destination database.

In addition, if the `bi_directional` parameter is set to `true`, then the corresponding user at the destination database must be able to use a database link to access the source database. This database link should have the same name as the global name of the source database.

To ensure that the user who runs this procedure has the necessary privileges, Oracle recommends that you configure a Streams administrator at each database. In this case, each database link should be created in the Streams administrator's schema.

See Also: *Oracle Streams Concepts and Administration* for information about configuring a Streams administrator

Actions Performed by the MAINTAIN_TABLESPACES Procedure

This section describes the specific actions performed by this procedure. In the description, the source database is the database where the MAINTAIN_TABLESPACES procedure is run, and the destination database is the database specified in the `destination_database` parameter.

First, at the source database, this procedure performs the following actions:

1. Adds supplemental log groups for all tables supported by Streams in the tablespace set
2. Configures a `SYS.AnyData` queue as a source queue that will stage changes to the database objects in the tablespace set

Next, if the `bi_directional` parameter is set to `true`, then this procedure performs the following actions at the source database (If the `bi_directional` parameter is set to `false`, then these actions are not performed, and the procedure continues at Step 5):

3. Configures a local apply process and adds rules to its positive rule set that instruct the apply process to apply DML changes to tables that are supported by Streams in the tablespace set. The apply process is configured to mark redo records with a tag value that is unique to the destination database, which is the source database of the changes.
4. Sets the key columns for tables that do not have a primary key using the `SET_KEY_COLUMNS` procedure in the `DBMS_APPLY_ADM` package

Next, this procedure performs the following actions at the source database:

5. Configures a propagation, and configures its rule sets to instruct the propagation to propagate changes from the source database to the destination database. If the `bi_directional` parameter is set to `true`, then the rule sets filter out changes that originated at the destination database.
6. Disables the propagation schedule for the propagation created in Step 5
7. Configures a local capture process and adds rules to its positive rule set that instruct the capture process to capture DML changes to tables that are supported by Streams in the tablespace set
8. Makes the specified tablespace set read-only

9. Clones the specified tablespace set using the `CLONE_TABLESPACES` procedure in the `DBMS_STREAMS_TABLESPACE_ADM` package. The Data Pump export dump file and the datafiles that comprise the cloned tablespace set are placed in the specified source directory as part of the clone tablespaces operation.
10. Makes the specified tablespace set read/write. Users and applications can resume operations on the tablespace set.
11. Starts the capture process configured in Step 7

Next, if the `bi_directional` parameter is set to `true`, then this procedure performs the following action at the source database (If the `bi_directional` parameter is set to `false`, then this action is not performed, and the procedure continues at Step 13):

12. Starts the apply process configured in Step 3

Next, this procedure performs the following action at the source database:

13. Uses the `DBMS_FILE_TRANSFER` package to copy the Data Pump export dump file and the datafiles for the tablespace set to the specified destination directory at the computer system running the destination database

Next, this procedure performs the following actions at the destination database:

14. Attaches the tablespace set using the `ATTACH_TABLESPACES` procedure in the `DBMS_STREAMS_TABLESPACE_ADM` package
15. Configures a local apply process and adds rules to its positive rule set that instruct the apply process to apply DML changes to tables that are supported by Streams in the tablespace set. The apply process is configured to mark redo records with a tag value that is unique to the source database of the changes.
16. Sets the key columns for tables that do not have a primary key using the `SET_KEY_COLUMNS` procedure in the `DBMS_APPLY_ADM` package
17. Configures a `SYS.AnyData` queue as a destination queue that will stage propagated DML changes to the tables in the tablespace set

Next, if the `bi_directional` parameter is set to `true`, then this procedure performs the following actions at the destination database (If the `bi_directional` parameter is set to `false`, then these actions are not performed, and the procedure continues at Step 24):

18. Adds supplemental log groups for all tables supported by Streams in the tablespace set

19. Configures a propagation, and configures its rule sets to instruct the propagation to propagate changes from this database to the source database. The rule sets filter out changes that originated at the source database.
20. Disables the propagation schedule for the propagation created in Step 19
21. Configures a local capture process and adds rules to its positive rule set that instruct the capture process to capture DML changes to tables that are supported by Streams in the tablespace set
22. Records the value of the current database SCN, and uses this value to set the instantiation SCNs of the objects in the tablespace set at the source database
23. Starts the capture process created in Step 21

Next, this procedure performs the following actions at the destination database:

24. Starts the apply process created in Step 15
25. Makes the tablespace set read/write

Next, if the `bi_directional` parameter is set to `true`, then this procedure performs the following action at the destination database (If the `bi_directional` parameter is set to `false`, then this action is not performed, and the procedure continues at Step 24):

26. Enables the propagation schedule for the propagation created in Step 19

Next, this procedure performs the final action at the source database:

27. Enables the propagation schedule for the propagation created in Step 5

To monitor the progress of the configuration, query the `V$SESSION_LONGOPS` dynamic performance view at the source database.

Note:

- To view all of the statements run by this procedure in detail, you can use the procedure to generate a script and then view the script in a text editor.
 - Each specified directory object must be created using the SQL statement `CREATE DIRECTORY`, and the user who invokes the `MAINTAIN_TABLESPACES` procedure must have `READ` and `WRITE` privilege on each one.
 - If the source and destination databases are running on different platforms, then this procedure, or the script generated by this procedure, converts transferred datafiles to the appropriate platform automatically.
-

See Also: *Oracle Database Administrator's Guide* for more information about self-contained tablespace sets

PURGE_SOURCE_CATALOG Procedure

This procedure removes all Streams data dictionary information at the local database for the specified object. You can use this procedure to remove Streams metadata that is not needed currently and will not be needed in the future.

Syntax

```
DBMS_STREAMS_ADM.PURGE_SOURCE_CATALOG(
    source_database      IN  VARCHAR2,
    source_object_name  IN  VARCHAR2,
    source_object_type  IN  VARCHAR2);
```

Parameters

Table 96–15 *PURGE_SOURCE_CATALOG Procedure Parameters*

Parameter	Description
source_database	The global name of the source database containing the object. If you do not include the domain name, then it is appended to the database name automatically. For example, if you specify DBS1 and the domain is .NET, then DBS1.NET is specified automatically.
source_object_name	The name of the object specified as [<i>schema_name</i> .] <i>object_name</i> . For example, hr.employees. If the schema is not specified, then the current user is the default.
source_object_type	Type of the object. Currently, TABLE is the only possible object type.

Usage Notes

The global name of the source database containing the object must be specified for the `source_database` parameter. If the current database is not the source database for the object, then data dictionary information about the object is removed at the current database, not the source database.

For example, suppose changes to the `hr.employees` table at the `dbs1.net` source database are being applied to the `hr.employees` table at the `dbs2.net` destination database. Also, suppose `hr.employees` at `dbs2.net` is not a source at all. In this case, specifying `dbs2.net` as the `source_database` for this table results in an error. However, specifying `dbs1.net` as the `source_database` for

this table while running the `PURGE_SOURCE_CATALOG` procedure at the `db2.net` database removes data dictionary information about the table at `db2.net`.

Do not run this procedure at a database if either of the following conditions are true:

- LCRs captured by the capture process for the object are or may be applied locally without reinstantiating the object.
- LCRs captured by the capture process for the object are or may be forwarded by the database without reinstantiating the object.

Note: These conditions do not apply to LCRs that were not created by the capture process. That is, these conditions do not apply to user-created LCRs.

REMOVE_QUEUE Procedure

This procedure removes the specified `SYS.AnyData` queue.

Specifically, this procedure performs the following actions:

1. Waits until all current enqueue and dequeue transactions commit.
2. Stops the queue, which means that no further enqueues into the queue or dequeues from the queue are allowed.
3. Drops the queue.
4. If the `drop_unused_queue_table` parameter is set to `true`, then drops the queue table if it is empty and no other queues are using it.
5. If the `cascade` parameter is set to `true`, then drops all of the Streams clients that are using the queue.

Note: The specified queue must be a `SYS.AnyData` queue.

Syntax

```
DBMS_STREAMS_ADM.REMOVE_QUEUE(
  queue_name          IN VARCHAR2,
  cascade             IN BOOLEAN DEFAULT false,
  drop_unused_queue_table IN BOOLEAN DEFAULT true);
```

Parameters

Table 96–16 REMOVE_QUEUE Procedure Parameters

Parameter	Description
<code>queue_name</code>	The name of the queue to remove, specified as <code>[schema_name .] queue_name</code> . For example, <code>strmadmin.streams_queue</code> . If the schema is not specified, then the current user is the default.
<code>cascade</code>	If <code>true</code> , then drops any Streams clients that use the queue. If <code>false</code> , then raises an error if there are any Streams clients that use the queue. Before you run this procedure with the <code>cascade</code> parameter set to <code>false</code> , make sure no Streams clients are using the queue currently.

Table 96–16 REMOVE_QUEUE Procedure Parameters

Parameter	Description
<code>drop_unused_queue_table</code>	If <code>true</code> and the queue table for the queue is empty, then the queue table is dropped. The queue table is not dropped if it contains any messages or if it is used by another queue. If <code>false</code> , then the queue table is not dropped

REMOVE_RULE Procedure

This procedure removes the specified rule or all rules from the rule set associated with the specified capture process, apply process, propagation, or messaging client.

If this procedure results in an empty positive rule set for a messaging client, then the messaging client is dropped automatically.

Note: If a rule was automatically created by the system, and you want to drop the rule, then you should use this procedure to remove the rule instead of the `DBMS_RULE_ADM.DROP_RULE` procedure. If you use the `DBMS_RULE_ADM.DROP_RULE` procedure, then some metadata about the rule may remain.

Syntax

```
DBMS_STREAMS_ADM.REMOVE_RULE(
    rule_name          IN  VARCHAR2,
    streams_type       IN  VARCHAR2,
    streams_name       IN  VARCHAR2,
    drop_unused_rule   IN  BOOLEAN  DEFAULT true,
    inclusion_rule     IN  BOOLEAN  DEFAULT true);
```

Parameters

Table 96–17 REMOVE_RULE Procedure Parameters

Parameter	Description
<code>rule_name</code>	The name of the rule to remove, specified as [<i>schema_name</i> .] <i>rule_name</i> . If NULL, then removes all rules from the specified capture process, apply process, propagation, or messaging client rule set. For example, to specify a rule in the <code>hr</code> schema named <code>prop_rule1</code> , enter <code>hr.prop_rule1</code> . If the schema is not specified, then the current user is the default.
<code>streams_type</code>	The type of Streams client, either <code>capture</code> for a capture process, <code>apply</code> for an apply process, <code>propagation</code> for a propagation, or <code>dequeue</code> for a messaging client

Table 96–17 (Cont.) REMOVE_RULE Procedure Parameters

Parameter	Description
<code>streams_name</code>	<p>The name of the Streams client, which may be a capture process, apply process, propagation, or messaging client. Do not specify an owner.</p> <p>If the specified Streams client does not exist, but there is metadata in the data dictionary that associates the rule with this client, then the metadata is removed.</p> <p>If the specified Streams client does not exist, and there is no metadata in the data dictionary that associates the rule with this client, then an error is raised.</p>
<code>drop_unused_rule</code>	<p>If <code>false</code>, then the rule is not dropped from the database.</p> <p>If <code>true</code> and the rule is not in any rule set, then the rule is dropped from the database.</p> <p>If <code>true</code> and the rule exists in any rule set, then the rule is not dropped from the database.</p>
<code>inclusion_rule</code>	<p>If <code>inclusion_rule</code> is <code>true</code>, then the rule is removed from the positive rule set for the Streams client.</p> <p>If <code>inclusion_rule</code> is <code>false</code>, then the rule is removed from the negative rule set for the Streams client.</p>

REMOVE_STREAMS_CONFIGURATION Procedure

This procedure removes the Streams configuration at the local database.

Syntax

```
DBMS_STREAMS_ADM.REMOVE_STREAMS_CONFIGURATION;
```

Usage Notes

Specifically, this procedure performs the following actions at the local database:

- Drops all capture processes
- If any tables have been prepared for instantiation, then aborts preparation for instantiation for the table using the `ABORT_TABLE_INSTANTIATION` procedure in the `DBMS_CAPTURE_ADM` package
- If any schemas have been prepared for instantiation, then aborts preparation for instantiation for the schema using the `ABORT_SCHEMA_INSTANTIATION` procedure in the `DBMS_CAPTURE_ADM` package
- If the database has been prepared for instantiation, then aborts preparation for instantiation for the database using the `ABORT_GLOBAL_INSTANTIATION` procedure in the `DBMS_CAPTURE_ADM` package
- Drops propagations that were created using either the `DBMS_STREAMS_ADM` package or the `DBMS_PROPAGATION_ADM` package. Before a propagation is dropped, its propagation job is disabled. Does not drop propagations that were created using the `DBMS_AQADM` package.
- Disables all propagation jobs used by propagations
- Drops all apply processes. If there are apply errors in the error queue for an apply process, then this procedure deletes these apply errors before it drops the apply process.
- Removes specifications for DDL handlers used by apply processes, but does not delete the PL/SQL procedures used by these handlers
- Removes specifications for message handlers used by apply processes, but does not delete the PL/SQL procedures used by these handlers
- Removes specifications for precommit handlers used by apply processes, but does not delete the PL/SQL procedures used by these handlers

- Removes the instantiation SCN and ignore SCN for each apply object and schema and for the entire database
- Removes messaging clients
- Unsets message notification specifications that were set using the `SET_MESSAGE_NOTIFICATION` procedure in the `DBMS_STREAMS_ADM` package
- Removes specifications for DML handlers and error handlers, but does not delete the PL/SQL procedures used by these handlers
- Removes update conflict handlers
- Removes specifications for substitute key columns for apply tables
- Drops rules that were created using the `DBMS_STREAMS_ADM` package. Does not drop rules that were created using the `DBMS_RULE_ADM` package.

This procedure stops capture processes and apply processes before it drops them.

Attention: Running this procedure is dangerous. You should run this procedure only if you are sure you want to remove the entire Streams configuration at a database.

Note:

- Running this procedure repeatedly does not cause errors. If the procedure fails to complete, then you can run it again.
 - This procedure commits multiple times.
-
-

See Also:

- [STOP_CAPTURE Procedure](#) on page 19-34 in the `DBMS_CAPTURE_ADM` package
- [STOP_APPLY Procedure](#) on page 15-59 in the `DBMS_APPLY_ADM` package
- [REMOVE_RULE Procedure](#) on page 96-96 in the `DBMS_STREAMS_ADM` package

SET_MESSAGE_NOTIFICATION Procedure

This procedure sets a notification for messages that can be dequeued by a specified Streams messaging client from a specified queue. A notification is sent when a message is enqueued into the specified queue and the specified messaging client can dequeue the message because the message satisfies its rule sets.

Syntax

```
DBMS_STREAMS_ADM.SET_MESSAGE_NOTIFICATION(  
    streams_name          IN  VARCHAR2,  
    notification_action   IN  VARCHAR2,  
    notification_type     IN  VARCHAR2    DEFAULT 'PROCEDURE',  
    notification_context  IN  SYS.AnyData  DEFAULT NULL,  
    include_notification  IN  BOOLEAN      DEFAULT true,  
    queue_name            IN  VARCHAR2     DEFAULT 'streams_queue');
```

Parameters

Table 96–18 SET_MESSAGE_NOTIFICATION Procedure Parameters

Parameter	Description
streams_name	The name of the Streams messaging client. Do not specify an owner. For example, if the user strmadmin is the messaging client, then specify strmadmin.

Table 96–18 (Cont.) SET_MESSAGE_NOTIFICATION Procedure Parameters

Parameter	Description
<code>notification_action</code>	<p>The action to be performed on message notification. Specify one of the following:</p> <ul style="list-style-type: none"> ■ For URL notifications, specify a URL without the prefix <code>http://</code>. For example, to specify the URL <code>http://www.company.com:8080</code>, enter the following: <code>www.company.com:8080</code> ■ For email notifications, specify an email address. For example, to specify an the email address <code>xyz@company.com</code>, enter the following: <code>xyz@company.com</code> ■ For PL/SQL procedure notifications, specify an existing user-defined PL/SQL procedure in the form <code>[schema_name.]procedure_name</code>. If the <code>schema_name</code> is not specified, then the user who invokes the <code>SET_MESSAGE_NOTIFICATION</code> procedure is the default. The procedure must be a <code>PLSQLCALLBACK</code> data structure. For example, to specify a procedure named <code>notify_orders</code> in the <code>oe</code> schema, enter the following: <code>oe.notify_orders</code> <p>See Also: Examples on page 96-103 for more information about message notification procedures</p>
<code>notification_type</code>	<p>The type of notification. Specify one of the following:</p> <ul style="list-style-type: none"> ■ <code>HTTP</code> if you specified a URL for <code>notification_action</code> ■ <code>MAIL</code> if you specified an email address for <code>notification_action</code> ■ <code>PROCEDURE</code> if you specified a user-defined procedure for <code>notification_action</code> <p>The type must match the specification for the <code>notification_action</code> parameter.</p>

Table 96–18 (Cont.) SET_MESSAGE_NOTIFICATION Procedure Parameters

Parameter	Description
notification_context	<p>The context of the notification. The context must be specified using RAW datatype information. For example, to specify the hexadecimal equivalent of 'FF', enter the following:</p> <pre>SYS.AnyData.ConvertRaw(HEXTORAW('FF'))</pre> <p>The notification context is passed the PL/SQL procedure in procedure notifications and is not relevant for mail or HTTP notifications.</p>
include_notification	<p>If true, then this notification is added for the specified streams_name and queue_name. That is, specifying true turns on the notification for the streams_name and queue_name.</p> <p>If false, then this notification is removed for the specified streams_name and queue_name. That is, specifying false turns off the notification for the streams_name and queue_name. If you specify false, then this procedure ignores any specified values for the notification_action or notification_context parameters.</p>
queue_name	<p>The name of a local SYS.AnyData queue, specified as [schema_name.]queue_name. The current database must contain the queue. The specified queue must be a SYS.AnyData queue.</p> <p>For example, to specify a queue named streams_queue in the strmadmin schema, enter strmadmin.streams_queue for this parameter. If the schema is not specified, then the current user is the default.</p>

Usage Notes

You can specify one of the following types of notifications:

- An email address to which message notifications are sent. When a relevant message is enqueued into the queue, an email with the message properties is mailed to the specified email address.
- A PL/SQL procedure to be invoked on a notification. When a relevant message is enqueued into the queue, the specified PL/SQL procedure is invoked with the message properties. This PL/SQL procedure may dequeue the message.

- An HTTP URL to which the notification is posted. When a relevant message is enqueued into the queue, a notification with the message properties is posted to the specified URL specified.

A client does not need to be connected to the database to receive a notification.

If you register for email notifications, then you should use the `DBMS_AQELM` package to set the host name and port name for the SMTP server that will be used by the database to send email notifications. If required, then you should set the send-from email address, which is set by the database as the `sent from` field. You need a Java-enabled database to use this feature.

If you register for HTTP notifications, you may want to use the `DBMS_AQELM` package to set the host name and port number for the proxy server and a list of no-proxy domains that will be used by the database to post HTTP notifications.

Each notification is an `AQXmlNotification`, which includes of the following:

- `notification_options`, which includes the following:
 - `destination` - The destination queue from which the message was dequeued
 - `consumer_name` - The name of the messaging client that dequeued the message
- `message_set` - The set of message properties

See Also:

- The documentation for the `DBMS_AQELM` package for more information on email notifications and HTTP notifications
- *Oracle Streams Concepts and Administration* for more information about setting message notifications
- *Oracle Streams Advanced Queuing User's Guide and Reference* and *Oracle XML DB Developer's Guide* for more information about message notifications and XML
- *Oracle Streams Concepts and Administration* for more information about how rules are used in Streams

Examples

If you use a message notification procedure, then this PL/SQL procedure must have the following signature:

```
PROCEDURE procedure_name(  
    context IN SYS.AnyData,  
    reginfo IN SYS.AQ$_REG_INFO,  
    descr   IN SYS.AQ$_DESCRIPTOR);
```

Here, *procedure_name* stands for the name of the procedure. The procedure is a PLSQLCALLBACK data structure that specifies the user-defined PL/SQL procedure to be invoked on message notification.

The following is a simple example of a notification procedure that dequeues a message of type `oe.user_msg` using the message identifier and consumer name sent by the notification:

```
CREATE OR REPLACE PROCEDURE oe.notification_dequeue(  
    context SYS.AnyData,  
    reginfo SYS.AQ$_REG_INFO,  
    descr   SYS.AQ$_DESCRIPTOR)  
AS  
    dequeue_options    DBMS_AQ.DEQUEUE_OPTIONS_T;  
    message_properties DBMS_AQ.MESSAGE_PROPERTIES_T;  
    message_handle     RAW(16);  
    message            oe.user_msg;  
BEGIN  
    -- Get the message identifier and consumer name from the descriptor  
    dequeue_options.msgid := descr.msg_id;  
    dequeue_options.consumer_name := descr.consumer_name;  
    -- Dequeue the message  
    DBMS_AQ.DEQUEUE(  
        queue_name      => descr.queue_name,  
        dequeue_options => dequeue_options,  
        message_properties => message_properties,  
        payload         => message,  
        msgid           => message_handle);  
    COMMIT;  
END;  
/
```

See Also: *PL/SQL Packages and Types Reference* for more information about PLSQLCALLBACK data structures

SET_RULE_TRANSFORM_FUNCTION Procedure

This procedure sets or removes the transformation function name for a rule-based transformation.

Syntax

```
DBMS_STREAMS_ADM.SET_RULE_TRANSFORM_FUNCTION(
    rule_name          IN  VARCHAR2,
    transform_function IN  VARCHAR2);
```

Parameters

Table 96–19 SET_RULE_TRANSFORM_FUNCTION Procedure Parameters

Parameter	Description
rule_name	<p>The name of the rule whose rule-based transformation function you are setting or removing, specified as <code>[schema_name.]rule_name</code>.</p> <p>For example, to specify a rule in the <code>hr</code> schema named <code>prop_rule1</code>, enter <code>hr.prop_rule1</code>. If the schema is not specified, then the current user is the default.</p>
transform_function	<p>Either the name of the transformation function to be used in the rule-based transformation for the rule or <code>NULL</code>.</p> <p>If you specify a transformation function name, then you must specify an existing function in one of the following forms:</p> <ul style="list-style-type: none"> ▪ <code>[schema_name.]function_name</code> ▪ <code>[schema_name.]package_name.function_name</code> <p>If the function is in a package, then the <code>package_name</code> must be specified. For example, to specify a function in the <code>transform_pkg</code> package in the <code>hr</code> schema named <code>executive_to_management</code>, enter <code>hr.transform_pkg.executive_to_management</code>. An error is returned if the specified procedure does not exist.</p> <p>If the <code>schema_name</code> is not specified, then the user who invokes the rule-based transformation function is the default.</p> <p>If you specify <code>NULL</code>, then removes the current rule-based transformation from the rule.</p>

Usage Notes

This procedure modifies the specified rule's action context to specify the transformation. A rule action context is optional information associated with a rule that is interpreted by the client of the rules engine after the rule evaluates to `TRUE` for an event. The client of the rules engine can be a user-created application or an internal feature of Oracle, such as Streams. The Streams clients include capture processes, propagations, apply processes, and messaging clients. The information in an action context is an object of type `SYS.RE$NV_LIST`, which consists of a list of name-value pairs.

A rule-based transformation in Streams always consists of the following name-value pair in an action context:

- The name is `STREAMS$_TRANSFORM_FUNCTION`.
- The value is a `SYS.AnyData` instance containing a PL/SQL function name specified as a `VARCHAR2`. This function performs the transformation.

The user that calls the transformation function must have `EXECUTE` privilege on the function. The following list describes which user calls the transformation function:

- If a transformation is specified for a rule used by a capture process, then the user who calls the transformation function is the capture user for the capture process.
- If a transformation is specified for a rule used by a propagation, then the user who calls the transformation function is the owner of the source queue for the propagation.
- If a transformation is specified on a rule used by an apply process, then the user who calls the transformation function is the apply user for the apply process.
- If a transformation is specified on a rule used by a messaging client, then the user who calls the transformation function is the user who invokes the messaging client.

Note: This procedure does not verify that the specified transformation function exists. If the function does not exist, then an error is raised when a Streams client tries to invoke the transformation function.

SET_UP_QUEUE Procedure

This procedure creates a queue table and a SYS.AnyData queue for use with the capture, propagate, and apply functionality of Streams.

Syntax

```
DBMS_STREAMS_ADM.SET_UP_QUEUE(
  queue_table      IN  VARCHAR2  DEFAULT 'streams_queue_table',
  storage_clause  IN  VARCHAR2  DEFAULT NULL,
  queue_name      IN  VARCHAR2  DEFAULT 'streams_queue',
  queue_user      IN  VARCHAR2  DEFAULT NULL,
  comment        IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 96–20 SET_UP_QUEUE Procedure Parameters

Parameter	Description
queue_table	<p>The name of the queue table specified as <code>[schema_name.]queue_table_name</code>. For example, <code>strmadmin.streams_queue_table</code>. If the schema is not specified, then the current user is the default.</p> <p>If the queue table owner is not specified, then the user who runs this procedure is automatically specified as the queue table owner.</p>
storage_clause	<p>The storage clause for queue table</p> <p>The storage parameter is included in the <code>CREATE TABLE</code> statement when the queue table is created. You can specify any valid table storage clause.</p> <p>If a tablespace is not specified here, then the queue table and all its related objects are created in the default user tablespace of the user who runs this procedure. If a tablespace is specified here, then the queue table and all its related objects are created in the tablespace specified in the storage clause.</p> <p>If <code>NULL</code>, then Oracle uses the storage characteristics of the tablespace in which the queue table is created.</p> <p>See Also: <i>Oracle Database SQL Reference</i> for more information about storage clauses</p>

Table 96–20 (Cont.) SET_UP_QUEUE Procedure Parameters

Parameter	Description
queue_name	<p>The name of the queue that will function as the <code>SYS.AnyData</code> queue, specified as <code>[schema_name.]queue_name</code>. For example, <code>strmadmin.streams_queue</code>.</p> <p>If the schema is not specified, then it defaults to the queue table owner. The owner of the queue table must also be the owner of the queue. The queue owner automatically has privileges to perform all queue operations on the queue.</p> <p>If the schema is not specified for this parameter, and the queue table owner is not specified in <code>queue_table</code>, then the current user is the default.</p>
queue_user	<p>The name of the user who requires <code>ENQUEUE</code> and <code>DEQUEUE</code> privileges for the queue. This user is also configured as a secure queue user of the queue. The queue user cannot grant these privileges to other users because they are not granted with the <code>GRANT</code> option.</p> <p>If <code>NULL</code>, then no privileges are granted. You can also grant queue privileges to the appropriate users using the <code>DBMS_AQADM</code> package.</p>
comment	The comment for the queue

Usage Notes

Set up includes the following actions:

- If the specified queue table does not exist, then this procedure runs the `CREATE_QUEUE_TABLE` procedure in the `DBMS_AQADM` package to create the queue table with the specified storage clause.
- If the specified queue name does not exist, then this procedure runs the `CREATE_QUEUE` procedure in the `DBMS_AQADM` package to create the queue.
- This procedure starts the queue.
- If a queue user is specified, then this procedure configures this user as a secure queue user of the queue and grants `ENQUEUE` and `DEQUEUE` privileges on the queue to the specified queue user.

To configure the queue user as a secure queue user, this procedure creates an Advanced Queuing agent with the same name as the user name, if one does not already exist. If an agent with this name already exists and is associated with the queue user only, then it is used. `SET_UP_QUEUE` then runs the `ENABLE_DB_`

ACCESS procedure in the DBMS_AQADM package, specifying the agent and the user.

This procedure creates a SYS.AnyData queue that is both a secure queue and a transactional queue.

Note:

- To enqueue events into and dequeue events from a queue, a queue user must have EXECUTE privilege on the DBMS_STREAMS_MESSAGING package or the DBMS_AQ package. The SET_UP_QUEUE procedure does not grant this privilege.
 - If the agent that SET_UP_QUEUE tries to create already exists and is associated with a user other than the user specified by queue_user, then an error is raised. In this case, rename or remove the existing agent, and retry SET_UP_QUEUE.
 - Queue names and queue table names can be a maximum of 24 bytes.
-
-

See Also: *Oracle Streams Concepts and Administration* for more information about secure queue users

DBMS_STREAMS_AUTH

The `DBMS_STREAMS_AUTH` package, one of a set of Streams packages, provides interfaces for granting privileges to Streams administrators and revoking privileges from Streams administrators.

See Also: *Oracle Streams Concepts and Administration* for more information about this package and Streams administrators

This chapter contains the following topic:

- [Summary of DBMS_STREAMS_AUTH Subprograms](#)

Summary of DBMS_STREAMS_AUTH Subprograms

Table 97–1 *DBMS_STREAMS_AUTH Package Subprograms*

Subprogram	Description
GRANT_ADMIN_PRIVILEGE Procedure on page 97-3	Either grants the privileges needed by a user to be a Streams administrator directly, or generates a script that can be used to grant these privileges
GRANT_REMOTE_ADMIN_ACCESS Procedure on page 97-6	Enables a remote Streams administrator to perform administrative actions at the local database by connecting to the grantee using a database link
REVOKE_ADMIN_PRIVILEGE Procedure on page 97-7	Either revokes Streams administrator privileges from a user directly, or generates a script that can be used to revoke these privileges
REVOKE_REMOTE_ADMIN_ACCESS Procedure on page 97-9	Disables a remote Streams administrator from performing administrative actions by connecting to the grantee using a database link

GRANT_ADMIN_PRIVILEGE Procedure

This procedure either grants the privileges needed by a user to be a Streams administrator directly, or generates a script that can be used to grant these privileges.

Syntax

```
DBMS_STREAMS_AUTH.GRANT_ADMIN_PRIVILEGE(
  grantee          IN VARCHAR2,
  grant_privileges IN BOOLEAN   DEFAULT true,
  file_name        IN VARCHAR2  DEFAULT NULL,
  directory_name   IN VARCHAR2  DEFAULT NULL);
```

Parameters

Table 97–2 GRANT_ADMIN_PRIVILEGE Procedure Parameters

Parameter	Description
grantee	The user to whom privileges are granted
grant_privileges	<p>If <code>true</code>, then the <code>GRANT_ADMIN_PRIVILEGE</code> procedure grants the privileges to the specified grantee directly, and adds the grantee to the <code>DBA_STREAMS_ADMINISTRATOR</code> data dictionary view with <code>YES</code> for both the <code>LOCAL_PRIVILEGES</code> column and the <code>ACCESS_FROM_REMOTE</code> column. If the user already has an entry in this data dictionary view, then this procedure does not make another entry, and no error is raised. If <code>true</code> and any of the grant statements fail, then an error is raised.</p> <p>If <code>false</code>, then the <code>GRANT_ADMIN_PRIVILEGE</code> procedure does not grant the privileges to the specified grantee directly, and does not add the grantee to the <code>DBA_STREAMS_ADMINISTRATOR</code> data dictionary view.</p> <p>You specify <code>false</code> when this procedure is generating a file that you will edit and then run. If you specify <code>false</code> and either the <code>file_name</code> or <code>directory_name</code> parameter is <code>NULL</code>, then an error is raised.</p>
file_name	<p>The name of the file generated by this procedure. The file contains all of the statements that grant the privileges. If a file with the specified file name exists in the specified directory name, then the grant statements are appended to the existing file.</p> <p>If <code>NULL</code>, then this procedure does not generate a file.</p>

Table 97-2 (Cont.) GRANT_ADMIN_PRIVILEGE Procedure Parameters

Parameter	Description
directory_name	<p>The directory into which the generated file is placed. The specified directory must be a directory object created using the SQL statement <code>CREATE DIRECTORY</code>. If you specify a directory, then the user who invokes this procedure must have <code>WRITE</code> privilege on the directory object.</p> <p>If the <code>file_name</code> parameter is <code>NULL</code>, then this parameter is ignored, and this procedure does not generate a file.</p> <p>If <code>NULL</code> and the <code>file_name</code> parameter is non-<code>NULL</code>, then an error is raised.</p>

Usage Notes

The user who runs this procedure must be an administrative user who can grant privileges to other users.

Specifically, this procedure grants the following privileges to the specified user:

- The `RESTRICTED SESSION` system privilege
- `EXECUTE` on the following packages:
 - `DBMS_APPLY_ADM`
 - `DBMS_AQ`
 - `DBMS_AQADM`
 - `DBMS_AQIN`
 - `DBMS_AQELM`
 - `DBMS_CAPTURE_ADM`
 - `DBMS_FLASHBACK`
 - `DBMS_PROPAGATION_ADM`
 - `DBMS_RULE_ADM`
 - `DBMS_STREAMS_ADM`
 - `DBMS_STREAMS_MESSAGING`
 - `DBMS_TRANSFORM`
- Privileges to enqueue events into and dequeue events from any queue

- Privileges to manage any queue
- Privileges to create, alter, and execute any of the following types of objects in the user's own schema and in other schemas:
 - Evaluation contexts
 - Rule sets
 - Rules

In addition, the grantee has the ability to grant these privileges to other users.

- `SELECT` privilege on data dictionary views related to Streams
- The ability to allow a remote Streams administrator to perform administrative actions through a database link by connecting to the grantee. This ability is enabled by running the `GRANT_REMOTE_ADMIN_ACCESS` procedure in this package.

Note:

- To view all of the statements run by this procedure in detail, you can use the procedure to generate a script and then view the script in a text editor.
 - This procedure does not grant any roles to the grantee.
 - This procedure grants only the privileges necessary to configure and administer a Streams environment. You may grant more privileges to the grantee if necessary.
-
-

See Also:

- "[GRANT_REMOTE_ADMIN_ACCESS Procedure](#)" on page 97-6
- *Oracle Streams Concepts and Administration* for more information about configuring a Streams administrator

GRANT_REMOTE_ADMIN_ACCESS Procedure

This procedure enables a remote Streams administrator to perform administrative actions at the local database by connecting to the grantee using a database link.

Syntax

```
DBMS_STREAMS_AUTH.GRANT_REMOTE_ADMIN_ACCESS(  
    grantee IN VARCHAR2);
```

Parameters

Table 97–3 GRANT_REMOTE_ADMIN_ACCESS Procedure Parameter

Parameter	Description
grantee	The user who allows remote access. The procedure adds the grantee to the DBA_STREAMS_ADMINISTRATOR data dictionary view with YES for the ACCESS_FROM_REMOTE column. If the user already has an entry in this data dictionary view, then this procedure does not make another entry. Instead, it updates the ACCESS_FROM_REMOTE column to YES.

Usage Notes

Typically, you run this procedure and specify a grantee at a local source database if a downstream capture process captures changes originating at the local source database. The Streams administrator at a downstream capture database administers the source database using this connection. You may also run this procedure at a database running an apply process so that a remote Streams administrator can set instantiation SCNs at the local database.

Note: The GRANT_ADMIN_PRIVILEGE procedure runs this procedure.

See Also: ["GRANT_ADMIN_PRIVILEGE Procedure"](#) on page 97-3

REVOKE_ADMIN_PRIVILEGE Procedure

This procedure either revokes Streams administrator privileges from a user directly, or generates a script that can be used to revoke these privileges.

Syntax

```
DBMS_STREAMS_AUTH.REVOKE_ADMIN_PRIVILEGE(
  grantee          IN  VARCHAR2,
  revoke_privileges IN  BOOLEAN  DEFAULT true,
  file_name        IN  VARCHAR2  DEFAULT NULL,
  directory_name   IN  VARCHAR2  DEFAULT NULL);
```

Parameters

Table 97–4 REVOKE_ADMIN_PRIVILEGE Procedure Parameters

Parameter	Description
grantee	The user from whom privileges are revoked
revoke_privileges	<p>If <code>true</code>, then the <code>REVOKE_ADMIN_PRIVILEGE</code> procedure revokes the privileges from the specified user directly, and removes the user from the <code>DBA_STREAMS_ADMINISTRATOR</code> data dictionary view. If the user does not have a record in this data dictionary view, then this procedure does not remove a record from the view, and no error is raised. If <code>true</code> and any of the revoke statements fail, then an error is raised. A revoke statement will fail if the user is not granted the privilege that is being revoked.</p> <p>If <code>false</code>, then the <code>REVOKE_ADMIN_PRIVILEGE</code> procedure does not revoke the privileges to the specified user directly, and does not remove the user from the <code>DBA_STREAMS_ADMINISTRATOR</code> data dictionary view.</p> <p>You specify <code>false</code> when this procedure is generating a file that you will edit and then run. If you specify <code>false</code> and either the <code>file_name</code> or <code>directory_name</code> parameter is <code>NULL</code>, then an error is raised.</p>
file_name	<p>The name of the file generated by this procedure. The file contains all of the statements that revoke the privileges. If a file with the specified file name exists in the specified directory name, then the revoke statements are appended to the existing file.</p> <p>If <code>NULL</code>, then this procedure does not generate a file.</p>

Table 97–4 (Cont.) REVOKE_ADMIN_PRIVILEGE Procedure Parameters

Parameter	Description
directory_name	<p>The directory into which the generated file is placed. The specified directory must be a directory object created using the SQL statement <code>CREATE DIRECTORY</code>. If you specify a directory, then the user who invokes this procedure must have <code>WRITE</code> privilege on the directory object.</p> <p>If the <code>file_name</code> parameter is <code>NULL</code>, then this parameter is ignored, and this procedure does not generate a file.</p> <p>If <code>NULL</code> and the <code>file_name</code> parameter is non-<code>NULL</code>, then an error is raised.</p>

Usage Notes

The user who runs this procedure must be an administrative user who can revoke privileges from other users. Specifically, this procedure revokes the privileges granted by running the `GRANT_ADMIN_PRIVILEGE` procedure in this package.

Note: To view all of the statements run by this procedure in detail, you can use the procedure to generate a script and then view the script in a text editor.

See Also: ["GRANT_ADMIN_PRIVILEGE Procedure"](#) on page 97-3

REVOKE_REMOTE_ADMIN_ACCESS Procedure

This procedure disables a remote Streams administrator from performing administrative actions by connecting to the grantee using a database link.

Note: The REVOKE_ADMIN_PRIVILEGE procedure runs this procedure.

See Also: ["REVOKE_ADMIN_PRIVILEGE Procedure"](#) on page 97-7

Syntax

```
DBMS_STREAMS_AUTH.REVOKE_REMOTE_ADMIN_ACCESS(
    grantee IN VARCHAR2);
```

Parameters

Table 97-5 REVOKE_REMOTE_ADMIN_ACCESS Procedure Parameter

Parameter	Description
grantee	<p>The user for whom access from a remote Streams administrator is disabled.</p> <p>If a row for the grantee exists in the DBA_STREAMS_ADMINISTRATOR data dictionary view, then the procedure updates the ACCESS_FROM_REMOTE column for the grantee to NO. If, after this update, both the LOCAL_PRIVILEGES column and the ACCESS_FROM_REMOTE column are NO for the grantee, then this procedure removes the grantee from the view.</p> <p>If no row for the grantee exists in the DBA_STREAMS_ADMINISTRATOR data dictionary view, then the procedure does not update the view and does not raise an error.</p>

DBMS_STREAMS_MESSAGING

The `DBMS_STREAMS_MESSAGING` package, one of a set of Streams packages, provides interfaces to enqueue messages into and dequeue messages from a `SYS.AnyData` queue.

See Also:

- *Oracle Streams Concepts and Administration* for more information about Streams and for an example that uses the procedures in this package
- *Oracle Streams Advanced Queuing User's Guide and Reference* for more information about queues and messaging

This chapter contains the following topic:

- [Summary of DBMS_STREAMS_MESSAGING Subprograms](#)

Summary of DBMS_STREAMS_MESSAGING Subprograms

Table 98–1 *DBMS_STREAMS_MESSAGING Package Subprograms*

Subprogram	Description
DEQUEUE Procedures on page 98-3	Uses the specified Streams messaging client to dequeue a message from the specified queue
ENQUEUE Procedures on page 98-6	The current user enqueues a message into the specified queue

DEQUEUE Procedures

These procedures use the specified Streams messaging client to dequeue a message from the specified queue.

Note: This procedure is overloaded. One version of this procedure contains the `msgid` OUT parameter, and the other does not.

Syntax

```
DBMS_STREAMS_MESSAGING.DEQUEUE(
  queue_name      IN   VARCHAR2,
  streams_name    IN   VARCHAR2,
  payload         OUT  SYS.AnyData,
  dequeue_mode    IN   VARCHAR2      DEFAULT 'REMOVE',
  navigation      IN   VARCHAR2      DEFAULT 'NEXT MESSAGE',
  wait            IN   BINARY_INTEGER DEFAULT FOREVER,
  msgid          OUT  RAW);
```

Parameters

Table 98–2 DEQUEUE Procedure Parameters

Parameter	Description
<code>queue_name</code>	<p>The name of the local queue from which messages will be dequeued, specified as [<i>schema_name</i>.]<i>queue_name</i>. The current database must contain the queue, and the queue must be a secure queue of <code>SYS.AnyData</code> type.</p> <p>For example, to specify a queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter. If the schema is not specified, then the current user is the default.</p>
<code>streams_name</code>	<p>The name of the Streams messaging client. For example, if the user <code>strmadmin</code> is the messaging client, then specify <code>strmadmin</code>.</p> <p>If <code>NULL</code> and a relevant messaging client for the queue exists, then the relevant messaging client is used. If <code>NULL</code> and multiple relevant messaging clients for the queue exist, then an error is raised.</p>
<code>payload</code>	The payload that is dequeued

Table 98–2 (Cont.) DEQUEUE Procedure Parameters

Parameter	Description
dequeue_mode	<p>Specify one of the following settings:</p> <p>REMOVE: Read the message and delete it. This setting is the default. The message can be retained in the queue table based on the retention properties.</p> <p>LOCKED: Read and obtain a write lock on the message. The lock lasts for the duration of the transaction. This setting is equivalent to a select for update statement.</p> <p>BROWSE: Read the message without acquiring any lock on the message. This specification is equivalent to a select statement.</p>
navigation	<p>Specifies the position of the message that will be retrieved. First, the position is determined. Second, the search criterion is applied. Finally, the message is retrieved.</p> <p>Specify one of the following settings:</p> <p>NEXT MESSAGE: Retrieve the next message that is available and matches the search criteria. If the previous message belongs to a message group, then retrieve the next available message that matches the search criteria and belongs to the message group. This setting is the default.</p> <p>NEXT TRANSACTION: Skip the remainder of the current message group (if any) and retrieve the first message of the next message group. This setting can only be used if message grouping is enabled for the current queue.</p> <p>FIRST MESSAGE: Retrieves the first message which is available and matches the search criteria. This setting resets the position to the beginning of the queue.</p> <p>Note: Each message group contains the messages in a single transaction.</p> <p>See Also: <i>Oracle Streams Advanced Queuing User's Guide and Reference</i> for more information about dequeue options</p>
wait	<p>Either FOREVER or NO_WAIT</p> <p>If FOREVER, then the dequeue call is blocked without a time out until a message is available in the queue.</p> <p>If NO_WAIT, then a wait time of zero seconds is used. In this case, the dequeue will return immediately even if there are no messages in the queue.</p>
msgid	Specifies the message identifier of the message that is dequeued

Exceptions

Table 98–3 *DEQUEUE Procedure Exceptions*

Exception	Description
ENDOF_CURTRANS	<p>Dequeue has reached the end of the messages in the current transaction. Specify this exception in the following way:</p> <pre>SYS.DBMS_STREAMS_MESSAGING.ENDOF_CURTRANS</pre> <p>Every dequeue procedure should include an exception handler that handles this exception.</p>
NOMOREMSGS	<p>There are no more messages in the queue for the dequeue operation. Specify this exception in the following way:</p> <pre>SYS.DBMS_STREAMS_MESSAGING.NOMOREMSGS</pre> <p>A dequeue procedure that specifies <code>NO_WAIT</code> for the <code>wait</code> parameter should include an exception handler that handles this exception.</p>

ENQUEUE Procedures

These procedures enable the current user to enqueue a message into the specified queue.

Note: This procedure is overloaded. One version of this procedure contains the `msgid` OUT parameter, and the other does not.

Syntax

```
DBMS_STREAMS_MESSAGING.ENQUEUE(
  queue_name IN VARCHAR2,
  payload    IN SYS.AnyData,
  msgid      OUT RAW);
```

Parameters

Table 98–4 ENQUEUE Procedure Parameters

Parameter	Description
<code>queue_name</code>	The name of the local queue into which messages will be enqueued, specified as <code>[schema_name .] queue_name</code> . The current database must contain the queue, and the queue must be a secure queue of <code>SYS.AnyData</code> type. For example, to specify a queue named <code>streams_queue</code> in the <code>strmadmin</code> schema, enter <code>strmadmin.streams_queue</code> for this parameter. If the schema is not specified, then the current user is the default.
<code>payload</code>	The payload that is enqueued
<code>msgid</code>	Specifies the message identifier of the message that is enqueued

Usage Notes

To successfully enqueue messages into a queue, the current user must be mapped to a unique Advanced Queuing agent with the same name as the current user. You can run the `DBMS_STREAMS_ADM.SET_UP_QUEUE` procedure and specify a user as the queue user to grant the necessary privileges to the user to perform enqueues. The Advanced Queuing agent is created automatically when you run `SET_UP_QUEUE` and specify a queue user.

See Also: ["SET_UP_QUEUE Procedure"](#) on page 96-107

DBMS_STREAMS_TABLESPACE_ADM

The `DBMS_STREAMS_TABLESPACE_ADM` package, one of a set of Streams packages, provides administrative interfaces for copying tablespaces between databases and moving tablespaces from one database to another. This package uses transportable tablespaces, Data Pump, and the `DBMS_FILE_TRANSFER` package.

See Also: *Oracle Streams Concepts and Administration* and *Oracle Streams Replication Administrator's Guide* for more information about this package and Streams

This chapter contains the following topics:

- [Using DBMS_STREAMS_TABLESPACE_ADM](#)
 - [Overview](#)
 - [Types](#)
- [Summary of DBMS_STREAMS_TABLESPACE_ADM Subprograms](#)

Using DBMS_STREAMS_TABLESPACE_ADM

- [Overview](#)
- [Types](#)

Overview

Either a simple tablespace or a self-contained tablespace set must be specified in each procedure in this package.

A **self-contained tablespace** has no references from the tablespace pointing outside of the tablespace. For example, if an index in the tablespace is for a table in a different tablespace, then the tablespace is not self-contained. A **simple tablespace** is a self-contained tablespace that uses only one datafile.

A simple tablespace must be specified in the following procedures:

- [ATTACH_SIMPLE_TABLESPACE Procedure](#)
- [CLONE_SIMPLE_TABLESPACE Procedure](#)
- [DETACH_SIMPLE_TABLESPACE Procedure](#)
- [PULL_SIMPLE_TABLESPACE Procedure](#)

A **self-contained tablespace set** has no references from inside the set of tablespaces pointing outside of the set of tablespaces. For example, if a partitioned table is partially contained in the set of tablespaces, then the set of tablespaces is not self-contained.

A self-contained tablespace set must be specified in the following procedures:

- [ATTACH_TABLESPACES Procedure](#)
- [CLONE_TABLESPACES Procedure](#)
- [DETACH_TABLESPACES Procedure](#)
- [PULL_TABLESPACES Procedure](#)

To determine whether a set of tablespaces is self-contained, use the `TRANSPORT_SET_CHECK` procedure in the Oracle supplied package `DBMS_TTS`.

See Also: *Oracle Database Administrator's Guide* for more information about self-contained tablespaces and tablespace sets

Types

This package contains the PL/SQL types listed in [Table 99-1](#).

Table 99-1 DBMS_STREAMS_TABLESPACE_ADM Types

Type	Description
DIRECTORY_OBJECT_SET Type on page 99-3	Contains the names of one or more directory objects
FILE Type on page 99-3	Contains the directory object associated with a directory and the name of the file in the directory
FILE_SET Type on page 99-4	Contains one or more files
TABLESPACE_SET Type on page 99-4	Contains the names of one or more tablespaces

DIRECTORY_OBJECT_SET Type

Contains the names of one or more directory objects. Each name must be a directory object created using the SQL statement `CREATE DIRECTORY`.

Syntax

```
TYPE DIRECTORY_OBJECT_SET IS TABLE OF VARCHAR2(32)
  INDEX BY BINARY_INTEGER;
```

FILE Type

Contains the directory object associated with a directory and the name of the file in the directory.

Syntax

```
TYPE FILE IS RECORD(
  directory_object VARCHAR2(32),
  file_name        VARCHAR2(4000));
```

Attributes

Table 99-2 FILE Attributes

Attribute	Description
<code>directory_object</code>	The name of a directory object. You must specify the name of a directory object created using the SQL statement <code>CREATE DIRECTORY</code> .

Table 99–2 FILE Attributes

Attribute	Description
<code>file_name</code>	The name of the file in the corresponding directory associated with the directory object

FILE_SET Type

Contains one or more files.

Syntax

```
TYPE FILE_SET IS TABLE OF FILE  
    INDEX BY BINARY_INTEGER;
```

TABLESPACE_SET Type

Contains the names of one or more tablespaces.

Syntax

```
TYPE TABLESPACE_SET IS TABLE OF VARCHAR2(32)  
    INDEX BY BINARY_INTEGER;
```

Summary of DBMS_STREAMS_TABLESPACE_ADM Subprograms

Table 99–3 DBMS_STREAMS_TABLESPACE_ADM Package Subprograms

Subprogram	Description
ATTACH_SIMPLE_TABLESPACE Procedure on page 99-6	Uses Data Pump to import a simple tablespace previously exported using the DBMS_STREAMS_TABLESPACE_ADM package or Data Pump export
ATTACH_TABLESPACES Procedure on page 99-8	Uses Data Pump to import a self-contained tablespace set previously exported using the DBMS_STREAMS_TABLESPACE_ADM package or Data Pump export
CLONE_SIMPLE_TABLESPACE Procedure on page 99-11	Clones a simple tablespace. The tablespace can later be attached to a database.
CLONE_TABLESPACES Procedure on page 99-14	Clones a set of self-contained tablespaces. The tablespaces can later be attached to a database.
DETACH_SIMPLE_TABLESPACE Procedure on page 99-17	Detaches a simple tablespace. The tablespace can later be attached to a database.
DETACH_TABLESPACES Procedure on page 99-19	Detaches a set of self-contained tablespaces. The tablespaces can later be attached to a database.
PULL_SIMPLE_TABLESPACE Procedure on page 99-22	Copies a simple tablespace from a remote database and attaches it to the current database
PULL_TABLESPACES Procedure on page 99-25	Copies a set of self-contained tablespaces from a remote database and attaches the tablespaces to the current database

ATTACH_SIMPLE_TABLESPACE Procedure

This procedure uses Data Pump to import a simple tablespace previously exported using the `DBMS_STREAMS_TABLESPACE_ADM` package or Data Pump export.

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.ATTACH_SIMPLE_TABLESPACE(
  directory_object      IN  VARCHAR2,
  tablespace_file_name IN  VARCHAR2,
  converted_file_name  IN  VARCHAR2  DEFAULT NULL,
  datafile_platform   IN  VARCHAR2  DEFAULT NULL,
  tablespace_name      OUT VARCHAR2);
```

Parameters

Table 99–4 *ATTACH_SIMPLE_TABLESPACE Procedure Parameters*

Parameter	Description
<code>directory_object</code>	<p>The directory that contains the Data Pump dump file and the datafile for the tablespace. You must specify the name of a directory object created using the SQL statement <code>CREATE DIRECTORY</code>.</p> <p>The name of the Data Pump export dump file must be the same as the datafile name for the tablespace, except with a <code>.dmp</code> extension. If the <code>converted_file_name</code> is non-NULL, specify the dump file produced by the export database, not the file name after conversion.</p> <p>The Data Pump import log file is written to this directory. The name of the log file is the same as the datafile name for the tablespace, except with an <code>.alg</code> extension. If a file already exists with the same name as the log file in the directory, then the file is overwritten.</p> <p>If NULL, then an error is raised.</p>
<code>tablespace_file_name</code>	<p>The name of the datafile for the tablespace being imported.</p> <p>If NULL, then an error is raised.</p>

Table 99–4 (Cont.) ATTACH_SIMPLE_TABLESPACE Procedure Parameters

Parameter	Description
<code>converted_file_name</code>	<p>If the <code>datafile_platform</code> parameter is non-NULL and is not the same as the platform of the local import database, then specify a file name for the converted datafile. The datafile is converted to the platform of the local import database and copied to the new file name. The existing datafile is not modified nor deleted.</p> <p>If non-NULL and the <code>datafile_platform</code> parameter is NULL, then this parameter is ignored.</p> <p>If non-NULL and the <code>datafile_platform</code> parameter specifies the same platform as the local import database, then this parameter is ignored.</p> <p>If NULL and the <code>datafile_platform</code> parameter is non-NULL, then an error is raised.</p>
<code>datafile_platform</code>	<p>Specify NULL if the platform is the same for the export database and the current import database.</p> <p>Specify the platform for the export database if the platform is different for the export database and the import database.</p> <p>You can determine the platform of a database by querying the <code>PLATFORM_NAME</code> column in the <code>V\$DATABASE</code> dynamic performance view. The <code>V\$TRANSPORTABLE_PLATFORM</code> dynamic performance view lists all platforms that support cross-platform transportable tablespaces.</p>
<code>tablespace_name</code>	<p>Contains the name of the attached tablespace. The attached tablespace is read-only. You can use this parameter in an <code>ALTER TABLESPACE</code> statement to make it read/write if necessary.</p>

Usage Notes

To run this procedure, a user must meet the following requirements:

- Have `IMP_FULL_DATABASE` role
- Have `READ` and `WRITE` privilege on the directory object that contains the Data Pump export dump file and the datafiles for the tablespaces in the set, specified by the `directory_object` parameter

See Also: [Overview](#) on page 99-2

ATTACH_TABLESPACES Procedure

This procedure uses Data Pump to import a self-contained tablespace set previously exported using the `DBMS_STREAMS_TABLESPACE_ADM` package or Data Pump export.

In addition, this procedure optionally can create datafiles for the tablespace set that can be used with the local platform, if the platform at the export database is different than the local database platform.

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.ATTACH_TABLESPACES(
  datapump_job_name IN OUT VARCHAR2,
  dump_file          IN      FILE,
  tablespace_files   IN      FILE_SET,
  converted_files    IN      FILE_SET,
  datafiles_platform IN      VARCHAR2 DEFAULT NULL,
  log_file           IN      FILE      DEFAULT NULL,
  tablespace_names   OUT     TABLESPACE_SET);
```

Parameters

Table 99–5 *ATTACH_TABLESPACES Procedure Parameters*

Parameter	Description
<code>data_pump_job_name</code>	The Data Pump job name. Specify a Data Pump job name if you want to adhere to naming conventions or if you want to track the job more easily. If <code>NULL</code> , then the system generates a Data Pump job name.
<code>dump_file</code>	The file name of the Data Pump dump file to import. If <code>NULL</code> or if a file attribute is <code>NULL</code> , then an error is raised.
<code>tablespace_files</code>	The file set that contains the datafiles for the tablespace set being imported. If <code>NULL</code> , then an error is raised.

Table 99–5 (Cont.) ATTACH_TABLESPACES Procedure Parameters

Parameter	Description
<code>converted_files</code>	<p>If the <code>datafiles_platform</code> parameter is non-NULL and is not the same as the platform for the local import database, then specify a file set with the names of the converted datafiles. The datafiles are converted to the platform of the local import database and copied to the new file names. In this case, the number of files in the specified file set must match the number of files in the file set specified for the <code>tablespace_files</code> parameter. The existing datafiles are not modified nor deleted.</p> <p>If non-NULL and the <code>datafiles_platform</code> parameter is NULL, then this parameter is ignored.</p> <p>If non-NULL and the <code>datafiles_platform</code> parameter specifies the same platform as the local import database, then this parameter is ignored.</p> <p>If NULL and the <code>datafiles_platform</code> parameter is non-NULL, then an error is raised.</p>
<code>datafiles_platform</code>	<p>Specify NULL if the platform is the same for the export database and the current import database.</p> <p>Specify the platform for the export database if the platform is different for the export database and the import database.</p> <p>You can determine the platform of a database by querying the <code>PLATFORM_NAME</code> column in the <code>V\$DATABASE</code> dynamic performance view. The <code>V\$TRANSPORTABLE_PLATFORM</code> dynamic performance view lists all platforms that support cross-platform transportable tablespaces.</p>
<code>log_file</code>	<p>Specify the log file name for the Data Pump import.</p> <p>If NULL or if at least one file parameter is NULL, then the system generates a log file name with the extension <code>.alg</code> and places it in the Data Pump export dump file directory.</p> <p>If a file already exists with the same name as the log file in the directory, then the file is overwritten.</p>
<code>tablespace_names</code>	<p>Contains the names of the attached tablespaces. The attached tablespace is read-only. You can use the names in this parameter in an <code>ALTER TABLESPACE</code> statement to make them read/write if necessary.</p>

Usage Notes

To run this procedure, a user must meet the following requirements:

- Have `IMP_FULL_DATABASE` role

- Have `READ` and `WRITE` privilege on the directory objects that contain the Data Pump export dump file and the datafiles for the tablespaces in the set, specified by the `dump_file` parameter and the `tablespace_files` parameter, respectively
- Have `WRITE` privilege on the directory object that will hold the Data Pump import log file, specified by the `log_file` parameter if it is non-NULL
- Have `WRITE` privilege on the directory objects that will hold the converted datafiles for the tablespaces in the set if platform conversion is necessary. These directory objects are specified by the `converted_files` parameter if it is non-NULL.

See Also:

- [Overview](#) on page 99-2
- [Summary of DBMS_STREAMS_TABLESPACE_ADM Subprograms](#) on page 99-5

CLONE_SIMPLE_TABLESPACE Procedure

Clones a simple tablespace. The specified tablespace must be online.

Specifically, this procedure performs the following actions:

1. Makes the specified tablespace read-only if it is not read-only
2. Uses Data Pump to export the metadata for the tablespace and places the dump file in the specified directory
3. Places the datafile for the specified tablespace in the specified directory
4. If this procedure made the tablespace read-only, then makes the tablespace read/write

In addition, this procedure optionally can create a datafile for the tablespace that can be used with a platform that is different than the local database platform.

To run this procedure, a user must meet the following requirements:

- Have `EXP_FULL_DATABASE` role
- Have access to at least one data dictionary view that contains information about the tablespaces. These views include `DBA_TABLESPACES` and `USER_TABLESPACES`.
- Have `MANAGE TABLESPACE` or `ALTER TABLESPACE` on a tablespace if the tablespace must be made read-only
- Have `READ` privilege on the directory object for the directory that contains the datafile for the tablespace. The name of this tablespace is specified by the `tablespace_name` parameter. If a directory object does not exist for this directory, then create the directory object and grant the necessary privileges before you run this procedure.
- Have `READ` and `WRITE` privilege on the directory object that will contain the Data Pump export dump file, specified by the `directory_object` parameter

After cloning a tablespace using this procedure, you can add the tablespace to a different database using the `ATTACH_SIMPLE_TABLESPACE` procedure. If the database is a remote database and you want to use the `ATTACH_SIMPLE_TABLESPACE` procedure, then you can transfer the dump file and datafile to the remote system using the `DBMS_FILE_TRANSFER` package, FTP, or some other method.

See Also:

- [Overview](#) on page 99-2
- [ATTACH_SIMPLE_TABLESPACE Procedure](#) on page 99-6 and [PULL_SIMPLE_TABLESPACE Procedure](#) on page 99-22

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.CLONE_SIMPLE_TABLESPACE(
    tablespace_name      IN  VARCHAR2,
    directory_object     IN  VARCHAR2,
    destination_platform IN  VARCHAR2 DEFAULT NULL,
    tablespace_file_name OUT VARCHAR2);
```

Parameters**Table 99–6** CLONE_SIMPLE_TABLESPACE Procedure Parameters

Parameter	Description
tablespace_name	The tablespace to be cloned. If NULL, then an error is raised.
directory_object	The directory where the Data Pump export dump file, the Data Pump export log file, and the datafile for the tablespace are placed. You must specify the name of a directory object created using the SQL statement <code>CREATE DIRECTORY</code> . The name of the Data Pump export dump file is the same as the datafile name for the tablespace, except with a <code>.dmp</code> extension. If a file already exists with the same name as the dump file in the directory, then an error is raised. The name of the log file is the same as the datafile name for the tablespace, except with a <code>.clg</code> extension. If a file already exists with the same name as the log file in the directory, then the file is overwritten. If NULL, then an error is raised.

Table 99–6 (Cont.) CLONE_SIMPLE_TABLESPACE Procedure Parameters

Parameter	Description
destination_platform	<p>Specify NULL if the platform is the same for the current export database and the intended import database.</p> <p>Specify the platform for the intended import database if the platform is different for the export database and the import database.</p> <p>You can determine the platform of a database by querying the PLATFORM_NAME column in the V\$DATABASE dynamic performance view. The V\$TRANSPORTABLE_PLATFORM dynamic performance view lists all platforms that support cross-platform transportable tablespaces.</p>
tablespace_file_name	<p>Contains the name of the cloned tablespace datafile. This datafile is placed in the directory specified by the parameter directory_object.</p>

CLONE_TABLESPACES Procedure

Clones a set of self-contained tablespaces. All of the tablespaces in the specified tablespace set must be online.

Specifically, this procedure performs the following actions:

1. Makes any read/write tablespace in the specified tablespace set read-only
2. Uses Data Pump to export the metadata for the tablespaces in the tablespace set and places the dump file in the specified directory
3. Places the datafiles that comprise the specified tablespace set in the specified directory
4. If this procedure made a tablespace read-only, then makes the tablespace read/write

In addition, this procedure optionally can create datafiles for the tablespace set that can be used with a platform that is different than the local database platform.

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.CLONE_TABLESPACES(
  datapump_job_name      IN OUT VARCHAR2,
  tablespace_names       IN      TABLESPACE_SET,
  dump_file              IN      FILE,
  tablespace_directory_objects IN  DIRECTORY_OBJECT_SET,
  destination_platform  IN      VARCHAR2 DEFAULT NULL,
  log_file               IN      FILE      DEFAULT NULL,
  tablespace_files       OUT     FILE_SET);
```

Parameters

Table 99–7 CLONE_TABLESPACES Procedure Parameters

Parameter	Description
<code>data_pump_job_name</code>	The Data Pump job name. Specify a Data Pump job name if you want to adhere to naming conventions or if you want to track the job more easily. If NULL, then the system generates a Data Pump job name.
<code>tablespace_names</code>	The tablespace set to be cloned. If NULL, then an error is raised.

Table 99–7 (Cont.) CLONE_TABLESPACES Procedure Parameters

Parameter	Description
dump_file	<p>The file name of the Data Pump dump file that is exported.</p> <p>If NULL or if a file attribute is NULL, then an error is raised.</p> <p>If the specified file already exists, then an error is raised.</p>
tablespace_directory_objects	<p>The set of directory objects into which the datafiles for the tablespaces are copied. If more than one directory object is in the set, then a datafile is copied to each directory object in the set in sequence. In this case, if the end of the directory object set is reached, then datafile copying starts again with the first directory object in the set.</p> <p>If NULL, then datafiles for the tablespace set are copied to the dump file directory.</p>
destination_platform	<p>Specify NULL if the platform is the same for the current export database and the intended import database.</p> <p>Specify the platform for the intended import database if the platform is different for the export database and the import database.</p> <p>You can determine the platform of a database by querying the PLATFORM_NAME column in the V\$DATABASE dynamic performance view. The V\$TRANSPORTABLE_PLATFORM dynamic performance view lists all platforms that support cross-platform transportable tablespaces.</p>
log_file	<p>Specify the log file name for the Data Pump export.</p> <p>If NULL or if at least one file parameter is NULL, then the system generates a log file name with the extension .clg and places it in the dump file directory.</p> <p>If a file already exists with the same name as the log file in the directory, then the file is overwritten.</p>
tablespace_files	<p>Contains the datafiles for the cloned tablespace set. These datafiles are placed in the directories specified by the directory objects in the parameter tablespace_directory_objects.</p>

Usage Notes

To run this procedure, a user must meet the following requirements:

- Have `EXP_FULL_DATABASE` role
- Have access to at least one data dictionary view that contains information about the tablespaces. These views include `DBA_TABLESPACES` and `USER_TABLESPACES`.
- Have `MANAGE TABLESPACE` or `ALTER TABLESPACE` on a tablespace if the tablespace must be made read-only
- Have `READ` privilege on the directory objects for the directories that contain the datafiles for the tablespace set. The names of these tablespaces are specified by the `tablespace_names` parameter. If a directory object does not exist for one or more of these directories, then create the directory objects and grant the necessary privileges before you run this procedure.
- Have `READ` and `WRITE` privilege on the directory object that will contain the Data Pump export dump file, specified by the `dump_file` parameter
- Have `WRITE` privilege on the directory objects that will contain the copied datafiles for the tablespaces in the set, specified by the `tablespace_directory_objects` parameter if non-NULL
- Have `WRITE` privilege on the directory object that will contain the Data Pump export log file, specified by the `log_file` parameter if non-NULL

After cloning a tablespace set using this procedure, you can add the tablespaces to a different database using the `ATTACH_TABLESPACES` procedure. If the database is a remote database and you want to use the `ATTACH_TABLESPACES` procedure, then you can transfer the dump file and datafiles to the remote system using the `DBMS_FILE_TRANSFER` package, FTP, or some other method.

See Also:

- [Overview](#) on page 99-2
- [Summary of DBMS_STREAMS_TABLESPACE_ADM Subprograms](#) on page 99-3
- [ATTACH_TABLESPACES Procedure](#) on page 99-8 and [PULL_TABLESPACES Procedure](#) on page 99-25

DETACH_SIMPLE_TABLESPACE Procedure

Detaches a simple tablespace. The specified tablespace must be online.

Specifically, this procedure performs the following actions:

1. Makes the specified tablespace read-only if it is not read-only
2. Uses Data Pump to export the metadata for the tablespace and places the dump file in the directory that contains the tablespace datafile
3. Drops the tablespace and its contents from the database

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.DETACH_SIMPLE_TABLESPACE(
    tablespace_name      IN VARCHAR2,
    directory_object     OUT VARCHAR2,
    tablespace_file_name OUT VARCHAR2);
```

Parameters

Table 99–8 *DETACH_SIMPLE_TABLESPACE Procedure Parameters*

Parameter	Description
<code>data_pump_job_name</code>	The Data Pump job name. Specify a Data Pump job name if you want to adhere to naming conventions or if you want to track the job more easily. If NULL, then the system generates a Data Pump job name.
<code>directory_object</code>	Contains the directory where the Data Pump export dump file and the Data Pump export log file are placed. The procedure uses the directory of the datafile for the tablespace. Therefore, make sure a directory object created using the SQL statement <code>CREATE DIRECTORY</code> exists for this directory. The name of the Data Pump export dump file is the same as the datafile name for the tablespace, except with a <code>.dmp</code> extension. If a file already exists with the same name as the dump file in the directory, then an error is raised. The name of the log file is the same as the datafile name for the tablespace, except with a <code>.dlg</code> extension. If a file already exists with the same name as the log file in the directory, then the file is overwritten.
<code>tablespace_file_name</code>	Contains the name of the detached tablespace datafile.

Usage Notes

To run this procedure, a user must meet the following requirements:

- Have `EXP_FULL_DATABASE` role
- Have access to at least one data dictionary view that contains information about the tablespaces. These views include `DBA_TABLESPACES` and `USER_TABLESPACES`.
- Have `DROP TABLESPACE` privilege
- Have `MANAGE TABLESPACE` or `ALTER TABLESPACE` on a tablespace if the tablespace must be made read-only
- Have `READ` and `WRITE` privilege on the directory object for the directory that contains the tablespace datafile. The name of this tablespace is specified by the `tablespace_name` parameter. If a directory object does not exist for this directory, then create the directory object and grant the necessary privileges before you run this procedure. This directory also will contain the Data Pump export dump file generated by this procedure.

After detaching a tablespace using this procedure, you can add the tablespace to a different database using the `ATTACH_SIMPLE_TABLESPACE` procedure. If the database is a remote database and you want to use the `ATTACH_SIMPLE_TABLESPACE` procedure, then you can transfer the dump file and datafile to the remote system using the `DBMS_FILE_TRANSFER` package, FTP, or some other method. You may use the two `OUT` parameters in this procedure to accomplish the attach or pull operation.

Note: Do not use the `DETACH_SIMPLE_TABLESPACE` procedure on a tablespace if the tablespace is using the Oracle-managed files feature. If you do, then the datafile for the tablespace is dropped automatically when the tablespace is dropped.

See Also:

- [Overview](#) on page 99-2
- [ATTACH_SIMPLE_TABLESPACE Procedure](#) on page 99-6 and [PULL_SIMPLE_TABLESPACE Procedure](#) on page 99-22
- *Oracle Database Administrator's Guide* for more information about the Oracle-managed files feature

DETACH_TABLESPACES Procedure

Detaches a set of self-contained tablespaces. All of the tablespaces in the specified tablespace set must be online and any table partitions must not span tablespaces in the tablespace set.

Specifically, this procedure performs the following actions:

1. Makes any read/write tablespace in the specified tablespace set read-only
2. Uses Data Pump to export the metadata for the tablespace set and places the dump file in the specified directory
3. Drops the tablespaces in the specified tablespace set and their contents from the database

To run this procedure, a user must meet the following requirements:

- Have `EXP_FULL_DATABASE` role
- Have access to at least one data dictionary view that contains information about the tablespaces. These views include `DBA_TABLESPACES` and `USER_TABLESPACES`.
- Have `DROP TABLESPACE` privilege
- Have `MANAGE TABLESPACE` or `ALTER TABLESPACE` on a tablespace if the tablespace must be made read-only
- Have `READ` privilege on the directory objects for the directories that contain the datafiles for the tablespace set. The names of these tablespaces are specified by the `tablespace_name` parameter. If a directory object does not exist for one or more of these directories, then create the directory objects and grant the necessary privileges before you run this procedure.
- Have `READ` and `WRITE` privilege on the directory object that will contain the Data Pump export dump file, specified by the `dump_file` parameter
- Have `WRITE` privilege on the directory object that will contain the Data Pump export the log file, specified by the `log_file` parameter if non-NULL

After detaching a tablespace set using this procedure, you can add the tablespaces in the set to a different database using the `ATTACH_TABLESPACES` procedure. If the database is a remote database and you want to use the `ATTACH_TABLESPACES` procedure, then you can transfer the dump file and datafiles to the remote system using the `DBMS_FILE_TRANSFER` package, FTP, or some other method.

Note: Do not use the `DETACH_TABLESPACES` procedure if any of the tablespaces in the tablespace set are using the Oracle-managed files feature. If you do, then the datafiles for these tablespaces are dropped automatically when the tablespaces are dropped.

See Also:

- [Overview](#) on page 99-2
- ["Summary of DBMS_STREAMS_TABLESPACE_ADM Subprograms"](#) on page 99-5
- [ATTACH_TABLESPACES Procedure](#) on page 99-8 and [PULL_TABLESPACES Procedure](#) on page 99-25
- *Oracle Database Administrator's Guide* for more information about the Oracle-managed files feature

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.DETACH_TABLESPACES(
  datapump_job_name IN OUT VARCHAR2,
  tablespace_names  IN      TABLESPACE_SET,
  dump_file         IN      FILE,
  log_file          IN      FILE DEFAULT NULL,
  tablespace_files  OUT     FILE_SET);
```

Parameters

Table 99–9 *DETACH_TABLESPACES Procedure Parameters*

Parameter	Description
<code>data_pump_job_name</code>	The Data Pump job name. Specify a Data Pump job name if you want to adhere to naming conventions or if you want to track the job more easily. If <code>NULL</code> , then the system generates a Data Pump job name.
<code>tablespace_names</code>	The tablespace set to be detached. If <code>NULL</code> , then an error is raised.
<code>dump_file</code>	The file name of the Data Pump dump file that is exported. If <code>NULL</code> or if a file attribute is <code>NULL</code> , then an error is raised. If the specified file already exists, then an error is raised.

Table 99–9 (Cont.) DETACH_TABLESPACES Procedure Parameters

Parameter	Description
log_file	Specify the log file name for the Data Pump export. If NULL or if at least one file parameter is NULL, then the system generates a log file name with the extension .dlg and places it in the dump file directory. If a file already exists with the same name as the log file in the directory, then the file is overwritten.
tablespace_files	Contains the names of the datafiles for the detached tablespace set.

PULL_SIMPLE_TABLESPACE Procedure

Copies a simple tablespace from a remote database and attaches it to the current database. The specified tablespace at the remote database must be online.

Specifically, this procedure performs the following actions:

1. Makes the specified tablespace read-only at the remote database if it is not read-only
2. Uses Data Pump to export the metadata for the tablespace
3. Uses a database link and the `DBMS_FILE_TRANSFER` package to transfer the datafile for the tablespace and the log file for the Data Pump export to the current database
4. Places the datafile for the specified tablespace and the log file for the Data Pump export in the specified directory at the local database
5. If this procedure made the tablespace read-only, then makes the tablespace read/write
6. Uses Data Pump to import the metadata for the tablespace in the at the local database

In addition, this procedure optionally can create a datafile for the tablespace that can be used with the local platform, if the platform at the remote database is different than the local database platform.

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.PULL_SIMPLE_TABLESPACE(
    tablespace_name      IN VARCHAR2,
    database_link        IN VARCHAR2,
    directory_object     IN VARCHAR2  DEFAULT NULL,
    conversion_extension IN VARCHAR2  DEFAULT NULL);
```

Parameters

Table 99–10 *PULL_SIMPLE_TABLESPACE Procedure Parameters*

Parameter	Description
<code>tablespace_name</code>	The tablespace to be pulled. If <code>NULL</code> , then an error is raised.

Table 99–10 (Cont.) PULL_SIMPLE_TABLESPACE Procedure Parameters

Parameter	Description
database_link	The name of the database link to the database that contains the tablespace to pull. If NULL, then an error is raised.
directory_object	The directory object to which the datafile for the tablespace is copied on the local database. You must specify the name of a directory object created using the SQL statement CREATE DIRECTORY. The Data Pump import log file is written to this directory. The name of the log file is the same as the datafile name for the tablespace, except with a .plg extension. If a file already exists with the same name as the log file in the directory, then the file is overwritten. If NULL, then an error is raised.
conversion_extension	Specify NULL if the platform is the same for the remote export database and the current import database. If the platform is different for the export database and the import database, then specify an extension for the tablespace datafile that is different than the extension for the tablespace datafile at the remote database. In this case, the procedure transfers the datafile to the import database and converts it to be compatible with the current import database platform automatically. After conversion is complete, the original datafile is deleted at the import database.

Usage Notes

To run this procedure, a user must meet the following requirements on the remote database:

- Have the EXP_FULL_DATABASE role
- Have execute privilege on the DBMS_STREAMS_TABLESPACE_ADM package
- Have access to at least one data dictionary view that contains information about the tablespaces. These views include DBA_TABLESPACES and USER_TABLESPACES.
- Have MANAGE TABLESPACE or ALTER TABLESPACE privilege on a tablespace if the tablespace must be made read-only
- Have READ privilege on the directory object for the directory that contains the datafile for the tablespace. The name of this tablespace is specified by the

`tablespace_name` parameter. If a directory object does not exist for this directory, then create the directory object and grant the necessary privileges before you run this procedure.

To run this procedure, a user must meet the following requirements on the local database:

- Have the roles `IMP_FULL_DATABASE` and `EXECUTE_CATALOG_ROLE`
- Have `WRITE` privilege on the directory object that will contain the Data Pump export the log file, specified by the `log_file` parameter if non-NULL
- Have `WRITE` privilege on the directory object that will hold the datafile for the tablespace, specified by the `directory_object` parameter

See Also: [Overview](#) on page 99-2

PULL_TABLESPACES Procedure

Copies a set of self-contained tablespaces from a remote database and attaches the tablespaces to the current database. All of the tablespaces in the specified tablespace set at the remote database must be online.

Specifically, this procedure performs the following actions:

1. Makes any read/write tablespace in the specified tablespace set at the remote database read-only
2. Uses Data Pump to export the metadata for the tablespaces in the tablespace set
3. Uses a database link and the `DBMS_FILE_TRANSFER` package to transfer the datafiles for the tablespace set and the log file for the Data Pump export to the current database
4. Places the datafiles that comprise the specified tablespace set in the specified directories at the local database
5. Places the log file for the Data Pump export in the specified directory at the local database
6. If this procedure made a tablespace read-only, then makes the tablespace read/write
7. Uses Data Pump to import the metadata for the tablespaces in the tablespace set at the local database

In addition, this procedure optionally can create datafiles for the tablespace set that can be used with the local platform, if the platform at the remote database is different than the local database platform.

Syntax

```
DBMS_STREAMS_TABLESPACE_ADM.PULL_TABLESPACES(
  datapump_job_name      IN OUT VARCHAR2,
  database_link          IN      VARCHAR2,
  tablespace_names       IN      TABLESPACE_SET,
  tablespace_directory_objects IN  DIRECTORY_OBJECT_SET,
  log_file               IN      FILE,
  conversion_extension   IN      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 99–11 *PULL_TABLESPACES Procedure Parameters*

Parameter	Description
<code>data_pump_job_name</code>	<p>The Data Pump job name. Specify a Data Pump job name if you want to adhere to naming conventions or if you want to track the job more easily.</p> <p>If <code>NULL</code>, then the system generates a Data Pump job name.</p>
<code>database_link</code>	<p>The name of the database link to the database that contains the tablespace set to pull.</p> <p>If <code>NULL</code>, then an error is raised.</p>
<code>tablespace_names</code>	<p>The tablespace set to be pulled.</p> <p>If <code>NULL</code>, then an error is raised.</p>
<code>tablespace_directory_objects</code>	<p>The set of directory objects to which the datafiles for the tablespaces are copied. If more than one directory object is in the set, then a datafile is copied to each directory object in the set in sequence. In this case, if the end of the directory object set is reached, then datafile copying starts again with the first directory object in the set.</p> <p>If <code>NULL</code>, then an error is raised.</p>
<code>log_file</code>	<p>Specify the log file name for the Data Pump export.</p> <p>If <code>NULL</code> or if at least one file parameter is <code>NULL</code>, then the system generates a log file name with the extension <code>.plg</code> and places it in one of the datafile directories.</p> <p>If a file already exists with the same name as the log file in the directory, then the file is overwritten.</p>

Table 99–11 (Cont.) PULL_TABLESPACES Procedure Parameters

Parameter	Description
<code>conversion_extension</code>	<p>Specify <code>NULL</code> if the platform is the same for the remote export database and the current import database.</p> <p>If the platform is different for the export database and the import database, then specify an extension for the tablespace datafiles that is different than the extension for the tablespace datafiles at the remote database. In this case, the procedure transfers the datafiles to the import database and converts them to be compatible with the current import database platform automatically. After conversion is complete, the original datafiles are deleted at the import database.</p>

Usage Notes

To run this procedure, a user must meet the following requirements on the remote database:

- Have the `EXP_FULL_DATABASE` role
- Have execute privilege on the `DBMS_STREAMS_TABLESPACE_ADM` package
- Have access to at least one data dictionary view that contains information about the tablespaces. These views include `DBA_TABLESPACES` and `USER_TABLESPACES`.
- Have `MANAGE TABLESPACE` or `ALTER TABLESPACE` privilege on a tablespace if the tablespace must be made read-only
- Have `READ` privilege on the directory objects for the directories that contain the datafiles for the tablespace set. The names of these tablespaces are specified by the `tablespace_names` parameter. If a directory object does not exist for one or more of these directories, then create the directory objects and grant the necessary privileges before you run this procedure.

To run this procedure, a user must meet the following requirements on the local database:

- Have the roles `IMP_FULL_DATABASE` and `EXECUTE_CATALOG_ROLE`
- Have `WRITE` privilege on the directory object that will contain the Data Pump export the log file, specified by the `log_file` parameter if non-`NULL`

- Have `WRITE` privilege on the directory objects that will hold the datafiles for the tablespaces in the set, specified by the `tablespace_directory_objects` parameter

See Also:

- [Overview](#) on page 99-2
- [Summary of DBMS_STREAMS_TABLESPACE_ADM Subprograms](#) on page 99-5

The `DBMS_TRACE` package contains the interface to trace PL/SQL functions, procedures, and exceptions.

This chapter contains the following topics:

- [Using DBMS_TRACE](#)
 - [Overview](#)
 - [Security Model](#)
 - [Constants](#)
 - [Restrictions](#)
 - [Operational Notes](#)
- [Summary of DBMS_TRACE Subprograms](#)

Using DBMS_TRACE

- [Overview](#)
- [Security Model](#)
- [Constants](#)
- [Restrictions](#)
- [Operational Notes](#)

Overview

DBMS_TRACE provides subprograms to start and stop PL/SQL tracing in a session. Oracle collects the trace data as the program executes and writes it to database tables.

A typical session involves:

- Starting PL/SQL tracing in session (DBMS_TRACE.SET_PLSQL_TRACE).
- Running an application to be traced.
- Stopping PL/SQL tracing in session (DBMS_TRACE.CLEAR_PLSQL_TRACE).

Security Model

This package must be created under SYS.

Constants

DBMS_TRACE uses these constants:

```
trace_all_calls          constant INTEGER := 1;
trace_enabled_calls      constant INTEGER := 2;
trace_all_exceptions     constant INTEGER := 4;
trace_enabled_exceptions constant INTEGER := 8;
trace_all_sql            constant INTEGER := 32;
trace_enabled_sql        constant INTEGER := 64;
trace_all_lines          constant INTEGER := 128;
trace_enabled_lines      constant INTEGER := 256;
```

```
trace_stop          constant INTEGER := 16384;
trace_pause         constant INTEGER := 4096;
trace_resume        constant INTEGER := 8192;
trace_limit         constant INTEGER := 16;
trace_major_version constant BINARY_INTEGER := 1;
trace_minor_version constant BINARY_INTEGER := 0;
```

Oracle recommends using the symbolic form for all these constants.

Restrictions

You cannot use PL/SQL tracing in a shared server environment.

Operational Notes

- [Controlling Data Volume](#)
- [Creating Database Tables to Collect DBMS_TRACE Output](#)
- [Collecting Trace Data](#)
- [Collected Data](#)
- [Trace Control](#)

Controlling Data Volume

Profiling large applications may produce a large volume of data. You can control the volume of data collected by *enabling* specific program units for trace data collection.

You can enable a program unit by compiling it debug. This can be done in one of two ways:

```
alter session set plsql_debug=true;
create or replace ... /* create the library units - debug information will be
generated */
```

or:

```
/* recompile specific library unit with debug option */
alter [PROCEDURE | FUNCTION | PACKAGE BODY] <libunit-name> compile debug;
```

Note: You cannot use the second method for anonymous blocks.

You can limit the amount of storage used in the database by retaining only the most recent 8,192 records (approximately) by including `TRACE_LIMIT` in the `TRACE_LEVEL` parameter of the `SET_PLSQL_TRACE` procedure.

Creating Database Tables to Collect DBMS_TRACE Output

You must create database tables into which the `DBMS_TRACE` package writes output. Otherwise, the data is not collected. To create these tables, run the script `TRACETAB.SQL`. The tables this script creates are owned by `SYS`.

Collecting Trace Data

The PL/SQL features you can trace are described in the script `DBMSPBT.SQL`. Some of the key tracing features are:

- [Tracing Calls](#)
- [Tracing Exceptions](#)
- [Tracing SQL](#)
- [Tracing Lines](#)

Additional features of `DBMS_TRACE` also allow pausing and resuming trace, and limiting the output.

Tracing Calls

Two levels of call tracing are available:

- Level 1: Trace all calls. This corresponds to the constant `trace_all_calls`.
- Level 2: Trace calls to enabled program units only. This corresponds to the constant `trace_enabled_calls`.

Enabling cannot be detected for remote procedure calls (RPCs); hence, RPCs are only traced with level 1.

Tracing Exceptions

Two levels of exception tracing are available:

- Level 1: Trace all exceptions. This corresponds to `trace_all_exceptions`.
- Level 2: Trace exceptions raised in enabled program units only. This corresponds to `trace_enabled_exceptions`.

Tracing SQL

Two levels of SQL tracing are available:

- Level 1: Trace all SQL. This corresponds to the constant `trace_all_sql`.
- Level 2: Trace SQL in enabled program units only. This corresponds to the constant `trace_enabled_sql`.

Tracing Lines

Two levels of line tracing are available:

- Level 1: Trace all lines. This corresponds to the constant `trace_all_lines`.
- Level 2: Trace lines in enabled program units only. This corresponds to the constant `trace_enabled_lines`.

When tracing lines, Oracle adds a record to the database each time the line number changes. This includes line number changes due to procedure calls and returns.

Note: For both all types of tracing, level 1 overrides level 2. For example, if both level 1 and level 2 are enabled, then level 1 takes precedence.

Collected Data

If tracing is requested only for enabled program units, and if the current program unit is not enabled, then no trace data is written.

When tracing calls, both the call and return are traced. The check for whether tracing is "enabled" passes if either the called routine or the calling routine is "enabled".

Call tracing will always output the program unit type, program unit name, and line number for both the caller and the callee. It will output the caller's stack depth. If the caller's unit is enabled, the calling procedure name will also be output. If the callee's unit is enabled, the called procedure name will be output.

Exception tracing writes out the line number. Raising the exception shows information on whether the exception is user-defined or pre-defined. It also shows the exception number in the case of pre-defined exceptions. Both the place where the exceptions are raised and their handler is traced. The check for tracing being "enabled" is done independently for the place where the exception is raised and the place where the exception is handled.

All calls to `DBMS_TRACE.SET_PLSQL_TRACE` and `DBMS_TRACE.CLEAR_PLSQL_TRACE` place a special trace record in the database. Therefore, it is always possible to determine when trace settings were changed.

Trace Control

As well as determining which items are collected, you can pause and resume the trace process. No information is gathered between the time that tracing is paused and the time that it is resumed. The constants `TRACE_PAUSE` and `TRACE_RESUME` are used to accomplish this. Trace records are generated to indicate that the trace was paused/resumed.

It is also possible to retain only the last 8,192 trace events of a run by using the constant `TRACE_LIMIT`. This allows tracing to be turned on without filling up the database. When tracing stops, the last 8,192 records are saved. The limit is approximate, since it is not checked on every trace record. At least the requested number of trace records will be generated; up to 1,000 additional records may be generated.

Summary of DBMS_TRACE Subprograms

Table 100–1 DBMS_TRACE Package Subprograms

Subprogram	Description
CLEAR_PLSQL_TRACE Procedure on page 100-8	Stops trace data dumping in session
PLSQL_TRACE_VERSION Procedure on page 100-9	Gets the version number of the trace package
SET_PLSQL_TRACE Procedure on page 100-10	Starts tracing in the current session

CLEAR_PLSQL_TRACE Procedure

This procedure disables trace data collection.

Syntax

```
DBMS_TRACE.CLEAR_PLSQL_TRACE;
```

PLSQL_TRACE_VERSION Procedure

This procedure gets the version number of the trace package. It returns the major and minor version number of the DBMS_TRACE package.

Syntax

```
DBMS_TRACE.PLSQL_TRACE_VERSION (  
    major OUT BINARY_INTEGER,  
    minor OUT BINARY_INTEGER);
```

Parameters

Table 100–2 PLSQL_TRACE_VERSION Procedure Parameters

Parameter	Description
major	Major version number of DBMS_TRACE.
minor	Minor version number of DBMS_TRACE.

SET_PLSQL_TRACE Procedure

This procedure enables PL/SQL trace data collection.

Syntax

```
DBMS_TRACE.SET_PLSQL_TRACE (  
    trace_level INTEGER);
```

Parameters

Table 100–3 SET_PLSQL_TRACE Procedure Parameters

Parameter	Description
trace_level	You must supply one or more of the constants as listed on page 100-2. By summing the constants, you can enable tracing of multiple PL/SQL language features simultaneously. The control constants "trace_pause", "trace_resume" and "trace_stop" should not be used in combination with other constants Also see " Collecting Trace Data " on page 100-4 for more information.

DBMS_TRANSACTION

The DBMS_TRANSACTION package provides access to SQL transaction statements from stored procedures.

See Also: *Oracle Database SQL Reference*

This chapter contains the following topics:

- [Using DBMS_TRANSACTION](#)
 - [Security Model](#)
- [Summary of DBMS_TRANSACTION Subprograms](#)

Using DBMS_TRANSACTION

- [Security Model](#)

Security Model

This package runs with the privileges of calling user, rather than the package owner SYS.

Summary of DBMS_TRANSACTION Subprograms

Table 101-1 DBMS_TRANSACTION Package Subprograms

Subprogram	Description
ADVISE_COMMIT Procedure on page 101-5	Equivalent to the SQL statement: ALTER SESSION ADVISE COMMIT
ADVISE_NOHING Procedure on page 101-6	Equivalent to the SQL statement: ALTER SESSION ADVISE NOTHING
ADVISE_ROLLBACK Procedure on page 101-7	Equivalent to the SQL statement: ALTER SESSION ADVISE ROLLBACK
BEGIN_DISCRETE_TRANSACTION Procedure on page 101-8	Sets "discrete transaction mode" for this transaction
COMMIT Procedure on page 101-9	Equivalent to the SQL statement: COMMIT
COMMIT_COMMENT Procedure on page 101-10	Equivalent to the SQL statement: COMMIT COMMENT <text>
COMMIT_FORCE Procedure on page 101-11	Equivalent to the SQL statement: COMMIT FORCE <text>, <number>"
LOCAL_TRANSACTION_ID Function on page 101-12	Returns the local (to instance) unique identifier for the current transaction
PURGE_LOST_DB_ENTRY Procedure on page 101-13	Enables removal of incomplete transactions from the local site when the remote database is destroyed or re-created before recovery completes
PURGE_MIXED Procedure on page 101-16	Deletes information about a given mixed outcome transaction
READ_ONLY Procedure on page 101-17	Equivalent to the SQL statement: SET TRANSACTION READ ONLY
READ_WRITE Procedure on page 101-18	equivalent to the SQL statement: SET TRANSACTION READ WRITE
ROLLBACK Procedure on page 101-19	Equivalent to the SQL statement: ROLLBACK

Table 101-1 (Cont.) DBMS_TRANSACTION Package Subprograms

Subprogram	Description
ROLLBACK_FORCE Procedure on page 101-20	Equivalent to the SQL statement: <code>ROLLBACK FORCE <text></code>
ROLLBACK_SAVEPOINT Procedure on page 101-21	Equivalent to the SQL statement: <code>ROLLBACK TO SAVEPOINT <savepoint_name></code>
SAVEPOINT Procedure on page 101-22	Equivalent to the SQL statement: <code>SAVEPOINT <savepoint_name></code>
STEP_ID Function on page 101-23	Returns local (to local transaction) unique positive integer that orders the DML operations of a transaction
USE_ROLLBACK_SEGMENT Procedure on page 101-24	Equivalent to the SQL statement: <code>SET TRANSACTION USE ROLLBACK SEGMENT <rb_seg_name></code>

ADVISE_COMMIT Procedure

This procedure is equivalent to the SQL statement:

```
ALTER SESSION ADVISE COMMIT
```

Syntax

```
DBMS_TRANSACTION.ADVISE_COMMIT;
```

ADVISE_NOTHING Procedure

This procedure is equivalent to the SQL statement:

```
ALTER SESSION ADVISE NOTHING
```

Syntax

```
DBMS_TRANSACTION.ADVISE_NOTHING;
```

ADVISE_ROLLBACK Procedure

This procedure is equivalent to the SQL statement:

```
ALTER SESSION ADVISE ROLLBACK
```

Syntax

```
DBMS_TRANSACTION.ADVISE_ROLLBACK;
```

BEGIN_DISCRETE_TRANSACTION Procedure

This procedure sets "discrete transaction mode" for this transaction.

Syntax

```
DBMS_TRANSACTION.BEGIN_DISCRETE_TRANSACTION;
```

Exceptions

Table 101–2 *BEGIN_DISCRETE_TRANSACTION Procedure Exceptions*

Exception	Description
ORA-08175	A transaction attempted an operation which cannot be performed as a discrete transaction. If this exception is encountered, then rollback and retry the transaction
ORA-08176	A transaction encountered data changed by an operation that does not generate rollback data: create index, direct load or discrete transaction. If this exception is encountered, then retry the operation that received the exception.

Examples

```
DISCRETE_TRANSACTION_FAILED exception;  
  pragma exception_init(DISCRETE_TRANSACTION_FAILED, -8175);  
CONSISTENT_READ_FAILURE exception;  
  pragma exception_init(CONSISTENT_READ_FAILURE, -8176);
```

COMMIT Procedure

This procedure is equivalent to the SQL statement:

```
COMMIT
```

This procedure is included for completeness, the functionality being already implemented as part of PL/SQL.

Syntax

```
DBMS_TRANSACTION.COMMIT;
```

COMMIT_COMMENT Procedure

This procedure is equivalent to the SQL statement:

```
COMMIT COMMENT <text>
```

Syntax

```
DBMS_TRANSACTION.COMMIT_COMMENT (  
    cmnt VARCHAR2);
```

Parameters

Table 101–3 COMMIT_COMMENT Procedure Parameters

Parameter	Description
cmnt	Comment to associate with this commit.

COMMIT_FORCE Procedure

This procedure is equivalent to the SQL statement:

```
COMMIT FORCE <text>, <number>"
```

Syntax

```
DBMS_TRANSACTION.COMMIT_FORCE (  
    xid VARCHAR2,  
    scn VARCHAR2 DEFAULT NULL);
```

Parameters

Table 101–4 COMMIT_FORCE Procedure Parameters

Parameter	Description
xid	Local or global transaction ID.
scn	System change number.

LOCAL_TRANSACTION_ID Function

This function returns the local (to instance) unique identifier for the current transaction. It returns null if there is no current transaction.

Syntax

```
DBMS_TRANSACTION.LOCAL_TRANSACTION_ID (  
    create_transaction BOOLEAN := FALSE)  
RETURN VARCHAR2;
```

Parameters

Table 101–5 LOCAL_TRANSACTION_ID Function Parameters

Parameter	Description
create_transaction	If true, then start a transaction if one is not currently active.

PURGE_LOST_DB_ENTRY Procedure

When a failure occurs during commit processing, automatic recovery consistently resolves the results at all sites involved in the transaction. However, if the remote database is destroyed or re-created before recovery completes, then the entries used to control recovery in `DBA_2PC_PENDING` and associated tables are never removed, and recovery will periodically retry. Procedure `PURGE_LOST_DB_ENTRY` enables removal of such transactions from the local site.

Syntax

```
DBMS_TRANSACTION.PURGE_LOST_DB_ENTRY (
    xid VARCHAR2);
```

Parameters

Table 101–6 *PURGE_LOST_DB_ENTRY Procedure Parameters*

Parameter	Description
<code>xid</code>	Must be set to the value of the <code>LOCAL_TRAN_ID</code> column in the <code>DBA_2PC_PENDING</code> table.

Usage Notes

WARNING: `PURGE_LOST_DB_ENTRY` should *only* be used when the other database is lost or has been re-created. Any other use may leave the other database in an unrecoverable or inconsistent state.

Before automatic recovery runs, the transaction may show up in `DBA_2PC_PENDING` as state "collecting", "committed", or "prepared". If the DBA has forced an in-doubt transaction to have a particular result by using "commit force" or "rollback force", then states "forced commit" or "forced rollback" may also appear. Automatic recovery normally deletes entries in any of these states. The only exception is when recovery finds a forced transaction which is in a state inconsistent with other sites in the transaction; in this case, the entry is left in the table and the `MIXED` column has the value 'yes'.

However, under certain conditions, it may not be possible for automatic recovery to run. For example, a remote database may have been permanently lost. Even if it is re-created, it gets a new database ID, so that recovery cannot identify it (a possible symptom is ORA-02062). In this case, the DBA may use the procedure `PURGE_LOST_DB_ENTRY` to clean up the entries in any state other than "prepared". The DBA does not need to be in any particular hurry to resolve these entries, because they are not holding any database resources.

The following table indicates what the various states indicate about the transaction and what the DBA actions should be:

Table 101-7 *PURGE_LOST_DB_ENTRY Procedure States*

State of Column	State of Global Transaction	State of Local Transaction	Normal DBA Action	Alternative DBA Action
Collecting	Rolled back	Rolled back	None	<code>PURGE_LOST_DB_ENTRY</code> (See Note 1)
Committed	Committed	Committed	None	<code>PURGE_LOST_DB_ENTRY</code> (See Note 1)
Prepared	Unknown	Prepared	None	<code>FORCE COMMIT</code> or <code>ROLLBACK</code>
Forced commit	Unknown	Committed	None	<code>PURGE_LOST_DB_ENTRY</code> (See Note 1)
Forced rollback	Unknown	Rolled back	None	<code>PURGE_LOST_DB_ENTRY</code> (See Note 1)
Forced commit (mixed)	Mixed	Committed	(See Note 2)	
Forced rollback (mixed)	Mixed	Rolled back	(See Note 2)	

NOTE 1: Use only if significant reconfiguration has occurred so that automatic recovery cannot resolve the transaction. Examples are total loss of the remote database, reconfiguration in software resulting in loss of two-phase commit capability, or loss of information from an external transaction coordinator such as a TP monitor.

NOTE 2: Examine and take any manual action to remove inconsistencies; then use the procedure `PURGE_MIXED`.

PURGE_MIXED Procedure

When in-doubt transactions are forced to commit or rollback (instead of letting automatic recovery resolve their outcomes), there is a possibility that a transaction can have a mixed outcome: Some sites commit, and others rollback. Such inconsistency cannot be resolved automatically by Oracle; however, Oracle flags entries in `DBA_2PC_PENDING` by setting the `MIXED` column to a value of 'yes'.

Oracle never automatically deletes information about a mixed outcome transaction. When the application or DBA is certain that all inconsistencies that might have arisen as a result of the mixed transaction have been resolved, this procedure can be used to delete the information about a given mixed outcome transaction.

Syntax

```
DBMS_TRANSACTION.PURGE_MIXED (  
    xid VARCHAR2);
```

Parameters

Table 101–8 *PURGE_MIXED Procedure Parameters*

Parameter	Description
<code>xid</code>	Must be set to the value of the <code>LOCAL_TRAN_ID</code> column in the <code>DBA_2PC_PENDING</code> table.

READ_ONLY Procedure

This procedure is equivalent to the SQL statement:

```
SET TRANSACTION READ ONLY
```

Syntax

```
DBMS_TRANSACTION.READ_ONLY;
```

READ_WRITE Procedure

This procedure is equivalent to the SQL statement:

```
SET TRANSACTION READ WRITE
```

Syntax

```
DBMS_TRANSACTION.READ_WRITE;
```

ROLLBACK Procedure

This procedure is equivalent to the SQL statement:

```
ROLLBACK
```

This procedure is included for completeness, the functionality being already implemented as part of PL/SQL.

Syntax

```
DBMS_TRANSACTION.ROLLBACK;
```

ROLLBACK_FORCE Procedure

This procedure is equivalent to the SQL statement:

```
ROLLBACK FORCE <text>
```

Syntax

```
DBMS_TRANSACTION.ROLLBACK_FORCE (  
    xid VARCHAR2);
```

Parameters

Table 101–9 *ROLLBACK_FORCE Procedure Parameters*

Parameter	Description
xid	Local or global transaction ID.

ROLLBACK_SAVEPOINT Procedure

This procedure is equivalent to the SQL statement:

```
ROLLBACK TO SAVEPOINT <savepoint_name>
```

This procedure is included for completeness, the functionality being already implemented as part of PL/SQL.

Syntax

```
DBMS_TRANSACTION.ROLLBACK_SAVEPOINT (  
    savept VARCHAR2);
```

Parameters

Table 101–10 ROLLBACK_SAVEPOINT Procedure Parameters

Parameter	Description
savept	Savepoint identifier.

SAVEPOINT Procedure

This procedure is equivalent to the SQL statement:

```
SAVEPOINT <savepoint_name>
```

This procedure is included for completeness, the feature being already implemented as part of PL/SQL.

Syntax

```
DBMS_TRANSACTION.SAVEPOINT (  
    savept VARCHAR2);
```

Parameters

Table 101–11 *SAVEPOINT Procedure Parameters*

Parameter	Description
savept	Savepoint identifier.

STEP_ID Function

This function returns local (to local transaction) unique positive integer that orders the DML operations of a transaction.

Syntax

```
DBMS_TRANSACTION.STEP_ID  
RETURN NUMBER;
```

USE_ROLLBACK_SEGMENT Procedure

This procedure is equivalent to the SQL statement:

```
SET TRANSACTION USE ROLLBACK SEGMENT <rb_seg_name>
```

Syntax

```
DBMS_TRANSACTION.USE_ROLLBACK_SEGMENT (  
    rb_name VARCHAR2);
```

Parameters

Table 101–12 *USE_ROLLBACK_SEGMENT Procedure Parameters*

Parameter	Description
rb_name	Name of rollback segment to use.

DBMS_TRANSFORM

The DBMS_TRANSFORM package provides an interface to the message format transformation features of Oracle Advanced Queuing.

See Also: *Oracle Streams Advanced Queuing User's Guide and Reference* for more on message format transformations.

This chapter contains the following topic:

- [Summary of DBMS_TRANSFORM Subprograms](#)

Summary of DBMS_TRANSFORM Subprograms

Table 102–1 *DBMS_TRANSFORM Package Subprograms*

Subprograms	Description
CREATE_TRANSFORMATION Procedure on page 102-3	Creates a transformation that maps an object of the source type to an object of the destination type
DROP_TRANSFORMATION Procedure on page 102-5	Drops the given transformation
MODIFY_TRANSFORMATION Procedure on page 102-6	Modifies an existing transformation

CREATE_TRANSFORMATION Procedure

This procedure creates a transformation that maps an object of the source type to an object of the target type. The transformation expression can be a SQL expression or a PL/SQL function. It must return an object of the target type.

Syntax

```
DBMS_TRANSFORM.CREATE_TRANSFORMATION (
  schema          VARCHAR2(30),
  name            VARCHAR2(30),
  from_schema     VARCHAR2(30),
  from_type       VARCHAR2(30),
  to_schema       VARCHAR2(30),
  to_type         VARCHAR2(30),
  transformation   VARCHAR2(4000));
```

Parameters

Table 102–2 CREATE_TRANSFORMATION Procedure Parameters

Parameter	Description
schema	Specifies the schema of the transformation.
name	Specifies the name of the transformation.
from_schema	Specifies the schema of the source type.
from_type	Specifies the source type.
to_schema	Specifies the target type schema.
to_type	Specifies the target type.
transformation	Specifies the transformation expression, returning an object of the target type. The expression must be a function returning an object of the target type or a constructor expression for the target type. You can choose not to specify a transformation expression and instead specify transformations for attributes of the target type using MODIFY_TRANSFORMATION.

Usage Notes

- The transformation expression must be a SQL expression or a PL/SQL function returning the type of the specified attribute of the target type.

- To create, modify or drop transformations, a user must be granted execute privileges on `DBMS_TRANSFORM`. The user must also have execute privileges on the user defined types that are the source and destination types of the transformation. In addition, the user must also have execute privileges on any PLSQL function being used in the transformation function.
- The transformation cannot write database state (perform DML) or commit or rollback the current transaction.
- The transformation must be a SQL function with source type as input type, returning an object of the target type. It could also be a SQL expression of target type, referring to a source type. All references to the source type must be of the form `source.user_data`.
- Both source and target types must be non-scalar database types. A null transformation expression maps to a null target object.
- For using the transformation at enqueue and dequeue time, the login user invoking the operation must have execute privileges on the PLSQL functions used by the transformation. For propagation, the owning schema of the queue must have these privileges.

DROP_TRANSFORMATION Procedure

This procedure drops the given transformation.

Syntax

```
DBMS_TRANSFORM.DROP_TRANSFORMATION (  
    schema      VARCHAR2(30),  
    name        VARCHAR2(30));
```

Parameters

Table 102–3 *DROP_TRANSFORMATION Procedure Parameters*

Parameter	Description
schema	Specifies the schema of the transformation.
name	Specifies the name of the transformation.

MODIFY_TRANSFORMATION Procedure

This procedure modifies the transformation expression for the given transformation.

Syntax

```
DBMS_TRANSFORM.MODIFY_TRANSFORMATION (  
    schema          VARCHAR2(30),  
    name            VARCHAR2(30),  
    attribute_number INTEGER,  
    transformation  VARCHAR2(4000));
```

Parameters

Table 102–4 *MODIFY_TRANSFORMATION Procedure Parameters*

Parameter	Description
schema	Specifies the schema of the transformation.
name	Specifies the name of the transformation.
attribute_number	The attribute of the target type for which the new transformation expression is being specified. When specifying the new transformation as a single expression of the target type, specify a value of 0.
transformation	The transformation expression must be a SQL expression or a PL/SQL function returning the type of the specified attribute of the target type. If the attribute_number is 0, then the expression must be a PL/SQL function returning an object of the target type or a constructor expression for the target type.

Usage Notes

- If the new transformation is a single expression of the target type, it may be specified with an `attribute_number` of 0. The new transformation may also be specified for each attribute of the target type.
- You can use this procedure to define the transformation as a separate expression for each attribute of the target type. For large transformations, this representation may be more readable and allow the application of fine grain control over the transformation. If the transformation expression was left

unspecified for some of the attributes of the target type, they are evaluated to null when the transformation is applied.

The `DBMS_TYPES` package consists of constants, which represent the built-in and user-defined types.

This chapter contains the following topics:

- [Using DBMS_TYPES](#)
 - [Constants](#)
 - [Exceptions](#)

Using DBMS_TYPES

Constants

The following table lists the constants in the DBMS_TYPES package.

Table 103–1 DBMS_TYPES Constants

Constant	Description
NO_DATA	Is only relevant if PieceWise is called, for a collection or anydataset. Denotes the end of collection/anydataset when all the elements have been accessed
SUCCESS	The operation succeeded
TYPECODE_BDOUBLE	A NUMBER type
TYPECODE_BFILE	A BFILE type
TYPECODE_BFLOAT	A NUMBER type
TYPECODE_BLOB	A BLOB type
TYPECODE_CFILE	A CFILE type
TYPECODE_CHAR	A CHAR type
TYPECODE_CLOB	A CLOB type
TYPECODE_DATE	A DATE type
TYPECODE_INTERVAL_DS	An INTERVAL_DS type
TYPECODE_INTERVAL_YM	A INTERVAL_YM type
TYPECODE_MLSLABEL	An MLSLABEL type
TYPECODE_NAMEDCOLLECTION	A named collection (VARRAY/nested table) type
TYPECODE_NUMBER	A NUMBER type
TYPECODE_OBJECT	An OBJECT type
TYPECODE_OPAQUE	An OPAQUE type
TYPECODE_RAW	A RAW type
TYPECODE_REF	A REF type
TYPECODE_TABLE	A nested table collection type

Table 103–1 DBMS_TYPES Constants

Constant	Description
TYPECODE_TIMESTAMP	A <code>TIMESTAMP</code> type
TYPECODE_TIMESTAMP_LTZ	A <code>TIMESTAMP_LTZ</code> type
TYPECODE_TIMESTAMP_TZ	A <code>TIMESTAMP_TZ</code> type
TYPECODE_VARCHAR2	A <code>VARCHAR2</code> type
TYPECODE_VARCHAR	A <code>VARCHAR</code> type
TYPECODE_VARRAY	A <code>VARRAY</code> collection type

Exceptions

- `INVALID_PARAMETERS`
- `INCORRECT_USAGE`
- `TYPE_MISMATCH`

The DBMS_UTILITY package provides various utility subprograms.

This chapter contains the following topics:

- [Using DBMS_UTILITY](#)
 - [Security Model](#)
 - [Types](#)
 - [Deprecated Subprograms](#)
- [Summary of DBMS_UTILITY Subprograms](#)

Using DBMS_UTILITY

- [Security Model](#)
- [Types](#)
- [Deprecated Subprograms](#)

Security Model

DBMS_UTILITY runs with the privileges of the calling user for the [NAME_RESOLVE Procedure](#), the [COMPILE_SCHEMA Procedure](#), and the [ANALYZE_SCHEMA Procedure](#). This is necessary so that the SQL works correctly.

The package does not run as SYS. The privileges are checked using DBMS_DDL.

Types

- [dblink_array](#)
- [index_table_type](#)
- [instance_record](#)
- [lname_array](#)
- [name_array](#)
- [number_array](#)
- [uncl_array](#)

dblink_array

```
TYPE dblink_array IS TABLE OF VARCHAR2(128) INDEX BY BINARY_INTEGER;
```

Lists of database links should be stored here.

index_table_type

```
TYPE index_table_type IS TABLE OF BINARY_INTEGER INDEX BY BINARY_INTEGER;
```

The order in which objects should be generated is returned here.

instance_record

```
TYPE instance_record IS RECORD (  
    inst_number    NUMBER,  
    inst_name      VARCHAR2(60));  
TYPE instance_table IS TABLE OF instance_record INDEX BY BINARY_INTEGER;
```

The list of active instance number and instance name.

The starting index of instance_table is 1; instance_table is dense.

lname_array

```
TYPE lname_array IS TABLE OF VARCHAR2(4000) index by BINARY_INTEGER;
```

Lists of Long NAME should be stored here, it includes fully qualified attribute names.

name_array

```
TYPE name_array IS TABLE OF VARCHAR2(30) INDEX BY BINARY_INTEGER;
```

Lists of NAME should be stored here.

number_array

```
TYPE number_array IS TABLE OF NUMBER INDEX BY BINARY_INTEGER;
```

The order in which objects should be generated is returned here for users.

uncl_array

```
TYPE uncl_array IS TABLE OF VARCHAR2(227) INDEX BY BINARY_INTEGER;
```

Lists of "USER"."NAME"."COLUMN"@LINK should be stored here.

Deprecated Subprograms

Obsolete with Oracle Database Release 10g:

- [ANALYZE_DATABASE Procedure](#)
- [ANALYZE_SCHEMA Procedure](#)

Summary of DBMS_UTILITY Subprograms

Table 104–1 DBMS_UTILITY Package Subprograms

Subprogram	Description
ANALYZE_DATABASE Procedure on page 104-6	Analyzes all the tables, clusters, and indexes in a database [see also Deprecated Subprograms]
ACTIVE_INSTANCES Procedure on page 104-8	Returns the active instance
ANALYZE_PART_OBJECT Procedure on page 104-9	Analyzes the given tables and indexes
ANALYZE_SCHEMA Procedure on page 104-10	Analyzes all the tables, clusters, and indexes in a schema [see also Deprecated Subprograms]
CANONICALIZE Procedure on page 104-12	Canonicalizes a given string
COMMA_TO_TABLE Procedures on page 104-14	Converts a comma-delimited list of names into a PL/SQL table of names
COMPILE_SCHEMA Procedure on page 104-15	Compiles all procedures, functions, packages, and triggers in the specified schema
CREATE_ALTER_TYPE_ERROR_TABLE Procedure on page 104-16	Creates an error table to be used in the EXCEPTION clause of the ALTER TYPE statement
CURRENT_INSTANCE Function on page 104-17	Returns the current connected instance number
DATA_BLOCK_ADDRESS_BLOCK Function on page 104-18	Gets the block number part of a data block address
DATA_BLOCK_ADDRESS_FILE Function on page 104-19	Gets the file number part of a data block address
DB_VERSION Procedure on page 104-20	Returns version information for the database
EXEC_DDL_STATEMENT Procedure on page 104-21	Executes the DDL statement in <code>parse_string</code>
FORMAT_ERROR_BACKTRACE Function on page 104-22	Formats the backtrace from the point of the current error to the exception handler where the error has been caught
FORMAT_ERROR_STACK Function on page 104-26	Formats the current error stack

Table 104–1 (Cont.) DBMS_UTILITY Package Subprograms

Subprogram	Description
FORMAT_CALL_STACK Function on page 104-27	Formats the current call stack
GET_CPU_TIME Function on page 104-28	Returns the current CPU time in 100th's of a second
GET_DEPENDENCY Procedure on page 104-29	Shows the dependencies on the object passed in.
GET_HASH_VALUE Function on page 104-30	Computes a hash value for the given string
GET_PARAMETER_VALUE Function on page 104-31	Gets the value of specified init.ora parameter
GET_TIME Function on page 104-33	Finds out the current time in 100th's of a second
IS_CLUSTER_DATABASE Function on page 104-34	Finds out if this database is running in cluster database mode
MAKE_DATA_BLOCK_ADDRESS Function on page 104-35	Creates a data block address given a file number and a block number
NAME_RESOLVE Procedure on page 104-36	Resolves the given name
NAME_TOKENIZE Procedure on page 104-38	Calls the parser to parse the given name
PORT_STRING Function on page 104-39	Returns a string that uniquely identifies the version of Oracle and the operating system
TABLE_TO_COMMA Procedures on page 104-40	Converts a PL/SQL table of names into a comma-delimited list of names
VALIDATE Procedure on page 104-41	Converts a PL/SQL table of names into a comma-delimited list of names

ANALYZE_DATABASE Procedure

Note: This subprogram is obsolete with release Oracle Database Release 10g. It is retained in documentation for reasons of backward compatibility. For current functionality, see "[DBMS_STATS](#)" on page 104-1.

This procedure runs the ANALYZE command on all the tables, clusters, and indexes in a database. Use this procedure to collect nonoptimizer statistics. For optimizer statistics, use the DBMS_STATS.GATHER_DATABASE_STATS procedure.

Syntax

```
DBMS_UTILITY.ANALYZE_DATABASE (
  method          VARCHAR2,
  estimate_rows   NUMBER  DEFAULT NULL,
  estimate_percent NUMBER  DEFAULT NULL,
  method_opt      VARCHAR2 DEFAULT NULL);
```

Parameters

Table 104–2 ANALYZE_DATABASE Procedure Parameters

Parameter	Description
method	One of ESTIMATE, COMPUTE or DELETE. If ESTIMATE, then either estimate_rows or estimate_percent must be nonzero.
estimate_rows	Number of rows to estimate.
estimate_percent	Percentage of rows to estimate. If estimate_rows is specified, then ignore this parameter.
method_opt	Method options of the following format: [FOR TABLE] [FOR ALL [INDEXED] COLUMNS] [SIZE n] [FOR ALL INDEXES]

Exceptions

Table 104–3 *ANALYZE_DATABASE Procedure Exceptions*

Exception	Description
ORA-20000	Insufficient privileges for some object in this database.

Usage Notes

Use this procedure to collect nonoptimizer statistics. For optimizer statistics, use the `DBMS_STATS.GATHER_TABLE_STATS` or `DBMS_STATS.GATHER_INDEX_STATS` procedure.

ACTIVE_INSTANCES Procedure

This procedure returns the active instance.

Syntax

```
DBMS_UTILITY.ACTIVE_INSTANCES (  
    instance_table OUT INSTANCE_TABLE,  
    instance_count OUT NUMBER);
```

Parameters

Table 104–4 *ACTIVE_INSTANCES Procedure Parameters*

Procedure	Description
instance_table	Contains a list of the active instance numbers and names. When no instance is up, the list is empty.
instance_count	Number of active instances.

ANALYZE_PART_OBJECT Procedure

This procedure is equivalent to SQL:

```
"ANALYZE TABLE|INDEX [<schema>.]<object_name> PARTITION <pname> [<command_type>]
[<command_opt>] [<sample_clause>]
```

Syntax

```
DBMS_UTILITY.ANALYZE_PART_OBJECT (
  schema          IN VARCHAR2 DEFAULT NULL,
  object_name     IN VARCHAR2 DEFAULT NULL,
  object_type     IN CHAR      DEFAULT 'T',
  command_type    IN CHAR      DEFAULT 'E',
  command_opt     IN VARCHAR2 DEFAULT NULL,
  sample_clause   IN VARCHAR2 DEFAULT 'sample 5 percent ');
```

Parameters

Table 104–5 ANALYZE_PART_OBJECT Procedure Parameters

Parameter	Description
schema	Schema of the object_name.
object_name	Name of object to be analyzed, must be partitioned.
object_type	Type of object, must be T (table) or I (index).
command_type	Must be V (validate structure)
command_opt	Other options for the command type. For C, E it can be FOR table, FOR all LOCAL indexes, FOR all columns or combination of some of the 'for' options of analyze statistics (table). For V, it can be CASCADE when object_type is T.
sample_clause	The sample clause to use when command_type is 'E'.

Usage Notes

For each partition of the object, run in parallel using job queues.

ANALYZE_SCHEMA Procedure

Note: This subprogram is obsolete with Oracle Database Release 10g. It is retained in documentation for reasons of backward compatibility. For current functionality, see "[DBMS_STATS](#)" on page 104-1.

This procedure runs the `ANALYZE` command on all the tables, clusters, and indexes in a schema. Use this procedure to collect nonoptimizer statistics. For optimizer statistics, use the `DBMS_STATS.GATHER_SCHEMA_STATS` procedure.

Syntax

```
DBMS_UTILITY.ANALYZE_SCHEMA (
  schema          VARCHAR2,
  method          VARCHAR2,
  estimate_rows   NUMBER   DEFAULT NULL,
  estimate_percent NUMBER   DEFAULT NULL,
  method_opt     VARCHAR2 DEFAULT NULL);
```

Parameters

Table 104–6 ANALYZE_SCHEMA Procedure Parameters

Parameter	Description
schema	Name of the schema.
method	One of <code>ESTIMATE</code> , <code>COMPUTE</code> or <code>DELETE</code> . If <code>ESTIMATE</code> , then either <code>estimate_rows</code> or <code>estimate_percent</code> must be nonzero.
estimate_rows	Number of rows to estimate.
estimate_percent	Percentage of rows to estimate. If <code>estimate_rows</code> is specified, then ignore this parameter.
method_opt	Method options of the following format: [FOR TABLE] [FOR ALL [INDEXED] COLUMNS] [SIZE n] [FOR ALL INDEXES]

Exceptions

Table 104-7 ANALYZE_SCHEMA Procedure Exceptions

Exception	Description
ORA-20000	Insufficient privileges for some object in this schema.

CANONICALIZE Procedure

This procedure canonicalizes the given string. The procedure handles a single reserved or key word (such as 'table'), and strips off white spaces for a single identifier so that ' table ' becomes TABLE.

Syntax

```
DBMS_UTILITY.CANONICALIZE(  
    name          IN   VARCHAR2,  
    canon_name    OUT  VARCHAR2,  
    canon_len     IN   BINARY_INTEGER);
```

Parameters

Table 104–8 CANONICALIZE Procedure Parameters

Parameter	Description
name	The string to be canonicalized.
canon_name	The canonicalized string
canon_len	The length of the string (in bytes) to canonicalize.

Return Values

Returns the first `canon_len` bytes in `canon_name`

Usage Notes

- If `name` is `NULL`, `canon_name` becomes `NULL`.
- If `name` is not a dotted name, and if `name` begins and ends with a double quote, remove both quotes. Alternatively, convert to upper case with `NLS_UPPER`. Note that this case does not include a name with special characters, such as a space, but is not doubly quoted.
- If `name` is a dotted name (such as a."b".c), for each component in the dotted name in the case in which the component begins and ends with a double quote, no transformation will be performed on this component. Alternatively, convert to upper case with `NLS_UPPER` and apply begin and end double quotes to the capitalized form of this component. In such a case, each canonicalized component will be concatenated together in the input position, separated by ".".

- Any other character after a[.b]* will be ignored.
- The procedure does not handle cases like 'A B.'

Examples

- a becomes A
- "a" becomes a
- "a".b becomes "a". "B"
- "a".b,c.f becomes "a". "B" with ",c.f" ignored.

COMMA_TO_TABLE Procedures

These procedures convert a comma-delimited list of names into a PL/SQL table of names. The second version supports fully-qualified attribute names.

Syntax

```
DBMS_UTILITY.COMMA_TO_TABLE (  
    list IN VARCHAR2,  
    tablen OUT BINARY_INTEGER,  
    tab OUT uncl_array);
```

```
DBMS_UTILITY.COMMA_TO_TABLE (  
    list IN VARCHAR2,  
    tablen OUT BINARY_INTEGER,  
    tab OUT lname_array);
```

Parameters

Table 104–9 COMMA_TO_TABLE Procedure Parameters

Parameter	Description
list	Comma separated list of tables.
tablen	Number of tables in the PL/SQL table.
tab	PL/SQL table which contains list of table names.

Return Values

A PL/SQL table is returned, with values 1 . . n and n+1 is null.

Usage Notes

The `list` must be a non-empty comma-delimited list: Anything other than a comma-delimited list is rejected. Commas inside double quotes do not count.

Entries in the comma-delimited list cannot include multibyte characters such as hyphens (-).

The values in `tab` are cut from the original list, with no transformations.

COMPILE_SCHEMA Procedure

This procedure compiles all procedures, functions, packages, and triggers in the specified schema. After calling this procedure, you should select from view ALL_OBJECTS for items with status of INVALID to see if all objects were successfully compiled.

To see the errors associated with INVALID objects, you may use the Enterprise Manager command:

```
SHOW ERRORS <type> <schema>.<name>
```

Syntax

```
DBMS_UTILITY.COMPILE_SCHEMA (
    schema          VARCHAR2,
    compile_all    BOOLEAN DEFAULT TRUE);
```

Parameters

Table 104–10 COMPILE_SCHEMA Procedure Parameters

Parameter	Description
schema	Name of the schema.

Exceptions

Table 104–11 COMPILE_SCHEMA Procedure Exceptions

Exception	Description
ORA-20000	Insufficient privileges for some object in this schema.

CREATE_ALTER_TYPE_ERROR_TABLE Procedure

This procedure creates an error table to be used in the EXCEPTION clause of the ALTER TYPE statement.

Syntax

```
DBMS_UTILITY.CREATE_ALTER_TYPE_ERROR_TABLE(  
    schema_name    IN    VARCHAR2,  
    table_name     IN    VARCHAR2);
```

Parameters

Table 104–12 CREATE_ALTER_TYPE_ERROR_TABLE Procedure Parameters

Parameter	Description
schema_name	The name of the schema.
table_name	The name of the table created.

Exceptions

An error is returned if the table already exists.

CURRENT_INSTANCE Function

This function returns the current connected instance number. It returns `NULL` when connected instance is down.

Syntax

```
DBMS_UTILITY.CURRENT_INSTANCE  
RETURN NUMBER;
```

DATA_BLOCK_ADDRESS_BLOCK Function

This function gets the block number part of a data block address.

Syntax

```
DBMS_UTILITY.DATA_BLOCK_ADDRESS_BLOCK (  
    dba NUMBER)  
RETURN NUMBER;
```

Parameters

Table 104–13 DATA_BLOCK_ADDRESS_BLOCK Function Parameters

Parameter	Description
dba	Data block address.

Pragmas

```
pragma restrict_references(data_block_address_block, WNDS, RNDS, WNPS, RNPS);
```

Return Values

Table 104–14 DATA_BLOCK_ADDRESS_BLOCK Function Return Values

Returns	Description
block	Block offset of the block.

Usage Notes

This function should not be used with datablocks which belong to bigfile tablespaces.

DATA_BLOCK_ADDRESS_FILE Function

This function gets the file number part of a data block address.

Syntax

```
DBMS_UTILITY.DATA_BLOCK_ADDRESS_FILE (
    dba NUMBER)
RETURN NUMBER;
```

Parameters

Table 104–15 DATA_BLOCK_ADDRESS_FILE Function Parameters

Parameter	Description
dba	Data block address.

Pragmas

```
pragma restrict_references (data_block_address_file, WNDS, RNDS, WNPS, RNPS);
```

Return Values

Table 104–16 DATA_BLOCK_ADDRESS_FILE Function Return Values

Returns	Description
file	File that contains the block.

Usage Notes

This function should not be used with datablocks which belong to bigfile tablespaces.

DB_VERSION Procedure

This procedure returns version information for the database.

Syntax

```
DBMS_UTILITY.DB_VERSION (  
    version          OUT VARCHAR2,  
    compatibility OUT VARCHAR2);
```

Parameters

Table 104–17 DB_VERSION Procedure Parameters

Parameter	Description
version	A string which represents the internal software version of the database (for example, 7.1.0.0.0). The length of this string is variable and is determined by the database version.
compatibility	The compatibility setting of the database determined by the "compatible" <code>init.ora</code> parameter. If the parameter is not specified in the <code>init.ora</code> file, then <code>NULL</code> is returned.

EXEC_DDL_STATEMENT Procedure

This procedure executes the DDL statement in `parse_string`.

Syntax

```
DBMS_UTILITY.EXEC_DDL_STATEMENT (  
    parse_string IN VARCHAR2);
```

Parameters

Table 104–18 EXEC_DDL_STATEMENT Procedure Parameters

Parameter	Description
<code>parse_string</code>	DDL statement to be executed.

FORMAT_ERROR_BACKTRACE Function

This procedure displays the call stack at the point where an exception was raised, even if the procedure is called from an exception handler in an outer scope. The output is similar to the output of the `SQLERRM` function, but not subject to the same size limitation.

Syntax

```
DBMS_UTILITY.FORMAT_ERROR_BACKTRACE
RETURN VARCHAR2;
```

Return Values

The backtrace string. A `NULL` string is returned if no error is currently being handled.

Examples

```
CREATE OR REPLACE PROCEDURE Log_Errors ( i_buff in varchar2 ) IS
  g_start_pos integer := 1;
  g_end_pos integer;

  FUNCTION Output_One_Line RETURN BOOLEAN IS
  BEGIN
    g_end_pos := Instr ( i_buff, Chr(10), g_start_pos );

    CASE g_end_pos > 0
      WHEN true THEN
        DBMS_OUTPUT.PUT_LINE ( Substr ( i_buff, g_start_pos,
          g_end_pos-g_start_pos ) );
        g_start_pos := g_end_pos+1;
        RETURN TRUE;

      WHEN FALSE THEN
        DBMS_OUTPUT.PUT_LINE ( Substr ( i_buff, g_start_pos,
          (Length(i_buff)-g_start_pos)+1 ) );
        RETURN FALSE;
    END CASE;
  END Output_One_Line;

BEGIN
  WHILE Output_One_Line() LOOP NULL;
  END LOOP;
END Log_Errors;
```

```
/

Set Doc Off
Set Feedback off
Set Echo Off

CREATE OR REPLACE PROCEDURE P0 IS
  e_01476 EXCEPTION; pragma exception_init ( e_01476, -1476 );
BEGIN
  RAISE e_01476;
END P0;
/
Show Errors

CREATE OR REPLACE PROCEDURE P1 IS
BEGIN
  P0();
END P1;
/
SHOW ERRORS

CREATE OR REPLACE PROCEDURE P2 IS
BEGIN
  P1();
END P2;
/
SHOW ERRORS

CREATE OR REPLACE PROCEDURE P3 IS
BEGIN
  P2();
END P3;
/
SHOW ERRORS

CREATE OR REPLACE PROCEDURE P4 IS
  BEGIN P3(); END P4;
/
CREATE OR REPLACE PROCEDURE P5 IS
  BEGIN P4(); END P5;
/
SHOW ERRORS

CREATE OR REPLACE PROCEDURE Top_Naive IS
BEGIN
```

FORMAT_ERROR_BACKTRACE Function

```
P5();
END Top_Naive;
/
SHOW ERRORS

CREATE OR REPLACE PROCEDURE Top_With_Logging IS
  -- NOTE: SqlErrm in principle gives the same info as Format_Error_Stack.
  -- But SqlErrm is subject to some length limits,
  -- while Format_Error_Stack is not.
BEGIN
  P5();
EXCEPTION
  WHEN OTHERS THEN
    Log_Errors ( 'Error_Stack...' || Chr(10) ||
                DBMS_UTILITY.FORMAT_ERROR_STACK() );
    Log_Errors ( 'Error_Backtrace...' || Chr(10) ||
                DBMS_UTILITY.FORMAT_ERROR_BACKTRACE() );
    DBMS_OUTPUT.PUT_LINE ( '-----' );
END Top_With_Logging;
/
SHOW ERRORS
```

```
-----

Set ServerOutput On
call Top_Naive()
/*
ERROR at line 1:
ORA-01476: divisor is equal to zero
ORA-06512: at "U.P0", line 4
ORA-06512: at "U.P1", line 3
ORA-06512: at "U.P2", line 3
ORA-06512: at "U.P3", line 3
ORA-06512: at "U.P4", line 2
ORA-06512: at "U.P5", line 2
ORA-06512: at "U.TOP_NAIVE", line 3
*/
;
```

```
Set ServerOutput On
call Top_With_Logging()
/*
Error_Stack...
ORA-01476: divisor is equal to zero
Error_Backtrace...
```



```
ORA-06512: at "U.P0", line 4
ORA-06512: at "U.P1", line 3
ORA-06512: at "U.P2", line 3
ORA-06512: at "U.P3", line 3
ORA-06512: at "U.P4", line 2
ORA-06512: at "U.P5", line 2
ORA-06512: at "U.TOP_WITH_LOGGING", line 6
-----
*/
;

/*
ORA-06512:
Cause:
    Backtrace message as the stack is
    unwound by unhandled exceptions.
Action:
    Fix the problem causing the exception
    or write an exception handler for this condition.
    Or you may need to contact your application administrator
    or database administrator.
*/
```

FORMAT_ERROR_STACK Function

This function formats the current error stack. This can be used in exception handlers to look at the full error stack.

Syntax

```
DBMS_UTILITY.FORMAT_ERROR_STACK  
RETURN VARCHAR2;
```

Return Values

This returns the error stack, up to 2000 bytes.

Return Values

See [FORMAT_ERROR_BACKTRACE Function](#) on page 104-22.

FORMAT_CALL_STACK Function

This function formats the current call stack. This can be used on any stored procedure or trigger to access the call stack. This can be useful for debugging.

Syntax

```
DBMS_UTILITY.FORMAT_CALL_STACK  
RETURN VARCHAR2;
```

Pragmas

```
pragma restrict_references(format_call_stack,WNDS);
```

Return Values

This returns the call stack, up to 2000 bytes.

GET_CPU_TIME Function

This function returns the current CPU time in 100th's of a second. The returned CPU time is the number of 100th's of a second from some arbitrary epoch.

Syntax

```
DBMS_UTILITY.GET_CPU_TIME  
RETURN NUMBER;
```

Return Values

Time is the number of 100th's of a second from some arbitrary epoch.

GET_DEPENDENCY Procedure

This procedure shows the dependencies on the object passed in.

Syntax

```
DBMS_UTILITY.GET_DEPENDENCY  
type      IN      VARCHAR2,  
schema    IN      VARCHAR2,  
name      IN      VARCHAR2);
```

Parameters

Table 104–19 *GET_DEPENDENCY Procedure Parameters*

Parameter	Description
type	The type of the object, for example if the object is a table give the type as 'TABLE'.
schema	The schema name of the object.
name	The name of the object.

GET_HASH_VALUE Function

This function computes a hash value for the given string.

Syntax

```
DBMS_UTILITY.GET_HASH_VALUE (  
    name          VARCHAR2,  
    base          NUMBER,  
    hash_size     NUMBER)  
RETURN NUMBER;
```

Parameters

Table 104–20 *GET_HASH_VALUE Function Parameters*

Parameter	Description
name	String to be hashed.
base	Base value for the returned hash value to start at.
hash_size	Desired size of the hash table.

Pragmas

```
pragma restrict_references(get_hash_value, WNDS, RNDS, WNPS, RNPS);
```

Return Values

A hash value based on the input string. For example, to get a hash value on a string where the hash value should be between 1000 and 3047, use 1000 as the base value and 2048 as the `hash_size` value. Using a power of 2 for the `hash_size` parameter works best.

GET_PARAMETER_VALUE Function

This function gets the value of specified `init.ora` parameter.

Syntax

```
DBMS_UTILITY.GET_PARAMETER_VALUE (
  parnam IN      VARCHAR2,
  intval IN OUT  BINARY_INTEGER,
  strval IN OUT  VARCHAR2)
RETURN BINARY_INTEGER;
```

Parameters

Table 104–21 *GET_PARAMETER_VALUE Function Parameters*

Parameter	Description
<code>parnam</code>	Parameter name.
<code>intval</code>	Value of an integer parameter or the value length of a string parameter.
<code>strval</code>	Value of a string parameter.

Return Values

Table 104–22 *GET_PARAMETER_VALUE Function Return Values*

Returns	Description
<code>partyp</code>	Parameter type: 0 if parameter is an integer/boolean parameter 1 if parameter is a string/file parameter

Usage Notes

When using `DBMS_UTILITY.GET_PARAMETER_VALUE`, only the first parameter setting of `/dir1` is returned when `init.ora` is set as follows:

```
utl_file_dir = /dir1
utl_file_dir = /dir2
```

However, the full comma-delimited string is returned if you are using:

```
utl_file_dir = /dir1, /dir2
```

Examples

```
DECLARE
  parnam VARCHAR2(256);
  intval BINARY_INTEGER;
  strval VARCHAR2(256);
  partyp BINARY_INTEGER;
BEGIN
  partyp := dbms_utility.get_parameter_value('max_dump_file_size',
                                             intval, strval);

  dbms_output.put('parameter value is: ');
  IF partyp = 1 THEN
    dbms_output.put_line(strval);
  ELSE
    dbms_output.put_line(intval);
  END IF;
  IF partyp = 1 THEN
    dbms_output.put('parameter value length is: ');
    dbms_output.put_line(intval);
  END IF;
  dbms_output.put('parameter type is: ');
  IF partyp = 1 THEN
    dbms_output.put_line('string');
  ELSE
    dbms_output.put_line('integer');
  END IF;
END;
```


GET_TIME Function

This function finds out the current time in 100th's of a second. It is primarily useful for determining elapsed time.

Syntax

```
DBMS_UTILITY.GET_TIME  
    RETURN NUMBER;
```

Return Values

Time is the number of 100th's of a second from some arbitrary epoch.

IS_CLUSTER_DATABASE Function

This function finds out if this database is running in cluster database mode.

Syntax

```
DBMS_UTILITY.IS_CLUSTER_DATABASE  
RETURN BOOLEAN;
```

Return Values

This function returns `TRUE` if this instance was started in cluster database mode; `FALSE` otherwise.

MAKE_DATA_BLOCK_ADDRESS Function

This function creates a data block address given a file number and a block number. A data block address is the internal structure used to identify a block in the database. This function is useful when accessing certain fixed tables that contain data block addresses.

Syntax

```
DBMS_UTILITY.MAKE_DATA_BLOCK_ADDRESS (
    file NUMBER,
    block NUMBER)
RETURN NUMBER;
```

Parameters

Table 104–23 MAKE_DATA_BLOCK_ADDRESS Function Parameters

Parameter	Description
file	File that contains the block.
block	Offset of the block within the file in terms of block increments.

Pragmas

```
pragma restrict_references (make_data_block_address, WNDS, RNDS, WNPS, RNPS);
```

Return Values

Table 104–24 MAKE_DATA_BLOCK_ADDRESS Function Return Values

Returns	Description
dba	Data block address.

NAME_RESOLVE Procedure

This procedure resolves the given name, including synonym translation and authorization checking as necessary.

Syntax

```
DBMS_UTILITY.NAME_RESOLVE (
    name          IN  VARCHAR2,
    context       IN  NUMBER,
    schema        OUT VARCHAR2,
    part1         OUT VARCHAR2,
    part2         OUT VARCHAR2,
    dblink        OUT VARCHAR2,
    part1_type    OUT NUMBER,
    object_number OUT NUMBER);
```

Parameters

Table 104–25 NAME_RESOLVE Procedure Parameters

Parameter	Description
name	Name of the object. This can be of the form [[a.]b.]c[@d], where a, b, c are SQL identifier and d is a dblink. No syntax checking is performed on the dblink. If a dblink is specified, or if the name resolves to something with a dblink, then object is not resolved, but the schema, part1, part2 and dblink OUT parameters are filled in. a, b and c may be delimited identifiers, and may contain Globalization Support (NLS) characters (single and multibyte).
context	Must be an integer between 0 and 8.
schema	Schema of the object: c. If no schema is specified in name, then the schema is determined by resolving the name.
part1	First part of the name. The type of this name is specified part1_type (synonym, procedure or package).
part2	If this is non-NULL, then this is a procedure name within the package indicated by part1.

Table 104–25 NAME_RESOLVE Procedure Parameters

Parameter	Description
<code>dblink</code>	If this is non-NULL, then a database link was either specified as part of <code>name</code> or <code>name</code> was a synonym which resolved to something with a database link. In this later case, <code>part1_type</code> indicates a synonym.
<code>part1_type</code>	Type of <code>part1</code> is: 5 - synonym 7 - procedure (top level) 8 - function (top level) 9 - package If a synonym, then it means that <code>name</code> is a synonym that translates to something with a database link. In this case, if further name translation is desired, then you must call the <code>DBMS_UTILITY.NAME_RESOLVE</code> procedure on this remote node.
<code>object_number</code>	Object identifier

Exceptions

All errors are handled by raising exceptions. A wide variety of exceptions are possible, based on the various syntax error that are possible when specifying object names.

NAME_TOKENIZE Procedure

This procedure calls the parser to parse the given name as "a [. b [. c]][@ dblink]". It strips double quotes, or converts to uppercase if there are no quotes. It ignores comments of all sorts, and does no semantic analysis. Missing values are left as NULL.

Syntax

```
DBMS_UTILITY.NAME_TOKENIZE (  
    name      IN  VARCHAR2,  
    a         OUT VARCHAR2,  
    b         OUT VARCHAR2,  
    c         OUT VARCHAR2,  
    dblink    OUT VARCHAR2,  
    nextpos   OUT BINARY_INTEGER);
```

Parameters

For each of a, b, c, dblink, tell where the following token starts in anext, bnext, cnext, dnext respectively.

PORT_STRING Function

This function returns a string that identifies the operating system and the TWO TASK PROTOCOL version of the database. For example, "VAX/VMX-7.1.0.0"

The maximum length is port-specific.

Syntax

```
DBMS_UTILITY.PORT_STRING  
RETURN VARCHAR2;
```

Pragmas

```
pragma restrict_references(port_string, WNDS, RNDS, WNPS, RNPS);
```

TABLE_TO_COMMA Procedures

These procedures converts a PL/SQL table of names into a comma-delimited list of names. This takes a PL/SQL table, 1 . . n, terminated with n+1 null. The second version supports fully-qualified attribute names.

Syntax

```
DBMS_UTILITY.TABLE_TO_COMMA (  
    tab    IN UNCL_ARRAY,  
    tablen OUT BINARY_INTEGER,  
    list   OUT VARCHAR2);
```

```
DBMS_UTILITY.TABLE_TO_COMMA (  
    tab    IN lname_array,  
    tablen OUT BINARY_INTEGER,  
    list   OUT VARCHAR2);
```

Parameters

Table 104–26 *TABLE_TO_COMMA Procedure Parameters*

Parameter	Description
tab	PL/SQL table which contains list of table names.
tablen	Number of tables in the PL/SQL table.
list	Comma separated list of tables.

Return Values

Returns a comma-delimited list and the number of elements found in the table.

VALIDATE Procedure

This procedure makes invalid database objects valid.

Syntax

```
DBMS_UTILITY.VALIDATE(  
    object_id      NUMBER);
```

Parameters

Table 104–27 VALIDATE Procedure Parameters

Parameter	Description
object_id	The ID number of object to be validated. This is the same as the value of the OBJECT_ID column from ALL_OBJECTS.

Usage Notes

No errors are raised if the object does not exist or is already valid or is an object that cannot be validated.

The `DBMS_WARNING` package provides a way to manipulate the behavior of PL/SQL warning messages, in particular by reading and changing the setting of the `PLSQL_WARNINGS` initialization parameter to control what kinds of warnings are suppressed, displayed, or treated as errors. This package provides the interface to query, modify and delete current system or session settings.

This chapter contains the following topics:

- [Using DBMS_WARNING](#)
 - [Security Model](#)
- [Summary of DBMS_WARNING Subprograms](#)

Using DBMS_WARNING

- [Security Model](#)

Security Model

Note that for all the following interfaces, if value of the scope parameter is `SYSTEM`, then the user must have `ALTER SYSTEM` privilege.

Summary of DBMS_WARNING Subprograms

Table 105–1 DBMS_WARNING Package Subprograms

Subprogram	Description
ADD_WARNING_SETTING_CAT Procedure on page 105-4	Modifies the current session or system warning settings of the <code>warning_category</code> previously supplied
ADD_WARNING_SETTING_NUM Procedure on page 105-5	Modifies the current session or system warning settings of the or <code>warning_number</code> previously supplied
GET_CATEGORY Function on page 105-6	Returns the category name, given the message number
GET_WARNING_SETTING_CAT Function on page 105-7	Returns the specific warning category in the session
GET_WARNING_SETTING_NUM Function on page 105-8	Returns the specific warning number in the session
GET_WARNING_SETTING_STRING Function on page 105-9	Returns the entire warning string for the current session
SET_WARNING_SETTING_STRING Procedure on page 105-10	Replaces previous settings with the new value

ADD_WARNING_SETTING_CAT Procedure

You can modify the current session's or system's warning settings with the value supplied. The value will be added to the existing parameter setting if the value for the `warning_category` or `warning_value` has not been set, or override the existing value. The effect of calling this function is same as adding the qualifier (`ENABLE/DISABLE/ERROR`) on the category specified to the end of the current session or system setting.

Syntax

```
DBMS_WARNING.ADD_WARNING_SETTING_CAT (  
    warning_category    IN    VARCHAR2,  
    warning_value       IN    VARCHAR2,  
    scope               IN    VARCHAR2);
```

Parameters

Table 105–2 ADD_WARNING_SETTING_CAT Procedure Parameters

Parameter	Description
<code>warning_category</code>	Name of the category. Allowed values are ALL, INFORMATIONAL, SEVERE and PERFORMANCE.
<code>warning_value</code>	Value for the category. Allowed values are ENABLE, DISABLE, and ERROR.
<code>scope</code>	Specifies if the changes are being performed in the session context or the system context. Allowed values are SESSION or SYSTEM.

ADD_WARNING_SETTING_NUM Procedure

You can modify the current `session` or `system` warning settings with the value supplied. If the value was already set, you will override the existing value. The effect of calling this function is same as adding the qualifier (`ENABLE / DISABLE / ERROR`) on the category specified to the end of the current session or system setting.

Syntax

```
DBMS_WARNING.ADD_WARNING_SETTING_NUM (
    warning_number    IN    NUMBER,
    warning_value     IN    VARCHAR2,
    scope             IN    VARCHAR2);
```

Parameters

Table 105–3 ADD_WARNING_SETTING_NUM Procedure Parameters

Parameter	Description
<code>warning_number</code>	The warning number. Allowed values are all valid warning numbers.
<code>warning_value</code>	Value for the category. Allowed values are <code>ENABLE</code> , <code>DISABLE</code> , and <code>ERROR</code> .
<code>scope</code>	Specifies if the changes are being performed in the <code>session</code> context or the <code>system</code> context. Allowed values are <code>SESSION</code> or <code>SYSTEM</code> .

GET_CATEGORY Function

This function returns the category name, given the message number.

Syntax

```
DBMS_WARNING.GET_CATEGORY (  
    warning_number IN pls_integer)  
RETURN VARCHAR2;
```

Parameters

Table 105–4 *GET_CATEGORY Function Parameters*

Parameter	Description
warning_number	The warning message number.

GET_WARNING_SETTING_CAT Function

This function returns the specific warning category setting for the current session.

Syntax

```
DBMS_WARNING.GET_WARNING_SETTING_CAT (  
    warning_category IN VARCHAR2)  
RETURN warning_value;
```

Parameters

Table 105–5 *GET_WARNING_SETTING_CAT Function Parameters*

Parameter	Description
warning_category	Name of the category. Allowed values are all valid category names (ALL, INFORMATIONAL, SEVERE and PERFORMANCE).

GET_WARNING_SETTING_NUM Function

This function returns the specific warning number setting for the current session.

Syntax

```
DBMS_WARNING.GET_WARNING_SETTING_NUM (  
    warning_number    IN    NUMBER)  
RETURN warning_value;
```

Parameters

Table 105–6 *GET_WARNING_SETTING_NUM Function Parameters*

Parameter	Description
warning_number	Warning number. Allowed values are all valid warning numbers.

GET_WARNING_SETTING_STRING Function

This function returns the entire warning string for the current session.

Syntax

```
DBMS_WARNING.GET_WARNING_SETTING_STRING  
RETURN pls_integer;
```

Usage Notes

Use this function when you do not have `SELECT` privilege on `v$parameter` or `v$paramater2` fixed tables, or if you want to parse the warning string yourself and then modify and set the new value using `SET_WARNING_SETTING_STRING`.

SET_WARNING_SETTING_STRING Procedure

This procedure replaces previous settings with the new value. The warning string may contain mix of category and warning numbers using the same syntax as used on the right hand side of '=' when issuing an ALTER SESSION or SYSTEM SET PLSQL_WARNINGS command. This will have same effect as ALTER SESSION OR ALTER SYSTEM command.

Syntax

```
DBMS_WARNING.SET_WARNING_SETTING_STRING (  
    warning_value IN VARCHAR2,  
    scope         IN VARCHAR2);
```

Parameters

Table 105–7 SET_WARNING_SETTING_STRING Procedure Parameters

Parameter	Description
warning_value	The new string that will constitute the new value.
scope	This will specify if the changes are being done in the session context, or system context. Allowed values are SESSION or SYSTEM.

DBMS_WORKLOAD_REPOSITORY

The `DBMS_WORKLOAD_REPOSITORY` package lets you manage the Workload Repository, performing operations such as managing snapshots and baselines.

The chapter contains the following topic:

- [Summary of DBMS_WORKLOAD_REPOSITORY Subprograms](#)

Summary of DBMS_WORKLOAD_REPOSITORY Subprograms

Table 106–1 *DBMS_WORKLOAD_REPOSITORY Package Subprograms*

Subprogram	Description
AWR_REPORT_HTML Function on page 106-3	Displays the AWR report in HTML
AWR_REPORT_TEXT Function on page 106-4	Displays the AWR report in text
CREATE_BASELINE Function and Procedure on page 106-5	Creates a single baseline
CREATE_SNAPSHOT Function and Procedure on page 106-6	Creates a manual snapshot immediately
DROP_BASELINE Procedure on page 106-7	Drops a range of snapshots
DROP_SNAPSHOT_RANGE Procedure on page 106-8	Activates service
MODIFY_SNAPSHOT_SETTINGS Procedure on page 106-9	Modifies the snapshot settings.

AWR_REPORT_HTML Function

This table function displays the AWR report in HTML.

Syntax

```
DBMS_WORKLOAD_REPOSITORY.AWR_REPORT_HTML(
  l_dbid      IN    NUMBER,
  l_inst_num  IN    NUMBER,
  l_bid       IN    NUMBER,
  l_eid       IN    NUMBER,
  l_options   IN    NUMBER DEFAULT 0)
RETURN awrrpt_text_type_table PIPELINED;
```

Parameters

Table 106–2 AWR_REPORT_HTML Parameters

Parameter	Description
<code>l_dbid</code>	The database identifier.
<code>l_inst_num</code>	The instance number.
<code>l_bid</code>	The 'Begin Snapshot' Id
<code>l_eid</code>	The 'End Snapshot' Id
<code>l_options</code>	A flag to specify to control the output of the report. Currently, Oracle supports one value : <ul style="list-style-type: none"> ▪ <code>l_options = 8</code>. Displays the ADDM specific portions of the report. These sections include the Buffer Pool Advice, Shared Pool Advice, PGA Target Advice, and Wait Class sections.

Return Values

The output will be one column of `VARCHAR2(150)`.

Usage Notes

You can call the function directly but Oracle recommends you use the `awrrpt.sql` script which prompts users for the required information.

AWR_REPORT_TEXT Function

This table function displays the AWR report in text.

Syntax

```
DBMS_WORKLOAD_REPOSITORY.AWR_REPORT_TEXT(
  l_dbid      IN    NUMBER,
  l_inst_num  IN    NUMBER,
  l_bid       IN    NUMBER,
  l_eid       IN    NUMBER,
  l_options   IN    NUMBER DEFAULT 0)
RETURN awrrpt_text_type_table PIPELINED;
```

Parameters

Table 106–3 AWR_REPORT_TEXT Parameters

Parameter	Description
l_dbid	The database identifier.
l_inst_num	The instance number.
l_bid	The 'Begin Snapshot' Id
l_eid	The 'End Snapshot' Id
l_options	A flag to specify to control the output of the report. Currently, Oracle supports one value : <ul style="list-style-type: none"> ▪ l_options - 8. Displays the ADDM specific portions of the report. These sections include the Buffer Pool Advice, Shared Pool Advice, PGA Target Advice, and Wait Class sections.

Return Values

The output will be one column of VARCHAR2 (80).

Usage Notes

You can call the function directly but Oracle recommends you use the `awrrpt.sql` script which prompts users for the required information.

CREATE_BASELINE Function and Procedure

This function and procedure creates a baseline.

Syntax

```
DBMS_WORKLOAD_REPOSITORY.CREATE_BASELINE(
  start_snap_id   IN  NUMBER,
  end_snap_id     IN  NUMBER,
  baseline_name   IN  VARCHAR2,
  dbid            IN  NUMBER DEFAULT NULL);
```

```
DBMS_WORKLOAD_REPOSITORY.CREATE_BASELINE(
  start_snap_id   IN  NUMBER,
  end_snap_id     IN  NUMBER,
  baseline_name   IN  VARCHAR2,
  dbid            IN  NUMBER DEFAULT NULL)
RETURN NUMBER;
```

Parameters

Table 106–4 CREATE_BASELINE Parameters

Parameter	Description
start_snap_id	The start snapshot sequence number.
end_snap_id	The end snapshot sequence number.
baseline_name	The name of baseline.
dbid	The database id (default to local DBID).

Examples

This example creates a baseline (named 'oltp_peakload_bl') between snapshots 105 and 107 for the local database:

```
EXECUTE DBMS_WORKLOAD_REPOSITORY.CREATE_BASELINE (start_snap_id => 105,
end_snap_id => 107,
baseline_name => 'oltp_peakload_bl');
```

If you query the DBA_HIST_BASELINE view after the Create Baseline action, you will see the newly created baseline in the Workload Repository.

CREATE_SNAPSHOT Function and Procedure

This function and procedure create snapshots. In the case of the function, the snapshot ID is returned.

Syntax

```
DBMS_WORKLOAD_REPOSITORY.CREATE_SNAPSHOT(  
    flush_level IN VARCHAR2 DEFAULT 'TYPICAL');
```

```
DBMS_WORKLOAD_REPOSITORY.CREATE_SNAPSHOT(  
    flush_level IN VARCHAR2 DEFAULT 'TYPICAL')  
RETURN NUMBER;
```

Parameters

Table 106–5 CREATE_SNAPSHOT Parameters

Parameter	Description
flush_level	The flush level for the snapshot is either 'TYPICAL' or 'ALL'

Examples

This example creates a manual snapshot at the TYPICAL level:

```
EXECUTE DBMS_WORKLOAD_REPOSITORY.CREATE_SNAPSHOT();
```

If you query the DEB_HIST_SNAPSHOT view after the CREATE_SNAPSHOT action, you will see one more snapshot ID added to the Workload Repository.

DROP_BASELINE Procedure

This procedure drops a baseline.

Syntax

```
DBMS_WORKLOAD_REPOSITORY.DROP_BASELINE(
  baseline_name IN VARCHAR2,
  cascade       IN BOOLEAN DEFAULT false,
  dbid          IN NUMBER DEFAULT NULL);
```

Parameters

Table 106–6 DROP_BASELINE Parameters

Parameter	Description
baseline_name	The name of baseline.
cascade	If TRUE, the pair of snapshots associated with the baseline will also be dropped. Otherwise, only the baseline is removed.
dbid	The (optional) database id (default to local DBID).

Examples

This example drops the baseline 'oltp_peakload_bl' without dropping the underlying snapshots:

```
EXECUTE DBMS_WORKLOAD_REPOSITORY.DROP_BASELINE (
  baseline_name => 'oltp_peakload_bl');
```

If you query the DBA_HIST_BASELINE view after the DROP_BASELINE action, you will see the specified baseline definition is removed. You can query the DBS_HIST_SNAPSHOT view to find that the underlying snapshots are left intact.

DROP_SNAPSHOT_RANGE Procedure

This procedure drops a range of snapshots.

Syntax

```
DBMS_WORKLOAD_REPOSITORY.DROP_SNAPSHOT_RANGE(  
    low_snap_id    IN NUMBER,  
    high_snap_id   IN NUMBER  
    dbid           IN NUMBER DEFAULT NULL);
```

Parameters

Table 106–7 DROP_SNAPSHOT_RANGE Procedure Parameters

Parameter	Description
low_snap_id	The low snapshot id of snapshots to drop.
high_snap_id	The high snapshot id of snapshots to drop.
dbid	The database id (default to local DBID).

Examples

This example drops the range of snapshots between snapshot id 102 to 105 for the local database:

```
EXECUTE DBMS_WORKLOAD_REPOSITORY.DROP_SNAPSHOT_RANGE(102, 105);
```

If you query the `dba_hist_snapshot` view after the Drop Snapshot action, you will see that snapshots 102 to 105 are removed from the Workload Repository.

MODIFY_SNAPSHOT_SETTINGS Procedure

This procedure controls two aspects of snapshot generation. The `INTERVAL` setting affects how often snapshots are automatically captured while the `RETENTION` setting affects how long snapshots are retained in the Workload Repository.

Syntax

```
DBMS_WORKLOAD_REPOSITORY.MODIFY_SNAPSHOT_SETTINGS( (
  retention  IN  NUMBER DEFAULT NULL,
  interval   IN  NUMBER DEFAULT NULL,
  dbid       IN  NUMBER DEFAULT NULL);
```

Parameters

Table 106–8 *MODIFY_SNAPSHOT_SETTINGS Procedure Parameters*

Parameter	Description
<code>retention</code>	The new retention time (in minutes). The specified value must be in the range of 1 day to 100 years. If <code>ZERO</code> is specified, the maximum value of 100 years will be used. If <code>NULL</code> is specified, the old value for retention is preserved.
<code>interval</code>	The new interval setting between each snapshot, in units of minutes. The specified value must be in the range between 10 minutes to 1 year. If <code>ZERO</code> is specified, the maximum value of 1 year will be used. If <code>NULL</code> is specified, the current value is preserved.
<code>dbid</code>	The database id (default to local DBID).

Examples

This example changes the `interval` setting to one hour and the `retention` setting to two weeks for the local database:

```
execute dbms_workload_repository.modify_snapshot_settings(interval => 60,
retention => 20160);
```

If you query the `DBA_HIST_WR_CONTROL` table after this procedure is executed, you will see the changes to these settings.

The `DBMS_WM` package provides an interface to Oracle Database Workspace Manager (often referred to as Workspace Manager).

- [Documentation of DBMS_WM](#)

Documentation of DBMS_WM

For a complete description of this package, see `DBMS_WM` in *Oracle Database Application Developer's Guide - Workspace Manager*.

The DBMS_XDB package supports the following features:

- Resource Management subprograms which complement Resource Views
- The Access Control List (ACL)-based Security Mechanism
- Configuration Session Management
- Creation of the XDB username

See Also:

- *Oracle XML DB Developer's Guide*
- *Oracle Database New Features*

This chapter contains the following topics:

- [Using DBMS_XDB](#)
 - [Overview](#)
 - [Constants](#)
- [Summary of DBMS_XDB Subprograms](#)

Using DBMS_XDB

- [Overview](#)
- [Constants](#)

Overview

The DBMS_XDB package supports the following features:

- The Resource Management functionality provides [LINK Procedure](#), [EXISTSRESOURCE Function](#), [LOCKRESOURCE Function](#), [GETLOCKTOKEN Procedure](#), [UNLOCKRESOURCE Function](#), [CREATERESOURCE Functions](#), [RENAMERESOURCE Procedure](#), [DELETERESOURCE Procedure](#), [GETRESOID Function](#), [CREATEOIDPATH Function](#), [REBUILDHIERARCHICALINDEX Procedure](#) and [CREATEFOLDER Function](#) methods, which complement Resource Views.
- The Access Control List (ACL)-based Security Mechanism can be used with in-hierarchy ACLs stored by the database or in-memory ACLs that may be stored outside the database. Some of these methods can be used for both Oracle resources and arbitrary database objects. Use [CHECKPRIVILEGES Function](#), [GETACLDOCUMENT Procedure](#), [CHANGEPRIVILEGES Function](#) and [GETPRIVILEGES Function](#) for Oracle Resources. [ACLCHECKPRIVILEGES Function](#) provides access to Oracle's ACL-based Security mechanism without storing objects in the Hierarchy.
- Configuration Session Management is supported by [CFG_REFRESH Procedure](#), [CFG_GET Function](#) and [CFG_UPDATE Procedure](#). methods.
- The XDB username is created during XDB installation. This user owns a set of default tables and packages. [GETXDB_TABLESPACE Function](#) and [MOVEXDB_TABLESPACE Procedure](#) enable movement of schemas to a specified tablespace, and support the default SYSAUX tablespace introduction

Constants

Table 108–1 *Defined Constants for DBMS_XDB*

Constant	Definition	Description
DELTE_RESOURCE	CONSTANT NUMBER :=1	Deletes a resource; fails if the resource has children.
DELETE_ RECURSIVE	CONSTANT NUMBER :=2	Deletes a resource and its children, if any.
DELETE_FORCE	CONSTANT NUMBER :=3	Deletes the resource, even if the object it contains is invalid.
DELETE_ RECURSIVE_ FORCE	CONSTANT NUMBER :=4	Deletes a resource and its children, if any, even if the object it contains is invalid.

Summary of DBMS_XDB Subprograms

Table 108–2 DBMS_XDB Package Subprograms

Subprogram	Description
ACLCHECKPRIVILEGES Function on page 108-6	Checks access privileges granted to the current user by specified ACL document on a resource whose owner is specified by the 'owner' parameter.
CFG_GET Function on page 108-7	Retrieves the session's configuration information
CFG_REFRESH Procedure on page 108-8	Refreshes the session's configuration information to the latest configuration
CFG_UPDATE Procedure on page 108-9	Updates the configuration information
CHANGEPRIVILEGES Function on page 108-10	Adds the given ACE to the given resource's ACL
CHECKPRIVILEGES Function on page 108-11	Checks access privileges granted to the current user on the specified resource
CREATEFOLDER Function on page 108-12	Creates a new folder resource in the hierarchy
CREATEOIDPATH Function on page 108-13	Creates a virtual path to the resource based on object ID
CREATERESOURCE Functions on page 108-14	Creates a new resource
DELETERESOURCE Procedure on page 108-17	Deletes a resource from the hierarchy
EXISTSRESOURCE Function on page 108-18	Determines if a resource is in the hierarchy, based on its absolute path
GETACLDOCUMENT Procedure on page 108-19	Retrieves ACL document that protects resource given its path name
GETLOCKTOKEN Procedure on page 108-20	Returns that resource's lock token for the current user given a path to a resource
GETPRIVILEGES Function on page 108-21	Gets all privileges granted to the current user on the given resource
GETRESOID Function on page 108-22	Returns the object ID of the resource from its absolute path

Table 108–2 (Cont.) DBMS_XDB Package Subprograms

Subprogram	Description
GETXDB_TABLESPACE Function on page 108-23	Returns the current tablespace of the XDB (user)
LINK Procedure on page 108-24	Creates a link to an existing resource
LOCKRESOURCE Function on page 108-25	Gets a WebDAV-style lock on that resource given a path to that resource
MOVEXDB_TABLESPACE Procedure on page 108-26	Moves the XDB (user) to the specified tablespace
REBUILDHIERARCHICALINDEX Procedure on page 108-27	Rebuilds the hierarchical index after import or export operations
RENAMERESOURCE Procedure on page 108-28	Renames the XDB resource
SETACL Procedure on page 108-29	Sets the ACL on the given resource
UNLOCKRESOURCE Function on page 108-30	Unlocks the resource given a lock token and resource path

ACLCHECKPRIVILEGES Function

This function checks access privileges granted to the current user by specified ACL document by the OWNER of the resource. Returns positive integer if all privileges are granted.

Syntax

```
DBMS_XDB.ACLCHECKPRIVILEGES(  
    acl_path IN VARCHAR2,  
    owner    IN VARCHAR2,  
    privs   IN xmltype)  
RETURN PLS_INTEGER;
```

Parameters

Table 108–3 *ACLCHECKPRIVILEGES Function Parameters*

Parameter	Description
<code>acl_path</code>	Absolute path in the Hierarchy for ACL document.
<code>owner</code>	Resource owner name; the pseudo user "DAV:owner" is replaced by this user during ACL privilege resolution.
<code>privs</code>	An <code>XMLType</code> instance of the privilege element specifying the requested set of access privileges. See description for CHECKPRIVILEGES Function .

CFG_GET Function

This function retrieves the session's configuration information as an `XMLType` instance.

Syntax

```
DBMS_XDB.CFG_GET  
RETURN SYS.XMLType;
```

CFG_REFRESH Procedure

This procedure refreshes the session's configuration information to the latest configuration.

Syntax

```
DBMS_XDB.CFG_REFRESH;
```


CFG_UPDATE Procedure

This procedure updates the configuration information and commits the change.

Syntax

```
DBMS_XDB.CFG_UPDATE(  
    xdbconfig IN SYS.XMLTYPE);
```

Parameters

Table 108–4 *CFG_UPDATE Procedure Parameters*

Parameter	Description
<code>xdbconfig</code>	The new configuration data.

CHANGEPRIVILEGES Function

This function adds the given ACE to the given resource's ACL.

Syntax

```
DBMS_XDB.CHANGEPRIVILEGES(  
    res_path IN VARCHAR2,  
    ace      IN XMLType)  
RETURN PLS_INTEGER;
```

Parameters

Table 108–5 *CHANGEPRIVILEGES Function Parameters*

Parameter	Description
res_path	Path name of the resource for which privileges need to be changed.
ace	An XMLType instance of the <ace> element which specifies the <principal>, the operation <grant> and the list of privileges.

Return Values

It returns a positive integer if the ACL was successfully modified.

Usage Notes

If no ACE with the same principal and the same operation (grant/deny) already exists in the ACL, the new ACE is added at the end of the ACL.

CHECKPRIVILEGES Function

This function checks access privileges granted to the current user on the specified resource.

Syntax

```
DBMS_XDB.CHECKPRIVILEGES(  
    res_path IN VARCHAR2,  
    privs    IN xmltype)  
RETURN PLS_INTEGER;
```

Parameters

Table 108–6 CHECKPRIVILEGES Function Parameters

Parameter	Description
res_path	Absolute path in the Hierarchy for resource.
privs	An XMLType instance of the privilege element specifying the requested set of access privileges.

Return Values

Returns positive integer if all requested privileges granted.

CREATEFOLDER Function

This function creates a new folder resource in the hierarchy.

Syntax

```
DBMS_XDB.CREATEFOLDER(  
    path IN VARCHAR2)  
RETURN BOOLEAN;
```

Parameters

Table 108–7 CREATEFOLDER Function Parameters

Parameter	Description
path	Path name for the new folder.

Return Values

Returns TRUE if operation successful; FALSE, otherwise. Returns TRUE if operation successful; FALSE, otherwise.

Usage Notes

The given path name's parent folder must already exist in the hierarchy: if '/folder1/folder2' is passed as the path parameter, then '/folder1' must already exist.

CREATEOIDPATH Function

This function creates a virtual path to the resource based on object ID.

Syntax

```
DBMS_XDB.CREATEOIDPATH(  
    oid    IN RAW)  
RETURN VARCHAR2;
```

Parameters

Table 108–8 *CREATEOIDPATH Function Parameters*

Parameter	Description
oid	Object ID of the resource.

CREATERESOURCE Functions

The functions create a new resource. The description of the overload options precede each version of the syntax

Syntax

Creates a new resource with the given string as its contents:

```
DBMS_XDB.CREATERESOURCE(  
    path    IN VARCHAR2,  
    data    IN VARCHAR2)  
RETURN BOOLEAN;
```

Creates a new resource with the given XMLType data as its contents:

```
DBMS_XDB.CREATERESOURCE(  
    path    IN VARCHAR2,  
    data    IN SYS.XMLTYPE)  
RETURN BOOLEAN;
```

Given a REF to an existing XMLType row, creates a resource whose contents point to that row. That row should not already exist inside another resource:

```
DBMS_XDB.CREATERESOURCE(  
    path      IN VARCHAR2,  
    datarow  IN REF SYS.XMLTYPE)  
RETURN BOOLEAN;
```

Creates a resource with the given BLOB as its contents, and specifies character set of the source BLOB:

```
DBMS_XDB.CREATERESOURCE(  
    path    IN VARCHAR2,  
    data    IN BLOB,  
    csid    IN NUMBER :=0)  
RETURN BOOLEAN;
```

Creates a resource with the given BFILE as its contents, and specifies character set of the source BFILE:

```
DBMS_XDB.CREATERESOURCE(
  path    IN  VARCHAR2,
  data    IN  BFILE,
  csid    IN  NUMBER :=0)
RETURN BOOLEAN;
```

Creates a resource with the given CLOB as its contents:

```
DBMS_XDB.CREATERESOURCE(
  path    IN  VARCHAR2,
  data    IN  CLOB)
RETURN BOOLEAN;
```

Parameters

Table 108–9 *CREATERESOURCE Function Parameters*

Parameter	Description
path	Path name of the resource to create. The path name's parent folder must already exist in the hierarchy. In other words, if <code>/foo/bar.txt</code> is passed in, then folder <code>/foo</code> must already exist.
data	The new resource's contents. The data will be parsed to check if it contains a schema-based XML document, and the contents will be stored as schema-based in the schema's default table. Otherwise, it will be saved as binary data.
datarow	REF to an <code>XMLType</code> row to be used as the contents.
csid	Character set id of the document. Must be a valid Oracle id; otherwise returns an error. If a zero CSID is specified then the data is defaulted to the database character set. Otherwise, the encoding of the data is determined as follows: <ul style="list-style-type: none"> ■ From the path extension, determine the resource's MIME type. ■ If the MIME type is <code>*/xml</code>, then the encoding is detected based on Appendix F of the W3C XML 1.0 Reference at http://www.w3.org/TR/2000/REC-xml-20001006; otherwise, it is defaulted to the database character set.

Return Values

Returns `TRUE` if operation successful; `FALSE`, otherwise.

DELETERESOURCE Procedure

This procedure deletes a resource from the hierarchy.

Syntax

```
DBMS_XDB.DELETERESOURCE(  
    path          IN          VARCHAR2,  
    delete_option IN          PLS_INTEGER);
```

Parameters

Table 108–10 *DELETERESOURCE Procedure Parameters*

Parameter	Description
path	Path name of the resource to delete.
delete_option	The option that controls how a resource is deleted; defined in Table 108–1 on page 108-3: <ul style="list-style-type: none">■ DELETE_RESOURCE■ DELETE_RECURSIVE■ DELETE_FORCE■ DELETE_RECURSIVE_FORCE

EXISTSRESOURCE Function

This function indicates if a resource is in the hierarchy. Matches resource by a string that represents its absolute path.

Syntax

```
DBMS_XDB.EXISTSRESOURCE(  
    abspath IN VARCHAR2)  
RETURN BOOLEAN;
```

Parameters

Table 108–11 *EXISTSRESOURCE Function Parameters*

Parameter	Description
abspath	Path name of the resource whose ACL document is required.

Return Values

Returns `TRUE` if the resource is found.

GETACLDOCUMENT Procedure

This procedure retrieves ACL document that protects resource given its path name.

Syntax

```
DBMS_XDB.GETACLDOCUMENT(  
    abspath IN VARCHAR2)  
RETURN sys.xmltype;
```

Parameters

Table 108–12 *GETACLDOCUMENT Function Parameters*

Parameter	Description
abspath	Path name of the resource whose ACL document is required.

Return Values

Returns the XMLType for ACL document.

GETLOCKTOKEN Procedure

Given a path to a resource, this procedure returns that resource's lock token for the current user.

Syntax

```
DBMS_XDB.GETLOCKTOKEN(  
  path          IN    VARCHAR2,  
  locktoken     OUT   VARCHAR2);
```

Parameters

Table 108–13 *GETLOCKTOKEN Procedure Parameters*

Parameter	Description
path	Path name to the resource.
locktoken	Logged-in user's lock token for the resource.

Usage Notes

The user must have `READPROPERTIES` privilege on the resource.

GETPRIVILEGES Function

This function gets all privileges granted to the current user on the given resource.

Syntax

```
DBMS_XDB.GETPRIVILEGES(  
    res_path    IN    VARCHAR2)  
    RETURN sys.xmltype;
```

Parameters

Table 108–14 *GETPRIVILEGES Function Parameters*

Parameter	Description
res_path	Absolute path in the hierarchy of the resource.

Return Values

Returns an `XMLType` instance of `<privilege>` element, which contains the list of all leaf privileges granted on this resource to the current user.

GETRESOID Function

Returns the object ID of the resource from its absolute path.

Syntax

```
DBMS_XDB.GETRESOID(  
    abspath IN VARCHAR2)  
RETURN RAW;
```

Parameters

Table 108–15 *GETRESOID Function Parameters*

Parameter	Description
abspath_path	Absolute path of the resource.

Return Values

Returns NULL if the resource is not present.

GETXDB_TABLESPACE Function

This function returns the current tablespace of the XDB (user).

Syntax

```
DBMS_XDB.GETXDB_TABLESPACE  
RETURN VARCHAR2;
```

LINK Procedure

This procedure creates a link to an existing resource.

Syntax

```
DBMS_XDB.LINK(  
    srcpath    IN  VARCHAR2,  
    linkfolder IN  VARCHAR2,  
    linkname   IN  VARCHAR2);
```

Parameters

Table 108–16 LINK Procedure Parameters

Parameter	Description
srcpath	Path name of the resource to which a link is made
linkfolder	Folder in which the new link is placed.
linkname	Name of the new link.

LOCKRESOURCE Function

Given a path to a resource, this function gets a WebDAV-style lock on that resource.

Syntax

```
DBMS_XDB.LOCKRESOURCE(
    path      IN  VARCHAR2,
    depthzero IN  BOOLEAN,
    shared    IN  boolean)
RETURN BOOLEAN;
```

Parameters

Table 108–17 LOCKRESOURCE Function Parameters

Parameter	Description
path	Path name of the resource to lock.
depthzero	NOT SUPPORTED. Only given resource is locked. In future releases, passing FALSE will obtain an infinite-depth lock.
shared	Passing TRUE will obtain a shared write lock.

Return Values

Returns TRUE if successful.

Usage Notes

The user must have UPDATE privileges on the resource.

MOVEXDB_TABLESPACE Procedure

This procedure moves the XDB (user) to the specified tablespace.

Syntax

```
DBMS_XDB.MOVEXDB_TABLESPACE(  
    new_tablespace IN VARCHAR2);
```

Parameters

Table 108–18 *MOVEXDB_TABLESPACE Procedure Parameters*

Parameter	Description
<code>new_tablespace</code>	Name of the tablespace where the XDB will be moved.

Usage Notes

This operation waits for all concurrent XDB sessions to exit.

REBUILDHIERARCHICALINDEX Procedure

This procedure rebuilds the hierarchical index after import or export operations. This is necessary because data cannot be exported from index tables.

Syntax

```
DBMS_XDB.REBUILDHIERARCHICALINDEX;
```

RENAMERESOURCE Procedure

This procedure renames the XDB resource.

Syntax

```
DBMS_XDB.RENAMERESOURCE(  
    srcpath      IN  VARCHAR2,  
    destfolder  IN  CARCHAR2,  
    newname     IN  VARCHAR2);
```

Parameters

Table 108–19 *RENAMERESOURCE Procedure Parameters*

Parameter	Description
srcpath	Absolute path in the Hierarchy for the source resource destination folder.
destfolder	Absolute path in the Hierarchy for the destination folder.
newname	Name of the child in the destination folder.

SETACL Procedure

Sets the ACL on the given resource to be the ACL specified by path.

Syntax

```
DBMS_XDB.SETACL(  
    res_path  IN  VARCHAR2,  
    acl_path  IN  VARCHAR2);
```

Parameters

Table 108–20 SETACL Procedure Parameters

Parameter	Description
res_path	Absolute path in the Hierarchy for resource.
acl_path	Absolute path in the Hierarchy for ACL.

Usage Notes

The user must have `<write-acl>` privileges on the resource.

UNLOCKRESOURCE Function

This function unlocks the resource given a lock token and a path to the resource.

Syntax

```
DBMS_XDB.UNLOCKRESOURCE(  
    path      IN VARCHAR2,  
    deltoken IN VARCHAR2)  
RETURN BOOLEAN;
```

Parameters

Table 108–21 UNLOCKRESOURCE Function Parameters

Parameter	Description
path	Path name to the resource.
deltoken	Lock token to be removed.

Return Values

Returns `TRUE` if operation successful.

Usage Notes

The user must have `UPDATE` privileges on the resource.

DBMS_XDB_VERSION

Oracle XML DB versioning APIs are found in the `DBMS_XDB_VERSION` package. Functions and procedures of `DBMS_XDB_VERSION` help to create a VCR and manage the versions in the version history.

This chapter contains the following topic:

- [Summary of DBMS_XDB_VERSION Subprograms](#)

See Also: *Oracle XML DB Developer's Guide*

Summary of DBMS_XDB_VERSION Subprograms

Table 109–1 DBMS_XDB_VERSION Package Subprograms

Method	Description
CHECKIN Function on page 109-3	Checks in a checked-out VCR and returns the resource id of the newly-created version
CHECKOUT Procedure on page 109-4	Checks out a VCR before updating or deleting it
GETCONTENTSBLobbyRES ID Function on page 109-5	Obtain contents as a BLOB
GETCONTENTSCLobbyRES ID Function on page 109-6	Obtain contents as a CLOB
GETCONTENTSXMLBYRESID Function on page 109-7	Obtain contents as an XMLType
GETPREDECESSORS Function on page 109-8	Retrieves the list of predecessors by path name
GETPREDSBYRESID Function on page 109-9	Retrieves the list of predecessors by resource id
GETRESOURCEBYRESID Function on page 109-9	Obtains the resource as an XMLType, given the resource object ID
GETSUCCESSORS Function on page 109-9	Retrieves the list of successors by path name
GETSUCCSBYRESID Function on page 109-12	Retrieves the list of successors by resource id
MAKEVERSIONED Function on page 109-13	Turns a regular resource whose path name is given into a version-controlled resource
UNCHECKOUT Function on page 109-14	Checks in a checked-out resource, returns the resource id of the version before the resource is checked out

CHECKIN Function

This function checks in a checked-out VCR and returns the resource id of the newly-created version.

Syntax

```
DBMS_XDB_VERSION.CHECKIN(  
    pathname VARCHAR2)  
RETURN DBMS_XDB.resid_type;
```

Parameters

Table 109–2 CHECKIN Function Parameters

Parameter	Description
pathname	The path name of the checked-out resource.

Usage Notes

This is not an auto-commit SQL operation. [CHECKIN Function](#) doesn't have to take the same path name that was passed to [CHECKOUT Procedure](#) operation. However, the [CHECKIN Function](#) path name and the [CHECKOUT Procedure](#) path name must be of the same resource for the operations to function correctly. If the resource has been renamed, the new name must be used to [CHECKIN Function](#) because the old name is either invalid or is currently bound with a different resource. Exception is raised if the path name does not exist. If the path name has been changed, the new path name must be used to [CHECKIN Function](#) the resource.

CHECKOUT Procedure

This procedure checks out a VCR before updating or deleting it.

Syntax

```
DBMS_XDB_VERSION.CHECKOUT(  
    pathname    VARCHAR2);
```

Parameters

Table 109–3 CHECKOUT Procedure Parameters

Parameter	Description
pathname	The path name of the VCR to be checked out.

Usage Notes

This is not an auto-commit SQL operation. Two users of the same workspace cannot [CHECKOUT Procedure](#) the same VCR at the same time. If this happens, one user must rollback. As a result, it is good practice to commit the [CHECKOUT Procedure](#) operation before updating a resource and avoid loss of the update if the transaction is rolled back. An exception is raised if the given resource is not a VCR, if the VCR is already checked out, if the resource doesn't exist.

GETCONTENTSBLOBBYRESID Function

This function obtain contents as a BLOB.

Syntax

```
DBMS_XDB_VERSION.GETCONTENTSBLOBBYRESID(  
    resid      DBMS_XDB.resid_type)  
RETURN BLOB;
```

Parameters

Table 109–4 *GETCONTENTSBLOBBYRESID Function Parameters*

Parameter	Description
resid	The resource id.

GETCONTENTSCLOBBYRESID Function

This function obtains contents as a CLOB.

Syntax

```
DBMS_XDB_VERSION.GETCONTENTSCLOBBYRESID(  
    resid      DBMS_XDB.resid_type)  
RETURN CLOB;
```

Parameters

Table 109–5 *GETCONTENTSCLOBBYRESID Function Parameters*

Parameter	Description
resid	The resource id.

GETCONTENTSXMLBYRESID Function

This function obtains contents as an XMLType.

Syntax

```
DBMS_XDB_VERSION.GETCONTENTSXMLBYRESID(  
    resid      DBMS_XDB.resid_type)  
RETURN XMLType;
```

Parameters

Table 109–6 *GETCONTENTSXMLBYRESID Function Parameters*

Parameter	Description
resid	The resource id.

Return Values

If the contents are not valid XML, returns NULL.

GETPREDECESSORS Function

This function retrieves the list of predecessors by the path name.

Syntax

```
DBMS_XDB_VERSION.GETPREDECESSORS(  
    pathname          VARCHAR2)  
RETURN resid_list_type;
```

Parameters

Table 109–7 *GETPREDECESSORS Function Parameters*

Parameter	Description
pathname	The path name of the resource.

Return Values

An exception is raised if `PATHNAME` is illegal.

GETPREDSBYRESID Function

This function retrieves the list of predecessors by resource id.

Syntax

```
DBMS_XDB_VERSION.GETPREDSBYRESID(  
    resid      resid_type)  
RETURN resid_list_type;
```

Parameters

Table 109–8 *GETPREDSBYRESID Function Parameters*

Parameter	Description
resid	The resource id.

Usage Notes

Getting predecessors by RESID is more efficient than by PATHNAME.

Exceptions

An exception is raised if the RESID is illegal.

GETRESOURCEBYRESID Function

This function obtains the resource as an `XMLType`, given the resource object ID. Because the system will not create a path name for versions, this function is useful for retrieving the resource using its resource id.

Syntax

```
DBMS_XDB_VERSION.GETRESOURCEBYRESID(  
    resid      resid_type)  
RETURN XMLType;
```

Parameters

Table 109–9 *GETRESOURCEBYRESID Function Parameters*

Parameter	Description
<code>resid</code>	The resource id.

GETSUCCESSORS Function

Given a version resource or a VCR, this function retrieves the list of the successors of the resource by the path name.

Syntax

```
DBMS_XDB_VERSION.GETSUCCESSORS(  
    pathname VARCHAR2)  
RETURN resid_list_type;
```

Parameters

Table 109–10 *GETSUCCESSORS Function Parameters*

Parameter	Description
pathname	The path name of the resource.

Usage Notes

Getting successors by RESID is more efficient than by PATHNAME.

Exceptions

An exception is raised if the PATHNAME is illegal.

GETSUCCSBYRESID Function

This function retrieves the list of the successors of the resource by resource id using version resource or VCR.

Syntax

```
DBMS_XDB_VERSION.GETSUCCSBYRESID(  
    resid    resid_type)  
RETURN resid_list_type;
```

Parameters

Table 109–11 *GETSUCCSBYRESID Function Parameters*

Parameter	Description
resid	The resource id.

Usage Notes

Getting successors by RESID is more efficient than by PATHNAME.

Exceptions

An exception is raised if the PATHNAME is illegal.

MAKEVERSIONED Function

This function turns a regular resource whose path name is given into a version-controlled resource. This new resource is then put under version control. All other path names continue to refer to the original resource.

Syntax

```
DBMS_XDB_VERSION.MAKEVERSIONED(
    pathname  VARCHAR2)
RETURN DBMS_XDB.resid_type;
```

Parameters

Table 109–12 MAKEVERSIONED Function Parameters

Parameter	Description
pathname	The path name of the resource to be put under version control.

Return Values

This function returns the resource ID of the first version, or root, of the VCR.

Usage Notes

If two or more path names are bound with the same resource, a copy of the resource will be created, and the given path name will be bound with the newly-created copy.

This is not an auto-commit SQL operation. An exception is raised if the resource doesn't exist.

- This call is legal for VCR, and neither exception nor warning is raised.
- This call is illegal for folder, version history, version resource, and ACL.
- No support for Schema-based resources is provided.

UNCHECKOUT Function

This function checks-in a checked-out resource and returns the resource id of the version before the resource is checked out.

Syntax

```
DBMS_XDB_VERSION.UNCHECKOUT(  
    pathname    VARCHAR2)  
RETURN DBMS_XDB.resid_type;
```

Parameters

Table 109–13 *UNCHECKOUT Function Parameters*

Parameter	Description
pathname	The path name of the checked-out resource.

Usage Notes

This is not an auto-commit SQL operation. [UNCHECKOUT Function](#) doesn't have to take the same path name that was passed to [CHECKOUT Procedure](#) operation. However, the [UNCHECKOUT Function](#) path name and the [CHECKOUT Procedure](#) path name must be of the same resource for the operations to function correctly. If the resource has been renamed, the new name must be used to [UNCHECKOUT Function](#), because the old name is either invalid or is currently bound with a different resource. If the path name has been changed, the new path name must be used to [UNCHECKOUT Function](#) the resource.

Exceptions

An exception is raised if the path name doesn't exist.

The DBMS_TTS package checks if the transportable set is self-contained. All violations are inserted into a temporary table that can be selected from the view TRANSPORT_SET_VIOLATIONS.

See Also:

- *Oracle Database Administrator's Guide*
- *Oracle Database Upgrade Guide*

This chapter contains the following topics:

- [Using DBMS_TTS](#)
 - [Security Model](#)
 - [Exceptions](#)
 - [Operational Notes](#)
- [Summary of DBMS_TTS Subprograms](#)

Using DBMS_TTS

- [Security Model](#)
- [Exceptions](#)
- [Operational Notes](#)

Security Model

Only users having the `execute_catalog_role` can execute this procedure. This role is initially only assigned to user `SYS`.

Exceptions

```
ts_not_found EXCEPTION;  
PRAGMA exception_init(ts_not_found, -29304);  
ts_not_found_num NUMBER := -29304;  
  
invalid_ts_list EXCEPTION;  
PRAGMA exception_init(invalid_ts_list, -29346);  
invalid_ts_list_num NUMBER := -29346;  
  
sys_or_tmp_ts EXCEPTION;  
PRAGMA exception_init(sys_or_tmp_ts, -29351);  
sys_or_tmp_ts_num NUMBER := -29351;
```

Operational Notes

With respect to transportable tablespaces, disabled and enabled referential integrity constraints are handled differently:

- A disabled referential integrity constraint does not violate the transportability rules and is dropped during the import phase.
- An enabled referential integrity constraint violates the transportability rules if it references a table in a tablespace outside the transportable set.

Summary of DBMS_TTS Subprograms

These two procedures are designed to be called by database administrators.

Table 110-1 DBMS_TTS Package Subprograms

Subprogram	Description
DOWNGRADE Procedure on page 110-4	Downgrades transportable tablespace related data
TRANSPORT_SET_CHECK Procedure on page 110-5	Checks if a set of tablespaces (to be transported) is self-contained

DOWNGRADE Procedure

This procedure downgrades transportable tablespace related data.

Syntax

```
DBMS_TTS.DOWNGRADE;
```


TRANSPORT_SET_CHECK Procedure

This procedure checks if a set of tablespaces (to be transported) is self-contained. After calling this procedure, the user may select from a view to see a list of violations, if there are any.

Syntax

```
DBMS_TTS.TRANSPORT_SET_CHECK (
    ts_list          IN VARCHAR2,
    incl_constraints IN BOOLEAN DEFAULT FALSE,
    full_check       IN BOOLEAN DEFAULT FALSE);
```

Parameters

Table 110–2 *TRANSPORT_SET_CHECK Procedure Parameters*

Parameter	Description
<code>ts_list</code>	List of tablespace, separated by comma.
<code>incl_constraints</code>	TRUE if you want to count in referential integrity constraints when examining if the set of tablespaces is self-contained. (The <code>incl_constraints</code> parameter is a default so that <code>TRANSPORT_SET_CHECK</code> will work if it is called with only the <code>ts_list</code> argument.)
<code>full_check</code>	Indicates whether a full or partial dependency check is required. If TRUE, treats all IN and OUT pointers (dependencies) and captures them as violations if they are not self-contained in the transportable set. The parameter should be set to TRUE for TSPITR or if a strict version of transportable is desired. By default the parameter is set to false. It will only consider OUT pointers as violations.

Examples

If the view does not return any rows, then the set of tablespaces is self-contained. For example,

```
SQLPLUS> EXECUTE DBMS_TTS.TRANSPORT_SET_CHECK('foo,bar', TRUE);
SQLPLUS> SELECT * FROM TRANSPORT_SET_VIOLATIONS;
```


The `DBMS_XDBT` package provides a convenient mechanism for administrators to set up a `CONTEXT` index on the Oracle XML DB hierarchy. The package contains procedures to create default preferences, create the index and set up automatic synchronization of the `CONTEXT` index

The `DBMS_XDBT` package also contains a set of package variables that describe the configuration settings for the index. These are intended to cover the basic customizations that installations may require, but is by no means a complete set.

See Also: *Oracle XML DB Developer's Guide*

This chapter contains the following topics:

- [Using DBMS_XDBT](#)
 - [Overview](#)
 - [Operational Notes](#)
- [Summary of DBMS_XDBT Subprograms](#)

Using DBMS_XDBT

- [Overview](#)
- [Operational Notes](#)

Overview

The DBMS_XDBT package can be used in the following fashion:

- Customize the package to set up the appropriate configuration.
- Drop any existing index preferences using the [DROPPREFERENCES Procedure](#) procedure.
- Create new index preferences using the [CREATEPREFERENCES Procedure](#) procedure.
- Create the CONTEXT index using the [CREATEINDEX Procedure](#) procedure.
- Set up automatic synchronization of the index using the [CONFIGUREAUTOSYNC Procedure](#) procedure.

Operational Notes

The DBMS_XDBT package can be customized by using a PL/SQL procedure or an anonymous block to set the relevant package variables, configuration settings, and then execute the procedures. A more general approach would be to introduce the appropriate customizations by modifying this package in place, or as a copy. The system must be configured to use job queues, and the jobs can be viewed through the USER_JOBS catalog views. This section describes the configuration settings, or package variables, available to customize the DBMS_XDBT package.

Table 111–1 General Indexing Settings for Customizing DBMS_XDBT

Parameter	Default Value	Description
IndexName	XDB\$CI	The name of the CONTEXT index.
IndexTablespace	XDB\$RESINFORCE	Tablespace used by tables and indexes comprising the CONTEXT index.
IndexMemory	128M	Memory used by index creation and SYNC; less than or equal to the MAX_INDEX_MEMORY system parameter (see the CTX_ADMIN package).
LogFile	'XdbCtxLog'	The log file used for ROWID during indexing. The LOG_DIRECTORY system parameter must be set already. NULL turns off ROWID logging.

Table 111–2 Filtering Settings for Customizing DBMS_XDBT

Parameter	Default Value	Description
SkipFilter_Types	image/%, audio/%, video/%, model/%	List of mime types that should not be indexed.
NullFilter_Types	text/plain, text/html, text/xml	List of mime types that do not need to use the INSO filter. Use this for text-based documents.
FilterPref	XDB\$CI_FILTER	Name of the filter preference.

Table 111–3 Stoplister Settings for Customizing DBMS_XDBT

Parameter	Default Value	Description
StoplisterPref	XDB\$CI_STOPLIST	Name of the stoplist.
StopWords	0..9; 'a'..'z'; 'A'..'Z'	List of stopwords, in excess of CTXSYS.DEFAULT_STOPLIST.

Table 111–4 Sectioning and Section Group Settings for Customizing DBMS_XDBT

Parameter	Default Value	Description
SectionGroup	HTML_SECTION_GROUP	Default sectioner. Use PATH_SECTION_GROUP or AUTO_SECTION_GROUP if repository contains mainly XML documents.
SectiongroupP_ref	XDB\$CI_SECTIONGROUP	Name of the section group.

Table 111–5 Other Index Preference Settings for Customizing DBMS_XDBT

Parameter	Default Value	Description
DatastorePref	XDB\$CI_DATASTORE	The name of the datastore preference.
StoragePref	XDB\$CI_STORAGE	The name of the storage preference.
WordlistPref	XDB\$CI_WORDLIST	The name of the wordlist preference.
DefaultLexerPref	XDB\$CI_DEFAULT_LEXER	The name of the default lexer preference.

Table 111–6 SYNC (CONTEXT Synchronization) Settings for Customizing DBMS_XDBT

Parameter	Default Value	Description
AutoSyncPolicy	SYNC_BY_PENDING_COUNT	Indicates when the index should be SYNCed. One of SYNC_BY_PENDING_COUNT, SYNC_BY_TIME, or SYNC_BY_PENDING_COUNT_AND_TIME.
MaxPendingCount	2	Maximum number of documents in the CTX_USER_PENDING queue before an index SYNC is triggered. Only if the AutoSyncPolicy is SYNC_BY_PENDING_COUNT or SYNC_BY_PENDING_COUNT_AND_TIME.
CheckPendingCount Interval	10 minutes	How often, in minutes, the pending queue should be checked. Only if the AutoSyncPolicy is SYNC_BY_PENDING_COUNT or SYNC_BY_PENDING_COUNT_AND_TIME.
SyncInterval	60 minutes	Indicates how often, in minutes, the index should be SYNCed. Only if the AutoSyncPolicy is SYNC_BY_TIME or SYNC_BY_PENDING_COUNT_AND_TIME.

Summary of DBMS_XDBT Subprograms

Table 111–7 DBMS_XDBT Package Subprograms

Subprogram	Description
CONFIGUREAUTOSYNC Procedure on page 111-6	Configures the <code>CONTEXT</code> index for automatic maintenance, <code>SYNC</code>
CREATEDATASTOREPREF Procedure on page 111-7	Creates a <code>USER</code> datastore preference for the <code>CONTEXT</code> index
CREATEFILTERPREF Procedure on page 111-8	Creates a filter preference for the <code>CONTEXT</code> index
CREATEINDEX Procedure on page 111-9	Creates the <code>CONTEXT</code> index on the XML DB hierarchy
CREATELEXERPREF Procedure on page 111-10	Creates a lexer preference for the <code>CONTEXT</code> index
CREATEPREFERENCES Procedure on page 111-11	Creates preferences required for the <code>CONTEXT</code> index on the XML DB hierarchy
CREATESECTIONGROUPOPREF Procedure on page 111-12	Creates a storage preference for the <code>CONTEXT</code> index
CREATESTOPLISTPREF Procedure on page 111-13	Creates a section group for the <code>CONTEXT</code> index
CREATESTORAGEPREF Procedure on page 111-14	Creates a wordlist preference for the <code>CONTEXT</code> index
CREATEWORLDSLIPREF Procedure on page 111-15	Creates a stoplist for the <code>CONTEXT</code> index
DROPPREFERENCES Procedure on page 111-16	Drops any existing preferences

CONFIGUREAUTOSYNC Procedure

This procedure sets up jobs for automatic SYNCs of the `CONTEXT` index.

Syntax

```
DBMS_XDBT.CONFIGUREAUTOSYNC;
```

Usage Notes

- The system must be configured for job queues for automatic synchronization. The jobs can be viewed using the `USER_JOBS` catalog views
- The configuration parameter `AutoSyncPolicy` can be set to choose an appropriate synchronization policy.

The synchronization can be based on one of the following:

Sync Basis	Description
<code>SYNC_BY_PENDING_COUNT</code>	The SYNC is triggered when the number of documents in the pending queue is greater than a threshold (See the MaxPendingCount configuration setting on page 111-4). The pending queue is polled at regular intervals (See the CheckPendingCountInterval configuration parameter on page 111-4) to determine if the number of documents exceeds the threshold.
<code>SYNC_BY_TIME</code>	The SYNC is triggered at regular intervals. (See the SyncInterval configuration parameter on page 111-4).
<code>SYNC_BY_PENDING_COUNT_AND_TIME</code>	A combination of both of the preceding options.

CREATEDATASTOREPREF Procedure

This procedure creates a user datastore preference for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATEDATASTOREPREF;
```

Usage Notes

- The name of the datastore preference can be modified; see the `DatastorePref` configuration setting.
- The default `USER` datastore procedure also filters the incoming document. The `DBMS_XDBT` package provides a set of configuration settings that control the filtering process.
- The `SkipFilter_Types` array contains a list of regular expressions. Documents with a mime type that matches one of these expressions are not indexed. Some of the properties of the document metadata, such as author, remain unindexed.
 - The `NullFilter_Types` array contains a list of regular expressions. Documents with a mime type that matches one of these expressions are not filtered; however, they are still indexed. This is intended to be used for documents that are text-based, such as HTML, XML and plain-text.
 - All other documents use the `INSO` filter through the `IFILTER` API.

CREATEFILTERPREF Procedure

This procedure creates a `NULL` filter preference for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATEFILTERPREF;
```

Usage Notes

- The name of the filter preference can be modified; see `FilterPref` configuration setting.
- The `USER` datastore procedure filters the incoming document; see [CREATEDATASTOREPREF Procedure](#) for more details.

CREATEINDEX Procedure

This procedure creates the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATEINDEX;
```

Usage Notes

- The name of the index can be changed; see the `IndexName` configuration setting.
- Set the `LogFile` configuration parameter to enable `ROWID` logging during index creation.
- Set the `IndexMemory` configuration parameter to determine the amount of memory that index creation, and later `SYNCs`, will use.

CREATELEXERPREF Procedure

This procedure creates a BASIC `lexer` preference for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATELEXERPREF;
```

Usage Notes

- The name of the `lexer` preference can be modified; see `LexerPref` configuration setting. No other configuration settings are provided.
- `MultiLexer` preferences are not supported.
- Base letter translation is turned on by default.

CREATEPREFERENCES Procedure

This procedure creates a set of default preferences based on the configuration settings.

Syntax

```
DBMS_XDBT.CREATEPREFERENCES;
```

CREATESECTIONGROUPPREF Procedure

This procedure creates a section group for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATESECTIONGROUPPREF;
```

Usage Notes

- The name of the section group can be changed; see the `SectiongroupPref` configuration setting.
- The HTML sectioner is used by default. No zone sections are created by default. If the vast majority of documents are XML, consider using the `AUTO_SECTION_GROUP` or the `PATH_SECTION_GROUP`; see the `SectionGroup` configuration setting.

CREATESTOPLISTPREF Procedure

This procedure creates a stoplist for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATESTOPLISTPREF;
```

Usage Notes

- The name of the stoplist can be modified; see the `StoplistPref` configuration setting.
- Numbers are not indexed.
- The `StopWords` array is a configurable list of stopwords. These are meant to be stopwords in addition to the set of stopwords in `CTXSYS.DEFAULT_STOPLIST`.

CREATESTORAGEPREF Procedure

This procedure creates a `BASIC_STORAGE` preference for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATESTORAGEPREF;
```

Usage Notes

- The name of the storage preference can be modified; see the `StoragePref` configuration setting.
- A tablespace can be specified for the tables and indexes comprising the `CONTEXT` index; see the `IndexTablespace` configuration setting.
- Prefix and Substring indexing are not turned on by default.
- The `I_INDEX_CLAUSE` uses key compression.

CREATEWORDLISTPREF Procedure

This procedure creates a wordlist preference for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.CREATEWORDLISTPREF;
```

Usage Notes

- The name of the wordlist preference can be modified; see the `WordlistPref` configuration setting. No other configuration settings are provided.
- `FUZZY_MATCH` and `STEMMER` attributes are set to `AUTO` (auto-language detection)

DROPPREFERENCES Procedure

This procedure drops any previously created preferences for the `CONTEXT` index on the XML DB hierarchy.

Syntax

```
DBMS_XDBT.DROPPREFERENCES;
```

The DBMS_XDBZ package controls the Oracle XML DB repository security, which is based on Access Control Lists (ACLs).

This chapter contains the following topic:

- [Summary of DBMS_XDBZ Subprograms](#)

See Also: *Oracle XML DB Developer's Guide*

Summary of DBMS_XDBZ Subprograms

Table 112–1 *DBMS_XDBZ Package Subprograms*

Method	Description
DISABLE_HIERARCHY Procedure on page 112-3	Disables repository support for the specified XMLType table or view
ENABLE_HIERARCHY Procedure on page 112-4	Enables repository support for the specified XMLType table or view
GET_ACLOID Function on page 112-5	Retrieves the ACL Object ID for the specified resource
GET_USERID Function on page 112-6	Retrieves the user ID for the specified user
IS_HIERARCHY_ENABLED Function on page 112-7	Determines if repository support for the specified XMLType table or view is enabled
PURGELDAPCACHE Function on page 112-8	Purges the LDAP nickname cache

DISABLE_HIERARCHY Procedure

This procedure disables repository support for a particular XMLType table or view.

Syntax

```
DBMS_XDBZ.DISABLE_HIERARCHY(  
    object_schema IN VARCHAR2,  
    object_name   IN VARCHAR2);
```

Parameters

Table 112–2 *DISABLE_HIERARCHY Procedure Parameters*

Parameter	Description
object_schema	The schema name of the XMLType table or view.
object_name	The name of the XMLType table or view.

ENABLE_HIERARCHY Procedure

This procedure enables repository support for a particular XMLType table or view. This allows the use of a uniform ACL-based security model across all documents in the repository.

Syntax

```
DBMS_XDBZ.ENABLE_HIERARCHY(  
    object_schema IN VARCHAR2,  
    object_name   IN VARCHAR2);
```

Parameters

Table 112–3 *ENABLE_HIERARCHY Procedure Parameters*

Parameter	Description
object_schema	The schema name of the XMLType table or view.
object_name	The name of the XMLType table or view.

GET_ACLOID Function

This function retrieves the ACL Object ID for the specified resource, if the repository path is known.

Syntax

```
DBMS_XDBZ.GET_ACLOID(  
    aclpath IN VARCHAR2,  
    acloid  OUT RAW)  
RETURN BOOLEAN;
```

Parameters

Table 112–4 GET_ACLOID Function Parameters

Parameter	Description
aclpath	ACL resource path for the repository.
acloid	The returned Object ID.

Return Values

Returns TRUE if successful.

GET_USERID Function

This function retrieves the user ID for the specified user name. The local database is searched first, and if found, the `USERID` is returned in 4-byte database format. Otherwise, the LDAP directory is searched, if available, and if found, the `USERID` is returned in 4-byte database format.

Syntax

```
DBMS_XDBZ.GET_USERID(  
    username IN VARCHAR2,  
    userid   OUT RAW,  
    format   IN  BINARY_INTEGER := NAME_FORMAT_SHORT)  
RETURN BOOLEAN;
```

Parameters

Table 112–5 *GET_USERID Function Parameters*

Parameter	Description
<code>username</code>	Name of the database or LDAP user.
<code>userid</code>	Return parameter for the matching user id.
<code>format</code>	Format of the specified user name; valid options are: <ul style="list-style-type: none">■ <code>DBMS_XDBZ.NAME_FORMAT_SHORT</code> (default) -- DB user name or LDAP nickname■ <code>DBMS_XDBZ.NAME_FORMAT_DISTINGUISHED</code> -- LDAP distinguished name.

Return Values

Returns `TRUE` if successful.

IS_HIERARCHY_ENABLED Function

This function determines if repository support for the specified XMLType table or view is enabled.

Syntax

```
DBMS_XDBZ.IS_HIERARCHY_ENABLED(  
    object_schema IN VARCHAR2,  
    object_name   IN VARCHAR2)  
RETURN BOOLEAN;
```

Parameters

Table 112–6 IS_HIERARCHY_ENABLED Function Parameters

Parameter	Description
object_schema	The schema name of the XMLType table or view.
object_name	The name of the XMLType table or view.

Return Values

Returns TRUE if enabled.

PURGELDAPCACHE Function

This function purges the LDAP nickname cache. Returns `TRUE` if successful.

Syntax

```
DBMS_XDBZ.PURGELDAPCACHE  
RETURN BOOLEAN;
```

The `DBMS_XMLDOM` package is used to access `XMLType` objects, and implements the Document Object Model (DOM), an application programming interface for HTML and XML documents.

See Also: *Oracle XML Developer's Kit Programmer's Guide*

This chapter contains the following topics:

- [Using DBMS_XMLDOM](#)
 - [Overview](#)
 - [Constants](#)
 - [Types](#)
 - [Exceptions](#)
- [Subprogram Groups](#)
- [Summary of DBMS_XMLDOM Subprograms](#)

Using DBMS_XMLDOM

- [Overview](#)
- [Constants](#)
- [Types](#)
- [Exceptions](#)
- [Subprogram Groups](#)

Overview

The Document Object Model (DOM) is an application programming interface (API) for HTML and XML documents. It defines the logical structure of documents, and the manner in which they are accessed and manipulated. In the DOM specification, the term "document" is used in the broad sense. XML is being increasingly used to represent many different kinds of information that may be stored in diverse systems. This information has been traditionally be seen as "data"; nevertheless, XML presents this data as documents, and the `DBMS_XMLDOM` package allows you access to both schema-based and non schema-based documents.

Note:

- Before database startup, the read-from and write-to directories in the `initialization.ORA` file must be specified; for example: `UTL_FILE_DIR=/mypath/insidemypath`.
- Read-from and write-to files must be on the server file system.


With DOM, anything found in an HTML or XML document can be accessed, changed, deleted, or added using the Document Object Model, with a few exceptions. In particular, the DOM interfaces for the XML internal and external subsets have not yet been specified.

One important objective of the W3C DOM specification is to provide a standard programming interface that can be used in a wide variety of environments, programming languages, and applications. Because the DOM standard is object-oriented while PL/SQL is essentially a procedural language, some changes had to be made:

- Various DOM interfaces such as `Node`, `Element`, and others have equivalent PL/SQL types `DOMNode`, `DOMLElement`, respectively.
- Various `DOMException` codes such as `WRONG_DOCUMENT_ERR`, `HIERARCHY_REQUEST_ERR`, and others, have similarly named PL/SQL exceptions.
- Various DOM Node type codes such as `ELEMENT_NODE`, `ATTRIBUTE_NODE`, and others, have similarly named PL/SQL constants.
- Subprograms defined on a DOM type become functions or procedures that accept it as a parameter. For example, to perform [APPENDCHILD Function](#) on a `DOMNode` `n`, the [APPENDCHILD Function](#) PL/SQL function on page 113-42 is provided.
- To perform `setAttribute` on a `DOMLElement` `elem`, use [SETATTRIBUTE Procedures](#) PL/SQL procedure on page 113-139.

DOM defines an inheritance hierarchy. For example, `Document`, `Element`, and `Attr` are defined to be subtypes of `Node` (see [Figure 113-1](#)). Thus, a method defined in the `Node` interface should be available in these as well. Since such inheritance is not supported in PL/SQL, it is implemented through direct invocation of the `MAKENODE` function. Calling `MAKENODE` on various DOM types converts these types into a `DOMNode`. The appropriate functions or procedures that accept `DOMNodes` can then be called to operate on these types. If, subsequently, type specific functionality is desired, the `DOMNode` can be converted back into the original type by the `makeXXX` functions, where `DOMXXX` is the desired DOM type.

Figure 113-1 Inheritance Diagram for DOM Types



The implementation of this interface follows the REC-DOM-Level-1-19981001.

Constants

Defined constants of `DBMS_XMLDOM` are listed in [Table 113-1](#).

Table 113-1 *Defined Constants for DBMS_XMLDOM*

Constant	Description
<code>ATTRIBUTE_NODE</code>	The Node is an Attribute.
<code>CDATA_SECTION_NODE</code>	The Node is a CDATASection.
<code>COMMENT_NODE</code>	The Node is a Comment.
<code>DOCUMENT_FRAGMENT_NODE</code>	The Node is a Document fragment.
<code>DOCUMENT_NODE</code>	The Node is a Document.
<code>DOCUMENT_TYPE_NODE</code>	The Node is a Document Type Definition.
<code>ELEMENT_NODE</code>	The Node is an Element.
<code>ENTITY_NODE</code>	The Node is an Entity.
<code>ENTITY_REFERENCE_NODE</code>	The Node is an Entity Reference.
<code>NOTATION_NODE</code>	The Node is a Notation.
<code>PROCESSING_INSTRUCTION_NODE</code>	The Node is a Processing Instruction.
<code>TEXT_NODE</code>	The Node is a Text node.

Types

The following types for `DBMS_XMLDOM.DOMTYPE` are defined in [Table 113-2](#):

Table 113-2 *XDB_XMLDOM Types*

Type	Description
<code>DOMATTR</code>	Implements the DOM Attribute interface.
<code>DOMCDATASECTION</code>	Implements the DOM CDATASection interface.
<code>DOMCHARACTERDATA</code>	Implements the DOM Character Data interface.
<code>DOMCOMMENT</code>	Implements the DOM Comment interface.

Table 113–2 (Cont.) XDB_XMLDOM Types

Type	Description
DOMDOCUMENT	Implements the DOM Document interface.
DOMDOCUMENTFRAGMENT	Implements the DOM DocumentFragment interface.
DOMDOCUMENTTYPE	Implements the DOM Document Type interface.
DOMELEMENT	Implements the DOM Element interface.
DOMENTITY	Implements the DOM Entity interface.
DOMENTITYREFERENCE	Implements the DOM EntityReference interface.
DOMIMPLEMENTATION	Implements the DOM Implementation interface.
DOMNAMEDNODEMAP	Implements the DOM Named Node Map interface.
DOMNODE	Implements the DOM Node interface.
DOMNODELIST	Implements the DOM NodeList interface.
DOMNOTATION	Implements the DOM Notation interface.
DOMPROCESSINGINSTRUCTION	Implements the DOM Processing instruction interface.
DOMTEXT	Implements the DOM Text interface.

Exceptions

The exceptions listed in [Table 113–3](#) are defined for DBMS_XMLDOM:

Table 113–3 Exceptions for DBMS_XMLDOM

Exception	Description
DOMSTRING_SIZE_ERR	If the specified range of text does not fit into a DOMString.
HIERARCHY_REQUEST_ERR	If any node is inserted somewhere it doesn't belong.
INDEX_SIZE_ERR	If index or size is negative, or greater than the allowed value.
INUSE_ATTRIBUTE_ERR	If an attempt is made to add an attribute that is already in use elsewhere.

Table 113–3 (Cont.) Exceptions for DBMS_XMLDOM

Exception	Description
INVALID_CHARACTER_ERR	If an invalid or illegal character is specified, such as in a name. See production 2 in the XML specification for the definition of a legal character, and production 5 for the definition of a legal name character.
NO_DATA_ALLOWED_ERROR	If data is specified for a node that does not support data.
NO_FOUND_ERR	If an attempt is made to reference a node in a context where it does not exist.
NO_MODIFICATION_ALLOWED_ERR	If an attempt is made to modify an object where modifications are not allowed.
NOT_SUPPORTED_ERR	If the implementation does not support the requested type of object or operation.
WRONG_DOCUMENT_ERR	If a node is used in a different document than the one that created it (that doesn't support it).

Subprogram Groups

DBMS_XMLDOM subprograms are divided into groups according to W3C Interfaces.

- [DOMNode Subprograms](#) on page 113-8
- [DOMAttr Subprograms](#) on page 113-11
- [DOMCDataSection Subprograms](#) on page 113-12
- [DOMCharacterData Subprograms](#) on page 113-13
- [DOMComment Subprograms](#) on page 113-14
- [DOMDocument Subprograms](#) on page 113-15
- [DOMDocumentFragment Subprograms](#) on page 113-17
- [DOMDocumentType Subprograms](#) on page 113-18
- [DOMElement Subprograms](#) on page 113-19
- [DOMEntity Subprograms](#) on page 113-20
- [DOMEntityReference Subprograms](#) on page 113-21
- [DOMImplementation Subprograms](#) on page 113-22
- [DOMNamedNodeMap Subprograms](#) on page 113-23
- [DOMNodeList Subprograms](#) on page 113-24
- [DOMNotation Subprograms](#) on page 113-25
- [DOMProcessingInstruction Subprograms](#) on page 113-26
- [DOMText Subprograms](#) on page 113-27

DOMNode Subprograms

Table 113–4 Summary of DOMNode Subprograms; DBMS_XMLDOM

Subprogram	Description
ADOPTNODE Procedure on page 113-41	Adopts a node from another document.
APPENDCHILD Function on page 113-42	Appends a new child to the node.
CLONENODE Function on page 113-44	Clones the node.
FREENODE Procedure on page 113-60	Frees all resources associated with the node.
GETATTRIBUTES Function on page 113-62	Retrieves the attributes of the node.
GETCHILDNODES Function on page 113-64	Retrieves the children of the node.
GETEXPANDEDNAME Procedure and Functions on page 113-71	Retrieves the expanded name of the node.
GETFIRSTCHILD Function on page 113-72	Retrieves the first child of the node.
GETLASTCHILD Function on page 113-74	Retrieves the last child of the node.
GETLOCALNAME Procedure and Functions on page 113-76	Retrieves the local part of the qualified name.
GETNAMESPACE Procedure and Functions on page 113-79	Retrieves the node's namespace URI.
GETNEXTSIBLING Function on page 113-80	Retrieves the next sibling of the node.
GETNODENAME Function on page 113-81	Retrieves the Name of the Node.
GETNODETYPE Function on page 113-82	Retrieves the Type of the node.
GETNODEVALUE Function on page 113-83	Retrieves the Value of the Node.
GETOWNERDOCUMENT Function on page 113-87	Retrieves the owner document of the node.
GETPARENTNODE Function on page 113-89	Retrieves the parent of this node.
GETPREFIX Function on page 113-90	Retrieves the namespace prefix.
GETPREVIOUSIBLING Function on page 113-91	Retrieves the previous sibling of the node.

Table 113–4 (Cont.) Summary of DOMNode Subprograms; DBMS_XMLDOM

Subprogram	Description
GETSCHEMANODE Function on page 113-94	Retrieves the associated schema URI.
HASATTRIBUTES Function on page 113-103	Tests if the node has attributes.
HASCHILDNODES Function on page 113-104	Tests if the node has child nodes.
IMPORTNODE Function on page 113-106	Imports a node from another document.
INSERTBEFORE Function on page 113-107	Inserts a child before the reference child.
ISNULL Functions on page 113-109	Tests if the node is NULL
MAKEATTR Function on page 113-114	Casts the node to an Attribute.
MAKECDATASECTION Function on page 113-115	Casts the node to a CDATA Section.
MAKECHARACTERDATA Function on page 113-116	Casts the node to Character Data.
MAKECOMMENT Function on page 113-117	Casts the node to a Comment.
MAKEDOCUMENT Function on page 113-118	Casts the node to a DOM Document.
MAKEDOCUMENTFRAGMENT Function on page 113-119	Casts the node to a DOM Document Fragment.
MAKEDOCUMENTTYPE Function on page 113-120	Casts the node to a DOM Document Type.
MAKEELEMENT Function on page 113-121	Casts the node to a DOM Element.
MAKEENTITY Function on page 113-122	Casts the node to a DOM Entity.
MAKEENTITYREFERENCE Function on page 113-123	Casts the node to a DOM Entity Reference.
MAKENOTATION Function on page 113-127	Casts the node to a DOM Notation.
MAKEPROCESSINGINSTRUCTION Function on page 113-128	Casts the node to a DOM Processing Instruction.
MAKETEXT Function on page 113-129	Casts the node to a DOM Text.

Table 113–4 (Cont.) Summary of DOMNode Subprograms; DBMS_XMLDOM

Subprogram	Description
REMOVECHILD Function on page 113-134	Removes a specified child from a node.
REPLACECHILD Function on page 113-136	Replaces the old child with a new child.
SETNODEVALUE Procedure on page 113-143	Sets the Value of the node.
SETPREFIX Procedure on page 113-144	Sets the namespace prefix.
WRITETOBUFFER Procedures on page 113-150	Writes the contents of the node to a buffer.
WRITETOCLOB Procedures on page 113-151	Writes the contents of the node to a clob.
WRITETOFILE Procedures on page 113-152	Writes the contents of the node to a file.

DOMAttr Subprograms

Table 113–5 Summary of DOMAttr Subprograms; DBMS_XMLDOM

Method	Description
GETEXPANDEDNAME Procedure and Functions on page 113-71	Retrieves the expanded name of the attribute.
GETLOCALNAME Procedure and Functions on page 113-76	Retrieves the local name of the attribute.
GETNAME Functions on page 113-77	Retrieves the name of the attribute.
GETNAMESPACE Procedure and Functions on page 113-79	Retrieves the NS URI of the attribute.
GETOWNERELEMENT Function on page 113-88	Retrieves the Element node, parent of the attribute.
GETQUALIFIEDNAME Functions on page 113-93	Retrieves the Qualified Name of the attribute.
GETSPECIFIED Function on page 113-95	Tests if attribute was specified in the element.
GETVALUE Function on page 113-99	Retrieves the value of the attribute.
ISNULL Functions on page 113-109	Tests if the Attribute node is NULL.
MAKENODE Functions on page 113-124	Casts the Attribute to a node.
SETVALUE Procedure on page 113-146	Sets the value of the attribute.

DOMCDataSection Subprograms

Table 113–6 Summary of DOMCdata Subprograms; DBMS_XMLDOM

Method	Description
ISNULL Functions on page 113-109	Tests if the CDataSection is NULL.
MAKENODE Functions on page 113-124	Casts the CDataSection to a node.

DOMCharacterData Subprograms

Table 113–7 Summary of DOMCharacterData Subprograms; DBMS_XMLDOM

Method	Description
APPENDDATA Procedure on page 113-43	Appends the given data to the node data.
DELETEDATA Procedure on page 113-54	Deletes the data from the given offSets.
GETDATA Functions on page 113-66	Retrieves the data of the node.
GETLENGTH Functions on page 113-75	Retrieves the length of the data.
INSERTDATA Procedure on page 113-108	Inserts the data in the node at the given offSets.
ISNULL Functions on page 113-109	Tests if the CharacterData is NULL.
MAKENODE Functions on page 113-124	Casts the CharacterData to a node.
REPLACEDATA Procedure on page 113-137	Changes a range of characters in the node.
SETDATA Procedures on page 113-141	Sets the data to the node.
SUBSTRINGDATA Function on page 113-149	Retrieves the substring of the data.

DOMComment Subprograms

Table 113–8 Summary of DOMComment Subprograms; DBMS_XMLDOM

Method	Description
ISNULL Functions on page 113-109	Tests if the comment is NULL.
MAKENODE Functions on page 113-124	Casts the Comment to a node.

DOM Document Subprograms

Table 113–9 Summary of DOM Document Subprograms; DBMS_XMLDOM

Method	Description
CREATEATTRIBUTE Functions on page 113-45	Creates an Attribute.
CREATEDATASECTION Function on page 113-46	Creates a <code>CDataSection</code> node.
CREATECOMMENT Function on page 113-47	Creates a Comment node.
CREATEDOCUMENT Function on page 113-48	Creates a new Document.
CREATEDOCUMENTFRAGMENT Function on page 113-49	Creates a new Document Fragment.
CREATEELEMENT Functions on page 113-50	Creates a new Element.
CREATEENTITYREFERENCE Function on page 113-51	Creates an Entity reference.
CREATEPROCESSINGINSTRUCTION Function on page 113-52	Creates a Processing Instruction.
CREATETEXTNODE Function on page 113-53	Creates a Text node.
FREEDOCFRAG Procedure on page 113-57	Frees the document fragment.
FREEDOCUMENT Procedure on page 113-59	Frees the document.
GETDOCTYPE Function on page 113-67	Retrieves the DTD of the document.
GETDOCUMENTELEMENT Function on page 113-68	Retrieves the root element of the document.
GETELEMENTSBYTAGNAME Functions on page 113-69	Retrieves the elements in the by tag name.
GETIMPLEMENTATION Function on page 113-73	Retrieves the DOM implementation.
GETSTANDALONE Function on page 113-96	Retrieves the standalone property of the document.
GETVERSION Function on page 113-100	Retrieves the version of the document.

Table 113–9 (Cont.) Summary of DOMDocument Subprograms; DBMS_XMLDOM

Method	Description
GETXMLTYPE Function on page 113-101	Retrieves the XMLTYPE associated with the DOM Document.
ISNULL Functions on page 113-109	Tests if the document is NULL.
MAKENODE Functions on page 113-124	Casts the document to a node.
NEWDOMDOCUMENT Functions on page 113-130	Creates a new document.
SETSTANDALONE Procedure on page 113-145	Sets the charset of the document.
SETSTANDALONE Procedure on page 113-145	Sets the standalone property of the document.
SETVERSION Procedure on page 113-147	Sets the version of the document.
WRITETOBUFFER Procedures on page 113-150	Writes the document to a buffer.
WRITETOCLOB Procedures on page 113-151	Writes the document to a CLOB.
WRITETOFILE Procedures on page 113-152	Writes the document to a file.

DOMDocumentFragment Subprograms

Table 113–10 Summary of DOMDocumentFragment Subprograms; DBMS_XMLDOM

Method	Description
FREEDOCFRAG Procedure on page 113-58	Frees the specified document fragment.
ISNULL Functions on page 113-109	Tests if the DocumentFragment is <code>NULL</code> .
MAKENODE Functions on page 113-124	Casts the Document Fragment to a node.
WRITETOBUFFER Procedures on page 113-150	Writes the contents of a document fragment into a buffer.

DOMDocumentType Subprograms

Table 113–11 Summary of DOMDocumentType Subprograms; DBMS_XMLDOM

Method	Description
FINDENTITY Function on page 113-55	Finds the specified entity in the document type.
FINDNOTATION Function on page 113-56	Finds the specified notation in the document type.
GETENTITIES Function on page 113-70	Retrieves the nodemap of entities in the Document type.
GETNAME Functions on page 113-77	Retrieves the name of the Document type.
GETNOTATIONS Function on page 113-85	Retrieves the nodemap of the notations in the Document type.
GETPUBLICID Functions on page 113-92	Retrieves the public ID of the document type.
GETSYSTEMID Functions on page 113-97	Retrieves the system ID of the document type.
ISNULL Functions on page 113-109	Tests if the Document Type is <code>NULL</code> .
MAKENODE Functions on page 113-124	Casts the document type to a node.

DOMElement Subprograms

Table 113–12 Summary of DOMElement Subprograms; DBMS_XMLDOM

Method	Description
GETATTRIBUTE Functions on page 113-61	Retrieves the attribute node by name.
GETATTRIBUTENODE Functions on page 113-63	Retrieves the attribute node by name.
GETCHILDRENBYTAGNAME Functions on page 113-65	Retrieves children of the element by tag name.
GETELEMENTSBYTAGNAME Functions on page 113-69	Retrieves elements in the subtree by tagname.
GETEXPANDEDNAME Procedure and Functions on page 113-71	Retrieves the expanded name of the element.
GETLOCALNAME Procedure and Functions on page 113-76	Retrieves the local name of the element.
GETNAMESPACE Procedure and Functions on page 113-79	Retrieves the NS URI of the element.
GETQUALIFIEDNAME Functions on page 113-93	Retrieves the qualified name of the element.
GETTAGNAME Function on page 113-98	Retrieves the Tag name of the element.
HASATTRIBUTE Functions on page 113-102	Tests if an attribute exists .
ISNULL Functions on page 113-109	Tests if the Element is NULL .
MAKENODE Functions on page 113-124	Casts the Element to a node.
NORMALIZE Procedure on page 113-131	Normalizes the text children of the element.
REMOVEATTRIBUTE Procedures on page 113-132	Removes the attribute specified by the name.
REMOVEATTRIBUTENODE Function on page 113-133	Removes the attribute node in the element.
RESOLVENAMESPACEPREFIX Function on page 113-138	Resolve the prefix to a namespace URI.
SETATTRIBUTE Procedures on page 113-139	Sets the attribute specified by the name.
SETATTRIBUTENODE Functions on page 113-140	Sets the attribute node in the element.

DOMEntity Subprograms

Table 113–13 *Summary of DOMEntity Subprograms; DBMS_XMLDOM*

Method	Description
GETNOTATIONNAME Function on page 113-84	Retrieves the notation name of the entity.
GETPUBLICID Functions on page 113-92	Retrieves the public Id of the entity.
GETSYSTEMID Functions on page 113-97	Retrieves the system Id of the entity.
ISNULL Functions on page 113-109	Tests if the Entity is NULL.
MAKENODE Functions on page 113-124	Casts the Entity to a node.

DOMEntityReference Subprograms

Table 113–14 Summary of DOMEntityReference Subprograms; DBMS_XMLDOM

Method	Description
ISNULL Functions on page 113-109	Tests if the DOMEntityReference is NULL.
MAKENODE Functions on page 113-124	Casts the DOMEntityReference to NULL.

DOMImplementation Subprograms

Table 113–15 *Summary of DOMImplementation Subprograms; DBMS_XMLDOM*

Method	Description
ISNULL Functions on page 113-109	Tests if the DOMImplementation node is NULL.
HASFEATURE Function on page 113-105	Tests if the DOMImplementation implements a feature.

DOMNamedNodeMap Subprograms

Table 113–16 Summary of DOMNamedNodeMap Subprograms; DBMS_XMLDOM

Method	Description
GETLENGTH Functions on page 113-75	Retrieves the number of items in the map.
GETNAMEDITEM Function on page 113-78	Retrieves the item specified by the name.
ISNULL Functions on page 113-109	Tests if the NamedNodeMap is NULL.
ITEM Functions on page 113-113	Retrieves the item given the index in the map.
REMOVENAMEDITEM Function on page 113-135	Removes the item specified by name.
SETNAMEDITEM Function on page 113-142	Sets the item in the map specified by the name.

DOMNodeList Subprograms

Table 113–17 *Summary of DOMNodeList Subprograms; DBMS_XMLDOM*

Method	Description
GETLENGTH Functions on page 113-75	Retrieves the number of items in the list.
ISNULL Functions on page 113-109	Tests if the <code>NodeList</code> is <code>NULL</code> .
ITEM Functions on page 113-113	Retrieves the item given the index in the <code>NodeList</code> .

DOMNotation Subprograms

Table 113–18 Summary of DOMNotation Subprograms; DBMS_XMLDOM

Method	Description
GETPUBLICID Functions on page 113-92	Retrieves the public Id of the notation.
GETSYSTEMID Functions on page 113-97	Retrieves the system Id of the notation.
ISNULL Functions on page 113-109	Tests if the Notation is NULL .
MAKENODE Functions on page 113-124	Casts the notation to a node.

DOMProcessingInstruction Subprograms

Table 113–19 Summary of *DOMProcessingInstruction* Subprograms; *DBMS_XMLDOM*

Method	Description
GETDATA Functions on page 113-66	Retrieves the data of the processing instruction.
GETTARGET Function on page 113-86	Retrieves the target of the processing instruction.
ISNULL Functions on page 113-109	Tests if the Processing Instruction is <code>NULL</code> .
MAKENODE Functions on page 113-124	Casts the Processing Instruction to a node.
SETDATA Procedures on page 113-141	Sets the data of the processing instruction.

DOMText Subprograms

Table 113–20 Summary of DOMText Subprograms; DBMS_XMLDOM

Method	Description
ISNULL Functions on page 113-109	Tests if the text is NULL .
MAKENODE Functions on page 113-124	Casts the text to a node.
SPLITTEXT Function on page 113-148	Splits the contents of the text node into 2 text nodes.

Summary of DBMS_XMLDOM Subprograms

Table 113–21 Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
ADOPTNODE Procedure on page 113-41	Adopts a node from another document (see DOMNode Subprograms on page 113-8)
APPENDCHILD Function on page 113-42	Appends a new child to the node (see DOMNode Subprograms on page 113-8)
APPENDDATA Procedure on page 113-43	Appends the given data to the node data (see DOMCharacterData Subprograms on page 113-13)
CLONENODE Function on page 113-44	Clones the node (see DOMNode Subprograms on page 113-8)
CREATEATTRIBUTE Functions on page 113-45	Creates an Attribute (see DOMDocument Subprograms on page 113-15)
CREATECDATASECTION Function on page 113-46	Creates a <code>CDataSection</code> node (see DOMDocument Subprograms on page 113-15)
CREATECOMMENT Function on page 113-47	Creates a Comment node (see DOMDocument Subprograms on page 113-15)
CREATEDOCUMENT Function on page 113-48	Creates a new Document (see DOMDocument Subprograms on page 113-15)
CREATEDOCUMENTFRAGMENT Function on page 113-49	Creates a new Document Fragment (see DOMDocument Subprograms on page 113-15)
CREATEELEMENT Functions on page 113-50	Creates a new Element (see DOMDocument Subprograms on page 113-15)
CREATEENTITYREFERENCE Function on page 113-51	Creates an Entity reference (see DOMDocument Subprograms on page 113-15)
CREATEPROCESSINGINSTRUCTION Function on page 113-52	Creates a Processing Instruction (see DOMDocument Subprograms on page 113-15)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
CREATETEXTNODE Function on page 113-53	Creates a Text node (see DOMDocument Subprograms on page 113-15)
DELETEDATA Procedure on page 113-54	Deletes the data from the given offSets (see DOMCharacterData Subprograms on page 113-13)
FINDENTITY Function on page 113-55	Finds the specified entity in the document type (see DOMDocumentType Subprograms on page 113-18)
FINDNOTATION Function on page 113-56	Finds the specified notation in the document type (see DOMDocumentType Subprograms on page 113-18)
FREEDOCFRAG Procedure on page 113-57	Frees the document fragment (see DOMDocument Subprograms on page 113-15)
FREEDOCFRAG Procedure on page 113-58	Frees the specified document fragment (see DOMDocumentFragment Subprograms on page 113-17)
FREEDOCUMENT Procedure on page 113-59	Frees the document (see DOMDocument Subprograms on page 113-15)
FREENODE Procedure on page 113-60	Frees all resources associated with the node (see DOMNode Subprograms on page 113-8).
GETATTRIBUTE Functions on page 113-61	Retrieves the attribute node by name (see DOMElement Subprograms on page 113-19)
GETATTRIBUTES Function on page 113-62	Retrieves the attributes of the node (see DOMNode Subprograms on page 113-8)
GETATTRIBUTENODE Functions on page 113-63	Retrieves the attribute node by name (see DOMElement Subprograms on page 113-19)
GETCHILDNODES Function on page 113-64	Retrieves the children of the node (see DOMNode Subprograms on page 113-8)
GETCHILDRENBYTAGNAME Functions on page 113-65	Retrieves children of the element by tag name (see DOMCharacterData Subprograms on page 113-13)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
GETDATA Functions on page 113-66	Retrieves <ul style="list-style-type: none"> ▪ the data of the node (see DOMCharacterData Subprograms on page 113-13) ▪ the data of the processing instruction (see DOMProcessingInstruction Subprograms on page 113-26)
GETDOCTYPE Function on page 113-67	Retrieves the DTD of the document (see DOMDocument Subprograms on page 113-15)
GETDOCUMENTELEMENT Function on page 113-68	Retrieves the root element of the document (see DOMDocument Subprograms on page 113-15)
GETELEMENTSBYTAGNAME Functions on page 113-69	Retrieves <ul style="list-style-type: none"> ▪ the elements in the by tag name (see DOMDocument Subprograms on page 113-15) ▪ elements in the subtree by tagname (see DOMElement Subprograms on page 113-19)
GETENTITIES Function on page 113-70	Retrieves the nodemap of entities in the Document type (see DOMDocumentType Subprograms on page 113-18)
GETEXPANDEDNAME Procedure and Functions on page 113-71	Retrieves <ul style="list-style-type: none"> ▪ the expanded name of the node (see DOMNode Subprograms on page 113-8) ▪ the expanded name of the attribute (see DOMAttr Subprograms on page 113-11) ▪ the expanded name of the element (DOMElement Subprograms on page 113-19)
GETFIRSTCHILD Function on page 113-72	Retrieves the first child of the node (see DOMNode Subprograms on page 113-8)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
GETIMPLEMENTATION Function on page 113-73	Retrieves the DOM implementation (DOMDocument Subprograms on page 113-15)
GETLASTCHILD Function on page 113-74	Retrieves the last child of the node (see DOMNode Subprograms on page 113-8)
GETLENGTH Functions on page 113-75	Retrieves <ul style="list-style-type: none"> <li data-bbox="815 522 1300 609">▪ the length of the data (see DOMCharacterData Subprograms on page 113-13) <li data-bbox="815 618 1300 704">▪ the number of items in the map (see DOMNamedNodeMap Subprograms on page 113-23) <li data-bbox="815 713 1300 800">▪ the number of items in the list (see DOMNodeList Subprograms on page 113-24)
GETLOCALNAME Procedure and Functions on page 113-76	Retrieves <ul style="list-style-type: none"> <li data-bbox="815 864 1279 951">▪ the local part of the qualified name (see DOMNode Subprograms on page 113-8) <li data-bbox="815 960 1279 1046">▪ the local name of the attribute (see DOMAttr Subprograms on page 113-11) <li data-bbox="815 1055 1279 1142">▪ the local name of the element (see DOMElement Subprograms on page 113-19)
GETNAME Functions on page 113-77	Retrieves <ul style="list-style-type: none"> <li data-bbox="815 1206 1315 1260">▪ the name of the attribute (see DOMAttr Subprograms on page 113-11) <li data-bbox="815 1269 1315 1361">▪ the name of the Document type (DOMDocumentType Subprograms on page 113-18)

Table 113-21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
GETNAMEDITEM Function on page 113-78	Retrieves <ul style="list-style-type: none"> an item specified by name (see DOMNamedNodeMap Subprograms on page 113-23) an item specified by name and namespace URI (see DOMNamedNodeMap Subprograms on page 113-23)
GETNAMESPACE Procedure and Functions on page 113-79	Retrieves <ul style="list-style-type: none"> the node's namespace URI (see DOMNode Subprograms on page 113-8) the NS URI of the attribute (see DOMAttr Subprograms on page 113-11) the NS URI of the element (see DOMELEMENT Subprograms on page 113-19)
GETNEXTSIBLING Function on page 113-80	Retrieves the next sibling of the node (see DOMNode Subprograms on page 113-8)
GETNODENAME Function on page 113-81	Retrieves the Name of the Node (see DOMNode Subprograms on page 113-8)
GETNODETYPE Function on page 113-82	Retrieves the Type of the node (see DOMNode Subprograms on page 113-8)
GETNODEVALUE Function on page 113-83	Retrieves the Value of the Node (see DOMNode Subprograms on page 113-8)
GETNOTATIONNAME Function on page 113-84	Retrieves the notation name of the entity (see DOMEntity Subprograms on page 113-20)
GETNOTATIONS Function on page 113-85	Retrieves the nodemap of the notations in the Document type (see DOMDocumentType Subprograms on page 113-18)
GETTARGET Function on page 113-86	Retrieves the target of the processing instruction (see DOMProcessingInstruction Subprograms on page 113-26)
GETOWNERDOCUMENT Function on page 113-87	Retrieves the owner document of the node (see DOMNode Subprograms on page 113-8)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
GETOWNERELEMENT Function on page 113-88	Retrieves the Element node, parent of the attribute (see DOMAttr Subprograms on page 113-11)
GETPARENTNODE Function on page 113-89	Retrieves the parent of this node (see DOMNode Subprograms on page 113-8)
GETPREFIX Function on page 113-90	Retrieves the namespace prefix (see DOMNode Subprograms on page 113-8)
GETPREVIOUSIBLING Function on page 113-91	Retrieves the previous sibling of the node (see DOMNode Subprograms on page 113-8)
GETPUBLICID Functions on page 113-92	Retrieves <ul style="list-style-type: none"> <li data-bbox="815 670 1312 753">▪ the public ID of the document type (see DOMDocumentType Subprograms on page 113-18) <li data-bbox="815 774 1312 828">▪ the public Id of the entity (see DOMEntity Subprograms on page 113-20) <li data-bbox="815 848 1236 925">▪ the public Id of the notation (see DOMNotation Subprograms on page 113-25)
GETQUALIFIEDNAME Functions on page 113-93	Retrieves <ul style="list-style-type: none"> <li data-bbox="815 987 1283 1071">▪ the Qualified Name of the attribute (see DOMAttr Subprograms on page 113-11) <li data-bbox="815 1091 1265 1168">▪ the qualified name of the element (see DOMELEMENT Subprograms on page 113-19)
GETSCHEMANODE Function on page 113-94	Retrieves the associated schema URI (see DOMNode Subprograms on page 113-8)
GETSPECIFIED Function on page 113-95	Tests if attribute was specified in the element. (see DOMAttr Subprograms on page 113-11)
GETSTANDALONE Function on page 113-96	Retrieves the standalone property of the document (see DOMDocument Subprograms on page 113-15)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
GETSYSTEMID Functions on page 113-97	Retrieves <ul style="list-style-type: none"> ▪ the system ID of the document type (see DOMDocumentType Subprograms on page 113-18) ▪ the system Id of the entity (see DOMEntity Subprograms on page 113-20) ▪ the system Id of the notation (DOMNotation Subprograms on page 113-25)
GETTAGNAME Function on page 113-98	Retrieves the Tag name of the element (see DOMElement Subprograms on page 113-19)
GETVALUE Function on page 113-99	Retrieves the value of the attribute (see DOMAttr Subprograms on page 113-11)
GETVERSION Function on page 113-100	Retrieves the version of the document (DOMDocument Subprograms on page 113-15)
GETXMLTYPE Function on page 113-101	Retrieves the XMLType associated with the DOM Document (see DOMDocument Subprograms on page 113-15)
HASATTRIBUTES Function on page 113-103	Tests if the node has attributes (see DOMNode Subprograms on page 113-8)
HASATTRIBUTE Functions on page 113-102	Tests if an attribute exists (see DOMElement Subprograms on page 113-19)
HASCHILDNODES Function on page 113-104	Tests if the node has child nodes (see DOMNode Subprograms on page 113-8)
HASFEATURE Function on page 113-105	Tests if the DOMImplementation implements a feature (see DOMImplementation Subprograms on page 113-22)
IMPORTNODE Function on page 113-106	Imports a node from another document (see DOMNode Subprograms on page 113-8)
INSERTBEFORE Function on page 113-107	Inserts a child before the reference child (see DOMNode Subprograms on page 113-8)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
INSERTDATA Procedure on page 113-108	Inserts the data in the node at the given offSets (see DOMCharacterData Subprograms on page 113-13)
ISNULL Functions on page 113-109	<p data-bbox="815 406 868 428">Tests</p> <ul style="list-style-type: none"> <li data-bbox="815 447 1248 501">▪ if the node is NULL (see DOMNode Subprograms on page 113-8) <li data-bbox="815 520 1219 602">▪ if the Attribute node is NULL (see DOMAttr Subprograms on page 113-11) <li data-bbox="815 621 1290 703">▪ if the CDataSection is NULL (see DOMCDataSection Subprograms on page 113-12) <li data-bbox="815 722 1315 803">▪ if the CharacterData is NULL (DOMCharacterData Subprograms on page 113-13) <li data-bbox="815 822 1248 904">▪ if the comment is NULL (see DOMComment Subprograms on page 113-14) <li data-bbox="815 923 1253 1005">▪ if the document is NULL (see DOMDocument Subprograms on page 113-15) <li data-bbox="815 1024 1268 1105">▪ if the DocumentFragment is NULL (see DOMDocumentFragment Subprograms on page 113-17) <li data-bbox="815 1124 1308 1206">▪ if the Document Type is NULL (see DOMDocumentType Subprograms on page 113-18) <li data-bbox="815 1225 1208 1279">▪ if the Element is NULL (see DOMELEMENT Subprograms on page 113-19) <li data-bbox="815 1298 1265 1380">▪ if the Entity is NULL (see DOMEntity Subprograms on page 113-20) <li data-bbox="815 1399 1315 1480">▪ if the DOMEntityReference is NULL (see DOMEntityReference Subprograms) <li data-bbox="815 1499 1315 1508">▪ if the DOMImplementation node is NULL (see DOMImplementation Subprograms on page 113-22)

Table 113-21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
ISNULL Functions on page 113-109 (contd.)	Tests <ul style="list-style-type: none"> ▪ if the <code>NamedNodeMap</code> is NULL (see DOMNamedNodeMap Subprograms on page 113-23) ▪ if the <code>NodeList</code> is NULL (see DOMNodeList Subprograms on page 113-24) ▪ if the <code>Notation</code> is NULL (see DOMNotation Subprograms on page 113-25) ▪ if the <code>Processing Instruction</code> is NULL (DOMProcessingInstruction Subprograms on page 113-26) ▪ if the <code>text</code> is NULL (see DOMText Subprograms on page 113-27)
IITEM Functions on page 113-113	Retrieves <ul style="list-style-type: none"> ▪ the item given the index in the map (see DOMNamedNodeMap Subprograms on page 113-23) ▪ the item given the index in the <code>NodeList</code> (see DOMNodeList Subprograms on page 113-24)
MAKEATTR Function on page 113-114	Casts the node to an Attribute (see DOMNode Subprograms on page 113-8)
MAKECDATASECTION Function on page 113-115	Casts the node to a CData Section (see DOMNode Subprograms on page 113-8)
MAKECHARACTERDATA Function on page 113-116	Casts the node to Character Data (see DOMNode Subprograms on page 113-8)
MAKECOMMENT Function on page 113-117	Casts the node to a Comment (see DOMNode Subprograms on page 113-8)
MAKEDOCUMENT Function on page 113-118	Casts the node to a DOM Document (see DOMNode Subprograms on page 113-8)
MAKEDOCUMENTFRAGMENT Function on page 113-119	Casts the node to a DOM Document Fragment (see DOMNode Subprograms on page 113-8)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
MAKEDOCUMENTTYPE Function on page 113-120	Casts the node to a DOM Document Type (see DOMNode Subprograms on page 113-8)
MAKEELEMENT Function on page 113-121	Casts the node to a DOM Element (see DOMNode Subprograms on page 113-8)
MAKEENTITY Function on page 113-122	Casts the node to a DOM Entity (see DOMNode Subprograms on page 113-8)
MAKEENTITYREFERENCE Function on page 113-123	Casts the node to a DOM Entity Reference (see DOMNode Subprograms on page 113-8)
MAKENODE Functions on page 113-124	Casts <ul style="list-style-type: none"> <li data-bbox="815 644 1272 697">▪ the Attribute to a node (see DOMAttr Subprograms on page 113-11) <li data-bbox="815 718 1286 800">▪ the CDatasection to a node (see DOMCDataSection Subprograms on page 113-12) <li data-bbox="815 821 1300 902">▪ the CharacterData to a node (see DOMCharacterData Subprograms on page 113-13) <li data-bbox="815 923 1243 1005">▪ the Comment to a node (see DOMComment Subprograms on page 113-14) <li data-bbox="815 1025 1243 1107">▪ the document to a node (see DOMDocument Subprograms on page 15) <li data-bbox="815 1128 1272 1209">▪ the Document Fragment to a node (see DOMDocumentFragment Subprograms on page 113-17) <li data-bbox="815 1230 1308 1312">▪ the document type to a node (see DOMDocumentType Subprograms on page 113-18) <li data-bbox="815 1333 1308 1414">▪ the Element to a node (see DOMElement Subprograms on page 113-19) <li data-bbox="815 1435 1258 1489">▪ the Entity to a node (see DOMEntity Subprograms on page 113-20)

Table 113-21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
MAKENODE Functions on page 113-124 (contd.)	Casts <ul style="list-style-type: none"> ▪ the <code>DOMEntityReference</code> to NULL (see DOMEntityReference Subprograms on page 113-21) ▪ the notation to a node (see DOMNotation Subprograms on page 113-25) ▪ the Processing Instruction to a node (see DOMProcessingInstruction Subprograms on page 113-26) ▪ the text to a node (see DOMText Subprograms on page 113-27)
MAKENOTATION Function on page 113-127	Casts the node to a DOM Notation (see DOMNode Subprograms on page 113-8)
MAKEPROCESSINGINSTRUCTION Function on page 113-128	Casts the node to a DOM Processing Instruction (see DOMNode Subprograms on page 113-8)
MAKETEXT Function on page 113-129	Casts the node to a DOM Text (see DOMNode Subprograms on page 113-8)
NEWDOMDOCUMENT Functions on page 113-130	Creates a new document (see DOMDocument Subprograms on page 113-15)
NORMALIZE Procedure on page 113-131	Normalizes the text children of the element (see DOMELEMENT Subprograms on page 113-19)
REMOVEATTRIBUTE Procedures on page 113-132	Removes the attribute specified by the name (see DOMELEMENT Subprograms on page 113-19)
REMOVEATTRIBUTENODE Function on page 113-133	Removes the attribute node in the element (see DOMELEMENT Subprograms on page 113-19)
REMOVECHILD Function on page 113-134	Removes a specified child from a node (see DOMNode Subprograms on page 113-8)
REMOVENAMEDITEM Function on page 113-135	Removes the item specified by name (see DOMNamedNodeMap Subprograms on page 113-23)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
REPLACECHILD Function on page 113-136	Replaces the old child with a new child (see DOMNode Subprograms on page 113-8)
REPLACEDATA Procedure on page 113-137	Changes a range of characters in the node (see DOMCharacterData Subprograms on page 113-13)
RESOLVENAMESPACEPREFIX Function on page 113-138	Resolve the prefix to a namespace URI (see DOMELEMENT Subprograms on page 113-19)
SETATTRIBUTE Procedures on page 113-139	Sets the attribute specified by the name (see DOMELEMENT Subprograms on page 113-19)
SETATTRIBUTENODE Functions on page 113-140	Sets the attribute node in the element (see DOMELEMENT Subprograms on page 113-19)
SETDATA Procedures on page 113-141	Sets <ul style="list-style-type: none"> ▪ the data to the node (see DOMCharacterData Subprograms on page 113-13) ▪ the data of the processing instruction (see DOMProcessingInstruction Subprograms on page 113-26))
SETNAMEDITEM Function on page 113-142	Sets the item in the map specified by the name (see DOMNamedNodeMap Subprograms on page 113-23)
SETNODEVALUE Procedure on page 113-143	Sets the Value of the node (see DOMNode Subprograms on page 113-8)
SETPREFIX Procedure on page 113-144	Sets the namespace prefix (see DOMNode Subprograms on page 113-8)
SETSTANDALONE Procedure on page 113-145	Sets the standalone property of the document (see DOMDocument Subprograms on page 113-15)
SETVALUE Procedure on page 113-146	Sets the value of the attribute (see DOMAttr Subprograms on page 113-11)

Table 113–21 (Cont.) Summary of DBMS_XMLDOM Package Subprogram

Subprogram	Description
SETVERSION Procedure on page 113-147	Sets the version of the document (see DOMDocument Subprograms on page 113-15)
SPLITTEXT Function on page 113-148	Splits the contents of the text node into 2 text nodes (see DOMText Subprograms on page 113-27)
SUBSTRINGDATA Function on page 113-149	Retrieves the substring of the data (DOMCharacterData Subprograms on page 113-13)
WRITETOBUFFER Procedures on page 113-150	Writes <ul style="list-style-type: none">the contents of the node to a buffer (see DOMNode Subprograms on page 113-8)the document to a buffer (see DOMDocument Subprograms on page 113-15)the contents of a document fragment into a buffer (see DOMDocumentFragment Subprograms on page 113-17)
WRITETOCLOB Procedures on page 113-151	Writes <ul style="list-style-type: none">the contents of the node to a CLOB (see DOMNode Subprograms on page 113-8)the document to a CLOB (see DOMDocument Subprograms on page 113-15)
WRITETOFILE Procedures on page 113-152	Writes <ul style="list-style-type: none">the contents of the node to a file (see DOMNode Subprograms on page 113-8)the document to a file (see DOMDocument Subprograms on page 113-15)

ADOPTNODE Procedure

This procedure adopts a node from another document; returns this new node.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.ADOPTNODE(  
    doc          IN  DOMDocument ,  
    importedNode IN  DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–22 *ADOPTNODE Function Parameters*

Parameter	Description
doc	Document that is adopting the node.
importedNode	Node to adopt.

APPENDCHILD Function

This function adds the node `NEWCHILD` to the end of the list of children of this node, and returns the newly added node. If the `NEWCHILD` is already in the tree, it is first removed.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.APPENDCHILD(  
    n           IN     DOMNode,  
    newChild   IN     DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–23 *APPENDCHILD Function Parameters*

Parameter	Description
<code>n</code>	<code>DOMNode</code> .
<code>newChild</code>	The child to be appended to the list of children of node <code>n</code> .

APPENDDATA Procedure

This procedure appends the string to the end of the character data of the node. Upon success, data provides access to the concatenation of data and the specified string argument.

See Also: [DOMCharacterData Subprograms](#) on page 113-13

Syntax

```
DBMS_XMLDOM.APPENDDATA(  
    cd      IN      DOMCharacterData,  
    arg     IN      VARCHAR2);
```

Parameters

Table 113–24 APPENDDATA Procedure Parameters

Parameter	Description
cd	DOMCharacterData.
arg	The data to append to the existing data.

CLONENODE Function

This function returns a duplicate of this node; serves as a generic copy constructor for nodes. The duplicate node has no parent; its parent node is `NULL`.

Cloning an Element copies all attributes and their values, including those generated by the XML processor to represent defaulted attributes, but this method does not copy any text it contains unless it is a deep clone, since the text is contained in a child Text node. Cloning an Attribute directly, as opposed to be cloned as part of an Element cloning operation, returns a specified attribute (specified is `TRUE`). Cloning any other type of node simply returns a copy of this node.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.CLONENODE(  
    n          IN    DOMNode,  
    deep      IN    BOOLEAN)  
RETURN DOMNode;
```

Parameters

Table 113–25 CLONENODE Function Parameters

Parameter	Description
n	DOMNode .
deep	Determines if children are to be cloned.

CREATEATTRIBUTE Functions

This function creates a `DOMAttr` node.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

Creates a `DOMAttr` with the specified name:

```
DBMS_XMLDOM.CREATEATTRIBUTE(  
    doc      IN   DOMDocument,  
    name     IN   VARCHAR2)  
RETURN DOMAttr;
```

Creates a `DOMAttr` with the specified name and namespace URI:

```
DBMS_XMLDOM.CREATEATTRIBUTE(  
    doc      IN   DOMDocument,  
    name     IN   VARCHAR2,  
    ns       IN   VARCHAR2)  
RETURN DOMAttr;
```

Parameters

Table 113–26 *CREATEATTRIBUTE Function Parameters*

Parameter	Description
<code>doc</code>	<code>DOMDocument</code> .
<code>name</code>	New attribute name.
<code>ns</code>	Namespace.

CREATECDATASECTION Function

This function creates a `DOMCDATASection` node.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.CREATECDATASECTION(  
    doc      IN      DOMDocument,  
    data     IN      VARCHAR2)  
RETURN DOMCDATASection;
```

Parameters

Table 113–27 *CREATECDATASECTION Function Parameters*

Parameter	Description
<code>doc</code>	DOMDocument.
<code>data</code>	Content of the <code>DOMCDATASection</code> node.

CREATECOMMENT Function

This function creates a DOMComment node.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.CREATECOMMENT(  
    doc      IN      DOMDocument,  
    data     IN      VARCHAR2)  
RETURN DOMComment;
```

Parameters

Table 113–28 *CREATECOMMENT Function Parameters*

Parameter	Description
doc	DOMDocument.
data	Content of the DOMComment node.

CREATEDOCUMENT Function

This function creates a `DOMDocument` with specified namespace URI, root element name, DTD.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.CREATEDOCUMENT(  
    namespaceURI    IN    VARCHAR2,  
    qualifiedName   IN    VARCHAR2,  
    doctype         IN    DOMType:=NULL)  
RETURN DOMDocument;
```

Parameters

Table 113–29 *CREATEDOCUMENT Function Parameters*

Parameter	Description
<code>namespaceURI</code>	Namespace URI.
<code>qualifiedName</code>	Root element name.
<code>doctype</code>	Document type.

CREATEDOCUMENTFRAGMENT Function

This function creates a `DOMDocumentFragment`.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.CREATEDOCUMENTFRAGMENT(  
    doc      IN      DOMDocument)  
RETURN DOMDocumentFragment;
```

Parameters

Table 113–30 *CREATEDOCUMENTFRAGMENT Function Parameters*

Parameter	Description
doc	DOMDocument.

CREATEELEMENT Functions

Creates a DOMELEMENT.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

Creates a DOMELEMENT with specified name:

```
DBMS_XMLDOM.CREATEELEMENT(  
    doc          IN      DOMDocument,  
    tagName     IN      VARCHAR2)  
RETURN DOMELEMENT;
```

Creates a DOMELEMENT with specified name and namespace URI:

```
DBMS_XMLDOM.CREATEELEMENT(  
    doc          IN      DOMDocument,  
    tagName     IN      VARCHAR2,  
    ns          IN      VARCHAR2)  
RETURN DOMELEMENT;
```

Parameters

Table 113–31 CREATEELEMENT Function Parameters

Parameter	Description
doc	DOMDocument.
tagName	Tagname for new DOMELEMENT.
ns	Namespace.

CREATEENTITYREFERENCE Function

This function creates a `DOMEntityReference` node.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.CREATEENTITYREFERENCE (  
    doc          IN      DOMDocument,  
    name        IN      VARCHAR2)  
RETURN DOMEntityReference;
```

Parameters

Table 113–32 *CREATEENTITYREFERENCE Function Parameters*

Parameter	Description
doc	DOMDocument.
name	New entity reference name.

CREATEPROCESSINGINSTRUCTION Function

This function creates a `DOMProcessingInstruction` node.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.CREATEPROCESSINGINSTRUCTION(  
    doc          IN          DOMDocument ,  
    target       IN          VARCHAR2 ,  
    data         IN          VARCHAR2 )  
RETURN DOMProcessingInstruction;
```

Parameters

Table 113–33 *CREATEPROCESSINGINSTRUCTION Function Parameters*

Parameter	Description
<code>doc</code>	<code>DOMDocument</code> .
<code>target</code>	Target of the new processing instruction.
<code>data</code>	Content data of the new processing instruction.

CREATETEXTNODE Function

This function creates a DOMText node.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.CREATETEXTNODE(  
    doc      IN      DOMDocument,  
    data     IN      VARCHAR2)  
RETURN DOMText;
```

Parameters

Table 113–34 *CREATETEXTNODE Function Parameters*

Parameter	Description
doc	DOMDocument.
data	Content of the DOMText node.

DELETEDATA Procedure

This procedure removes a range of characters from the node. Upon success, data and length reflect the change.

See Also: [DOMCharacterData Subprograms](#) on page 113-13

Syntax

```
DBMS_XMLDOM.DELETEDATA(  
    cd          IN      DOMCharacterData,  
    offset     IN      NUMBER,  
    cnt        IN      NUMBER);
```

Parameters

Table 113–35 DELETEDATA PROCEDURE Parameters

Parameter	Description
cd	DOMCharacterData.
offset	The offset from which to delete the data.
cnt	The number of characters (starting from offset) to delete.

FINDENTITY Function

This function finds an entity in the given DTD; returns that entity if found.

See Also: [DOMDocumentType Subprograms](#) on page 113-18

Syntax

```
DBMS_XMLDOM.FINDENTITY(  
    dt      IN      DOMDocumentType,  
    name   IN      VARCHAR2,  
    par    IN      BOOLEAN)  
RETURN DOMEntity;
```

Parameters

Table 113–36 *FINDENTITY Function Parameters*

Parameter	Description
dt	The DTD.
name	Entity to find.
par	Flag to indicate type of entity; TRUE for parameter entity and FALSE for normal entity.

FINDNOTATION Function

This function finds the notation in the given DTD; returns it, if found.

See Also: [DOMDocumentType Subprograms](#) on page 113-18

Syntax

```
DBMS_XMLDOM.FINDNOTATION(  
    dt          IN      DOMDocumentType,  
    name       IN      VARCHAR2)  
RETURN DOMNotation;
```

Parameters

Table 113–37 *FINDNOTATION Function Parameters*

Parameter	Description
dt	The DTD.
name	The notation to find.

FREEDOCFRAG Procedure

This procedure frees the specified document fragment.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.FREEDOCFRAG(  
    df      IN      DOMDocumentFragment);
```

Parameters

Table 113–38 *FREEDOCFRAG Procedure Parameters*

Parameter	Description
df	DOM document fragment.

FREEDOCFRAG Procedure

This procedure frees the specified document fragment.

See Also: [DOMDocumentFragment Subprograms](#) on page 113-17

Syntax

```
DBMS_XMLDOM.FREEDOCFRAG(  
    df      IN  DOMDocumentFragment);
```

Parameters

Table 113–39 *FREEDOCFRAG Procedure Parameters*

Parameter	Description
df	DOM document fragment.

FREEDOCUMENT Procedure

This procedure frees `DOMDocument` object.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.FREEDOCUMENT(  
    doc      IN      DOMDocument);
```

Parameters

Table 113–40 *FREEDOCUMENT Procedure Parameters*

Parameter	Description
<code>doc</code>	<code>DOMDocument</code> .

FREENODE Procedure

This procedure frees all resources associated with a Node.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.FREENODE(
    n          IN          DOMNode);
```

Parameters

Table 113–41 *FREENODE Procedure Parameters*

Parameter	Description
n	DOMNode.

GETATTRIBUTE Functions

Returns the value of a DOMELEMENT's attribute by name.

See Also: [DOMELEMENT Subprograms](#) on page 113-19

Syntax

Returns the value of a DOMELEMENT's attribute by name:

```
DBMS_XMLDOM.GETATTRIBUTE (
    elem      IN      DOMELEMENT,
    name      IN      VARCHAR2)
RETURN VARCHAR2;
```

Returns the value of a DOMELEMENT's attribute by name and namespace URI:

```
DBMS_XMLDOM.GETATTRIBUTE (
    elem      IN      DOMELEMENT,
    name      IN      VARCHAR2,
    ns        IN      VARCHAR2)
RETURN VARCHAR2;
```

Parameters

Table 113–42 *GETATTRIBUTE Function Parameters*

Parameter	Description
elem	The DOMELEMENT.
name	Attribute name.
ns	Namespace.

GETATTRIBUTES Function

This function retrieves a `NamedNodeMap` containing the attributes of this node (if it is an `Element`) or `NULL` otherwise.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETATTRIBUTES(  
    n          IN          DOMNode)  
RETURN DOMNamedNodeMap;
```

Parameters

Table 113–43 *GETATTRIBUTES Function Parameters*

Parameter	Description
n	DOMNode.

GETATTRIBUTENODE Functions

Returns an attribute node from the `DOMElement` by name.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

Returns an attribute node from the `DOMElement` by name:

```
DBMS_XMLDOM.GETATTRIBUTENODE(
    elem      IN      DOMElement,
    name      IN      VARCHAR2)
RETURN DOMAttr;
```

Returns an attribute node from the `DOMElement` by name and namespace URI:

```
DBMS_XMLDOM.GETATTRIBUTENODE(
    elem      IN      DOMElement,
    name      IN      VARCHAR2,
    ns        IN      VARCHAR2)
RETURN DOMAttr;
```

Parameters

Table 113–44 *GETATTRIBUTENODE Function Parameters*

Parameter	Description
<code>elem</code>	The <code>DOMElement</code> .
<code>name</code>	Attribute name; * matches any attribute.
<code>ns</code>	Namespace.

GETCHILDNODES Function

This function retrieves a `NodeList` that contains all children of this node. If there are no children, this is a `NodeList` containing no nodes.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETCHILDNODES(  
    n          IN  DOMNode)  
RETURN DOMNodeList;
```

Parameters

Table 113–45 *GETCHILDNODES Function Parameters*

Parameter	Description
n	DOMNode.

GETCHILDRENBYTAGNAME Functions

Returns the children of the `DOMElement`.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

Returns children of the `DOMElement` given the tag name:

```
DBMS_XMLDOM.GETCHILDRENBYTAGNAME(
    elem      IN      DOMElement,
    name      IN      VARCHAR2)
RETURN DOMNodeList;
```

Returns children of the `DOMElement` given the tag name and namespace:

```
DBMS_XMLDOM.GETCHILDRENBYTAGNAME(
    elem      IN      DOMElement,
    name      IN      VARCHAR2,
    ns        IN      VARCHAR2)
RETURN DOMNodeList;
```

Parameters

Table 113–46 *GETCHILDRENBYTAGNAME Function Parameters*

Parameter	Description
<code>elem</code>	The <code>DOMElement</code> .
<code>name</code>	Tag name.
<code>ns</code>	Namespace.

GETDATA Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Gets the character data of the node that implements this interface (See Also: [DOMCharacterData Subprograms](#) on page 113-13):

```
DBMS_XMLDOM.GETDATA(  
    cd      IN    DOMCharacterData)  
RETURN VARCHAR2;
```

Returns the content data of the DOMProcessingInstruction (See Also: [DOMProcessingInstruction Subprograms](#) on page 113-26):

```
DBMS_XMLDOM.GETDATA(  
    pi      IN    DOMProcessingInstruction)  
RETURN VARCHAR2;
```

Parameters

Table 113–47 GETDATA Function Parameters

Parameter	Description
cd	DOMCharacterData.
pi	The DOMProcessingInstruction.

GETDOCTYPE Function

This function returns the DTD associated to the DOMDocument.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.GETDOCTYPE(  
    doc      IN      DOMDocument)  
RETURN domdocumenttype;
```

Parameters

Table 113–48 *GETDOCTYPE Function Parameters*

Parameter	Description
doc	DOMDocument.

GETDOCUMENTELEMENT Function

This function returns the root element of the DOMDocument.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.GETDOCUMENTELEMENT(  
    doc      IN      DOMDocument)  
RETURN DOMELEMENT;
```

Parameters

Table 113–49 *GETDOCUMENTELEMENT Function Parameters*

Parameter	Description
doc	DOMDocument.

GETELEMENTSBYTAGNAME Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Returns a `DOMNodeList` of all the elements with a given tagname (See Also: [DOMDocument Subprograms](#) on page 113-15):

```
DBMS_XMLDOM.GETELEMENTSBYTAGNAME (
    doc          IN    DOMDocument,
    tagname      IN    VARCHAR2)
RETURN DOMNodeList;
```

Returns the element children of the `DOMElement` given the tag name (See Also: [DOMElement Subprograms](#) on page 113-19):

```
DBMS_XMLDOM.GETELEMENTSBYTAGNAME (
    elem        IN    DOMElement,
    name        IN    VARCHAR2)
RETURN DOMNodeList;
```

Returns the element children of the `DOMElement` given the tag name and namespace (See Also: [DOMElement Subprograms](#) on page 113-19):

```
DBMS_XMLDOM.GETELEMENTSBYTAGNAME (
    elem        IN    DOMElement,
    name        IN    VARCHAR2,
    ns          IN    VARCHAR2)
RETURN DOMNodeList;
```

Parameters

Table 113–50 *GETELEMENTSBYTAGNAME Function Parameters*

Parameter	Description
<code>doc</code>	<code>DOMDocument</code> .
<code>tagname</code>	Name of the tag to match on.
<code>elem</code>	The <code>DOMElement</code> .
<code>name</code>	Tag name; using a wildcard(*) would match any tag.
<code>ns</code>	Namespace.

GETENTITIES Function

This function retrieves a `NamedNodeMap` containing the general entities, both external and internal, declared in the DTD.

See Also: [DOMDocumentType Subprograms](#) on page 113-18

Syntax

```
DBMS_XMLDOM.GETENTITIES(  
    dt          IN      DOMDocumentType)  
RETURN DOMNamedNodeMap;
```

Parameters

Table 113–51

Parameter	Description
dt	DOMDocumentType.

GETEXPANDEDNAME Procedure and Functions

GETEXPANDEDNAME is overloaded as a procedure and two functions. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Retrieves the expanded name of the Node if it is in an Element or Attribute type; otherwise, returns NULL (See Also: [DOMNode Subprograms](#) on page 113-8)

```
DBMS_XMLDOM.GETEXPANDEDNAME(
    n          IN          DOMNode
    data      OUT          VARCHAR);
```

Returns the expanded name of the DOMAttr (See Also: [DOMAttr Subprograms](#) on page 113-11):

```
DBMS_XMLDOM.GETEXPANDEDNAME(
    a          IN          DOMAttr)
RETURN VARCHAR2;
```

Returns the expanded name of the DOMELEMENT (See Also: [DOMELEMENT Subprograms](#) on page 113-19):

```
DBMS_XMLDOM.GETEXPANDEDNAME(
    elem      IN          DOMELEMENT)
RETURN VARCHAR2;
```

Parameters

Table 113–52 GETEXPANDEDNAME Procedure and Function Parameters

Parameter	Description
n	DOMNode.
data	Returned expanded name of the Node.
a	DOMAttr.
elem	DOMELEMENT.

GETFIRSTCHILD Function

This function retrieves the first child of this node. If there is no such node, this returns `NULL`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETFIRSTCHILD(  
    n          IN          DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–53 *GETFIRSTCHILD Function Parameters*

Parameter	Description
n	DOMNode.

GETIMPLEMENTATION Function

This function returns the `DOMImplementation` object that handles this `DOMDocument`.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.GETIMPLEMENTATION(  
    doc      IN      DOMDocument)  
RETURN DOMImplementation;
```

Parameters

Table 113–54 *GETIMPLEMENTATION Function Parameters*

Parameter	Description
doc	DOMDocument.

GETLASTCHILD Function

This function retrieves the last child of this node. If there is no such node, this returns `NULL`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETLASTCHILD(  
    n      IN  DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–55 *GETLASTCHILD Function Parameters*

Parameter	Description
n	DOMNode.

GETLENGTH Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Gets the number of characters in the data. This may have the value zero, because CharacterData nodes may be empty (See Also: [DOMCharacterData Subprograms](#) on page 113-13):

```
DBMS_XMLDOM.GETLENGTH(
    cd      IN      DOMCharacterData)
RETURN NUMBER;
```

Gets the number of nodes in this map. The range of valid child node indexes is 0 to length-1, inclusive (See Also: [DOMNamedNodeMap Subprograms](#) on page 113-23):

```
DBMS_XMLDOM.GETLENGTH(
    nnm     IN      DOMNamedNodeMap)
RETURN NUMBER;
```

Gets the number of nodes in the list. The range of valid child node indexes is 0 to length-1, inclusive (See Also: [DOMNodeList Subprograms](#) on page 113-24):

```
DBMS_XMLDOM.GETLENGTH(
    nl      IN      DOMNodeList)
RETURN NUMBER;
```

Parameters

Table 113–56 GETLENGTH Function Parameters

Parameter	Description
cd	DOMCharacterData.
nnm	DOMNamedNodeMap.
nl	DOMNodeList.

GETLOCALNAME Procedure and Functions

This function is overloaded as a procedure and two functions. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Retrieves the local part of the node's qualified name (See Also: [DOMNode Subprograms](#) on page 113-8):

```
DBMS_XMLDOM.GETLOCALNAME (  
    n          IN      DOMNode,  
    data      OUT     VARCHAR2);
```

Returns the local name of the `DOMAttr` (See Also: [DOMAttr Subprograms](#) on page 113-11):

```
DBMS_XMLDOM.GETLOCALNAME (  
    a          IN      DOMAttr)  
RETURN VARCHAR2;
```

Returns the local name of the `DOMElement` (See Also: [DOMElement Subprograms](#) on page 113-19)

```
DBMS_XMLDOM.GETLOCALNAME (  
    elem      IN      DOMElement)  
RETURN VARCHAR2;
```

Parameters

Table 113–57 *GETLOCALNAME Procedure and Function Parameters*

Parameter	Description
n	DOMNode
data	Returned local name.
a	DOMAttr.
elem	DOMElement.

GETNAME Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Returns the name of this attribute (See Also: [DOMAttr Subprograms](#) on page 113-11):

```
DBMS_XMLDOM.GETNAME(  
    a          IN      DOMAttr)  
RETURN VARCHAR2;
```

Retrieves the name of DTD, or the name immediately following the DOCTYPE keyword (See Also: [DOMDocumentType Subprograms](#) on page 113-18):

```
DBMS_XMLDOM.GETNAME(  
    dt          IN      DOMDocumentType)  
RETURN VARCHAR2;
```

Parameters

Table 113–58 GETNAME Function Parameters

Parameter	Description
a	DOMAttr.
dt	DOMDocumentType.

GETNAMEDITEM Function

This function retrieves a node specified by name.

See Also: [DOMNamedNodeMap Subprograms](#) on page 113-23

Syntax

Retrieves a node specified by name:

```
DBMS_XMLDOM.GETNAMEDITEM(  
    nnm DOMNamedNodeMap,  
    name IN VARCHAR2)  
RETURN DOMNode;
```

Retrieves a node specified by name and namespace URI:

```
DBMS_XMLDOM.GETNAMEDITEM(  
    nnm DOMNamedNodeMap,  
    name IN VARCHAR2,  
    ns IN VARCHAR2)  
RETURN DOMNode;
```

Parameters

Table 113–59 *GETNAMEDITEM Function Parameters*

Parameter	Description
nnm	DOMNamedNodeMap.
name	Name of the item to be retrieved.
ns	Namespace.

GETNAMESPACE Procedure and Functions

GETNAMESPACE is overloaded as a procedure and two functions. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Retrieves the namespace URI associated with the node (See Also: [DOMNode Subprograms](#) on page 113-8):

```
DBMS_XMLDOM.GETNAMESPACE (
    n          IN    DOMNode,
    data      OUT   VARCHAR2);
```

Retrieves the namespace of the DOMAttr (See Also: [DOMAttr Subprograms](#) on page 113-11):

```
DBMS_XMLDOM.GETNAMESPACE (
    a          IN    DOMAttr)
RETURN VARCHAR2;
```

Retrieves the namespace of the DOMELEMENT (See Also: [DOMELEMENT Subprograms](#) on page 113-19):

```
DBMS_XMLDOM.GETNAMESPACE (
    elem      IN    DOMELEMENT)
RETURN VARCHAR2;
```

Parameters

Table 113–60 GETNAMESPACE Procedure and Function Parameters

Parameter	Description
n	DOMNode.
data	Returned namespace URI.
a	DOMAttr.
elem	DOMELEMENT.

GETNEXTSIBLING Function

This function retrieves the node immediately following this node. If there is no such node, this returns `NULL`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETNEXTSIBLING(  
    n          IN      DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–61 *GETNEXTSIBLING Function Parameters*

Parameter	Description
n	DOMNode.

GETNODENAME Function

This function gets the name of the node depending on its type.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETNODENAME(  
    n          IN      DOMNode)  
RETURN VARCHAR2;
```

Parameters

Table 113–62 *GETNODENAME Function Parameters*

Parameter	Description
n	DOMNode.

GETNODETYPE Function

This function retrieves a code representing the type of the underlying object.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETNODETYPE(  
    n          IN      DOMNode)  
RETURN NUMBER;
```

Parameters

Table 113–63 GETNODETYPE Function Parameters

Parameter	Description
n	DOMNode.

GETNODEVALUE Function

This function gets the value of this node, depending on its type.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETNODEVALUE (  
    n          IN      DOMNode)  
RETURN VARCHAR2;
```

Parameters

Table 113–64 *GETNODEVALUE Function Parameters*

Parameter	Description
n	DOMNode.

GETNOTATIONNAME Function

This function returns the notation name of the `DOMEntity`.

See Also: [DOMEntity Subprograms](#) on page 113-20

Syntax

```
DBMS_XMLDOM.GETNOTATIONNAME(  
    ent          IN      DOMEntity)  
RETURN VARCHAR2;
```

Parameters

Table 113–65 *GETNOTATIONNAME Function Parameters*

Parameter	Description
ent	<code>DOMEntity</code> .

GETNOTATIONS Function

This function retrieves a `NamedNodeMap` containing the notations declared in the DTD.

See Also: [DOMDocumentType Subprograms](#) on page 113-18

Syntax

```
DBMS_XMLDOM.GETNOTATIONS(  
    dt          IN      DOMDocumentType)  
RETURN DOMNamedNodeMap;
```

Parameters

Table 113–66 *GETNOTATIONS Function Parameters*

Parameter	Description
dt	DOMDocumentType.

GETTARGET Function

This function returns the target of the `DOMProcessingInstruction`.

See Also: [DOMProcessingInstruction Subprograms](#) on page 113-26

Syntax

```
DBMS_XMLDOM.GETTARGET(  
    pi          IN      DOMProcessingInstruction)  
RETURN VARCHAR2;
```

Parameters

Table 113–67 *GETTARGET Function Parameters*

Parameter	Description
<code>pi</code>	<code>DOMProcessingInstruction</code> .

GETOWNERDOCUMENT Function

This function retrieves the Document object associated with this node. This is also the Document object used to create new nodes. When this node is a Document or a Document Type that is not used with any Document yet, this is `NULL`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETOWNERDOCUMENT(  
    n          IN      DOMNode)  
RETURN DOMDocument;
```

Parameters

Table 113–68 *GETOWNERDOCUMENT Function Parameters*

Parameter	Description
n	DOMNode.

GETOWNERELEMENT Function

This function retrieves the Element node to which the specified Attribute is attached.

See Also: [DOMAttr Subprograms](#) on page 113-11

Syntax

```
DBMS_XMLDOM.GETOWNERELEMENT(  
    a          IN    DOMAttr)  
RETURN DOMELEMENT;
```

Parameters

Table 113–69 *GETOWNERELEMENT Function Parameters*

Parameter	Description
a	Attribute.

GETPARENTNODE Function

This function retrieves the parent of this node. All nodes, except `Attr`, `Document`, `DocumentFragment`, `Entity`, and `Notation` may have a parent. However, if a node has just been created and not yet added to the tree, or if it has been removed from the tree, this is `NULL`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETPARENTNODE(  
    n          IN      DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–70 *GETPARENTNODE Function Parameters*

Parameter	Description
n	DOMNode.

GETPREFIX Function

This function retrieves the namespace prefix of the node.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETPREFIX(  
    n          IN      DOMNode)  
RETURN VARCHAR2;
```

Parameters

Table 113–71 *GETPREFIX Function Parameters*

Parameter	Description
n	DOMNode.

GETPREVIOUSIBLING Function

This function retrieves the node immediately preceding this node. If there is no such node, this returns NULL.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETPREVIOUSIBLING(  
    n          IN      DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–72 *GETPREVIOUSIBLING Function Parameters*

Parameter	Description
n	DOMNode.

GETPUBLICID Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Returns the public identifier of the given DTD (See Also: [DOMDocumentType Subprograms](#) on page 113-18):

```
DBMS_XMLDOM.GETPUBLICID(  
    dt          IN      DOMDocumentType)  
RETURN VARCHAR2;
```

Returns the public identifier of the DOMEntity (See Also: [DOMEntity Subprograms](#) on page 113-20):

```
DBMS_XMLDOM.GETPUBLICID(  
    ent        IN      DOMEntity)  
RETURN VARCHAR2;
```

Returns the public identifier of the DOMNotation (See Also: [DOMNotation Subprograms](#) on page 113-25):

```
DBMS_XMLDOM.GETPUBLICID(  
    n          IN      DOMNotation)  
RETURN VARCHAR2;
```

Parameters

Table 113–73 GETPUBLICID Function Parameters

Parameter	Description
dt	The DTD.
ent	DOMEntity.
n	DOMNotation.

GETQUALIFIEDNAME Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Returns the qualified name of the `DOMAttr` (See Also: [DOMAttr Subprograms](#) on page 113-11):

```
DBMS_XMLDOM.GETQUALIFIEDNAME(  
    a          IN      DOMAttr)  
RETURN VARCHAR2;
```

Returns the qualified name of the `DOMElement` (See Also: [DOMElement Subprograms](#) on page 113-19):

```
DBMS_XMLDOM.GETQUALIFIEDNAME(  
    elem      IN      DOMElement)  
RETURN VARCHAR2;
```

Parameters

Table 113–74 *GETQUALIFIEDNAME Functions Parameters*

Parameter	Description
a	DOMAttr.
elem	DOMElement.

GETSCHEMANODE Function

This function retrieves the schema URI associated with the node.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.GETSCHEMANODE(  
    n          IN    DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–75 *GETSCHEMANODE Function Parameters*

Parameter	Description
n	DOMNode.

GETSPECIFIED Function

If this attribute was explicitly given a value in the original document, this is true; otherwise, it is false.

See Also: [DOMAttr Subprograms](#) on page 113-11

Syntax

```
DBMS_XMLDOM.GETSPECIFIED(  
    a          IN      DOMAttr)  
RETURN BOOLEAN;
```

Parameters

Table 113–76 *GETSPECIFIED Function Parameters*

Parameter	Description
a	DOMAttr.

GETSTANDALONE Function

This function returns the standalone property associated with the `DOMDocument`.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.GETSTANDALONE(  
    doc          IN      DOMDocument)  
RETURN VARCHAR2;
```

Parameters

Table 113–77 *GETSTANDALONE Function Parameters*

Parameter	Description
<code>doc</code>	<code>DOMDocument</code> .

GETSYSTEMID Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Returns the system id of the given DTD (See Also: [DOMDocumentType Subprograms](#) on page 113-18):

```
DBMS_XMLDOM.GETSYSTEMID(
    dt          IN      DOMDocumentType)
RETURN VARCHAR2;
```

Returns the system identifier of the DOMEntity (See Also: [DOMEntity Subprograms](#) on page 113-20):

```
DBMS_XMLDOM.GETSYSTEMID(
    ent        IN      DOMEntity)
RETURN VARCHAR2;
```

Returns the system identifier of the DOMNotation (See Also: [DOMNotation Subprograms](#) on page 113-25):

```
DBMS_XMLDOM.GETSYSTEMID(
    n          IN      DOMNotation)
RETURN VARCHAR2;
```

Parameters

Table 113–78 GETSYSTEMID Function Parameters

Parameter	Description
dt	The DTD.
ent	DOMEntity.
n	DOMNotation.

GETTAGNAME Function

This function returns the name of the `DOMElement`.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

```
DBMS_XMLDOM.GETTAGNAME(  
    elem      IN      DOMElement)  
RETURN VARCHAR2;
```

Parameters

Table 113–79 *GETTAGNAME Function Parameters*

Parameter	Description
elem	The <code>DOMElement</code> .

GETVALUE Function

This function retrieves the value of the attribute.

See Also: [DOMAttr Subprograms](#) on page 113-11

Syntax

```
DBMS_XMLDOM.GETVALUE(  
    a          IN      DOMAttr)  
RETURN VARCHAR2;
```

Parameters

Table 113–80 *GETVALUE Function Parameters*

Parameter	Description
a	DOMAttr.

GETVERSION Function

This function returns the version of the DOMDocument.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.GETVERSION(  
    doc          IN      DOMDocument)  
RETURN VARCHAR2;
```

Parameters

Table 113–81 *GETVERSION Function Parameters*

Parameter	Description
doc	DOMDocument.

GETXMLTYPE Function

This function returns the `XMLType` associated with the `DOMDocument`.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.GETXMLTYPE(  
    doc          IN      DOMDocument)  
RETURN SYS.XMLType;
```

Parameters

Table 113–82 *GETXMLTYPE Function Parameters*

Parameter	Description
doc	DOMDocument.

HASATTRIBUTE Functions

Verifies whether an attribute has been defined for `DOMElement`, or has a default value.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

Verifies whether an attribute with the specified name has been defined for `DOMElement`:

```
DBMS_XMLDOM.HASATTRIBUTE(  
    elem      IN      DOMElement,  
    name      IN VARCHAR2)  
RETURN VARCHAR2;
```

Verifies whether an attribute with specified name and namespace URI has been defined for `DOMElement`; namespace enabled:

```
DBMS_XMLDOM.HASATTRIBUTE(  
    elem      IN      DOMElement,  
    name IN VARCHAR2,  
    ns IN VARCHAR2)  
RETURN VARCHAR2;
```

Parameters

Table 113–83 HASATTRIBUTE Function Parameters

Parameter	Description
<code>elem</code>	The <code>DOMElement</code> .
<code>name</code>	Attribute name; * matches any attribute.
<code>ns</code>	Namespace.

HASATTRIBUTES Function

This function returns whether this node has any attributes.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.HASATTRIBUTES(  
    n          IN      DOMNode)  
RETURN BOOLEAN;
```

Parameters

Table 113–84 *HASATTRIBUTES Function Parameters*

Parameter	Description
n	DOMNode.

HASCHILDNODES Function

This function determines whether this node has any children.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.HASCHILDNODES(  
    n          IN      DOMNode)  
RETURN BOOLEAN;
```

Parameters

Table 113–85 HASCHILDNODES Function Parameters

Parameter	Description
n	DOMNode.

HASFEATURE Function

This function tests if the `DOMImplementation` implements a specific feature.

See Also: [DOMImplementation Subprograms](#) on page 113-22

Syntax

```
DBMS_XMLDOM.HASFEATURE(  
    di          IN      DOMImplementation,  
    feature     IN      VARCHAR2,  
    version     IN      VARCHAR2)  
RETURN BOOLEAN;
```

Parameters

Table 113–86 *HASFEATURE Function Parameters*

Parameter	Description
<code>di</code>	<code>DOMImplementation</code> .
<code>feature</code>	The feature to check for.
<code>version</code>	The version of the DOM to check in.

IMPORTNODE Function

This function imports a node from an external document and returns this new node.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.IMPORTNODE(  
    doc           IN      DOMDocument,  
    importedNode IN      DOMNode,  
    deep          IN      BOOLEAN)  
RETURN DOMNode;
```

Parameters

Table 113–87 *IMPORTNODE Function Parameters*

Parameter	Description
doc	Document from which the node is imported.
importedNode	Node to import.
deep	Setting for recursive import. <ul style="list-style-type: none">■ If this value is <code>TRUE</code>, the entire subtree of the node will be imported with the node.■ If this value is <code>FALSE</code>, only the node itself will be imported.

INSERTBEFORE Function

This function inserts the node `NEWCHILD` before the existing child node `REFCHILD`. If `REFCHILD` is `NULL`, insert `NEWCHILD` at the end of the list of children.

If `NEWCHILD` is a `DocumentFragment` object, all of its children are inserted, in the same order, before `REFCHILD`. If the `NEWCHILD` is already in the tree, it is first removed.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.INSERTBEFORE(  
    n           IN      DOMNode,  
    newChild   IN      DOMNode,  
    refChild   IN      DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–88 *INSERTBEFORE Function Parameters*

Parameter	Description
<code>n</code>	<code>DOMNode</code> .
<code>newChild</code>	The child to be inserted in the <code>DOMNode</code> .
<code>refChild</code>	The reference node before which the <code>NEWCHILD</code> is to be inserted.

INSERTDATA Procedure

This procedure inserts a string at the specified character offset.

See Also: [DOMCharacterData Subprograms](#) on page 113-13

Syntax

```
DBMS_XMLDOM.INSERTDATA(  
    cd          IN      DOMCharacterData,  
    offset     IN      NUMBER,  
    arg        IN      VARCHAR2);
```

Parameters

Table 113–89 *INSERTDATA Procedure Parameters*

Parameter	Description
cd	DOMCharacterData.
offset	The offset at which to insert the data.
arg	The value to be inserted.

ISNULL Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Checks if the given `DOMNode` is `NULL`. Returns `TRUE` if it is `NULL`, `FALSE` otherwise (See Also: [DOMNode Subprograms](#) on page 113-8):

```
DBMS_XMLDOM.ISNULL(  
    n          IN      DOMNode)  
RETURN BOOLEAN;
```

Checks that the given `DOMAttr` is `NULL`; returns `TRUE` if it is `NULL`, `FALSE` otherwise (See Also: [DOMAttr Subprograms](#) on page 113-11):

```
DBMS_XMLDOM.ISNULL(  
    a          IN      DOMAttr)  
RETURN BOOLEAN;
```

Checks that the given `DOMCDataSection` is `NULL`; returns `TRUE` if it is `NULL`, `FALSE` otherwise (See Also: [DOMCDataSection Subprograms](#) on page 113-12):

```
DBMS_XMLDOM.ISNULL(  
    cds        IN      DOMCDataSection)  
RETURN BOOLEAN;
```

Checks that the given `DOMCharacterData` is `NULL`; returns `TRUE` if it is `NULL`, `FALSE` otherwise (See Also: [DOMCharacterData Subprograms](#) on page 113-13):

```
DBMS_XMLDOM.ISNULL(  
    cd         IN      DOMCharacterData)  
RETURN BOOLEAN;
```

Checks that the given `DOMComment` is `NULL`; returns `TRUE` if it is `NULL`, `FALSE` otherwise (See Also: [DOMComment Subprograms](#) on page 113-14):

```
DBMS_XMLDOM.ISNULL(  
    com        IN      DOMComment)  
RETURN BOOLEAN;
```

Checks that the given `DOMDocument` is `NULL`; returns `TRUE` if it is `NULL`, `FALSE` otherwise (See Also: [DOMDocument Subprograms](#) on page 113-15):

```
DBMS_XMLDOM.ISNULL(  
    doc        IN      DOMDocument)
```

```
RETURN BOOLEAN;
```

Checks that the given `DOMDocumentFragment` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMDocumentFragment Subprograms](#) on page 113-17):

```
DBMS_XMLDOM.ISNULL(  
    df      IN      DOMDocumentFragment)  
RETURN BOOLEAN;
```

Checks that the given `DOMDocumentType` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMDocumentType Subprograms](#) on page 113-18):

```
DBMS_XMLDOM.ISNULL(  
    dt      IN      DOMDocumentType)  
RETURN BOOLEAN;
```

Checks that the given `DOMElement` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMElement Subprograms](#) on page 113-19):

```
DBMS_XMLDOM.ISNULL(  
    elem    IN      DOMElement)  
RETURN BOOLEAN;
```

Checks that the given `DOMEntity` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMEntity Subprograms](#) on page 113-20):

```
DBMS_XMLDOM.ISNULL(  
    ent     IN      DOMEntity)  
RETURN BOOLEAN;
```

Checks that the given `DOMEntityReference` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMEntityReference Subprograms](#) on page 113-21):

```
DBMS_XMLDOM.ISNULL(  
    eref    IN      DOMEntityReference)  
RETURN BOOLEAN;
```

Checks that the `DOMImplementation` is NULL; returns TRUE if it is NULL (See Also: [DOMImplementation Subprograms](#) on page 113-22):

```
DBMS_XMLDOM.ISNULL(  
    di      IN      DOMImplementation)  
RETURN BOOLEAN;
```


Checks that the given `DOMNamedNodeMap` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMNamedNodeMap Subprograms](#) on page 113-23):

```
DBMS_XMLDOM.ISNULL(  
    nnm          IN      DOMNamedNodeMap)  
RETURN BOOLEAN;
```

Checks that the given `DOMNodeList` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMNodeList Subprograms](#) on page 113-24):

```
DBMS_XMLDOM.ISNULL(  
    nl          IN      DOMNodeList)  
RETURN BOOLEAN;
```

Checks that the given `DOMNotation` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMNotation Subprograms](#) on page 113-25):

```
DBMS_XMLDOM.ISNULL(  
    n          IN      DOMNotation)  
RETURN BOOLEAN;
```

Checks that the given `DOMProcessingInstruction` is NULL; returns TRUE if it is (See Also: [DOMProcessingInstruction Subprograms](#) on page 113-26):

```
DBMS_XMLDOM.ISNULL(  
    pi          IN      DOMProcessingInstruction)  
RETURN BOOLEAN;
```

Checks that the given `DOMText` is NULL; returns TRUE if it is NULL, FALSE otherwise (See Also: [DOMText Subprograms](#) on page 113-27):

```
DBMS_XMLDOM.ISNULL(  
    t          IN      DOMText)  
RETURN BOOLEAN;
```

Parameters

Table 113–90 *ISNULL Function Parameters*

Parameter	Description
n	DOMNode to check.
a	DOMAttr to check.
cds	DOMCDataSection to check.
cd	DOMCharacterData to check.

Table 113–90 (Cont.) ISNULL Function Parameters

Parameter	Description
com	DOMComment to check.
doc	DOMDocument to check.
dF	DOMDocumentFragment to check.
dt	DOMDocumentType to check.
elem	DOMElement to check.
ent	DOMEntity to check.
eref	DOMEntityReference to check.
di	DOMImplementation to check.
nm	DOMNameNodeMap to check.
nl	DOMNodeList to check.
n	DOMNotation to check.
pi	DOMProcessingInstruction to check.
t	DOMText to check.

ITEM Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Returns the item in the map which corresponds to the `INDEX` parameter. If `INDEX` is greater than or equal to the number of nodes in this map, this returns `NULL` (See Also: [DOMNamedNodeMap Subprograms](#) on page 113-23):

```
DBMS_XMLDOM.ITEM(
    nnm      IN      DOMNamedNodeMap,
    index    IN      NUMBER)
RETURN DOMNode;
```

Returns the item in the collection which corresponds to the `INDEX` parameter. If `index` is greater than or equal to the number of nodes in the list, this returns `NULL` (See Also: [DOMNodeList Subprograms](#) on page 113-24):

```
DBMS_XMLDOM.ITEM(
    nl      IN      DOMNodeList,
    index   IN      NUMBER)
RETURN DOMNode;
```

Parameters

Table 113–91 *ITEM Function Parameters*

Parameter	Description
<code>nnm</code>	<code>DOMNamedNodeMap</code> .
<code>index</code>	The index in the node map at which the item is to be retrieved.
<code>nl</code>	<code>DOMNodeList</code>
<code>index</code>	The index in the <code>NodeList</code> used to retrieve the item.

MAKEATTR Function

This function casts a given `DOMNode` to a `DOMAttr`, and returns the `DOMAttr`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEATTR(  
    n          IN    DOMNode)  
RETURN DOMAttr;
```

Parameters

Table 113–92 *MAKEATTR Function Parameters*

Parameter	Description
n	DOMNode to cast

MAKECDATASECTION Function

This function casts a given DOMNode to a DOMCDataSection.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKECDATASECTION(  
    n          IN      DOMNode)  
RETURN DOMCDataSection;
```

Parameters

Table 113–93 MAKECDATASECTION Function Parameters

Parameter	Description
n	DOMNode to cast.

MAKECHARACTERDATA Function

This function casts a given `DOMNode` to a `DOMCharacterData`, and returns the `DOMCharacterData`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKECHARACTERDATA(  
    n          IN      DOMNode)  
RETURN DOMCharacterData;
```

Parameters

Table 113–94 MAKECHARACTERDATA Function Parameters

Parameter	Description
n	DOMNode to cast.

MAKECOMMENT Function

This function casts a given DOMNode to a DOMComment, and returns the DOMComment.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKECOMMENT(  
    n          IN      DOMNode)  
RETURN DOMComment;
```

Parameters

Table 113–95 MAKECOMMENT Function Parameters

Parameter	Description
n	DOMNode to cast.

MAKEDOCUMENT Function

This function casts a given `DOMNode` to a `DOMDocument`, and returns the `DOMDocument`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEDOCUMENT(  
    n          IN      DOMNode)  
RETURN DOMDocument;
```

Parameters

Table 113–96 *MAKEDOCUMENT Function Parameters*

Parameter	Description
n	DOMNode to cast.

MAKEDOCUMENTFRAGMENT Function

This function casts a given DOMNode to a DOMDocumentFragment, and returns the DOMDocumentFragment.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEDOCUMENTFRAGMENT(  
    n          IN      DOMNode)  
RETURN DOMDocumentFragment;
```

Parameters

Table 113–97 *MAKEDOCUMENTFRAGMENT Function Parameters*

Parameter	Description
n	DOMNode to cast.

MAKEDOCUMENTTYPE Function

This function casts a given `DOMNode` to a `DOMDocumentType` and returns the `DOMDocumentType`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEDOCUMENTTYPE (  
    n          IN      DOMNode)  
RETURN DOMDocumentType;
```

Parameters

Table 113–98 *MAKEDOCUMENTTYPE Function Parameters*

Parameter	Description
n	DOMNode to cast.

MAKEELEMENT Function

This function casts a given DOMNode to a DOMELEMENT, and returns the DOMELEMENT.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEELEMENT(  
    n          IN      DOMNode)  
RETURN DOMELEMENT;
```

Parameters

Table 113–99 MAKEELEMENT Function Parameters

Parameter	Description
n	DOMNode to cast.

MAKEENTITY Function

This function casts a given `DOMNode` to a `DOMEntity`, and returns the `DOMEntity`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEENTITY(  
    n          IN      DOMNode)  
RETURN DOMEntity;
```

Parameters

Table 113–100 MAKEENTITY Function Parameters

Parameter	Description
n	DOMNode to cast.

MAKEENTITYREFERENCE Function

This function casts a given DOMNode to a DOMEntityReference, and returns the DOMEntityReference.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEENTITYREFERENCE(  
    n          IN      DOMNode)  
RETURN DOMEntityReference;
```

Parameters

Table 113–101 MAKEENTITYREFERENCE Function Parameters

Parameter	Description
n	DOMNode to cast.

MAKENODE Functions

This function is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Casts given DOMAttr to a DOMNode, and returns the DOMNode (See Also: [DOMAttr Subprograms](#) on page 113-11):

```
DBMS_XMLDOM.MAKENODE(  
    a          IN    DOMAttr)  
RETURN DOMNode;
```

Casts the DOMCDataSection to a DOMNode, and returns that DOMNode (See Also: [DOMCDataSection Subprograms](#) on page 113-12):

```
DBMS_XMLDOM.MAKENODE(  
    cds        IN    DOMCDataSection)  
RETURN DOMNode;
```

Casts the given DOMCharacterData as a DOMNode, and returns that DOMNode (See Also: [DOMCharacterData Subprograms](#) on page 113-13):

```
DBMS_XMLDOM.MAKENODE(  
    cd         IN    DOMCharacterData)  
RETURN DOMNode;
```

Casts the given DOMComment to a DOMNode, and returns that DOMNode (See Also: [DOMComment Subprograms](#) on page 113-14):

```
DBMS_XMLDOM.MAKENODE(  
    com        IN    DOMComment)  
RETURN DOMNode;
```

Casts the DOMDocument to a DOMNode, and returns that DOMNode (See Also: [DOMDocument Subprograms](#) on page 113-15):

```
DBMS_XMLDOM.MAKENODE(  
    doc        IN    DOMDocument)  
RETURN DOMNode;
```

Casts the given DOMDocumentFragment to a DOMNode, and returns that DOMNode (See Also: [DOMDocumentFragment Subprograms](#) on page 113-17):

```
DBMS_XMLDOM.MAKENODE(  
    df         IN    DOMDocumentFragment)
```

```
RETURN DOMNode;
```

Casts the given DOMDocumentType to a DOMNode, and returns that DOMNode (See Also: [DOMDocumentType Subprograms](#) on page 113-18):

```
DBMS_XMLDOM.MAKENODE(  
    dt          IN    DOMDocumentType)  
RETURN DOMNode;
```

Casts the given DOMELEMENT to a DOMNode, and returns that DOMNode (See Also: [DOMELEMENT Subprograms](#) on page 113-19):

```
DBMS_XMLDOM.MAKENODE(  
    elem        IN    DOMELEMENT)  
RETURN DOMNode;
```

Casts given DOMEntity to a DOMNode, and returns that DOMNode (See Also: [DOMEntity Subprograms](#) on page 113-20):

```
DBMS_XMLDOM.MAKENODE(  
    ent         IN    DOMEntity)  
RETURN DOMNode;
```

Casts the DOMEntityReference to a DOMNode, and returns that DOMNode (See Also: [DOMEntityReference Subprograms](#) on page 113-21):

```
DBMS_XMLDOM.MAKENODE(  
    eref        IN    DOMEntityReference)  
RETURN DOMNode;
```

Casts the DOMNotation to a DOMNode, and returns that DOMNode (See Also: [DOMNotation Subprograms](#) on page 113-25):

```
DBMS_XMLDOM.MAKENODE(  
    n           IN    DOMNotation)  
RETURN DOMNode;
```

Casts the DOMProcessingInstruction to a DOMNode, and returns the DOMNode (See Also: [DOMProcessingInstruction Subprograms](#) on page 113-26):

```
DBMS_XMLDOM.MAKENODE(  
    pi         IN    DOMProcessingInstruction)  
RETURN DOMNode;
```

Casts the `DOMText` to a `DOMNode`, and returns that `DOMNode` (See Also: [DOMText Subprograms](#) on page 113-27):

```
DBMS_XMLDOM.MAKENODE(  
  t          IN  DOMText)  
RETURN DOMNode;
```

Parameters

Table 113–102 *MAKENODE Function Parameters*

Parameter	Description
a	DOMAttr to cast.
cds	DOMCDataSection to cast.
cd	DOMCharacterData to cast.
com	DOMComment to cast.
doc	DOMDocument to cast.
df	DOMDocumentFragment to cast.
dt	DOMDocumentType to cast.
elem	DOMElement to cast.
ent	DOMEntity to cast.
eref	DOMEntityReference to cast.
n	DOMNotation to cast.
pi	DOMProcessingInstruction to cast.
t	DOMText to cast.

MAKENOTATION Function

This function casts a given DOMNode to a DOMNotation, and returns the DOMNotation.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKENOTATION(  
    n          IN      DOMNode)  
RETURN DOMNotation;
```

Parameters

Table 113–103 *MAKENOTATION Function Parameters*

Parameter	Description
n	DOMNode to cast

MAKEPROCESSINGINSTRUCTION Function

This function casts a given `DOMNode` to a `DOMProcessingInstruction`, and returns the `DOMProcessingInstruction`.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKEPROCESSINGINSTRUCTION(  
    n          IN      DOMNode)  
RETURN DOMProcessingInstruction;
```

Parameters

Table 113–104 MAKEPROCESSINGINSTRUCTION Function Parameters

Parameter	Description
n	DOMNode to cast

MAKETEXT Function

This function casts a given DOMNode to a DOMText, and returns the DOMText.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.MAKETEXT(  
    n          IN      DOMNode)  
RETURN DOMText;
```

Parameters

Table 113–105 *MAKETEXT Function Parameters*

Parameter	Description
n	DOMNode to cast

NEWDOMDOCUMENT Functions

Returns a new `DOMDocument` instance.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

Returns a new `DOMDocument` instance:

```
DBMS_XMLDOM.NEWDOMDOCUMENT  
RETURN DOMDocument ;
```

Returns a new `DOMDocument` instance created from the specified `XMLType` object:

```
DBMS_XMLDOM.NEWDOMDOCUMENT(  
    xmlDoc    IN sys.XMLType)  
RETURN DOMDocument ;
```

Returns a new `DOMDocument` instance created from the specified `CLOB`:

```
DBMS_XMLDOM.NEWDOMDOCUMENT(  
    clob      IN    CLOB)  
RETURN DOMDocument ;
```

Parameters

Table 113–106 *NEWDOMDOCUMENT Function Parameters*

Parameter	Description
<code>xmlDoc</code>	<code>XMLType</code> source for the <code>DOMDocument</code> .
<code>clob</code>	<code>CLOB</code> source for the <code>DOMDocument</code> .

NORMALIZE Procedure

This procedure normalizes the text children of the `DOMElement`.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

```
DBMS_XMLDOM.NORMALIZE(  
    elem          IN      DOMElement);
```

Parameters

Table 113–107 *NORMALIZE Procedure Parameters*

Parameter	Description
elem	The <code>DOMElement</code> .

REMOVEATTRIBUTE Procedures

Removes an attribute from the `DOMElement` by name.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

Removes the value of a `DOMElement`'s attribute by name:

```
DBMS_XMLDOM.REMOVEATTRIBUTE(  
    elem      IN      DOMElement,  
    name      IN      VARCHAR2);
```

Removes the value of a `DOMElement`'s attribute by name and namespace URI.

```
DBMS_XMLDOM.REMOVEATTRIBUTE(  
    elem      IN      DOMElement,  
    name      IN      VARCHAR2,  
    ns        IN      VARCHAR2);
```

Parameters

Table 113–108 REMOVEATTRIBUTE Procedure Parameters

Parameter	Description
<code>elem</code>	The <code>DOMElement</code> .
<code>name</code>	Attribute name.
<code>ns</code>	Namespace.

REMOVEATTRIBUTENODE Function

This function removes the specified attribute node from the `DOMElement`. The method returns the removed node.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

```
DBMS_XMLDOM.REMOVEATTRIBUTENODE(  
    elem      IN      DOMElement,  
    oldAttr   IN      DOMAttr)  
RETURN DOMAttr;
```

Parameters

Table 113–109 REMOVEATTRIBUTENODE Function Parameters

Parameter	Description
<code>elem</code>	The <code>DOMElement</code> .
<code>oldAttr</code>	The old <code>DOMAttr</code> .

REMOVECHILD Function

This function removes the child node indicated by `OLDCHILD` from the list of children, and returns it.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.REMOVECHILD(  
    n           IN      DOMNode,  
    oldChild   IN      DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–110 REMOVECHILD Function Parameters

Parameter	Description
<code>n</code>	DOMNode.
<code>oldChild</code>	The child of the node <code>n</code> to be removed.

REMOVENAMEDITEM Function

This function removes from the map a node specified by name; returns this node. When this map contains the attributes attached to an element, if the removed attribute is known to have a default value, an attribute immediately appears containing the default value as well as the corresponding namespace URI, local name, and prefix when applicable.

See Also: [DOMNamedNodeMap Subprograms](#) on page 113-23

Syntax

Removes a node specified by name:

```
DBMS_XMLDOM.REMOVENAMEDITEM(
    nnm      IN      DOMNamedNodeMap,
    name     IN      VARCHAR2)
RETURN DOMNode;
```

Removes a node specified by name and namespace URI:

```
DBMS_XMLDOM.REMOVENAMEDITEM(
    nnm      IN      DOMNamedNodeMap,
    name     IN      VARCHAR2,
    ns       IN      VARCHAR2)
RETURN DOMNode;
```

Parameters

Table 113–111 *REMOVENAMEDITEM Function Parameters*

Parameter	Description
nnm	DOMNamedNodeMap
name	The name of the item to be removed from the map
ns	Namespace

REPLACECHILD Function

This function replaces the child node `OLDCHILD` with `NEWCHILD` in the list of children, and returns the `OLDCHILD` node. If `NEWCHILD` is a `DocumentFragment` object, `OLDCHILD` is replaced by all of the `DocumentFragment` children, which are inserted in the same order. If the `NEWCHILD` is already in the tree, it is first removed.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.REPLACECHILD(  
    n                IN    DOMNode,  
    newChild        IN    DOMNode,  
    oldChild        IN    DOMNode)  
RETURN DOMNode;
```

Parameters

Table 113–112 REPLACECHILD Function Parameters

Parameter	Description
<code>n</code>	DOMNode.
<code>newChild</code>	The new child which is to replace the old child.
<code>oldChild</code>	The child of the node <code>n</code> which is to be replaced.

REPLACEDATA Procedure

This procedure changes a range of characters in the node. Upon success, data and length reflect the change.

See Also: [DOMCharacterData Subprograms](#) on page 113-13

Syntax

```
DBMS_XMLDOM.REPLACEDATA(
  cd          IN      DOMCharacterData,
  offset      IN      NUMBER,
  cnt         IN      NUMBER,
  arg         IN      VARCHAR2);
```

Parameters

Table 113–113 *REPLACEDATA Procedure Parameters*

Parameter	Description
cd	DOMCharacterData.
offset	The offset at which to replace.
cnt	The number of characters to replace.
arg	The value to replace with.

RESOLVENAMESPACEPREFIX Function

This function resolves the given namespace prefix, and returns the resolved namespace.

See Also: [DOMELEMENT Subprograms](#) on page 113-19

Syntax

```
DBMS_XMLDOM.RESOLVENAMESPACEPREFIX(  
    elem      IN      DOMELEMENT,  
    prefix    IN      VARCHAR2)  
RETURN VARCHAR2;
```

Parameters

Table 113–114 RESOLVENAMESPACEPREFIX Function Parameters

Parameter	Description
<code>elem</code>	The DOMELEMENT.
<code>prefix</code>	Namespace prefix.

SETATTRIBUTE Procedures

Sets the value of a DOMELEMENT's attribute by name.

See Also: [DOMELEMENT Subprograms](#) on page 113-19

Syntax

Sets the value of a DOMELEMENT's attribute by name:

```
DBMS_XMLDOM.SETATTRIBUTE(  
    elem DOMELEMENT,  
    name IN VARCHAR2,  
    value IN VARCHAR2);
```

Sets the value of a DOMELEMENT's attribute by name and namespace URI:

```
DBMS_XMLDOM.SETATTRIBUTE(  
    elem DOMELEMENT,  
    name IN VARCHAR2,  
    value IN VARCHAR2,  
    ns IN VARCHAR2);
```

Parameters

Table 113–115 SETATTRIBUTE Function Parameters

Parameter	Description
elem	The DOMELEMENT.
name	Attribute name.
value	Attribute value.
ns	Namespace.

SETATTRIBUTENODE Functions

Adds a new attribute node to the `DOMElement`.

See Also: [DOMElement Subprograms](#) on page 113-19

Syntax

Adds a new attribute node to the `DOMElement`:

```
DBMS_XMLDOM.SETATTRIBUTENODE(  
    elem DOMElement,  
    newAttr IN DOMAttr)  
RETURN DOMAttr;
```

Adds a new attribute node to the `DOMElement`; namespace enabled:

```
DBMS_XMLDOM.SETATTRIBUTENODE(  
    elem DOMElement,  
    newAttr IN DOMAttr,  
    ns IN VARCHAR2)  
RETURN DOMAttr;
```

Parameters

Table 113–116 *SETATTRIBUTENODE Function Parameters*

Parameter	Description
<code>elem</code>	The <code>DOMElement</code> .
<code>newAttr</code>	The new <code>DOMAttr</code> .
<code>ns</code>	The namespace.

SETDATA Procedures

This procedure is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Sets the character data of the node that implements this interface (See Also: [DOMCharacterData Subprograms](#) on page 113-13):

```
DBMS_XMLDOM.SETDATA(
  cd      IN      DOMCharacterData,
  data    IN      VARCHAR2);
```

Sets the content data of the DOMProcessingInstruction (See Also: [DOMProcessingInstruction Subprograms](#) on page 113-13):

```
DBMS_XMLDOM.SETDATA(
  pi      IN      DOMProcessingInstruction,
  data    IN      VARCHAR2);
```

Parameters

Table 113–117 SETDATA Procedure Parameters

Parameter	Description
cd	DOMCharacterData.
data	The data to which the node is set.
pi	DOMProcessingInstruction.
data	New processing instruction content data.

SETNAMEDITEM Function

This function adds a node using its `nodeName` attribute. If a node with that name is already present in this map, it is replaced by the new one. The old node is returned on replacement; if no replacement is made, `NULL` is returned.

As the `nodeName` attribute is used to derive the name under which the node must be stored, multiple nodes of certain types, those that have a "special" string value, cannot be stored because the names would clash. This is seen as preferable to allowing nodes to be aliased.

See Also: [DOMNamedNodeMap Subprograms](#) on page 113-23

Syntax

Adds a node using its `nodeName` attribute:

```
DBMS_XMLDOM.SETNAMEDITEM(  
    nnm      IN      DOMNamedNodeMap,  
    arg      IN      DOMNode)  
RETURN DOMNode;
```

Adds a node using its `nodeName` attribute and namespace URI:

```
DBMS_XMLDOM.SETNAMEDITEM(  
    nnm      IN      DOMNamedNodeMap,  
    arg      IN      DOMNode,  
    ns       IN      VARCHAR2)  
RETURN DOMNode;
```

Parameters

Table 113–118 *SETNAMEDITEM Function Parameters*

Parameter	Description
<code>nnm</code>	<code>DOMNamedNodeMap</code> .
<code>arg</code>	The Node to be added using its <code>nodeName</code> attribute.
<code>ns</code>	Namespace.

SETNODEVALUE Procedure

This procedure sets the value of this node, depending on its type. When it is defined to be `NULL`, setting it has no effect.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.SETNODEVALUE(  
    n          IN      DOMNode,  
    nodeValue IN      VARCHAR2);
```

Parameters

Table 113–119 *SETNODEVALUE Procedure Parameters*

Parameter	Description
n	DOMNode.
nodeValue	The value to which node is set.

SETPREFIX Procedure

This procedure sets the namespace prefix for this node to the given value.

See Also: [DOMNode Subprograms](#) on page 113-8

Syntax

```
DBMS_XMLDOM.SETPREFIX(  
    n          IN      DOMNode,  
    prefix    IN      VARCHAR2);
```

Parameters

Table 113–120 *SETPREFIX Procedure Parameters*

Parameter	Description
n	DOMNode.
prefix	The value for the namespace prefix of the node.

SETSTANDALONE Procedure

This procedure sets the standalone property of the `DOMDocument`.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.SETSTANDALONE(  
    doc          IN      DOMDocument,  
    newvalue     IN      VARCHAR2);
```

Parameters

Table 113–121 *SETSTANDALONE Procedure Parameters*

Parameter	Description
<code>doc</code>	<code>DOMDocument</code> .
<code>newvalue</code>	Value of the standalone property of the document.

SETVALUE Procedure

This procedure sets the value of the attribute.

See Also: [DOMAttr Subprograms](#) on page 113-11

Syntax

```
DBMS_XMLDOM.SETVALUE(  
    a          IN      DOMAttr,  
    value     IN      VARCHAR2);
```

Parameters

Table 113–122 SETVALUE Procedure Parameters

Parameter	Description
a	DOMAttr.
value	The value to set the attribute to.

SETVERSION Procedure

This procedure sets the version of the DOMDocument.

See Also: [DOMDocument Subprograms](#) on page 113-15

Syntax

```
DBMS_XMLDOM.SETVERSION(  
    doc          IN      DOMDocument ,  
    version     IN      VARCHAR2);
```

Parameters

Table 113–123 SETVERSION Procedure Parameters

Parameter	Description
doc	DOMDocument.
version	The version of the document.

SPLITTEXT Function

This function breaks this `DOMText` node into two `DOMText` nodes at the specified offset.

See Also: [DOMText Subprograms](#) on page 113-27

Syntax

```
DBMS_XMLDOM.SPLITTEXT(  
    t          IN    DOMText,  
    offset    IN    NUMBER)  
RETURN DOMText;
```

Parameters

Table 113–124 SPLITTEXT Function Parameters

Parameter	Description
<code>t</code>	<code>DOMText</code> .
<code>offset</code>	Offset at which to split.

SUBSTRINGDATA Function

This function extracts a range of data from the node.

See Also: [DOMCharacterData Subprograms](#) on page 113-13

Syntax

```
DBMS_XMLDOM.SUBSTRINGDATA(  
    cd          IN    DOMCharacterData,  
    offset     IN    NUMBER,  
    cnt        IN    NUMBER)  
RETURN VARCHAR2;
```

Parameters

Table 113–125 SUBSTRINGDATA Function Parameters

Parameter	Description
cd	DOMCharacterData.
offset	The starting offset of the data from which to get the data.
cnt	The number of characters (from the offset) of the data to get.

WRITETOBUFFER Procedures

This procedure is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Writes XML node to specified buffer using the database character set (See Also: [DOMNode Subprograms](#) on page 113-8):

```
DBMS_XMLDOM.WRITETOBUFFER(  
    n          IN          DOMNode,  
    buffer     IN OUT     VARCHAR2);
```

Writes XML document to a specified buffer using database character set (See Also: [DOMDocument Subprograms](#) on page 113-15):

```
DBMS_XMLDOM.WRITETOBUFFER(  
    doc        IN          DOMdocument,  
    buffer     IN OUT     VARCHAR2);
```

Writes the contents of the specified document fragment into a buffer using the database character set (See Also: [DOMDocumentFragment Subprograms](#) on page 113-17):

```
DBMS_XMLDOM.WRITETOBUFFER(  
    df         IN          DOMDocumentFragment,  
    buffer     IN OUT     VARCHAR2);
```

Parameters

Table 113–126 *WRITETOBUFFER Procedure Parameters*

Parameter	Description
n	DOMNode.
buffer	Buffer to write to.
doc	DOMDocument.
df	DOM document fragment.

WRITETOCLOB Procedures

This procedure is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Writes XML node to specified CLOB using the database character set (See Also: [DOMNode Subprograms](#) on page 113-8):

```
DBMS_XMLDOM.WRITETOCLOB(
  n          IN          DOMNode,
  c1         IN OUT     CLOB);
```

Writes XML document to a specified CLOB using database character set (See Also: [DOMDocument Subprograms](#) on page 113-15):

```
DBMS_XMLDOM.WRITETOCLOB(
  doc        IN          DOMdocument,
  c1         IN OUT     CLOB);
```

Parameters

Table 113–127 WRITETOCLOB Procedure Parameters

Parameter	Description
n	DOMNode.
c1	CLOB to write to.
doc	DOMDocument.

WRITETOFILE Procedures

This procedure is overloaded. The specific forms of functionality are described alongside the syntax declarations.

Syntax

Writes XML node to specified file using the database character set (See Also: [DOMNode Subprograms](#)):

```
DBMS_XMLDOM.WRITETOFILE(
    n          IN      DOMNode,
    fileName   IN      VARCHAR2);
```

Writes XML node to specified file using the given character set, which is passed in as a separate parameter (See Also: [DOMNode Subprograms](#)):

```
DBMS_XMLDOM.WRITETOFILE(  n DOMNode,
    fileName   IN      VARCHAR2,
    charset    IN      VARCHAR2);
```

Writes an XML document to a specified file using database character set (See Also : [DOMDocument Subprograms](#)):

```
DBMS_XMLDOM.WRITETOFILE(
    doc        IN      DOMDocument,
    fileName   IN      VARCHAR2);
```

Writes an XML document to a specified file using given character set (See Also : [DOMDocument Subprograms](#)):

```
DBMS_XMLDOM.WRITETOFILE(
    doc        IN      DOMDocument,
    fileName   IN      VARCHAR2,
    charset    IN      VARCHAR2);
```

Parameters

Table 113–128 WRITETOFILE Procedure Parameters

Parameter	Description
n	DOMNode.
fileName	File to write to.
charset	Given character set.

Table 113–128 *WRITETOFILE Procedure Parameters*

Parameter	Description
doc	DOMDocument.
charset	Character set.

The `DBMS_XMLGEN` package converts the results of a SQL query to a canonical XML format. The package takes an arbitrary SQL query as input, converts it to XML format, and returns the result as a `CLOB`. This package is similar to the `DBMS_XMLQUERY` package, except that it is written in C and compiled into the kernel. This package can only be run on the database.

This chapter contains the following topic:

- [Summary of DBMS_XMLGEN Subprograms](#)

See Also: *Oracle XML DB Developer's Guide*, for more information on XML support and on examples of using `DBMS_XMLGEN`

Summary of DBMS_XMLGEN Subprograms

Table 114–1 Summary of DBMS_XMLGEN Package Subprograms

Subprogram	Description
CLOSECONTEXT Procedure on page 114-4	Closes the context and releases all resources
CONVERT Functions on page 114-5	Converts the XML into the escaped or unescaped XML equivalent
GETNUMROWSPROCESSED Function on page 114-6	Gets the number of SQL rows that were processed in the last call to GETXML Functions
GETXML Functions on page 114-7	Gets the XML document
GETXMLTYPE Functions on page 114-9	Gets the XML document and returns it as XMLType
NEWCONTEXT Functions on page 114-10	Creates a new context handle
RESTARTQUERY Procedure on page 114-11	Restarts the query to start fetching from the beginning
SETCONVERTSPECIALCHARS Procedure on page 114-12	Sets whether special characters such as \$, which are non-XML characters, should be converted or not to their escaped representation
SETMAXROWS Procedure on page 114-13	Sets the maximum number of rows to be fetched each time
SETNULLHANDLING Procedure on page 114-14	Sets NULL handling options
SETROWSETTAG Procedure on page 114-15	Sets the name of the element enclosing the entire result
SETROWTAG Procedure on page 114-16	Sets the name of the element enclosing each row of the result
SETSKIPROWS Procedure on page 114-17	Sets the number of rows to skip every time before generating the XML.
USEITEMTAGSFORCOLL Procedure on page 114-18	Forces the use of the collection column name appended with the tag <code>_ITEM</code> for collection elements

Table 114–1 (Cont.) Summary of DBMS_XMLGEN Package Subprograms

Subprogram	Description
USENULLATTRIBUTEINDICATOR Procedure on page 114-19	Specified whether to use an XML attribute to indicate NULLness, or to do it by omitting the inclusion of the particular entity in the XML document.

CLOSECONTEXT Procedure

This procedure closes a given context and releases all resources associated with it, including the SQL cursor and bind and define buffers. After this call, the handle cannot be used for a subsequent function call.

Syntax

```
DBMS_XMLGEN.CLOSECONTEXT (  
    ctx IN ctxHandle);
```

Parameters

Table 114–2 *CLOSECONTEXT Procedure Parameters*

Parameter	Description
ctx	The context handle to close.

CONVERT Functions

This function converts the XML data into the escaped or unescapes XML equivalent, and returns XML CLOB data in encoded or decoded format. There are several version of the function.

Syntax

Uses XMLDATA in string form (VARCHAR2):

```
DBMS_XMLGEN.CONVERT (
    xmlData IN VARCHAR2,
    flag    IN NUMBER := ENTITY_ENCODE)
RETURN VARCHAR2;
```

Uses XMLDATA in CLOB form:

```
DBMS_XMLGEN.CONVERT (
    xmlData IN CLOB,
    flag    IN NUMBER := ENTITY_ENCODE)
RETURN CLOB;
```

Parameters

Table 114–3 CONVERT Function Parameters

Parameter	Description
xmlData	The XML CLOB data to be encoded or decoded.
flag	The flag setting; ENTITY_ENCODE (default) for encode, and ENTITY_DECODE for decode.

Usage Notes

This function escapes the XML data if the ENTITY_ENCODE is specified. For example, the escaped form of the character < is <. Unescaping is the reverse transformation.

GETNUMROWSPROCESSED Function

This function retrieves the number of SQL rows processed when generating the XML using the [GETXML Functions](#) call. This count does not include the number of rows skipped before generating the XML. Note that [GETXML Functions](#) always generates an XML document, even if there are no rows present.

Syntax

```
DBMS_XMLGEN.GETNUMROWSPROCESSED (  
    ctx      IN      ctxHandle)  
RETURN NUMBER;
```

Parameters

Table 114–4 *GETNUMROWSPROCESSED Function Parameters*

Parameter	Description
ctx	The context handle obtained from the NEWCONTEXT Functions call.

Usage Notes

This function is used to determine the terminating condition if calling [GETXML Functions](#) in a loop.

GETXML Functions

This function gets the XML document. The function is overloaded.

Syntax

Gets the XML document by fetching the maximum number of rows specified. It appends the XML document to the CLOB passed in. Use this version of [GETXML Functions](#) to avoid any extra CLOB copies and to reuse the same CLOB for subsequent calls. Because of the CLOB reuse, this [GETXML Functions](#) call is potentially more efficient:

```
DBMS_XMLGEN.GETXML (
    ctx          IN ctxHandle,
    tmpclob      IN OUT NCOPY CLOB,
    dtdOrSchema IN number := NONE)
RETURN BOOLEAN;
```

Generates the XML document and returns it as a temporary CLOB. The temporary CLOB obtained from this function must be freed using the `DBMS_LOB.FREETEMPORARY` call:

```
DBMS_XMLGEN.GETXML (
    ctx          IN ctxHandle,
    dtdOrSchema IN number := NONE)
RETURN CLOB;
```

Converts the results from the SQL query string to XML format, and returns the XML as a temporary CLOB, which must be subsequently freed using the `DBMS_LOB.FREETEMPORARY` call:

```
DBMS_XMLGEN.GETXML (
    sqlQuery     IN VARCHAR2,
    dtdOrSchema  IN number := NONE)
RETURN CLOB;
```

Parameters

Table 114–5 GETXML Function Parameters

Parameter	Description
CTX	The context handle obtained from the <code>newContext</code> call.
TMPCLOB	The CLOB to which the XML document is appended.

Table 114–5 (Cont.) GETXML Function Parameters

Parameter	Description
sqlQuery	The SQL query string.
dtdOrSchema	Generate a DTD or a schema? Only <code>NONE</code> is supported.

Usage Notes

When the rows indicated by the [SETSKIPROWS Procedure](#) call are skipped, the maximum number of rows as specified by the [SETMAXROWS Procedure](#) call (or the entire result if not specified) is fetched and converted to XML. Use the [GETNUMROWSPROCESSED Function](#) to check if any rows were retrieved.

GETXMLTYPE Functions

This function gets the XML document and returns it as an `XMLTYPE`. `XMLTYPE` operations can be performed on the results. This function is overloaded.

Syntax

Generates the XML document and returns it as a `sys.XMLType`:

```
DBMS_XMLGEN.GETXMLTYPE (
    ctx          IN ctxhandle,
    dtdOrSchema IN number := NONE)
RETURN sys.XMLType;
```

Converts the results from the SQL query string to XML format, and returns the XML as a `sys.XMLType`:

```
DBMS_XMLGEN.GETXMLTYPE (
    sqlQuery     IN VARCHAR2,
    dtdOrSchema IN number := NONE)
RETURN sys.XMLType
```

Parameters

Table 114–6 GETXMLTYPE Function Parameters

Parameter	Description
<code>ctx</code>	The context handle obtained from the <code>newContext</code> call.
<code>sqlQuery</code>	The SQL query string.
<code>dtdOrSchema</code>	Generate a DTD or a schema? Only <code>NONE</code> is supported.

NEWCONTEXT Functions

This function generates and returns a new context handle. This context handle is used in [GETXML Functions](#) and other functions to get XML back from the result. There are several version of the function.

Syntax

Generates a new context handle from a query:

```
DBMS_XMLGEN.NEWCONTEXT (  
    query      IN VARCHAR2)  
RETURN ctxHandle;
```

Generates a new context handle from a query string in the form of a PL/SQL ref cursor:

```
DBMS_XMLGEN.NEWCONTEXT (  
    queryString IN SYS_REFCURSOR)  
RETURN ctxHandle;
```

Parameters

Table 114–7 NEWCONTEXT Function Parameters

Parameter	Description
query	The query, in the form of a VARCHAR, the result of which must be converted to XML.
queryString	The query string in the form of a PL/SQL ref cursor, the result of which must be converted to XML.

RESTARTQUERY Procedure

This procedure restarts the query and generates the XML from the first row. It can be used to start executing the query again, without having to create a new context.

Syntax

```
DBMS_XMLGEN.RESTARTQUERY (  
    ctx IN ctxHandle);
```

Parameters

Table 114–8 *RESTARTQUERY Procedure Parameters*

Parameter	Description
ctx	The context handle corresponding to the current query.

SETCONVERTSPECIALCHARS Procedure

This procedure sets whether or not special characters in the XML data must be converted into their escaped XML equivalent. For example, the < sign is converted to <. The default is to perform conversions. This function improves performance of XML processing when the input data cannot contain any special characters such as <, >, ", ', which must be escaped. It is expensive to scan the character data to replace the special characters, particularly if it involves a lot of data.

Syntax

```
DBMS_XMLGEN.SETCONVERTSPECIALCHARS (  
    ctx    IN ctxHandle,  
    conv   IN BOOLEAN);
```

Parameters

Table 114–9 SETCONVERTSPECIALCHARS Procedure Parameters

Parameter	Description
ctx	The context handle obtained from one of the NEWCONTEXT Functions calls.
conv	TRUE indicates that conversion is needed.

SETMAXROWS Procedure

This procedure sets the maximum number of rows to fetch from the SQL query result for every invocation of the [GETXML Functions](#) call. It is used when generating paginated results. For example, when generating a page of XML or HTML data, restrict the number of rows converted to XML or HTML by setting the `maxRows` parameter.

Syntax

```
DBMS_XMLGEN.SETMAXROWS (  
    ctx      IN ctxHandle,  
    maxRows  IN NUMBER);
```

Parameters

Table 114–10 *SETMAXROWS Procedure Parameters*

Parameter	Description
<code>ctx</code>	The context handle corresponding to the query executed.
<code>maxRows</code>	The maximum number of rows to get for each call to GETXML Functions .

SETNULLHANDLING Procedure

This procedure sets NULL handling options, handled through the `flag` parameter setting.

Syntax

```
DBMS_XMLGEN.SETNULLHANDLING(  
    ctx IN ctx,  
    flag IN NUMBER);
```

Parameters

Table 114–11 *SETNULLHANDLING Procedure Parameters*

Parameter	Description
<code>ctx</code>	The context handle corresponding to the query executed.
<code>flag</code>	The NULL handling option set. <ul style="list-style-type: none">■ <code>DROP_NULLS CONSTANT NUMBER:= 0</code>; (Default) Leaves out the tag for NULL elements.■ <code>NULL_ATTR CONSTANT NUMBER:= 1</code>; Sets <code>xsi:nil="true"</code>.■ <code>EMPTY_TAG CONSTANT NUMBER:= 2</code>; Sets, for example, <code><foo/></code>.

SETROWSETTAG Procedure

This procedure sets the name of the root element of the document. The default name is ROWSET.

Syntax

```
DBMS_XMLGEN.SETROWSETTAG (  
    ctx             IN ctxHandle,  
    rowSetTagName  IN VARCHAR2);
```

Parameters

Table 114–12 SETROWSETTAG Procedure Parameters

Parameter	Description
ctx	The context handle obtained from the NEWCONTEXT Functions call.
rowSetTagName	The name of the document element. Passing NULL indicates that you do not want the ROWSET element present.

Usage Notes

The user can set the ROWSETTAG to NULL to suppress the printing of this element. However, an error is produced if both the row and the rowset are NULL and there is more than one column or row in the output. This is because the generated XML would not have a top-level enclosing tag, and so would be invalid.

SETROWTAG Procedure

This procedure sets the name of the element separating all the rows. The default name is ROW.

Syntax

```
DBMS_XMLGEN.SETROWTAG (  
    ctx          IN ctxHandle,  
    rowTagName  IN VARCHAR2);
```

Parameters

Table 114–13 SETROWTAG Procedure Parameters

Parameter	Description
ctx	The context handle obtained from the NEWCONTEXT Functions call.
rowTagName	The name of the ROW element. Passing NULL indicates that you do not want the ROW element present.

Usage Notes

The user can set the name of the element to NULL to suppress the ROW element itself. However, an error is produced if both the row and the rowset are NULL and there is more than one column or row in the output. This is because the generated XML would not have a top-level enclosing tag, and so would be invalid.

SETSKIPROWS Procedure

This procedure skips a given number of rows before generating the XML output for every call to the [GETXML Functions](#). It is used when generating paginated results for stateless Web pages using this utility. For example, when generating the first page of XML or HTML data, set `skiprows` to zero. For the next set, set the `skiprows` to the number of rows obtained in the first case. See [GETNUMROWSPROCESSED Function](#) on page 114-6.

Syntax

```
DBMS_XMLGEN.SETSKIPROWS (  
    ctx          IN ctxHandle,  
    skipRows    IN NUMBER);
```

Parameters

Table 114–14 SETSKIPROWS Procedure Parameters

Parameter	Description
<code>ctx</code>	The context handle corresponding to the query executed.
<code>skipRows</code>	The number of rows to skip for each call to <code>getXML</code> .

USEITEMTAGSFORCOLL Procedure

This procedure overrides the default name of the collection elements. The default name for collection elements is the type name itself.

Syntax

```
DBMS_XMLGEN.USEITEMTAGSFORCOLL (  
    ctx IN ctxHandle);
```

Parameters

Table 114–15 *USEITEMTAGSFORCOLL Procedure Parameters*

Parameter	Description
ctx	The context handle.

Usage Notes

Using this function, you can override the default to use the name of the column with the `_ITEM` tag appended to it. If there is a collection of `NUMBER`, the default tag name for the collection elements is `NUMBER`.

USENULLATTRIBUTEINDICATOR Procedure

This procedure specifies whether to use an XML attribute to indicate NULLness, or to do it by omitting the inclusion of the particular entity in the XML document. It is used as a shortcut for the [SETNULLHANDLING Procedure](#).

Syntax

```
DBMS_XMLGEN.USENULLATTRIBUTEINDICATOR(  
    ctx          IN    ctxType,  
    attrind     IN    BOOLEAN := TRUE);
```

Parameters

Table 114–16 *USENULLATTRIBUTEINDICATOR Procedure Parameters*

Parameter	Description
ctx	Context handle.
attrind	Use attribute to indicate NULL?

DBMS_XMLPARSER

Using `DBMS_XMLPARSER`, you can access the contents and structure of XML documents. XML describes a class of data XML document objects. It partially describes the behavior of computer programs which process them. By construction, XML documents are conforming SGML documents.

XML documents are made up of storage units called entities, which contain either parsed or unparsed data. Parsed data is made up of characters, some of which form character data, and some of which form markup. Markup encodes a description of the document's storage layout and logical structure. XML provides a mechanism to impose constraints on the storage layout and logical structure.

A software module called an XML processor is used to read XML documents and provide access to their content and structure. It is assumed that an XML processor is doing its work on behalf of another module, called the application. This PL/SQL implementation of the XML processor (or parser) follows the W3C XML specification REC-xml-19980210 and includes the required behavior of an XML processor in terms of how it must read XML data and the information it must provide to the application.

The default behavior for this PL/SQL XML parser is to build a parse tree that can be accessed by DOM APIs, validate it if a DTD is found (otherwise, it is non-validating), and record errors if an error log is specified. If parsing fails, an application error is raised.

This chapter contains the following topics:

- [Summary of DBMS_XMLPARSER Subprograms](#)

See Also: *Oracle XML DB Developer's Guide*

Summary of DBMS_XMLPARSER Subprograms

Table 115–1 *DBMS_XMLPARSER Package Subprograms*

Method	Description
FREEPARSER on page 115-2	Frees a parser object.
GETDOCTYPE on page 115-3	Gets parsed DTD.
GETDOCUMENT on page 115-3	Gets DOM document.
GETRELEASEVERSION on page 115-4	Returns the release version of Oracle XML Parser for PL/SQL.
GETVALIDATIONMODE on page 115-4	Returns validation mode.
NEWPARSER on page 115-4	Returns a new parser instance
PARSE on page 115-4	Parses XML stored in the given url/file.
PARSEBUFFER on page 115-5	Parses XML stored in the given buffer
PARSECLOB on page 115-6	Parses XML stored in the given clob
PARSEDTD on page 115-6	Parses DTD stored in the given url/file
PARSEDTDBUFFER on page 115-7	Parses DTD stored in the given buffer
PARSEDTDCLOB on page 115-7	Parses DTD stored in the given clob
SETBASEDIR on page 115-8	Sets base directory used to resolve relative URLs.
SETDOCTYPE on page 115-8	Sets DTD.
SETERRORLOG on page 115-8	Sets errors to be sent to the specified file
SETPRESERVEWHITESPACE on page 115-9	Sets white space preserve mode
SETVALIDATIONMODE on page 115-9	Sets validation mode.
SHOWWARNINGS on page 115-10	Turns warnings on or off.

FREEPARSER

Frees a parser object.

Syntax

```
PROCEDURE FREEPARSER(
  P PARSER);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.

GETDOCTYPE

Returns the parsed DTD; this function must be called only after a DTD is parsed.

Syntax

```
FUNCTION GETDOCTYPE(
  P PARSER)
RETURN DOMDOCUMENTTYPE;
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.

GETDOCUMENT

Returns the document node of a DOM tree document built by the parser; this function must be called only after a document is parsed.

Syntax

```
FUNCTION GETDOCUMENT(
  P PARSER)
RETURN DOMDOCUMENT;
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.

GETRELEASEVERSION

Returns the release version of the Oracle XML parser for PL/SQL.

Syntax

```
FUNCTION GETRELEASEVERSION  
RETURN VARCHAR2;
```

GETVALIDATIONMODE

Retrieves validation mode; `TRUE` for validating, `FALSE` otherwise.

Syntax

```
FUNCTION GETVALIDATIONMODE(  
    P_PARSER)  
RETURN BOOLEAN;
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.

NEWPARSER

Returns a new parser instance. This function must be called before the default behavior of Parser can be changed and if other parse methods need to be used.

Syntax

```
FUNCTION NEWPARSER  
RETURN PARSER;
```

PARSE

Parses XML stored in the given URL or file. An application error is raised if parsing fails. There are several versions of this method.

Syntax	Description
<pre>FUNCTION PARSE(URL VARCHAR2) RETURN DOMDOCUMENT;</pre>	Returns the built DOM Document. This is meant to be used when the default parser behavior is acceptable and just a url/file needs to be parsed.
<pre>PROCEDURE PARSE(P PARSE, URL VARCHAR2);</pre>	Any changes to the default parser behavior should be effected before calling this procedure.

Parameter	IN / OUT	Description
URL	(IN)	Complete path of the url/file to be parsed.
P	(IN)	Parser instance.

PARSEBUFFER

Parses XML stored in the given buffer. Any changes to the default parser behavior should be effected before calling this procedure. An application error is raised if parsing fails.

Syntax

```
PROCEDURE PARSEBUFFER(
  P  PARSE,
  DOC VARCHAR2);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
DOC	(IN)	XML document buffer to parse.

PARSECLOB

Parses XML stored in the given clob. Any changes to the default parser behavior should be effected before calling this procedure. An application error is raised if parsing fails.

Syntax

```
PROCEDURE PARSECLOB(  
    P   _PARSER,  
    DOC CLOB);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
DOC	(IN)	XML document buffer to parse.

PARSEDTD

Parses the DTD stored in the given URL or file. Any changes to the default parser behavior should be effected before calling this procedure. An application error is raised if parsing fails.

Syntax

```
PROCEDURE PARSEDTD(  
    P   _PARSER,  
    URL  VARCHAR2,  
    ROOT VARCHAR2);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
URL	(IN)	Complete path of the URL or file to be parsed.
ROOT	(IN)	Name of the root element.

PARSEDTDBUFFER

Parses the DTD stored in the given buffer. Any changes to the default parser behavior should be effected before calling this procedure. An application error is raised if parsing fails.

Syntax

```
PROCEDURE PARSEDTDBUFFER(
    P    PARSE,
    DTD  VARCHAR2,
    ROOT VARCHAR2);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
DTD	(IN)	DTD buffer to parse.
ROOT	(IN)	Name of the root element.

PARSEDTDCLOB

Parses the DTD stored in the given clob. Any changes to the default parser behavior should be effected before calling this procedure. An application error is raised if parsing fails.

Syntax

```
PROCEDURE PARSEDTDCLOB(
    P    PARSE,
    DTD  CLOB,
    ROOT VARCHAR2);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
DTD	(IN)	DTD Clob to parse.
ROOT	(IN)	Name of the root element.

SETBASEDIR

Sets base directory used to resolve relative URLs. An application error is raised if parsing fails.

Syntax

```
PROCEDURE SETBASEDIR(  
    P    PARSER,  
    DIR VARCHAR2);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
DIR	(IN)	Directory used as a base directory.

SETDOCTYPE

Sets a DTD to be used by the parser for validation. This call should be made before the document is parsed.

Syntax

```
PROCEDURE SETDOCTYPE(  
    P    PARSER,  
    DTD DOMDOCUMENTTYPE);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
DTD	(IN)	DTD to set.

SETERRORLOG

Sets errors to be sent to the specified file.

Syntax

```
PROCEDURE SETERRORLOG(  
    P    PARSER,  
    FILENAME VARCHAR2);
```


Parameter	IN / OUT	Description
P	(IN)	Parser instance.
FILENAME	(IN)	Complete path of the file to use as the error log.

SETPRESERVEWHITESPACE

Sets whitespace preserving mode.

Syntax

```
PROCEDURE SETPRESERVEWHITESPACE(
    P    PARSER,
    YES  BOOLEAN);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
YES	(IN)	Mode to set: TRUE - preserve, FALSE - don't preserve.

SETVALIDATIONMODE

Sets validation mode.

Syntax

```
PROCEDURE SETVALIDATIONMODE(
    P    PARSER,
    YES  BOOLEAN);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
YES	(IN)	Mode to set: TRUE - validate, FALSE - don't validate.

SHOWWARNINGS

Turns warnings on or off.

Syntax

```
PROCEDURE SHOWWARNINGS(  
    P    PARSE,   
    YES BOOLEAN);
```

Parameter	IN / OUT	Description
P	(IN)	Parser instance.
YES	(IN)	Mode to set: TRUE - show warnings, FALSE - don't show warnings.

DBMS_XMLQUERY

DBMS_XMLQUERY provides database-to-XMLType functionality. Whenever possible, use DBMS_XMLGEN, a built-in package in C, instead of DBMS_XMLQUERY.

See Also: *Oracle XML DB Developer's Guide*

This chapter contains the following topics:

- [Using DBMS_XMLQUERY](#)
 - [Constants](#)
 - [Types](#)
- [Summary of DBMS_XMLQUERY Subprograms](#)

Using DBMS_XMLQUERY

- [Constants](#)

Constants

Table 116–1 Constants of DBMS_XMLQUERY

Constant	Description
DB_ENCODING	Used to signal that the DB character encoding is to be used.
DEFAULT_ROWSETTAG	The tag name for the element enclosing the XML generated from the result set (that is, for most cases the root node tag name) -- ROWSET.
DEFAULT_ERRORTAG	The default tag to enclose raised errors -- ERROR.
DEFAULT_ROWIDATTR	The default name for the cardinality attribute of XML elements corresponding to <code>db.records</code> -- NUM
DEFAULT_ROWTAG	The default tag name for the element corresponding to <code>db.records</code> -- ROW
DEFAULT_DATE_FORMAT	Default date mask -- 'MM/dd/yyyy HH:mm:ss'
ALL_ROWS	Indicates that all rows are needed in the output.
NONE	Used to specifies that the output should not contain any XML metadata (for example, no DTD).
DTD	Used to specify that the generation of the DTD is desired.
SCHEMA	Used to specify that the generation of the XML Schema is desired.
LOWER_CASE	Use lower case tag names.
UPPER_CASE	Use upper case tag names.

Types

Table 116–2 Types of DBMS_XMLQUERY

Type	Description
ctxType	The type of the query context handle. This is the return type of NEWCONTEXT .

Summary of DBMS_XMLQUERY Subprograms

Table 116–3 DBMS_XMLQUERY Package Subprograms

Method	Description
CLOSECONTEXT on page 116-4	Closes or deallocates a particular query context.
GETDTD on page 116-5	Generates the DTD.
GETEXCEPTIONCONTENT on page 116-5	Returns the thrown exception's error code and error message.
GETNUMROWSPROCESSED on page 116-6	Returns the number of rows processed for the query.
GETVERSION on page 116-6	Prints the version of the XSU in use.
GETXML on page 116-7	Generates the XML document.
NEWCONTEXT on page 116-8	Creates a query context and it returns the context handle.
PROPAGATEORIGINALEXCEPTION on page 116-8	Tells the XSU that if an exception is raised, and is being thrown, the XSU should throw the very exception raised; rather than, wrapping it with an <code>OracleXMLSQLException</code> .
REMOVEXSLTPARAM on page 116-9	Removes a particular top-level stylesheet parameter.
SETBINDVALUE on page 116-9	Sets a value for a particular bind name.
SETCOLLIDATTRNAME on page 116-10	Sets the name of the id attribute of the collection element's separator tag.
SETDATAHEADER on page 116-10	Sets the XML data header.
SETDATEFORMAT on page 116-11	Sets the format of the generated dates in the XML document.
SETENCODINGTAG on page 116-11	Sets the encoding processing instruction in the XML document.
SETERRORTAG on page 116-12	Sets the tag to be used to enclose the XML error documents.
SETMAXROWS on page 116-12	Sets the maximum number of rows to be converted to XML.
SETMETAHEADER on page 116-13	Sets the XML meta header.

Table 116–3 (Cont.) DBMS_XMLQUERY Package Subprograms

Method	Description
SETRAISEEXCEPTION on page 116-13	Tells the XSU to throw the raised exceptions.
SETRAISENOROWSEXCEPTION on page 116-14	Tells the XSU to throw or not to throw an <code>OracleXMLNoRowsException</code> in the case when for one reason or another, the XML document generated is empty.
SETROWIDATTRNAME on page 116-14	Sets the name of the id attribute of the row enclosing tag.
SETROWIDATTRVALUE on page 116-15	Specifies the scalar column whose value is to be assigned to the id attribute of the row enclosing tag.
SETROWSETTAG on page 116-15	Sets the tag to be used to enclose the XML dataset.
SETROWTAG on page 116-15	Sets the tag to be used to enclose the XML element.
SETSKIPROWS on page 116-16	Sets the number of rows to skip.
SETSQLTOXMLNAMEESCAPING on page 116-16	This turns on or off escaping of XML tags in the case that the SQL object name, which is mapped to a XML identifier, is not a valid XML identifier.
SETSTYLESHEETHEADER on page 116-17	Sets the stylesheet header.
SETTAGCASE on page 116-17	Specified the case of the generated XML tags.
SETXSLT on page 116-18	Registers a stylesheet to be applied to generated XML.
SETXSLTPARAM on page 116-19	Sets the value of a top-level stylesheet parameter.
USENULLATTRIBUTEINDICATOR on page 116-19	Specifies weather to use an XML attribute to indicate NULLness.
USETYPEFORCOLLELEMTAG on page 116-20	Tells the XSU to use the collection element's type name as the collection element tag name.

CLOSECONTEXT

Closes or deallocates a particular query context

Syntax

```
PROCEDURE CLOSECONTEXT(  
    CTXHDL IN CTXTYPE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

GETDTD

Generates and returns the DTD based on the SQL query used to initialize the context. The options are described in the following table.

Syntax	Description
<pre>FUNCTION GETDTD(CTXHDL IN CTXTYPE, WITHVER IN BOOLEAN := FALSE) RETURN CLOB;</pre>	Function that generates the DTD based on the SQL query used to initialize the context.
<pre>PROCEDURE GETDTD(CTXHDL IN CTXTYPE, XDOC IN CLOB, WITHVER IN BOOLEAN := FALSE);</pre>	Procedure that generates the DTD based on the SQL query used to initialize the context; specifies the output CLOB for XML document result.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
WITHVER	(IN)	Generate the version information? TRUE for yes .
XDOC	(IN)	CLOB into which to write the generated XML document.

GETEXCEPTIONCONTENT

Returns the thrown exception's SQL error code and error message through the procedure's OUT parameters. This procedure is a work around the JVM functionality

GETNUMROWSPROCESSED

that obscures the original exception by its own exception, rendering PL/SQL unable to access the original exception content.

Syntax

```
PROCEDURE GETEXCEPTIONCONTENT(  
    CTXHDL IN CTXTYPE,  
    ERRNO OUT NUMBER,  
    ERRMSG OUT VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
ERRNO	(OUT)	Error number.
ERRMSG	(OUT)	Error message.

GETNUMROWSPROCESSED

Return the number of rows processed for the query.

Syntax

```
FUNCTION GETNUMROWSPROCESSED(  
    CTXHDL IN CTXTYPE)  
RETURN NUMBER;
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

GETVERSION

Prints the version of the XSU in use.

Syntax

```
PROCEDURE GETVERSION();
```

GETXML

Creates the new context, executes the query, gets the XML back and closes the context. This is a convenience function. The context doesn't have to be explicitly opened or closed. The options are described in the following table.

Syntax	Description
<pre>FUNCTION GETXML(SQLQUERY IN VARCHAR2, METATYPE IN NUMBER := NONE) RETURN CLOB;</pre>	This function uses a SQL query in string form.
<pre>FUNCTION GETXML(SQLQUERY IN CLOB, METATYPE IN NUMBER := NONE) RETURN CLOB;</pre>	This function uses a SQL query in CLOB form.
<pre>FUNCTION GETXML(CTXHDL IN CTXTYPE, METATYPE IN NUMBER := NONE) RETURN CLOB;</pre>	This function generates the XML document based on a SQL query used to initialize the context.
<pre>PROCEDURE GETXML(CTXHDL IN CTXTYPE, XDOC IN CLOB, METATYPE IN NUMBER := NONE);</pre>	This procedure generates the XML document based on the SQL query used to initialize the context.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
METATYPE	(IN)	XML metadata type (NONE, DTD, or SCHEMA).
SQLQUERY	(IN)	SQL query.
XDOC	(IN)	CLOB into which to write the generated XML document.

NEWCONTEXT

Creates a query context and it returns the context handle. The options are described in the following table.

Syntax	Description
<pre>FUNCTION NEWCONTEXT(SQLQUERY IN VARCHAR2) RETURN CTXTYPE;</pre>	Creates a query context from a string.
<pre>FUNCTION NEWCONTEXT(SQLQUERY IN CLOB) RETURN CTXTYPE;</pre>	Creates a query context from a CLOB.

Parameter	IN / OUT	Description
SQLQUERY	(IN)	SQL query, the results of which to convert to XML.

PROPAGATEORIGINALEXCEPTION

Specifies whether to throw every original exception raised or to wrap it in an `OracleXMLSQLException`.

Syntax

```
PROCEDURE propagateOriginalException(  
    CTXHDL IN CTXTYPE,  
    FLAG IN BOOLEAN);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	TRUE if want to propagate original exception, FALSE to wrap in <code>OracleXMLException</code> .

REMOVEXSLTPARAM

Removes the value of a top-level stylesheet parameter. If no stylesheet is registered, this method is not operational.

Syntax

```
PROCEDURE REMOVEXSLTPARAM(
    CTXHDL IN CTXTYPE,
    NAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
NAME	(IN)	Name of the top level stylesheet parameter.

SETBINDVALUE

Sets a value for a particular bind name.

Syntax

```
PROCEDURE SETBINDVALUE(
    CTXHDL IN CTXTYPE,
    BINDNAME IN VARCHAR2,
    BINDVALUE IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
BINDNAME	(IN)	Bind name.
BINDVALUE	(IN)	Bind value.

SETCOLLIDATTRNAME

Sets the name of the id attribute of the collection element's separator tag. Passing `NULL` or an empty string for the tag causes the row id attribute to be omitted.

Syntax

```
PROCEDURE SETCOLLIDATTRNAME(  
    CTXHDL IN CTXTYPE,  
    ATTRNAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
ATTRNAME	(IN)	Attribute name.

SETDATAHEADER

Sets the XML data header. The data header is an XML entity that is appended at the beginning of the query-generated XML entity, the `rowset`. The two entities are enclosed by the `docTag` argument. The last data header specified is used. Passing `NULL` for the `header` parameter unsets the data header.

Syntax

```
PROCEDURE SETDATAHEADER(  
    CTXHDL IN CTXTYPE,  
    HEADER IN CLOB := NULL,  
    TAG IN VARCHAR2 := NULL);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
HEADER	(IN)	Header.
TAG	(IN)	Tag used to enclose the data header and the rowset.

SETDATEFORMAT

Sets the format of the generated dates in the XML document. The syntax of the date format pattern, the date mask, should conform to the requirements of the `java.text.SimpleDateFormat` class. Setting the mask to `NULL` or an empty string sets the default mask -- `DEFAULT_DATE_FORMAT`.

Syntax

```
PROCEDURE SETDATEFORMAT(  
    CTXHDL IN CTXTYPE,  
    MASK IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
MASK	(IN)	The date mask.

SETENCODINGTAG

Sets the encoding processing instruction in the XML document.

Syntax

```
PROCEDURE SETENCODINGTAG(  
    CTXHDL IN CTXTYPE,  
    ENC IN VARCHAR2 := DB_ENCODING);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
ENC	(IN)	The encoding to use.

SETERRORTAG

Sets the tag to be used to enclose the XML error documents.

Syntax

```
PROCEDURE SETERRORTAG(  
    CTXHDL IN CTXTYPE,  
    TAG IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
TAG	(IN)	Tag name.

SETMAXROWS

Sets the maximum number of rows to be converted to XML. By default, there is no set maximum.

Syntax

```
PROCEDURE SETMAXROWS (  
    CTXHDL IN CTXTYPE,  
    ROWS IN NUMBER);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
ROWS	(IN)	Maximum number of rows to generate.

SETMETAHEADER

Sets the XML meta header. When set, the header is inserted at the beginning of the metadata part (DTD or XMLSchema) of each XML document generated by this object. The last meta header specified is used. Passing in `NULL` for the `header` parameter unsets the meta header.

Syntax

```
PROCEDURE SETMETAHEADER(
    CTXHDL IN CTXTYPE,
    HEADER IN CLOB := NULL);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
HEADER	(IN)	Header.

SETRAISEEXCEPTION

Specifies whether to throw raised exceptions. If this call isn't made or if `FALSE` is passed to the `FLAG` argument, the XSU catches the SQL exceptions and generates an XML document from the exception message.

Syntax

```
PROCEDURE SETRAISEEXCEPTION(
    CTXHDL IN CTXTYPE,
    FLAG IN BOOLEAN:=TRUE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Throw raised exceptions? TRUE for yes, otherwise FALSE.

SETRAISENOROWSEXCEPTION

Specifies whether to throw an `OracleXMLNoRowsException` when the generated XML document is empty. By default, the exception is not thrown.

Syntax

```
PROCEDURE SETRAISENOROWSEXCEPTION(  
    CTXHDL IN CTXTYPE,  
    FLAG IN BOOLEAN:=FALSE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Throws an <code>OracleXMLNoRowsException</code> if set to <code>TRUE</code> .

SETROWIDATTRNAME

Sets the name of the id attribute of the row enclosing tag. Passing `NULL` or an empty string for the tag causes the row id attribute to be omitted.

Syntax

```
PROCEDURE SETROWIDATTRNAME(  
    CTXHDL IN CTXTYPE,  
    ATTRNAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
ATTRNAME	(IN)	Attribute name.

SETRROWIDATTRVALUE

Specifies the scalar column whose value is to be assigned to the `id` attribute of the row enclosing tag. Passing `NULL` or an empty string for the `colName` assigns the row count value (0, 1, 2 and so on) to the row `id` attribute.

Syntax

```
PROCEDURE SETROWIDATTRVALUE(  
    CTXHDL IN CTXTYPE,  
    COLNAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
COLNAME	(IN)	Column whose value is to be assigned to the row <code>id</code> attribute.

SETRROWSETTAG

Sets the tag to be used to enclose the XML dataset.

Syntax

```
PROCEDURE SETROWSETTAG(  
    CTXHDL IN CTXTYPE,  
    TAG IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
TAG	(IN)	Tag name.

SETRROWTAG

Sets the tag to be used to enclose the XML element corresponding to a `db.record`.

Syntax

```
PROCEDURE SETROWTAG(
    CTXHDL IN CTXTYPE,
    TAG IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
TAG	(IN)	Tag name.

SETSKIPROWS

Sets the number of rows to skip. By default, 0 rows are skipped.

Syntax

```
PROCEDURE SETSKIPROWS(
    CTXHDL IN CTXTYPE,
    ROWS IN NUMBER);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
ROWS	(IN)	Maximum number of rows to skip.

SETSQLTOXMLNAMEESCAPING

This turns on or off escaping of XML tags in the case that the SQL object name, which is mapped to a XML identifier, is not a valid XML identifier.

Syntax

```
PROCEDURE SETSQLTOXMLNAMEESCAPING(
    CTXHDL IN CTXTYPE,
```

```
FLAG IN BOOLEAN := TRUE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Turn on escaping? TRUE for yes, otherwise FALSE.

SETSTYLESHEETHEADER

Sets the stylesheet header (the stylesheet processing instructions) in the generated XML document. Passing `NULL` for the `uri` argument will unset the stylesheet header and the stylesheet type.

Syntax

```
PROCEDURE SETSTYLESHEETHEADER(
    CTXHDL IN CTXTYPE,
    URI IN VARCHAR2,
    TYPE IN VARCHAR2 := 'TEXT/XSL');
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
URI	(IN)	Stylesheet URI.
TYPE	(IN)	Stylesheet type; defaults to "text/xsl".

SETTAGCASE

Specifies the case of the generated XML tags.

Syntax

```
PROCEDURE SETTAGCASE(
    CTXHDL IN CTXTYPE,
```

```
TCASE IN NUMBER);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
TCASE	(IN)	The tag's case: <ul style="list-style-type: none">■ 0 for as are■ 1 for lower case■ 2 for upper case

SETXSLT

Registers a stylesheet to be applied to generated XML. If a stylesheet was already registered, it is replaced by the new one. The options are described in the following table. Passing NULL for the `uri` argument or an empty string for the `stylesheet` argument will unset the stylesheet header and type.

Syntax	Description
<pre>PROCEDURE SETXSLT(CTXHDL IN CTXTYPE, URI IN VARCHAR2, REF IN VARCHAR2 := NULL);</pre>	To un-register the stylesheet pass in a null for the uri.
<pre>PROCEDURE SETXSLT(CTXHDL IN CTXTYPE, STYLESHEET CLOB, REF IN VARCHAR2 := NULL);</pre>	To un-register the stylesheet pass in a null or an empty string for the stylesheet.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
URI	(IN)	Stylesheet URI.
STYLESHEET	(IN)	Stylesheet.

Parameter	IN / OUT	Description
REF	(IN)	URL to include, imported and external entities.

SETXSLTPARAM

Sets the value of a top-level stylesheet parameter. The parameter value is expected to be a valid XPath expression; the string literal values would therefore have to be quoted explicitly. If no stylesheet is registered, this method is not operational.

Syntax

```
PROCEDURE SETXSLTPARAM(
    CTXHDL IN CTXTYPE,
    NAME IN VARCHAR2,
    VALUE IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
NAME	(IN)	Name of the top level stylesheet parameter.
VALUE	(IN)	Value to be assigned to the stylesheet parameter.

USENULLATTRIBUTEINDICATOR

Specifies whether to use an XML attribute to indicate NULLness, or to do this by omitting the particular entity in the XML document.

Syntax

```
PROCEDURE SETNULLATTRIBUTEINDICATOR(
    CTXHDL IN CTXTYPE,
    FLAG IN BOOLEAN);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Sets attribute to NULL if TRUE, omits from XML document if FALSE.

USETYPEFORCOLLELEMTAG

Specifies whether to use the collection element's type name as its element tag name. By default, the tag name for elements of a collection is the collection's tag name followed by `_item`.

Syntax

```
PROCEDURE USETYPEFORCOLLELEMTAG(
    CTXHDL IN CTXTYPE,
    FLAG IN BOOLEAN := TRUE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Turn on use of the type name?

DBMS_XMLSAVE provides XML to database-type functionality.

See Also: *Oracle XML DB Developer's Guide*

This chapter contains the following topics:

- [Using DBMS_XMLSAVE](#)
 - [Constants](#)
 - [Types](#)
- [Summary of DBMS_XMLSAVE Subprograms](#)

Using DBMS_XMLSAVE

- [Constants](#)
- [Types](#)

Constants

Table 117–1 Constants of DBMS_XMLSAVE

Constant	Description
DEFAULT_ROWTAG	The default tag name for the element corresponding to database records -- ROW
DEFAULT_DATE_FORMAT	Default date mask: 'MM/dd/yyyy HH:mm:ss'
MATCH_CASE	Used to specify that when mapping XML elements to database entities; the XSU should be case sensitive.
IGNORE_CASE	Used to specify that when mapping XML elements to database entities the XSU should be case insensitive.

Types

Table 117–2 Types of DBMS_XMLSAVE

Type	Description
ctxType	The type of the query context handle. The type of the query context handle. This the return type of NEWCONTEXT .

Summary of DBMS_XMLSAVE Subprograms

Table 117–3 DBMS_XMLSAVE Package Subprograms

Method	Description
CLEARKEYCOLUMNLIST on page 117-4	Clears the key column list.
CLEARUPDATECOLUMNLIST on page 117-4	Clears the update column list.
CLOSECONTEXT on page 117-5	It closes/deallocates a particular save context.
DELETEXML on page 117-5	Deletes records specified by data from the XML document, from the table specified at the context creation time.
GETEXCEPTIONCONTENT on page 117-6	Via its arguments, this method returns the thrown exception's error code and error message.
INSERTXML on page 117-6	Inserts the XML document into the table specified at the context creation time.
NEWCONTEXT on page 117-7	Creates a save context, and returns the context handle.
PROPAGATEORIGINALEXCEPTION on page 117-7	Tells the XSU that if an exception is raised, and is being thrown, the XSU should throw the very exception raised; rather than, wrapping it with an <code>OracleXMLSQLException</code> .
REMOVEXSLTPARAM on page 117-8	Removes the value of a top-level stylesheet parameter
SETBATCHSIZE on page 117-8	Changes the batch size used during DML operations.
SETDATEFORMAT on page 117-9	Sets the commit batch size.
SETCOMMITBATCH on page 117-9	Sets the format of the generated dates in the XML document.
SETIGNORECASE on page 117-10	The XSU does mapping of XML elements to database.
SETKEYCOLUMN on page 117-10	This methods adds a column to the key column list.
SETPRESERVEWHITESPACE on page 117-11	Tells the XSU whether to preserve whitespace or not.
SETROWTAG on page 117-11	Names the tag used in the XML document to enclose the XML elements corresponding to database.

Table 117-3 (Cont.) DBMS_XMLSAVE Package Subprograms

Method	Description
SETSQLTOXMLNAMEESCAPING on page 117-11	This turns on or off escaping of XML tags in the case that the SQL object name, which is mapped to a XML identifier, is not a valid XML identifier.
SETUPDATECOLUMN on page 117-12	Adds a column to the update column list.
SETXSLT on page 117-12	Registers a XSL transform to be applied to the XML to be saved.
SETXSLTPARAM on page 117-13	Sets the value of a top-level stylesheet parameter.
UPDATEXML on page 117-14	Updates the table given the XML document.

CLEARKEYCOLUMNLIST

Clears the key column list.

Syntax

```
PROCEDURE CLEARKEYCOLUMNLIST(
    CTXHDL IN CTXTYPE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

CLEARUPDATECOLUMNLIST

Clears the update column list.

Syntax

```
PROCEDURE CLEARUPDATECOLUMNLIST(
    CTXHDL IN CTXTYPE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

CLOSECONTEXT

Closes/deallocates a particular save context.

Syntax

```
PROCEDURE CLOSECONTEXT(
    CTXHDL IN CTXTYPE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

DELETEXML

Deletes records specified by data from the XML document from the table specified at the context creation time, and returns the number of rows deleted. The options are described in the following table.

Syntax	Description
<pre>FUNCTION DELETEXML(CTXHDL IN CTXTYPE, XDOC IN VARCHAR2) RETURN NUMBER;</pre>	Uses a VARCHAR2 type for the XDOC parameter.
<pre>FUNCTION DELETEXML(CTXHDL IN CTXTYPE, XDOC IN CLOB) RETURN NUMBER;</pre>	Uses a CLOB type for the XDOC parameter.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
XDOC	(IN)	String containing the XML document.

GETEXCEPTIONCONTENT

Through its arguments, this method returns the thrown exception's error code and error message, SQL error code. This is to get around the fact that the JVM throws an exception on top of whatever exception was raised; thus, rendering PL/SQL unable to access the original exception.

Syntax

```
PROCEDURE GETEXCEPTIONCONTENT(  
    CTXHDL IN CTXTYPE,  
    ERRNO OUT NUMBER,  
    ERRMSG OUT VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
ERRNO	(IN)	Error number.
ERRMSG	(IN)	Error message.

INSERTXML

Inserts the XML document into the table specified at the context creation time, and returns the number of rows inserted. The options are described in the following table.

Syntax	Description
<pre>FUNCTION INSERTXML(CTXHDL IN CTXTYPE, XDOC IN VARCHAR2) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a VARCHAR2.
<pre>FUNCTION INSERTXML(CTXHDL IN CTXTYPE, XDOC IN CLOB) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a CLOB.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
XDOC	(IN)	String containing the XML document.

NEWCONTEXT

Creates a save context, and returns the context handle.

Syntax

```
FUNCTION NEWCONTEXT(
    TARGETTABLE IN VARCHAR2)
RETURN CTXTYPE;
```

Parameter	IN / OUT	Description
TARGETTABLE	(IN)	The target table into which to load the XML document.

PROPAGATEORIGINALEXCEPTION

Tells the XSU that if an exception is raised, and is being thrown, the XSU should throw the very exception raised; rather than, wrapping it with an `OracleXMLSQLException`.

Syntax

```
PROCEDURE PROPAGATEORIGINALEXCEPTION(
    CTXHDL IN CTXTYPE,
    FLAG IN BOOLEAN);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Propagate the original exception? 0=FALSE, 1=TRUE.

REMOVEXSLTPARAM

Removes the value of a top-level stylesheet parameter.

Syntax

```
PROCEDURE REMOVEXSLTPARAM(  
    CTXHDL IN CTXTYPE,  
    NAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
NAME	(IN)	Parameter name.

SETBATCHSIZE

Changes the batch size used during DML operations. When performing inserts, updates or deletes, it is better to batch the operations so that they get executed in one shot rather than as separate statements. The flip side is that more memory is needed to buffer all the bind values. Note that when batching is used, a commit occurs only after a batch is executed. So if one of the statement inside a batch fails, the whole batch is rolled back. This is a small price to pay considering the performance gain; nevertheless, if this behavior is unacceptable, then set the batch size to 1.

Syntax

```
PROCEDURE SETBATCHSIZE(  
    CTXHDL IN CTXTYPE,  
    BATCHSIZE IN NUMBER);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
BATCHSIZE	(IN)	Batch size.

SETCOMMITBATCH

Sets the commit batch size. The commit batch size refers to the number of records inserted after which a commit should follow. If `BATCHSIZE` is less than 1 or the session is in "auto-commit" mode, using the XSU does not make any explicit commits. By default, `COMMITBATCH` is 0.

Syntax

```
PROCEDURE SETCOMMITBATCH(
    CTXHDL IN CTXTYPE,
    BATCHSIZE IN NUMBER);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
BATCHSIZE	(IN)	Commit batch size.

SETDATEFORMAT

Sets the format of the generated dates in the XML document. The syntax of the date format pattern, the date mask, should conform to the requirements of the class `java.text.SimpleDateFormat`. Setting the mask to `<code>null</code>` or an empty string unsets the date mask.

Syntax

```
PROCEDURE SETDATEFORMAT(
    CTXHDL IN CTXTYPE,
    MASK IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
MASK	(IN)	Syntax of the date format pattern..

SETIGNORECASE

The XSU does mapping of XML elements to db columns/attributes based on the element names (XML tags). This function tells the XSU to do this match case insensitive.

Syntax

```
PROCEDURE SETIGNORECASE(  
    CTXHDL IN CTXTYPE,  
    FLAG IN NUMBER);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Ignore tag case in the XML doc? 0=FALSE, 1=TRUE.

SETKEYCOLUMN

This method adds a column to the "key column list". The value for the column cannot be NULL. In case of update or delete, the columns in the key column list make up the WHERE clause of the statement. The key columns list must be specified before updates can complete; this is optional for delete operations.

Syntax

```
PROCEDURE SETKEYCOLUMN(  
    CTXHDL IN CTXTYPE,  
    COLNAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
COLNAME	(IN)	Column to be added to the key column list; cannot be NULL.

SETPRESERVEWHITESPACE

Tells the XSU whether or not to preserve whitespace.

Syntax

```
PROCEDURE SETPRESERVEWHITESPACE(
    CTXHDL IN CTXTYPE,
    FLAG IN BOOLEAN := TRUE);
```

Parameter	IN / OUT	Description
ctxHdl	(IN)	Context handle.
flag	(IN)	Should XSU preserve whitespace?

SETROWTAG

Names the tag used in the XML document to enclose the XML elements corresponding to db. records.

Syntax

```
PROCEDURE SETROWTAG(
    CTXHDL IN CTXTYPE,
    TAG IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
TAG	(IN)	Tag name.

SETSQLTOXMLNAMEESCAPING

Turns on or off escaping of XML tags in the case that the SQL object name, which is mapped to a XML identifier, is not a valid XML identifier.

Syntax

```
PROCEDURE SETSQLTOXMLNAMEESCAPING(  
    CTXHDL IN CTXTYPE,  
    FLAG IN BOOLEAN := TRUE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
FLAG	(IN)	Turn on escaping?

SETUPDATECOLUMN

Adds a column to the update column list. In case of insert, the default is to insert values to all the columns in the table; on the other hand, in case of updates, the default is to only update the columns corresponding to the tags present in the ROW element of the XML document. When the update column list is specified, the columns making up this list alone will get updated or inserted into.

Syntax

```
PROCEDURE SETUPDATECOLUMN(  
    CTXHDL IN CTXTYPE,  
    COLNAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
COLNAME	(IN)	Column to be added to the update column list.

SETXSLT

Registers an XSL transform to be applied to the XML to be saved. If a stylesheet was already registered, it gets replaced by the new one. To un-register the stylesheet, pass in null for the URI. The options are described in the following table.

Syntax	Description
<pre>PROCEDURE setXSLT(ctxHdl IN ctxType, uri IN VARCHAR2, ref IN VARCHAR2 := null);</pre>	Passes in the stylesheet through a URI.
<pre>PROCEDURE setXSLT(ctxHdl IN ctxType, stylesheet IN CLOB, ref IN VARCHAR2 := null);</pre>	Passes in the stylesheet through a CLOB.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
URI	(IN)	URI to the stylesheet to register.
REF	(IN)	URL for include, import, and external entities.
STYLESHEET	(IN)	CLOB containing the stylesheet to register.

SETXSLTPARAM

Sets the value of a top-level stylesheet parameter. The parameter is expected to be a valid XPath expression; literal values would therefore have to be explicitly quoted.

Syntax

```
PROCEDURE SETXSLTPARAM(
  CTXHDL IN CTXTYPE,
  NAME IN VARCHAR2,
  VALUE IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
NAME	(IN)	Parameter name.
VALUE	(IN)	Parameter value as an XPath expression

UPDATEXML

Updates the table specified at the context creation time with data from the XML document, and returns the number of rows updated. The options are described in the following table.

Syntax	Description
<pre>FUNCTION UPDATEXML(CTXHDL IN CTXTYPE, XDOC IN VARCHAR2) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a VARCHAR2.
<pre>FUNCTION UPDATEXML(CTXHDL IN CTXTYPE, XDOC IN CLOB) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a CLOB.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
XDOC	(IN)	String containing the XML document.

DBMS_XMLSCHEMA

DBMS_XMLSCHEMA package provides procedures to register and delete XML schemas. It is created by script `dbmsxsch.sql` during Oracle database installation.

This chapter contains the following topics:

- [Constants of DBMS_XMLSCHEMA](#)
- [Summary of DBMS_XMLSCHEMA Subprograms](#)
- [Catalog Views of the DBMS_XMLSCHEMA](#)

See Also: *Oracle XML DB Developer's Guide*

Constants of DBMS_XMLSCHEMA

Table 118–1 Constants of DBMS_XMLSCHEMA

Constant	Description
DELETE_RESTRICT	CONSTANT NUMBER := 1;
DELETE_INVALIDATE	CONSTANT NUMBER := 2;
DELETE_CASCADE	CONSTANT NUMBER := 3;
DELETE_CASCADE_FORCE	CONSTANT NUMBER := 4;

Summary of DBMS_XMLSCHEMA Subprograms

Table 118–2 DBMS_XMLSCHEMA Package Subprograms

Method	Description
COMPILESCHEMA on page 118-4	Used to re-compile an already registered XML schema. This is useful for bringing a schema in an invalid state to a valid state.
COPYEVOLVE on page 118-5	Evolves registered schemas so that existing XML instances remain valid.
DELETESCHEMA on page 118-8	Removes the schema from the database.
GENERATEBEAN on page 118-10	Generates the Java bean code corresponding to a registered XML schema
GENERATESCHEMA on page 118-11	Generates an XML schema from an oracle type name.
GENERATESCHEMAS on page 118-12	Generates several XML schemas from an oracle type name.
REGISTERSCHEMA on page 118-13	Registers the specified schema for use by Oracle. This schema can then be used to store documents conforming to this.
REGISTERURI on page 118-16	Registers an XMLSchema specified by a URI name.

COMPILESCHEMA

This procedure can be used to re-compile an already registered XML schema. This is useful for bringing a schema in an invalid state to a valid state. Can result in a `ORA-31001 exception: invalid resource handle or path name.`

Syntax

```
PROCEDURE COMPILESCHEMA(  
    SCHEMAURL IN VARCHAR2);
```

Parameter	IN / OUT	Description
SCHEMAURL	(IN)	URL identifying the schema.

COPYEVOLVE

Evolves registered schemas so that existing XML instances remain valid. You should back up all schemas and documents prior to invocation because **COPYEVOLVE** deletes all conforming documents prior to implementing the schema evolution.

This procedure is accomplished in according to the following basic scenario (alternative actions are controlled by the procedure's parameters):

- copies data in schema based XMLType tables to temporary table storage
- drops old tables
- deletes old schemas
- registers new schemas
- creates new XMLType tables
- Populates new tables with data in temporary storage; auxiliary structures (constraints, triggers, indexes, and others) are not preserved
- drops temporary tables

See Also:

- Schema Evolution chapter of the *Oracle XML DB Developer's Guide* for examples on how to evolve existing schemas
- *Oracle Database Error Messages* for information on exceptions specific to schema evolution, ORA-30142 through ORA-30946.

Syntax

```
PROCEDURE COPYEVOLVE(  
    SCHEMAURLS IN XDB$STRUG_LIST_T,  
    NEWSCHEMAS IN XMLSEQUENCETYPE,  
    TRANSFORMS IN XMLSEQUENCETYPE:=NULL,  
    PRESERVEOLDDOCS IN BOOLEAN:=FALSE,  
    MAPTABLENAME IN VARCHAR2:=NULL,  
    GENERATETABLES IN BOOLEAN:=TRUE,  
    FORCE IN BOOLEAN:=FALSE,  
    SCHEMAOWNERS IN XDB$STRING_LIST_T:=NULL);
```

Parameter	IN / OUT	Description
SCHEMAURLS	(IN)	Varray of URLs of all schemas to be evolved. Should include the dependent schemas. Unless the <code>FORCE</code> parameter is <code>TRUE</code> , URLs should be in the order of dependency.
NEWSCHEMAS	(IN)	Varray of new schema documents. Should be specified in same order as the corresponding URLs.
TRANSFORMS	(IN)	Varray of transforming XSL documents to be applied to schema-based documents. Should be specified in same order as the corresponding URLs. Optional if no transformations are required.
PRESERVEOLDDOCS	(IN)	Default is <code>FALSE</code> , and temporary tables with old data are dropped. If <code>TRUE</code> , these table are still available after schema evolution is complete.
MAPTABNAME	(IN)	Specifies the name of the table mapping permanent to temporary tables during the evolution process. Valid columns are: <ul style="list-style-type: none"> ■ <code>SCHEMA_URL</code> - <code>VARCHAR2(700)</code> - URL of schema to which this table conforms ■ <code>SCHEMA_OWNER</code> - <code>VARCHAR2(30)</code> - Owner of the schema ■ <code>ELEMENT_NAME</code> - <code>VARCHAR2(256)</code> - Element to which this table conforms ■ <code>TAB_NAME</code> - <code>VARCHAR2(65)</code> - Qualified table name: <code><owner_name>.<table_name></code> ■ <code>COL_NAME</code> - <code>VARCHAR2(4000)</code> - Name of the column (<code>NULL</code> for <code>XMLType</code> tables) ■ <code>TEMP_TABNAME</code> - <code>VARCHAR2(30)</code> - Name of temporary tables which holds data for this table.
GENERATETABLES	(IN)	Default is <code>TRUE</code> , and new tables will be generated. If <code>FALSE</code> : <ul style="list-style-type: none"> ■ new tables will not be generated after registration of new schemas ■ <code>PRESERVEOLDDOCS</code> must be <code>TRUE</code> ■ <code>MAPTABLENAME</code> must be non-<code>NULL</code>
FORCE	(IN)	Default is <code>FALSE</code> . If <code>TRUE</code> , ignores errors generated during schema evolution. Used when there are circular dependencies among schemas to ensure that all schemas are stored despite possible errors in registration.

Parameter	IN / OUT	Description
SCHEMAOWNERS	(IN)	Varray of names of schema owners. Should be specified in same order as the corresponding URLs. Default is NULL, assuming that all schemas are owned by the current user.

DELETESHEMA

Deletes the XML Schema specified by the URL. Can result in a `ORA-31001` exception: invalid resource handle or path name.

Syntax

```
PROCEDURE DELETESHEMA(  
    SCHEMAURL IN VARCHAR2,  
    DELETE_OPTION IN PLS_INTEGER := DELETE_RESTRICT);
```

Parameter	IN / OUT	Description
SCHEMAURL	(IN)	URL identifying the schema to be deleted.
DELETE_OPTION	(IN)	Option for deleting schema. Valid values are: <ul style="list-style-type: none">■ DELETE_RESTRICT - Schema deletion fails if there are any tables or schemas that depend on this schema.■ DELETE_INVALIDATE - Schema deletion does not fail if there are any dependencies. Instead, it simply invalidates all dependent objects.■ DELETE_CASCADE - Schema deletion will also drop all default SQL types and default tables. The deletion fails if there are any stored instances conforming to this schema.■ DELETE_CASCADE_FORCE - Similar to DELETE_CASCADE, except that it does not check for any stored instances conforming to this schema. Also ignores any errors.

GENERATEBEAN

This procedure can be used to generate the Java bean code corresponding to a registered XML schema. Note that there is also an option to generate the beans as part of the registration procedure itself. Can result in a `ORA-31001` exception: invalid resource handle or path name.

Syntax

```
PROCEDURE GENERATEBEAN(  
    SCHEMAURL IN VARCHAR2);
```

Parameter	IN / OUT	Description
SCHEMAURL	(IN)	Name identifying a registered XML schema.

GENERATESCHEMA

These functions generate XML schema(s) from an Oracle type name. Inlines all in one schema (XMLType). Can result in a `ORA-31001` exception: invalid resource handle or path name.

Syntax

```
FUNCTION GENERATESCHEMA(
  SCHEMANAME IN VARCHAR2,
  TYPENAME IN VARCHAR2,
  ELEMENTNAME IN VARCHAR2 := NULL,
  RECURSE IN BOOLEAN := TRUE,
  ANNOTATE IN BOOLEAN := TRUE,
  EMBEDCOLL IN BOOLEAN := TRUE )
RETURN SYS.XMLTYPE;
```

Parameter	IN / OUT	Description
SCHEMANAME	(IN)	Name of the database schema containing the type.
TYPENAME	(IN)	Name of the Oracle type.
ELEMENTNAME	(IN)	The name of the top level element in the XML Schema defaults to TYPENAME.
RECURSE	(IN)	Whether or not to also generate schema for all types referred to by the type specified.
ANNOTATE	(IN)	Whether or not to put the SQL annotations in the XML Schema.
EMBEDCOLL	(IN)	Should the collections be embedded in the type which refers to them, or create a complexType? Cannot be FALSE if annotations are turned on.

GENERATESCHEMAS

These functions generate XML schema(s) from an Oracle type name. Returns a collection of `XMLTypes`, one XML Schema document for each database schema. Can result in a `ORA-31001` exception: invalid resource handle or path name.

Syntax

```
FUNCTION GENERATESCHEMA(  
    SCHEMANAME IN VARCHAR2,  
    TYPENAME IN VARCHAR2,  
    ELEMENTNAME IN VARCHAR2 := NULL,  
    SCHEMAURL IN VARCHAR2 := NULL,  
    ANNOTATE IN BOOLEAN := TRUE,  
    EMBEDCOLL IN BOOLEAN := TRUE )  
RETURN SYS.XMLTYPE;
```

Parameter	IN / OUT	Description
SCHEMANAME	(IN)	Name of the database schema containing the type.
TYPENAME	(IN)	Name of the Oracle type.
ELEMENTNAME	(IN)	The name of the top level element in the XML Schema defaults to <code>TYPENAME</code> .
SCHEMAURL	(IN)	Specifies base URL where schemas will be stored, needed by top level schema for import statement.
ANNOTATE	(IN)	Whether or not to put the SQL annotations in the XML Schema.
EMBEDCOLL	(IN)	Should the collections be embedded in the type which refers to them, or create a <code>complexType</code> ? Cannot be <code>FALSE</code> if annotations are turned on.

REGISTERSHEMA

Registers the specified schema for use by the database.

Syntax	Description
<pre>PROCEDURE REGISTERSHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN VARCHAR2, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := FALSE, GENTABLES IN BOOLEAN := TRUE, FORCE IN BOOLEAN := FALSE, OWNER IN VARCHAR2 := NULL);</pre>	Registers a schema specified as a VARCHAR2.
<pre>PROCEDURE REGISTERSHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN BFILE, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := FALSE, FORCE IN BOOLEAN := FALSE, OWNER IN VARCHAR2 := NULL);</pre>	Registers the schema specified as a BFILE. The contents of the schema document must be in the database character set.
<pre>PROCEDURE REGISTERSHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN BFILE, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := TRUE, GENTABLES IN BOOLEAN := TRUE, FORCE IN BOOLEAN := TRUE, OWNER IN VARCHAR2 := '', CSID IN NUMBER);</pre>	Registers the schema specified as a BFILE and identifies the character set id of the schema document.
<pre>PROCEDURE REGISTERSHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN BLOB, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := FALSE, FORCE IN BOOLEAN := FALSE, OWNER IN VARCHAR2 := NULL);</pre>	Registers the schema specified as a BLOB. The contents of the schema document must be in the database character set.

Syntax	Description
<pre>PROCEDURE REGISTERSCHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN BLOB, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := TRUE, GENTABLES IN BOOLEAN := TRUE, FORCE IN BOOLEAN := TRUE, OWNER IN VARCHAR2 := '', CSID IN NUMBER);</pre>	Registers the schema specified as a BLOB and identifies the character set id of the schema document.
<pre>PROCEDURE REGISTERSCHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN CLOB, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := FALSE, FORCE IN BOOLEAN := FALSE, OWNER IN VARCHAR2 := NULL);</pre>	Registers the schema specified as a CLOB.
<pre>PROCEDURE REGISTERSCHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN SYS.XMLTYPE, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := FALSE, FORCE IN BOOLEAN := FALSE, OWNER IN VARCHAR2 := NULL);</pre>	Registers the schema specified as an XMLType.
<pre>PROCEDURE REGISTERSCHEMA(SCHEMAURL IN VARCHAR2, SCHEMADOC IN SYS.URITYPE, LOCAL IN BOOLEAN := TRUE, GENTYPES IN BOOLEAN := TRUE, GENBEAN IN BOOLEAN := FALSE, FORCE IN BOOLEAN := FALSE, OWNER IN VARCHAR2 := NULL);</pre>	Registers the schema specified as a URIType.

Parameter	IN / OUT	Description
SCHEMAURL	(IN)	URL that uniquely identifies the schema document. This value is used to derive the path name of the schema document within the database hierarchy. Can be used inside SCHEMALOCATION attribute of XML Schema import element.
SCHEMADOC	(IN)	A valid XML schema document.
LOCAL	(IN)	Is this a local or global schema? <ul style="list-style-type: none"> ■ By default, all schemas are registered as local schemas, under <code>/sys/schemas/<username>/...</code> ■ If a schema is registered as global, it is added under <code>/sys/schemas/PUBLIC/...</code> <p>You need write privileges on the directory to be able to register a schema as global.</p>
GENTYPES	(IN)	Should the schema compiler generate object types? By default, <code>TRUE</code> .
GENBEAN	(IN)	Should the schema compiler generate Java beans? By default, <code>FALSE</code> .
GENTABLES	(IN)	Should the schema compiler generate default tables? By default, <code>TRUE</code>
FORCE	(IN)	If this parameter is set to <code>TRUE</code> , the schema registration will not raise errors. Instead, it creates an invalid XML schema object in case of any errors. By default, the value of this parameter is <code>FALSE</code> .
OWNER	(IN)	This parameter specifies the name of the database user owning the XML schema object. By default, the user registering the schema owns the XML schema object. This parameter can be used to register a XML schema to be owned by a different database user.
CSID	(IN)	Identifies the character set of the input schema document; if this value is 0, the schema document's encoding is determined by the current rule for "text/xml" MIME type.

REGISTERURI

Registers an XML Schema specified by a URI name.

Syntax

```
PROCEDURE REGISTERURI(
    SCHEMAURL IN VARCHAR2,
    SCHEMADOCURI IN VARCHAR2,
    LOCAL IN BOOLEAN := TRUE,
    GENTYPES IN BOOLEAN := TRUE,
    GENBEAN IN BOOLEAN := FALSE,
    GENTABLES IN BOOLEAN := TRUE,
    FORCE IN BOOLEAN := FALSE,
    OWNER IN VARCHAR2 := NULL);
```

Parameter	IN / OUT	Description
SCHEMAURL	(IN)	Uniquely identifies the schema document. Can be used inside SCHEMALOCATION attribute of XML Schema import element.
SCHEMADOCURI	(IN)	Pathname (URI) corresponding to the physical location of the schema document. The URI path could be based on HTTP, FTP, DB or Oracle XML DB protocols. This function constructs a URIType instance using the URIFactory - and invokes the REGISTERSCHEMA function.
LOCAL	(IN)	Is this a local or global schema? By default, all schemas are registered as local schemas, under /sys/schemas/<username>/... If a schema is registered as global, it is added under /sys/schemas/PUBLIC/... The user needs write privileges on the directory to register a global schema.
GENTYPES	(IN)	Should the compiler generate object types? By default, TRUE.
GENBEAN	(IN)	Should the compiler generate Java beans? By default, FALSE.
GENTABLES	(IN)	Should the compiler generate default tables? TRUE by default.
FORCE	(IN)	TRUE: schema registration will not raise errors. Instead, it creates an invalid XML schema object in case of any errors. By default, the value of this parameter is FALSE.

Parameter	IN / OUT	Description
OWNER	(IN)	This parameter specifies the name of the database user owning the XML schema object. By default, the user registering the schema owns the XML schema object. This parameter can be used to register a XML schema to be owned by a different database user.

Catalog Views of the DBMS_XMLSCHEMA

Table 118–3 Summary of Catalog View Schemas

Schema	Description
USER_XML_SCHEMAS on page 118-19	All registered XML Schemas owned by the user.
ALL_XML_SCHEMAS on page 118-20	All registered XML Schemas usable by the current user.
DBA_XML_SCHEMAS on page 118-21	All registered XML Schemas in the database.
DBA_XML_TABLES on page 118-22	All XMLType tables in the system.
USER_XML_TABLES on page 118-23	All XMLType tables owned by the current user.
ALL_XML_TABLES on page 118-24	All XMLType tables usable by the current user.
DBA_XML_TAB_COLS on page 118-25	All XMLType table columns in the system.
USER_XML_TAB_COLS on page 118-26	All XMLType table columns in tables owned by the current user.
ALL_XML_TAB_COLS on page 118-27	All XMLType table columns in tables usable by the current user.
DBA_XML_VIEWS on page 118-28	All XMLType views in the system.
USER_XML_VIEWS on page 118-29	All XMLType views owned by the current user.
ALL_XML_VIEWS on page 118-30	All XMLType views usable by the current user.
DBA_XML_VIEW_COLS on page 118-31	All XMLType view columns in the system.
USER_XML_VIEW_COLS on page 118-32	All XMLType view columns in views owned by the current user.
ALL_XML_VIEW_COLS on page 118-33	All XMLType view columns in views usable by the current user.

USER_XML_SCHEMAS

Lists all schemas (local and global) belonging to the current user.

Column	Datatype	Description
SCHEMA_URL	VARCHAR2	URL of XML schema
LOCAL	VARCHAR2	Local schema (YES/NO)
SCHEMA	XMLTYPE	XML Schema document

ALL_XML_SCHEMAS

Lists all local schemas belonging to the current user and all global schemas.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning XML schema
SCHEMA_URL	VARCHAR2	URL of XML schema
LOCAL	VARCHAR2	Local schema (YES/NO)
SCHEMA	XMLTYPE	XML Schema document

DBA_XML_SCHEMAS

Lists all registered local and global schemas in the system.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning XML schema
SCHEMA_URL	VARCHAR2	URL of XML schema
LOCAL	VARCHAR2	Local schema (YES/NO)
SCHEMA	XMLTYPE	XML Schema document

DBA_XML_TABLES

Lists all XMLType tables in the system.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning table
TABLE_NAME	VARCHAR2	Name of XMLType table
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element
STORAGE_TYPE	VARCHAR2	Storage type: CLOB / OBJECT-RELATIONAL

USER_XML_TABLES

Lists all local XMLType tables belonging to the current user.

Column	Datatype	Description
TABLE_NAME	VARCHAR2	Name of XMLType table
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element
STORAGE_TYPE	VARCHAR2	Storage type: CLOB / OBJECT-RELATIONAL

ALL_XML_TABLES

Lists all local XMLType tables belonging to the current user and all global tables visible to the current user.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning table
TABLE_NAME	VARCHAR2	Name of XMLType table
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element
STORAGE_TYPE	VARCHAR2	Storage type: CLOB / OBJECT-RELATIONAL

DBA_XML_TAB_COLS

Lists all XMLType columns in the system.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning table
TABLE_NAME	VARCHAR2	Name of table
COLUMN_NAME	VARCHAR2	Name of XMLType column
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element
STORAGE_TYPE	VARCHAR2	Storage type: CLOB / OBJECT-RELATIONAL

USER_XML_TAB_COLS

Lists all XMLType columns in tables belonging to the current user.

Column	Datatype	Description
TABLE_NAME	VARCHAR2	Name of table
COLUMN_NAME	VARCHAR2	Name of XMLType column
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element
STORAGE_TYPE	VARCHAR2	Storage type: CLOB / OBJECT-RELATIONAL

ALL_XML_TAB_COLS

Lists all XMLType columns in tables belonging to the current user and all global tables visible to the current user.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning table
TABLE_NAME	VARCHAR2	Name of table
COLUMN_NAME	VARCHAR2	Name of XMLType column
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element
STORAGE_TYPE	VARCHAR2	Storage type: CLOB / OBJECT-RELATIONAL

DBA_XML_VIEWS

Lists all XMLType views in the system.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning view
VIEW_NAME	VARCHAR2	Name of XMLType view
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element

USER_XML_VIEWS

Lists all local XMLType views belonging to the current user.

Column	Datatype	Description
VIEW_NAME	VARCHAR2	Name of XMLType view
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element

ALL_XML_VIEWS

Lists all local XMLType views belonging to the current user and all global views visible to the current user.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning view
VIEW_NAME	VARCHAR2	Name of XMLType view
XMLSCHEMA	VARCHAR2	XML Schema URL
ELEMENT_NAME	VARCHAR2	XML Schema element

DBA_XML_VIEW_COLS

Lists all XMLType columns in the system.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning view.
VIEW_NAME	VARCHAR2	Name of view.
COLUMN_NAME	VARCHAR2	Name of XMLType column.
XMLSCHEMA	VARCHAR2	XML Schema URL.
ELEMENT_NAME	VARCHAR2	XML Schema element.

USER_XML_VIEW_COLS

Lists all XMLType columns in views belonging to the current user.

Column	Datatype	Description
VIEW_NAME	VARCHAR2	Name of view.
COLUMN_NAME	VARCHAR2	Name of XMLType column.
XMLSCHEMA	VARCHAR2	XML Schema URL.
ELEMENT_NAME	VARCHAR2	XML Schema element.

ALL_XML_VIEW_COLS

Lists all XMLType columns in views belonging to the current user and all global views visible to the current user.

Column	Datatype	Description
OWNER	VARCHAR2	Database user owning view.
VIEW_NAME	VARCHAR2	Name of view.
COLUMN_NAME	VARCHAR2	Name of XMLType column.
XMLSCHEMA	VARCHAR2	XML Schema URL.
ELEMENT_NAME	VARCHAR2	XML Schema element.

DBMS_XMLSTORE provides the ability to store XML data in relational tables.

See Also:

- *Oracle XML DB Developer's Guide*

This chapter contains the following sections:

- [Using DBMS_XMLSTORE](#)
 - [Types](#)
- [Summary of DBMS_XMLSTORE Subprograms](#)

Using DBMS_XMLSTORE

Types

Table 119–1 *Types of DBMS_XMLSTORE*

Type	Description
ctxType	The type of the query context handle. This is the return type of NEWCONTEXT .

Summary of DBMS_XMLSTORE Subprograms

Table 119–2 DBMS_XMLSTORE Package Subprograms

Method	Description
CLEARKEYCOLUMNLIST on page 119-4	Clears the key column list.
CLEARUPDATECOLUMNLIST on page 119-5	Clears the update column list.
CLOSECONTEXT on page 119-6	It closes/deallocates a particular save context.
DELETEXML on page 119-7	Deletes records specified by data from the XML document, from the table specified at the context creation time.
INSERTXML on page 119-8	Inserts the XML document into the table specified at the context creation time.
NEWCONTEXT on page 119-9	Creates a save context, and returns the context handle.
SETKEYCOLUMN on page 119-10	This method adds a column to the key column list.
SETROWTAG on page 119-11	Names the tag used in the XML document, to enclose the XML elements corresponding to the database.
SETUPDATECOLUMN on page 119-12	Adds a column to the "update column list".
UPDATERXML on page 119-13	Updates the table given the XML document.

CLEARKEYCOLUMNLIST

Clears the key column list.

Syntax

```
PROCEDURE CLEARKEYCOLUMNLIST(  
    CTXHDL IN CTXTYPE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

CLEARUPDATECOLUMNLIST

Clears the update column list.

Syntax

```
PROCEDURE CLEARUPDATECOLUMNLIST(  
    CTXHDL IN CTXTYPE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

CLOSECONTEXT

Closes/deallocates a particular save context.

Syntax

```
PROCEDURE CLOSECONTEXT(  
    CTXHDL IN CTXTYPE);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.

DELETXML

Deletes records specified by data from the XML document from the table specified at the context creation time, and returns the number of rows deleted.

Syntax	Description
<pre>FUNCTION DELETXML(CTXHDL IN CTXPTYPE, XDOC IN VARCHAR2) RETURN NUMBER;</pre>	Uses a VARCHAR2 type for the XDOC parameter.
<pre>FUNCTION DELETXML(CTXHDL IN CTXTYPE, XDOC IN CLOB) RETURN NUMBER;</pre>	Uses a CLOB type for the XDOC parameter.
<pre>FUNCTION DELETXML(CTXHDL IN CTXTYPE, XDOC IN XMLTYPE) RETURN NUMBER;</pre>	Uses an XMLType type for the XDOC parameter.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
XDOC	(IN)	String containing the XML document.

INSERTXML

Inserts the XML document into the table specified at the context creation time, and returns the number of rows inserted.

Syntax	Description
<pre>FUNCTION INSERTXML(CTXHDL IN CTXTYPE, XDOC IN VARCHAR2) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a VARCHAR2.
<pre>FUNCTION INSERTXML(CTXHDL IN CTXTYPE, XDOC IN CLOB) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a CLOB.
<pre>FUNCTION INSERTXML(CTXHDL IN CTXTYPE, XDOC IN XMLTYPE) RETURN NUMBER;</pre>	Passes in the XDOC parameter as an XMLType.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
XDOC	(IN)	String containing the XML document.

NEWCONTEXT

Creates a save context, and returns the context handle.

Syntax

```
FUNCTION NEWCONTEXT(  
    TARGETTABLE IN VARCHAR2)  
RETURN CTXTYPE;
```

Parameter	IN / OUT	Description
TARGETTABLE	(IN)	The target table into which to load the XML document.

SETKEYCOLUMN

This method adds a column to the "key column list". The value for the column cannot be `NULL`. In case of update or delete, the columns in the key column list make up the `WHERE` clause of the statement. The key columns list must be specified before updates can complete; this is optional for delete operations

Syntax

```
PROCEDURE SETKEYCOLUMN(  
    CTXHDL IN CTXTYPE,  
    COLNAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
COLNAME	(IN)	Column to be added to the key column list; cannot be <code>NULL</code> .

SETROWTAG

Names the tag used in the XML document, to enclose the XML elements corresponding to database records.

Syntax

```
PROCEDURE SETROWTAG(  
    CTXHDL IN CTXTYPE,  
    TAG IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
TAG	(IN)	Tag name.

SETUPDATECOLUMN

Adds a column to the update column list. In case of insert, the default is to insert values to all the columns in the table; on the other hand, in case of updates, the default is to only update the columns corresponding to the tags present in the `ROW` element of the XML document. When the update column list is specified, the columns making up this list alone will get updated or inserted into.

Syntax

```
PROCEDURE SETUPDATECOLUMN(  
    CTXHDL IN CTXTYPE,  
    COLNAME IN VARCHAR2);
```

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
COLNAME	(IN)	Column to be added to the update column list.

UPDATEXML

Updates the table specified at the context creation time with data from the XML document, and returns the number of rows updated. The options are described in the following table.

Syntax	Description
<pre>FUNCTION UPDATEXML(CTXHDL IN CTXTYPE, XDOC IN VARCHAR2) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a VARCHAR2.
<pre>FUNCTION UPDATEXML(CTXHDL IN CTXTYPE, XDOC IN CLOB) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a CLOB.
<pre>FUNCTION UPDATEXML(CTXHDL IN CTXTYPE, XDOC IN XMLTYPE) RETURN NUMBER;</pre>	Passes in the XDOC parameter as a XMLType.

Parameter	IN / OUT	Description
CTXHDL	(IN)	Context handle.
XDOC	(IN)	String containing the XML document.

The `DBMS_XPLAN` package provides an easy way to display the output of the `EXPLAIN PLAN` command in several, predefined formats. You can also use the `DBMS_XPLAN` package to display the plan of a statement stored in the Automatic Workload Repository (AWR). It further provides a way to display the SQL execution plan and SQL execution runtime statistics for cached SQL cursors based on the information stored in the `V$SQL_PLAN` and `V$SQL_PLAN_STATISTICS_ALL` fixed views.

For more information on the `EXPLAIN PLAN` command and the AWR, see *Oracle Database Performance Tuning Guide*. For more information on the `V$SQL_PLAN` and `V$SQL_PLAN_STATISTICS` fixed views, see *Oracle Database Reference*.

This chapter contains the following topics:

- [Using DBMS_XPLAN](#)
 - [Overview](#)
 - [Security Model](#)
 - [Examples](#)
- [Summary of DBMS_XPLAN Subprograms](#)

Using DBMS_XPLAN

- [Overview](#)
- [Security Model](#)
- [Examples](#)

Overview

The DBMS_XPLAN package supplies three table functions:

- `DISPLAY`, to format and display the contents of a plan table
- `DISPLAY_CURSOR`, to format and display the contents of the execution plan of any loaded cursor.
- `DISPLAY_AWR` to format and display the contents of the execution plan of a stored SQL statement in the AWR.

Security Model

This package runs with the privileges of the calling user, not the package owner (SYS). The table function `DISPLAY_CURSOR` requires to have select privileges on the following fixed views: `V$SQL_PLAN`, `V$SESSION` and `V$SQL_PLAN_STATISTICS_ALL`.

Using the `DISPLAY_AWR` function requires to have `SELECT` privileges on `DBA_HIST_SQL_PLAN`, `DBA_HIST_SQLTEXT`, and `V$DATABASE`.

All these privileges are automatically granted as part of the `SELECT_CATALOG` role.

Examples

Displaying a Plan Table Using DBMS_XPLAN.DISPLAY

Execute an explain plan command on a `SELECT` statement:

```
EXPLAIN PLAN FOR
SELECT * FROM emp e, dept d
WHERE e.deptno = d.deptno
```

```
AND e.ename='benoit';
```

Display the plan using the DBMS_XPLAN.DISPLAY table function

```
SET LINESIZE 130
SET PAGESIZE 0
SELECT * FROM table(DBMS_XPLAN.DISPLAY);
```

This query produces the following output:

Plan hash value: 3693697075

```
-----
```

Id	Operation	Name	Rows	Bytes	Cost (%CPU)	Time
0	SELECT STATEMENT		1	57	6 (34)	00:00:01
* 1	HASH JOIN		1	57	6 (34)	00:00:01
* 2	TABLE ACCESS FULL	EMP	1	37	3 (34)	00:00:01
3	TABLE ACCESS FULL	DEPT	4	80	3 (34)	00:00:01

```
-----
```

Predicate Information (identified by operation id):

```
-----
1 - access("E"."DEPTNO"="D"."DEPTNO")
2 - filter("E"."ENAME"='benoit')
```

15 rows selected.

Displaying a Cursor Execution Plan Using DBMS_XPLAN.DISPLAY_CURSOR

By default, the table function DISPLAY_CURSOR formats the execution plan for the last SQL statement executed by the session. For example:

```
SELECT ename FROM emp e, dept d
WHERE e.deptno = d.deptno
AND e.empno=7369;
```

ENAME

SMITH

To display the execution plan of the last executed statement for that session:

```
SET PAGESIZE 0
SELECT * FROM table(DBMS_XPLAN.DISPLAY_CURSOR);
```

This query produces the following output:

Plan hash value: 3693697075, SQL hash value: 2096952573, child number: 0

```
-----
SELECT ename FROM emp e, dept d WHERE e.deptno = d.deptno
AND e.empno=7369
```

```
-----
```

Id	Operation	Name	Rows	Bytes	Cost (%CPU)	Time
0	SELECT STATEMENT					
* 1	HASH JOIN		1	16	6 (34)	00:00:01
* 2	TABLE ACCESS FULL	EMP	1	13	3 (34)	00:00:01
3	TABLE ACCESS FULL	DEPT	4	12	3 (34)	00:00:01

```
-----
```

Predicate Information (identified by operation id):

- ```

```
- 1 - access("E"."DEPTNO"="D"."DEPTNO")
  - 2 - filter("E"."EMPNO"=7369)

21 rows selected.

**You can also use the table function `DISPLAY_CURSOR` to display the execution plan for any loaded cursor stored in the cursor cache. In that case, you must supply a reference to the child cursor to the table function. This includes the SQL ID of the statement and optionally the child number.**

**Run a query with a distinctive comment:**

```
SELECT /* TOTO */ ename, dname
FROM dept d join emp e USING (deptno);
```

**Get `sql_id` and `child_number` for the preceding statement:**

```
SELECT sql_id, child_number
FROM v$sql
WHERE sql_text LIKE '%TOTO%';
```

```
SQL_ID CHILD_NUMBER

```

|               |   |
|---------------|---|
| gwp663cqh5qbf | 0 |
|---------------|---|

**Display the execution plan for the cursor:**

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY_CURSOR(('gwp663cqh5qbf',0));
```

Plan hash value: 3693697075, SQL ID: gwp663cqh5qbf, child number: 0



```

SELECT /* TOTO */ ename, dname
FROM dept d JOIN emp e USING (deptno);
```

```

```

| Id  | Operation         | Name | Rows | Bytes | Cost (%CPU) | Time     |
|-----|-------------------|------|------|-------|-------------|----------|
| 0   | SELECT STATEMENT  |      |      |       | 7 (100)     |          |
| 1   | SORT GROUP BY     |      | 4    | 64    | 7 (43)      | 00:00:01 |
| * 2 | HASH JOIN         |      | 14   | 224   | 6 (34)      | 00:00:01 |
| 3   | TABLE ACCESS FULL | DEPT | 4    | 44    | 3 (34)      | 00:00:01 |
| 4   | TABLE ACCESS FULL | EMP  | 14   | 70    | 3 (34)      | 00:00:01 |

```

```

```
Predicate Information (identified by operation id):
```

```

2 - access("E"."DEPTNO"="D"."DEPTNO")
```

Instead of issuing two queries, one to get the `sql_id` and `child_number` pair and one to display the plan, you can combine these in a single query:

Display the execution plan of all cursors matching the string 'TOTO':

```
SELECT t.*
FROM v$sql s, table(DBMS_XPLAN.DISPLAY_CURSOR(s.sql_id, s.child_number)) t WHERE
sql_text LIKE '%TOTO%';
```

### Displaying a Plan Table with Parallel Information

By default, only relevant information is reported by the `display` and `display_cursor` table functions. In [Displaying a Plan Table Using DBMS\\_XPLAN.DISPLAY](#) on page 120-2, the query does not execute in parallel. Hence, information related to the parallelization of the plan is not reported. As shown in the following example, parallel information is reported only if the query executes in parallel.

```
ALTER TABLE emp PARALLEL;
EXPLAIN PLAN for
SELECT * FROM emp e, dept d
WHERE e.deptno = d.deptno
AND e.ename = 'hermann'
ORDER BY e.empno;
```

Display the plan using the `DBMS_XPLAN.DISPLAY` table function

```
SET LINESIZE 130
```

## Examples

```
SET PAGESIZE 0
SELECT * FROM table(DBMS_XPLAN.DISPLAY);
Plan hash value: 3693697345
```

| Id   | Operation          | Name     | Rows | Bytes | Cost (%CPU) | Time     | TQ    | INOUT | PQ Distrib |
|------|--------------------|----------|------|-------|-------------|----------|-------|-------|------------|
| 0    | SELECT STATEMENT   |          | 1    | 117   | 6 (50)      | 00:00:01 |       |       |            |
| 1    | PX COORDINATOR     |          |      |       |             |          |       |       |            |
| 2    | PX SEND QC (ORDER) | :TQ10003 | 1    | 117   | 6 (50)      | 00:00:01 | Q1,03 | P->S  | QC (ORDER) |
| 3    | SORT ORDER BY      |          | 1    | 117   | 6 (50)      | 00:00:01 | Q1,03 | PCWP  |            |
| 4    | PX RECEIVE         |          | 1    | 117   | 5 (40)      | 00:00:01 | Q1,03 | PCWP  |            |
| 5    | PX SEND RANGE      | :TQ10002 | 1    | 117   | 5 (40)      | 00:00:01 | Q1,02 | P->P  | RANGE      |
| * 6  | HASH JOIN          |          | 1    | 117   | 5 (40)      | 00:00:01 | Q1,02 | PCWP  |            |
| 7    | PX RECEIVE         |          | 1    | 87    | 2 (50)      | 00:00:01 | Q1,02 | PCWP  |            |
| 8    | PX SEND HASH       | :TQ10001 | 1    | 87    | 2 (50)      | 00:00:01 | Q1,01 | P->P  | HASH       |
| 9    | PX BLOCK ITERATOR  |          | 1    | 87    | 2 (50)      | 00:00:01 | Q1,01 | PCWC  |            |
| * 10 | TABLE ACCESS FULL  | EMP      | 1    | 87    | 2 (50)      | 00:00:01 | Q1,01 | PCWP  |            |
| 11   | BUFFER SORT        |          |      |       |             |          | Q1,02 | PCWC  |            |
| 12   | PX RECEIVE         |          | 4    | 120   | 3 (34)      | 00:00:01 | Q1,02 | PCWP  |            |
| 13   | PX SEND HASH       | :TQ10000 | 4    | 120   | 3 (34)      | 00:00:01 |       | S->P  | HASH       |
| 14   | TABLE ACCESS FULL  | DEPT     | 4    | 120   | 3 (34)      | 00:00:01 |       |       |            |

Predicate Information (identified by operation id):

```
6 - access("E"."DEPTNO"="D"."DEPTNO")
10 - filter("E"."ENAME"='hermann')
```

When the query is parallel, information related to parallelism is reported: table queue number (TQ column), table queue type (INOUT) and table queue distribution method (PQ Distrib).

By default, if several plans in the plan table match the `statement_id` parameter passed to the `display` table function (default value is `NULL`), only the plan corresponding to the last `EXPLAIN PLAN` command is displayed. Hence, there is no need to purge the plan table after each `EXPLAIN PLAN`. However, you should purge the plan table regularly (for example, by using the `TRUNCATE TABLE` command) to ensure good performance in the execution of the `DISPLAY` table function.

For ease of use, you can define a view on top of the `display` table function and then use that view to display the output of the `EXPLAIN PLAN` command:

### Using a View to Display Last Explain Plan

```
define plan view
CREATE VIEW PLAN AS SELECT * FROM TABLE(DBMS_XPLAN.DISPLAY);
```

```
display the output of the last explain plan command
SELECT * FROM PLAN;
```

---

## Summary of DBMS\_XPLAN Subprograms

**Table 120–1** *DBMS\_XPLAN Package Subprograms*

| <b>Subprogram</b>                                      | <b>Description</b>                                            |
|--------------------------------------------------------|---------------------------------------------------------------|
| <a href="#">DISPLAY_AWR Function</a> on page 120-9     | Displays the contents of an execution plan stored in the AWR  |
| <a href="#">DISPLAY Function</a> on page 120-11        | Displays the contents of the plan table                       |
| <a href="#">DISPLAY_CURSOR Function</a> on page 120-13 | Displays the execution plan of any cursor in the cursor cache |

## DISPLAY\_AWR Function

This table function displays the contents of an execution plan stored in the AWR.

### Syntax

```
DBMS_XPLAN.DISPLAY_AWR(
 sql_id IN VARCHAR2,
 plan_hash_value IN NUMBER DEFAULT NULL,
 db_id IN NUMBER DEFAULT NULL,
 format IN VARCHAR2 DEFAULT TYPICAL);
```

### Parameters

**Table 120–2** *DISPLAY\_AWR Table Function Parameters*

| Parameter       | Description                                                                                                                                                                                                                                                     |
|-----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| sql_id          | Specifies the <code>SQL_ID</code> of the SQL statement. You can retrieve the appropriate value for the SQL statement of interest by querying the column <code>SQL_ID</code> in <code>DBA_HIST_SQLTEXT</code> .                                                  |
| plan_hash_value | Specifies the <code>PLAN_HASH_VALUE</code> of a SQL statement. This parameter is optional. If omitted, the table function will return all stored execution plans for a given <code>SQL_ID</code> .                                                              |
| db_id           | Specifies the <code>database_id</code> for which the plan of the SQL statement, identified by <code>SQL_ID</code> should be displayed. If not supplied, the <code>database_id</code> of the local database will be used, as shown in <code>V\$DATABASE</code> . |
| format          | Controls the level of details for the plan. It has the same set of values than the table function <code>DISPLAY</code> , that is, <code>BASIC</code> , <code>TYPICAL</code> , <code>SERIAL</code> and <code>ALL</code> .                                        |

### Usage Notes

To use the `DISPLAY_AWR` functionality, the calling user must have `SELECT` privilege on `DBA_HIST_SQL_PLAN`, `DBA_HIST_SQLTEXT`, and `V$DATABASE`, otherwise it will show an appropriate error message.

### Examples

To display the execution plan of all children associated to the SQL ID 'atfwcg8anrykp':

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY_AWR('atfwcg8anrykp'));
```

**To display the execution plan of all stored SQL statements containing the string 'TOTO':**

```
SELECT tf.* FROM DBA_HIST_SQLTEXT ht, table
 (DBMS_XPLAN.DISPLAY_AWR(ht.sql_id,null, null, 'ALL')) tf
WHERE ht.sql_text like '%TOTO%';
```

## DISPLAY Function

This table function displays the contents of the plan table.

### Syntax

```
DBMS_XPLAN.DISPLAY(
 table_name IN VARCHAR2 DEFAULT 'PLAN_TABLE',
 statement_id IN VARCHAR2 DEFAULT NULL,
 format IN VARCHAR2 DEFAULT 'TYPICAL');
```

### Parameters

**Table 120–3** *DISPLAY Table Function Parameters*

| Parameter    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|--------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| table_name   | Specifies the table name where the plan is stored. This parameter defaults to <code>PLAN_TABLE</code> , which is the default plan table for the <code>EXPLAIN PLAN</code> command. If <code>NULL</code> is specified it also defaults to <code>PLAN_TABLE</code> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| statement_id | Specifies the <code>statement_id</code> of the plan to be displayed. This parameter defaults to <code>NULL</code> , which is the default when the <code>EXPLAIN PLAN</code> command is executed without a <code>set statement_id</code> clause. If no <code>statement_id</code> is specified, the function will show you the plan of the most recent explained statement.                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| format       | Controls the level of details for the plan. It accepts four values: <ul style="list-style-type: none"> <li>■ <b>BASIC</b>: Displays the minimum information in the plan—the operation ID, the object name, and the operation option.</li> <li>■ <b>TYPICAL</b>: This is the default. Displays the most relevant information in the plan. Partition pruning, parallelism, and predicates are displayed only when available.</li> <li>■ <b>ALL</b>: Maximum level. Includes information displayed with the <b>TYPICAL</b> level and adds projection information as well as SQL statements generated for parallel execution servers (only if parallel).</li> <li>■ <b>SERIAL</b>: Like <b>TYPICAL</b> except that the parallel information is not displayed, even if the plan executes in parallel.</li> </ul> |

### Examples

To display the result of the last `EXPLAIN PLAN` command stored in the plan table:

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY);
```

**To display from other than the default plan table, "my\_plan\_table":**

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY('my_plan_table'));
```

**To display the minimum plan information:**

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY('plan_table', null, 'basic'));
```

**To display the plan for a statement identified by 'foo', such as statement\_id='foo':**

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY('plan_table', 'foo'));
```



## DISPLAY\_CURSOR Function

This table function displays the explain plan of any cursor loaded in the cursor cache.

### Syntax

```
DBMS_XPLAN.DISPLAY_CURSOR(
 sql_id IN VARCHAR2 DEFAULT NULL,
 child_number IN NUMBER DEFAULT NULL,
 format IN VARCHAR2 DEFAULT 'TYPICAL');
```

### Parameters

**Table 120–4** *DISPLAY\_CURSOR Function Parameters*

| Parameter    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|--------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| sql_id       | Specifies the <code>SQL_ID</code> of the SQL statement in the cursor cache. You can retrieve the appropriate value by querying the column <code>SQL_ID</code> in <code>V\$SQL</code> or <code>V\$SQLAREA</code> . Alternatively, you could choose the column <code>PREV_SQL_ID</code> for a specific session out of <code>V\$SESSION</code> . This parameter defaults to <code>NULL</code> in which case the plan of the last cursor executed by the session will be displayed.                                                                                                                                                                                                                                                                                                           |
| child_number | Child number of the cursor to display. If not supplied, the execution plan of all cursors matching the supplied <code>sql_id</code> parameter are displayed. The <code>child_number</code> can be specified only if <code>sql_id</code> is specified.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| format       | Controls the level of details for the plan. It has the same set of values than the table function 'DISPLAY', that is, 'BASIC', 'TYPICAL', 'SERIAL' and 'ALL'. Two additional values are also supported to display run-time statistics for the cursor: <ul style="list-style-type: none"> <li>■ <code>RUNSTATS_LAST</code>: Displays the runtime statistics for the last execution of the cursor.</li> <li>■ <code>RUNSTATS_TOT</code>: Displays the total aggregated runtime statistics for all executions of a specific SQL statement since the statement was first parsed and executed.</li> </ul> Format options 'RUNSTATS_LAST' and 'RUNSTATS_TOT' can only be used if the target cursor was compiled and executed with the initialization parameter 'statistics_level' set to 'ALL'. |

### Usage Notes:

To use the `DISPLAY_CURSOR` functionality, the calling user must have `SELECT` privilege on the fixed views `V$SQL_PLAN_STATISTICS_ALL`, `V$SQL` and `V$SQL_PLAN`, otherwise it will show an appropriate error message.

### Examples

To display the execution plan of the last SQL statement executed by the current session:

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY_CURSOR);
```

To display the execution plan of all children associated to the SQL ID 'atfwcg8anrykp':

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY_CURSOR('atfwcg8anrykp'));
```

To display runtime statistics for the cursor included in the preceding statement:

```
SELECT * FROM table(DBMS_XPLAN.DISPLAY_CURSOR('atfwcg8anrykp', null, 'RUNSTATS_LAST'));
```

---

## DBMS\_XSLPROCESSOR

With `DBMS_XSLPROCESSOR`, you can access the contents and structure of XML documents. The Extensible Stylesheet Language Transformation (XSLT) describes rules for transforming a source tree into a result tree. A transformation expressed in XSLT is called a stylesheet. The transformation specified is achieved by associating patterns with templates defined in the stylesheet. A template is instantiated to create part of the result tree. This PL/SQL implementation of the XSL processor followed the W3C XSLT working draft rev WD-xslt-19990813 and included the required behavior of an XSL processor in terms of how it must read XSLT stylesheets and the transformation it must effect.

The following is the default behavior for this PL/SQL XSL Processor:

- A result tree which can be accessed by DOM APIs is built
- Errors are not recorded unless an error log is specified; however, an application error will be raised if parsing fails

This chapter contains the following topics:

- [Summary of DBMS\\_XSLPROCESSOR Subprograms](#)

**See Also:**

- *Oracle XML DB Developer's Guide*

---

## Summary of DBMS\_XSLPROCESSOR Subprograms

**Table 121–1 DBMS\_XSLPROCESSOR Package Subprograms**

| Method                                         | Description                                                  |
|------------------------------------------------|--------------------------------------------------------------|
| <a href="#">CLOB2FILE</a> on page 121-2        | Writes content of a CLOB into a file.                        |
| <a href="#">FREEPROCESSOR</a> on page 121-3    | Frees a processor object.                                    |
| <a href="#">FREESTYLESHEET</a> on page 121-3   | Frees a stylesheet object.                                   |
| <a href="#">NEWPROCESSOR</a> on page 121-4     | Returns a new processor instance.                            |
| <a href="#">NEWSTYLESHEET</a> on page 121-4    | Creates a new stylesheet from input and reference URLs.      |
| <a href="#">PROCESSXSL</a> on page 121-5       | Transforms an input XML document.                            |
| <a href="#">READ2CLOB</a> on page 121-7        | Reads content of the file into a CLOB.                       |
| <a href="#">REMOVEPARAM</a> on page 121-7      | Removes a top-level stylesheet parameter                     |
| <a href="#">RESETPARAMS</a> on page 121-8      | Resets the top-level stylesheet parameters                   |
| <a href="#">SELECTNODES</a> on page 121-8      | Selects nodes from a DOM tree that match a pattern.          |
| <a href="#">SELECTSINGLENODE</a> on page 121-8 | Selects the first node from the tree that matches a pattern. |
| <a href="#">SETERRORLOG</a> on page 121-9      | Sets errors to be sent to the specified file.                |
| <a href="#">SETPARAM</a> on page 121-9         | Sets a top-level parameter in the stylesheet.                |
| <a href="#">SHOWWARNINGS</a> on page 121-10    | Turns warnings on or off.                                    |
| <a href="#">TRANSFORMNODE</a> on page 121-10   | Transforms a node in a DOM tree using a stylesheet.          |
| <a href="#">VALUEOF</a> on page 121-11         | Gets the value of the first node that matches a pattern.     |

### CLOB2FILE

Write content of a CLOB into a file.

#### Syntax

```
PROCEDURE CLOB2FILE(
 CL CLOB;
 FLOCATION VARCHAR2,
 FNAME VARCHAR2,
```

```
CSID IN NUMBER:=0);
```

| Parameter | IN / OUT | Description                                                                                                                                                                                                               |
|-----------|----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| CLOB      | -        | File directory                                                                                                                                                                                                            |
| FLOCATION | -        | File directory                                                                                                                                                                                                            |
| FNAME     | -        | File name                                                                                                                                                                                                                 |
| CSID      | ( IN)    | Character set id of the file <ul style="list-style-type: none"> <li>■ Must be a valid Oracle id; otherwise returns an error</li> <li>■ If 0, content of the output file will be in the database character set.</li> </ul> |

## FREPROCESSOR

Frees a `Processor` object.

### Syntax

```
PROCEDURE FREPROCESSOR(
 P PROCESSOR);
```

| Parameter | IN / OUT | Description |
|-----------|----------|-------------|
| P         | ( IN)    | Processor.  |

## FREESTYLESHEET

Frees a `Stylesheet` object.

### Syntax

```
PROCEDURE FREESTYLESHEET(
 SS STYLESHEET);
```

| Parameter | IN / OUT | Description |
|-----------|----------|-------------|
| SS        | ( IN )   | Stylesheet. |

## NEWPROCESSOR

Returns a new `Processor` instance. This function must be called before the default behavior of `Processor` can be changed and if other processor methods need to be used.

### Syntax

```
FUNCTION NEWPROCESSOR
RETURN PROCESSOR;
```

## NEWSTYLESHEET

Creates and returns a new `Stylesheet` instance. The options are described in the following table.

| Syntax                                                                                                      | Description                                                                                                             |
|-------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------|
| <pre>FUNCTION NEWSTYLESHEET(<br/>    XMLDOC DOMDOCUMENT,<br/>    REF VARCHAR2)<br/>RETURN STYLESHEET;</pre> | Creates and returns a new <code>stylesheet</code> instance using the given <code>DOMDocument</code> and reference URLs. |
| <pre>FUNCTION NEWSTYLESHEET(<br/>    INP VARCHAR2,<br/>    REF VARCHAR2)<br/>RETURN STYLESHEET;</pre>       | Creates and returns a new <code>Stylesheet</code> instance using the given input and reference URLs.                    |

| Parameter | IN / OUT | Description                                       |
|-----------|----------|---------------------------------------------------|
| XMLDOC    | ( IN )   | <code>DOMDocument</code> to use for construction. |
| INP       | ( IN )   | Input URL to use for construction.                |
| REF       | ( IN )   | Reference URL                                     |

## PROCESSXSL

Transforms input XMLDocument. Any changes to the default processor behavior should be effected before calling this procedure. An application error is raised if processing fails. The options are described in the following table.

| Syntax                                                                                                                                    | Description                                                                                                                            |
|-------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| <pre>FUNCTION PROCESSXSL(   P      PROCESSOR,   SS     STYLE SHEET,   XMLDOC DOMDOCUMENT), RETURN  DOMDOCUMENTFRAGMENT;</pre>             | Transforms input XMLDocument using given DOMDocument and stylesheet, and returns the resultant document fragment.                      |
| <pre>FUNCTION PROCESSXSL(   P      PROCESSOR,   SS     STYLE SHEET,   URL    VARCHAR2, RETURN  DOMDOCUMENTFRAGMENT;</pre>                 | Transforms input XMLDocument using given document as URL and the Stylesheet, and returns the resultant document fragment.              |
| <pre>FUNCTION PROCESSXSL(   P      PROCESSOR,   SS     STYLE SHEET,   CLB    CLOB) RETURN  DOMDOCUMENTFRAGMENT;</pre>                     | Transforms input XMLDocument using given document as CLOB and the Stylesheet, and returns the resultant document fragment.             |
| <pre>PROCEDURE PROCESSXSL(   P      PROCESSOR,   SS     STYLE SHEET,   XMLDOC DOMDOCUMENT,   DIR    VARCHAR2,   FILENAME VARCHAR2);</pre> | Transforms input XMLDocument using given DOMDocument and the stylesheet, and writes the output to the specified file.                  |
| <pre>PROCEDURE PROCESSXSL(   P      PROCESSOR,   SS     STYLE SHEET,   URL    VARCHAR2,   DIR    VARCHAR2,   FILENAME VARCHAR2);</pre>    | Transforms input XMLDocument using given URL and the stylesheet, and writes the output to the specified file in a specified directory. |
| <pre>PROCEDURE PROCESSXSL(   P      PROCESSOR,   SS     STYLE SHEET,   XMLDOC DOMDOCUMENT,   CL IN OUT CLOB);</pre>                       | Transforms input XMLDocument using given DOMDocument and the stylesheet, and writes the output to a CLOB.                              |

| Syntax                                                                                                                                           | Description                                                                                                                                                                                     |
|--------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <pre>FUNCTION PROCESSXSL(   P      PROCESSOR,   SS     STYLESHEET,   XMLDF  DOMDOCUMENTFRAGMENT) RETURN  DOMDOCUMENTFRAGMENT;</pre>              | <p>Transforms input <code>XMLDocumentFragment</code> using given <code>DOMDocumentFragment</code> and the stylesheet, and returns the resultant document fragment.</p>                          |
| <pre>PROCEDURE PROCESSXSL(   P      PROCESSOR,   SS     STYLESHEET,   XMLDF  DOMDOCUMENTFRAGMENT,   DIR    VARCHAR2,   FILENAME VARCHAR2);</pre> | <p>Transforms input <code>XMLDocumentFragment</code> using given <code>DOMDocumentFragment</code> and the stylesheet, and writes the output to the specified file in a specified directory.</p> |
| <pre>PROCEDURE PROCESSXSL(   P      PROCESSOR,   SS     STYLESHEET,   XMLDF  DOMDOCUMENTFRAGMENT,   BUF IN OUT VARCHAR2);</pre>                  | <p>Transforms input <code>XMLDocumentFragment</code> using given <code>DOMDocumentFragment</code> and the stylesheet, and writes the output to a buffer.</p>                                    |
| <pre>PROCEDURE PROCESSXSL(   P      PROCESSOR,   SS     STYLESHEET,   XMLDF  DOMDOCUMENTFRAGMENT,   CL IN OUT CLOB);</pre>                       | <p>Transforms input <code>XMLDocumentFragment</code> using given <code>DOMDocumentFragment</code> and the stylesheet, and writes the output to a CLOB.</p>                                      |

| Parameter | IN / OUT | Description                                         |
|-----------|----------|-----------------------------------------------------|
| P         | (IN)     | Processor instance.                                 |
| SS        | (IN)     | Stylesheet instance.                                |
| XMLDOC    | (IN)     | XML document being transformed.                     |
| URL       | (IN)     | URL for the information being transformed.          |
| CLB       | (IN)     | CLOB containing information to be transformed.      |
| DIR       | (IN)     | Directory where processing output file is saved.    |
| FILENAME  | (IN)     | Processing output file.                             |
| CL        | (IN/OUT) | CLOB to which the processing output is saved.       |
| XMLDF     | (IN)     | <code>XMLDocumentFragment</code> being transformed. |



## READ2CLOB

Read content of a file into a CLOB.

### Syntax

```
FUNCTION READ2CLOB(
 FLOCATION VARCHAR2,
 FNAME VARCHAR2,
 CSID IN NUMBER:=0)
RETURN CLOB;
```

| Parameter | IN / OUT | Description                                                                                                                                                                                                        |
|-----------|----------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| FLOCATION | -        | File directory                                                                                                                                                                                                     |
| FNAME     | -        | File name                                                                                                                                                                                                          |
| CSID      | (IN)     | Character set id of the file <ul style="list-style-type: none"> <li>■ Must be a valid Oracle id; otherwise returns an error</li> <li>■ If 0, input file is assumed to be in the database character set.</li> </ul> |

## REMOVEPARAM

Removes a top level stylesheet parameter.

### Syntax

```
PROCEDURE REMOVEPARAM(
 SS STYLE SHEET,
 NAME VARCHAR2);
```

| Parameter | IN / OUT | Description            |
|-----------|----------|------------------------|
| SS        | (IN)     | Stylesheet instance.   |
| NAME      | (IN)     | Name of the parameter. |

## RESETPARAMS

Resets the top-level stylesheet parameters.

### Syntax

```
PROCEDURE RESETPARAMS(
 SS STYLE SHEET);
```

| Parameter | IN / OUT | Description          |
|-----------|----------|----------------------|
| ss        | ( IN)    | Stylesheet instance. |

## SELECTNODES

Selects nodes which match the given pattern from a DOM tree, and returns the result of the selection.

### Syntax

```
FUNCTION SELECTNODES(
 N DOMNODE,
 PATTERN VARCHAR2)
RETURN DOMNODELIST;
```

| Parameter | IN / OUT | Description               |
|-----------|----------|---------------------------|
| N         | ( IN)    | Root DOMNode of the tree. |
| PATTERN   | ( IN)    | Pattern to use.           |

## SELECTSINGLENODE

Selects the first node from the tree that matches the given pattern, and returns that node.

**Syntax**

```
FUNCTION SELECTSINGLENODE(
 N DOMNODE,
 PATTERN VARCHAR2)
RETURN DOMNODE;
```

| Parameter | IN / OUT | Description               |
|-----------|----------|---------------------------|
| N         | ( IN )   | Root DOMNode of the tree. |
| PATTERN   | ( IN )   | Pattern to use.           |

**SETERRORLOG**

Sets errors to be sent to the specified file.

**Syntax**

```
PROCEDURE SETERRORLOG(
 P PROCESSOR,
 FILENAME VARCHAR2);
```

| Parameter | IN / OUT | Description                                        |
|-----------|----------|----------------------------------------------------|
| P         | ( IN )   | Processor instance.                                |
| FILENAME  | ( IN )   | complete path of the file to use as the error log. |

**SETPARAM**

Sets a top level parameter in the stylesheet. The parameter value must be a valid XPath expression. Literal string values must be quoted.

**Syntax**

```
PROCEDURE SETPARAM(
 SS STYLESHEET,
 NAME VARCHAR2,
 VALUE VARCHAR2);
```

## SHOWWARNINGS

---

| Parameter | IN / OUT | Description             |
|-----------|----------|-------------------------|
| SS        | ( IN )   | Stylesheet instance.    |
| NAME      | ( IN )   | Name of the parameter.  |
| VALUE     | ( IN )   | Value of the parameter. |

## SHOWWARNINGS

Turns warnings on ( TRUE ) or off ( FALSE ).

### Syntax

```
PROCEDURE SHOWWARNINGS(
 P PROCESSOR,
 YES BOOLEAN);
```

| Parameter | IN / OUT | Description                                         |
|-----------|----------|-----------------------------------------------------|
| P         | ( IN )   | Processor instance.                                 |
| YES       | ( IN )   | Mode to set: TRUE to show warnings, FALSE otherwise |

## TRANSFORMNODE

Transforms a node in a DOM tree using the given stylesheet, and returns the result of the transformation as a `DOMDocumentFragment`.

### Syntax

```
FUNCTION TRANSFORMNODE(
 N DOMNODE,
 SS STYLE SHEET)
RETURN DOMDOCUMENTFRAGMENT;
```

| Parameter | IN / OUT | Description           |
|-----------|----------|-----------------------|
| N         | ( IN )   | DOMNode to transform. |
| SS        | ( IN )   | Stylesheet to use.    |

## VALUEOF

Retrieves the value of the first node from the tree that matches the given pattern.

### Syntax

```
PROCEDURE VALUEOF(
 N DOMNODE,
 PATTERN VARCHAR2,
 VAL OUT VARCHAR2);
```

| Parameter | IN / OUT | Description                          |
|-----------|----------|--------------------------------------|
| N         | (IN)     | Node whose value is being retrieved. |
| PATTERN   | (IN)     | Pattern to use.                      |
| VAL       | (OUT)    | Retrieved value.                     |



---

## DEBUG\_EXTPROC

The `DEBUG_EXTPROC` package enables you to start up the `extproc` agent within a session. This utility package can help you debug external procedures.

This chapter contains the following topics:

- [Using `DEBUG\_EXTPROC`](#)
  - [Security Model](#)
  - [Operational Notes](#)
  - [Rules and Limits](#)
- [Summary of `DEBUG\_EXTPROC` Subprograms](#)

---

## Using DEBUG\_EXTPROC

- [Security Model](#)
- [Operational Notes](#)
- [Rules and Limits](#)

### Security Model

Your Oracle account must have `EXECUTE` privileges on the package and `CREATE LIBRARY` privileges.

### Operational Notes

To install the package, run the script `DBGEXTP.SQL`.

- Install/load this package in the Oracle `USER` where you want to debug the 'extproc' process.
- Ensure that you have execute privileges on package `DEBUG_EXTPROC`

```
SELECT SUBSTR(OBJECT_NAME, 1, 20)
FROM USER_OBJECTS
WHERE OBJECT_NAME = 'DEBUG_EXTPROC';
```
- You can install this package as any other user, as long as you have `EXECUTE` privileges on the package.

---

---

**Note:** These notes assumes that you built your shared library with debug symbols to aid in the debugging process. Please check the C compiler manual pages for the appropriate C compiler switches to build the shared library with debug symbols.

---

---

Having installed the package, proceed accordingly:

- Start a brand new oracle session through `SQL*Plus` or `OCI` program by connecting to `ORACLE`.



- Execute procedure `DEBUG_EXTPROC.STARTUP_EXTPROC_AGENT` to startup the extproc agent in this session; for example, execute `DEBUG_EXTPROC.STARTUP_EXTPROC_AGENT`; Do not exit this session, because that terminates the extproc agent.
- Determine the PID of the extproc agent that was started up for this session.
- Using a debugger (for example, `gdb`, `dbx`, or the native system debugger), load the extproc executable and attach to the running process.
- Set a breakpoint on function 'pextproc' and let the debugger continue with its execution.
- Now execute your external procedure in the same session where you first executed `DEBUG_EXTPROC.STARTUP_EXTPROC_AGENT`
- Your debugger should now break in function 'pextproc'. At this point in time, the shared library referenced by your PL/SQL external function would have been loaded and the function resolved. Now set a breakpoint in your C function and let the debugger continue its execution.

Because PL/SQL loads the shared library at runtime, the debugger you use may or may not automatically be able to track the new symbols from the shared library. You may have to issue some debugger command to load the symbols (for example, 'share' in `gdb`)

- The debugger should now break in your C function. Its assumed that you had built the shared library with debugging symbols.
- Now proceed with your debugging.

## Rules and Limits

---

---

**Note:** `DEBUG_EXTPROC` works only on platforms with debuggers that can attach to a running process.

---

---

---

## Summary of DEBUG\_EXTPROC Subprograms

**Table 122-1** *DEBUG\_EXTPROC Package Subprograms*

| <b>Subprogram</b>                                             | <b>Description</b>                                 |
|---------------------------------------------------------------|----------------------------------------------------|
| <a href="#">STARTUP_EXTPROC_AGENT Procedure</a> on page 122-5 | Starts up the extproc agent process in the session |

---

## STARTUP\_EXTPROC\_AGENT Procedure

This procedure starts up the extproc agent process in the session. This enables you to get the PID of the executing process. This PID is needed to be able to attach to the running process using a debugger.

### Syntax

```
DEBUG_EXTPROC.STARTUP_EXTPROC_AGENT;
```



The `HTF` (hypertext functions) and `HTP` (hypertext procedures) packages generate HTML tags. For example, the `HTF.ANCHOR` function generates the HTML anchor tag, `<A>`.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

This chapter contains the following topics:

- [Using HTF](#)
  - [Operational Notes](#)
  - [Rules and Limits](#)
  - [Examples](#)
- [Summary of Tags](#)
- [Summary of HTF Subprograms](#)

## Using HTF

- [Operational Notes](#)
- [Rules and Limits](#)
- [Examples](#)

### Operational Notes

For every HTF function that generates one or more HTML tags, there is a corresponding HTP procedure with identical parameters with the following exception:

- The [PRINTS Procedure](#) and the [PS Procedure](#) do not have HTF function equivalents. Use the [ESCAPE\\_SC Function](#) or the [ESCAPE\\_URL Function](#) if you need a string conversion function. Note that while there is a [ESCAPE\\_SC Procedure](#) that performs the same operation as the [PRINTS Procedure](#) and the [PS Procedure](#), there is no procedural equivalent for the [ESCAPE\\_URL Function](#).
- The [FORMAT\\_CELL Function](#) does not have an HTP equivalent. The function formats column values inside an HTML table using [TABLEDATA Function](#) which does have an HTP equivalent in the [TABLEDATA Procedure](#). The advantage of this using the [FORMAT\\_CELL Function](#) is that it allows for better control over the HTML tables.

The function versions do not directly generate output in your web page. Instead, they pass their output as return values to the statements that invoked them. Use these functions when you need to nest calls. To print the output of HTF functions, call the functions from within the `HTF.PRINT` function. It then prints its parameters to the generated web page.

### Rules and Limits

If you use values of the LONG data type in functions such as `HTF.PRINT`, `HTF.PRN`, `HTF.PA` or `OWA_UTIL.CELLSPRINT`, only the first 32 K of the LONG data is used. The LONG data is bound to a VARCHAR2 data type in the function.

## Examples

The following commands generate a simple HTML document:

```
CREATE OR REPLACE PROCEDURE hello AS
BEGIN
 HTP.P (HTF.HTMLOPEN); -- generates <HTML>
 HTP.P (HTF.HEADOPEN); -- generates <HEAD>
 HTP.P (HTF.TITLE('Hello')); -- generates <TITLE>Hello</TITLE>
 HTP.P (HTF.HEADCLOSE); -- generates </HEAD>
 HTP.P (HTF.BODYOPEN); -- generates <BODY>
 HTP.P (HTF.HEADER(1, 'Hello')); -- generates <H1>Hello</H1>
 HTP.P (HTF.BODYCLOSE); -- generates </BODY>
 HTP.P (HTF.HTMLCLOSE); -- generates </HTML>
END;
```

## Summary of Tags

---

### HTML, HEAD, and BODY Tags

[HTMLOPEN Function](#), [HTMLCLOSE Function](#) - generate <HTML> and </HTML>

[HEADOPEN Function](#), [HEADCLOSE Function](#) - generate <HEAD> and </HEAD>

[BODYOPEN Function](#), [BODYCLOSE Function](#) - generate <BODY> and </BODY>

### Comment Tag

[COMMENT Function](#) - generates <!-- and -->

### Tags in the <HEAD> Area

[BASE Function](#) - generates <BASE>

[LINKREL Function](#) - generates <LINK> with the REL attribute

[LINKREV Function](#) - generates <LINK> with the REV attribute

[TITLE Function](#) - generates <TITLE>

[META Function](#) - generates <META>

[SCRIPT Function](#) - generates <SCRIPT>

[STYLE Function](#) - generates <STYLE>

[ISINDEX Function](#) - generates <ISINDEX>

### Applet Tags

[APPLETOPEN Function](#), [APPLETCLOSE Function](#) - generate <APPLET> and </APPLET>

[PARAM Function](#) - generates <PARAM>

### List Tags

[OLISTOPEN Function](#), [OLISTCLOSE Function](#) - generate <OL> and </OL>

[ULISTOPEN Function](#), [ULISTCLOSE Function](#) - generate <UL> and </UL>

[DLISTOPEN Function](#), [DLISTCLOSE Function](#) - generate <DL> and </DL>

[DLISTTERM Function](#) - generates <DT>



**DLISTDEF Function** - generates <DD>

**DIRLISTOPEN Function, DIRLISTCLOSE Function** - generate <DIR> and </DIR>

**LISTHEADER Function** - generates <LH>

**LISTINGOPEN Function, LISTINGCLOSE Function** - generate <LISTING> and </LISTING>

**MENULISTOPEN Function** - generate <MENU> and </MENU>

**LISTITEM Function** - generates <LI>

## Form Tags

**FORMOPEN Function, FORMCLOSE Function** - generate <FORM> and </FORM>

**FORMCHECKBOX Function** - generates <INPUT TYPE="CHECKBOX">

**FORMHIDDEN Function** - generates <INPUT TYPE="HIDDEN">

**FORMIMAGE Function** - generates <INPUT TYPE="IMAGE">

**FORMPASSWORD Function** - generates <INPUT TYPE="PASSWORD">

**FORMRADIO Function** - generates <INPUT TYPE="RADIO">

**FORMSELECTOPEN Function, FORMSELECTCLOSE Function** - generate <SELECT> and </SELECT>

**FORMSELETOPTION Function** - generates <OPTION>

**FORMTEXT Function** - generates <INPUT TYPE="TEXT">

**FORMTEXTAREA Function** - generate <TEXTAREA>

**FORMTEXTAREAOPEN Function, FORMTEXTAREACLOSE Function** - generate <TEXTAREA> and </TEXTAREA>

**FORMRESET Function** - generates <INPUT TYPE="RESET">

**FORMSUBMIT Function** - generates <INPUT TYPE="SUBMIT">

## Table Tags

**TABLEOPEN Function, TABLECLOSE Function** - generate <TABLE> and </TABLE>

**TABLECAPTION Function** - generates <CAPTION>

**TABLEROWOPEN Function, TABLEROWCLOSE Function** - generate `<TR>` and `</TR>`

**TABLEHEADER Function** - generates `<TH>`

**TABLEDATA Function** - generates `<TD>`

## IMG, HR, and A Tags

**HR Function, LINE Function** - generate `<HR>`

**IMG Function, IMG2 Function** - generate `<IMG>`

**ANCHOR Function, ANCHOR2 Function** - generate `<A>`

**MAPOPEN Function, MAPCLOSE Function** - generate `<MAP>` and `</MAP>`

## Paragraph Formatting Tags

**HEADER Function** - generates heading tags (`<H1>` to `<H6>`)

**PARA Function, PARAGRAPH Function** - generate `<P>`

**PRN Functions, PRINT Functions** - generate any text that is passed in

**PRN Functions, S Function** - generate any text that is passed in; special characters in HTML are escaped

**PREOPEN Function, PRECLOSE Function** - generate `<PRE>` and `</PRE>`

**BLOCKQUOTEOPEN Function, BLOCKQUOTECLOSE Function** - generate `<BLOCKQUOTE>` and `</BLOCKQUOTE>`

**DIV Function** - generates `<DIV>`

**NL Function, BR Function** - generate `<BR>`

**NOBR Function** - generates `<NOBR>`

**WBR Function** - generates `<WBR>`

**PLAINTEXT Function** - generates `<PLAINTEXT>`

**ADDRESS Function** - generates `<ADDRESS>`

**MAILTO Function** - generates `<A>` with the `MAILTO` attribute

**AREA Function** - generates `<AREA>`

**BGSOUND Function** - generates `<BGSOUND>`

## Character Formatting Tags

**BASEFONT Function** - generates <BASEFONT>

**BIG Function** - generates <BIG>

**BOLD Function** - generates <B>

**CENTER Function** - generates <CENTER> and </CENTER>

**CENTEROPEN Function, CENTERCLOSE Function** - generate <CENTER> and </CENTER>

**CITE Function** - generates <CITE>

**CODE Function** - generates <CODE>

**DFN Function** - generates <DFN>

**EM Function, EMPHASIS Function** - generate <EM>

**FONTOPEN Function, FONTCLOSE Function** - generate <FONT> and </FONT>

**ITALIC Function** - generates <I>

**KBD Function, KEYBOARD Function** - generate <KBD> and </KBD>

**S Function** - generates <S>

**SAMPLE Function** - generates <SAMP>

**SMALL Function** - generates <SMALL>

**STRIKE Function** - generates <STRIKE>

**STRONG Function** - generates <STRONG>

**SUB Function** - generates <SUB>

**SUP Function** - generates <SUP>

**TELETYPE Function** - generates <TT>

**UNDERLINE Function** - generates <U>

**VARIABLE Function** - generates <VAR>

## Frame Tags

**FRAME Function** - generates <FRAME>

**FRAMESETOPEN Function, FRAMESETCLOSE Function** - generate <FRAMESET> and </FRAMESET>

[NOFRAMESOPEN Function, NOFRAMESCLOSE Function](#) - generate  
<NOFRAMES> and </NOFRAMES>

---

## Summary of HTF Subprograms

**Table 123–1** *HTF Package Subprograms*

| Subprogram                                              | Description                                                                                               |
|---------------------------------------------------------|-----------------------------------------------------------------------------------------------------------|
| <a href="#">ADDRESS Function</a> on page 123-17         | Generates the <ADDRESS> and </ADDRESS> tags which specify the address, author and signature of a document |
| <a href="#">ANCHOR Function</a> on page 123-18          | Generates the <A> and </A> tags which specify the source or destination of a hypertext link               |
| <a href="#">ANCHOR2 Function</a> on page 123-19         | Generates the <A> and </A> tags which specify the source or destination of a hypertext link               |
| <a href="#">APPLETCLOSE Function</a> on page 123-20     | Closes the applet invocation with the </APPLET> tag                                                       |
| <a href="#">APPLETOPEN Function</a> on page 123-21      | Generates the <APPLET> tag which begins the invocation of a Java applet                                   |
| <a href="#">AREA Function</a> on page 123-23            | Generates the <AREA> tag, which defines a client-side image map                                           |
| <a href="#">BASE Function</a> on page 123-24            | Generates the <BASE> tag which records the URL of the document                                            |
| <a href="#">BASEFONT Function</a> on page 123-25        | Generates the <BASEFONT> tag which specifies the base font size for a Web page                            |
| <a href="#">BGSOUND Function</a> on page 123-26         | Generates the <BGSOUND> tag which includes audio for a Web page                                           |
| <a href="#">BIG Function</a> on page 123-27             | Generates the <BIG> and </BIG> tags which direct the browser to render the text in a bigger font          |
| <a href="#">BLOCKQUOTECLOSE Function</a> on page 123-28 | Generates the </BLOCKQUOTE> tag which mark the end of a section of quoted text                            |
| <a href="#">BLOCKQUOTEOPEN Function</a> on page 123-29  | Generates the <BLOCKQUOTE> tag, which marks the beginning of a section of quoted text                     |
| <a href="#">BODYCLOSE Function</a> on page 123-30       | Generates the </BODY> tag which marks the end of a body section of an HTML document                       |
| <a href="#">BODYOPEN Function</a> on page 123-31        | Generates the <BODY> tag which marks the beginning of the body section of an HTML document                |

**Table 123–1 (Cont.) HTF Package Subprograms**

| <b>Subprogram</b>                                    | <b>Description</b>                                                                                                                             |
|------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">BOLD Function</a> on page 123-32         | Generates the <B> and </B> tags which direct the browser to display the text in boldface                                                       |
| <a href="#">BR Function</a> on page 123-33           | Generates the <BR> tag which begins a new line of text                                                                                         |
| <a href="#">CENTER Function</a> on page 123-34       | Generates the <CENTER> and </CENTER> tags which center a section of text within a Web page                                                     |
| <a href="#">CENTERCLOSE Function</a> on page 123-35  | Generates the </CENTER> tag which marks the end of a section of text to center                                                                 |
| <a href="#">CENTEROPEN Function</a> on page 123-36   | Generates the <CENTER> tag which mark the beginning of a section of text to center                                                             |
| <a href="#">CITE Function</a> on page 123-37         | Generates the <CITE> and </CITE> tags which direct the browser to render the text as a citation                                                |
| <a href="#">CODE Function</a> on page 123-38         | Generates the <CODE> and </CODE> tags which direct the browser to render the text in monospace font or however "code" is defined stylistically |
| <a href="#">COMMENT Function</a> on page 123-39      | Generates This function generates the comment tags<br><!-- ctext -->                                                                           |
| <a href="#">DFN Function</a> on page 123-40          | Generates the <DFN> and </DFN> tags which direct the browser to mark the text as italics or however "definition" is defined stylistically      |
| <a href="#">DIRLISTCLOSE Function</a> on page 123-41 | Generates the </DIR> tag which ends a directory list section                                                                                   |
| <a href="#">DIRLISTOPEN Function</a> on page 123-42  | Generates the <DIR> which starts a directory list section                                                                                      |
| <a href="#">DIV Function</a> on page 123-43          | Generates the <DIV> tag which creates document divisions                                                                                       |
| <a href="#">DLISTCLOSE Function</a> on page 123-44   | Generates the </DL> tag which ends a definition list                                                                                           |
| <a href="#">DLISTOPEN Function</a> on page 123-45    | Generates the <DL> tag which starts a definition list                                                                                          |
| <a href="#">DLISTDEF Function</a> on page 123-46     | Generates the <DD> tag, which inserts definitions of terms                                                                                     |
| <a href="#">DLISTTERM Function</a> on page 123-47    | Generates the <DT> tag which defines a term in a definition list <DL>                                                                          |
| <a href="#">EM Function</a> on page 123-48           | Generates the <EM> and </EM> tags, which define text to be emphasized                                                                          |

**Table 123–1 (Cont.) HTF Package Subprograms**

| <b>Subprogram</b>                                       | <b>Description</b>                                                                                                                     |
|---------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">EMPHASIS Function</a> on page 123-49        | Generates the <EM> and </EM> tags, which define text to be emphasized                                                                  |
| <a href="#">ESCAPE_SC Function</a> on page 123-50       | Replaces characters that have special meaning in HTML with their escape sequences                                                      |
| <a href="#">ESCAPE_URL Function</a> on page 123-51      | Replaces characters that have special meaning in HTML and HTTP with their escape sequences                                             |
| <a href="#">FONTCLOSE Function</a> on page 123-53       | Generates the </FONT> tag which marks the end of a section of text with the specified font characteristics                             |
| <a href="#">FONTOPEN Function</a> on page 123-53        | Generates the <FONT> which marks the beginning of section of text with the specified font characteristics                              |
| <a href="#">FORMAT_CELL Function</a> on page 123-54     | formats column values inside an HTML table using the <a href="#">TABLEDATA Function</a>                                                |
| <a href="#">FORMCHECKBOX Function</a> on page 123-55    | Generates the <INPUT> tag with TYPE="checkbox" which inserts a checkbox element in a form                                              |
| <a href="#">FORMCLOSE Function</a> on page 123-56       | Generates the </FORM> tag which marks the end of a form section in an HTML document                                                    |
| <a href="#">FORMFILE Function</a> on page 123-57        | Generates the <INPUT> tag with TYPE="file" which inserts a file form element, and is used for file uploading for a given page          |
| <a href="#">FORMHIDDEN Function</a> on page 123-58      | Generates the <INPUT> tag with TYPE="hidden" which inserts a hidden form element                                                       |
| <a href="#">FORMIMAGE Function</a> on page 123-59       | Generates the <INPUT> tag with TYPE="image" which creates an image field that the user clicks to submit the form immediately           |
| <a href="#">FORMOPEN Function</a> on page 123-60        | Generates the <FORM> tag which marks the beginning of a form section in an HTML document                                               |
| <a href="#">FORMPASSWORD Function</a> on page 123-61    | Generates the <INPUT> tag with TYPE="password" which creates a single-line text entry field                                            |
| <a href="#">FORMRADIO Function</a> on page 123-62       | Generates the <INPUT> tag with TYPE="radio", which creates a radio button on the HTML form                                             |
| <a href="#">FORMRESET Function</a> on page 123-63       | Generates the <INPUT> tag with TYPE="reset" which creates a button that, when selected, resets the form fields to their initial values |
| <a href="#">FORMSELECTCLOSE Function</a> on page 123-64 | Generates the </SELECT> tag which marks the end of a Select form element                                                               |

**Table 123–1 (Cont.) HTF Package Subprograms**

| <b>Subprogram</b>                                         | <b>Description</b>                                                                                                                                                                  |
|-----------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">FORMSELECTOPEN Function</a> on page 123-65    | Generates the <code>&lt;/SELECT&gt;</code> tag which marks the beginning of a Select form element                                                                                   |
| <a href="#">FORMSELECTOPTION Function</a> on page 123-67  | Generates the <code>&lt;OPTION&gt;</code> tag which represents one choice in a Select element                                                                                       |
| <a href="#">FORMSUBMIT Function</a> on page 123-68        | Generates the <code>&lt;INPUT&gt;</code> tag with <code>TYPE="submit"</code> which creates a button that, when clicked, submits the form                                            |
| <a href="#">FORMTEXT Function</a> on page 123-69          | Generates the <code>&lt;INPUT&gt;</code> tag with <code>TYPE="text"</code> , which creates a field for a single line of text                                                        |
| <a href="#">FORMTEXTAREA Function</a> on page 123-70      | Generates the <code>&lt;TEXTAREA&gt;</code> tag, which creates a text field that has no predefined text in the text area                                                            |
| <a href="#">FORMTEXTAREA2 Function</a> on page 123-71     | Generates the <code>&lt;TEXTAREA&gt;</code> tag, which creates a text field that has no predefined text in the text area with the ability to specify a wrap style                   |
| <a href="#">FORMTEXTAREACLOSE Function</a> on page 123-72 | Generates the <code>&lt;/TEXTAREA&gt;</code> tag which ends a text area form element                                                                                                |
| <a href="#">FORMTEXTAREAOPEN Function</a> on page 123-73  | Generates the <code>&lt;TEXTAREA&gt;</code> which marks the beginning of a text area form element                                                                                   |
| <a href="#">FORMTEXTAREAOPEN2 Function</a> on page 123-74 | Generates the <code>&lt;TEXTAREA&gt;</code> which marks the beginning of a text area form element with the ability to specify a wrap style                                          |
| <a href="#">FRAME Function</a> on page 123-75             | Generates the <code>&lt;FRAME&gt;</code> tag which defines the characteristics of a frame created by a <code>&lt;FRAMESET&gt;</code> tag                                            |
| <a href="#">FRAMESETCLOSE Function</a> on page 123-76     | Generates the <code>&lt;/FRAMESET&gt;</code> tag which ends a frameset section                                                                                                      |
| <a href="#">FRAMESETOPEN Function</a> on page 123-77      | Generates the <code>&lt;/FRAMESET&gt;</code> tag which begins a frameset section                                                                                                    |
| <a href="#">HEADCLOSE Function</a> on page 123-78         | Generates the <code>&lt;/HEAD&gt;</code> tag which marks the end of an HTML document head section                                                                                   |
| <a href="#">HEADOPEN Function</a> on page 123-79          | Generates the <code>&lt;HEAD&gt;</code> tag which marks the beginning of the HTML document head section                                                                             |
| <a href="#">HEADER Function</a> on page 123-80            | Generates opening heading tags ( <code>&lt;H1&gt;</code> to <code>&lt;H6&gt;</code> ) and their corresponding closing tags ( <code>&lt;/H1&gt;</code> to <code>&lt;/H6&gt;</code> ) |
| <a href="#">HR Function</a> on page 123-81                | Generates the <code>&lt;HR&gt;</code> tag, which generates a line in the HTML document                                                                                              |



**Table 123–1 (Cont.) HTF Package Subprograms**

| <b>Subprogram</b>                                    | <b>Description</b>                                                                                                                                                                  |
|------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">HTMLCLOSE Function</a> on page 123-83    | Generates the <code>&lt;/HTML&gt;</code> tag which marks the end of an HTML document                                                                                                |
| <a href="#">HTMLOPEN Function</a> on page 123-83     | Generates the <code>&lt;HTML&gt;</code> tag which marks the beginning of an HTML document                                                                                           |
| <a href="#">IMG Function</a> on page 123-84          | Generates the <code>&lt;IMG&gt;</code> tag which directs the browser to load an image onto the HTML page                                                                            |
| <a href="#">IMG2 Function</a> on page 123-85         | Generates the <code>&lt;IMG&gt;</code> tag which directs the browser to load an image onto the HTML page with the option of specifying values for the <code>USEMAP</code> attribute |
| <a href="#">ISINDEX Function</a> on page 123-86      | Creates a single entry field with a prompting text, such as "enter value," then sends that value to the URL of the page or program                                                  |
| <a href="#">ITALIC Function</a> on page 123-87       | Generates the <code>&lt;I&gt;</code> and <code>&lt;/I&gt;</code> tags which direct the browser to render the text in italics                                                        |
| <a href="#">KBD Function</a> on page 123-88          | Generates the <code>&lt;KBD&gt;</code> and <code>&lt;/KBD&gt;</code> tags which direct the browser to render the text in monospace font                                             |
| <a href="#">KEYBOARD Function</a> on page 123-89     | Generates the <code>&lt;KBD&gt;</code> and <code>&lt;/KBD&gt;</code> tags, which direct the browser to render the text in monospace font                                            |
| <a href="#">LINE Function</a> on page 123-90         | Generates the <code>&lt;HR&gt;</code> tag, which generates a line in the HTML document                                                                                              |
| <a href="#">LINKREL Function</a> on page 123-91      | Generates the <code>&lt;LINK&gt;</code> tag with the <code>REL</code> attribute which delineates the relationship described by the hypertext link from the anchor to the target     |
| <a href="#">LINKREV Function</a> on page 123-92      | Generates the <code>&lt;LINK&gt;</code> tag with the <code>REV</code> attribute which delineates the relationship described by the hypertext link from the target to the anchor     |
| <a href="#">LISTHEADER Function</a> on page 123-93   | Generates the <code>&lt;LH&gt;</code> and <code>&lt;/LH&gt;</code> tags which print an HTML tag at the beginning of the list                                                        |
| <a href="#">LISTINGCLOSE Function</a> on page 123-94 | Generates the <code>&lt;/LISTING&gt;</code> tags which marks the end of a section of fixed-width text in the body of an HTML page                                                   |
| <a href="#">LISTINGOPEN Function</a> on page 123-95  | Generates the <code>&lt;LISTING&gt;</code> tag which marks the beginning of a section of fixed-width text in the body of an HTML page                                               |
| <a href="#">LISTITEM Function</a> on page 123-96     | Generates the <code>&lt;LI&gt;</code> tag, which indicates a list item                                                                                                              |

**Table 123–1 (Cont.) HTF Package Subprograms**

| <b>Subprogram</b>                                      | <b>Description</b>                                                                                                            |
|--------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">MAILTO Function</a> on page 123-97         | Generates the <A> tag with the HREF set to 'mailto' prepended to the mail address argument                                    |
| <a href="#">MAPCLOSE Function</a> on page 123-98       | Generates the </MAP> tag which marks the end of a set of regions in a client-side image map                                   |
| <a href="#">MAPOPEN Function</a> on page 123-99        | Generates the <MAP> tag which mark the beginning of a set of regions in a client-side image map                               |
| <a href="#">MENULISTCLOSE Function</a> on page 123-100 | Generates the </MENU> tag which ends a list that presents one line for each item                                              |
| <a href="#">MENULISTOPEN Function</a> on page 123-101  | Generates the <MENU> tag which create a list that presents one line for each item                                             |
| <a href="#">META Function</a> on page 123-102          | Generates the <META> tag, which embeds meta-information about the document and also specifies values for HTTP headers         |
| <a href="#">NL Function</a> on page 123-103            | Generates the <BR> tag which begins a new line of text                                                                        |
| <a href="#">NOBR Function</a> on page 123-104          | Generates the <NOBR> and </NOBR> tags which turn off line-breaking in a section of text                                       |
| <a href="#">NOFRAMESCLOSE Function</a> on page 123-105 | Generates the </NOFRAMES> tag which marks the end of a no-frames section                                                      |
| <a href="#">NOFRAMESOPEN Function</a> on page 123-106  | Generates the <NOFRAMES> tag which mark the beginning of a no-frames section                                                  |
| <a href="#">OLISTCLOSE Function</a> on page 123-107    | Generates the </OL> tag which defines the end of an ordered list                                                              |
| <a href="#">OLISTOPEN Function</a> on page 123-108     | Generates the <OL> tag which marks the beginning of an ordered list                                                           |
| <a href="#">PARA Function</a> on page 123-109          | Generates the <P> tag which indicates that the text that comes after the tag is to be formatted as a paragraph                |
| <a href="#">PARAGRAPH Function</a> on page 123-110     | Adds attributes to the <P> tag                                                                                                |
| <a href="#">PARAM Function</a> on page 123-111         | Generates the <PARAM> tag which specifies parameter values for Java applets                                                   |
| <a href="#">PLAINTEXT Function</a> on page 123-112     | Generates the <PLAINTEXT> and </PLAINTEXT> tags which direct the browser to render the text they surround in fixed-width type |
| <a href="#">PRECLOSE Function</a> on page 123-113      | Generates the </PRE> tag which marks the end of a section of preformatted text in the body of the HTML page                   |

**Table 123–1 (Cont.) HTF Package Subprograms**

| <b>Subprogram</b>                                     | <b>Description</b>                                                                                                                                             |
|-------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">PREOPEN Function</a> on page 123-114      | Generates the <PRE> tag which marks the beginning of a section of preformatted text in the body of the HTML page                                               |
| <a href="#">PRINT Functions</a> on page 123-115       | Generates the specified parameter as a string terminated with the \n newline character                                                                         |
| <a href="#">PRN Functions</a> on page 123-116         | Generates the specified parameter as a string                                                                                                                  |
| <a href="#">S Function</a> on page 123-117            | Generates the <S> and </S> tags which direct the browser to render the text they surround in strikethrough type                                                |
| <a href="#">SAMPLE Function</a> on page 123-118       | Generates the <SAMP> and </SAMP> tags which direct the browser to render the text they surround in monospace font or however "sample" is defined stylistically |
| <a href="#">SCRIPT Function</a> on page 123-119       | Generates the <SCRIPT> and </SCRIPT> tags which contain a script written in languages such as JavaScript and VBscript                                          |
| <a href="#">SMALL Function</a> on page 123-120        | Generates the <SMALL> and </SMALL> tags, which direct the browser to render the text they surround using a small font                                          |
| <a href="#">STRIKE Function</a> on page 123-121       | Generates the <STRIKE> and </STRIKE> tags which direct the browser to render the text they surround in strikethrough type                                      |
| <a href="#">STRONG Function</a> on page 123-122       | Generates the <STRONG> and </STRONG> tags which direct the browser to render the text they surround in bold or however "strong" is defined stylistically       |
| <a href="#">STYLE Function</a> on page 123-123        | Generates the <STYLE> and </STYLE> tags which include a style sheet in a Web page                                                                              |
| <a href="#">SUB Function</a> on page 123-124          | Generates the <SUB> and </SUB> tags which direct the browser to render the text they surround as subscript                                                     |
| <a href="#">SUP Function</a> on page 123-125          | Generates the <SUP> and </SUP> tags which direct the browser to render the text they surround as superscript                                                   |
| <a href="#">TABLECAPTION Function</a> on page 123-126 | Generates the <CAPTION> and </CAPTION> tags which place a caption in an HTML table                                                                             |
| <a href="#">TABLEDATA Function</a> on page 123-127    | Generates the <TD> and </TD> tags which insert data into a cell of an HTML table                                                                               |
| <a href="#">TABLEHEADER Function</a> on page 123-128  | Generates the <TH> and </TH> tags which insert a header cell in an HTML table.                                                                                 |

**Table 123–1 (Cont.) HTF Package Subprograms**

| <b>Subprogram</b>                                      | <b>Description</b>                                                                                                                                                                                |
|--------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <a href="#">TABLECLOSE Function</a> on page 123-129    | Generates the <code>&lt;/TABLE&gt;</code> tag which marks the end of an HTML table                                                                                                                |
| <a href="#">TABLEOPEN Function</a> on page 123-130     | Generates the <code>&lt;TABLE&gt;</code> tag which marks the beginning of an HTML table                                                                                                           |
| <a href="#">TABLEROWCLOSE Function</a> on page 123-131 | Generates the <code>&lt;/TR&gt;</code> tag which marks the end of a new row in an HTML table                                                                                                      |
| <a href="#">TABLEROWOPEN Function</a> on page 123-132  | Generates the <code>&lt;TR&gt;</code> tag which marks the beginning of a new row in an HTML table                                                                                                 |
| <a href="#">TELETYPE Function</a> on page 123-133      | Generates the <code>&lt;TT&gt;</code> and <code>&lt;/TT&gt;</code> tags which direct the browser to render the text they surround in a fixed width typewriter font, for example, the courier font |
| <a href="#">TITLE Function</a> on page 123-134         | Generates the <code>&lt;TITLE&gt;</code> and <code>&lt;/TITLE&gt;</code> tags which specify the text to display in the titlebar of the browser window                                             |
| <a href="#">ULISTCLOSE Function</a> on page 123-135    | Generates the <code>&lt;/UL&gt;</code> tag which marks the end of an unordered list                                                                                                               |
| <a href="#">ULISTOPEN Function</a> on page 123-136     | Generates the <code>&lt;UL&gt;</code> tag which marks the beginning of an unordered list                                                                                                          |
| <a href="#">UNDERLINE Function</a> on page 123-137     | Generates the <code>&lt;U&gt;</code> and <code>&lt;/U&gt;</code> tags, which direct the browser to render the text they surround with an underline                                                |
| <a href="#">VARIABLE Function</a> on page 123-138      | Generates the <code>&lt;VAR&gt;</code> and <code>&lt;/VAR&gt;</code> tags which direct the browser to render the text they surround in italics or however "variable" is defined stylistically.    |
| <a href="#">WBR Function</a> on page 123-139           | Generates the <code>&lt;WBR&gt;</code> tag, which inserts a soft line break within a section of NOBR text                                                                                         |

## ADDRESS Function

This function generates the `<ADDRESS>` and `</ADDRESS>` tags which specify the address, author and signature of a document.

### Syntax

```
HTF.ADDRESS (
 cvalue IN VARCHAR2
 cnowrap IN VARCHAR2 DEFAULT NULL
 cclear IN VARCHAR2 DEFAULT NULL
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–2 ADDRESS Function Parameters**

| Parameter                | Description                                                                                                         |
|--------------------------|---------------------------------------------------------------------------------------------------------------------|
| <code>cvalue</code>      | The string that goes between the <code>&lt;ADDRESS&gt;</code> and <code>&lt;/ADDRESS&gt;</code> tags.               |
| <code>cnowrap</code>     | If the value for this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is included in the tag |
| <code>cclear</code>      | The value for the <code>CLEAR</code> attribute.                                                                     |
| <code>cattributes</code> | The other attributes to be included as-is in the tag                                                                |

### Examples

This function generates

```
<ADDRESS CLEAR="cclear" NOWRAP cattributes>cvalue</ADDRESS>
```

## ANCHOR Function

This function and the [ANCHOR2 Function](#) functions generate the `<A>` and `</A>` HTML tags which specify the source or destination of a hypertext link. The difference between these subprograms is that the [ANCHOR2 Function](#) provides a target and therefore can be used for a frame.

### Syntax

```
HTF.ANCHOR (
 curl IN VARCHAR2,
 ctext IN VARCHAR2,
 cname IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–3 ANCHOR Function Parameters**

Parameter	Description
<code>curl</code>	The value for the <code>HREF</code> attribute.
<code>ctext</code>	The string that goes between the <code>&lt;A&gt;</code> and <code>&lt;/A&gt;</code> tags.
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
ctext
```

### Usage Notes

This tag accepts several attributes, but either `HREF` or `NAME` is required. `HREF` specifies to where to link. `NAME` allows this tag to be a target of a hypertext link.

## ANCHOR2 Function

This function and the [ANCHOR Function](#) generate the <A> and </A> HTML tags which specify the source or destination of a hypertext link. The difference between these subprograms is that this functions provides a target and therefore can be used for a frame.

### Syntax

```
HTF.ANCHOR2 (
 curl IN VARCHAR2,
 ctext IN VARCHAR2,
 cname IN VARCHAR2 DEFAULT NULL,
 ctarget in varchar2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–4 ANCHOR2 Function Parameters**

Parameter	Description
curl	The value for the HREF attribute.
ctext	The string that goes between the <A> and </A> tags.
cname	The value for the NAME attribute
ctarget	The value for the TARGET attribute.
cattributes	The other attributes to be included as-is in the tag

### Examples

This function generates

```
ctext
```

## APPLETCLOSE Function

This function closes the applet invocation with the `</APPLET>` tag. You must first invoke the a Java applet using [APPLETOPEN Function](#) on page 123-21

### Syntax

```
HTF.APPLETCLOSE
RETURN VARCHAR2;
```



## APPLETOPEN Function

This function generates the `<APPLET>` tag which begins the invocation of a Java applet. You close the applet invocation with [APPLETCLOSE Function](#) on page 123-20 which generates the `</APPLET>` tag.

### Syntax

```
HTF.APPLETOPEN (
 ccode IN VARCHAR2,
 cheight IN NUMBER,
 cwidth IN NUMBER,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–5** *APPLETOPEN Function Parameters*

Parameter	Description
<code>ccode</code>	The the value for the <code>CODE</code> attribute which specifies the name of the applet class.
<code>cheight</code>	The value for the <code>HEIGHT</code> attribute.
<code>cwidth</code>	The value for the <code>WIDTH</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<APPLET CODE=ccode HEIGHT=cheight WIDTH=cwidth cattributes>
```

so that, for example,

```
HTF.appletopen('testclass.class', 100, 200, 'CODEBASE="/ows-applets"')
```

generates

```
<APPLET CODE="testclass.class" height=100 width=200 CODEBASE="/ows-applets">
```

## Usage Notes

- Specify parameters to the Java applet using the [PARAM Function](#) function on page 123-111.
- Use the `cattributes` parameter to specify the `CODEBASE` attribute since the PL/SQL cartridge does not know where to find the class files. The `CODEBASE` attribute specifies the virtual path containing the class files.

## AREA Function

This function generates the <AREA> tag, which defines a client-side image map. The <AREA> tag defines areas within the image and destinations for the areas.

### Syntax

```
HTF.AREA (
 ccoords IN VARCHAR2
 cshape IN VARCHAR2 DEFAULT NULL,
 chref IN VARCHAR2 DEFAULT NULL,
 cnohref IN VARCHAR2 DEFAULT NULL,
 ctarget IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–6 AREA Function Parameters**

Parameter	Description
<code>ccords</code>	The the value for the <code>COORDS</code> attribute.
<code>cshape</code>	The value for the <code>SHAPE</code> attribute.
<code>chref</code>	The value for the <code>HREF</code> attribute.
<code>cnohref</code>	If the value for this parameter is not <code>NULL</code> , the <code>NOHREF</code> attribute is added to the tag.
<code>ctarget</code>	The value for the <code>TARGET</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<AREA COORDS="ccoords" SHAPE="cshape" HREF="chref" NOHREF TARGET="ctarget"
cattributes>
```

## BASE Function

This function generates the <BASE> tag which records the URL of the document.

### Syntax

```
HTF.BASE (
 ctarget IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–7** *BASE Function Parameters*

Parameter	Description
<code>ctarget</code>	The value for the <code>TARGET</code> attribute which establishes a window name to which all links in this document are targeted.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<BASE HREF="<current URL>" TARGET="ctarget" cattributes>
```

## BASEFONT Function

This function generates the `<BASEFONT>` tag which specifies the base font size for a Web page.

### Syntax

```
HTF.BASEFONT (
 nsize IN INTEGER)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–8** *BASEFONT Function Parameters*

Parameter	Description
<code>nsize</code>	The value for the <code>SIZE</code> attribute.

### Examples

This function generates

```
<BASEFONT SIZE="nsize">
```

## BGSOUND Function

This function generates the <BGSOUND> tag which includes audio for a Web page.

### Syntax

```
HTF.BGSOUND (
 csrc IN VARCHAR2,
 cloop IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–9 BGSOUND Function Parameters**

Parameter	Description
<code>csrc</code>	The value for the SRC attribute.
<code>clloop</code>	The value for the LOOP attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<BGSOUND SRC="csrc" LOOP="clloop" cattributes>
```

## BIG Function

This function generates the <BIG> and </BIG> tags which direct the browser to render the text in a bigger font.

### Syntax

```
HTF.BIG (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–10** *BIG Function Parameters*

Parameter	Description
<code>ctext</code>	The the text that goes between the tags.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<BIG cattributes>ctext</BIG>
```

## BLOCKQUOTECLOSE Function

This function generates the `</BLOCKQUOTE>` tag which mark the end of a section of quoted text. You mark the beginning of a section of text by means of the [BLOCKQUOTEOPEN Function](#).

### Syntax

```
HTF.BLOCKQUOTECLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</BLOCKQUOTE>
```



## BLOCKQUOTEOPEN Function

This function generates the <BLOCKQUOTE> tag, which marks the beginning of a section of quoted text. You mark the end of a section of text by means of the [BLOCKQUOTECLOSE Function](#).

### Syntax

```
HTF.BLOCKQUOTEOPEN (
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–11** *BLOCKQUOTEOPEN Function Parameters*

Parameter	Description
cnowrap	If the value for this parameter is not NULL, the NOWRAP attribute is added to the tag.
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<BLOCKQUOTE CLEAR="cclear" NOWRAP cattributes>
```

## BODYCLOSE Function

This function generates the `</BODY>` tag which marks the end of a body section of an HTML document. You mark the beginning of a body section by means of the [BODYOPEN Function](#).

### Syntax

```
HTF.BODYCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</BODY>
```

## BODYOPEN Function

This function generates the <BODY> tag which marks the beginning of the body section of an HTML document. You mark the end of a body section by means of the [BODYCLOSE Function](#).

### Syntax

```
HTF.BODYOPEN (
 cbackground IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–12 BODYOPEN Function Parameters**

Parameter	Description
cbackground	The value for the BACKGROUND attribute which specifies a graphic file to use for the background of the document.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<BODY background="cbackground" cattributes>
```

so that

```
HTF.BODYOPEN('/img/background.gif')
RETURN VARCHAR2;
```

generates:

```
<BODY background="/img/background.gif">
```

## BOLD Function

This function generates the `<B>` and `</B>` tags which direct the browser to display the text in boldface.

### Syntax

```
HTF.BOLD (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–13 BOLD Function Parameters**

Parameter	Description
<code>ctext</code>	The text that goes between the tags.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<B cattributes>ctext
```

## BR Function

This function generates the `<BR>` tag which begins a new line of text. It performs the same operation as the [NL Function](#).

### Syntax

```
HTF.BR(
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–14 BR Function Parameters**

Parameter	Description
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<BR CLEAR="cclear" cattributes>
```

## CENTER Function

This function generates the `<CENTER>` and `</CENTER>` tags which center a section of text within a Web page.

### Syntax

```
HTF.CENTER (
 ctext IN VARCHAR2)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–15** *CENTER Parameters*

Parameter	Description
<code>ctext</code>	The text that goes between the tags.

### Examples

This function generates

```
<CENTER>ctext</CENTER>
```

## CENTERCLOSE Function

This function generates the `</CENTER>` tag which marks the end of a section of text to center. You mark the beginning of a section of text to center by means of the [CENTEROPEN Function](#).

### Syntax

```
HTF.CENTERCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</CENTER>
```

## CENTEROPEN Function

This function generates the <CENTER> tag which mark the beginning of a section of text to center. You mark the beginning of a of a section of text to center by means of the [CENTERCLOSE Function](#).

### Syntax

```
HTF.CENTEROPEN
 RETURN VARCHAR2;
```

### Examples

This function generates

```
<CENTER>
```



## CITE Function

This function generates the `<CITE>` and `</CITE>` tags which direct the browser to render the text as a citation.

### Syntax

```
HTF.CITE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–16** *CITE Function Parameters*

Parameter	Description
<code>ctext</code>	The text to render as citation.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<CITE cattributes>ctext</CITE>
```

## CODE Function

This function generates the `<CODE>` and `</CODE>` tags which direct the browser to render the text in monospace font or however "code" is defined stylistically.

### Syntax

```
HTF.CODE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–17** *CODE Function Parameters*

Parameter	Description
<code>ctext</code>	The text to render as code.
<code>cattributes</code>	The other attributes to be included as-is in the tag

### Examples

This function generates

```
<CODE cattributes>ctext</CODE>
```

## COMMENT Function

This function generates the comment tags.

### Syntax

```
HTF.COMMENT (
 ctext IN VARCHAR2)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–18** *COMMENT Function Parameters*

Parameter	Description
<code>ctext</code>	The comment.

### Examples

This function generates

```
<!-- ctext -->
```

## DFN Function

This function generates the `<DFN>` and `</DFN>` tags which direct the browser to mark the text in italics or however "definition" is described stylistically.

### Syntax

```
HTF.DFN (
 ctext IN VARCHAR2)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–19 DFN Function Parameters**

Parameter	Description
<code>ctext</code>	The text to render in italics.

### Examples

This function generates

```
<DFN>ctext</DFN>
```

## DIRLISTCLOSE Function

This function generates the `</DIR>` tag which ends a directory list section. You start a directory list section with the [DIRLISTOPEN Function](#).

### Syntax

```
HTF.DIRLISTCLOSE
 RETURN VARCHAR2;
```

### Usage Notes

A directory list presents a list of items that contains up to 20 characters. Items in this list are typically arranged in columns, 24 characters wide. Insert the `<LI>` tag directly or invoke the [LISTITEM Function](#) so that the `<LI>` tag appears directly after the `</DIR>` tag to define the items as a list.

### Examples

This function generates

```
</DIR>
```

## DIRLISTOPEN Function

This function generates the `<DIR>` which starts a directory list section. You end a directory list section with the [DIRLISTCLOSE Function](#).

### Syntax

```
HTF.DIRLISTOPEN
 RETURN VARCHAR2;
```

### Usage Notes

A directory list presents a list of items that contains up to 20 characters. Items in this list are typically arranged in columns, 24 characters wide. Insert the `<LI>` tag directly or invoke the [LISTITEM Function](#) so that the `<LI>` tag appears directly after the `</DIR>` tag to define the items as a list.

### Examples

This function generates

```
<DIR>
```

## DIV Function

This function generates the <DIV> tag which creates document divisions.

### Syntax

```
HTF.DIV (
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–20** *DIV Function Parameters*

Parameter	Description
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<DIV ALIGN="calign" cattributes>
```

## DLISTCLOSE Function

This function generates the `</DL>` tag which ends a definition list. You start a definition list by means of the [DLISTOPEN Function](#).

### Syntax

```
HTF.DLISTCLOSE
RETURN VARCHAR2;
```

### Usage Notes

A definition list looks like a glossary: it contains terms and definitions. Terms are inserted using the [DLISTTERM Function](#) and definitions are inserted using the [DLISTDEF Function](#).

### Examples

This function generates

```
</DL>
```



## DLISTOPEN Function

This function generates the <DL> tag which starts a definition list. You end a definition list by means of the [DLISTCLOSE Function](#).

### Syntax

```
HTF.DLISTOPEN (
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–21** *DLISTOPEN Function Parameters*

Parameter	Description
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Usage Notes

A definition list looks like a glossary: it contains terms and definitions. Terms are inserted using the [DLISTTERM Function](#) and definitions are inserted using the [DLISTDEF Function](#).

### Examples

This function generates

```
<DL CLEAR="cclear" cattributes>
```

## DLISTDEF Function

This function generates the <DD> tag, which inserts definitions of terms. Use this tag for a definition list <DL>. Terms are tagged <DT> and definitions are tagged <DD>.

### Syntax

```
HTF.DLISTDEF (
 ctext IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–22** *DLISTDEF Function Parameters*

Parameter	Description
<code>ctext</code>	The definition of the term.
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<DD CLEAR="cclear" cattributes>ctext
```

## DLISTTERM Function

This function generates the <DT> tag which defines a term in a definition list <DL>.

### Syntax

```
HTF.DLISTTERM (
 ctext IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–23** *DLISTTERM Function Parameters*

Parameter	Description
<code>ctext</code>	The term.
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<DT CLEAR="cclear" cattributes>ctext
```

## EM Function

This function generates the `<EM>` and `</EM>` tags, which define text to be emphasized. It performs the same task as the [EMPHASIS Function](#).

### Syntax

```
HTF.EM(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–24** *EM Function Parameters*

Parameter	Description
<code>ctext</code>	The text to emphasize.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<EM cattributes>ctext
```

## EMPHASIS Function

This function generates the `<EM>` and `</EM>` tags, which define text to be emphasized. It performs the same task as the [EM Function](#).

### Syntax

```
HTF.EMPHASIS(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–25 EMPHASIS Function Parameters**

Parameter	Description
<code>ctext</code>	The text to emphasize.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<EM cattributes>ctext
```

## ESCAPE\_SC Function

This function replaces characters that have special meaning in HTML with their escape sequences. The following characters are converted:

- & to &amp;#x26;
- " to &quot;
- < to &lt;
- > to &gt;

This function performs the same operation as HTP. [PRINTS Procedure](#) and HTP. [PS Procedure](#).

### Syntax

```
HTF.ESCAPE_SC(
 ctext IN VARCHAR2);
```

### Parameters

**Table 123–26** *ESCAPE\_SC Procedure Parameters*

Parameter	Description
ctext	The text string to convert.

## ESCAPE\_URL Function

This function replaces characters that have special meaning in HTML and HTTP with their escape sequences. The following characters are converted:

- & to &amp;
- " to &quot;
- < to &lt;
- > to &gt;
- % to &25

### Syntax

```
HTF.ESCAPE_URL(
 p_url IN VARCHAR2);
```

### Parameters

**Table 123–27** *ESCAPE\_URL Procedure Parameters*

Parameter	Description
p_url	The string to convert.

## FONTCLOSE Function

This function generates the `</FONT>` tag which marks the end of a section of text with the specified font characteristics. You mark the beginning of the section text by means of the [FONTOPEN Function](#).

### Syntax

```
HTF.FONTCLOSE
 RETURN VARCHAR2;
```

### Examples

This function generates

```

```



## FONTOPEN Function

This function generates the <FONT> which marks the beginning of section of text with the specified font characteristics. You mark the end of the section text by means of the [FONTCLOSE Function](#).

### Syntax

```
HTF.FONTOPEN(
 ccolor IN VARCHAR2 DEFAULT NULL,
 cface IN VARCHAR2 DEFAULT NULL,
 csize IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–28** *FONTOPEN Function Parameters*

Parameter	Description
<code>ccolor</code>	The value for the <code>COLOR</code> attribute.
<code>cface</code>	The value for the <code>FACE</code> attribute
<code>csize</code>	The value for the <code>SIZE</code> attribute
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```

```

## FORMAT\_CELL Function

This function formats column values inside an HTML table using the [TABLEDATA Function](#). It allows for better control over the HTML tables.

### Syntax

```
HTF.FORMAT_CELL(
 columnValue IN VARCHAR2
 format_numbers IN VARCHAR2 DEFAULT NULL
RETURN VARCHAR2;
```

### Parameters

**Table 123–29** *FORMAT\_CELL Function Parameters*

Parameter	Description
columnValue	The value that needs to be formatted in an HTML table.
format_numbers	The format that numeric data is displayed in. If the value of this parameter is not NULL, the number fields are right-justified and rounded to two decimal places.

### Examples

This function generates

```
<TD >columnValue</TD>
```

## FORMCHECKBOX Function

This function generates the `<INPUT>` tag with `TYPE="checkbox"` which inserts a checkbox element in a form. A checkbox element is a button that the user toggles on or off.

### Syntax

```
HTF.FORMCHECKBOX(
 cname IN VARCHAR2,
 cvalue IN VARCHAR2 DEFAULT 'ON' ,
 cchecked IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–30** *FORMCHECKBOX Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cchecked</code>	If the value for this parameter is not <code>NULL</code> , the <code>CHECKED</code> attribute is added to the tag.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="checkbox" NAME="cname" VALUE="cvalue" CHECKED cattributes>
```

## FORMCLOSE Function

This function generates the `</FORM>` tag which marks the end of a form section in an HTML document. You mark the beginning of the form section by means of the [FORMOPEN Function](#).

### Syntax

```
HTF.FORMCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</FORM>
```

## FORMFILE Function

This function generates the `<INPUT>` tag with `TYPE="file"` which inserts a file form element. This is used for file uploading for a given page.

### Syntax

```
HTF.FORMFILE(
 cname IN VARCHAR2,
 caccept IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–31 FORMFILE Function Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>caccept</code>	A comma-delimited list of MIME types for upload.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="file" NAME="cname" ACCEPT="caccept" cattributes>
```

## FORMHIDDEN Function

This function generates the `<INPUT>` tag with `TYPE="hidden"`, which inserts a hidden form element. This element is not seen by the user. It submits additional values to the script.

### Syntax

```
HTF.FORMHIDDEN(
 cname IN VARCHAR2,
 cvalue IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–32** *FORMHIDDEN Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="hidden" NAME="cname" VALUE="cvalue" cattributes>
```

## FORMIMAGE Function

This function generates the <INPUT> tag with `TYPE="image"` which creates an image field that the user clicks to submit the form immediately. The coordinates of the selected point are measured in pixels, and returned (along with other contents of the form) in two name/value pairs. The x coordinate is submitted under the name of the field with `.x` appended, and the y coordinate with `.y` appended. Any `VALUE` attribute is ignored.

### Syntax

```
HTF.FORMIMAGE(
 cname IN VARCHAR2,
 csrc IN VARCHAR2,
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–33** *FORMIMAGE Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>csrc</code>	The value for the <code>SRC</code> attribute that specifies the image file.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="image" NAME="cname" SRC="csrc" ALIGN="calign" cattributes>
```

## FORMOPEN Function

This function generates the `<FORM>` tag which marks the beginning of a form section in an HTML document. You mark the end of the form section by means of the [FORMCLOSE Function](#).

### Syntax

```
HTF.FORMOPEN(
 curl IN VARCHAR2,
 cmethod IN VARCHAR2 DEFAULT 'POST',
 ctarger IN VARCHAR2 DEFAULT NULL,
 cenctype IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–34 FORMOPEN Function Parameters**

Parameter	Description
<code>curl</code>	The URL of the Web Request Broker or CGI script where the contents of the form is sent. This parameter is required.
<code>cmethod</code>	The value for the <code>METHOD</code> attribute. The value can be "GET" or "POST".
<code>ctarger</code>	The value for the <code>TARGET</code> attribute.
<code>cenctype</code>	The value for the <code>ENCTYPE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<FORM ACTION="curl" METHOD="cmethod" TARGET="ctarger" ENCTYPE="cenctype"
cattributes>
```



## FORMPASSWORD Function

This function generates the <INPUT> tag with TYPE="password" which creates a single-line text entry field. When the user enters text in the field, each character is represented by one asterisk. This is used for entering passwords.

### Syntax

```
HTF.FORMPASSWORD(
 cname IN VARCHAR2,
 csize IN VARCHAR2,
 cmaxlength IN VARCHAR2 DEFAULT NULL,
 cvalue IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–35** *FORMPASSWORD Function Parameters*

Parameter	Description
cname	The value for the NAME attribute.
csize	The value for the SIZE attribute.
cmmaxlength	The value for the MAXLENGTH attribute.
cvalue	The value for the VALUE attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="password" NAME="cname" SIZE="csize" MAXLENGTH="cmmaxlength"
VALUE="cvalue" cattributes>
```

## FORMRADIO Function

This function generates the `<INPUT>` tag with `TYPE="radio"`, which creates a radio button on the HTML form. Within a set of radio buttons, the user selects only one. Each radio button in the same set has the same name, but different values. The selected radio button generates a name/value pair.

### Syntax

```
HTF.FORMRADIO(
 cname IN VARCHAR2,
 cvalue IN VARCHAR2,
 cchecked IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–36 FORMRADIO Function Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cchecked</code>	If the value for this parameter is not <code>NULL</code> , the <code>CHECKED</code> attribute is added to the tag.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="radio" NAME="cname" VALUE="cvalue" CHECKED cattributes>
```

## FORMRESET Function

This function generates the `<INPUT>` tag with `TYPE="reset"` which creates a button that, when selected, resets the form fields to their initial values.

### Syntax

```
HTF.FORMRESET(
 cvalue IN VARCHAR2 DEFAULT 'Reset',
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–37** *FORMRESET Function Parameters*

Parameter	Description
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="reset" VALUE="cvalue" cattributes>
```

## FORMSELECTCLOSE Function

This function generates the `</SELECT>` tag which marks the end of a Select form element. A Select form element is a listbox where the user selects one or more values. You mark the beginning of Select form element by means of the [FORMSELECTOPEN Function](#). The values are inserted using [FORMSELECTOPTION Function](#).

### Syntax

```
HTF.FORMSELECTCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</SELECT>
```

as shown under [Examples](#) of the [FORMSELECTOPEN Function](#).

## FORMSELECTOPEN Function

This function generates the `<SELECT>` tags which creates a Select form element. A Select form element is a listbox where the user selects one or more values. You mark the end of Select form element by means of the [FORMSELECTCLOSE Function](#). The values are inserted using [FORMSELETOPTION Function](#).

### Syntax

```
HTF.FORMSELECTOPEN(
 cname IN VARCHAR2,
 cprompt IN VARCHAR2 DEFAULT NULL,
 nsize IN INTEGER DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–38 FORMSELECTOPEN Function Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cprompt</code>	The string preceding the list box.
<code>nsize</code>	The value for the <code>SIZE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
cprompt <SELECT NAME="cname" SIZE="nsize" cattributes>
</SELECT>
```

so that

```
HTF.FORMSELECTOPEN('greatest_player';
 'Pick the greatest player:');
HTF.FORMSELETOPTION('Messier');
HTF.FORMSELETOPTION('Howe');
HTF.FORMSELETOPTION('Gretzky');
HTF.FORMSELECTCLOSE;
```

### **generates**

```
Pick the greatest player:
<SELECT NAME="greatest_player">
<OPTION>Messier
<OPTION>Howe
<OPTION>Gretzky
</SELECT>
```

## FORMSELETOPTION Function

This function generates the <OPTION> tag which represents one choice in a Select element.

### Syntax

```
HTF.FORMSELETOPTION(
 cvalue IN VARCHAR2,
 cselected IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–39** *FORMSELETOPTION Function Parameters*

Parameter	Description
cvalue	The text for the option.
cvalue	If the value for this parameter is not NULL, the SELECTED attribute is added to the tag.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<OPTION SELECTED cattributes>cvalue
```

as shown under [Examples](#) of the [FORMSELECTOPEN Function](#).

## FORMSUBMIT Function

This function generates the `<INPUT>` tag with `TYPE="submit"` which creates a button that, when clicked, submits the form. If the button has a `NAME` attribute, the button contributes a name/value pair to the submitted data.

### Syntax

```
HTF.FORMSUBMIT(
 cname IN VARCHAR2 DEFAULT NULL,
 cvalue IN VARCHAR2 DEFAULT 'Submit',
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–40 FORMSUBMIT Function Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="submit" NAME="cname" VALUE="cvalue" cattributes>
```



## FORMTEXT Function

This function generates the `<INPUT>` tag with `TYPE="text"`, which creates a field for a single line of text.

### Syntax

```
HTF.FORMTEXT(
 cname IN VARCHAR2,
 csize IN VARCHAR2 DEFAULT NULL,
 cmaxlength IN VARCHAR2 DEFAULT NULL,
 cvalue IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–41** *FORMTEXT Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>csize</code>	The value for the <code>SIZE</code> attribute.
<code>cmaxlength</code>	The value for the <code>MAXLENGTH</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<INPUT TYPE="text" NAME="cname" SIZE="csize" MAXLENGTH="cmmaxlength"
VALUE="cvalue" cattributes>
```

## FORMTEXTAREA Function

This function generates the `<TEXTAREA>` tag, which creates a text field that has no predefined text in the text area. This field enables entering several lines of text. The same operation is performed by the [FORMTEXTAREA2 Function](#) which in addition has the `cwrap` parameter that lets you specify a wrap style.

### Syntax

```
HTF.FORMTEXTAREA(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–42** *FORMTEXTAREA Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>nrows</code>	The value for the <code>ROWS</code> attribute. This is an integer.
<code>ncolumns</code>	The value for the <code>COLS</code> attribute. This is an integer.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign"
cattributes></TEXTAREA>
```

## FORMTEXTAREA2 Function

This function generates the `<TEXTAREA>` tag, which creates a text field that has no predefined text in the text area. This field enables entering several lines of text. The same operation is performed by the [FORMTEXTAREA Function](#) except that in that case you cannot specify a wrap style.

### Syntax

```
HTF.FORMTEXTAREA2(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–43** *FORMTEXTAREA2 Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>nrows</code>	The value for the <code>ROWS</code> attribute. This is an integer.
<code>ncolumns</code>	The value for the <code>COLS</code> attribute. This is an integer.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cwrap</code>	The value for the <code>WRAP</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign" WRAP="cwrap"
cattributes></TEXTAREA>
```

## FORMTEXTAREACLOSE Function

This function generates the `</TEXTAREA>` tag which ends a text area form element. You open a text area element by means of either [FORMTEXTAREAOPEN Function](#) or [FORMTEXTAREAOPEN2 Function](#).

### Syntax

```
HTF.FORMTEXTAREACLOSE
 RETURN VARCHAR2;
```

### Examples

This function generates

```
</TEXTAREA>
```

## FORMTEXTAREAOPEN Function

This function generates the <TEXTAREA> which marks the beginning of a text area form element. The same operation is performed by the [FORMTEXTAREAOPEN2 Function](#) which in addition has the `cwrap` parameter that lets you specify a wrap style. You mark the end of a text area form element by means of the [FORMTEXTAREACLOSE Function](#).

### Syntax

```
HTF.FORMTEXTAREAOPEN(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–44** *FORMTEXTAREAOPEN Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>nrows</code>	The value for the <code>ROWS</code> attribute. This is an integer.
<code>ncolumns</code>	The value for the <code>COLS</code> attribute. This is an integer.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign" cattributes>
```

## FORMTEXTAREAOPEN2 Function

This function generates the `<TEXTAREA>` which marks the beginning of a text area form element. The same operation is performed by the [FORMTEXTAREAOPEN Function](#) except that in that case you cannot specify a wrap style. You mark the end of a text area form element by means of the [FORMTEXTAREACLOSE Function](#).

### Syntax

```
HTF.FORMTEXTAREAOPEN2(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–45** *FORMTEXTAREAOPEN2 Function Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>nrows</code>	The value for the <code>ROWS</code> attribute. This is an integer.
<code>ncolumns</code>	The value for the <code>COLS</code> attribute. This is an integer.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cwrap</code>	The value for the <code>WRAP</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign" WRAP =
"cwrap" cattributes>
```

## FRAME Function

This function generates the <FRAME> tag which defines the characteristics of a frame created by a <FRAMESET> tag.

### Syntax

```
HTF.FRAME(
 csrc IN VARCHAR2,
 cname IN VARCHAR2 DEFAULT NULL,
 cmarginwidth IN VARCHAR2 DEFAULT NULL,
 cmarginheight IN VARCHAR2 DEFAULT NULL,
 cscrolling IN VARCHAR2 DEFAULT NULL,
 cnoresize IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–46** *FRAME Function Parameters*

Parameter	Description
csrc	The URL to display in the frame.
cname	The value for the NAME attribute.
cmarginwidth	The value for the MARGINWIDTH attribute.
cscrolling	The value for the SCROLLING attribute.
cnoresize	If the value for this parameter is not NULL, the NORESIZE attribute is added to the tag.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<FRAME SRC="csrc" NAME="cname" MARGINWIDTH="cmarginwidth"
MARGINHEIGHT="cmarginheight" SCROLLING="cscrolling" NORESIZE cattributes>
```

## FRAMESETCLOSE Function

This function generates the `</FRAMESET>` tag which ends a frameset section. You mark the beginning of a frameset section by means of the [FRAMESETOPEN Function](#).

### Syntax

```
HTF.FRAMESETCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</FRAMESET>
```



## FRAMESETOPEN Function

This function generates the <FRAMESET> tag which define a frameset section. You mark the end of a frameset section by means of the [FRAMESETCLOSE Function](#).

### Syntax

```
HTF.FRAMESETOPEN(
 crows IN VARCHAR2 DEFAULT NULL,
 ccols IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–47** *FRAMESETOPEN Function Parameters*

Parameter	Description
<code>crows</code>	The value for the <code>ROWS</code> attribute.
<code>ccols</code>	The value for the <code>COLS</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<FRAMESET ROWS="crows" COLS="ccols" cattributes>
```

## HEADCLOSE Function

This function generates the `</HEAD>` tag which marks the end of an HTML document head section. You mark the beginning of an HTML document head section by means of the [HEADOPEN Function](#).

### Syntax

```
HTF.HEADCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</HEAD>
```

## HEADOPEN Function

This function generates the <HEAD> tag which marks the beginning of the HTML document head section. You mark the end of an HTML document head section by means of the [HEADCLOSE Function](#).

### Syntax

```
HTF.HEADOPEN
RETURN VARCHAR2;
```

### Examples

This function generates

```
<HEAD>
```

## HEADER Function

This function generates opening heading tags (<H1> to <H6>) and their corresponding closing tags (</H1> to </H6>).

### Syntax

```
HTF.HEADER(
 nsize IN INTEGER,
 cheader IN VARCHAR2,
 calign IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–48** *HEADER Function Parameters*

Parameter	Description
nsize	The the heading level. This is an integer between 1 and 6.
cheader	The text to display in the heading.
calign	The value for the ALIGN attribute.
cnowrap	The value for the NOWRAP attribute.
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

```
HTF.header (1, 'Overview')
RETURN VARCHAR2;
```

produces:

```
<H1>Overview</H1>
```

## HR Function

This function generates the <HR> tag, which generates a line in the HTML document. This subprogram performs the same operation as the [LINE Function](#).

### Syntax

```
HTF.HR(
 cclear IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–49 HR Function Parameters**

Parameter	Description
<code>cclear</code>	The value for the CLEAR attribute.
<code>csrc</code>	The value for the SRC attribute which specifies a custom image as the source of the line.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<HR CLEAR="cclear" SRC="csrc" cattributes>
```

## HTMLCLOSE Function

This function generates the `</HTML>` tag which marks the end of an HTML document. You use the [HTMLOPEN Function](#) to mark the beginning of an HTML document.

### Syntax

```
HTF.HTMLCLOSE
 RETURN VARCHAR2;
```

### Examples

This function generates

```
</HTML>
```

## HTMLOPEN Function

This function generates the <HTML> tag which marks the beginning of an HTML document. You use the [HTMLCLOSE Function](#) to mark the end of the an HTML document.

### Syntax

```
HTF.HTMLOPEN
 RETURN VARCHAR2;
```

### Examples

This function generates

```
<HTML>
```

## IMG Function

This function generates the <IMG> tag which directs the browser to load an image onto the HTML page. The [IMG2 Function](#) performs the same operation but additionally uses the `cusemap` parameter.

### Syntax

```
HTF.IMG(
 curl IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 calt IN VARCHAR2 DEFAULT NULL,
 cismap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–50** *IMG Function Parameters*

Parameter	Description
<code>curl</code>	The value for the SRC attribute.
<code>calign</code>	The value for the ALIGN attribute.
<code>calt</code>	The value for the ALT attribute which specifies alternative text to display if the browser does not support images.
<code>cismap</code>	If the value for this parameter is not NULL, the ISMAP attribute is added to the tag. The attribute indicates that the image is an imagemap.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```

```



## IMG2 Function

This function generates the <IMG> tag, which directs the browser to load an image onto the HTML page. The [IMG Function](#) performs the same operation but does not use the `cusemap` parameter.

### Syntax

```
HTF.IMG2(
 curl IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 calt IN VARCHAR2 DEFAULT NULL,
 cismap IN VARCHAR2 DEFAULT NULL,
 cusemap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–51** *IMG2 Function Parameters*

Parameter	Description
<code>curl</code>	The value for the SRC attribute.
<code>calign</code>	The value for the ALIGN attribute.
<code>calt</code>	The value for the ALT attribute which specifies alternative text to display if the browser does not support images.
<code>cismap</code>	If the value for this parameter is not NULL, the ISMAP attribute is added to the tag. The attribute indicates that the image is an imagemap.
<code>cusemap</code>	The value for the USEMAP attribute which specifies a client-side image map.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```

```

## ISINDEX Function

This function creates a single entry field with a prompting text, such as "*enter value*," then sends that value to the URL of the page or program.

### Syntax

```
HTF.ISINDEX(
 cprompt IN VARCHAR2 DEFAULT NULL,
 curl IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–52** *ISINDEX Function Parameters*

Parameter	Description
<code>cprompt</code>	The value for the <code>PROMPT</code> attribute.
<code>curl</code>	The value for the <code>HREF</code> attribute.

### Examples

This function generates

```
<ISINDEX PROMPT="cprompt" HREF="curl">
```

## ITALIC Function

This function generates the `<I>` and `</I>` tags which direct the browser to render the text in italics.

### Syntax

```
HTF.ITALIC(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–53** *ITALIC Function Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in italics.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<I cattributes>ctext</I>
```

## KBD Function

This function generates the `<KBD>` and `</KBD>` tags which direct the browser to render the text in monospace font. This subprogram performs the same operation as the [KEYBOARD Function](#).

### Syntax

```
HTF.KBD(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–54 KBD Function Parameters**

Parameter	Description
<code>ctext</code>	The text to be rendered in monospace.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<KBD cattributes>ctext</KBD>
```

## KEYBOARD Function

This function generates the `<KBD>` and `</KBD>` tags, which direct the browser to render the text in monospace font. This subprogram performs the same operation as the [KBD Function](#).

### Syntax

```
HTF.KEYBOARD(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–55** *KEYBOARD Function Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in monospace.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<KBD cattributes>ctext</KBD>
```

## LINE Function

This function generates the <HR> tag, which generates a line in the HTML document. This subprogram performs the same operation as the [HR Function](#).

### Syntax

```
HTF.LINE(
 cclear IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–56** *LINE Function Parameters*

Parameter	Description
<code>cclear</code>	The value for the CLEAR attribute.
<code>csrc</code>	The value for the SRC attribute which specifies a custom image as the source of the line.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<HR CLEAR="cclear" SRC="csrc" cattributes>
```

## LINKREL Function

This function generates the `<LINK>` tag with the `REL` attribute which delineates the relationship described by the hypertext link from the anchor to the target. This is only used when the `HREF` attribute is present. This is the opposite of [LINKREV Function](#). This tag indicates a relationship between documents but does not create a link. To create a link, use the [ANCHOR Function](#).

### Syntax

```
HTF.LINKREL(
 crel IN VARCHAR2,
 curl IN VARCHAR2,
 ctitle IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–57 LINKREL Function Parameters**

Parameter	Description
<code>crel</code>	The value for the <code>REL</code> attribute.
<code>curl</code>	The value for the <code>URL</code> attribute.
<code>ctitle</code>	The value for the <code>TITLE</code> attribute.

### Examples

This function generates

```
<LINK REL="crel" HREF="curl" TITLE="ctitle">
```

## LINKREV Function

This function generates the <LINK> tag with the REV attribute which delineates the relationship described by the hypertext link from the target to the anchor. This is the opposite of the [LINKREL Function](#). This tag indicates a relationship between documents, but does not create a link. To create a link, use the [ANCHOR Function](#).

### Syntax

```
HTF.LINKREV(
 crev IN VARCHAR2,
 curl IN VARCHAR2,
 ctitle IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–58 LINKREV Function Parameters**

Parameter	Description
crel	The value for the REV attribute.
curl	The value for the URL attribute.
ctitle	The value for the TITLE attribute.

### Examples

This function generates

```
<LINK REV="crev" HREF="curl" TITLE="ctitle">
```



## LISTHEADER Function

This function generates the <LH> and </LH> tags which print an HTML tag at the beginning of the list.

### Syntax

```
HTF.LISTHEADER(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–59** LISTHEADER Function Parameters

Parameter	Description
ctext	The text to place between <LH> and </LH>.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<LH cattributes>ctext</LH>
```

## LISTINGCLOSE Function

This function generates the `</LISTING>` tags which marks the end of a section of fixed-width text in the body of an HTML page. To mark the beginning of a section of fixed-width text in the body of an HTML page, use the [LISTINGOPEN Function](#).

### Syntax

```
HTF.LISTINGCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</LISTING>
```

## LISTINGOPEN Function

This function generates the `<LISTING>` tag which marks the beginning of a section of fixed-width text in the body of an HTML page. To mark the end of a section of fixed-width text in the body of an HTML page, use the [LISTINGCLOSE Function](#).

### Syntax

```
HTF.LISTINGOPEN
RETURN VARCHAR2;
```

### Examples

This function generates

```
<LISTING>
```

## LISTITEM Function

This function generates the `<LI>` tag, which indicates a list item.

### Syntax

```
HTF.LISTITEM(
 ctext IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cdingbat IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–60** LISTITEM Function Parameters

Parameter	Description
<code>ctext</code>	The text for the list item.
<code>cclear</code>	The value for the CLEAR attribute.
<code>cdingbat</code>	The value for the DINGBAT attribute.
<code>csrc</code>	The value for the SRC attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<LI CLEAR="cclear" DINGBAT="cdingbat" SRC="csrc" cattributes>ctext
```

## MAILTO Function

This function generates the <A> tag with the HREF set to 'mailto' prepended to the mail address argument.

### Syntax

```
HTF.MAILTO(
 caddress IN VARCHAR2,
 ctext IN VARCHAR2,
 cname IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–61 MAILTO Function Parameters**

Parameter	Description
caddress	The email address of the recipient.
ctext	The clickable portion of the link.
cname	The value for the NAME attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
ctext
```

so that

```
HTF.mailto('pres@white_house.gov','Send Email to the President');
```

generates:

```
Send Email to the President
```

## MAPCLOSE Function

This function generates the `</MAP>` tag which marks the end of a set of regions in a client-side image map. To mark the beginning of a set of regions in a client-side image map, use the [MAOPEN Function](#).

### Syntax

```
HTF.MAPCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</MAP>
```

## MAPOPEN Function

This function generates the <MAP> tag which mark the beginning of a set of regions in a client-side image map. To mark the end of a set of regions in a client-side image map, use the [MAPCLOSE Function](#).

### Syntax

```
HTF.MAPOPEN(
 cname IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–62** MAPOPEN Function Parameters

Parameter	Description
<code>cname</code>	The value for the NAME attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<MAP NAME="cname" cattributes>
```

## MENULISTCLOSE Function

This function generates the `</MENU>` tag which ends a list that presents one line for each item. To begin a list of this kind, use the [MENULISTOPEN Function](#). The items in the list appear more compact than an unordered list. The [LISTITEM Function](#) defines the list items in a menu list.

### Syntax

```
HTF.MENULISTCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</MENU>
```



## MENULISTOPEN Function

This function generates the <MENU> tag which create a list that presents one line for each item. To end a list of this kind, use the [MENULISTCLOSE Function](#). The items in the list appear more compact than an unordered list. The [LISTITEM Function](#) defines the list items in a menu list.

### Syntax

```
HTF.MENULISTOPEN
 RETURN VARCHAR2;
```

### Examples

This function generates

```
<MENU>
```

## META Function

This function generates the <META> tag, which embeds meta-information about the document and also specifies values for HTTP headers. For example, you can specify the expiration date, keywords, and author name.

### Syntax

```
HTF.META(
 chttp_equiv IN VARCHAR2,
 cname IN VARCHAR2,
 ccontent IN VARCHAR2)
RETURN VARCHAR2;
```

### Parameters

**Table 123–63 META Function Parameters**

Parameter	Description
chttp_equiv	The value for the CHTTP_EQUIV attribute.
cname	The value for the NAME attribute.
ccontent	The value for the CONTENT attribute.

### Examples

This function generates

```
<META HTTP-EQUIV="chttp_equiv" NAME ="cname" CONTENT="ccontent">
```

so that

```
HTF.meta ('Refresh', NULL, 120);
```

generates

```
<META HTTP-EQUIV="Refresh" CONTENT=120>
```

On some Web browsers, this causes the current URL to be reloaded automatically every 120 seconds.

## NL Function

This function generates the `<BR>` tag which begins a new line of text. It performs the same operation as the [BR Function](#).

### Syntax

```
HTF.NL(
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–64 NL Function Parameters**

Parameter	Description
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<BR CLEAR="cclear" cattributes>
```

## NOBR Function

This function generates the `<NOBR>` and `</NOBR>` tags which turn off line-breaking in a section of text.

### Syntax

```
HTF.NOBR(
 ctext IN VARCHAR2)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–65 NOBR Function Parameters**

Parameter	Description
<code>ctext</code>	The text that is to be rendered on one line.

### Examples

This function generates

```
<NOBR>ctext</NOBR>
```

## NOFRAMESCLOSE Function

This function generates the `</NOFRAMES>` tag which marks the end of a no-frames section. To mark the beginning of a no-frames section, use the [FRAMESETOPEN Function](#). See also [FRAME Function](#), [FRAMESETOPEN Function](#) and [FRAMESETCLOSE Function](#).

### Syntax

```
HTF.NOFRAMESCLOSE
 RETURN VARCHAR2;
```

### Examples

This function generates

```
</NOFRAMES>
```

## NOFRAMESOPEN Function

This function generates the <NOFRAMES> tag which mark the beginning of a no-frames section. To mark the end of a no-frames section, use the [FRAMESETCLOSE Function](#). See also [FRAME Function](#), [FRAMESETOPEN Function](#) and [FRAMESETCLOSE Function](#).

### Syntax

```
HTF.NOFRAMESOPEN
 RETURN VARCHAR2;
```

### Examples

This function generates

```
<NOFRAMES>
```

## OLISTCLOSE Function

This function generates the `</OL>` tag which defines the end of an ordered list. An ordered list presents a list of numbered items. To mark the beginning of a list of this kind, use the [OLISTOPEN Function](#). Numbered items are added using [LISTITEM Function](#).

### Syntax

```
HTF.OLISTCLOSE
 RETURN VARCHAR2;
```

### Examples

This function generates

```

```

## OLISTOPEN Function

This function generates the <OL> tag which marks the beginning of an ordered list. An ordered list presents a list of numbered items. To mark the end of a list of this kind, use the [OLISTCLOSE Function](#). Numbered items are added using [LISTITEM Function](#).

### Syntax

```
HTF.OLISTOPEN(
 cclear IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–66** *OLISTOPEN Function Parameters*

Parameter	Description
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cwrap</code>	The value for the <code>WRAP</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<OL CLEAR="cclear" WRAP="cwrap" cattributes>
```



## PARA Function

This function generates the <P> tag which indicates that the text that comes after the tag is to be formatted as a paragraph. You can add attributes to the tag by means of the [PARAGRAPH Function](#).

### Syntax

```
HTF.PARA
RETURN VARCHAR2;
```

### Examples

This function generates

```
<P>
```

## PARAGRAPH Function

You can use this function to add attributes to the <P> tag created by the [PARA Function](#).

### Syntax

```
HTF.PARAGRAPH(
 calign IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–67** *PARAGRAPH Function Parameters*

Parameter	Description
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cnowrap</code>	If the value for this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<P ALIGN="calign" NOWRAP CLEAR="cclear" cattributes>
```

## PARAM Function

This function generates the <PARAM> tag which specifies parameter values for Java applets. The values can reference HTML variables. To invoke a Java applet from a Web page, use [APPLETOPEN Function](#) to begin the invocation. Use one [PARAM Function](#) for each desired name-value pair, and use [APPLETCLOSE Function](#) to end the applet invocation.

### Syntax

```
HTF.PARAM(
 cname IN VARCHAR2
 cvalue IN VARCHAR2)
RETURN VARCHAR2;
```

### Parameters

**Table 123–68** *PARAM Function Parameters*

Parameter	Description
cname	The value for the NAME attribute.
cvalue	The value for the VALUE attribute.

### Examples

This function generates

```
<PARAM NAME=cname VALUE="cvalue">
```

## PLAINTEXT Function

This function generates the `<PLAINTEXT>` and `</PLAINTEXT>` tags which direct the browser to render the text they surround in fixed-width type.

### Syntax

```
HTF.PLAINTEXT(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–69** *PLAINTEXT Function Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in fixed-width font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<PLAINTEXT cattributes>ctext</PLAINTEXT>
```

## PRECLOSE Function

This function generates the `</PRE>` tag which marks the end of a section of preformatted text in the body of the HTML page. To mark the beginning of a section of preformatted text in the body of the HTML page, use the [PREOPEN Function](#).

### Syntax

```
HTF.PRECLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```
</PRE>
```

## PREOPEN Function

This function generates the <PRE> tag which marks the beginning of a section of preformatted text in the body of the HTML page. To mark the end of a section of preformatted text in the body of the HTML page, use the [PRECLOSE Function](#).

### Syntax

```
HTF.PREOPEN(
 cclear IN VARCHAR2 DEFAULT NULL,
 cwidth IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–70** *PREOPEN Function Parameters*

Parameter	Description
<code>cclear</code>	The value for the CLEAR attribute.
<code>cwidth</code>	The value for the WIDTH attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<PRE CLEAR="cclear" WIDTH="cwidth" cattributes>
```

## PRINT Functions

These functions generate the specified parameter as a string terminated with the `\n` newline character. The [PRN Functions](#) performs the same operation but does not terminate with a newline character.

### Syntax

```
HTF.PRINT (
 cbuf IN VARCHAR2)
RETURN VARCHAR2;
```

```
HTF.PRINT (
 dbuf IN DATE)
RETURN VARCHAR2;
```

```
HTF.PRINT (
 nbuf IN NUMBER)
RETURN VARCHAR2;
```

### Parameters

**Table 123–71 PRINT Function Parameters**

Parameter	Description
cbuf	The string to generate terminated by a newline.
dbuf	The string to generate terminated by a newline.
nbuf	The string to generate terminated by a newline.

### Usage Notes

- The `\n` character is not the same as `<BR>`. The `\n` character formats the HTML source but it does not affect how the browser renders the HTML source. Use `<BR>` to control how the browser renders the HTML source.
- These functions do not have function equivalents.

## PRN Functions

These functions generate the specified parameter as a string. Unlike the [PRINT Functions](#) the string is not terminated with the `\n` newline character.

### Syntax

```
HTF.PRN (
 cbuf IN VARCHAR2)
 RETURN VARCHAR2;
```

```
HTF.PRN (
 dbuf IN DATE)
 RETURN VARCHAR2;
```

```
HTF.PRN (
 nbuf IN NUMBER)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–72 PRN Function Parameters**

Parameter	Description
cbuf	The string to generate (not terminated by a newline).
dbuf	The string to generate (not terminated by a newline).
nbuf	The string to generate (not terminated by a newline).

### Usage Notes

These functions do not have function equivalents.



## S Function

This function generates the `<S>` and `</S>` tags which direct the browser to render the text they surround in strikethrough type. This performs the same operation as [STRIKE Function](#).

### Syntax

```
HTF.S (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–73 S Function Parameters**

Parameter	Description
<code>ctext</code>	The text to be rendered in strikethrough type.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<S cattributes>ctext</S>
```

## SAMPLE Function

This function generates the `<SAMP>` and `</SAMP>` tags which direct the browser to render the text they surround in monospace font or however "sample" is defined stylistically.

### Syntax

```
HTF.SAMPLE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–74** *SAMPLE Function Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in monospace font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<SAMP cattributes>ctext</SAMP>
```

## SCRIPT Function

This function generates the `<SCRIPT>` and `</SCRIPT>` tags which contain a script written in languages such as JavaScript and VBScript.

### Syntax

```
HTF.SCRIPT (
 cscript IN VARCHAR2,
 clanguage IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–75** *SCRIPT Function Parameters*

Parameter	Description
<code>cscript</code>	The text of the script. This is the text that makes up the script itself, not the name of a file containing the script.
<code>clanguage</code>	The language in which the script is written. If this parameter is omitted, the user's browser determines the scripting language.

### Examples

This function generates

```
<SCRIPT LANGUAGE=clanguage>cscript</SCRIPT>
```

so that

```
HTF.script ('Erupting_Volcano', 'Javascript');
```

generates

```
<SCRIPT LANGUAGE=Javascript>"script text here"</SCRIPT>
```

This causes the browser to run the script enclosed in the tags.

## SMALL Function

This function generates the `<SMALL>` and `</SMALL>` tags, which direct the browser to render the text they surround using a small font.

### Syntax

```
HTF.SMALL (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–76** *SMALL Function Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in small font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<SMALL cattributes>ctext</SMALL>
```

## STRIKE Function

This function generates the `<STRIKE>` and `</STRIKE>` tags which direct the browser to render the text they surround in strikethrough type. This performs the same operation as [S Function](#).

### Syntax

```
STRIKE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–77** *STRIKE Function Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in strikethrough type.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<STRIKE cattributes>ctext</STRIKE>
```

## STRONG Function

This function generates the `<STRONG>` and `</STRONG>` tags which direct the browser to render the text they surround in bold or however "strong" is defined.

### Syntax

```
HTF.STRONG(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–78** *STRONG Function Parameters*

Parameter	Description
<code>ctext</code>	The text to be emphasized.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<STRONG cattributes>ctext
```

## STYLE Function

This function generates the `<STYLE>` and `</STYLE>` tags which include a style sheet in a Web page. You can get more information about style sheets at <http://www.w3.org>. This feature is not compatible with browsers that support only HTML versions 2.0 or earlier. Such browsers will ignore this tag.

### Syntax

```
HTF.STYLE(
 cstyle IN VARCHAR2)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–79** *STYLE Function Parameters*

Parameter	Description
<code>cstyle</code>	The the style information to include.

### Examples

This function generates

```
<STYLE>cstyle</STYLE>
```

## SUB Function

This function generates the `<SUB>` and `</SUB>` tags which direct the browser to render the text they surround as subscript.

### Syntax

```
HTF.SUB(
 ctext IN VARCHAR2,
 calign in VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–80 SUB Function Parameters**

Parameter	Description
<code>ctext</code>	The text to render in subscript.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
_{ctext}
```



## SUP Function

This function generates the `<SUP>` and `</SUP>` tags which direct the browser to render the text they surround as superscript.

### Syntax

```
HTF.SUP(
 ctext IN VARCHAR2,
 calign in VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–81** *SUP Function Parameters*

Parameter	Description
<code>ctext</code>	The text to render in superscript.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
^{ctext}
```

## TABLECAPTION Function

This function generates the `<CAPTION>` and `</CAPTION>` tags which place a caption in an HTML table.

### Syntax

```
HTF.TABLECAPTION(
 ccaption IN VARCHAR2,
 calign in VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–82** TABLECAPTION Function Parameters

Parameter	Description
<code>c</code> text	The text for the caption.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<CAPTION ALIGN="calign" cattributes>ccaption</CAPTION>
```

## TABLEDATA Function

This function generates the `<TD>` and `</TD>` tags which insert data into a cell of an HTML table.

### Syntax

```
HTF.TABLEDATA(
 cvalue IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 cdp IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 crowspan IN VARCHAR2 DEFAULT NULL,
 ccolspan IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–83** TABLEDATA Function Parameters

Parameter	Description
<code>cvalue</code>	The data for the cell in the table.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cdp</code>	The value for the <code>DP</code> attribute.
<code>cnowrap</code>	If the value of this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>ccolspan</code>	The value for the <code>COLSPAN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TD ALIGN="calign" DP="cdp" ROWSPAN="crowspan" COLSPAN="ccolspan" NOWRAP
cattributes>cvalue</TD>
```

## TABLEHEADER Function

This function generates the `<TH>` and `</TH>` tags which insert a header cell in an HTML table. The `<TH>` tag is similar to the `<TD>` tag except that the text in this case the rows are usually rendered in bold type.

### Syntax

```
HTF.TABLEHEADER(
 cvalue IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 cdp IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 crowspan IN VARCHAR2 DEFAULT NULL,
 ccolspan IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–84 TABLEHEADER Function Parameters**

Parameter	Description
<code>cvalue</code>	The data for the cell in the table.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cdp</code>	The value for the <code>DP</code> attribute.
<code>cnowrap</code>	If the value of this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>crispen</code>	The value for the <code>ROWSPAN</code> attribute.
<code>ccolspan</code>	The value for the <code>COLSPAN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TH ALIGN="calign" DP="cdp" ROWSPAN="crowspan" COLSPAN="ccolspan" NOWRAP
cattributes>cvalue</TH>
```

## TABLECLOSE Function

This function generates the `</TABLE>` tag which marks the end of an HTML table. To define the beginning of an HTML table, use the [TABLEOPEN Function](#).

### Syntax

```
HTF.TABLECLOSE
 RETURN VARCHAR2;
```

### Examples

This function generates

```
</TABLE>
```

## TABLEOPEN Function

This function generates the <TABLE> tag which marks the beginning of an HTML table. To define the end of an HTML table, use the [TABLECLOSE Function](#).

### Syntax

```
HTF.TABLEOPEN(
 cborder IN VARCHAR2 DEFAULT NULL
 calign IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–85** TABLEOPEN Function Parameters

Parameter	Description
border	The value for the BORDER attribute.
calign	The value for the ALIGN attribute.
cnowrap	If the value of this parameter is not NULL, the NOWRAP attribute is added to the tag.
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TABLE "cborder" NOWRAP ALIGN="calign" CLEAR="cclear" cattributes>
```

## TABLEROWCLOSE Function

This function generates the `</TR>` tag which marks the end of a new row in an HTML table. To mark the beginning of a new row, use the [TABLEROWOPEN Function](#).

### Syntax

```
HTF.TABLEROWCLOSE
 RETURN VARCHAR2;
```

### Examples

This function generates

```
</TABLE>
```

## TABLEROWOPEN Function

This function generates the `<TR>` tag which marks the beginning of a new row in an HTML table. To mark the end of a new row, use the [TABLEROWCLOSE Function](#).

### Syntax

```
HTF.TABLEROWOPEN(
 calign IN VARCHAR2 DEFAULT NULL,
 cvalign IN VARCHAR2 DEFAULT NULL,
 cdp IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–86** *TABLEROWOPEN Function Parameters*

Parameter	Description
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cvalign</code>	The value for the <code>VALIGN</code> attribute.
<code>cdp</code>	The value for the <code>DP</code> attribute.
<code>cnowrap</code>	If the value of this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<<TR ALIGN="calign" VALIGN="cvalign" DP="cdp" NOWRAP cattributes>
```



## TELETYPE Function

This function generates the `<TT>` and `</TT>` tags which direct the browser to render the text they surround in a fixed width typewriter font, for example, the courier font.

### Syntax

```
HTF.TELETYPE(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–87** TELETYPE Function Parameters

Parameter	Description
<code>ctext</code>	The text to render in a fixed width typewriter font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<TT cattributes>ctext</TT>
```

## TITLE Function

This function generates the `<TITLE>` and `</TITLE>` tags which specify the text to display in the titlebar of the browser window.

### Syntax

```
HTF.TITLE(
 ctitle IN VARCHAR2)
 RETURN VARCHAR2;
```

### Parameters

**Table 123–88** *TITLE Function Parameters*

Parameter	Description
<code>ctitle</code>	The text to display in the titlebar of the browser window.

### Examples

This function generates

```
<TITLE>ctitle</TITLE>
```

## ULISTCLOSE Function

This function generates the `</UL>` tag which marks the end of an unordered list. An unordered list presents items with bullets. To mark the beginning of an unordered list, use the [ULISTOPEN Function](#). Add list items with [LISTITEM Function](#).

### Syntax

```
HTF.ULISTCLOSE
RETURN VARCHAR2;
```

### Examples

This function generates

```

```

## ULISTOPEN Function

This function generates the <UL> tag which marks the beginning of an unordered list. An unordered list presents items with bullets. To mark the end of an unordered list, use the [ULISTCLOSE Function](#). Add list items with [LISTITEM Function](#).

### Syntax

```
HTF.ULISTOPEN(
 cclear IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cdingbat IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–89** *ULISTOPEN Function Parameters*

Parameter	Description
<code>cclear</code>	The value for the CLEAR attribute.
<code>cwrap</code>	The value for the WRAP attribute.
<code>cdingbat</code>	The value for the DINGBAT attribute.
<code>csrc</code>	The value for the SRC attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<UL CLEAR="cclear" WRAP="cwrap" DINGBAT="cdingbat" SRC="csrc" cattributes>
```

## UNDERLINE Function

This function generates the `<U>` and `</U>` tags, which direct the browser to render the text they surround with an underline.

### Syntax

```
HTF.UNDERLINE(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–90** *UNDERLINE Function Parameters*

Parameter	Description
<code>ctext</code>	The text to render with an underline.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<U cattributes>ctext</U>
```

## VARIABLE Function

This function generates the <VAR> and </VAR> tags which direct the browser to render the text they surround in italics or however "variable" is defined stylistically.

### Syntax

```
HTF.VARIABLE(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Parameters

**Table 123–91** VARIABLE Function Parameters

Parameter	Description
<code>ctext</code>	The text to render in italics.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This function generates

```
<VAR cattributes>ctext</VAR>
```

## WBR Function

This function generates the <WBR> tag, which inserts a soft line break within a section of NOBR text.

### Syntax

```
HTF.WBR
RETURN VARCHAR2;
```

### Examples

This function generates

```
<WBR>
```





---

## HTMLDB\_CUSTOM\_AUTH

The HTMLDB\_CUSTOM\_AUTH package provides an interface for authentication and session management.

- [Documentation of HTMLDB\\_CUSTOM\\_AUTH](#)

---

## Documentation of HTMLDB\_CUSTOM\_AUTH

For a complete description of this package within the context of HTMLDB, see `HTMLDB_CUSTOM_AUTH` in the *Oracle HTML DB User's Guide*.

---

## HTMLDB\_APPLICATION

The HTMLDB\_APPLICATION package enables users to take advantage of global variables.

- [Documentation of HTMLDB\\_APPLICATION](#)

---

## Documentation of HTMLDB\_APPLICATION

For a complete description of this package within the context of HTMLDB, see HTMLDB\_APPLICATION in the *Oracle HTML DB User's Guide*.

The HTMLDB\_ITEM package enables users to create form elements dynamically based on a SQL query instead of creating individual items page by page.

- [Documentation of HTMLDB\\_ITEM](#)

---

## Documentation of HTMLDB\_ITEM

For a complete description of this package within the context of HTMLDB, see `HTMLDB_ITEM` in the *Oracle HTML DB User's Guide*.

The `HTMLDB_UTIL` package provides utilities for getting and setting session state, getting files, checking authorizations for users, resetting different states for users, and also getting and setting preferences for users.

- [Documentation of HTMLDB\\_UTIL](#)

---

## Documentation of HTMLDB\_UTIL

For a complete description of this package within the context of HTMLDB, see `HTMLDB_UTIL` in the *Oracle HTML DB User's Guide*.



The `HTP` (hypertext procedures) and `HTF` (hypertext functions) packages generate HTML tags. For example, the `HTP.ANCHOR` procedure generates the HTML anchor tag, `<A>`.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

This chapter contains the following topics:

- [Using HTP](#)
  - [Operational Notes](#)
  - [Rules and Limits](#)
  - [Examples](#)
- [Summary of Tags](#)
- [Summary of HTP Subprograms](#)

## Using HTP

- [Operational Notes](#)
- [Rules and Limits](#)
- [Examples](#)

### Operational Notes

For every HTP procedure that generates one or more HTML tags, there is a corresponding HTF function with identical parameters with the following exception:

- The [PRINTS Procedure](#) and the [PS Procedure](#) do not have HTF function equivalents. Use the [ESCAPE\\_SC Function](#) or the [ESCAPE\\_URL Function](#) if you need a string conversion function. Note that while there is a [ESCAPE\\_SC Procedure](#) that performs the same operation as the [PRINTS Procedure](#) and the [PS Procedure](#), there is no procedural equivalent for the [ESCAPE\\_URL Function](#).
- The [FORMAT\\_CELL Function](#) does not have an HTP equivalent. The function formats column values inside an HTML table using [TABLEDATA Function](#) which does have an HTP equivalent in the [TABLEDATA Procedure](#). The advantage of this using the [FORMAT\\_CELL Function](#) is that it allows for better control over the HTML tables.

The function versions do not directly generate output in your web page. Instead, they pass their output as return values to the statements that invoked them. Use these functions when you need to nest calls. To print the output of HTF functions, call the functions from within the `HTP.PRINT` procedure. It then prints its parameters to the generated web page.

### Rules and Limits

If you use values of the LONG data type in procedures such as `HTP.PRINT`, `HTP.PRN`, `HTP.PRINTS`, `HTP.PA` or `OWA_UTIL.CELLSPRINT`, only the first 32 K of the LONG data is used. The LONG data is bound to a VARCHAR2 data type in the procedure.

## Examples

The following commands generate a simple HTML document:

```
CREATE OR REPLACE PROCEDURE hello AS
BEGIN
 HTP.HTMLOPEN; -- generates <HTML>
 HTP.HEADOPEN; -- generates <HEAD>
 HTP.TITLE('Hello'); -- generates <TITLE>Hello</TITLE>
 HTP.HEADCLOSE; -- generates </HEAD>
 HTP.BODYOPEN; -- generates <BODY>
 HTP.HEADER(1, 'Hello'); -- generates <H1>Hello</H1>
 HTP.BODYCLOSE; -- generates </BODY>
 HTP.HTMLCLOSE; -- generates </HTML>
END;
```

## Summary of Tags

---

### HTML, HEAD, and BODY Tags

[HTMLOPEN Procedure](#), [HTMLCLOSE Procedure](#) - generate <HTML> and </HTML>

[HEADOPEN Procedure](#), [HEADCLOSE Procedure](#) - generate <HEAD> and </HEAD>

[BODYOPEN Procedure](#), [BODYCLOSE Procedure](#) - generate <BODY> and </BODY>

### Comment Tag

[COMMENT Procedure](#) - generates <!-- and -->

### Tags in the <HEAD> Area

[BASE Procedure](#) - generates <BASE>

[LINKREL Procedure](#) - generates <LINK> with the REL attribute

[LINKREV Procedure](#) - generates <LINK> with the REV attribute

[TITLE Procedure](#) - generates <TITLE>

[META Procedure](#) - generates <META>

[SCRIPT Procedure](#) - generates <SCRIPT>

[STYLE Procedure](#) - generates <STYLE>

[ISINDEX Procedure](#) - generates <ISINDEX>

### Applet Tags

[APPLETOPEN Procedure](#), [APPLETCLOSE Procedure](#) - generate <APPLET> and </APPLET>

[PARAM Procedure](#) - generates <PARAM>

### List Tags

[OLISTOPEN Procedure](#), [OLISTCLOSE Procedure](#) - generate <OL> and </OL>

[ULISTOPEN Procedure](#), [ULISTCLOSE Procedure](#) - generate <UL> and </UL>

[DLISTOPEN Procedure](#), [DLISTCLOSE Procedure](#) - generate <DL> and </DL>

[DLISTTERM Procedure](#) - generates <DT>

[DLISTDEF Procedure](#) - generates <DD>

[DIRLISTOPEN Procedure](#), [DIRLISTCLOSE Procedure](#) - generate <DIR> and </DIR>

[LISTHEADER Procedure](#) - generates <LH>

[LISTINGOPEN Procedure](#), [LISTINGCLOSE Procedure](#) - generate <LISTING> and </LISTING>

[MENULISTOPEN Procedure](#) - generate <MENU> and </MENU>

[LISTITEM Procedure](#) - generates <LI>

## Form Tags

[FORMOPEN Procedure](#), [FORMCLOSE Procedure](#) - generate <FORM> and </FORM>

[FORMCHECKBOX Procedure](#) - generates <INPUT TYPE="CHECKBOX">

[FORMHIDDEN Procedure](#) - generates <INPUT TYPE="HIDDEN">

[FORMIMAGE Procedure](#) - generates <INPUT TYPE="IMAGE">

[FORMPASSWORD Procedure](#) - generates <INPUT TYPE="PASSWORD">

[FORMRADIO Procedure](#) - generates <INPUT TYPE="RADIO">

[FORMSELECTOPEN Procedure](#), [FORMSELECTCLOSE Procedure](#) - generate <SELECT> and </SELECT>

[FORMSELETOPTION Procedure](#) - generates <OPTION>

[FORMTEXT Procedure](#) - generates <INPUT TYPE="TEXT">

[FORMTEXTAREA Procedure](#) - generate <TEXTAREA>

[FORMTEXTAREAOPEN Procedure](#), [FORMTEXTAREACLOSE Procedure](#) - generate <TEXTAREA> and </TEXTAREA>

[FORMRESET Procedure](#) - generates <INPUT TYPE="RESET">

[FORMSUBMIT Procedure](#) - generates <INPUT TYPE="SUBMIT">

## Table Tags

[TABLEOPEN Procedure](#), [TABLECLOSE Procedure](#) - generate <TABLE> and </TABLE>

[TABLECAPTION Procedure](#) - generates <CAPTION>

[TABLEROWOPEN Procedure](#), [TABLEROWCLOSE Procedure](#) - generate <TR> and </TR>

[TABLEHEADER Procedure](#) - generates <TH>

[TABLEDATA Procedure](#) - generates <TD>

## IMG, HR, and A Tags

[HR Procedure](#), [LINE Procedure](#) - generate <HR>

[IMG Procedure](#), [IMG2 Procedure](#) - generate <IMG>

[ANCHOR Procedure](#), [ANCHOR2 Procedure](#) - generate <A>

[MAPOPEN Procedure](#), [MAPCLOSE Procedure](#) - generate <MAP> and </MAP>

## Paragraph Formatting Tags

[HEADER Procedure](#) - generates heading tags (<H1> to <H6>)

[PARA Procedure](#), [PARAGRAPH Procedure](#) - generate <P>

[PRN Procedures](#), [PRINT Procedures](#) - generate any text that is passed in

[PRINTS Procedure](#), [PS Procedure](#) - generate any text that is passed in; special characters in HTML are escaped

[PREOPEN Procedure](#), [PRECLOSE Procedure](#) - generate <PRE> and </PRE>

[BLOCKQUOTEOPEN Procedure](#), [BLOCKQUOTECLOSE Procedure](#) - generate <BLOCKQUOTE> and </BLOCKQUOTE>

[DIV Procedure](#) - generates <DIV>

[NL Procedure](#), [BR Procedure](#) - generate <BR>

[NOBR Procedure](#) - generates <NOBR>

[WBR Procedure](#) - generates <WBR>

[PLAINTEXT Procedure](#) - generates <PLAINTEXT>

[ADDRESS Procedure](#) - generates <ADDRESS>

[MAILTO Procedure](#) - generates <A> with the MAILTO attribute

[AREA Procedure](#) - generates <AREA>

[BGSOUND Procedure](#) - generates <BGSOUND>

## Character Formatting Tags

**BASEFONT Procedure** - generates <BASEFONT>

**BIG Procedure** - generates <BIG>

**BOLD Procedure** - generates <B>

**CENTER Procedure** - generates <CENTER> and </CENTER>

**CENTEROPEN Procedure, CENTERCLOSE Procedure** - generate <CENTER> and </CENTER>

**CITE Procedure** - generates <CITE>

**CODE Procedure** - generates <CODE>

**DFN Procedure** - generates <DFN>

**EM Procedure, EMPHASIS Procedure** - generate <EM>

**FONTOPEN Procedure, FONTCLOSE Procedure** - generate <FONT> and </FONT>

**ITALIC Procedure** - generates <I>

**KBD Procedure, KEYBOARD Procedure** - generate <KBD> and </KBD>

**S Procedure** - generates <S>

**SAMPLE Procedure** - generates <SAMP>

**SMALL Procedure** - generates <SMALL>

**STRIKE Procedure** - generates <STRIKE>

**STRONG Procedure** - generates <STRONG>

**SUB Procedure** - generates <SUB>

**SUP Procedure** - generates <SUP>

**TELETYPE Procedure** - generates <TT>

**UNDERLINE Procedure** - generates <U>

**VARIABLE Procedure** - generates <VAR>

## Frame Tags

**FRAME Procedure** - generates <FRAME>

**FRAMESETOPEN Procedure, FRAMESETCLOSE Procedure** - generate <FRAMESET> and </FRAMESET>

[NOFRAMESOPEN Procedure, NOFRAMESCLOSE Procedure](#) - generate  
<NOFRAMES> and </NOFRAMES>



---

## Summary of HTP Subprograms

**Table 128–1** *HTP Package Subprograms*

Subprogram	Description
<a href="#">ADDRESS Procedure</a> on page 128-17	Generates the <code>&lt;ADDRESS&gt;</code> and <code>&lt;/ADDRESS&gt;</code> tags which specify the address, author and signature of a document
<a href="#">ANCHOR Procedure</a> on page 128-18	Generates the <code>&lt;A&gt;</code> and <code>&lt;/A&gt;</code> tags which specify the source or destination of a hypertext link
<a href="#">ANCHOR2 Procedure</a> on page 128-19	Generates the <code>&lt;A&gt;</code> and <code>&lt;/A&gt;</code> tags which specify the source or destination of a hypertext link
<a href="#">APPLETCLOSE Procedure</a> on page 128-20	Closes the applet invocation with the <code>&lt;/APPLET&gt;</code> tag
<a href="#">APPLETOPEN Procedure</a> on page 128-21	Generates the <code>&lt;APPLET&gt;</code> tag which begins the invocation of a Java applet
<a href="#">AREA Procedure</a> on page 128-23	Generates the <code>&lt;AREA&gt;</code> tag, which defines a client-side image map
<a href="#">BASE Procedure</a> on page 128-24	Generates the <code>&lt;BASE&gt;</code> tag which records the URL of the document
<a href="#">BASEFONT Procedure</a> on page 128-25	Generates the <code>&lt;BASEFONT&gt;</code> tag which specifies the base font size for a Web page
<a href="#">BGSOUND Procedure</a> on page 128-26	Generates the <code>&lt;BGSOUND&gt;</code> tag which includes audio for a Web page
<a href="#">BIG Procedure</a> on page 128-27	Generates the <code>&lt;BIG&gt;</code> and <code>&lt;/BIG&gt;</code> tags which direct the browser to render the text in a bigger font
<a href="#">BLOCKQUOTECLOSE Procedure</a> on page 128-28	Generates the <code>&lt;/BLOCKQUOTE&gt;</code> tag which mark the end of a section of quoted text
<a href="#">BLOCKQUOTEOPEN Procedure</a> on page 128-29	Generates the <code>&lt;BLOCKQUOTE&gt;</code> tag, which marks the beginning of a section of quoted text
<a href="#">BODYCLOSE Procedure</a> on page 128-30	Generates the <code>&lt;/BODY&gt;</code> tag which marks the end of a body section of an HTML document
<a href="#">BODYOPEN Procedure</a> on page 128-31	Generates the <code>&lt;BODY&gt;</code> tag which marks the beginning of the body section of an HTML document

**Table 128–1 (Cont.) HTP Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">BOLD Procedure</a> on page 128-32	Generates the <B> and </B> tags which direct the browser to display the text in boldface
<a href="#">BR Procedure</a> on page 128-33	Generates the   tag which begins a new line of text
<a href="#">CENTER Procedure</a> on page 128-34	Generates the <CENTER> and </CENTER> tags which center a section of text within a Web page
<a href="#">CENTERCLOSE Procedure</a> on page 128-35	Generates the </CENTER> tag which marks the end of a section of text to center
<a href="#">CENTEROPEN Procedure</a> on page 128-36	Generates the <CENTER> tag which mark the beginning of a section of text to center
<a href="#">CITE Procedure</a> on page 128-37	Generates the <CITE> and </CITE> tags which direct the browser to render the text as a citation
<a href="#">CODE Procedure</a> on page 128-38	Generates the <CODE> and </CODE> tags which direct the browser to render the text in monospace font or however "code" is defined stylistically
<a href="#">COMMENT Procedure</a> on page 128-39	Generates This procedure generates the comment tags <!-- ctext -->
<a href="#">DFN Procedure</a> on page 128-40	Generates the <DFN> and </DFN> tags which direct the browser to mark the text as italics or however "definition" is defined stylistically
<a href="#">DIRLISTCLOSE Procedure</a> on page 128-41	Generates the </DIR> tag which ends a directory list section
<a href="#">DIRLISTOPEN Procedure</a> on page 128-42	Generates the <DIR> which starts a directory list section
<a href="#">DIV Procedure</a> on page 128-43	Generates the <DIV> tag which creates document divisions
<a href="#">DLISTCLOSE Procedure</a> on page 128-44	Generates the </DL> tag which ends a definition list
<a href="#">DLISTOPEN Procedure</a> on page 128-45	Generates the <DL> tag which starts a definition list
<a href="#">DLISTDEF Procedure</a> on page 128-46	Generates the <DD> tag, which inserts definitions of terms
<a href="#">DLISTTERM Procedure</a> on page 128-47	Generates the <DT> tag which defines a term in a definition list <DL>
<a href="#">EM Procedure</a> on page 128-48	Generates the <EM> and </EM> tags, which define text to be emphasized

**Table 128–1 (Cont.) HTP Package Subprograms**

Subprogram	Description
<a href="#">EMPHASIS Procedure</a> on page 128-49	Generates the <EM> and </EM> tags, which define text to be emphasized
<a href="#">ESCAPE_SC Procedure</a> on page 128-50	Replaces characters that have special meaning in HTML with their escape sequences
<a href="#">FONTCLOSE Procedure</a> on page 128-52	Generates the </FONT> tag which marks the end of a section of text with the specified font characteristics
<a href="#">FONTOPEN Procedure</a> on page 128-52	Generates the <FONT> which marks the beginning of section of text with the specified font characteristics
<a href="#">FORMCHECKBOX Procedure</a> on page 128-53	Generates the <INPUT> tag with TYPE="checkbox" which inserts a checkbox element in a form
<a href="#">FORMCLOSE Procedure</a> on page 128-54	Generates the </FORM> tag which marks the end of a form section in an HTML document
<a href="#">FORMOPEN Procedure</a> on page 128-55	Generates the <FORM> tag which marks the beginning of a form section in an HTML document
<a href="#">FORMFILE Procedure</a> on page 128-56	Generates the <INPUT> tag with TYPE="file" which inserts a file form element, and is used for file uploading for a given page
<a href="#">FORMHIDDEN Procedure</a> on page 128-57	Generates the <INPUT> tag with TYPE="hidden" which inserts a hidden form element
<a href="#">FORMIMAGE Procedure</a> on page 128-58	Generates the <INPUT> tag with TYPE="image" which creates an image field that the user clicks to submit the form immediately
<a href="#">FORMPASSWORD Procedure</a> on page 128-59	Generates the <INPUT> tag with TYPE="password" which creates a single-line text entry field
<a href="#">FORMRADIO Procedure</a> on page 128-60	Generates the <INPUT> tag with TYPE="radio", which creates a radio button on the HTML form
<a href="#">FORMRESET Procedure</a> on page 128-61	Generates the <INPUT> tag with TYPE="reset" which creates a button that, when selected, resets the form fields to their initial values
<a href="#">FORMSELECTCLOSE Procedure</a> on page 128-62	Generates the </SELECT> tag which marks the end of a Select form element
<a href="#">FORMSELECTOPEN Procedure</a> on page 128-63	Generates the </SELECT> tag which marks the beginning of a Select form element
<a href="#">FORMSELETOPTION Procedure</a> on page 128-65	Generates the <OPTION> tag which represents one choice in a Select element

**Table 128–1 (Cont.) HTP Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">FORMSUBMIT Procedure</a> on page 128-66	Generates the <INPUT> tag with TYPE="submit" which creates a button that, when clicked, submits the form
<a href="#">FORMTEXT Procedure</a> on page 128-67	Generates the <INPUT> tag with TYPE="text", which creates a field for a single line of text
<a href="#">FORMTEXTAREA Procedure</a> on page 128-68	Generates the <TEXTAREA> tag, which creates a text field that has no predefined text in the text area
<a href="#">FORMTEXTAREA2 Procedure</a> on page 128-69	Generates the <TEXTAREA> tag, which creates a text field that has no predefined text in the text area with the ability to specify a wrap style
<a href="#">FORMTEXTAREACLOSE Procedure</a> on page 128-70	Generates the </TEXTAREA> tag which ends a text area form element
<a href="#">FORMTEXTAREAOPEN Procedure</a> on page 128-71	Generates the <TEXTAREA> which marks the beginning of a text area form element
<a href="#">FORMTEXTAREAOPEN2 Procedure</a> on page 128-72	Generates the <TEXTAREA> which marks the beginning of a text area form element with the ability to specify a wrap style
<a href="#">FRAME Procedure</a> on page 128-73	Generates the <FRAME> tag which defines the characteristics of a frame created by a <FRAMESET> tag
<a href="#">FRAMESETCLOSE Procedure</a> on page 128-74	Generates the </FRAMESET> tag which ends a frameset section
<a href="#">FRAMESETOPEN Procedure</a> on page 128-75	Generates the </FRAMESET> tag which begins a frameset section
<a href="#">HEADCLOSE Procedure</a> on page 128-76	Generates the </HEAD> tag which marks the end of an HTML document head section
<a href="#">HEADOPEN Procedure</a> on page 128-77	Generates the <HEAD> tag which marks the beginning of the HTML document head section
<a href="#">HEADER Procedure</a> on page 128-78	Generates opening heading tags (<H1> to <H6>) and their corresponding closing tags (</H1> to </H6>)
<a href="#">HR Procedure</a> on page 128-79	Generates the <HR> tag, which generates a line in the HTML document
<a href="#">HTMLCLOSE Procedure</a> on page 128-81	Generates the </HTML> tag which marks the end of an HTML document
<a href="#">HTMLOPEN Procedure</a> on page 128-81	Generates the <HTML> tag which marks the beginning of an HTML document

**Table 128–1 (Cont.) HTP Package Subprograms**

Subprogram	Description
<a href="#">IMG Procedure</a> on page 128-82	Generates the <IMG> tag which directs the browser to load an image onto the HTML page
<a href="#">IMG2 Procedure</a> on page 128-83	Generates the <IMG> tag which directs the browser to load an image onto the HTML page with the option of specifying values for the USEMAP attribute
<a href="#">ISINDEX Procedure</a> on page 128-84	Creates a single entry field with a prompting text, such as "enter value," then sends that value to the URL of the page or program
<a href="#">ITALIC Procedure</a> on page 128-85	Generates the <I> and </I> tags which direct the browser to render the text in italics
<a href="#">KBD Procedure</a> on page 128-86	Generates the <KBD> and </KBD> tags which direct the browser to render the text in monospace font
<a href="#">KEYBOARD Procedure</a> on page 128-87	Generates the <KBD> and </KBD> tags, which direct the browser to render the text in monospace font
<a href="#">LINE Procedure</a> on page 128-88	Generates the <HR> tag, which generates a line in the HTML document
<a href="#">LINKREL Procedure</a> on page 128-89	Generates the <LINK> tag with the REL attribute which delineates the relationship described by the hypertext link from the anchor to the target
<a href="#">LINKREV Procedure</a> on page 128-90	Generates the <LINK> tag with the REV attribute which delineates the relationship described by the hypertext link from the target to the anchor
<a href="#">LISTHEADER Procedure</a> on page 128-91	Generates the <LH> and </LH> tags which print an HTML tag at the beginning of the list
<a href="#">LISTINGCLOSE Procedure</a> on page 128-92	Generates the </LISTING> tags which marks the end of a section of fixed-width text in the body of an HTML page
<a href="#">LISTINGOPEN Procedure</a> on page 128-93	Generates the <LISTING> tag which marks the beginning of a section of fixed-width text in the body of an HTML page
<a href="#">LISTITEM Procedure</a> on page 128-94	Generates the <LI> tag, which indicates a list item
<a href="#">MAILTO Procedure</a> on page 128-95	Generates the <A> tag with the HREF set to 'mailto' prepended to the mail address argument
<a href="#">MAPCLOSE Procedure</a> on page 128-96	Generates the </MAP> tag which marks the end of a set of regions in a client-side image map

**Table 128–1 (Cont.) HTP Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">MAPOPEN Procedure</a> on page 128-97	Generates the <MAP> tag which mark the beginning of a set of regions in a client-side image map
<a href="#">MENULISTCLOSE Procedure</a> on page 128-98	Generates the </MENU> tag which ends a list that presents one line for each item
<a href="#">MENULISTOPEN Procedure</a> on page 128-99	Generates the <MENU> tag which create a list that presents one line for each item
<a href="#">META Procedure</a> on page 128-100	Generates the <META> tag, which embeds meta-information about the document and also specifies values for HTTP headers
<a href="#">NL Procedure</a> on page 128-101	Generates the   tag which begins a new line of text
<a href="#">NOBR Procedure</a> on page 128-102	Generates the <NOBR> and </NOBR> tags which turn off line-breaking in a section of text
<a href="#">NOFRAMESCLOSE Procedure</a> on page 128-103	Generates the </NOFRAMES> tag which marks the end of a no-frames section
<a href="#">NOFRAMESOPEN Procedure</a> on page 128-104	Generates the <NOFRAMES> tag which mark the beginning of a no-frames section
<a href="#">OLISTCLOSE Procedure</a> on page 128-105	Generates the </OL> tag which defines the end of an ordered list
<a href="#">OLISTOPEN Procedure</a> on page 128-106	Generates the <OL> tag which marks the beginning of an ordered list
<a href="#">PARA Procedure</a> on page 128-107	Generates the <P> tag which indicates that the text that comes after the tag is to be formatted as a paragraph
<a href="#">PARAGRAPH Procedure</a> on page 128-108	Adds attributes to the <P> tag
<a href="#">PARAM Procedure</a> on page 128-109	Generates the <PARAM> tag which specifies parameter values for Java applets
<a href="#">PLAINTEXT Procedure</a> on page 128-110	Generates the <PLAINTEXT> and </PLAINTEXT> tags which direct the browser to render the text they surround in fixed-width type
<a href="#">PRECLOSE Procedure</a> on page 128-111	Generates the </PRE> tag which marks the end of a section of preformatted text in the body of the HTML page
<a href="#">PREOPEN Procedure</a> on page 128-112	Generates the <PRE> tag which marks the beginning of a section of preformatted text in the body of the HTML page
<a href="#">PRINT Procedures</a> on page 128-113	Generates the specified parameter as a string terminated with the \n newline character

**Table 128–1 (Cont.) HTP Package Subprograms**

Subprogram	Description
<a href="#">PRINTS Procedure</a> on page 128-114	Generates a string and replaces the following characters with the corresponding escape sequence
<a href="#">PRN Procedures</a> on page 128-115	Generates the specified parameter as a string
<a href="#">PS Procedure</a> on page 128-116	Generates a string and replaces the following characters with the corresponding escape sequence.
<a href="#">S Procedure</a> on page 128-117	Generates the <S> and </S> tags which direct the browser to render the text they surround in strikethrough type
<a href="#">SAMPLE Procedure</a> on page 128-118	Generates the <SAMP> and </SAMP> tags which direct the browser to render the text they surround in monospace font or however "sample" is defined stylistically
<a href="#">SCRIPT Procedure</a> on page 128-119	Generates the <SCRIPT> and </SCRIPT> tags which contain a script written in languages such as JavaScript and VBscript
<a href="#">SMALL Procedure</a> on page 128-120	Generates the <SMALL> and </SMALL> tags, which direct the browser to render the text they surround using a small font
<a href="#">STRIKE Procedure</a> on page 128-121	Generates the <STRIKE> and </STRIKE> tags which direct the browser to render the text they surround in strikethrough type
<a href="#">STRONG Procedure</a> on page 128-122	Generates the <STRONG> and </STRONG> tags which direct the browser to render the text they surround in bold or however "strong" is defined stylistically
<a href="#">STYLE Procedure</a> on page 128-123	Generates the <STYLE> and </STYLE> tags which include a style sheet in a Web page
<a href="#">SUB Procedure</a> on page 128-124	Generates the <SUB> and </SUB> tags which direct the browser to render the text they surround as subscript
<a href="#">SUP Procedure</a> on page 128-125	Generates the <SUP> and </SUP> tags which direct the browser to render the text they surround as superscript
<a href="#">TABLECAPTION Procedure</a> on page 128-126	Generates the <CAPTION> and </CAPTION> tags which place a caption in an HTML table
<a href="#">TABLEDATA Procedure</a> on page 128-127	Generates the <TD> and </TD> tags which insert data into a cell of an HTML table
<a href="#">TABLEHEADER Procedure</a> on page 128-128	Generates the <TH> and </TH> tags which insert a header cell in an HTML table.

**Table 128–1 (Cont.) HTP Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">TABLECLOSE Procedure</a> on page 128-129	Generates the <code>&lt;/TABLE&gt;</code> tag which marks the end of an HTML table
<a href="#">TABLEOPEN Procedure</a> on page 128-130	Generates the <code>&lt;TABLE&gt;</code> tag which marks the beginning of an HTML table
<a href="#">TABLEROWCLOSE Procedure</a> on page 128-131	Generates the <code>&lt;/TR&gt;</code> tag which marks the end of a new row in an HTML table
<a href="#">TABLEROWOPEN Procedure</a> on page 128-132	Generates the <code>&lt;TR&gt;</code> tag which marks the beginning of a new row in an HTML table
<a href="#">TELETYPE Procedure</a> on page 128-133	Generates the <code>&lt;TT&gt;</code> and <code>&lt;/TT&gt;</code> tags which direct the browser to render the text they surround in a fixed width typewriter font, for example, the courier font
<a href="#">TITLE Procedure</a> on page 128-134	Generates the <code>&lt;TITLE&gt;</code> and <code>&lt;/TITLE&gt;</code> tags which specify the text to display in the titlebar of the browser window
<a href="#">ULISTCLOSE Procedure</a> on page 128-135	Generates the <code>&lt;/UL&gt;</code> tag which marks the end of an unordered list
<a href="#">ULISTOPEN Procedure</a> on page 128-136	Generates the <code>&lt;UL&gt;</code> tag which marks the beginning of an unordered list
<a href="#">UNDERLINE Procedure</a> on page 128-137	Generates the <code>&lt;U&gt;</code> and <code>&lt;/U&gt;</code> tags, which direct the browser to render the text they surround with an underline
<a href="#">VARIABLE Procedure</a> on page 128-138	Generates the <code>&lt;VAR&gt;</code> and <code>&lt;/VAR&gt;</code> tags which direct the browser to render the text they surround in italics or however "variable" is defined stylistically.
<a href="#">WBR Procedure</a> on page 128-139	Generates the <code>&lt;WBR&gt;</code> tag, which inserts a soft line break within a section of NOBR text



## ADDRESS Procedure

This procedure generates the `<ADDRESS>` and `</ADDRESS>` tags which specify the address, author and signature of a document.

### Syntax

```
HTP.ADDRESS (
 cvalue IN VARCHAR2
 cnowrap IN VARCHAR2 DEFAULT NULL
 cclear IN VARCHAR2 DEFAULT NULL
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–2 ADDRESS Procedure Parameters**

Parameter	Description
<code>cvalue</code>	The string that goes between the <code>&lt;ADDRESS&gt;</code> and <code>&lt;/ADDRESS&gt;</code> tags.
<code>cnowrap</code>	If the value for this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is included in the tag
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag

### Examples

This procedure generates

```
<ADDRESS CLEAR="cclear" NOWRAP cattributes>cvalue</ADDRESS>
```

## ANCHOR Procedure

This procedure and the [ANCHOR2 Procedure](#) procedures generate the `<A>` and `</A>` HTML tags which specify the source or destination of a hypertext link. The difference between these subprograms is that the [ANCHOR2 Procedure](#) provides a target and therefore can be used for a frame.

### Syntax

```
HTP.ANCHOR (
 curl IN VARCHAR2,
 ctext IN VARCHAR2,
 cname IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–3 ANCHOR Procedure Parameters**

Parameter	Description
<code>curl</code>	The value for the <code>HREF</code> attribute.
<code>ctext</code>	The string that goes between the <code>&lt;A&gt;</code> and <code>&lt;/A&gt;</code> tags.
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
ctext
```

### Usage Notes

This tag accepts several attributes, but either `HREF` or `NAME` is required. `HREF` specifies to where to link. `NAME` allows this tag to be a target of a hypertext link.

## ANCHOR2 Procedure

This procedure and the [ANCHOR Procedure](#) generate the <A> and </A> HTML tags which specify the source or destination of a hypertext link. The difference between these subprograms is that this procedure provides a target and therefore can be used for a frame.

### Syntax

```
HTP.ANCHOR2 (
 curl IN VARCHAR2,
 ctext IN VARCHAR2,
 cname IN VARCHAR2 DEFAULT NULL,
 ctarget IN varchar2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–4 ANCHOR2 Procedure Parameters**

Parameter	Description
curl	The value for the HREF attribute.
ctext	The string that goes between the <A> and </A> tags.
cname	The value for the NAME attribute
ctarget	The value for the TARGET attribute.
cattributes	The other attributes to be included as-is in the tag

### Examples

This procedure generates

```
ctext
```

## APPLETCLOSE Procedure

This procedure closes the applet invocation with the `</APPLET>` tag. You must first invoke the a Java applet using [APPLETOPEN Procedure](#) on page 128-21

### Syntax

```
HTP.APPLETCLOSE;
```

## APPLETOPEN Procedure

This procedure generates the `<APPLET>` tag which begins the invocation of a Java applet. You close the applet invocation with [APPLETCLOSE Procedure](#) on page 128-20 which generates the `</APPLET>` tag.

### Syntax

```
HTP.APPLETOPEN (
 ccode IN VARCHAR2,
 cheight IN NUMBER,
 cwidth IN NUMBER,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–5** *APPLETOPEN Procedure Parameters*

Parameter	Description
<code>ccode</code>	The the value for the <code>CODE</code> attribute which specifies the name of the applet class.
<code>cheight</code>	The value for the <code>HEIGHT</code> attribute.
<code>cwidth</code>	The value for the <code>WIDTH</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<APPLET CODE=ccode HEIGHT=cheight WIDTH=cwidth cattributes>
```

so that, for example,

```
HTP.appletopen('testclass.class', 100, 200, 'CODEBASE="/ows-applets"')
```

generates

```
<APPLET CODE="testclass.class" height=100 width=200 CODEBASE="/ows-applets">
```

## Usage Notes

- Specify parameters to the Java applet using the [PARAM Procedure](#) procedure on page 128-109.
- Use the `cattributes` parameter to specify the `CODEBASE` attribute since the PL/SQL cartridge does not know where to find the class files. The `CODEBASE` attribute specifies the virtual path containing the class files.

## AREA Procedure

This procedure generates the <AREA> tag, which defines a client-side image map. The <AREA> tag defines areas within the image and destinations for the areas.

### Syntax

```
HTP.AREA (
 ccoords IN VARCHAR2
 cshape IN VARCHAR2 DEFAULT NULL,
 chref IN VARCHAR2 DEFAULT NULL,
 cnohref IN VARCHAR2 DEFAULT NULL,
 ctarget IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–6 AREA Procedure Parameters**

Parameter	Description
<code>ccords</code>	The the value for the <code>COORDS</code> attribute.
<code>cshape</code>	The value for the <code>SHAPE</code> attribute.
<code>chref</code>	The value for the <code>HREF</code> attribute.
<code>cnohref</code>	If the value for this parameter is not <code>NULL</code> , the <code>NOHREF</code> attribute is added to the tag.
<code>ctarget</code>	The value for the <code>TARGET</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<AREA COORDS="ccords" SHAPE="cshape" HREF="chref" NOHREF TARGET="ctarget"
cattributes>
```

## BASE Procedure

This procedure generates the <BASE> tag which records the URL of the document.

### Syntax

```
HTP.BASE (
 ctarget IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–7** *BASE Procedure Parameters*

Parameter	Description
<code>ctarget</code>	The value for the <code>TARGET</code> attribute which establishes a window name to which all links in this document are targeted.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<BASE HREF="<current URL>" TARGET="ctarget" cattributes>
```



## BASEFONT Procedure

This procedure generates the <BASEFONT> tag which specifies the base font size for a Web page.

### Syntax

```
HTP.BASEFONT (
 nsize IN INTEGER);
```

### Parameters

**Table 128–8** *BASEFONT Procedure Parameters*

Parameter	Description
nsize	The value for the SIZE attribute.

### Examples

This procedure generates

```
<BASEFONT SIZE="nsize">
```

## BGSOUND Procedure

This procedure generates the <BGSOUND> tag which includes audio for a Web page.

### Syntax

```
HTP.BGSOUND (
 csrc IN VARCHAR2,
 cloop IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–9 BGSOUND Procedure Parameters**

Parameter	Description
<code>csrc</code>	The value for the SRC attribute.
<code>clloop</code>	The value for the LOOP attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<BGSOUND SRC="csrc" LOOP="clloop" cattributes>
```

## BIG Procedure

This procedure generates the <BIG> and </BIG> tags which direct the browser to render the text in a bigger font.

### Syntax

```
HTP.BIG (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–10** *BIG Procedure Parameters*

Parameter	Description
ctext	The the text that goes between the tags.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<BIG cattributes>ctext</BIG>
```

## BLOCKQUOTECLOSE Procedure

This procedure generates the `</BLOCKQUOTE>` tag which mark the end of a section of quoted text. You mark the beginning of a section of text by means of the [BLOCKQUOTEOPEN Procedure](#).

### Syntax

```
HTP.BLOCKQUOTECLOSE;
```

### Examples

This procedure generates

```
</BLOCKQUOTE>
```

## BLOCKQUOTEOPEN Procedure

This procedure generates the <BLOCKQUOTE> tag, which marks the beginning of a section of quoted text. You mark the end of a section of text by means of the [BLOCKQUOTECLOSE Procedure](#).

### Syntax

```
HTP.BLOCKQUOTEOPEN (
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–11** *BLOCKQUOTEOPEN Procedure Parameters*

Parameter	Description
cnowrap	If the value for this parameter is not NULL, the NOWRAP attribute is added to the tag.
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<BLOCKQUOTE CLEAR="cclear" NOWRAP cattributes>
```

## BODYCLOSE Procedure

This procedure generates the `</BODY>` tag which marks the end of a body section of an HTML document. You mark the beginning of a body section by means of the [BODYOPEN Procedure](#).

### Syntax

```
HTP.BODYCLOSE;
```

### Examples

This procedure generates

```
</BODY>
```

## BODYOPEN Procedure

This procedure generates the <BODY> tag which marks the beginning of the body section of an HTML document. You mark the end of a body section by means of the [BODYCLOSE Procedure](#).

### Syntax

```
HTP.BODYOPEN (
 cbackground IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–12 BODYOPEN Procedure Parameters**

Parameter	Description
cbackground	The value for the BACKGROUND attribute which specifies a graphic file to use for the background of the document.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<BODY background="cbackground" cattributes>
```

so that

```
HTP.BODYOPEN('/img/background.gif');
```

generates:

```
<BODY background="/img/background.gif">
```

## BOLD Procedure

This procedure generates the `<B>` and `</B>` tags which direct the browser to display the text in boldface.

### Syntax

```
HTP.BOLD (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–13 BOLD Procedure Parameters**

Parameter	Description
<code>ctext</code>	The text that goes between the tags.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<B cattributes>ctext
```



## BR Procedure

This procedure generates the <BR> tag which begins a new line of text. It performs the same operation as the [NL Procedure](#).

### Syntax

```
HTP.BR(
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–14 BR Procedure Parameters**

Parameter	Description
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<BR CLEAR="cclear" cattributes>
```

## CENTER Procedure

This procedure generates the `<CENTER>` and `</CENTER>` tags which center a section of text within a Web page.

### Syntax

```
HTP.CENTER (
 ctext IN VARCHAR2);
```

### Parameters

**Table 128–15** *CENTER Parameters*

Parameter	Description
<code>ctext</code>	The text that goes between the tags.

### Examples

This procedure generates

```
<CENTER>ctext</CENTER>
```

## CENTERCLOSE Procedure

This procedure generates the `</CENTER>` tag which marks the end of a section of text to center. You mark the beginning of a section of text to center by means of the [CENTEROPEN Procedure](#).

### Syntax

```
HTP.CENTERCLOSE ;
```

### Examples

This procedure generates

```
</CENTER>
```

## CENTEROPEN Procedure

This procedure generates the `<CENTER>` tag which mark the beginning of a section of text to center. You mark the beginning of a of a section of text to center by means of the [CENTERCLOSE Procedure](#).

### Syntax

```
HTP . CENTEROPEN ;
```

### Examples

This procedure generates

```
<CENTER>
```

## CITE Procedure

This procedure generates the `<CITE>` and `</CITE>` tags which direct the browser to render the text as a citation.

### Syntax

```
HTP.CITE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–16** *CITE Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to render as citation.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<CITE cattributes>ctext</CITE>
```

## CODE Procedure

This procedure generates the `<CODE>` and `</CODE>` tags which direct the browser to render the text in monospace font or however "code" is defined stylistically.

### Syntax

```
HTP.CODE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–17** *CODE Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to render as code.
<code>cattributes</code>	The other attributes to be included as-is in the tag

### Examples

This procedure generates

```
<CODE cattributes>ctext</CODE>
```

## COMMENT Procedure

This procedure generates the comment tags.

### Syntax

```
HTP.COMMENT (
 ctext IN VARCHAR2);
```

### Parameters

**Table 128–18** *COMMENT Procedure Parameters*

Parameter	Description
<code>ctext</code>	The comment.

### Examples

This procedure generates

```
<!-- ctext -->
```

## DFN Procedure

This procedure generates the `<DFN>` and `</DFN>` tags which direct the browser to mark the text in italics or however "definition" is described stylistically.

### Syntax

```
HTP.DFN (
 ctext IN VARCHAR2);
```

### Parameters

**Table 128–19 DFN Procedure Parameters**

Parameter	Description
<code>ctext</code>	The text to render in italics.

### Examples

This procedure generates

```
<DFN>ctext</DFN>
```



## DIRLISTCLOSE Procedure

This procedure generates the `</DIR>` tag which ends a directory list section. You start a directory list section with the [DIRLISTOPEN Procedure](#).

### Syntax

```
HTP.DIRLISTCLOSE;
```

### Usage Notes

A directory list presents a list of items that contains up to 20 characters. Items in this list are typically arranged in columns, 24 characters wide. Insert the `<LI>` tag directly or invoke the [LISTITEM Procedure](#) so that the `<LI>` tag appears directly after the `</DIR>` tag to define the items as a list.

### Examples

This procedure generates

```
</DIR>
```

## DIRLISTOPEN Procedure

This procedure generates the `<DIR>` which starts a directory list section. You end a directory list section with the [DIRLISTCLOSE Procedure](#).

### Syntax

```
HTP.DIRLISTOPEN;
```

### Usage Notes

A directory list presents a list of items that contains up to 20 characters. Items in this list are typically arranged in columns, 24 characters wide. Insert the `<LI>` tag directly or invoke the [LISTITEM Procedure](#) so that the `<LI>` tag appears directly after the `</DIR>` tag to define the items as a list.

### Examples

This procedure generates

```
<DIR>
```

## DIV Procedure

This procedure generates the <DIV> tag which creates document divisions.

### Syntax

```
HTP.DIV (
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–20** *DIV Procedure Parameters*

Parameter	Description
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<DIV ALIGN="calign" cattributes>
```

## DLISTCLOSE Procedure

This procedure generates the `</DL>` tag which ends a definition list. You start a definition list by means of the [DLISTOPEN Procedure](#).

### Syntax

```
HTP.DLISTCLOSE;
```

### Usage Notes

A definition list looks like a glossary: it contains terms and definitions. Terms are inserted using the [DLISTTERM Procedure](#) and definitions are inserted using the [DLISTDEF Procedure](#).

### Examples

This procedure generates

```
</DL>
```

## DLISTOPEN Procedure

This procedure generates the <DL> tag which starts a definition list. You end a definition list by means of the [DLISTCLOSE Procedure](#).

### Syntax

```
HTP.DLISTOPEN (
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–21** *DLISTOPEN Procedure Parameters*

Parameter	Description
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Usage Notes

A definition list looks like a glossary; it contains terms and definitions. Terms are inserted using the [DLISTTERM Procedure](#) and definitions are inserted using the [DLISTDEF Procedure](#).

### Examples

This procedure generates

```
<DL CLEAR="cclear" cattributes>
```

## DLISTDEF Procedure

This procedure generates the <DD> tag, which inserts definitions of terms. Use this tag for a definition list <DL>. Terms are tagged <DT> and definitions are tagged <DD>.

### Syntax

```
HTP.DLISTDEF (
 ctext IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–22** *DLISTDEF Procedure Parameters*

Parameter	Description
<code>ctext</code>	The definition of the term.
<code>cclear</code>	The value for the CLEAR attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<DD CLEAR="cclear" cattributes>ctext
```

## DLISTTERM Procedure

This procedure generates the <DT> tag which defines a term in a definition list <DL>.

### Syntax

```
HTP.DLISTTERM (
 ctext IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–23** *DLISTERM Procedure Parameters*

Parameter	Description
<code>ctext</code>	The term.
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<DT CLEAR="cclear" cattributes>ctext
```

## EM Procedure

This procedure generates the `<EM>` and `</EM>` tags, which define text to be emphasized. It performs the same task as the [EMPHASIS Procedure](#).

### Syntax

```
HTP.EM(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–24** *EM Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to emphasize.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<EM cattributes>ctext
```



## EMPHASIS Procedure

This procedure generates the `<EM>` and `</EM>` tags, which define text to be emphasized. It performs the same task as the [EM Procedure](#).

### Syntax

```
HTP.EMPHASIS(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–25 EMPHASIS Procedure Parameters**

Parameter	Description
<code>ctext</code>	The text to emphasize.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<EM cattributes>ctext
```

## ESCAPE\_SC Procedure

This procedure replaces characters that have special meaning in HTML with their escape sequences. The following characters are converted:

- & to &amp;#x26;
- " to &quot;
- < to &lt;
- > to &gt;

This procedure performs the same operation as [PRINTS Procedures](#) and [PS Procedure](#).

### Syntax

```
HTP.ESCAPE_SC(
 ctext IN VARCHAR2);
```

### Parameters

**Table 128–26** *ESCAPE\_SC Procedure Parameters*

Parameter	Description
ctext	The text string to convert.

## FONTCLOSE Procedure

This procedure generates the `</FONT>` tag which marks the end of a section of text with the specified font characteristics. You mark the beginning of the section text by means of the [FONTOPEN Procedure](#).

### Syntax

```
HTP.FONTCLOSE;
```

### Examples

This procedure generates

```

```

## FONTOPEN Procedure

This procedure generates the `<FONT>` which marks the beginning of section of text with the specified font characteristics. You mark the end of the section text by means of the [FONTCLOSE Procedure](#).

### Syntax

```
HTP.FONTOPEN(
 ccolor IN VARCHAR2 DEFAULT NULL,
 cface IN VARCHAR2 DEFAULT NULL,
 csize IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–27** *FONTOPEN Procedure Parameters*

Parameter	Description
<code>ccolor</code>	The value for the <code>COLOR</code> attribute.
<code>cface</code>	The value for the <code>FACE</code> attribute
<code>csize</code>	The value for the <code>SIZE</code> attribute
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```

```

## FORMCHECKBOX Procedure

This procedure generates the `<INPUT>` tag with `TYPE="checkbox"` which inserts a checkbox element in a form. A checkbox element is a button that the user toggles on or off.

### Syntax

```
HTP.FORMCHECKBOX(
 cname IN VARCHAR2,
 cvalue IN VARCHAR2 DEFAULT 'ON' ,
 cchecked IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–28** *FORMCHECKBOX Procedure Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cchecked</code>	If the value for this parameter is not <code>NULL</code> , the <code>CHECKED</code> attribute is added to the tag.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="checkbox" NAME="cname" VALUE="cvalue" CHECKED cattributes>
```

## FORMCLOSE Procedure

This procedure generates the `</FORM>` tag which marks the end of a form section in an HTML document. You mark the beginning of the form section by means of the [FORMOPEN Procedure](#).

### Syntax

```
HTP.FORMCLOSE;
```

### Examples

This procedure generates

```
</FORM>
```

## FORMOPEN Procedure

This procedure generates the <FORM> tag which marks the beginning of a form section in an HTML document. You mark the end of the form section by means of the [FORMCLOSE Procedure](#).

### Syntax

```
HTP.FORMOPEN(
 curl IN VARCHAR2,
 cmethod IN VARCHAR2 DEFAULT 'POST',
 ctarget IN VARCHAR2 DEFAULT NULL,
 cenctype IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–29 FORMOPEN Procedure Parameters**

Parameter	Description
curl	The URL of the WRB or CGI script where the contents of the form is sent. This parameter is required.
cmethod	The value for the METHOD attribute. The value can be "GET" or "POST".
ctarget	The value for the TARGET attribute.
cenctype	The value for the ENCTYPE attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<FORM ACTION="curl" METHOD="cmethod" TARGET="ctarget" ENCTYPE="cenctype"
cattributes>
```

## FORMFILE Procedure

This procedure generates the `<INPUT>` tag with `TYPE="file"` which inserts a file form element. This is used for file uploading for a given page.

### Syntax

```
HTP.FORMFILE(
 cname IN VARCHAR2,
 caccept IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–30 FORMFILE Procedure Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>caccept</code>	A comma-delimited list of MIME types for upload.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="file" NAME="cname" ACCEPT="caccept" cattributes>
```



## FORMHIDDEN Procedure

This procedure generates the `<INPUT>` tag with `TYPE="hidden"`, which inserts a hidden form element. This element is not seen by the user. It submits additional values to the script.

### Syntax

```
HTP.FORMHIDDEN(
 cname IN VARCHAR2,
 cvalue IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–31** *FORMHIDDEN Procedure Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="hidden" NAME="cname" VALUE="cvalue" cattributes>
```

## FORMIMAGE Procedure

This procedure generates the `<INPUT>` tag with `TYPE="image"` which creates an image field that the user clicks to submit the form immediately. The coordinates of the selected point are measured in pixels, and returned (along with other contents of the form) in two name/value pairs. The x coordinate is submitted under the name of the field with `.x` appended, and the y coordinate with `.y` appended. Any `VALUE` attribute is ignored.

### Syntax

```
HTP.FORMIMAGE(
 cname IN VARCHAR2,
 csrc IN VARCHAR2,
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–32** *FORMIMAGE Procedure Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>csrc</code>	The value for the <code>SRC</code> attribute that specifies the image file.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="image" NAME="cname" SRC="csrc" ALIGN="calign" cattributes>
```

## FORMPASSWORD Procedure

This procedure generates the `<INPUT>` tag with `TYPE="password"` which creates a single-line text entry field. When the user enters text in the field, each character is represented by one asterisk. This is used for entering passwords.

### Syntax

```
HTP.FORMPASSWORD(
 cname IN VARCHAR2,
 csize IN VARCHAR2,
 cmaxlength IN VARCHAR2 DEFAULT NULL,
 cvalue IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–33** *FORMPASSWORD Procedure Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>csize</code>	The value for the <code>SIZE</code> attribute.
<code>cmmaxlength</code>	The value for the <code>MAXLENGTH</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="password" NAME="cname" SIZE="csize" MAXLENGTH="cmmaxlength"
VALUE="cvalue" cattributes>
```

## FORMRADIO Procedure

This procedure generates the `<INPUT>` tag with `TYPE="radio"`, which creates a radio button on the HTML form. Within a set of radio buttons, the user selects only one. Each radio button in the same set has the same name, but different values. The selected radio button generates a name/value pair.

### Syntax

```
HTP.FORMRADIO(
 cname IN VARCHAR2,
 cvalue IN VARCHAR2,
 cchecked IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–34 FORMRADIO Procedure Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cchecked</code>	If the value for this parameter is not <code>NULL</code> , the <code>CHECKED</code> attribute is added to the tag.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="radio" NAME="cname" VALUE="cvalue" CHECKED cattributes>
```

## FORMRESET Procedure

This procedure generates the `<INPUT>` tag with `TYPE="reset"` which creates a button that, when selected, resets the form fields to their initial values.

### Syntax

```
HTP.FORMRESET(
 cvalue IN VARCHAR2 DEFAULT 'Reset',
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–35** *FORMRESET Procedure Parameters*

Parameter	Description
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="reset" VALUE="cvalue" cattributes>
```

## FORMSELECTCLOSE Procedure

This procedure generates the `</SELECT>` tag which marks the end of a Select form element. A Select form element is a listbox where the user selects one or more values. You mark the beginning of Select form element by means of the [FORMSELECTOPEN Procedure](#). The values are inserted using [FORMSELECTOPTION Procedure](#).

### Syntax

```
HTP.FORMSELECTCLOSE;
```

### Examples

This procedure generates

```
</SELECT>
```

as shown under [Examples](#) of the [FORMSELECTOPEN Procedure](#).

## FORMSELECTOPEN Procedure

This procedure generates the <SELECT> tags which creates a Select form element. A Select form element is a listbox where the user selects one or more values. You mark the end of Select form element by means of the [FORMSELECTCLOSE Procedure](#). The values are inserted using [FORMSELECTOPTION Procedure](#).

### Syntax

```
FORMSELECTOPEN(
 cname IN VARCHAR2,
 cprompt IN VARCHAR2 DEFAULT NULL,
 nsize IN INTEGER DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–36 FORMSELECTOPEN Procedure Parameters**

Parameter	Description
cname	The value for the NAME attribute.
cprompt	The string preceding the list box.
nsize	The value for the SIZE attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
cprompt <SELECT NAME="cname" SIZE="nsize" cattributes>
</SELECT>
```

so that

```
HTP.FORMSELECTOPEN('greatest_player';
 'Pick the greatest player:');
HTP.FORMSELECTOPTION('Messier');
HTP.FORMSELECTOPTION('Howe');
HTP.FORMSELECTOPTION('Gretzky');
HTP.FORMSELECTCLOSE;
```

generates

```
Pick the greatest player:
<SELECT NAME="greatest_player">
<OPTION>Messier
<OPTION>Howe
<OPTION>Gretzky
</SELECT>
```



## FORMSELETOPTION Procedure

This procedure generates the <OPTION> tag which represents one choice in a Select element.

### Syntax

```
HTP.FORMSELETOPTION(
 cvalue IN VARCHAR2,
 cselected IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–37 FORMSELETOPTION Procedure Parameters**

Parameter	Description
cvalue	The text for the option.
cvalue	If the value for this parameter is not NULL, the SELECTED attribute is added to the tag.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<OPTION SELECTED cattributes>cvalue
```

as shown under [Examples](#) of the [FORMSELECTOPEN Procedure](#).

## FORMSUBMIT Procedure

This procedure generates the `<INPUT>` tag with `TYPE="submit"` which creates a button that, when clicked, submits the form. If the button has a `NAME` attribute, the button contributes a name/value pair to the submitted data.

### Syntax

```
HTP.FORMSUBMIT(
 cname IN VARCHAR2 DEFAULT NULL,
 cvalue IN VARCHAR2 DEFAULT 'Submit',
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–38 FORMSUBMIT Procedure Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="submit" NAME="cname" VALUE="cvalue" cattributes>
```

## FORMTEXT Procedure

This procedure generates the `<INPUT>` tag with `TYPE="text"`, which creates a field for a single line of text.

### Syntax

```
HTP.FORMTEXT(
 cname IN VARCHAR2,
 csize IN VARCHAR2 DEFAULT NULL,
 cmaxlength IN VARCHAR2 DEFAULT NULL,
 cvalue IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–39** *FORMTEXT Procedure Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>csize</code>	The value for the <code>SIZE</code> attribute.
<code>cmaxlength</code>	The value for the <code>MAXLENGTH</code> attribute.
<code>cvalue</code>	The value for the <code>VALUE</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<INPUT TYPE="text" NAME="cname" SIZE="csize" MAXLENGTH="cmmaxlength"
VALUE="cvalue" cattributes>
```

## FORMTEXTAREA Procedure

This procedure generates the `<TEXTAREA>` tag, which creates a text field that has no predefined text in the text area. This field enables entering several lines of text. The same operation is performed by the [FORMTEXTAREA2 Procedure](#) which in addition has the `cwrap` parameter that lets you specify a wrap style.

### Syntax

```
HTP.FORMTEXTAREA(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–40** *FORMTEXTAREA Procedure Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>nrows</code>	The value for the <code>ROWS</code> attribute. This is an integer.
<code>ncolumns</code>	The value for the <code>COLS</code> attribute. This is an integer.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign"
cattributes></TEXTAREA>
```

## FORMTEXTAREA2 Procedure

This procedure generates the <TEXTAREA> tag, which creates a text field that has no predefined text in the text area. This field enables entering several lines of text. The same operation is performed by the [FORMTEXTAREA Procedure](#) except that in that case you cannot specify a wrap style.

### Syntax

```
HTP.FORMTEXTAREA2(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–41** FORMTEXTAREA2 Procedure Parameters

Parameter	Description
cname	The value for the NAME attribute.
nrows	The value for the ROWS attribute. This is an integer.
ncolumns	The value for the COLS attribute. This is an integer.
calign	The value for the ALIGN attribute.
cwrap	The value for the WRAP attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign" WRAP="cwrap"
cattributes></TEXTAREA>
```

## FORMTEXTAREACLOSE Procedure

This procedure generates the `</TEXTAREA>` tag which ends a text area form element. You open a text area element by means of either [FORMTEXTAREAOPEN Procedure](#) or [FORMTEXTAREAOPEN2 Procedure](#).

### Syntax

```
HTP.FORMTEXTAREACLOSE;
```

### Examples

This procedure generates

```
</TEXTAREA>
```

## FORMTEXTAREAOPEN Procedure

This procedure generates the <TEXTAREA> which marks the beginning of a text area form element. The same operation is performed by the [FORMTEXTAREAOPEN2 Procedure](#) which in addition has the `cwrap` parameter that lets you specify a wrap style. You mark the end of a text area form element by means of the [FORMTEXTAREACLOSE Procedure](#).

### Syntax

```
HTP.FORMTEXTAREAOPEN(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–42 FORMTEXTAREAOPEN Procedure Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>nrows</code>	The value for the <code>ROWS</code> attribute. This is an integer.
<code>ncolumns</code>	The value for the <code>COLS</code> attribute. This is an integer.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign" cattributes>
```

## FORMTEXTAREAOPEN2 Procedure

This procedure generates the <TEXTAREA> which marks the beginning of a text area form element. The same operation is performed by the [FORMTEXTAREAOPEN Procedure](#) except that in that case you cannot specify a wrap style. You mark the end of a text area form element by means of the [FORMTEXTAREACLOSE Procedure](#).

### Syntax

```
HTP.FORMTEXTAREAOPEN2(
 cname IN VARCHAR2,
 nrows IN INTEGER,
 ncolumns IN INTEGER,
 calign IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–43** *FORMTEXTAREAOPEN2 Procedure Parameters*

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>nrows</code>	The value for the <code>ROWS</code> attribute. This is an integer.
<code>ncolumns</code>	The value for the <code>COLS</code> attribute. This is an integer.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cwrap</code>	The value for the <code>WRAP</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TEXTAREA NAME="cname" ROWS="nrows" COLS="ncolumns" ALIGN="calign" WRAP =
"cwrap" cattributes>
```



## FRAME Procedure

This procedure generates the <FRAME> tag which defines the characteristics of a frame created by a <FRAMESET> tag.

### Syntax

```
HTP.FRAME(
 csrc IN VARCHAR2,
 cname IN VARCHAR2 DEFAULT NULL,
 cmarginwidth IN VARCHAR2 DEFAULT NULL,
 cmarginheight IN VARCHAR2 DEFAULT NULL,
 cscrolling IN VARCHAR2 DEFAULT NULL,
 cnoresize IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–44** *FRAME Procedure Parameters*

Parameter	Description
csrc	The URL to display in the frame.
cname	The value for the NAME attribute.
cmarginwidth	The value for the MARGINWIDTH attribute.
cscrolling	The value for the SCROLLING attribute.
cnoresize	If the value for this parameter is not NULL, the NORESIZE attribute is added to the tag.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<FRAME SRC="csrc" NAME="cname" MARGINWIDTH="cmarginwidth"
MARGINHEIGHT="cmarginheight" SCROLLING="cscrolling" NORESIZE cattributes>
```

## FRAMESETCLOSE Procedure

This procedure generates the `</FRAMESET>` tag which ends a frameset section. You mark the beginning of a frameset section by means of the [FRAMESETOPEN Procedure](#).

### Syntax

```
HTP.FRAMESETCLOSE;
```

### Examples

This procedure generates

```
</FRAMESET>
```

## FRAMESETOPEN Procedure

This procedure generates the <FRAMESET> tag which define a frameset section. You mark the end of a frameset section by means of the [FRAMESETCLOSE Procedure](#).

### Syntax

```
HTP.FRAMESETOPEN(
 crows IN VARCHAR2 DEFAULT NULL,
 ccols IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–45** *FRAMESETOPEN Procedure Parameters*

Parameter	Description
crows	The value for the ROWS attribute.
ccols	The value for the COLS attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<FRAMESET ROWS="crows" COLS="ccols" cattributes>
```

## HEADCLOSE Procedure

This procedure generates the `</HEAD>` tag which marks the end of an HTML document head section. You mark the beginning of an HTML document head section by means of the [HEADOPEN Procedure](#).

### Syntax

```
HTP.HEADCLOSE;
```

### Examples

This procedure generates

```
</HEAD>
```

## HEADOPEN Procedure

This procedure generates the <HEAD> tag which marks the beginning of the HTML document head section. You mark the end of an HTML document head section by means of the [HEADCLOSE Procedure](#).

### Syntax

```
HTP.HEADOPEN;
```

### Examples

This procedure generates

```
<HEAD>
```

## HEADER Procedure

This procedure generates opening heading tags ( <H1> to <H6> ) and their corresponding closing tags ( </H1> to </H6> ).

### Syntax

```
HTP.HEADER(
 nsize IN INTEGER,
 cheader IN VARCHAR2,
 calign IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–46** *HEADER Procedure Parameters*

Parameter	Description
nsize	The the heading level. This is an integer between 1 and 6.
cheader	The text to display in the heading.
calign	The value for the ALIGN attribute.
cnowrap	The value for the NOWRAP attribute.
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

```
HTP.header (1, 'Overview');
```

produces:

```
<H1>Overview</H1>
```

## HR Procedure

This procedure generates the <HR> tag, which generates a line in the HTML document. This subprogram performs the same operation as the [LINE Procedure](#).

### Syntax

```
HTP.HR(
 cclear IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–47 HR Procedure Parameters**

Parameter	Description
<code>cclear</code>	The value for the CLEAR attribute.
<code>csrc</code>	The value for the SRC attribute which specifies a custom image as the source of the line.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<HR CLEAR="cclear" SRC="csrc" cattributes>
```

## HTMLCLOSE Procedure

This procedure generates the `</HTML>` tag which marks the end of an HTML document. You use the [HTMLOPEN Procedure](#) to mark the beginning of an HTML document.

### Syntax

```
HTP.HTMLCLOSE;
```

### Examples

This procedure generates

```
</HTML>
```



## HTMLOPEN Procedure

This procedure generates the <HTML> tag which marks the beginning of an HTML document. You use the [HTMLCLOSE Procedure](#) to mark the end of the an HTML document.

### Syntax

```
HTP.HTMLOPEN;
```

### Examples

This procedure generates

```
<HTML>
```

## IMG Procedure

This procedure generates the `<IMG>` tag which directs the browser to load an image onto the HTML page. The [IMG2 Procedure](#) performs the same operation but additionally uses the `cusemap` parameter.

### Syntax

```
HTP.IMG(
 curl IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 calt IN VARCHAR2 DEFAULT NULL,
 cismap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–48** *IMG Procedure Parameters*

Parameter	Description
<code>curl</code>	The value for the SRC attribute.
<code>calign</code>	The value for the ALIGN attribute.
<code>calt</code>	The value for the ALT attribute which specifies alternative text to display if the browser does not support images.
<code>cismap</code>	If the value for this parameter is not NULL, the ISMAP attribute is added to the tag. The attribute indicates that the image is an imagemap.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```

```

## IMG2 Procedure

This procedure generates the <IMG> tag, which directs the browser to load an image onto the HTML page. The [IMG Procedure](#) performs the same operation but does not use the `cusemap` parameter.

### Syntax

```
HTP.IMG2(
 curl IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 calt IN VARCHAR2 DEFAULT NULL,
 cismap IN VARCHAR2 DEFAULT NULL,
 cusemap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–49** *IMG2 Procedure Parameters*

Parameter	Description
<code>curl</code>	The value for the SRC attribute.
<code>calign</code>	The value for the ALIGN attribute.
<code>calt</code>	The value for the ALT attribute which specifies alternative text to display if the browser does not support images.
<code>cismap</code>	If the value for this parameter is not NULL, the ISMAP attribute is added to the tag. The attribute indicates that the image is an imagemap.
<code>cusemap</code>	The value for the USEMAP attribute which specifies a client-side image map.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```

```

## ISINDEX Procedure

This procedure creates a single entry field with a prompting text, such as "*enter value*," then sends that value to the URL of the page or program.

### Syntax

```
HTP.ISINDEX(
 cprompt IN VARCHAR2 DEFAULT NULL,
 curl IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–50 ISINDEX Procedure Parameters**

Parameter	Description
<code>cprompt</code>	The value for the PROMPT attribute.
<code>curl</code>	The value for the HREF attribute.

### Examples

This procedure generates

```
<ISINDEX PROMPT="cprompt" HREF="curl">
```

## ITALIC Procedure

This procedure generates the `<I>` and `</I>` tags which direct the browser to render the text in italics.

### Syntax

```
HTP.ITALIC(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–51** *ITALIC Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in italics.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<I cattributes>ctext</I>
```

## KBD Procedure

This procedure generates the `<KBD>` and `</KBD>` tags which direct the browser to render the text in monospace font. This subprogram performs the same operation as the [KEYBOARD Procedure](#).

### Syntax

```
HTP.KBD(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–52** *KBD Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in monospace.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<KBD cattributes>ctext</KBD>
```

## KEYBOARD Procedure

This procedure generates the <KBD> and </KBD> tags, which direct the browser to render the text in monospace font. This subprogram performs the same operation as the [KBD Procedure](#).

### Syntax

```
HTP.KEYBOARD(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–53** *KEYBOARD Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in monospace.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<KBD cattributes>ctext</KBD>
```

## LINE Procedure

This procedure generates the <HR> tag, which generates a line in the HTML document. This subprogram performs the same operation as the [HR Procedure](#).

### Syntax

```
HTP.LINE(
 cclear IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–54** *LINE Procedure Parameters*

Parameter	Description
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>csrc</code>	The value for the <code>SRC</code> attribute which specifies a custom image as the source of the line.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<HR CLEAR="cclear" SRC="csrc" cattributes>
```



## LINKREL Procedure

This procedure generates the `<LINK>` tag with the `REL` attribute which delineates the relationship described by the hypertext link from the anchor to the target. This is only used when the `HREF` attribute is present. This is the opposite of [LINKREV Procedure](#). This tag indicates a relationship between documents but does not create a link. To create a link, use the [ANCHOR Procedure](#).

### Syntax

```
HTP.LINKREL(
 crel IN VARCHAR2,
 curl IN VARCHAR2,
 ctitle IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–55** *LINKREL Procedure Parameters*

Parameter	Description
<code>crel</code>	The value for the <code>REL</code> attribute.
<code>curl</code>	The value for the <code>URL</code> attribute.
<code>ctitle</code>	The value for the <code>TITLE</code> attribute.

### Examples

This procedure generates

```
<LINK REL="crel" HREF="curl" TITLE="ctitle">
```

## LINKREV Procedure

This procedure generates the `<LINK>` tag with the `REV` attribute which delineates the relationship described by the hypertext link from the target to the anchor. This is the opposite of the [LINKREL Procedure](#). This tag indicates a relationship between documents, but does not create a link. To create a link, use the [ANCHOR Procedure](#).

### Syntax

```
HTP.LINKREV(
 crev IN VARCHAR2,
 curl IN VARCHAR2,
 ctitle IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–56 LINKREV Procedure Parameters**

Parameter	Description
<code>crel</code>	The value for the <code>REV</code> attribute.
<code>curl</code>	The value for the <code>URL</code> attribute.
<code>ctitle</code>	The value for the <code>TITLE</code> attribute.

### Examples

This procedure generates

```
<LINK REV="crev" HREF="curl" TITLE="ctitle">
```

## LISTHEADER Procedure

This procedure generates the <LH> and </LH> tags which print an HTML tag at the beginning of the list.

### Syntax

```
HTP.LISTHEADER(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–57 LISTHEADER Procedure Parameters**

Parameter	Description
ctext	The text to place between <LH> and </LH>.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<LH cattributes>ctext</LH>
```

## LISTINGCLOSE Procedure

This procedure generates the `</LISTING>` tags which marks the end of a section of fixed-width text in the body of an HTML page. To mark the beginning of a section of fixed-width text in the body of an HTML page, use the [LISTINGOPEN Procedure](#).

### Syntax

```
HTP.LISTINGCLOSE;
```

### Examples

This procedure generates

```
</LISTING>
```

## LISTINGOPEN Procedure

This procedure generates the `<LISTING>` tag which marks the beginning of a section of fixed-width text in the body of an HTML page. To mark the end of a section of fixed-width text in the body of an HTML page, use the [LISTINGCLOSE Procedure](#).

### Syntax

```
HTP.LISTINGOPEN;
```

### Examples

This procedure generates

```
<LISTING>
```

## LISTITEM Procedure

This procedure generates the `<LI>` tag, which indicates a list item.

### Syntax

```
HTP.LISTITEM(
 ctext IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cdingbat IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–58** LISTITEM Procedure Parameters

Parameter	Description
<code>ctext</code>	The text for the list item.
<code>cclear</code>	The value for the CLEAR attribute.
<code>cdingbat</code>	The value for the DINGBAT attribute.
<code>csrc</code>	The value for the SRC attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<LI CLEAR="cclear" DINGBAT="cdingbat" SRC="csrc" cattributes>ctext
```

## MAILTO Procedure

This procedure generates the <A> tag with the `HREF` set to 'mailto' prepended to the mail address argument.

### Syntax

```
HTP.MAILTO(
 caddress IN VARCHAR2,
 ctext IN VARCHAR2,
 cname IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–59 MAILTO Procedure Parameters**

Parameter	Description
<code>caddress</code>	The email address of the recipient.
<code>ctext</code>	The clickable portion of the link.
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
ctext
```

so that

```
HTP.mailto('pres@white_house.gov','Send Email to the President');
```

generates:

```
Send Email to the President
```

## MAPCLOSE Procedure

This procedure generates the `</MAP>` tag which marks the end of a set of regions in a client-side image map. To mark the beginning of a set of regions in a client-side image map, use the [MAOPEN Procedure](#).

### Syntax

```
HTP.MAPCLOSE;
```

### Examples

This procedure generates

```
</MAP>
```



## MAOPEN Procedure

This procedure generates the <MAP> tag which mark the beginning of a set of regions in a client-side image map. To mark the end of a set of regions in a client-side image map, use the [MAPCLOSE Procedure](#).

### Syntax

```
HTP.MAOPEN(
 cname IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–60 MAOPEN Procedure Parameters**

Parameter	Description
<code>cname</code>	The value for the <code>NAME</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<MAP NAME="cname" cattributes>
```

## MENULISTCLOSE Procedure

This procedure generates the `</MENU>` tag which ends a list that presents one line for each item. To begin a list of this kind, use the [MENULISTOPEN Procedure](#). The items in the list appear more compact than an unordered list. The [LISTITEM Procedure](#) defines the list items in a menu list.

### Syntax

```
HTP.MENULISTCLOSE;
```

### Examples

This procedure generates

```
</MENU>
```

## MENULISTOPEN Procedure

This procedure generates the <MENU> tag which create a list that presents one line for each item. To end a list of this kind, use the [MENULISTCLOSE Procedure](#). The items in the list appear more compact than an unordered list. The [LISTITEM Procedure](#) defines the list items in a menu list.

### Syntax

```
HTP.MENULISTOPEN;
```

### Examples

This procedure generates

```
<MENU>
```

## META Procedure

This procedure generates the <META> tag, which embeds meta-information about the document and also specifies values for HTTP headers. For example, you can specify the expiration date, keywords, and author name.

### Syntax

```
HTP.META(
 chttp_equiv IN VARCHAR2,
 cname IN VARCHAR2,
 ccontent IN VARCHAR2);
```

### Parameters

**Table 128–61 META Procedure Parameters**

Parameter	Description
chttp_equiv	The value for the CHTTP_EQUIV attribute.
cname	The value for the NAME attribute.
ccontent	The value for the CONTENT attribute.

### Examples

This procedure generates

```
<META HTTP-EQUIV="chttp_equiv" NAME ="cname" CONTENT="ccontent">
```

so that

```
HTP.meta ('Refresh', NULL, 120);
```

generates

```
<META HTTP-EQUIV="Refresh" CONTENT=120>
```

On some Web browsers, this causes the current URL to be reloaded automatically every 120 seconds.

## NL Procedure

This procedure generates the <BR> tag which begins a new line of text. It performs the same operation as the [BR Procedure](#).

### Syntax

```
HTP.NL(
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–62 NL Procedure Parameters**

Parameter	Description
cclear	The value for the CLEAR attribute.
cattributes	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<BR CLEAR="cclear" cattributes>
```

## NOBR Procedure

This procedure generates the `<NOBR>` and `</NOBR>` tags which turn off line-breaking in a section of text.

### Syntax

```
HTP.NOBR(
 ctext IN VARCHAR2);
```

### Parameters

**Table 128–63 NOBR Procedure Parameters**

Parameter	Description
<code>ctext</code>	The text that is to be rendered on one line.

### Examples

This procedure generates

```
<NOBR>ctext</NOBR>
```

## NOFRAMESCLOSE Procedure

This procedure generates the `</NOFRAMES>` tag which marks the end of a no-frames section. To mark the beginning of a no-frames section, use the [FRAMESETOPEN Procedure](#). See also [FRAME Procedure](#), [FRAMESETOPEN Procedure](#) and [FRAMESETCLOSE Procedure](#).

### Syntax

```
HTP.NOFRAMESCLOSE;
```

### Examples

This procedure generates

```
</NOFRAMES>
```

## NOFRAMESOPEN Procedure

This procedure generates the `<NOFRAMES>` tag which mark the beginning of a no-frames section. To mark the end of a no-frames section, use the [FRAMESETCLOSE Procedure](#). See also [FRAME Procedure](#), [FRAMESETOPEN Procedure](#) and [FRAMESETCLOSE Procedure](#).

### Syntax

```
HTP.NOFRAMESOPEN;
```

### Examples

This procedure generates

```
<NOFRAMES>
```



## OLISTCLOSE Procedure

This procedure generates the `</OL>` tag which defines the end of an ordered list. An ordered list presents a list of numbered items. To mark the beginning of a list of this kind, use the [OLISTOPEN Procedure](#). Numbered items are added using [LISTITEM Procedure](#).

### Syntax

```
HTP.OLISTCLOSE;
```

### Examples

This procedure generates

```

```

## OLISTOPEN Procedure

This procedure generates the `<OL>` tag which marks the beginning of an ordered list. An ordered list presents a list of numbered items. To mark the end of a list of this kind, use the [OLISTCLOSE Procedure](#). Numbered items are added using [LISTITEM Procedure](#).

### Syntax

```
HTP.OLISTOPEN(
 cclear IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–64 OLISTOPEN Procedure Parameters**

Parameter	Description
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cwrap</code>	The value for the <code>WRAP</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<OL CLEAR="cclear" WRAP="cwrap" cattributes>
```

## PARA Procedure

This procedure generates the `<P>` tag which indicates that the text that comes after the tag is to be formatted as a paragraph. You can add attributes to the tag by means of the [PARAGRAPH Procedure](#).

### Syntax

```
HTP.PARA;
```

### Examples

This procedure generates

```
<P>
```

## PARAGRAPH Procedure

You can use this procedure to add attributes to the <P> tag created by the [PARA Procedure](#).

### Syntax

```
HTP.PARAGRAPH(
 calign IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–65** PARAGRAPH Procedure Parameters

Parameter	Description
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cnowrap</code>	If the value for this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<P ALIGN="calign" NOWRAP CLEAR="cclear" cattributes>
```

## PARAM Procedure

This procedure generates the <PARAM> tag which specifies parameter values for Java applets. The values can reference HTML variables. To invoke a Java applet from a Web page, use [APPLETOPEN Procedure](#) to begin the invocation. Use one [PARAM Procedure](#) for each desired name-value pair, and use [APPLETCLOSE Procedure](#) to end the applet invocation.

### Syntax

```
HTP.PARAM(
 cname IN VARCHAR2
 cvalue IN VARCHAR2);
```

### Parameters

**Table 128–66** *PARAM Procedure Parameters*

Parameter	Description
cname	The value for the NAME attribute.
cvalue	The value for the VALUE attribute.

### Examples

This procedure generates

```
<PARAM NAME=cname VALUE="cvalue">
```

## PLAINTEXT Procedure

This procedure generates the `<PLAINTEXT>` and `</PLAINTEXT>` tags which direct the browser to render the text they surround in fixed-width type.

### Syntax

```
HTP.PLAINTEXT(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–67** *PLAINTEXT Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in fixed-width font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<PLAINTEXT cattributes>ctext</PLAINTEXT>
```

## PRECLOSE Procedure

This procedure generates the `</PRE>` tag which marks the end of a section of preformatted text in the body of the HTML page. To mark the beginning of a section of preformatted text in the body of the HTML page, use the [PREOPEN Procedure](#).

### Syntax

```
HTP.PRECLOSE;
```

### Examples

This procedure generates

```
</PRE>
```

## PREOPEN Procedure

This procedure generates the `<PRE>` tag which marks the beginning of a section of preformatted text in the body of the HTML page. To mark the end of a section of preformatted text in the body of the HTML page, use the [PRECLOSE Procedure](#).

### Syntax

```
HTP.PREOPEN(
 cclear IN VARCHAR2 DEFAULT NULL,
 cwidth IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–68** *PREOPEN Procedure Parameters*

Parameter	Description
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cwidth</code>	The value for the <code>WIDTH</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<PRE CLEAR="cclear" WIDTH="cwidth" cattributes>
```



## PRINT Procedures

These procedures generate the specified parameter as a string terminated with the `\n` newline character. The [PRN Procedures](#) performs the same operation but does not terminate with a newline character.

### Syntax

```
HTP.PRINT (
 cbuf IN VARCHAR2);
```

```
HTP.PRINT (
 dbuf IN DATE);
```

```
HTP.PRINT (
 nbuf IN NUMBER);
```

### Parameters

**Table 128–69 PRINT Procedure Parameters**

Parameter	Description
cbuf	The string to generate terminated by a newline.
dbuf	The string to generate terminated by a newline.
nbuf	The string to generate terminated by a newline.

### Usage Notes

- The `\n` character is not the same as `<BR>`. The `\n` character formats the HTML source but it does not affect how the browser renders the HTML source. Use `<BR>` to control how the browser renders the HTML source.
- These procedures do not have function equivalents.

## PRINTS Procedure

This procedure generates a string and replaces the following characters with the corresponding escape sequence.

- `<` to `&lt;`
- `>` to `&gt;`
- `"` to `&quot;`
- `&` to `&amp;`

If not replaced, the special characters are interpreted as HTML control characters and produce garbled output. This procedure and the [PS Procedure](#) perform the same operation as the [PRN Procedures](#) but with character substitution.

### Syntax

```
HTP.PRINTS (
 ctext IN VARCHAR2);
```

### Parameters

**Table 128–70 PRINTS Procedure Parameters**

Parameter	Description
<code>ctext</code>	The string where to perform character substitution.

### Usage Notes

This procedure does not have an HTF function equivalent (see [Operational Notes](#) on page 128-2 for the HTF implementation).

## PRN Procedures

These procedures generate the specified parameter as a string. Unlike the [PRINT Procedures](#) the string is not terminated with the \n newline character.

### Syntax

```
HTP.PRN (
 cbuf IN VARCHAR2);
```

```
HTP.PRN (
 dbuf IN DATE);
```

```
HTP.PRN (
 nbuf IN NUMBER);
```

### Parameters

**Table 128–71** PRN Procedure Parameters

Parameter	Description
cbuf	The string to generate (not terminated by a newline).
dbuf	The string to generate (not terminated by a newline).
nbuf	The string to generate (not terminated by a newline).

### Usage Notes

These procedures do not have function equivalents.

## PS Procedure

This procedure generates a string and replaces the following characters with the corresponding escape sequence.

- `<` to `&lt;`
- `>` to `&gt;`
- `"` to `&quot;`
- `&` to `&amp;`

If not replaced, the special characters are interpreted as HTML control characters and produce garbled output. This procedure and the [PRINTS Procedure](#) perform the same operation as the [PRN Procedures](#) but with character substitution.

### Syntax

```
HTP.PS (
 ctext IN VARCHAR2);
```

### Parameters

**Table 128–72 PS Procedure Parameters**

Parameter	Description
<code>ctext</code>	The string where to perform character substitution.

### Usage Notes

This procedure does not have an HTF function equivalent (see [Operational Notes](#) on page 128-2 for the HTF implementation).

## S Procedure

This procedure generates the `<S>` and `</S>` tags which direct the browser to render the text they surround in strikethrough type. This performs the same operation as [STRIKE Procedure](#).

### Syntax

```
HTP.S (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–73 S Procedure Parameters**

Parameter	Description
<code>ctext</code>	The text to be rendered in strikethrough type.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<S cattributes>ctext</S>
```

## SAMPLE Procedure

This procedure generates the `<SAMP>` and `</SAMP>` tags which direct the browser to render the text they surround in monospace font or however "sample" is defined stylistically.

### Syntax

```
HTP.SAMPLE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–74** *SAMPLE Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in monospace font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<SAMP cattributes>ctext</SAMP>
```

## SCRIPT Procedure

This procedure generates the `<SCRIPT>` and `</SCRIPT>` tags which contain a script written in languages such as JavaScript and VBScript.

### Syntax

```
HTP.SCRIPT (
 cscript IN VARCHAR2,
 clanguage IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–75** *SCRIPT Procedure Parameters*

Parameter	Description
<code>cscript</code>	The text of the script. This is the text that makes up the script itself, not the name of a file containing the script.
<code>clanguage</code>	The language in which the script is written. If this parameter is omitted, the user's browser determines the scripting language.

### Examples

This procedure generates

```
<SCRIPT LANGUAGE=clanguage>cscript</SCRIPT>
```

so that

```
HTP.script ('Erupting_Volcano', 'Javascript');
```

generates

```
<SCRIPT LANGUAGE=Javascript>"script text here"</SCRIPT>
```

This causes the browser to run the script enclosed in the tags.

## SMALL Procedure

This procedure generates the `<SMALL>` and `</SMALL>` tags, which direct the browser to render the text they surround using a small font.

### Syntax

```
HTP.SMALL (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–76** *SMALL Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in small font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<SMALL cattributes>ctext</SMALL>
```



## STRIKE Procedure

This procedure generates the `<STRIKE>` and `</STRIKE>` tags which direct the browser to render the text they surround in strikethrough type. This performs the same operation as [S Procedure](#).

### Syntax

```
HTP.STRIKE (
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–77** *STRIKE Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be rendered in strikethrough type.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<STRIKE cattributes>ctext</STRIKE>
```

## STRONG Procedure

This procedure generates the `<STRONG>` and `</STRONG>` tags which direct the browser to render the text they surround in bold or however "strong" is defined.

### Syntax

```
HTP.STRONG(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–78** *STRONG Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to be emphasized.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<STRONG cattributes>ctext
```

## STYLE Procedure

This procedure generates the `<STYLE>` and `</STYLE>` tags which include a style sheet in a Web page. You can get more information about style sheets at <http://www.w3.org>. This feature is not compatible with browsers that support only HTML versions 2.0 or earlier. Such browsers will ignore this tag.

### Syntax

```
HTP.STYLE(
 cstyle IN VARCHAR2);
```

### Parameters

**Table 128–79** *STYLE Procedure Parameters*

Parameter	Description
<code>cstyle</code>	The the style information to include.

### Examples

This procedure generates

```
<STYLE>cstyle</STYLE>
```

## SUB Procedure

This procedure generates the `<SUB>` and `</SUB>` tags which direct the browser to render the text they surround as subscript.

### Syntax

```
HTP.SUB(
 ctext IN VARCHAR2,
 calign in VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–80 SUB Procedure Parameters**

Parameter	Description
<code>ctext</code>	The text to render in subscript.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
_{ctext}
```

## SUP Procedure

This procedure generates the `<SUP>` and `</SUP>` tags which direct the browser to render the text they surround as superscript.

### Syntax

```
HTP.SUP(
 ctext IN VARCHAR2,
 calign in VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–81** *SUP Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to render in superscript.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
^{ctext}
```

## TABLECAPTION Procedure

This procedure generates the `<CAPTION>` and `</CAPTION>` tags which place a caption in an HTML table.

### Syntax

```
HTP.TABLECAPTION(
 ccaption IN VARCHAR2,
 calign in VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–82 TABLECAPTION Procedure Parameters**

Parameter	Description
<code>cctx</code>	The text for the caption.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<CAPTION ALIGN="calign" cattributes>cctx</CAPTION>
```

## TABLEDATA Procedure

This procedure generates the `<TD>` and `</TD>` tags which insert data into a cell of an HTML table.

### Syntax

```
HTP.TABLEDATA(
 cvalue IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 cdp IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 crowspan IN VARCHAR2 DEFAULT NULL,
 ccolspan IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–83 TABLEDATA Procedure Parameters**

Parameter	Description
<code>cvalue</code>	The data for the cell in the table.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cdp</code>	The value for the <code>DP</code> attribute.
<code>cnowrap</code>	If the value of this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>ccolspan</code>	The value for the <code>COLSPAN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TD ALIGN="calign" DP="cdp" ROWSPAN="crowspan" COLSPAN="ccolspan" NOWRAP
cattributes>cvalue</TD>
```

## TABLEHEADER Procedure

This procedure generates the `<TH>` and `</TH>` tags which insert a header cell in an HTML table. The `<TH>` tag is similar to the `<TD>` tag except that the text in this case the rows are usually rendered in bold type.

### Syntax

```
HTP.TABLEHEADER(
 cvalue IN VARCHAR2 DEFAULT NULL,
 calign IN VARCHAR2 DEFAULT NULL,
 cdp IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 crowspan IN VARCHAR2 DEFAULT NULL,
 ccolspan IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–84** TABLEHEADER Procedure Parameters

Parameter	Description
<code>cvalue</code>	The data for the cell in the table.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cdp</code>	The value for the <code>DP</code> attribute.
<code>cnowrap</code>	If the value of this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>crispen</code>	The value for the <code>ROWSPAN</code> attribute.
<code>ccolspan</code>	The value for the <code>COLSPAN</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TH ALIGN="calign" DP="cdp" ROWSPAN="crowspan" COLSPAN="ccolspan" NOWRAP
cattributes>cvalue</TH>
```



## TABLECLOSE Procedure

This procedure generates the `</TABLE>` tag which marks the end of an HTML table. To define the beginning of an HTML table, use the [TABLEOPEN Procedure](#).

### Syntax

```
HTP.TABLECLOSE;
```

### Examples

This procedure generates

```
</TABLE>
```

## TABLEOPEN Procedure

This procedure generates the <TABLE> tag which marks the beginning of an HTML table. To define the end of an HTML table, use the [TABLECLOSE Procedure](#).

### Syntax

```
HTP.TABLEOPEN(
 cborder IN VARCHAR2 DEFAULT NULL
 calign IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cclear IN VARCHAR2 DEFAULT NULL
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–85** TABLEOPEN Procedure Parameters

Parameter	Description
<code>border</code>	The value for the <code>BORDER</code> attribute.
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cnowrap</code>	If the value of this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TABLE "cborder" NOWRAP ALIGN="calign" CLEAR="cclear" cattributes>
```

## TABLEROWCLOSE Procedure

This procedure generates the `</TR>` tag which marks the end of a new row in an HTML table. To mark the beginning of a new row, use the [TABLEROWOPEN Procedure](#).

### Syntax

```
HTP.TABLEROWCLOSE;
```

### Examples

This procedure generates

```
</TABLE>
```

## TABLEROWOPEN Procedure

This procedure generates the `<TR>` tag which marks the beginning of a new row in an HTML table. To mark the end of a new row, use the [TABLEROWCLOSE Procedure](#).

### Syntax

```
HTP.TABLEROWOPEN(
 calign IN VARCHAR2 DEFAULT NULL,
 cvalign IN VARCHAR2 DEFAULT NULL,
 cdp IN VARCHAR2 DEFAULT NULL,
 cnowrap IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–86** *TABLEROWOPEN Procedure Parameters*

Parameter	Description
<code>calign</code>	The value for the <code>ALIGN</code> attribute.
<code>cvalign</code>	The value for the <code>VALIGN</code> attribute.
<code>cdp</code>	The value for the <code>DP</code> attribute.
<code>cnowrap</code>	If the value of this parameter is not <code>NULL</code> , the <code>NOWRAP</code> attribute is added to the tag.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<<TR ALIGN="calign" VALIGN="cvalign" DP="cdp" NOWRAP cattributes>
```

## TELETYPE Procedure

This procedure generates the `<TT>` and `</TT>` tags which direct the browser to render the text they surround in a fixed width typewriter font, for example, the courier font.

### Syntax

```
HTP.TELETYPE(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–87 TELETYPE Procedure Parameters**

Parameter	Description
<code>ctext</code>	The text to render in a fixed width typewriter font.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<TT cattributes>ctext</TT>
```

## TITLE Procedure

This procedure generates the `<TITLE>` and `</TITLE>` tags which specify the text to display in the titlebar of the browser window.

### Syntax

```
HTP.TITLE(
 ctitle IN VARCHAR2);
```

### Parameters

**Table 128–88** *TITLE Procedure Parameters*

Parameter	Description
<code>ctitle</code>	The text to display in the titlebar of the browser window.

### Examples

This procedure generates

```
<TITLE>ctitle</TITLE>
```

## ULISTCLOSE Procedure

This procedure generates the `</UL>` tag which marks the end of an unordered list. An unordered list presents items with bullets. To mark the beginning of an unordered list, use the [ULISTOPEN Procedure](#). Add list items with [LISTITEM Procedure](#).

### Syntax

```
HTP.ULISTCLOSE;
```

### Examples

This procedure generates

```
</TABLE>
```

## ULISTOPEN Procedure

This procedure generates the `<UL>` tag which marks the beginning of an unordered list. An unordered list presents items with bullets. To mark the end of an unordered list, use the [ULISTCLOSE Procedure](#). Add list items with [LISTITEM Procedure](#).

### Syntax

```
HTP.ULISTOPEN(
 cclear IN VARCHAR2 DEFAULT NULL,
 cwrap IN VARCHAR2 DEFAULT NULL,
 cdingbat IN VARCHAR2 DEFAULT NULL,
 csrc IN VARCHAR2 DEFAULT NULL,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–89** *ULISTOPEN Procedure Parameters*

Parameter	Description
<code>cclear</code>	The value for the <code>CLEAR</code> attribute.
<code>cwrap</code>	The value for the <code>WRAP</code> attribute.
<code>cdingbat</code>	The value for the <code>DINGBAT</code> attribute.
<code>csrc</code>	The value for the <code>SRC</code> attribute.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<UL CLEAR="cclear" WRAP="cwrap" DINGBAT="cdingbat" SRC="csrc" cattributes>
```



## UNDERLINE Procedure

This procedure generates the `<U>` and `</U>` tags, which direct the browser to render the text they surround with an underline.

### Syntax

```
HTP.UNDERLINE(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–90** *UNDERLINE Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to render with an underline.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<U cattributes>ctext</U>
```

## VARIABLE Procedure

This procedure generates the `<VAR>` and `</VAR>` tags which direct the browser to render the text they surround in italics or however "variable" is defined stylistically.

### Syntax

```
HTP.VARIABLE(
 ctext IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 128–91** *VARIABLE Procedure Parameters*

Parameter	Description
<code>ctext</code>	The text to render in italics.
<code>cattributes</code>	The other attributes to be included as-is in the tag.

### Examples

This procedure generates

```
<VAR cattributes>ctext</VAR>
```

## WBR Procedure

This procedure generates the <WBR> tag, which inserts a soft line break within a section of NOBR text.

### Syntax

```
HTP.WBR ;
```

### Examples

This procedure generates

```
<WBR>
```



The `OWA_CACHE` package provides an interface that enables the PL/SQL Gateway cache to improve the performance of PL/SQL web applications.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using OWA\\_CACHE](#)
- [Summary of OWA\\_CACHE Subprograms](#)

---

## Using OWA\_CACHE

- [Constants](#)

### Constants

- `system_level CONSTANT VARCHAR(6) := 'SYSTEM' ;`
- `user_level CONSTANT VARCHAR(4) := 'USER' ;`

---

## Summary of OWA\_CACHE Subprograms

**Table 129–1 OWA\_CACHE Package Subprograms**

Subprogram	Description
<a href="#">DISABLE Procedure</a> on page 129-4	Disables the cache for this particular request
<a href="#">GET_ETAG Function</a> on page 129-5	Returns the tag associated with the cached content (used in the Validation technique model only)
<a href="#">GET_LEVEL Function</a> on page 129-6	Returns the caching level (used in the Validation technique model only)
<a href="#">SET_CACHE Procedure</a> on page 129-7	Sets up the cache headers for validation model cache type
<a href="#">SET_EXPIRES Procedure</a> on page 129-8	Sets up the cache headers for expires model cache type
<a href="#">SET_NOT_MODIFIED Procedure</a> on page 129-9	Sets up the headers for a not modified cache hit (used in the Validation technique model only)
<a href="#">SET_SURROGATE_CONTROL Procedure</a> on page 129-10	Sets up the headers for a surrogate-control header for web cache

## DISABLE Procedure

This procedure disables the cache for this particular request.

### Syntax

```
OWA_CACHE.DISABLE;
```



## GET\_ETAG Function

This function returns the tag associated with the cached content. It is used in the Validation technique only.

### Syntax

```
OWA_CACHE.GET_ETAG
RETURN VARCHAR2;
```

### Return Values

The tag for cache hit, otherwise NULL.

## GET\_LEVEL Function

This returns the caching level. It is used in the Validation technique model only.

### Syntax

```
OWA_CACHE.GET_LEVEL
RETURN VARCHAR2;
```

### Return Values

The caching level string ('USER' or 'SYSTEM') for cache hit, otherwise NULL.

## SET\_CACHE Procedure

This sets up the cache headers for validation model cache type.

### Syntax

```
OWA_CACHE.SET_CACHE(
 p_etag IN VARCHAR2,
 p_level IN VARCHAR2);
```

### Parameters

**Table 129–2** SET\_CACHE Procedure Parameters

Parameter	Description
p_etag	The etag associated with this content
p_level	The caching level ('USER' or 'SYSTEM').

### Exceptions

VALUE\_ERROR is thrown if

- p\_etag is greater than 55
- p\_level is not 'USER' or 'SYSTEM'

## SET\_EXPIRES Procedure

This procedure sets up the cache headers for expires model cache type.

### Syntax

```
OWA_CACHE.SET_EXPIRES(
 p_expires IN NUMBER,
 p_level IN VARCHAR2);
```

### Parameters

**Table 129–3 SET\_EXPIRES Procedure Parameters**

Parameter	Description
p_expires	The number of minutes this content is valid.
p_level	The caching level ('USER' or 'SYSTEM').

### Exceptions

VALUE\_ERROR is thrown if

- p\_expires is negative or zero
- p\_level is not 'USER' or 'SYSTEM'
- p\_expires is > 525600 (1 year)

## SET\_NOT\_MODIFIED Procedure

This procedure sets up the headers for a not-modified cache hit. It is used in the Validation technique only.

### Syntax

```
OWA_CACHE.SET_NOT_MODIFIED;
```

### Exceptions

VALUE\_ERROR is thrown if If the `etag` was not passed in

## SET\_SURROGATE\_CONTROL Procedure

This procedure sets the headers for a surrogate-control header for web cache

### Syntax

```
OWA_CACHE.SET_SURROGATE_CONTROL(
 p_value IN VARCHAR2);
```

### Parameters

**Table 129–4** *SET\_SURROGATE\_CONTROL Procedure Parameters*

Parameter	Description
p_value	The value to be passed as the Surrogate-Control header.

### Exceptions

VALUE\_ERROR is thrown if If p\_value is greater than 55 in length.

The OWA\_COOKIE package provides an interface for sending and retrieving HTTP cookies from the client's browser.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using OWA\\_COOKIE](#)
  - [Overview](#)
  - [Types](#)
  - [Rules and Limits](#)
- [Summary of OWA\\_COOKIE Subprograms](#)

## Using OWA\_COOKIE

- [Overview](#)
- [Types](#)
- [Rules and Limits](#)

### Overview

Cookies are opaque strings sent to the browser to maintain state between HTTP calls. State can be maintained throughout the client's sessions, or longer if an expiration date is included. The system date is calculated with reference to the information specified in the OWA\_CUSTOM package.

### Types

This data type contains cookie name-value pairs. Since the HTTP standard allows cookie names to be overloaded (that is, multiple values can be associated with the same cookie name), there is a PL/SQL `RECORD` holding all values associated with a given cookie name.

```
TYPE vc_arr IS TABLE OF VARCHAR2(4000) INDEX BY BINARY_INTEGER.
```

```
TYPE COOKIE IS RECORD (
 name VARCHAR2(4000),
 vals vc_arr,
 num_vals INTEGER);
```

### Rules and Limits

All HTTP headers must be in English and the ASCII character set. If the headers are generated from the database, verify they are created in the English language.



## Summary of OWA\_COOKIE Subprograms

*Table 130–1 OWA\_COOKIE Package Subprograms*

<b>Subprogram</b>	<b>Description</b>
<a href="#">GET Function</a> on page 130-4	Gets the value of the specified cookie
<a href="#">GET_ALL Procedure</a> on page 130-5	Gets all cookie name-value pairs
<a href="#">REMOVE Procedure</a> on page 130-6	Removes the specified cookie
<a href="#">SEND procedure</a> on page 130-7	Generates a "Set-Cookie" line in the HTTP header

## GET Function

This function returns the values associated with the specified cookie. The values are returned in a `OWA_COOKIE.COOKIE` DATA TYPE.

### Syntax

```
OWA_COOKIE.GET(
 name IN VARCHAR2)
RETURN COOKIE;
```

### Parameters

**Table 130–2** *GET Procedure Parameters*

Parameter	Description
name	The name of the cookie.

### Return Values

`OWA_COOKIE.COOKIE` DATA TYPE.

## GET\_ALL Procedure

This procedure returns all cookie names and their values from the client's browser. The values appear in the order in which they were sent from the browser.

### Syntax

```
OWA_COOKIE.GET_ALL(
 names OUT vc_arr,
 vals OUT vc_arr,
 num_vals OUT INTEGER);
```

### Parameters

**Table 130–3** *GET\_ALL Procedure Parameters*

Parameter	Description
names	The names of the cookies.
vals	The values of the cookies.
num_vals	The number of cookie-value pairs.

## REMOVE Procedure

This procedure forces a cookie to expire immediately by setting the "expires" field of a Set-Cookie line in the HTTP header to "01-Jan-1990". This procedure must be called within the context of an HTTP header.

### Syntax

```
OWA_COOKIE.REMOVE(
 name IN VARCHAR2,
 val IN VARCHAR2,
 path IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 130–4 REMOVE Procedure Parameters**

Parameter	Description
name	The name of the cookie to expire.
val	The value of the cookie.
path	[Currently unused]

## SEND procedure

This procedure generates a Set-Cookie line, which transmits a cookie to the client. This procedure must occur in the context of an HTTP header.

### Syntax

```
OWA_COOKIE.SEND(
 name in varchar2,
 value in varchar2,
 expires in date DEFAULT NULL,
 path in varchar2 DEFAULT NULL,
 domain in varchar2 DEFAULT NULL,
 secure in varchar2 DEFAULT NULL);
```

### Parameters

**Table 130–5 SEND Procedure Parameters**

<b>Parameter</b>	<b>Description</b>
name	The name of the cookie.
value	The value of the cookie.
expires	The date at which the cookie will expire
path	The value for the path field.
domain	The value for the domain field.
secure	If the value of this parameter is not NULL, the "secure" field is added to the line.



The `OWA_CUSTOM` package provides a Global PLSQL Agent Authorization callback function. It is used when PLSQL Agent's authorization scheme is set to `GLOBAL` or `CUSTOM` when there is no overriding `OWA_CUSTOM` package.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using OWA\\_CUSTOM](#)
  - [Constants](#)
- [Summary of OWA\\_CUSTOM Subprograms](#)

---

## Using OWA\_CUSTOM

- [Constants](#)

### Constants

- `dbms_server_timezone` CONSTANT VARCHAR2(3) := 'PST';
- `dbms_server_gmtdiff` CONSTANT NUMBER := NULL;



## Summary of OWA\_CUSTOM Subprograms

*Table 131-1 OWA\_CUSTOM Package Subprograms*

<b>Subprogram</b>	<b>Description</b>
<a href="#">AUTHORIZE Function</a> on page 131-4	Provides a Global PLSQL Agent Authorization callback function

## AUTHORIZE Function

This function is used when PLSQL Agent's authorization scheme is set to GLOBAL or CUSTOM when there is no overriding OWA\_CUSTOM package.

### Syntax

```
OWA_CUSTOM.AUTHORIZE
 RETURN BOOLEAN;
```

The `OWA_IMAGE` package provides an interface to access the coordinates where a user clicked on an image.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using OWA\\_IMAGE](#)
  - [Overview](#)
  - [Types](#)
  - [Variables](#)
  - [Examples](#)
- [Summary of OWA\\_IMAGE Subprograms](#)

---

## Using OWA\_IMAGE

- [Overview](#)
- [Types](#)
- [Variables](#)
- [Examples](#)

### Overview

Use this package when you have any image map whose destination links invoke the PL/SQL Gateway.

### Types

This data type (`point`) contain the X and Y values of a coordinate, and so provides the coordinates of a user's click on an imagemap. It is defined as:

```
TYPE POINT IS TABLE OF VARCHAR2(32767) INDEX BY BINARY_INTEGER
```

### Variables

This package variable (`null_point`) of `TYPE POINT` is used to default point parameters. Both the X and the Y fields of this variable are `NULL`.

### Examples

```
CREATE OR REPLACE PROCEDURE process_image
 (my_img in OWA_IMAGE.POINT)
AS
 x integer := OWA_IMAGE.GET_X(my_img);
 y integer := OWA_IMAGE.GET_Y(my_img);
BEGIN
 /* process the coordinate */
END
```

---

## Summary of OWA\_IMAGE Subprograms

*Table 132-1 OWA\_IMAGE Package Subprograms*

<b>Subprogram</b>	<b>Description</b>
<a href="#">GET_X Function</a> on page 132-4	Gets the X value of a point type
<a href="#">GET_Y Function</a> on page 132-5	Gets the Y value of a point type

---

## GET\_X Function

This function returns the x coordinate of the point where the user clicked on an image map.

### Syntax

```
OWA_IMAGE.GET_X(
 p IN point)
RETURN INTEGER;
```

### Parameters

**Table 132–2** *GET\_X Procedure Parameters*

Parameter	Description
p	The point where the user clicked.

### Return Values

The X coordinate as an integer.

## GET\_Y Function

This function returns the Y coordinate of the point where the user clicked on an image map.

### Syntax

```
OWA_IMAGE.GET_Y(
 p IN point)
RETURN INTEGER;
```

### Parameters

**Table 132–3** *GET\_Y Procedure Parameters*

Parameter	Description
p	The point where the user clicked.

### Return Values

The Y coordinate as an integer.





---

## OWA\_OPT\_LOCK

The `OWA_OPT_LOCK` package contains subprograms that impose optimistic locking strategies so as to prevent lost updates.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

This chapter contains the following topics:

- [Using OWA\\_OPT\\_LOCK](#)
  - [Overview](#)
  - [Types](#)
- [Summary of OWA\\_OPT\\_LOCK Subprograms](#)

## Using OWA\_OPT\_LOCK

- [Overview](#)
- [Types](#)

### Overview

The OWA\_OPT\_LOCK package contains subprograms that impose optimistic locking strategies, so as to prevent lost updates.

It checks if the row that the user is interested in updating has been changed by someone else in the meantime.

The PL/SQL Gateway cannot use conventional database locking schemes because HTTP is a stateless protocol. The OWA\_OPT\_LOCK package gives you two ways of dealing with the lost update problem:

- The hidden fields method stores the previous values in hidden fields in the HTML page. When the user requests an update, the PL/SQL Gateway checks these values against the current state of the database. The update operation is performed only if the values match. To use this method, call the `owa_opt_lock.store_values` procedure.
- The checksum method stores a checksum rather than the values themselves. To use this method, call the `owa_opt_lock.checksum` function.

These methods are optimistic. They do not prevent other users from performing updates, but they do reject the current update if an intervening update has occurred.

### Types

This data type is a PL/SQL table intended to hold ROWIDs.

```
TYPE VCARRAY IS TABLE OF VARCHAR2(2000) INDEX BY BINARY_INTEGER
```

Note that this is different from the `OWA_TEXT.VC_ARR` DATA TYPE.

## Summary of OWA\_OPT\_LOCK Subprograms

*Table 133-1 OWA\_CACHE Package Subprograms*

<b>Subprogram</b>	<b>Description</b>
<a href="#">CHECKSUM Functions</a> on page 133-4	Returns the checksum value
<a href="#">GET_ROWID Function</a> on page 133-5	Returns the ROWID value
<a href="#">STORE_VALUES Procedure</a> on page 133-6	Stores unmodified values in hidden fields for later verification
<a href="#">VERIFY_VALUES Function</a> on page 133-7	Verifies the stored values against modified values

## CHECKSUM Functions

This function returns a `checksum` value for a specified string, or for a row in a table. For a row in a table, the function calculates the `checksum` value based on the values of the columns in the row. This function comes in two versions.

The first version returns a `checksum` based on the specified string. This is a "pure" 32-bit `checksum` executed by the database and based on the Internet 1 protocol.

The second version returns a `checksum` based on the values of a row in a table. This is a "impure" 32-bit `checksum` based on the Internet 1 protocol.

### Syntax

```
OWA_OPT_LOCK.CHECKSUM(
 p_buff IN VARCHAR2)
 RETURN NUMBER;
```

```
OWA_OPT_LOCK.CHECKSUM(
 p_owner IN VARCHAR2,
 p_tname IN VARCHAR2,
 p_rowid IN ROWID)
 RETURN NUMBER;
```

### Parameters

**Table 133–2** *CHECKSUM Procedure Parameters*

Parameter	Description
<code>p_buff</code>	The nstring where you want to calculate the <code>checksum</code> .
<code>p_owner</code>	The owner of the table.
<code>p_tname</code>	The table name.
<code>p_rowid</code>	The row in <code>p_tname</code> where you want to calculate the <code>checksum</code> value. Use the <a href="#">GET_ROWID Function</a> to convert VCARRAY values to proper rowids.

## GET\_ROWID Function

This function returns the ROWID data type from the specified OWA\_OPT\_LOCK.VCARRAY DATA TYPE.

### Syntax

```
OWA_OPT_LOCK.GET_ROWID(
 p_old_values IN varray)
RETURN ROWID;
```

### Parameters

**Table 133–3** *GET\_ROWID Procedure Parameters*

Parameter	Description
p_old_values	This parameter is usually passed in from an HTML form.

## STORE\_VALUES Procedure

This procedure stores the column values of the row that you want to update later. The values are stored in hidden HTML form elements.

### Syntax

```
OWA_OPT_LOCK.STORE_VALUES(
 p_owner IN VARCHAR2,
 p_tname IN VARCHAR2,
 p_rowid IN ROWID);
```

### Parameters

**Table 133–4** STORE\_VALUES Procedure Parameters

Parameter	Description
p_owner	The owner of the table.
p_tname	The name of the table.
p_rowid	The row where you want to store values.

### Usage Notes

Before updating the row, compare these values with the current row values to ensure that the values in the row have not been changed. If the values have changed, you can warn the users and let them decide if the update should take place.

The procedure generates series of hidden form elements:

- One hidden form element is created for the table owner. The name of the element is "old\_p\_tname", where p\_tname is the name of the table. The value of the element is the owner name.
- One hidden form element is created for the table name. The name of the element is "old\_p\_tname", where p\_tname is the name of the table. The value of the element is the table name.
- One element is created for each column in the row. The name of the element is "old\_p\_tname", where p\_tname is the name of the table. The value of the element is the column value.

See also the [VERIFY\\_VALUES Function](#).

## VERIFY\_VALUES Function

This function verifies whether values in the specified row have been updated since the last query. Use this function with the [STORE\\_VALUES Procedure](#).

### Syntax

```
OWA_OPT_LOCK.VERIFY_VALUES(
 p_old_values IN varray)
RETURN BOOLEAN;
```

### Parameters

**Table 133–5** *VERIFY\_VALUES Procedure Parameters*

Parameter	Description
p_old_values	<p>A PL/SQL table containing the following information:</p> <ul style="list-style-type: none"> <li>▪ p_old_values(1) specifies the owner of the table.</li> <li>▪ p_old_values(2) specifies the table.</li> <li>▪ p_old_values(3) specifies the rowid of the row to verify.</li> </ul> <p>The remaining indexes contain values for the columns in the table.</p> <p>Typically, this parameter is passed in from the HTML form, where you have previously called the <a href="#">STORE_VALUES Procedure</a> to store the row values on hidden form elements.</p>

### Return Values

TRUE if no other update has been performed, otherwise FALSE.





---

---

## OWA\_PATTERN

The OWA\_PATTERN package provides an interface to locate text patterns within strings and replace the matched string with another string.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using OWA\\_PATTERN](#)
  - [Types](#)
  - [Operational Notes](#)
- [Summary of OWA\\_PATTERN Subprograms](#)

## Using OWA\_PATTERN

- [Types](#)
- [Operational Notes](#)

### Types

You can use a pattern as both an input and output parameter. Thus, you can pass the same regular expression to OWA\_PATTERN function calls, and it only has to be parsed once.

- `OWA_PATTERN.PATTERN`

### Operational Notes

The OWA\_PATTERN subprograms are overloaded. Specifically, there are six versions of MATCH, and four each of AMATCH and CHANGE. The subprograms use the following parameters:

- `line` - This is the target to be examined for a match. It can be more than one line of text or a `owa_text.multi_line` data type.
- `pat` - This is the pattern that the subprograms attempt to locate in line. The pattern can contain regular expressions. In the `owa_pattern.change` function and procedure, this parameter is called `from_str`.
- `flags` - This specifies whether the search is case-sensitive or if substitutions are done globally.

Use regular expressions with the subprograms in this package. You Specify a regular expression by creating the string you want to match interspersed with various wildcard tokens and quantifiers.

- [Wildcards](#)
- [Quantifiers](#)
- [Flags](#)

### Wildcards

Wildcard tokens match something other than themselves:

**Table 134–1 Wildcard tokens recognized by OWA\_PATTERN package**

Token	Description
^	Matches newline or the beginning of the target
\$	Matches newline or the end of the target
\n	Matches newline
.	Matches any character except newline
\t	Matches tab
\d	Matches digits [0-9]
\D	Matches non-digits [not 0-9]
\w	Matches word characters (0-9, a-z, A-Z, or _)
\W	Matches non-word characters (not 0-9, a-z, A-Z, or _)
\s	Matches whitespace characters (blank, tab, or newline).
\S	Matches non-whitespace characters (not blank, tab, or newline)
\b	Matches "word" boundaries (between \w and \W)
\x<HEX>	Matches the value in the current character set of the two hexadecimal digits
\<OCT>	Matches the value in the current character set of the two or three octal digits
\	Followed by any character not covered by another case matches that character
&	Applies only to CHANGE. This causes the string that matched the regular expression to be included in the string that replaces it. This differs from the other tokens in that it specifies how a target is changed rather than how it is matched. This is explained further under <a href="#">CHANGE Functions and Procedures</a> .

## Quantifiers

Any tokens except & can have their meaning extended by any of the following quantifiers. You can also apply these quantifiers to literals:

**Table 134–2 Quantifiers**

Quantifier	Description
?	0 or 1 occurrence(s)
*	0 or more occurrences
+	1 or more occurrence(s)

**Table 134–2 Quantifiers**

<b>Quantifier</b>	<b>Description</b>
{ <i>n</i> }	Exactly <i>n</i> occurrences
{ <i>n</i> , }	At least <i>n</i> occurrences
{ <i>n</i> , <i>m</i> }	At least <i>n</i> , but not more than <i>m</i> , occurrences

## Flags

In addition to targets and regular expressions, the OWA\_PATTERN functions and procedures use flags to affect how they are interpreted.

**Table 134–3 Flags**

<b>Flag</b>	<b>Description</b>
i	This indicates a case-insensitive search.
g	This applies only to CHANGE. It indicates a global replace. That is, all portions of the target that match the regular expression are replaced.

## Summary of OWA\_PATTERN Subprograms

*Table 134-4 OWA\_CACHE Package Subprograms*

Subprogram	Description
<a href="#">AMATCH Function</a> on page 134-6	Determines if a string contains the specified pattern. It lets you specify where in the string the match has to occur
<a href="#">CHANGE Functions and Procedures</a> on page 134-8	Replaces a pattern within a string. If you call it as a function it returns the number of times the regular expression was found and replaced
<a href="#">GETPAT Procedure</a> on page 134-10	Generates a pattern data type from a VARCHAR2 type
<a href="#">MATCH Function</a> on page 134-11	Determines if a string contains the specified pattern

## AMATCH Function

This function specifies if a pattern occurs in a particular location in a string. There are four versions to this function:

- The first and second versions of the function do not save the matched tokens (these are saved in the `backrefs` parameters in the third and fourth versions). The difference between the first and second versions is the `pat` parameter, which can be a `VARCHAR2` or a pattern data type.
- The third and fourth versions of the function save the matched tokens in the `backrefs` parameter. The difference between the third and fourth versions is the `pat` parameter, which can be a `VARCHAR2` or a pattern data type.

---

---

**Note:** If multiple overlapping strings match the regular expression, this function takes the longest match.

---

---

### Syntax

```
OWA_PATTERN.AMATCH(
 line IN VARCHAR2,
 from_loc IN INTEGER,
 pat IN VARCHAR2,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN INTEGER;
```

```
OWA_PATTERN.AMATCH(
 line IN VARCHAR2,
 from_loc IN INTEGER,
 pat IN OUT PATTERN,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN INTEGER;
```

```
OWA_PATTERN.AMATCH(
 line IN VARCHAR2
 from_loc IN INTEGER
 pat IN varchar2
 backrefs OUT owa_text.vc_arr
 flags IN VARCHAR2 DEFAULT NULL)
RETURN INTEGER;
```

```
OWA_PATTERN.AMATCH(
 line IN VARCHAR2
```

```

 from_loc IN INTEGER
 pat IN OUT PATTERN
 backrefs OUT owa_text.vc_arr
 flags IN VARCHAR2 DEFAULT NULL)
RETURN INTEGER;
```

## Parameters

**Table 134–5** *AMATCH Procedure Parameters*

Parameter	Description
line	The text to search in.
from_loc	The location (in number of characters) in <code>line</code> where the search is to begin.
pat	The string to match. It can contain regular expressions. This can be either a <code>VARCHAR2</code> or a pattern. If it is a pattern, the output value of this parameter is the pattern matched.
backrefs	The text that is matched. Each token that is matched is placed in a cell in the <code>OWA_TEXT.VC_ARR</code> DATA TYPE PL/SQL table.
flags	Whether or not the search is case-sensitive. If the value of this parameter is "i", the search is case-insensitive. Otherwise the search is case-sensitive.

## Return Values

The index of the character after the end of the match, counting from the beginning of `line`. If there was no match, the function returns 0.

## CHANGE Functions and Procedures

This function or procedure searches and replaces a string or `multi_line` data type. If multiple overlapping strings match the regular expression, this subprogram takes the longest match.

### Syntax

```
OWA_PATTERN.CHANGE(
 line IN OUT VARCHAR2,
 from_str IN VARCHAR2,
 to_str IN VARCHAR2,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN INTEGER;
```

```
OWA_PATTERN.CHANGE(
 line IN OUT VARCHAR2,
 from_str IN VARCHAR2,
 to_str IN VARCHAR2,
 flags IN VARCHAR2 DEFAULT NULL);
```

```
owa_pattern.change(
 mline IN OUT owa_text.multi_line,
 from_str IN VARCHAR2,
 to_str IN VARCHAR2,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN INTEGER;
```

```
OWA_PATTERN.CHANGE(
 mline IN OUT owa_text.multi_line,
 from_str IN VARCHAR2,
 to_str IN VARCHAR2,
 flags IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 134–6** *CHANGE Procedure Parameters*

Parameter	Description
<code>line</code>	The text to search in. The output value of this parameter is the altered string.



**Table 134–6 (Cont.) CHANGE Procedure Parameters**

Parameter	Description
mline	The text to search in. This is a <code>owa_text.multi_line</code> data type. The output value of this parameter is the altered string.
from_str	The regular expression to replace.
to_str	The substitution pattern.
flags	Whether or not the search is case-sensitive, and whether or not changes are to be made globally. If "i" is specified, the search is case-insensitive. If "g" is specified, changes are made to all matches. Otherwise, the function stops after the first substitution is made.

## Return Values

As a function, it returns the number of substitutions made. If the flag "g" is not used, this number can only be 0 or 1 and only the first match is replaced. The flag "g" specifies to replace all matches with the regular expression.

## Examples

### Example 1:

```
OWA_PATTERN.CHANGE('Cats in pajamas', 'C.+in', '& red ')
```

The regular expression matches the substring "Cats in". It then replaces this string with "& red". The ampersand character "&" indicates "Cats in" because that is what matched the regular expression. Thus, this procedure replaces the string "Cats in pajamas" with "Cats in red". If you call this as a function instead of a procedure, the value returned is 1, indicating that a single substitution has been made.

### Example 2:

```
CREATE OR REPLACE PROCEDURE test_pattern as theline VARCHAR2(256);
num_found INTEGER;
BEGIN
 theline := 'what is the goal?';
 num_found := OWA_PATTERN.CHANGE(theline, 'goal', 'idea', 'g');
 HTP.PRINT(num_found); -- num_found is 1
 HTP.PRINT(theline); -- theline is 'what is the idea?'
END;
/
SHOW ERRORS
```

## GETPAT Procedure

This procedure converts a `VARCHAR2` string into an `OWA_PATTERN.PATTERN DATA TYPE`.

### Syntax

```
OWA_PATTERN.GETPAT(
 arg IN VARCHAR2,
 pat IN OUT pattern);
```

### Parameters

**Table 134–7** *GETPAT Procedure Parameters*

Parameter	Description
<code>arg</code>	The string to convert.
<code>pat</code>	the <code>OWA_PATTERN.PATTERN DATA TYPE</code> initialized with <code>arg</code> .

## MATCH Function

This function determines if a string contains the specified pattern. The pattern can contain regular expressions. If multiple overlapping strings can match the regular expression, this function takes the longest match.

### Syntax

```
owa_pattern.match(
 line IN VARCHAR2,
 pat IN VARCHAR2,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN BOOLEAN;
```

```
owa_pattern.match(
 line IN VARCHAR2,
 pat IN OUT PATTERN,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN BOOLEAN;
```

```
owa_pattern.match(
 line IN VARCHAR2,
 pat IN VARCHAR2,
 backrefs OUT owa_text.vc_arr,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN BOOLEAN;
```

```
OWA_PATTERN.MATCH(
 line IN VARCHAR2,
 pat IN OUT PATTERN,
 backrefs OUT owa_text.vc_arr,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN BOOLEAN;
```

```
owa_pattern.match(
 mline IN owa_text.multi_line,
 pat IN VARCHAR2,
 rlist OUT owa_text.row_list,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN BOOLEAN;
```

```
OWA_PATTERN.MATCH(
 mline IN owa_text.multi_line,
 pat IN OUT pattern,
```

```

 rlist OUT owa_text.row_list,
 flags IN VARCHAR2 DEFAULT NULL)
RETURN BOOLEAN;
```

## Parameters

**Table 134–8** *CHANGE Procedure Parameters*

Parameter	Description
line	The line to search in.
mline	The text to search in. This is a <code>owa_text.multi_line</code> data type..
pat	The pattern to match. This is either a <code>VARCHAR2</code> or a <code>OWA_PATTERN.PATTERN DATA TYPE</code> . If it is a pattern, the output value of this parameter is the pattern matched.
backrefs	The text that is matched. Each token that is matched is placed in a cell in the <code>OWA_TEXT.VC_ARR DATA TYPE PL/SQL</code> table. This parameter is a <code>row_list</code> that holds each string in the target that was matched by a sequence of tokens in the regular expression.
rlist	An output parameter containing a list of matches.
flags	Whether or not the search is case-sensitive. If the value of this parameter is "i", the search is case-insensitive. Otherwise the search is case-sensitive.

## Return Values

TRUE if a match was found, FALSE otherwise.

## Examples

KAZOO is the target where it is searching for the `zoo.*` regular expression. The period indicates any character other than newline, and the asterisk matches 0 or more of the preceding characters. In this case, it matches any character other than the newline.

Therefore, this regular expression specifies that a matching target consists of `zoo`, followed by any set of characters neither ending in nor including a newline (which does not match the period). The `i` flag indicates to ignore case in the search. In this case, the function returns TRUE, which indicates that a match had been found.

```
boolean foundMatch;
```

```
foundMatch := owa_pattern.match('KAZOO', 'zoo.*', 'i');
```

The following example searches for the string "goal" followed by any number of characters in `sometext`. If found,

```
sometext VARCHAR2(256);
pat VARCHAR2(256);

sometext := 'what is the goal?';
pat := 'goal.*';
IF OWA_PATTERN.MATCH(sometext, pat)
 THEN
 HTP.PRINT('Match found');
 ELSE
 HTP.PRINT('Match not found');
END IF;
```

## Operational Notes

- The regular expression in this function can be either a `VARCHAR2` or an `OWA_PATTERN.PATTERN DATA TYPE`. Create an `OWA_PATTERN.PATTERN DATA TYPE` from a string using the `OWA_PATTERN.GETPAT` procedure.
- Create a `MULTI_LINE DATA TYPE` from a long string using the `OWA_TEXT.STREAM2MULTI` procedure. If a `multi_line` is used, the `rlist` parameter specifies a list of chunks where matches were found.
- If the line is a string and not a `multi_line`, you can add an optional output parameter called `backrefs`. This parameter is a `row_list` that holds each string in the target that was matched by a sequence of tokens in the regular expression.



The OWA\_SEC package provides an interface for custom authentication.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using OWA\\_SEC](#)
  - [Operational Notes](#)
- [Summary of OWA\\_SEC Subprograms](#)

---

## Using OWA\_SEC

- [Operational Notes](#)

### Operational Notes

Parameters that have default values are optional.



---

## Summary of OWA\_SEC Subprograms

**Table 135–1 OWA\_SEC Package Subprograms**

Subprogram	Description
<a href="#">GET_CLIENT_HOSTNAME Function</a> on page 135-4	Returns the client's hostname
<a href="#">GET_CLIENT_IP Function</a> on page 135-5	Returns the client's IP address
<a href="#">GET_PASSWORD Function</a> on page 135-6	Returns the password that the user entered
<a href="#">GET_USER_ID Function</a> on page 135-7	Returns the username that the user entered
<a href="#">SET_AUTHORIZATION Procedure</a> on page 135-8	Enables the PL/SQL application to use custom authentication
<a href="#">SET_PROTECTION_REALM Procedure</a> on page 135-10	Defines the realm that the page is in

## GET\_CLIENT\_HOSTNAME Function

This function returns the hostname of the client.

### Syntax

```
OWA_SEC.GET_CLIENT_HOSTNAME
RETURN VARCHAR2;
```

### Return Values

The hostname.

## GET\_CLIENT\_IP Function

This function returns the IP address of the client.

### Syntax

```
OWA_SEC.GET_CLIENT_IP
RETURN OWA_UTIL.IP_ADDRESS;
```

### Return Values

The IP address. The `owa_util.ip_address` data type is a PL/SQL table where the first four elements contain the four numbers of the IP address. For example, if the IP address is 123.45.67.89 and the variable `ipaddr` is of the `owa_util.ip_address` data type, the variable would contain the following values:

```
ipaddr(1) = 123
ipaddr(2) = 45
ipaddr(3) = 67
ipaddr(4) = 89
```

## GET\_PASSWORD Function

This function returns the password that the user used to log in.

### Syntax

```
OWA_SEC.GET_PASSWORD
RETURN VARCHAR2;
```

### Return Values

The password.

### Usage Notes

For security reasons, this function returns a true value only when custom authentication is used. If you call this function when you are not using custom authentication, the function returns an undefined value. Thus, the database passwords are not exposed.

## GET\_USER\_ID Function

This function returns the username that the user used to log in.

### Syntax

```
OWA_SEC.GET_USER_ID
RETURN VARCHAR2;
```

### Return Values

The username.

## SET\_AUTHORIZATION Procedure

This procedure, called in the initialization portion of the [OWA\\_CUSTOM](#) package, sets the authorization scheme for the PL/SQL Gateway. This implements your `authorize` function, which authorizes the user before his requested procedure is run. The placement of the `authorize` function depends on the scheme you select.

### Syntax

```
OWA_SEC.SET_AUTHORIZATION(
 scheme IN INTEGER);
```

## Parameters

**Table 135–2 SET\_AUTHORIZATION Procedure Parameters**

Parameter	Description
scheme	<p>The authorization scheme. It is one of the following schemes for SET_AUTHORIZATION:</p> <ul style="list-style-type: none"> <li>■ OWA_SEC.NO_CHECK - Specifies that the PL/SQL application is not to do any custom authentication. This is the default.</li> <li>■ OWA_SEC.GLOBAL - Defines an authorize function that is called for all users and all procedures. This is the OWA_CUSTOM.AUTHORIZE Function in the "sys" schema.</li> <li>■ OWA_SEC.PER_PACKAGE - Define an authorize function that is called when procedures in a package or anonymous procedures are called. If the procedures are in a package, the <i>package</i>.AUTHORIZE function in the user's schema is called to authorize the user. If the procedures are not in a package, then the anonymous authorize function in the user's schema is called.</li> <li>■ OWA_SEC.CUSTOM - Implements different authorize functions for each user. The function OWA_CUSTOM.AUTHORIZE Function in the user's schema is called to authorize the user. If the user's schema does not contain an OWA_CUSTOM.AUTHORIZE Function, the PL/SQL Gateway looks for it in the "sys" schema.</li> </ul> <p>The custom authorize function has the following signature:</p> <pre>FUNCTION AUTHORIZE RETURN BOOLEAN;</pre> <p>If the function returns TRUE, authentication succeeded. If it returns FALSE, authentication failed. If the authorize function is not defined, the Gateway returns an error and fails.</p>

## SET\_PROTECTION\_REALM Procedure

This procedure sets the realm of the page that is returned to the user. The user enters a username and login that already exist in the realm.

### Syntax

```
OWA_SEC.SET_PROTECTION_REALM(
 realm IN VARCHAR2);
```

### Parameters

**Table 135–3** *SET\_PROTECTION\_REALM Procedure Parameters*

Parameter	Description
realm	The realm where the page belongs. This string is displayed to the user.



The `OWA_TEXT` package contains subprograms used by `OWA_PATTERN` for manipulating strings. They are externalized so you can use them directly.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using OWA\\_TEXT](#)
  - [Types](#)
- [Summary of OWA\\_TEXT Subprograms](#)

---

## Using OWA\_TEXT

- [Types](#)

### Types

- [MULTI\\_LINE DATA TYPE](#)
- [ROW\\_LIST DATA TYPE](#)
- [VC\\_ARR DATA TYPE](#)

### MULTI\_LINE DATA TYPE

This data type is a PL/SQL record that holds large amounts of text. The rows field, of type `OWA_TEXT.VC_ARR DATA TYPE`, contains the text data in the record.

```
TYPE multi_line IS RECORD (
 rows vc_arr,
 num_rows INTEGER,
 partial_row BOOLEAN);
```

### ROW\_LIST DATA TYPE

This is the data type for holding data to be processed.

```
TYPE row_list IS RECORD (
 rows int_arr,
 num_rows INTEGER);
```

```
int_arr IS DEFINED AS:
TYPE int_arr IS TABLE OF INTEGER INDEX BY BINARY_INTEGER;
```

### VC\_ARR DATA TYPE

This is a component of the [MULTI\\_LINE DATA TYPE](#) and is used for holding large amounts of text.

```
TYPE vc_arr IS TABLE OF VARCHAR2(32767) INDEX BY BINARY_INTEGER;
```

---

## Summary of OWA\_TEXT Subprograms

**Table 136–1 OWA\_TEXT Package Subprograms**

Subprogram	Description
<a href="#">ADD2MULTI Procedure</a> on page 136-4	Adds text to an existing <code>multi_line</code> type
<a href="#">NEW_ROW_LIST Function and Procedure</a> on page 136-5	Creates a new <code>row_list</code>
<a href="#">PRINT_MULTI Procedure</a> on page 136-6	Prints out the contents of a <code>multi_list</code>
<a href="#">PRINT_ROW_LIST Procedure</a> on page 136-7	Prints out the contents of a <code>row_list</code>
<a href="#">STREAM2MULTI Procedure</a> on page 136-8	Converts a <code>varchar2</code> to a <code>multi_line</code> type

## ADD2MULTI Procedure

This procedure adds content to an existing `MULTI_LINE DATA TYPE`.

### Syntax

```
OWA_TEXT.ADD2MULTI(
 stream IN VARCHAR2,
 mline IN OUT MULTI_LINE,
 continue IN BOOLEAN DEFAULT TRUE);
```

### Parameters

**Table 136–2** ADD2MULTI Procedure Parameters

Parameter	Description
<code>stream</code>	The text to add.
<code>mline</code>	The <code>OWA_TEXT.MULTI_LINE DATA TYPE</code> . The output of this parameter contains <i>stream</i> .
<code>continue</code>	If <code>TRUE</code> , the procedure appends <i>stream</i> within the previous final row (assuming it is less than 32K). If <code>FALSE</code> , the procedure places <i>stream</i> in a new row.

## NEW\_ROW\_LIST Function and Procedure

This function or procedure creates a new `OWA_TEXT.ROW_LIST` DATA TYPE. The function version uses no parameters and returns a new empty `row_list`. The procedure version creates the `row_list` data type as an output parameter.

### Syntax

```
OWA_TEXT.NEW_ROW_LIST
 RETURN ROW_LIST;

OWA_TEXT.NEW_ROW_LIST(
 rlist OUT row_list);
```

### Parameters

**Table 136–3** *NEW\_ROW\_LIST Procedure Parameters*

Parameter	Description
<code>rlist</code>	This is an output parameter containing the new <code>row_list</code> data type

### Return Values

The function version returns the new `row_list` data type.

## PRINT\_MULTI Procedure

This procedure uses the [PRINT Procedures](#) or the [PRN Procedures](#) to print the "rows" field of the OWA\_TEXT.MULTI\_LINE DATA TYPE.

### Syntax

```
OWA_TEXT.PRINT_MULTI(
 mline IN multi_line);
```

### Parameters

**Table 136–4 PRINT\_MULTI Procedure Parameters**

Parameter	Description
mline	The multi_line data type to print.

### Return Values

The contents of the multi\_line.

## PRINT\_ROW\_LIST Procedure

This procedure uses [PRINT Procedures](#) or the [PRN Procedures](#) to print the "rows" field of the OWA\_TEXT.ROW\_LIST DATA TYPE.

### Syntax

```
OWA_TEXT.PRINT_ROW_LIST(
 rlist IN multi_line);
```

### Parameters

**Table 136–5** *PRINT\_ROW\_LIST Procedure Parameters*

Parameter	Description
rlist	The row_list data type to print.

### Return Values

The contents of the row\_list.

## STREAM2MULTI Procedure

This procedure converts a string to a `multi_line` data type.

### Syntax

```
OWA_TEXT.STREAM2MULTI(
 stream IN VARCHAR2
 mline OUT multi_line);
```

### Parameters

**Table 136–6** *STREAM2MULTI Procedure Parameters*

Parameter	Description
<code>stream</code>	The string to convert.
<code>mline</code>	The stream in <code>OWA_TEXT.MULTI_LINE DATA TYPE</code> format



The `OWA_UTIL` package contains utility subprograms for performing operations such as getting the value of CGI environment variables, printing the data that is returned to the client, and printing the results of a query in an HTML table.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

This chapter contains the following topics:

- [Using OWA\\_UTIL](#)
  - [Overview](#)
  - [Types](#)
- [Summary of OWA\\_UTIL Subprograms](#)

---

## Using OWA\_UTIL

- [Overview](#)
- [Types](#)

### Overview

The OWA\_UTIL package contains three types of utility subprograms.

- Dynamic SQL Utilities enable you to produce pages with dynamically generated SQL code.
- HTML utilities enable you to retrieve the values of CGI environment variables and perform URL redirects.
- Date utilities enable correct date-handling. Date values are simple strings in HTML, but are treated as a data type by the Oracle database.

### Types

- [DATETYPE Data Type](#)
- [IDENT\\_ARR Data Type](#)
- [IP\\_ADDRESS Data Type](#)

#### DATETYPE Data Type

The [TODATE Function](#) converts an item of this type to the type DATE, which is understood and properly handled as data by the database. The procedure [CHOOSE\\_DATE Procedure](#) enables the user to select the desired date.

```
TYPE dateType IS TABLE OF VARCHAR2(10) INDEX BY BINARY_INTEGER;
```

#### IDENT\_ARR Data Type

This data type is used for an array.

```
TYPE ident_arr IS TABLE OF VARCHAR2(30) INDEX BY BINARY_INTEGER;
```

## IP\_ADDRESS Data Type

This data type is used by the [GET\\_CLIENT\\_IP Function](#) in the [OWA\\_SEC](#) package.

```
TYPE ip_address IS TABLE OF INTEGER INDEX BY BINARY_INTEGER;
```

---

## Summary of OWA\_UTIL Subprograms

**Table 137-1 OWA\_UTIL Package Subprograms**

Subprogram	Description
<a href="#">BIND_VARIABLES Function</a> on page 137-6	prepares a SQL query and binds variables to it
<a href="#">CALENDARPRINT Procedures</a> on page 137-7	prints a calendar
<a href="#">CELLSPRINT Procedures</a> on page 137-9	prints the contents of a query in an HTML table
<a href="#">CHOOSE_DATE Procedure</a> on page 137-12	generates HTML form elements that allow the user to select a date
<a href="#">GET_CGI_ENV Function</a> on page 137-14	returns the value of the specified CGI environment variable
<a href="#">GET_OWA_SERVICE_PATH Function</a> on page 137-15	returns the full virtual path for the PL/SQL Gateway
<a href="#">GET_PROCEDURE Function</a> on page 137-16	returns the name of the procedure that is invoked by the PL/SQL Gateway
<a href="#">HTTP_HEADER_CLOSE Procedure</a> on page 137-17	closes the HTTP header
<a href="#">LISTPRINT Procedure</a> on page 137-18	generates a HTML form element that contains data from a query
<a href="#">MIME_HEADER Procedure</a> on page 137-20	generates the Content-type line in the HTTP header
<a href="#">PRINT_CGI_ENV Procedure</a> on page 137-21	generates a list of all CGI environment variables and their values
<a href="#">REDIRECT_URL Procedure</a> on page 137-22	generates the Location line in the HTTP header
<a href="#">SHOWPAGE Procedure</a> on page 137-23	prints a page generated by the HTP and HTF packages in SQL*Plus
<a href="#">SHOWSOURCE Procedure</a> on page 137-24	prints the source for the specified subprogram
<a href="#">SIGNATURE procedure</a> on page 137-25	prints a line that says that the page is generated by the PL/SQL Agent

**Table 137–1 (Cont.) OWA\_UTIL Package Subprograms (Cont.)**

<b>Subprogram</b>	<b>Description</b>
<a href="#">STATUS_LINE Procedure</a> on page 137-26	generates the Status line in the HTTP header
<a href="#">TABLEPRINT Function</a> on page 137-27	prints the data from a table in the database as an HTML table
<a href="#">TODATE Function</a> on page 137-31	converts dateType data to the standard PL/SQL date type
<a href="#">WHO_CALLED_ME Procedure</a> on page 137-32	returns information on the caller of the procedure.

## BIND\_VARIABLES Function

This function prepares a SQL query by binding variables to it, and stores the output in an opened cursor. Use this function as a parameter to a procedure sending a dynamically generated query. Specify up to 25 bind variables.

### Syntax

```
OWA_UTIL.BIND_VARIABLES(
 theQuery IN VARCHAR2 DEFAULT NULL,
 bv1Name IN VARCHAR2 DEFAULT NULL,
 bv1Value IN VARCHAR2 DEFAULT NULL,
 bv2Name IN VARCHAR2 DEFAULT NULL,
 bv2Value IN VARCHAR2 DEFAULT NULL,
 bv3Name IN VARCHAR2 DEFAULT NULL,
 bv3Value IN VARCHAR2 DEFAULT NULL,
 ...
 bv25Name IN VARCHAR2 DEFAULT NULL,
 bv25Value IN VARCHAR2 DEFAULT NULL)
RETURN INTEGER;
```

### Parameters

**Table 137–2** *BIND\_VARIABLES Function Parameters*

Parameter	Description
theQuery	The SQL query statement which must be a SELECT statement
bv1Name	The name of the variable
bv1Value	The value of the variable

### Return Values

An integer identifying the opened cursor.

## CALENDARPRINT Procedures

These procedures creates a calendar in HTML with a visible border. Each date in the calendar can contain any number of hypertext links.

This procedure has 2 versions.

- Version 1 uses a hard-coded query stored in a varchar2 string.
- Version 2 uses a dynamic query prepared with the [BIND\\_VARIABLES Function](#).

### Syntax

```
OWA_UTIL.CALENDARPRINT(
 p_query IN VARCHAR2,
 p_mf_only IN VARCHAR2 DEFAULT 'N');
```

```
OWA_UTIL.CALENDARPRINT(
 p_cursor IN INTEGER,
 p_mf_only IN VARCHAR2 DEFAULT 'N');
```

### Parameters

**Table 137–3 CALENDARPRINT Procedure Parameters**

Parameter	Description
p_query	A PL/SQL query.
p_cursor	A PL/SQL cursor containing the same format as p_query.
p_mf_only	If "N" (the default), the generated calendar includes Sunday through Saturday. Otherwise, it includes Monday through Friday only.

### Usage Notes

Design your query as follows:

- The first column is a DATE. This correlates the information produced by the query with the calendar output generated by the procedure.
- The query output must be sorted on this column using ORDER BY.
- The second column contains the text, if any, that you want printed for that date.

- The third column contains the destination for generated links. Each item in the second column becomes a hypertext link to the destination given in this column. If this column is omitted, the items in the second column are simple text, not links.



## CELLSPRINT Procedures

This procedure generates an HTML table from the output of a SQL query. SQL atomic data items are mapped to HTML cells and SQL rows to HTML rows. You must write the code to begin and end the HTML table. There are nine versions of this procedure:

- The first version passes the results of a query into an index table. Perform the query and CELLSPRINT does the formatting. To have more control in generating an HTML table from the output of an SQL query, use the [FORMAT\\_CELL Function](#) in the [HTF](#) package.
- The second and third versions display rows (up to the specified maximum) returned by the query or cursor.
- The fourth and fifth versions exclude a specified number of rows from the HTML table. Use the fourth and fifth versions to scroll through result sets by saving the last row seen in a hidden form element.
- The sixth through ninth versions are the same as the first four versions, except that they return a row count output parameter.

### Syntax

```
OWA_UTIL.CELLSPRINT(
 p_colCnt IN INTEGER,
 p_resultTbl IN vc_arr,
 p_format_numbers IN VARCHAR2 DEFAULT NULL);
```

```
OWA_UTIL.CELLSPRINT(
 p_theQuery IN VARCHAR2,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL);
```

```
OWA_UTIL.CELLSPRINT(
 p_theCursor IN INTEGER,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL);
```

```
OWA_UTIL.CELLSPRINT(
 p_theQuery IN VARCHAR2,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL,
 p_skip_rec IN NUMBER DEFAULT 0,
```

```

 p_more_data OUT BOOLEAN);

OWA_UTIL.CELLSPRINT(
 p_theCursor IN INTEGER,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL,
 p_skip_rec IN NUMBER DEFAULT 0,
 p_more_data OUT BOOLEAN);

OWA_UTIL.CELLSPRINT(
 p_theQuery IN VARCHAR2,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL,
 p_recCnt OUT NUMBER);

OWA_UTIL.CELLSPRINT(
 p_theCursor IN INTEGER,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL,
 p_recCnt OUT NUMBER);

OWA_UTIL.CELLSPRINT(
 p_theQuery IN VARCHAR2,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL,
 p_skip_rec IN NUMBER DEFAULT 0,
 p_more_data OUT BOOLEAN,
 p_recCnt OUT NUMBER);

OWA_UTIL.CELLSPRINT(
 p_theCursor IN INTEGER,
 p_max_rows IN NUMBER DEFAULT 100,
 p_format_numbers IN VARCHAR2 DEFAULT NULL,
 p_skip_rec IN NUMBER DEFAULT 0,
 p_more_data OUT BOOLEAN,
 p_recCnt OUT NUMBER);

```

## Parameters

**Table 137–4** *CELLSPRINT Procedure Parameters*

Parameter	Description
p_query	A PL/SQL query.

**Table 137-4 (Cont.) CELLSPRINT Procedure Parameters**

Parameter	Description
p_colCnt	The number of columns in the table.
p_theQuery	A SQL SELECT statement.
p_theCursor	A cursor ID. This can be the return value from the <a href="#">BIND_VARIABLES Function</a> .
p_max_rows	The maximum number of rows to print.
p_format_numbers	If the value of this parameter is not NULL, number fields are right justified and rounded to two decimal places.
p_skip_rec	The number of rows to exclude from the HTML table.
p_more_data	TRUE if there are more rows in the query or cursor, FALSE otherwise.
p_recCnt	The number of rows that have been returned by the query. This value does not include skipped rows (if any).
p_resultTbl	The index table which will contain the result of the query. Each entry in the query will correspond to one column value.

## Examples

This function generates

```
<tr><td>QueryResultItem</td><td>QueryResultItem</td></tr>...
```

## CHOOSE\_DATE Procedure

This procedure generates three HTML form elements that allow the user to select the day, the month, and the year.

### Syntax

```
OWA_UTIL.CHOOSE_DATE(
 p_name IN VARCHAR2,
 p_date IN DATE DEFAULT SYSDATE);
```

### Parameters

**Table 137–5** CHOOSE\_DATE Procedure Parameters

Parameter	Description
p_name	The name of the form elements.
p_date	The initial date that is selected when the HTML page is displayed.

### Usage Notes

- The parameter in the procedure that receives the data from these elements must be a [GET\\_CGI\\_ENV Function](#).
- Use the [TODATE Function](#) to convert the [GET\\_CGI\\_ENV Function](#) value to the standard Oracle DATE data type.

### Examples

```
<SELECT NAME="p_name" SIZE="1">
<OPTION value="01">1
 ...
<OPTION value="31">31
</SELECT>
-
<SELECT NAME="p_name" SIZE="1">
<OPTION value="01">JAN
 ...
<OPTION value="12">DEC
</SELECT>
```

```
-
<SELECT NAME="p_name" SIZE="1">
<OPTION value="1992">1992
 ...
<OPTION value="2002">2002
</SELECT>
```

## GET\_CGI\_ENV Function

This function returns the value of the specified CGI environment variable.

### Syntax

```
OWA_UTIL.GET_CGI_ENV(
 param_name IN VARCHAR2)
RETURN VARCHAR2;
```

### Parameters

**Table 137–6** *GET\_CGI\_ENV Function Parameters*

Parameter	Description
param_name	The name of the CGI environment variable. It is case-insensitive.

### Return Values

The value of the specified CGI environment variable. If the variable is not defined, the function returns NULL.

## GET\_OWA\_SERVICE\_PATH Function

This function returns the full virtual path of the PL/SQL Gateway that is handling the request.

### Syntax

```
OWA_UTIL.GET_OWA_SERVICE_PATH
RETURN VARCHAR2;
```

### Return Values

A virtual path of the PL/SQL Gateway that is handling the request.

## GET\_PROCEDURE Function

This function returns the name of the procedure that is being invoked by the PL/SQL Gateway.

### Syntax

```
OWA_UTIL.GET_PROCEDURE
RETURN VARCHAR2;
```

### Return Values

The name of a procedure, including the package name if the procedure is defined in a package.



## HTTP\_HEADER\_CLOSE Procedure

This procedure generates a newline character to close the HTTP header.

### Syntax

```
OWA_UTIL.HTTP_HEADER_CLOSE;
```

### Return Values

A newline character, which closes the HTTP header.

### Usage Notes

- Use this procedure if you have not closed the header by using the `bclose_header` parameter in calls such as [MIME\\_HEADER Procedure](#), [REDIRECT\\_URL Procedure](#), or [STATUS\\_LINE Procedure](#)
- The HTTP header must be closed before any `HTTP.PRINT` or `HTTP.PRN` calls.

## LISTPRINT Procedure

This procedure generates an HTML selection list form element from the output of a SQL query. There are two versions of this procedure.

- The first version contains a hard-coded SQL query.
- The second version uses a dynamic query prepared with the [BIND\\_VARIABLES Function](#).

### Syntax

```
OWA_UTIL.LISTPRINT(
 p_theQuery IN VARCHAR2,
 p_cname IN VARCHAR2,
 p_nsize IN NUMBER,
 p_multiple IN BOOLEAN DEFAULT FALSE);
```

```
OWA_UTIL.LISTPRINT(
 p_theCursor IN INTEGER,
 p_cname IN VARCHAR2,
 p_nsize IN NUMBER,
 p_multiple IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 137–7 LISTPRINT Procedure Parameters**

Parameter	Description
p_theQuery	The SQL query.
p_theCursor	The cursor ID. This can be the return value from the <a href="#">BIND_VARIABLES Function</a> .
p_cname	The name of the HTML form element.
p_nsize	The size of the form element (this controls how many items the user can see without scrolling).
p_multiple	Whether multiple selection is permitted.

### Usage Notes

The columns in the output of the query are handled in the following manner:

- The first column specifies the values that are sent back. These values are for the `VALUE` attribute of the `OPTION` tag.
- The second column specifies the values that the user sees.
- The third column specifies whether or not the row is marked as `SELECTED` in the `OPTION` tag. If the value is not `NULL`, the row is selected.

## Examples

```
<SELECT NAME="p_cname" SIZE="p_nsize">
<OPTION SELECTED value='value_from_the_first_column'>value_from_the_second_
column
<OPTION SELECTED value='value_from_the_first_column'>value_from_the_second_
column
 ...
</SELECT>
```

## MIME\_HEADER Procedure

This procedure changes the default MIME header that the script returns. This procedure must come before any `HTP.PRINT` or `HTP.PRN` calls to direct the script not to use the default MIME header.

### Syntax

```
OWA_UTIL.MIME_HEADER(
 ccontent_type IN VARCHAR2 DEFAULT 'text/html',
 bclose_header IN BOOLEAN DEFAULT TRUE,
 ccharset IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 137–8** *MIME\_HEADER Procedure Parameters*

Parameter	Description
<code>ccontent_type</code>	The MIME type to generate
<code>bclose_header</code>	Whether or not to close the HTTP header. If <code>TRUE</code> , two newlines are sent, which closes the HTTP header. Otherwise, one newline is sent, and the HTTP header remains open.
<code>ccharset</code>	The character set to use. The character set only makes sense if the MIME type is of type 'text'. Therefore, the character set is only tagged on to the Content-Type header only if the MIME type passed in is of type 'text'. Any other MIME type, such as 'image', will not have any character set tagged on.

### Examples

Content-type: <ccontent\_type> charset=<ccharset>

so that

```
owa_util.mime_header('text/plain', false, 'ISO-8859-4')
```

generates

```
Content-type: text/plain; charset=ISO-8859-4\n
```

## PRINT\_CGI\_ENV Procedure

This procedure generates all the CGI environment variables and their values made available by the PL/SQL Gateway to the stored procedure.

### Syntax

```
OWA_UTIL.PRINT_CGI_ENV;
```

### Examples

This procedure generates a list in the following format:

```
cgi_env_var_name = value\n
```

## REDIRECT\_URL Procedure

This procedure specifies that the application server is to visit the specified URL. The URL may specify either a web page to return or a program to execute.

### Syntax

```
OWA_UTIL.REDIRECT_URL(
 curl IN VARCHAR2
 bclose_header IN BOOLEAN DEFAULT TRUE);
```

### Parameters

**Table 137–9 REDIRECT\_URL Function Parameters**

Parameter	Description
curl	The URL to visit.
bclose_header	Whether or not to close the HTTP header. If TRUE, two newlines are sent, which closes the HTTP header. Otherwise, one newline is sent, and the HTTP header remains open.

### Usage Notes

This procedure must come before any [HTTP](#) or [HTF](#) procedure or function call.

### Examples

This procedure generates

```
Location: <curl>\n\n
```

## SHOWPAGE Procedure

This procedure prints out the HTML output of a procedure in SQL\*Plus. The procedure must use the [HTP](#) or [HTF](#) packages to generate the HTML page, and this procedure must be issued after the [HTP](#) or [HTF](#) page-generating subprogram has been called and before any other [HTP](#) or [HTF](#) subprograms are directly or indirectly called.

### Syntax

```
OWA_UTIL.SHOWPAGE;
```

### Usage Notes

- This method is useful for generating pages filled with static data.
- This procedure uses [DBMS\\_OUTPUT](#) and is limited to 255 characters for each line and an overall buffer size of 1,000,000 bytes.

### Examples

The output of `htp` procedure is displayed in SQL\*Plus, SQL\*DBA, or Oracle Server Manager. For example:

```
SQL> set serveroutput on
SQL> spool gretzky.html
SQL> execute hockey.pass("Gretzky")
SQL> execute owa_util.showpage
SQL> exit
```

This would generate an HTML page that could be accessed from Web browsers.

## SHOWSOURCE Procedure

This procedure prints the source of the specified procedure, function, or package. If a procedure or function which belongs to a package is specified, then the entire package is displayed.

### Syntax

```
OWA_UTIL.SHOWSOURCE (
 cname IN VARCHAR2);
```

### Parameters

**Table 137–10** *SHOWSOURCE Procedure Parameters*

Parameter	Description
cname	The function or procedure whose source you want to show.



## SIGNATURE procedure

This procedure generates an HTML line followed by a signature line on the HTML document. If a parameter is specified, the procedure also generates a hypertext link to view the PL/SQL source for that procedure. The link calls the [SHOWSOURCE Procedure](#).

### Syntax

```
OWA_UTIL.SIGNATURE;

OWA_UTIL.SIGNATURE (
 cname IN VARCHAR2);
```

### Parameters

**Table 137–11** SIGNATURE Procedure Parameters

Parameter	Description
cname	The function or procedure whose source you want to show.

### Examples

Without a parameter, the procedure generates a line that looks like the following:

```
This page was produced by the PL/SQL Agent on August 9, 2001 09:30.
```

With a parameter, the procedure generates a signature line in the HTML document that looks like the following:

```
This page was produced by the PL/SQL Agent on 8/09/01 09:30
View PL/SQL Source
```

## STATUS\_LINE Procedure

This procedure sends a standard HTTP status code to the client. This procedure must come before any `http.print` or `http.prn` calls so that the status code is returned as part of the header, rather than as "content data".

### Syntax

```
OWA_UTIL.STATUS_LINE(
 nstatus IN INTEGER,
 creason IN VARCHAR2 DEFAULT NULL,
 bclose_header IN BOOLEAN DEFAULT TRUE);
```

### Parameters

**Table 137–12** STATUS\_LINE Procedure Parameters

Parameter	Description
<code>nstatus</code>	The status code.
<code>creason</code>	The string for the status code.
<code>bclose_header</code>	Whether or not to close the HTTP header. If <code>TRUE</code> , two newlines are sent, which closes the HTTP header. Otherwise, one newline is sent, and the HTTP header remains open.

### Examples

This procedure generates

```
Status: <nstatus> <creason>\n\n
```

## TABLEPRINT Function

This function generates either preformatted tables or HTML tables (depending on the capabilities of the user's browser) from database tables.

### Syntax

```
OWA_UTIL.TABLEPRINT(
 ctable IN VARCHAR2,
 cattributes IN VARCHAR2 DEFAULT NULL,
 ntable_type IN INTEGER DEFAULT HTML_TABLE,
 ccolumns IN VARCHAR2 DEFAULT '*',
 cclauses IN VARCHAR2 DEFAULT NULL,
 ccol_aliases IN VARCHAR2 DEFAULT NULL,
 nrow_min IN NUMBER DEFAULT 0,
 nrow_max IN NUMBER DEFAULT NULL)
RETURN BOOLEAN;
```

### Parameters

**Table 137–13** TABLEPRINT Function Parameters

Parameter	Description
<code>ctable</code>	The database table.
<code>cattributes</code>	Other attributes to be included as-is in the tag.
<code>ntable_type</code>	How to generate the table. Specify "HTML_TABLE" to generate the table using <TABLE> tags or "PRE_TABLE" to generate the table using the <PRE> tags.
<code>ccolumns</code>	A comma-delimited list of columns from <code>ctable</code> to include in the generated table.
<code>cclauses</code>	WHERE or ORDER BY clauses, which specify which rows to retrieve from the database table, and how to order them.
<code>ccol_aliases</code>	A comma-delimited list of headings for the generated table.
<code>nrow_min</code>	The first row, of those retrieved, to display.
<code>nrow_max</code>	The last row, of those retrieved, to display.

### Return Values

Returns TRUE if there are more rows beyond the `nrow_max` requested, FALSE otherwise.

## Usage Notes

- RAW columns are supported, but LONG RAW columns are not. References to LONG RAW columns will print the result 'Not Printable'.
- Note that in this function, `cattributes` is the second rather than the last parameter.

## Examples

For browsers that do not support HTML tables, create the following procedure:

```
CREATE OR REPLACE PROCEDURE showemps IS
 ignore_more BOOLEAN;
BEGIN
 ignore_more := OWA_UTIL.TABLEPRINT('emp', 'BORDER', OWA_UTIL.PRE_TABLE);
END;
```

Requesting a URL such as

`http://myhost:7777/pls/hr/showemps`

returns to the following to the client:

<PRE>

| EMPNO | ENAME  | JOB       | MGR  | HIREDATE  | SAL  | COMM | DEPTNO |
|-------|--------|-----------|------|-----------|------|------|--------|
| 7369  | SMITH  | CLERK     | 7902 | 17-DEC-80 | 800  |      | 20     |
| 7499  | ALLEN  | SALESMAN  | 7698 | 20-FEB-81 | 1600 | 300  | 30     |
| 7521  | WARD   | SALESMAN  | 7698 | 22-FEB-81 | 1250 | 500  | 30     |
| 7566  | JONES  | MANAGER   | 7839 | 02-APR-81 | 2975 |      | 20     |
| 7654  | MARTIN | SALESMAN  | 7698 | 28-SEP-81 | 1250 | 1400 | 30     |
| 7698  | BLAKE  | MANAGER   | 7839 | 01-MAY-81 | 2850 |      | 30     |
| 7782  | CLARK  | MANAGER   | 7839 | 09-JUN-81 | 2450 |      | 10     |
| 7788  | SCOTT  | ANALYST   | 7566 | 09-DEC-82 | 3000 |      | 20     |
| 7839  | KING   | PRESIDENT |      | 17-NOV-81 | 5000 |      | 10     |
| 7844  | TURNER | SALESMAN  | 7698 | 08-SEP-81 | 1500 | 0    | 30     |
| 7876  | ADAMS  | CLERK     | 7788 | 12-JAN-83 | 1100 |      | 20     |
| 7900  | JAMES  | CLERK     | 7698 | 03-DEC-81 | 950  |      | 30     |
| 7902  | FORD   | ANALYST   | 7566 | 03-DEC-81 | 3000 |      | 20     |
| 7934  | MILLER | CLERK     | 7782 | 23-JAN-82 | 1300 |      | 10     |

</PRE>

To view the employees in department 10, and only their employee ids, names, and salaries, create the following procedure:

```

CREATE OR REPLACE PROCEDURE showemps_10 IS
 ignore_more BOOLEAN;
begin
 ignore_more := OWA_UTIL.TABLEPRINT
 ('EMP', 'BORDER', OWA_UTIL.PRE_TABLE,
 'empno, ename, sal', 'WHERE deptno=10 ORDER BY empno',
 'Employee Number, Name, Salary');
END;

```

### A request for a URL like

`http://myhost:7777/pls/hr/showemps_10`

would return the following to the client:

```

<PRE>

| Employee Number |Name | Salary |

| 7782 | CLARK | 2450 |
| 7839 | KING | 5000 |
| 7934 | MILLER | 1300 |

</PRE>

```

For browsers that support HTML tables, to view the department table in an HTML table, create the following procedure:

```

CREATE OR REPLACE PROCEDURE showdept IS
 ignore_more BOOLEAN;
BEGIN
 ignore_more := owa_util.tableprint('dept', 'BORDER');
END;

```

### A request for a URL like

`http://myhost:7777/pls/hr/showdept`

would return the following to the client:

```

<TABLE BORDER>
<TR>
<TH>DEPTNO</TH>
<TH>DNAME</TH>
<TH>LOC</TH>
</TR>
<TR>

```

```
<TD ALIGN="LEFT">10</TD>
<TD ALIGN="LEFT">ACCOUNTING</TD>
<TD ALIGN="LEFT">NEW YORK</TD>
</TR>
<TR>
<TD ALIGN="LEFT">20</TD>
<TD ALIGN="LEFT">RESEARCH</TD>
<TD ALIGN="LEFT">DALLAS</TD>
</TR>
<TR>
<TD ALIGN="LEFT">30</TD>
<TD ALIGN="LEFT">SALES</TD>
<TD ALIGN="LEFT">CHICAGO</TD>
</TR>
<TR>
<TD ALIGN="LEFT">40</TD>
<TD ALIGN="LEFT">OPERATIONS</TD>
<TD ALIGN="LEFT">BOSTON</TD>
</TR>
</TABLE>
```

A Web browser would format this to look like the following table:

<b>DEPTNO</b>	<b>DNAME</b>	<b>LOC</b>
10	ACCOUNTING	NEW YORK
20	RESEARCH	DALLAS
30	SALES	CHICAGO

## TODATE Function

This function converts the [DATETYPE Data Type](#) to the standard Oracle DATE type.

### Syntax

```
OWA_UTIL.TODATE(
 p_dateArray IN dateType)
RETURN DATE;
```

### Parameters

**Table 137–14** *TODATE Function Parameters*

Parameter	Description
p_dateArray	The value to convert.

## WHO\_CALLED\_ME Procedure

This procedure returns information (in the form of output parameters) about the PL/SQL code unit that invoked it.

### Syntax

```
OWA_UTIL.WHO_CALLED_ME(
 owner OUT VARCHAR2,
 name OUT VARCHAR2,
 lineno OUT NUMBER,
 caller_t OUT VARCHAR2);
```

### Parameters

**Table 137–15** WHO\_CALLED\_ME Procedure Parameters

Parameter	Description
owner	The owner of the program unit.
name	The name of the program unit. This is the name of the package, if the calling program unit is wrapped in a package, or the name of the procedure or function if the calling program unit is a standalone procedure or function. If the calling program unit is part of an anonymous block, this is NULL.
lineno	The line number within the program unit where the call was made.
caller_t	The type of program unit that made the call. The possibilities are: package body, anonymous block, procedure, and function. Procedure and function are only for standalone procedures and functions.



The SDO\_CS package contains functions and procedures for working with coordinate systems. You can perform explicit coordinate transformations on a single geometry or an entire layer of geometries (that is, all geometries in a specified column in a table).

- [Documentation of SDO\\_CS](#)

---

## Documentation of SDO\_CS

For a complete description of this package within the context of Oracle Spatial, see SDO\_CS in the *Oracle Spatial User's Guide and Reference*.

The `SDO_GCDR` package contains the Oracle Spatial geocoding subprograms, which let you geocode unformatted postal addresses.

- [Documentation of SDO\\_GCDR](#)

## Documentation of SDO\_GCDR

For a complete description of this package within the context of Oracle Spatial, see SDO\_GCDR in *Oracle Spatial User's Guide and Reference*.

The SDO\_GEOM package contains the geometry functions, which can be grouped into the following categories:

- **Relationship (True/False) between two objects:** RELATE, WITHIN\_DISTANCE
- **Validation:** VALIDATE\_GEOMETRY, VALIDATE\_LAYER
- **Single-object operations:** SDO\_ARC\_DENSIFY, SDO\_AREA, SDO\_BUFFER, SDO\_CENTROID, SDO\_CONVEXHULL, SDO\_LENGTH, SDO\_MBR, SDO\_POINTONSURFACE
- **Two-object operations:** SDO\_DISTANCE, SDO\_DIFFERENCE, SDO\_INTERSECTION, SDO\_UNION, SDO\_XOR

This chapter contains the following topic:

- [Documentation of SDO\\_GEOM](#)

---

## Documentation of SDO\_GEOM

For a complete description of this package within the context of Oracle Spatial, see SDO\_GEOM in the *Oracle Spatial User's Guide and Reference*.

The `SDO_GEOR` package contains functions and procedures for the Oracle Spatial GeoRaster feature, which lets you store, index, query, analyze, and deliver raster image data and its associated spatial vector geometry data and metadata.

- [Documentation of SDO\\_GEOR](#)

---

## Documentation of SDO\_GEOR

For complete description of this package within the context of Oracle Spatial, see SDO\_GEOR in the *Oracle Spatial GeoRaster*.



---

## SDO\_GEOR\_UTL

The `SDO_GEOR_UTL` package contains utility functions and procedures for the Oracle Spatial GeoRaster feature, including those related to using triggers with GeoRaster data.

- [Documentation of SDO\\_GEOR\\_UTL](#)

---

## Documentation of SDO\_GEOR\_UTL

For complete description of this package within the context of Oracle Spatial, see `SDO_GEOR_UTL` in the *Oracle Spatial GeoRaster*.

The SDO\_LRS package contains functions that create, modify, query, and convert linear referencing elements.

- [Documentation of SDO\\_LRS](#)

---

## Documentation of SDO\_LRS

For a complete description of this package within the context of Oracle Spatial, see `SDO_LRS` in the *Oracle Spatial User's Guide and Reference*.

---

## SDO\_MIGRATE

The `SDO_MIGRATE` package lets you upgrade geometry tables from previous releases of Oracle Spatial.

- [Documentation of SDO\\_MIGRATE](#)

---

## Documentation of SDO\_MIGRATE

For a complete description of this package within the context of Oracle Spatial, see `SDO_MIGRATE` in the *Oracle Spatial User's Guide and Reference*.

The `SDO_NET` package contains functions and procedures for working with data modeled as nodes and links in a network.

- [Documentation of SDO\\_NET](#)

---

## Documentation of SDO\_NET

For a complete description of this package within the context of Oracle Spatial, see SDO\_NET in the *Oracle Spatial Topology and Network Data Models*.



The SDO\_SAM package contains functions and procedures for spatial analysis and data mining.

- [Documentation of SDO\\_SAM](#)

---

## Documentation of SDO\_SAM

For a complete description of this package within the context of Oracle Spatial, see `SDO_SAM` in the *Oracle Spatial User's Guide and Reference*.

The SDO\_TOPO package contains subprograms for creating and managing Oracle Spatial topologies.

- [Documentation of SDO\\_TOPO](#)

---

## Documentation of SDO\_TOPO

For a complete description of this package within the context of Oracle Spatial, see SDO\_TOPO in the *Oracle Spatial Topology and Network Data Models*.

---

## SDO\_TOPO\_MAP

The `SDO_TOPO_MAP` package contains subprograms for editing Oracle Spatial topologies using a cache (TopoMap object).

- [Documentation of SDO\\_TOPO\\_MAP](#)

---

## Documentation of SDO\_TOPO\_MAP

For a complete description of this package within the context of Oracle Spatial, see `SDO_TOPO_MAP` in the *Oracle Spatial Topology and Network Data Models*.

The SDO\_TUNE package contains Spatial tuning functions and procedures.

- [Documentation of SDO\\_TUNE](#)

---

## Documentation of SDO\_TUNE

For complete description of this package within the context of Oracle Spatial, see `SDO_TUNE` in the *Oracle Spatial User's Guide and Reference*.



The `SDO_UTIL` package contains the utility functions and procedures for Oracle Spatial.

- [Documentation of SDO\\_UTIL](#)

---

## Documentation of SDO\_UTIL

For complete description of this package within the context of Oracle Spatial, see `SDO_UTIL` in the *Oracle Spatial User's Guide and Reference*.

The UTL\_COLL package lets PL/SQL programs use collection locators to query and update.

This chapter contains the following topics:

- [Summary of UTL\\_COLL Subprograms](#)

---

## Summary of UTL\_COLL Subprograms

**Table 151–1 UTL\_COLL Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">IS_LOCATOR Function</a> on page 151-3	Determines whether a collection item is actually a locator or not

## IS\_LOCATOR Function

This function determines whether a collection item is actually a locator or not.

### Syntax

```
UTL_COLL.IS_LOCATOR (
 coln IN STANDARD)
 RETURNS BOOLEAN;
```

### Pragmas

Asserts WNDS, WNPS and RNPS pragmas

### Parameters

**Table 151–2 IS\_LOCATOR Function Parameters**

Parameter	Description
coln	Nested table or varray item.

### Return Values

**Table 151–3 IS\_LOCATOR Function Return Values**

Return Value	Description
1	Collection item is indeed a locator.
0	Collection item is not a locator.

### Examples

```
CREATE OR REPLACE TYPE list_t as TABLE OF VARCHAR2(20);
/

CREATE OR REPLACE TYPE phone_book_t AS OBJECT (
 pno number,
 ph list_t);
/

CREATE TABLE phone_book OF phone_book_t
 NESTED TABLE ph STORE AS nt_ph;
```

```
CREATE TABLE phone_book1 OF phone_book_t
 NESTED TABLE ph STORE AS nt_ph_1 RETURN LOCATOR;

INSERT INTO phone_book VALUES(1, list_t('650-633-5707','650-323-0953'));
INSERT INTO phone_book1 VALUES(1, list_t('415-555-1212'));

CREATE OR REPLACE PROCEDURE chk_coll IS
 plist list_t;
 plist1 list_t;
BEGIN
 SELECT ph INTO plist FROM phone_book WHERE pno=1;

 SELECT ph INTO plist1 FROM phone_book1 WHERE pno=1;

 IF (UTL_COLL.IS_LOCATOR(plist)) THEN
 DBMS_OUTPUT.PUT_LINE('plist is a locator');
 ELSE
 DBMS_OUTPUT.PUT_LINE('plist is not a locator');
 END IF;

 IF (UTL_COLL.IS_LOCATOR(plist1)) THEN
 DBMS_OUTPUT.PUT_LINE('plist1 is a locator');
 ELSE
 DBMS_OUTPUT.PUT_LINE('plist1 is not a locator');
 END IF;

END chk_coll;

SET SERVEROUTPUT ON
EXECUTE chk_coll;
```

The UTL\_COMPRESS package provides a set of data compression utilities.

This chapter contains the following topics:

- [Using UTL\\_COMPRESS](#)
  - [Constants](#)
  - [Exceptions](#)
  - [Operational Notes](#)
- [Summary of UTL\\_COMPRESS Subprograms](#)

## Using UTL\_COMPRESS

- [Constants](#)
- [Exceptions](#)
- [Operational Notes](#)

### Constants

Define max number of handles for piecewise operations:

```
UTLCOMP_MAX_HANDLE CONSTANT PLS_INTEGER := 5;
```

### Exceptions

**Table 152–1 UTL\_COMPRESS Exceptions**

Exception	Description
BUFFER_TOO_SMALL	The compressed representation is too big.
DATA_ERROR	The input or output data stream was found to be an invalid format.
INVALID_ARGUMENT	One of the arguments was an invalid type or value.
INVALID_HANDLE	Invalid handle for piecewise compress or uncompress.
STREAM_ERROR	An error occurred during compression or uncompression of the data stream

### Operational Notes

- It is the caller's responsibility to free the temporary LOB returned by the LZ\* functions with `DBMS_LOB.FREETEMPORARY` call.
- A BFILE passed into LZ\_COMPRESS\* or LZ\_UNCOMPRESS\* has to be opened by `DBMS_LOB.FILEOPEN`.
- Under special circumstances (especially if the input has already been compressed) the output produced by one of the UTL\_COMPRESS subprograms may be the same size, or even slightly larger than, the input.



- The output of the UTL\_COMPRESS compressed data is compatible with gzip(with -n option)/gunzip on a single file.

---

## Summary of UTL\_COMPRESS Subprograms

**Table 152–2 UTL\_COMPRESS Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">ISOPEN Function</a> on page 152-5	Checks to see if the handle to a piecewise (un)compress context is open or closed
<a href="#">LZ_COMPRESS Functions and Procedures</a> on page 152-6	Compresses data using Lempel-Ziv compression algorithm
<a href="#">LZ_COMPRESS_ADD Procedure</a> on page 152-8	Adds a piece of compressed data
<a href="#">LZ_COMPRESS_CLOSE</a> on page 152-9	Closes and finishes piecewise compress operation
<a href="#">LZ_COMPRESS_OPEN</a> on page 152-10	Initializes a piecewise context that maintains the compress state and data
<a href="#">LZ_UNCOMPRESS Functions and Procedures</a> on page 152-11	Accepts compressed input, verifies it to be a valid and uncompresses it
<a href="#">LZ_UNCOMPRESS_EXTRACT Procedure</a> on page 152-13	Extracts a piece of uncompressed data
<a href="#">LZ_UNCOMPRESS_OPEN Function</a> on page 152-14	Initializes a piecewise context that maintains the uncompress state and data
<a href="#">LZ_UNCOMPRESS_CLOSE Procedure</a> on page 152-15	Closes and finishes the piecewise uncompress

## ISOPEN Function

This function checks to see if the handle to a piecewise (un)compress context is open or closed.

### Syntax

```
UTL_COMPRESS.ISOPEN(
 handle in binary_integer)
RETURN BOOLEAN;
```

### Parameters

**Table 152–3 ISOPEN Function Parameters**

Parameter	Description
handle	The handle to a piecewise uncompress context.

### Return Values

TRUE if the given piecewise handle is opened, otherwise FALSE.

### Examples

```
IF (UTL_COMPRESS.ISOPEN(myhandle) = TRUE) then
 UTL_COMPRESS.LZ_COMPRESS_CLOSE(myhandle, lob_1);
END IF;
```

Alternatively:

```
IF (UTL_COMPRESS.ISOPEN(myhandle) = TRUE) THEN
 UTL_COMPRESS.LZ_UNCOMPRESS_CLOSE(myhandle);
END IF;
```

## LZ\_COMPRESS Functions and Procedures

These functions and procedures compress data using Lempel-Ziv compression algorithm.

### Syntax

This function accept a RAW as input, compress it and return the compressed RAW result and metadata:

```
UTL_COMPRESS.LZ_COMPRESS (
 src IN RAW,
 quality IN BINARY_INTEGER DEFAULT 6)
RETURN RAW;
```

This function accept a BLOB as input, compress it and returns a temporary BLOB for the compressed data:

```
UTL_COMPRESS.LZ_COMPRESS (
 src IN BLOB,
 quality IN BINARY_INTEGER DEFAULT 6)
RETURN BLOB;
```

This procedure returns the compressed data into the existing BLOB(dst) which is trimmed to the compressed data size:

```
UTL_COMPRESS.LZ_COMPRESS (
 src IN BLOB,
 dst IN OUT NOCOPY BLOB,
 quality IN BINARY_INTEGER DEFAULT 6);
```

This function returns a temporary BLOB for the compressed data:

```
UTL_COMPRESS.LZ_COMPRESS (
 src IN BFILE,
 quality IN BINARY_INTEGER DEFAULT 6)
RETURN BLOB;
```

This procedure will return the compressed data into the existing BLOB(dst) which is trimmed to the compressed data size:

```
UTL_COMPRESS.LZ_COMPRESS (
 src IN BFILE,
 dst IN OUT NOCOPY BLOB,
 quality IN BINARY_INTEGER DEFAULT 6);
```

## Parameters

**Table 152–4** *LZ\_COMPRESS Function and Procedures Parameters*

Parameter	Description
src	Data (RAW, BLOB or BFILE) to be compressed.
dst	Destination for compressed data
quality	An integer in the range 1 to 9, 1=fast compression, 9=best compression, default=6

## Usage Notes

- `quality` is an optional compression tuning value. It allows the UTL\_COMPRESS user to choose between speed and compression quality, meaning the percentage of reduction in size. A faster compression speed will result in less compression of the data. A slower compression speed will result in more compression of the data. Valid values are [1..9], with 1=fastest and 9=slowest. The default 'quality' value is 6.

## LZ\_COMPRESS\_ADD Procedure

This procedure adds a piece of compressed data.

### Syntax

```
UTL_COMPRESS.LZ_COMPRESS_ADD (
 handle IN BINARY_INTEGER,
 dst IN OUT NOCOPY BLOB,
 src IN RAW);
```

### Parameters

**Table 152–5 LZ\_COMPRESS\_ADD Procedure Parameters**

Parameter	Description
handle	The handle to a piecewise compress context.
dst	The opened LOB from LZ_COMPRESS_OPEN to store compressed data.
src	The input data to be compressed.

### Exceptions

- `invalid_handle` - out of range invalid or unopened handle.
- `invalid_argument` - NULL handle, src, dst, or invalid dst.

## LZ\_COMPRESS\_CLOSE

This procedure closes and finishes piecewise compress operation.

### Syntax

```
UTL_COMPRESS.LZ_COMPRESS_CLOSE (
 handle IN BINARY_INTEGER,
 dst IN OUT NOCOPY BLOB);
```

### Parameters

**Table 152–6 LZ\_COMPRESS\_CLOSE Procedure Parameters**

Parameter	Description
handle	The handle to a piecewise compress context.
dst	The opened LOB from LZ_COMPRESS_OPEN to store compressed data.

### Exceptions

- `invalid_handle` - out of range invalid or uninitialized handle.
- `invalid_argument` - NULL handle, `dst`, or invalid `dst`.

## LZ\_COMPRESS\_OPEN

This function initializes a piecewise context that maintains the compress state and data.

### Syntax

```
UTL_COMPRESS.LZ_COMPRESS_OPEN (
 dst IN OUT NOCOPY BLOB,
 quality IN BINARY_INTEGER DEFAULT 6)
RETURN BINARY_INTEGER;
```

### Parameters

**Table 152–7 LZ\_COMPRESS\_OPEN Function Parameters**

Parameter	Description
dst	User supplied LOB to store compressed data.
quality	Speed versus efficiency of resulting compressed output. <ul style="list-style-type: none"><li>Valid values are the range 1..9, with a default value of 6.</li><li>1=fastest compression, 9=slowest compression and best compressed file size.</li></ul>

### Return Values

A handle to an initialized piecewise compress context.

### Exceptions

- invalid\_handle - invalid handle, too many open handles.
- invalid\_argument - NULL dst or invalid quality specified.

### Usage Notes

Close the opened handle with LZ\_COMPRESS\_CLOSE

- once the piecewise compress is completed
- in the event of an exception in the middle of process because lack of doing so will cause these handles to leak.



## LZ\_UNCOMPRESS Functions and Procedures

This procedure accepts as input a RAW, BLOB or BFILE compressed string, verifies it to be a valid compressed value, uncompresses it using Lempel-Ziv compression algorithm, and returns the uncompressed RAW or BLOB result.

### Syntax

This function returns uncompressed data as RAW:

```
UTL_COMPRESS.LZ_UNCOMPRESS(
 src IN RAW)
 RETURN RAW;
```

This function returns uncompressed data as a temporary BLOB:

```
UTL_COMPRESS.LZ_UNCOMPRESS(
 src IN BLOB)
 RETURN BLOB;
```

This procedure returns the uncompressed data into the existing BLOB(dst), which will be trimmed to the uncompressed data size:

```
UTL_COMPRESS.LZ_UNCOMPRESS(
 src IN BLOB,
 dst IN OUT NOCOPY BLOB);
```

This function returns a temporary BLOB for the uncompressed data:

```
UTL_COMPRESS.LZ_UNCOMPRESS(
 src IN BFILE)
 RETURN BLOB;
```

This procedure returns the uncompressed data into the existing BLOB(dst). The original dst data will be overwritten.

```
UTL_COMPRESS.LZ_UNCOMPRESS(
 src IN BFILE,
 dst IN OUT NOCOPY BLOB);
```

## Parameters

**Table 152–8** *LZ\_UNCOMPRESS Function and Procedures Parameters*

<b>Parameter</b>	<b>Description</b>
<code>src</code>	Compressed data.
<code>dst</code>	Destination for uncompressed data.

## LZ\_UNCOMPRESS\_EXTRACT Procedure

This procedure extracts a piece of uncompressed data.

### Syntax

```
UTL_COMPRESS.LZ_UNCOMPRESS_EXTRACT(
 handle IN BINARY_INTEGER,
 dst OUT NOCOPY RAW);
```

### Parameters

**Table 152–9** LZ\_UNCOMPRESS\_EXTRACT Function Parameters

Parameter	Description
handle	The handle to a piecewise uncompress context.
dst	The uncompressed data.

### Exceptions

- `no_data_found` - finished uncompress.
- `invalid_handle` - out of range invalid or uninitialized handle.
- `invalid_argument` - NULL handle.

## LZ\_UNCOMPRESS\_OPEN Function

This function initializes a piecewise context that maintains the uncompress state and data.

### Syntax

```
UTL_COMPRESS.LZ_UNCOMPRESS_OPEN(
 src IN BLOB)
RETURN BINARY_INTEGER;
```

### Parameters

**Table 152–10 LZ\_UNCOMPRESS\_OPEN Function Parameters**

Parameter	Description
src	The input data to be uncompressed.

### Return Values

A handle to an initialized piecewise compress context.

### Exceptions

- `invalid_handle` - invalid handle, too many open handles.
- `invalid_argument` - NULL src.

### Usage Notes

Close the opened handle with `LZ_UNCOMPRESS_CLOSE`

- once the piecewise uncompress is completed
- in the event of an exception in the middle of process because lack of doing so will cause these handles to leak.

## LZ\_UNCOMPRESS\_CLOSE Procedure

This procedure closes and finishes the piecewise uncompress.

### Syntax

```
UTL_COMPRESS.LZ_UNCOMPRESS_CLOSE(
 handle IN BINARY_INTEGER);
```

### Parameters

**Table 152–11** LZ\_UNCOMPRESS\_CLOSE Procedure Parameters

Parameter	Description
handle	The handle to a piecewise uncompress context.

### Exceptions

- `invalid_handle` - out of range invalid or uninitialized handle.
- `invalid_argument` - NULL handle.



The UTL\_DBWS package provides database web services.

This chapter contains the following topics:

- [Using UTL\\_DBWS](#)
  - [Supported Keys and Default Settings for Standard Call Properties](#)
- [Summary of UTL\\_DBWS Subprograms](#)

---

## Using UTL\_DBWS

- [Supported Keys and Default Settings for Standard Call Properties](#)

### Supported Keys and Default Settings for Standard Call Properties

**Table 153–1 Supported Keys and Default Settings for Standard Call Properties**

Key	Explanation of Value, Default value
'USERNAME '	User name for authentication.
'PASSWORD '	Password for authentication.
'ENCODINGSTYLE_URI '	Encoding style specified as a namespace URI. The default value is the SOAP 1.1 encoding <a href="http://schemas.xmlsoap.org/soap/encoding/">http://schemas.xmlsoap.org/soap/encoding/</a> .
'OPERATION_STYLE '	Standard property for operation style. Set to 'RPC' if the operation style is RPC, 'DOCUMENT' if the operation style is document.
'SESSION_MAINTAIN '	This boolean property is used by a service client to indicate whether or not it wants to participate in a session with a service endpoint. If this property is set to 'TRUE', the service client indicates that it wants the session to be maintained. If set to 'FALSE', the session is not maintained. The default value for this property is 'FALSE'
'SOAPACTION_USE '	This boolean property indicates whether or not SOAPAction is to be used. The default value of this property is 'FALSE'.
'SOAPACTION_URI '	Indicates the SOAPAction URI if the SOAPACTION_USE property is set to 'TRUE'



---

## Summary of UTL\_DBWS Subprograms

**Table 153–2 UTL\_DBWS Subprograms**

Subprogram	Description
<a href="#">CREATE_CALL Function</a> on page 153-4	Creates a Call instance
<a href="#">CREATE_SERVICE Function</a> on page 153-5	Creates a Service instance
<a href="#">GET_IN_PARAMETER_TYPES Function</a> on page 153-6	Lists the XML type of the input parameters of the Call that is returned
<a href="#">GET_OUT_PARAMETER_TYPES Function</a> on page 153-7	Lists the XML type of the output parameters of the Call that is returned
<a href="#">GET_OUTPUT_VALUES Function</a> on page 153-8	Obtains the output arguments after a Call invocation
<a href="#">GET_PORTS Function</a> on page 153-9	Lists the qualified names of all of the ports in a service
<a href="#">GET_PROPERTY Function</a> on page 153-10	Returns the value of a particular property on a Call
<a href="#">GET_RETURN_TYPE Function</a> on page 153-11	Lists the XML type that is returned by the given Call
<a href="#">GET_SERVICES Function</a> on page 153-12	Lists the qualified names of the services defined in a WDSL document
<a href="#">INVOKE Function</a> on page 153-13	Invokes a specific operation using a synchronous request-response interaction mode
<a href="#">RELEASE_ALL_SERVICES Procedure</a> on page 153-14	Releases all Service instances
<a href="#">RELEASE_CALL Procedure</a> on page 153-15	Releases a particular Call instance
<a href="#">RELEASE_SERVICE Procedure</a> on page 153-16	Releases a particular Service instance
<a href="#">REMOVE_PROPERTY Procedure</a> on page 153-17	Clears the value of a particular property on a Call
<a href="#">SET_PROPERTY Procedure</a> on page 153-18	Sets the value of a particular property on a Call

## CREATE\_CALL Function

This procedure creates a Call instance.

### Syntax

```
UTL_DBWS.CREATE_CALL (
 service_handle SERVICE,
 port_name QNAME,
 operation_name QNAME)
RETURN CALL;
```

### Parameters

**Table 153–3 CREATE\_CALL Function Parameters**

Parameter	Description
service_handle	The Service instance to be called.
port_name	The qualified name for the port. Use the first port if this is NULL.
operation_name	The qualified name for the operation.

### Return Values

**Table 153–4 CREATE\_CALL Return Values**

Parameter	Description
CALL	Returns a handle to the Call instance.

## CREATE\_SERVICE Function

This procedure creates a Service instance.

### Syntax

```
UTL_DBWS.CREATE_SERVICE(
 wsdl_document_location URITYPE,
 service_name QNAME)
RETURN SERVICE;
```

### Parameters

**Table 153–5 CREATE\_SERVICE Function Parameters**

Parameter	Description
wsdl_document_location	The URL for the WSDL document location for the service
service_name	The qualified name for the service. Use the first service if this is NULL.

### Return Values

**Table 153–6 CREATE\_SERVICE Return Values**

Parameter	Description
SERVICE	Returns a handle to the Service instance.

## GET\_IN\_PARAMETER\_TYPES Function

This procedure lists the XML type of the input parameters of the Call that is returned.

### Syntax

```
UTL_DBWS.GET_IN_PARAMETER_TYPES(
 call_handle CALL)
RETURN QNAME_LIST;
```

### Parameters

**Table 153–7** *GET\_IN\_PARAMETER\_TYPES Function Parameters*

Parameter	Description
call_handle	The Service instance whose input types are returned.

### Return Values

**Table 153–8** *GET\_IN\_PARAMETER\_TYPES Function Return Values*

Parameter	Description
QNAME_LIST	The list of the XML type of the input parameters of the Call that is returned.

## GET\_OUT\_PARAMETER\_TYPES Function

This procedure lists the XML type of the output parameters of the Call that is returned.

### Syntax

```
UTL_DBWS.GET_OUT_PARAMETER_TYPES(
 call_handle CALL)
RETURN QNAME_LIST;
```

### Parameters

**Table 153–9 GET\_OUT\_PARAMETER\_TYPES Function Parameters**

Parameter	Description
call_handle	The Service instance whose output types are returned.

### Return Values

**Table 153–10 GET\_OUT\_PARAMETER\_TYPES Function Return Values**

Parameter	Description
QNAME_LIST	The list of the XML type of the input parameters of the Call that is returned.

## GET\_OUTPUT\_VALUES Function

This procedure obtains the output arguments after a Call invocation.

### Syntax

```
UTL_DBWS.GET_OUTPUT_VALUES(
 call_handle CALL)
RETURN ANYDATA_LIST;
```

### Parameters

**Table 153–11** *GET\_OUTPUT\_VALUES Function Parameters*

Parameter	Description
call_handle	The instance of the Call.

### Return Values

**Table 153–12** *GET\_OUTPUT\_VALUES Function Return Values*

Parameter	Description
ANYDATA_LIST	Returns the output arguments in order.

## GET\_PORTS Function

This procedure lists the qualified names of all of the ports in a service.

### Syntax

```
UTL_DBWS.GET_PORTS(
 service_handle SERVICE)
 RETURN QNAME_LIST;
```

### Parameters

**Table 153–13** *GET\_PORTS Function Parameters*

Parameter	Description
service_handle	The service instance whose ports are returned

### Return Values

**Table 153–14** *GET\_PORTS Function Return Values*

Parameter	Description
QNAME_LIST	Returns a list of the qualified names of all ports in a service

## GET\_PROPERTY Function

This procedure returns the value of a particular property on a Call.

### Syntax

```
UTL_DBWS.GET_PROPERTY(
 call_handle CALL,
 key VARCHAR2)
RETURN value VARCHAR2;
```

### Parameters

**Table 153–15** *GET\_PROPERTY Function Parameters*

Parameter	Description
call_handle	The the instance of the Call
key	The key for the property (see <a href="#">Using UTL_DBWS</a> on page 153-2)

### Return Values

**Table 153–16** *GET\_PROPERTY Function Return Values*

Parameter	Description
value	Returns the value of a particular property on a Call.



## GET\_RETURN\_TYPE Function

This procedure lists the XML type that is returned by the given Call.

### Syntax

```
UTL_DBWS.GET_RETURN_TYPE (
 call_handle CALL)
 RETURN QNAME;
```

### Parameters

**Table 153–17** *GET\_RETURN\_TYPE Function Parameters*

Parameter	Description
call_handle	The Service instance whose return type is returned.

### Return Values

**Table 153–18** *GET\_RETURN\_TYPE Function Return Values*

Parameter	Description
QNAME	The type that is returned.

## GET\_SERVICES Function

This function lists the qualified names of the services defined in a WSDL document.

### Syntax

```
UTL_DBWS.GET_SERVICES(
 wsdl_document_location URITYPE)
RETURN QNAME_LIST;
```

### Parameters

**Table 153–19** *GET\_RETURN\_TYPE Function Parameters*

Parameter	Description
wsdl_document_location	The Service instance whose return type is returned.

### Return Values

**Table 153–20** *GET\_RETURN\_TYPE Function Return Values*

Parameter	Description
QNAME_LIST	A list of the qualified names of the services defined in the WSDL document.

## INVOKE Function

This procedure invokes a specific operation using a synchronous request-response interaction mode.

### Syntax

```
UTL_DBWS.INVOKE(
 call_handle CALL,
 input_params ANYDATA_LIST)
RETURN ANYDATA;
```

### Parameters

**Table 153–21 INVOKE Function Parameters**

Parameter	Description
call_handle	The Service instance whose return type is returned.
input_params	The input parameters for this invocation.

### Return Values

**Table 153–22 INVOKE Function Return Values**

Parameter	Description
ANYDATA	Returns the return value or NULL.

## RELEASE\_ALL\_SERVICES Procedure

This procedure releases all Service instances.

### Syntax

```
UTL_DBWS.RELEASE_ALL_SERVICES;
```

## RELEASE\_CALL Procedure

This procedure releases a particular Call instance.

### Syntax

```
UTL_DBWS.RELEASE_CALL(
 call_handle CALL);
```

### Parameters

**Table 153–23** *RELEASE\_CALL Procedure Parameters*

Parameter	Description
call_handle	The Call instance that is to be released.

## RELEASE\_SERVICE Procedure

This procedure releases a particular Service instance.

### Syntax

```
UTL_DBWS.RELEASE_SERVICE (
 service_handle SERVICE);
```

### Parameters

**Table 153–24** *RELEASE\_SERVICE Procedure Parameters*

Parameter	Description
service_handle	The Service instance that is to be released.

### Usage Notes

This will implicitly release all Call instances that have been created for this Service instance.

## REMOVE\_PROPERTY Procedure

This procedure clears the value of a particular property on a Call.

### Syntax

```
UTL_DBWS.REMOVE_PROPERTY(
 call_handle CALL,
 key VARCHAR2);
```

### Parameters

**Table 153–25 REMOVE\_PROPERTY Procedure Parameters**

Parameter	Description
call_handle	The Call instance.
key	The key for the property (see <a href="#">Using UTL_DBWS</a> on page 153-2).

## SET\_PROPERTY Procedure

This procedure sets the value of a particular property on a Call.

### Syntax

```
UTL_DBWS.SET_PROPERTY(
 call_handle CALL,
 key VARCHAR2,
 value VARCHAR2);
```

### Parameters

**Table 153–26** SET\_PROPERTY Function Parameters

Parameter	Description
call_handle	The instance of the Call.
key	The key for the property (see <a href="#">Using UTL_DBWS</a> on page 153-2).
value	The value for the property.



The `UTL_ENCODE` package provides functions that encode `RAW` data into a standard encoded format so that the data can be transported between hosts. You can use `UTL_ENCODE` functions to encode the body of email text. The package also contains the decode counterpart functions of the encode functions. The functions follow published standards for encoding to accommodate non-Oracle utilities on the sending or receiving ends.

This chapter contains the following topic:

- [Summary of UTL\\_ENCODE Subprograms](#)

---

## Summary of UTL\_ENCODE Subprograms

**Table 154–1 UTL\_ENCODE Package Subprograms**

Subprogram	Description
<a href="#">BASE64_DECODE Function</a> on page 154-3	Reads the base 64-encoded RAW input string and decodes it to its original RAW value
<a href="#">BASE64_ENCODE Function</a> on page 154-4	Encodes the binary representation of the RAW value into base 64 elements and returns it in the form of a RAW string
<a href="#">MIMEHEADER_DECODE Function</a> on page 154-5	Decodes a string from mime header format
<a href="#">MIMEHEADER_ENCODE Function</a> on page 154-7	Encodes a string into mime header format
<a href="#">QUOTED_PRINTABLE_DECODE Function</a> on page 154-9	Reads the varchar2 quoted printable format input string and decodes it to the corresponding RAW string
<a href="#">QUOTED_PRINTABLE_ENCODE Function</a> on page 154-10	Reads the RAW input string and encodes it to the corresponding quoted printable format string
<a href="#">TEXT_DECODE Function</a> on page 154-11	Decodes a character set sensitive text string
<a href="#">TEXT_ENCODE Function</a> on page 154-13	Encodes a character set sensitive text string
<a href="#">UUDECODE Function</a> on page 154-15	Reads the RAW uuencode format input string and decodes it to the corresponding RAW string
<a href="#">UUENCODE Function</a> on page 154-16	Reads the RAW input string and encodes it to the corresponding uuencode format string

## BASE64\_DECODE Function

This function reads the base 64-encoded RAW input string and decodes it to its original RAW value.

### Syntax

```
UTL_ENCODE.BASE64_DECODE (
 r IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma RESTRICT_REFERENCES(base64_decode, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 154–2** *BASE64\_DECODE Function Parameters*

Parameter	Description
r	The RAW string containing base 64-encoded data. There are no defaults or optional parameters.

### Return Values

**Table 154–3** *BASE64\_DECODE Function Return Values*

Return	Description
RAW	Contains the decoded string

## BASE64\_ENCODE Function

This function encodes the binary representation of the RAW value into base 64 elements and returns it in the form of a RAW string.

### Syntax

```
UTL_ENCODE.BASE64_ENCODE (
 r IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma RESTRICT_REFERENCES(base64_encode, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 154–4** *BASE64\_ENCODE Function Parameters*

Parameter	Description
r	The RAW value to be encoded. There are no defaults or optional parameters.

### Return Values

**Table 154–5** *BASE64\_ENCODE Function Return Values*

Return	Description
RAW	Contains the encoded base 64 elements

## MIMEHEADER\_DECODE Function

This function accepts as input an "encoded word" of the form:

```
=?<charset>?<encoding>?<encoded text>?=
=?ISO-8859-1?Q?Here is some encoded text?=
```

The `<encoded text>` is encapsulated in mime header tags which give the `MIMEHEADER_DECODE` function information about how to decode the string. The mime header metadata tags are stripped from the input string and the `<encoded text>` is converted to the base database character set as follows:

- If this is a UTF16 platform, convert the encoded text from UTF16 to ASCII
- If this is an EBCDIC platform, convert the encoded text from EBCDIC to ASCII
- If this is an ASCII or UTF8 platform, no conversion needed

The string is decoded using either quoted-printable or base64 decoding, as specified by the `<encoding>` metadata tag in the encoded word. The resulting converted and decoded text is returned to the caller as a `VARCHAR2` string.

### Syntax

```
UTL_ENCODE.MIMEHEADER_DECODE (
 buf IN VARCHAR2 CHARACTER SET ANY_CS)
RETURN data VARCHAR2 CHARACTER SET buf%CHARSET;
```

### Parameters

**Table 154–6** *MIMEHEADER\_DECODE Function Parameters*

Parameter	Description
buf	The encoded text data with mime header format tags.

### Return Values

**Table 154–7** *MIMEHEADER\_DECODE Function Return Values*

Return	Description
data	The encoded text data with mime header format tags

### Examples

```
v2:=utl_encode.mimeheader_decode('=?ISO-8859-1?Q?Here is some encoded text?');
```

## MIMEHEADER\_ENCODE Function

This function accepts as input an "encoded word" of the form:

```
=?<charset>?<encoding>?<encoded text>?=
=?ISO-8859-1?Q?Here is some text?=
```

The `buf` input parameter is the text to be encoded and becomes the `<encoded text>`.

The `<encoding>` value is either "Q" or "B" for quoted-printable encode or base64 encoding respectively. The `ENCODING` input parameter accepts as valid values `UTL_ENCODE.QUOTED_PRINTABLE` or `UTL_ENCODE.BASE64` or `NULL`. If `NULL`, quoted-printable encoding is selected as a default value.

The `<charset>` value is specified as the input parameter `encode_charset`. If `NULL`, the database character set is selected as a default value.

The mimeheader encoding process includes conversion of the `buf` input string to the character set specified by the `encode_charset` parameter. The converted string is encoded to either quoted-printable or base64 encoded format. The mime header tags are appended and prepended.

Finally, the string is converted to the base character set of the database:

- If this is a UTF16 platform, convert the encoded text to UTF16
- If this is an EBCDIC platform, convert the encoded text to EBCDIC
- If this is an ASCII or UTF8 platform, no conversion needed.

## Syntax

```
UTL_ENCODE.MIMEHEADER_ENCODE (
 buf IN VARCHAR2 CHARACTER SET ANY_CS,
 encode_charset IN VARCHAR2 DEFAULT NULL,
 encoding IN PLS_INTEGER DEFAULT NULL)
RETURN string VARCHAR2 CHARACTER SET buf%CHARSET;
```

## Parameters

**Table 154–8** *MIMEHEADER\_ENCODE Function Parameters*

Parameter	Description
<code>buf</code>	The text data.

**Table 154–8 (Cont.) MIMEHEADER\_ENCODE Function Parameters**

<b>Parameter</b>	<b>Description</b>
encode_charset	The target character set.
encoding	The encoding format. Valid values are UTL_ENCODE.BASE64, UTL_ENCODE.QUOTED_PRINTABLE and NULL

## Return Values

**Table 154–9 BASE64\_ENCODE Function Return Values**

<b>Return</b>	<b>Description</b>
string	A VARCHAR2 encoded string with mime header format tags.



## QUOTED\_PRINTABLE\_DECODE Function

This function reads the `varchar2` quoted printable format input string and decodes it to the corresponding `RAW` string.

### Syntax

```
UTL_ENCODE.QUOTED_PRINTABLE_DECODE (
 r IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma RESTRICT_REFERENCES(quoted_printable_decode, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 154–10 QUOTED\_PRINTABLE\_DECODE Function Parameters**

Parameters	Description
<code>r</code>	The <code>RAW</code> string containing a quoted printable data string. There are no defaults or optional parameters.

### Return Values

**Table 154–11 QUOTED\_PRINTABLE\_DECODE Function Return Values**

Return	Description
<code>RAW</code>	The decoded string

## QUOTED\_PRINTABLE\_ENCODE Function

This function reads the RAW input string and encodes it to the corresponding quoted printable format string.

### Syntax

```
UTL_ENCODE.QUOTED_PRINTABLE_ENCODE (
 r IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma RESTRICT_REFERENCES(quoted_printable_encode, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 154–12** *QUOTED\_PRINTABLE\_ENCODE Function Parameters*

Parameter	Description
r	The RAW string. There are no defaults or optional parameters.

### Return Values

**Table 154–13** *QUOTED\_PRINTABLE\_ENCODE Function Return Values*

Return	Description
RAW	Contains the quoted printable string

## TEXT\_DECODE Function

This function converts the input text to the target character set as specified by the `encode_charset` parameter, if not `NULL`. The encoded text is converted to the base character set of database, as follows:

- If this is a UTF16 platform, convert the encoded text from UTF16 to ASCII
- If this is an EBCDIC platform, convert the encoded text from EBCDIC to ASCII
- If this is an ASCII or UTF8 platform, no conversion needed

You can decode from either quoted-printable or base64 format, with regard to each encoding parameter. If `NULL`, quoted-printable is selected as a default decoding format. If `encode_charset` is not `NULL`, you convert the string from the specified character set to the database character set. The resulting decoded and converted text string is returned to the caller.

### Syntax

```
UTL_ENCODE.TEXT_DECODE(
 buf IN VARCHAR2 CHARACTER SET ANY_CS,
 encode_charset IN VARCHAR2 DEFAULT NULL,
 encoding IN PLS_INTEGER DEFAULT NULL)
RETURN string VARCHAR2 CHARACTER SET buf%CHARSET;
```

### Parameters

**Table 154–14** *TEXT\_DECODE Function Parameters*

Parameter	Description
<code>buf</code>	The encoded text data.
<code>encode_charset</code>	The source character set.
<code>encoding</code>	The encoding format. Valid values are <code>UTL_ENCODE.BASE64</code> , <code>UTL_ENCODE.QUOTED_PRINTABLE</code> and <code>NULL</code> .

### Return Values

**Table 154–15** *QUOTED\_PRINTABLE\_ENCODE Function Return Values*

Return	Description
<code>string</code>	A <code>VARCHAR2</code> decoded text string.

### Examples

```
v2:=UTL_ENCODE.TEXT_DECODE(
 'Here is some text',
 WE8ISO8859P1,
 UTL_ENCODE.BASE64);
```

## TEXT\_ENCODE Function

This function converts the input text to the target character set as specified by the `encode_charset` parameter, if not `NULL`. The text is encoded to either base64 or quoted-printable format, as specified by the `encoding` parameter. Quoted-printable is selected as a default if `ENCODING` is `NULL`.

The encoded text is converted to the base character set of the database:

- If this is a UTF16 platform, convert the encoded text to UTF16
- If this is an EBCDIC platform, convert the encoded text to EBCDIC
- If this is an ASCII or UTF8 platform, no conversion needed

The resulting encoded and converted text string is returned to the caller.

### Syntax

```
UTL_ENCODE.TEXT_ENCODE (
 buf IN VARCHAR2 CHARACTER SET ANY_CS,
 encode_charset IN VARCHAR2 DEFAULT NULL,
 encoding IN PLS_INTEGER DEFAULT NULL)
RETURN string VARCHAR2 CHARACTER SET buf%CHARSET;
```

### Parameters

**Table 154–16** *TEXT\_ENCODE Function Parameters*

Parameter	Description
<code>buf</code>	The text data.
<code>encode_charset</code>	The target character set.
<code>encoding</code>	The encoding format. Valid values are <code>UTL_ENCODE.BASE64</code> , <code>UTL_ENCODE.QUOTED_PRINTABLE</code> and <code>NULL</code> .

### Return Values

**Table 154–17** *TEXT\_ENCODE Function Return Values*

Return	Description
<code>string</code>	A <code>VARCHAR2</code> encoded string with mime header format tags.

### Examples

```
v2:=utl_encode.text_encode(
 'Here is some text',
 'WE8ISO8859P1',
 UTL_ENCODE.BASE64);
```

## UUDECODE Function

This function reads the RAW uuencode format input string and decodes it to the corresponding RAW string. See "[UUENCODE Function](#)" on page 154-16 for discussion of the cumulative nature of UUENCODE and UUDECODE for data streams.

### Syntax

```
UTL_ENCODE.UUDECODE (
 r IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma RESTRICT_REFERENCES(uudecode, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 154–18 UUDECODE Function Parameters**

Parameter	Description
r	The RAW string containing the uuencoded data string. There are no defaults or optional parameters.

### Return Values

**Table 154–19 UUDECODE Function Return Values**

Return	Description
RAW	The decoded RAW string

## UUENCODE Function

This function reads the RAW input string and encodes it to the corresponding uuencode format string. The output of this function is cumulative, in that it can be used to encode large data streams, by splitting the data stream into acceptably sized RAW values, encoded, and concatenated into a single encoded string.

### Syntax

```
UTL_ENCODE.UUENCODE (
 r IN RAW,
 type IN PLS_INTEGER DEFAULT 1,
 filename IN VARCHAR2 DEFAULT NULL,
 permission IN VARCHAR2 DEFAULT NULL) RETURN RAW;
```

### Pragmas

```
pragma RESTRICT_REFERENCES(uuencode, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 154–20** UUENCODE Function Parameters

Parameter	Description
r	RAW string
type	Optional number parameter containing the type of uuencoded output. Options: complete—a defined PL/SQL constant with a value of 1. (default) header_piece ...middle_piece ...end_piece
filename	Optional varchar2 parameter containing the uuencode filename; the default is uuencode.txt
permission	Optional varchar2 parameter containing the permission mode; the default is 0 (a text string zero).

### Return Values

**Table 154–21** UUENCODE Function Return Values

Return	Description
RAW	Contains the uuencode format string



With the `UTL_FILE` package, PL/SQL programs can read and write operating system text files. `UTL_FILE` provides a restricted version of operating system stream file I/O.

This chapter contains the following topics:

- [Using UTL\\_FILE](#)
  - [Security Model](#)
  - [Types](#)
  - [Operational Notes](#)
  - [Rules and Limits](#)
  - [Exceptions](#)
  - [Examples](#)
- [Summary of UTL\\_FILE Subprograms](#)

## Using UTL\_FILE

- [Security Model](#)
- [Types](#)
- [Operational Notes](#)
- [Rules and Limits](#)
- [Exceptions](#)
- [Examples](#)

### Security Model

UTL\_FILE is available for both client-side and server-side PL/SQL. Both the client (text I/O) and server implementations are subject to server-side file system permission checking.

In the past, accessible directories for the UTL\_FILE functions were specified in the initialization file using the UTL\_FILE\_DIR parameter. However, UTL\_FILE\_DIR access is not recommended. It is recommended that you use the CREATE DIRECTORY feature, which replaces UTL\_FILE\_DIR. Directory objects offer more flexibility and granular control to the UTL\_FILE application administrator, can be maintained dynamically (that is, without shutting down the database), and are consistent with other Oracle tools. CREATE DIRECTORY privilege is granted only to SYS and SYSTEM by default.

---

---

**Note:** Use the CREATE DIRECTORY feature instead of UTL\_FILE\_DIR for directory access verification.

---

---

On UNIX systems, the owner of a file created by the FOPEN function is the owner of the shadow process running the instance. Normally, this owner is ORACLE. Files created using FOPEN are always writable and readable using the UTL\_FILE subprograms, but non privileged users who need to read these files outside of PL/SQL may need access from a system administrator.

---

---

**Caution:** ■

- The privileges needed to access files in a directory object are operating system specific. UTL\_FILE directory object privileges give you read and write access to all files within the specified directory.
  - Attempting to apply invalid options will give rise to unpredictable results.
- 
- 

## Types

The contents of FILE\_TYPE are private to the UTL\_FILE package. You should not reference or change components of this record.

```
TYPE file_type IS RECORD (
 id BINARY_INTEGER,
 datatype BINARY_INTEGER);
```

## Operational Notes

The file location and file name parameters are supplied to the FOPEN function as separate strings, so that the file location can be checked against the list of accessible directories as specified by the ALL\_DIRECTORIES view of accessible directory objects. Together, the file location and name must represent a legal filename on the system, and the directory must be accessible. A subdirectory of an accessible directory is not necessarily also accessible; it too must be specified using a complete path name matching an ALL\_DIRECTORIES object.

UTL\_FILE implicitly interprets line terminators on read requests, thereby affecting the number of bytes returned on a GET\_LINE call. For example, the len parameter of UTL\_FILE.GET\_LINE specifies the requested number of bytes of character data. The number of bytes actually returned to the user will be the lesser of:

- The GET\_LINE len parameter, or
- The number of bytes until the next line terminator character, or
- The max\_linesize parameter specified by UTL\_FILE.FOPEN

The FOPEN max\_linesize parameter must be a number in the range 1 and 32767. If unspecified, Oracle supplies a default value of 1024. The GET\_LINE len parameter must be a number in the range 1 and 32767. If unspecified, Oracle

supplies the default value of `max_linesize`. If `max_linesize` and `len` are defined to be different values, then the lesser value takes precedence.

`UTL_FILE.GET_RAW` ignores line terminators and returns the actual number of bytes requested by the `GET_RAW len` parameter.

When data encoded in one character set is read and Globalization Support is told (such as by means of `NLS_LANG`) that it is encoded in another character set, the result is indeterminate. If `NLS_LANG` is set, it should be the same as the database character set.

## Rules and Limits

Operating system-specific parameters, such as C-shell environment variables under UNIX, cannot be used in the file location or file name parameters.

`UTL_FILE` I/O capabilities are similar to standard operating system stream file I/O (`OPEN`, `GET`, `PUT`, `CLOSE`) capabilities, but with some limitations. For example, you call the `FOPEN` function to return a file handle, which you use in subsequent calls to `GET_LINE` or `PUT` to perform stream I/O to a file. When file I/O is done, you call `FCLOSE` to complete any output and free resources associated with the file.

---

---

**Note:** The `UTL_FILE` package is similar to the client-side `TEXT_IO` package currently provided by Oracle Procedure Builder. Restrictions for a server implementation require some API differences between `UTL_FILE` and `TEXT_IO`. In PL/SQL file I/O, errors are returned using PL/SQL exceptions.

---

---

## Exceptions

**Table 155–1** *UTL\_FILE Package Exceptions*

Exception Name	Description
<code>INVALID_PATH</code>	File location is invalid.
<code>INVALID_MODE</code>	The <code>open_mode</code> parameter in <code>FOPEN</code> is invalid.
<code>INVALID_FILEHANDLE</code>	File handle is invalid.
<code>INVALID_OPERATION</code>	File could not be opened or operated on as requested.
<code>READ_ERROR</code>	Operating system error occurred during the read operation.

**Table 155–1 (Cont.) UTL\_FILE Package Exceptions**

Exception Name	Description
WRITE_ERROR	Operating system error occurred during the write operation.
INTERNAL_ERROR	Unspecified PL/SQL error
CHARSETMISMATCH	A file is opened using FOPEN_NCHAR, but later I/O operations use nonchar functions such as PUTF or GET_LINE.
FILE_OPEN	The requested operation failed because the file is open.
INVALID_MAXLINESIZE	The MAX_LINESIZE value for FOPEN( ) is invalid; it should be within the range 1 to 32767.
INVALID_FILENAME	The filename parameter is invalid.
ACCESS_DENIED	Permission to access to the file location is denied.
INVALID_OFFSET	Causes of the INVALID_OFFSET exception: <ul style="list-style-type: none"> <li>■ ABSOLUTE_OFFSET = NULL and RELATIVE_OFFSET = NULL, or</li> <li>■ ABSOLUTE_OFFSET &lt; 0, or</li> <li>■ Either offset caused a seek past the end of the file</li> </ul>
DELETE_FAILED	The requested file delete operation failed.
RENAME_FAILED	The requested file rename operation failed.

Procedures in UTL\_FILE can also raise predefined PL/SQL exceptions such as NO\_DATA\_FOUND or VALUE\_ERROR.

## Examples

### Example 1

---



---

**Note:** The examples are UNIX-specific.

---



---

Given the following:

```
SQL> CREATE DIRECTORY log_dir AS '/appl/gl/log';
SQL> GRANT READ ON DIRECTORY log_dir TO DBA;

SQL> CREATE DIRECTORY out_dir AS '/appl/gl/user'';
```

```
SQL> GRANT READ ON DIRECTORY user_dir TO PUBLIC;
```

The following file locations and filenames are valid and accessible as follows:

File Location	Filename	Accessible By
/appl/gl/log	L12345.log	Users with DBA privilege
/appl/gl/user	u12345.tmp	All users

The following file locations and filenames are invalid:

File Location	Filename	Invalid Because
/appl/gl/log/backup	L12345.log	# subdirectories are not accessible
/APPL/gl/log	L12345.log	# directory strings must follow case sensitivity rules as required by the O/S
/appl/gl/log	backup/L1234.log	# filenames may not include portions of directory paths
/user/tmp	L12345.log	# no corresponding CREATE DIRECTORY command has been issued

## Example 2

```
DECLARE
 V1 VARCHAR2(32767);
 F1 UTL_FILE.FILE_TYPE;
BEGIN
 -- In this example MAX_LINESIZE is less than GET_LINE's length request
 -- so the number of bytes returned will be 256 or less if a line terminator is
 -- seen.
 F1 := UTL_FILE.FOPEN('MYDIR', 'MYFILE', 'R', 256);
 UTL_FILE.GET_LINE(F1, V1, 32767);
 UTL_FILE.FCLOSE(F1);

 -- In this example, FOPEN's MAX_LINESIZE is NULL and defaults to 1024,
 -- so the number of bytes returned will be 1024 or less if a line terminator
 -- is seen.
 F1 := UTL_FILE.FOPEN('MYDIR', 'MYFILE', 'R');
 UTL_FILE.GET_LINE(F1, V1, 32767);
 UTL_FILE.FCLOSE(F1);
```

```
-- In this example, GET_LINE doesn't specify a number of bytes, so it defaults
to
-- the same value as FOPEN's MAX_LINESIZE which is NULL in this case and
defaults to 1024.
-- So the number of bytes returned will be 1024 or less if a line terminator
is seen.
F1 := UTL_FILE.FOPEN('MYDIR','MYFILE','R');
UTL_FILE.GET_LINE(F1,v1);
UTL_FILE.FCLOSE(F1);
END;
```

---

## Summary of UTL\_FILE Subprograms

**Table 155–2 UTL\_FILE Subprograms**

Subprogram	Description
<a href="#">FCLOSE Procedure</a> on page 155-10	Closes a file
<a href="#">FCLOSE_ALL Procedure</a> on page 155-11	Closes all open file handles
<a href="#">FCOPY Procedure</a> on page 155-12	Copies a contiguous portion of a file to a newly created file
<a href="#">FFLUSH Procedure</a> on page 155-13	Physically writes all pending output to a file
<a href="#">FGETATTR Procedure</a> on page 155-14	Reads and returns the attributes of a disk file
<a href="#">FGETPOS Function</a> on page 155-15	Returns the current relative offset position within a file, in bytes
<a href="#">FOPEN Function</a> on page 155-16	Opens a file for input or output
<a href="#">FOPEN_NCHAR Function</a> on page 155-18	Opens a file in Unicode for input or output
<a href="#">FREMOVE Procedure</a> on page 155-19	Deletes a disk file, assuming that you have sufficient privileges
<a href="#">FRENAME Procedure</a> on page 155-20	Renames an existing file to a new name, similar to the UNIX <code>mv</code> function
<a href="#">FSEEK Procedure</a> on page 155-21	Adjusts the file pointer forward or backward within the file by the number of bytes specified
<a href="#">GET_LINE Procedure</a> on page 155-22	Reads text from an open file
<a href="#">GET_LINE_NCHAR Procedure</a> on page 155-24	Reads text in Unicode from an open file
<a href="#">GET_RAW Function</a> on page 155-25	Reads a <code>RAW</code> string value from a file and adjusts the file pointer ahead by the number of bytes read
<a href="#">IS_OPEN Function</a> on page 155-26	Determines if a file handle refers to an open file



**Table 155-2 (Cont.) UTL\_FILE Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">NEW_LINE Procedure</a> on page 155-27	Writes one or more operating system-specific line terminators to a file
<a href="#">PUT Procedure</a> on page 155-28	Writes a string to a file
<a href="#">PUTF Procedure</a> on page 155-29	A <code>PUT</code> procedure with formatting
<a href="#">PUT_NCHAR Procedure</a> on page 155-31	Writes a Unicode string to a file
<a href="#">PUT_RAW Function</a> on page 155-32	Accepts as input a <code>RAW</code> data value and writes the value to the output buffer
<a href="#">PUT_LINE Procedure</a> on page 155-33	Writes a line to a file, and so appends an operating system-specific line terminator
<a href="#">PUT_LINE_NCHAR Procedure</a> on page 155-34	Writes a Unicode line to a file
<a href="#">PUTF_NCHAR Procedure</a> on page 155-35	A <code>PUT_NCHAR</code> procedure with formatting, and writes a Unicode string to a file, with formatting

## FCLOSE Procedure

This procedure closes an open file identified by a file handle.

### Syntax

```
UTL_FILE.FCLOSE (
 file IN OUT FILE_TYPE);
```

### Parameters

**Table 155–3 FCLOSE Procedure Parameters**

Parameter	Description
file	Active file handle returned by an FOPEN or FOPEN_NCHAR call.

### Usage Notes

If there is buffered data yet to be written when FCLOSE runs, then you may receive a WRITE\_ERROR exception when closing a file.

### Exceptions

```
WRITE_ERROR
INVALID_FILEHANDLE
```

## FCLOSE\_ALL Procedure

This procedure closes all open file handles for the session. This should be used as an emergency cleanup procedure, for example, when a PL/SQL program exits on an exception.

### Syntax

```
UTL_FILE.FCLOSE_ALL;
```

### Usage Notes

---

---

**Note:** FCLOSE\_ALL does not alter the state of the open file handles held by the user. This means that an IS\_OPEN test on a file handle after an FCLOSE\_ALL call still returns TRUE, even though the file has been closed. No further read or write operations can be performed on a file that was open before an FCLOSE\_ALL.

---

---

### Exceptions

```
WRITE_ERROR
```

## FCOPY Procedure

This procedure copies a contiguous portion of a file to a newly created file. By default, the whole file is copied if the `start_line` and `end_line` parameters are omitted. The source file is opened in read mode. The destination file is opened in write mode. A starting and ending line number can optionally be specified to select a portion from the center of the source file for copying.

### Syntax

```
UTL_FILE.FCOPY (
 location IN VARCHAR2,
 filename IN VARCHAR2,
 dest_dir IN VARCHAR2,
 dest_file IN VARCHAR2,
 start_line IN PLS_INTEGER DEFAULT 1,
 end_line IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 155–4** *FCOPY Procedure Parameters*

Parameters	Description
<code>location</code>	The directory location of the source file, a <code>DIRECTORY_NAME</code> from the <code>ALL_DIRECTORIES</code> view (case sensitive)
<code>filename</code>	The source file to be copied
<code>dest_dir</code>	The destination directory where the destination file is created.
<code>dest_file</code>	The destination file created from the source file.
<code>start_line</code>	The line number at which to begin copying. The default is 1 for the first line.
<code>end_line</code>	The line number at which to stop copying. The default is <code>NULL</code> , signifying end of file.

## FFLUSH Procedure

**FFLUSH** physically writes pending data to the file identified by the file handle. Normally, data being written to a file is buffered. The **FFLUSH** procedure forces the buffered data to be written to the file. The data must be terminated with a newline character.

Flushing is useful when the file must be read while still open. For example, debugging messages can be flushed to the file so that they can be read immediately.

### Syntax

```
UTL_FILE.FFLUSH (
 file IN FILE_TYPE);
invalid_maxlinesize EXCEPTION;
```

### Parameters

**Table 155–5 FFLUSH Procedure Parameters**

Parameters	Description
file	Active file handle returned by an <b>FOPEN</b> or <b>FOPEN_NCHAR</b> call.

### Exceptions

```
INVALID_FILEHANDLE
INVALID_OPERATION
WRITE_ERROR
```

## FGETATTR Procedure

This procedure reads and returns the attributes of a disk file.

### Syntax

```
UTL_FILE.FGETATTR(
 location IN VARCHAR2,
 filename IN VARCHAR2,
 exists OUT BOOLEAN,
 file_length OUT NUMBER,
 blocksize OUT NUMBER);
```

### Parameters

**Table 155–6** *FGETATTR Procedure Parameters*

Parameters	Description
location	Directory location of the source file, a <code>DIRECTORY_NAME</code> from the <code>ALL_DIRECTORIES</code> view (case sensitive).
filename	The name of the file to be examined.
exists	A <code>BOOLEAN</code> for whether or not the file exists.
file_length	The length of the file in bytes. <code>NULL</code> if file does not exist.
blocksize	The file system block size in bytes. <code>NULL</code> if the file does not exist.

## FGETPOS Function

This function returns the current relative offset position within a file, in bytes.

### Syntax

```
UTL_FILE.FGETPOS (
 fileid IN file_type)
 RETURN PLS_INTEGER;
```

### Parameters

**Table 155–7 FGETPOS Parameters**

Parameters	Description
fileid	The directory location of the source file

### Return Values

FGETPOS returns the relative offset position for an open file, in bytes. It raises an exception if the file is not open. It returns 0 for the beginning of the file.

## FOPEN Function

This function opens a file. You can specify the maximum line size and have a maximum of 50 files open simultaneously. See also "[FOPEN\\_NCHAR Function](#)" on page 155-18.

### Syntax

```
UTL_FILE.FOPEN (
 location IN VARCHAR2,
 filename IN VARCHAR2,
 open_mode IN VARCHAR2,
 max_linesize IN BINARY_INTEGER)
RETURN file_type;
```

### Parameters

**Table 155–8 FOPEN Function Parameters**

Parameter	Description
location	Directory location of file. This string is a directory object name and is case sensitive. The default is uppercase. Read privileges must be granted on this directory object for the UTL_FILE user to run FOPEN.
filename	File name, including extension (file type), without directory path. If a directory path is given as a part of the filename, it is ignored by FOPEN. On Unix, the filename cannot end with /.
open_mode	Specifies how the file is opened. Modes include: r -- read text w -- write text a -- append text rb -- read byte mode wb -- write byte mode ab -- append byte mode  If you try to open a file specifying 'a' or 'ab' for open_mode but the file does not exist, the file is created in write mode.



**Table 155–8 FOPEN Function Parameters**

Parameter	Description
max_linesize	Maximum number of characters for each line, including the newline character, for this file. (minimum value 1, maximum value 32767). If unspecified, Oracle supplies a default value of 1024.

## Return Values

FOPEN returns a file handle, which must be passed to all subsequent procedures that operate on that file. The specific contents of the file handle are private to the UTL\_FILE package, and individual components should not be referenced or changed by the UTL\_FILE user.

**Table 155–9 FOPEN Function Return Values**

Return	Description
file_type	Handle to open file.

## Usage Notes

The file location and file name parameters must be supplied to the FOPEN function as quoted strings so that the file location can be checked against the list of accessible directories as specified by the ALL\_DIRECTORIES view of accessible directory objects.

## Exceptions

INVALID\_PATH: File location or name was invalid.  
 INVALID\_MODE: The open\_mode string was invalid.  
 INVALID\_OPERATION: File could not be opened as requested.  
 INVALID\_MAXLINESIZE: Specified max\_linesize is too large or too small.

## FOPEN\_NCHAR Function

This function opens a file in Unicode for input or output, with the maximum line size specified. You can have a maximum of 50 files open simultaneously. With this function, you can read or write a text file in Unicode instead of in the database charset. See also [FOPEN Function](#) on page 155-16.

### Syntax

```
UTL_FILE.FOPEN_NCHAR (
 location IN VARCHAR2,
 filename IN VARCHAR2,
 open_mode IN VARCHAR2,
 max_linesize IN BINARY_INTEGER)
RETURN file_type;
```

### Parameters

**Table 155–10** *FOPEN\_NCHAR Function Parameters*

Parameter	Description
location	Directory location of file.
filename	File name (including extension).
open_mode	Open mode (r,w,a,rb,wb,ab).
max_linesize	Maximum number of characters for each line, including the newline character, for this file. (minimum value 1, maximum value 32767).

## FREMOVE Procedure

This procedure deletes a disk file, assuming that you have sufficient privileges.

### Syntax

```
UTL_FILE.FREMOVE (
 location IN VARCHAR2,
 filename IN VARCHAR2);
```

### Parameters

**Table 155–11** *FREMOVE Procedure Parameters*

Parameters	Description
location	The directory location of the file, a DIRECTORY_NAME from ALL_DIRECTORIES (case sensitive)
filename	The name of the file to be deleted

### Usage Notes

The FREMOVE procedure does not verify privileges before deleting a file. The O/S verifies file and directory permissions. An exception is returned on failure.

## FRENAME Procedure

This procedure renames an existing file to a new name, similar to the UNIX `mv` function.

### Syntax

```
UTL_FILE.FRENAME (
 location IN VARCHAR2,
 filename IN VARCHAR2,
 dest_dir IN VARCHAR2,
 dest_file IN VARCHAR2,
 overwrite IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 155–12** *FRENAME Procedure Parameters*

Parameters	Description
<code>location</code>	The directory location of the source file, a <code>DIRECTORY_NAME</code> from the <code>ALL_DIRECTORIES</code> view (case sensitive).
<code>filename</code>	The source file to be renamed.
<code>dest_dir</code>	The destination directory of the destination file, a <code>DIRECTORY_NAME</code> from the <code>ALL_DIRECTORIES</code> view (case sensitive).
<code>dest_file</code>	The new name of the file.
<code>overwrite</code>	The default is <code>FALSE</code> .

### Usage Notes

Permission on both the source and destination directories must be granted. You can use the `overwrite` parameter to specify whether or not to overwrite a file if one exists in the destination directory. The default is `FALSE` for no overwrite.

## FSEEK Procedure

This procedure adjusts the file pointer forward or backward within the file by the number of bytes specified.

### Syntax

```
UTL_FILE.FSEEK (
 fid IN utl_file.file_type,
 absolute_offset IN PL_INTEGER DEFAULT NULL,
 relative_offset IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 155–13 FSEEK Procedure Parameters**

Parameters	Description
fid	The file ID.
absolute_offset	The absolute location to which to seek; default = NULL
relative_offset	The number of bytes to seek forward or backward; positive = forward, negative integer = backward, zero = current position, default = NULL

### Usage Notes

Using `FSEEK`, you can read previous lines in the file without first closing and reopening the file. You must know the number of bytes by which you want to navigate.

If `relative_offset`, the procedure seeks forward. If `relative_offset > 0`, or backward, if `relative_offset < 0`, the procedure seeks through the file by the number of `relative_offset` bytes specified.

If the beginning of the file is reached before the number of bytes specified, then the file pointer is placed at the beginning of the file. If the end of the file is reached before the number of bytes specified, then an `INVALID_OFFSET` error is raised.

If `absolute_offset`, the procedure seeks to an absolute location specified in bytes.

## GET\_LINE Procedure

This procedure reads text from the open file identified by the file handle and places the text in the output buffer parameter. Text is read up to, but not including, the line terminator, or up to the end of the file, or up to the end of the `len` parameter. It cannot exceed the `max_linesize` specified in `FOPEN`.

### Syntax

```
UTL_FILE.GET_LINE (
 file IN FILE_TYPE,
 buffer OUT VARCHAR2,
 len IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 155–14** *GET\_LINE Procedure Parameters*

Parameters	Description
<code>file</code>	Active file handle returned by an <code>FOPEN</code> call. The file must be open for reading (mode <code>r</code> ); otherwise an <code>INVALID_OPERATION</code> exception is raised.
<code>buffer</code>	Data buffer to receive the line read from the file.
<code>len</code>	The number of bytes read from the file. Default is <code>NULL</code> . If <code>NULL</code> , Oracle supplies the value of <code>max_linesize</code> .

### Usage Notes

If the line does not fit in the buffer, a `VALUE_ERROR` exception is raised. If no text was read due to end of file, the `NO_DATA_FOUND` exception is raised. If the file is opened for byte mode operations, the `INVALID_OPERATION` exception is raised.

Because the line terminator character is not read into the buffer, reading blank lines returns empty strings.

The maximum size of the `buffer` parameter is 32767 bytes unless you specify a smaller size in `FOPEN`. If unspecified, Oracle supplies a default value of 1024. See also "[GET\\_LINE\\_NCHAR Procedure](#)" on page 155-24.

### Exceptions

`INVALID_FILEHANDLE`

INVALID\_OPERATION  
READ\_ERROR  
NO\_DATA\_FOUND  
VALUE\_ERROR

## GET\_LINE\_NCHAR Procedure

This procedure reads text from the open file identified by the file handle and places the text in the output buffer parameter. With this function, you can read a text file in Unicode instead of in the database charset. See also "[GET\\_LINE\\_NCHAR Procedure](#)" on page 155-24.

### Syntax

```
UTL_FILE.GET_LINE_NCHAR (
 file IN FILE_TYPE,
 buffer OUT NVARCHAR2,
 len IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 155–15** *GET\_LINE\_NCHAR Procedure Parameters*

Parameters	Description
<code>file</code>	Active file handle returned by an <code>FOPEN_NCHAR</code> call. The file must be open for reading (mode <code>r</code> ). If the file is opened by <code>FOPEN</code> instead of <code>FOPEN_NCHAR</code> , a <code>CHARSETMISMATCH</code> exception is raised.
<code>buffer</code>	Data buffer to receive the line read from the file.
<code>len</code>	The number of bytes read from the file. Default is <code>NULL</code> . If <code>NULL</code> , Oracle supplies the value of <code>max_linesize</code> .



## GET\_RAW Function

This function reads a RAW string value from a file and adjusts the file pointer ahead by the number of bytes read. `UTL_FILE.GET_RAW` ignores line terminators and returns the actual number of bytes requested by the `GET_RAW len` parameter.

### Syntax

```
UTL_FILE.GET_RAW (
 fid IN utl_file.file_type,
 r OUT NOCOPY RAW,
 len IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 155–16** *GET\_RAW Procedure Parameters*

Parameters	Description
<code>fid</code>	The file ID.
<code>r</code>	The RAW data.
<code>len</code>	The number of bytes read from the file. Default is <code>NULL</code> . If <code>NULL</code> , <code>len</code> is assumed to be the maximum length of RAW.

## IS\_OPEN Function

This function tests a file handle to see if it identifies an open file. `IS_OPEN` reports only whether a file handle represents a file that has been opened, but not yet closed. It does not guarantee that there will be no operating system errors when you attempt to use the file handle.

### Syntax

```
UTL_FILE.IS_OPEN (
 file IN FILE_TYPE)
RETURN BOOLEAN;
```

### Parameters

**Table 155–17 IS\_OPEN Function Parameters**

Parameter	Description
<code>file</code>	Active file handle returned by an <code>FOPEN</code> or <code>FOPEN_NCHAR</code> call.

### Return Values

TRUE or FALSE

## NEW\_LINE Procedure

This procedure writes one or more line terminators to the file identified by the input file handle. This procedure is separate from `PUT` because the line terminator is a platform-specific character or sequence of characters.

### Syntax

```
UTL_FILE.NEW_LINE (
 file IN FILE_TYPE,
 lines IN NATURAL := 1);
```

### Parameters

**Table 155–18** *NEW\_LINE Procedure Parameters*

Parameters	Description
<code>file</code>	Active file handle returned by an <code>FOPEN</code> or <code>FOPEN_NCHAR</code> call.
<code>lines</code>	Number of line terminators to be written to the file.

### Exceptions

```
INVALID_FILEHANDLE
INVALID_OPERATION
WRITE_ERROR
```

## PUT Procedure

PUT writes the text string stored in the `buffer` parameter to the open file identified by the file handle. The file must be open for write operations. No line terminator is appended by PUT; use `NEW_LINE` to terminate the line or use `PUT_LINE` to write a complete line with a line terminator. See also "[PUT\\_NCHAR Procedure](#)" on page 155-31.

### Syntax

```
UTL_FILE.PUT (
 file IN FILE_TYPE,
 buffer IN VARCHAR2);
```

### Parameters

**Table 155–19** *PUT Procedure Parameters*

Parameters	Description
<code>file</code>	Active file handle returned by an <code>FOPEN_NCHAR</code> call. The file must be open for writing.
<code>buffer</code>	Buffer that contains the text to be written to the file.  You must have opened the file using mode <code>w</code> or mode <code>a</code> ; otherwise, an <code>INVALID_OPERATION</code> exception is raised.

### Usage Notes

The maximum size of the `buffer` parameter is 32767 bytes unless you specify a smaller size in `FOPEN`. If unspecified, Oracle supplies a default value of 1024. The sum of all sequential PUT calls cannot exceed 32767 without intermediate buffer flushes.

### Exceptions

```
INVALID_FILEHANDLE
INVALID_OPERATION
WRITE_ERROR
```

## PUTF Procedure

This procedure is a formatted `PUT` procedure. It works like a limited `printf()`. See also "[PUTF\\_NCHAR Procedure](#)" on page 155-35.

### Syntax

```
UTL_FILE.PUTF (
 file IN FILE_TYPE,
 format IN VARCHAR2,
 [arg1 IN VARCHAR2 DEFAULT NULL,
 . . .
 arg5 IN VARCHAR2 DEFAULT NULL]);
```

### Parameters

**Table 155–20** *PUTF Procedure Parameters*

Parameters	Description
file	Active file handle returned by an <code>FOPEN</code> call.
format	Format string that can contain text as well as the formatting characters <code>\n</code> and <code>%s</code> .
arg1..arg5	From one to five operational argument strings. Argument strings are substituted, in order, for the <code>%s</code> formatters in the format string. If there are more formatters in the format parameter string than there are arguments, then an empty string is substituted for each <code>%s</code> for which there is no argument.

### Usage Notes

The format string can contain any text, but the character sequences `%s` and `\n` have special meaning.

Character Sequence	Meaning
<code>%s</code>	Substitute this sequence with the string value of the next argument in the argument list.
<code>\n</code>	Substitute with the appropriate platform-specific line terminator.

## Examples

The following example writes the lines:

```
Hello, world!
I come from Zork with greetings for all earthlings.

my_world varchar2(4) := 'Zork';
...
PUTF(my_handle, 'Hello, world!\nI come from %s with %s.\n',
 my_world,
 'greetings for all earthlings');
```

**If there are more %s formatters in the format parameter than there are arguments, then an empty string is substituted for each %s for which there is no matching argument.**

## Exceptions

```
INVALID_FILEHANDLE
INVALID_OPERATION
WRITE_ERROR
```

## PUT\_NCHAR Procedure

This procedure writes the text string stored in the `buffer` parameter to the open file identified by the file handle. With this function, you can write a text file in Unicode instead of in the database charset. See also "[PUT Procedure](#)" on page 155-28.

### Syntax

```
UTL_FILE.PUT_NCHAR (
 file IN FILE_TYPE,
 buffer IN NVARCHAR2);
```

### Parameters

**Table 155–21** *PUT\_NCHAR Procedure Parameters*

Parameters	Description
<code>file</code>	Active file handle returned by an <code>FOPEN_NCHAR</code> call. If the file is opened by <code>FOPEN</code> instead of <code>FOPEN_NCHAR</code> , a <code>CHARSETMISMATCH</code> exception is raised.
<code>buffer</code>	Buffer that contains the text to be written to the file. You must have opened the file using mode <code>w</code> or mode <code>a</code> ; otherwise, an <code>INVALID_OPERATION</code> exception is raised.

### Usage Notes

The maximum size of the `buffer` parameter is 32767 bytes unless you specify a smaller size in `FOPEN`. If unspecified, Oracle supplies a default value of 1024. The sum of all sequential `PUT` calls cannot exceed 32767 without intermediate buffer flushes.

## PUT\_RAW Function

This function accepts as input a RAW data value and writes the value to the output buffer.

### Syntax

```
UTL_FILE.PUT_RAW (
 fid IN utl_file.file_type,
 r IN RAW,
 autoflush IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 155–22 PUT\_RAW Procedure Parameters**

Parameters	Description
fid	The file ID.
r	The RAW data written to the buffer.
autoflush	If TRUE, performs a flush after writing the value to the output buffer; default is FALSE.

### Usage Notes

You can request an automatic flush of the buffer by setting the third argument to TRUE.

The maximum size of the `buffer` parameter is 32767 bytes unless you specify a smaller size in `FOPEN`. If unspecified, Oracle supplies a default value of 1024. The sum of all sequential `PUT` calls cannot exceed 32767 without intermediate buffer flushes.



## PUT\_LINE Procedure

This procedure writes the text string stored in the `buffer` parameter to the open file identified by the file handle. The file must be open for write operations. `PUT_LINE` terminates the line with the platform-specific line terminator character or characters.

See also "[PUT\\_LINE\\_NCHAR Procedure](#)" on page 155-34.

### Syntax

```
UTL_FILE.PUT_LINE (
 file IN FILE_TYPE,
 buffer IN VARCHAR2,
 autoflush IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 155–23** *PUT\_LINE Procedure Parameters*

Parameters	Description
<code>file</code>	Active file handle returned by an <code>FOPEN</code> call.
<code>buffer</code>	Text buffer that contains the lines to be written to the file.
<code>autoflush</code>	Flushes the buffer to disk after the <code>WRITE</code> .

### Usage Notes

The maximum size of the `buffer` parameter is 32767 bytes unless you specify a smaller size in `FOPEN`. If unspecified, Oracle supplies a default value of 1024. The sum of all sequential `PUT` calls cannot exceed 32767 without intermediate buffer flushes.

### Exceptions

```
INVALID_FILEHANDLE
INVALID_OPERATION
WRITE_ERROR
```

## PUT\_LINE\_NCHAR Procedure

This procedure writes the text string stored in the `buffer` parameter to the open file identified by the file handle. With this function, you can write a text file in Unicode instead of in the database charset. See also "[PUT\\_LINE Procedure](#)" on page 155-33.

### Syntax

```
UTL_FILE.PUT_LINE_NCHAR (
 file IN FILE_TYPE,
 buffer IN NVARCHAR2);
```

### Parameters

**Table 155–24** *PUT\_LINE\_NCHAR Procedure Parameters*

Parameters	Description
<code>file</code>	Active file handle returned by an <code>FOPEN_NCHAR</code> call. The file must be open for writing.
<code>buffer</code>	Text buffer that contains the lines to be written to the file.

### Usage Notes

The maximum size of the `buffer` parameter is 32767 bytes unless you specify a smaller size in `FOPEN`. If unspecified, Oracle supplies a default value of 1024. The sum of all sequential `PUT` calls cannot exceed 32767 without intermediate buffer flushes.

## PUTF\_NCHAR Procedure

This procedure is a formatted `PUT_NCHAR` procedure. Using `PUTF_NCHAR`, you can write a text file in Unicode instead of in the database charset. See also "[PUTF\\_NCHAR Procedure](#)" on page 155-35 and "[PUT\\_LINE Procedure](#)" on page 155-33.

### Syntax

```
UTL_FILE.PUTF_NCHAR (
 file IN FILE_TYPE,
 format IN NVARCHAR2,
 [arg1 IN NVARCHAR2 DEFAULT NULL,
 . . .
 arg5 IN NVARCHAR2 DEFAULT NULL]);
```

### Parameters

**Table 155–25** *PUTF\_NCHAR Procedure Parameters*

Parameters	Description
file	Active file handle returned by an <code>FOPEN_NCHAR</code> call. The file must be open for reading (mode <code>r</code> ). If the file is opened by <code>FOPEN</code> instead of <code>FOPEN_NCHAR</code> , a <code>CHARSETMISMATCH</code> exception is raised.
format	Format string that can contain text as well as the formatting characters <code>\n</code> and <code>%s</code> .
arg1..arg5	From one to five operational argument strings. Argument strings are substituted, in order, for the <code>%s</code> formatters in the format string. If there are more formatters in the format parameter string than there are arguments, then an empty string is substituted for each <code>%s</code> for which there is no argument.

### Usage Notes

The maximum size of the `buffer` parameter is 32767 bytes unless you specify a smaller size in `FOPEN`. If unspecified, Oracle supplies a default value of 1024. The sum of all sequential `PUT` calls cannot exceed 32767 without intermediate buffer flushes.



The `UTL_HTTP` package makes Hypertext Transfer Protocol (HTTP) callouts from SQL and PL/SQL. You can use it to access data on the Internet over HTTP.

When the package fetches data from a Web site using HTTPS, it requires Oracle Wallet Manager to set up an Oracle wallet. Non-HTTPS fetches do not require an Oracle wallet.

**See Also:**

- [Chapter 166, "UTL\\_URL"](#)
- [Chapter 164, "UTL\\_SMTP"](#)
- *Oracle Advanced Security Administrator's Guide* for more information on Wallet Manager

This chapter contains the following topics:

- [Using UTL\\_HTTP](#)
  - [Overview](#)
  - [Constants](#)
  - [Types](#)
  - [Exceptions](#)
  - [Examples](#)
- [Subprogram Groups](#)
- [Summary of UTL\\_HTTP Subprograms](#)

## Using UTL\_HTTP

- [Overview](#)
- [Constants](#)
- [Types](#)
- [Exceptions](#)
- [Examples](#)

### Overview

With UTL\_HTTP, you can write PL/SQL programs that communicate with Web (HTTP) servers. UTL\_HTTP also contains a function that can be used in SQL queries. The package also supports HTTP over the Secured Socket Layer protocol (SSL), also known as HTTPS, directly or through an HTTP proxy. Other Internet-related data-access protocols (such as the File Transfer Protocol (FTP) or the Gopher protocol) are also supported using an HTTP proxy server that supports those protocols.

### Constants

**Table 156–1 Constants**

Constant and Syntax	Purpose
<code>HTTP_VERSION_1_0 CONSTANT VARCHAR2(10) := 'HTTP/1.0';</code>	Denotes HTTP version 1.0 that can be used in the function <code>begin_request</code> .
<code>HTTP_VERSION_1 CONSTANT VARCHAR2(10) := 'HTTP/1.1';</code>	Denotes HTTP version 1.1 that can be used in the function <code>begin_request</code> .
<code>DEFAULT_HTTP_PORT CONSTANT PLS_INTEGER := 80;</code>	The default TCP/IP port (80) at which a Web server or proxy server listens
<code>DEFAULT_HTTPS_PORT CONSTANT PLS_INTEGER := 443;</code>	The default TCP/IP port (443) at which an HTTPS Web server listens

**Table 156–2 HTTP 1.1 Status Codes:****Constant and Syntax**

```
HTTP_VERSION_1_0 CONSTANT VARCHAR2(10) := 'HTTP/1.0';
```

```
HTTP_VERSION_1 CONSTANT VARCHAR2(10) := 'HTTP/1.1';
```

```
DEFAULT_HTTP_PORT CONSTANT PLS_INTEGER := 80;
```

```
DEFAULT_HTTPS_PORT CONSTANT PLS_INTEGER := 443;
```

The following denote all the HTTP 1.1 status codes:

```
HTTP_CONTINUE CONSTANT PLS_INTEGER := 100;
```

```
HTTP_SWITCHING_PROTOCOLS CONSTANT PLS_INTEGER := 101;
```

```
HTTP_OK CONSTANT PLS_INTEGER := 200;
```

```
HTTP_CREATED CONSTANT PLS_INTEGER := 201;
```

```
HTTP_ACCEPTED CONSTANT PLS_INTEGER := 202;
```

```
HTTP_NON_AUTHORITATIVE_INFO CONSTANT PLS_INTEGER := 203;
```

```
HTTP_NO_CONTENT CONSTANT PLS_INTEGER := 204;
```

```
HTTP_RESET_CONTENT CONSTANT PLS_INTEGER := 205;
```

```
HTTP_PARTIAL_CONTENT CONSTANT PLS_INTEGER := 206;
```

```
HTTP_MULTIPLE_CHOICES CONSTANT PLS_INTEGER := 300;
```

```
HTTP_MOVED_PERMANENTLY CONSTANT PLS_INTEGER := 301;
```

```
HTTP_FOUND CONSTANT PLS_INTEGER := 302;
```

```
HTTP_SEE_OTHER CONSTANT PLS_INTEGER := 303;
```

```
HTTP_NOT_MODIFIED CONSTANT PLS_INTEGER := 304;
```

```
HTTP_USE_PROXY CONSTANT PLS_INTEGER := 305;
```

```
HTTP_TEMPORARY_REDIRECT CONSTANT PLS_INTEGER := 307;
```

```
HTTP_BAD_REQUEST CONSTANT PLS_INTEGER := 400;
```

```
HTTP_UNAUTHORIZED CONSTANT PLS_INTEGER := 401;
```

```
HTTP_PAYMENT_REQUIRED CONSTANT PLS_INTEGER := 402;
```

```
HTTP_FORBIDDEN CONSTANT PLS_INTEGER := 403;
```

```
HTTP_NOT_FOUND CONSTANT PLS_INTEGER := 404;
```

```
HTTP_NOT_ACCEPTABLE CONSTANT PLS_INTEGER := 406;
```

**Table 156–2 (Cont.) HTTP 1.1 Status Codes:****Constant and Syntax**

---

```
HTTP_PROXY_AUTH_REQUIRED CONSTANT PLS_INTEGER := 407;
HTTP_REQUEST_TIME_OUT CONSTANT PLS_INTEGER := 408;
HTTP_CONFLICT CONSTANT PLS_INTEGER := 409;
HTTP_GONE CONSTANT PLS_INTEGER := 410;
HTTP_LENGTH_REQUIRED CONSTANT PLS_INTEGER := 411;
HTTP_PRECONDITION_FAILED CONSTANT PLS_INTEGER := 412;
HTTP_REQUEST_ENTITY_TOO_LARGE CONSTANT PLS_INTEGER := 413;
HTTP_REQUEST_URI_TOO_LARGE CONSTANT PLS_INTEGER := 414;
HTTP_UNSUPPORTED_MEDIA_TYPE CONSTANT PLS_INTEGER := 415;
HTTP_REQ_RANGE_NOT_SATISFIABLE CONSTANT PLS_INTEGER := 416;
HTTP_EXPECTATION_FAILED CONSTANT PLS_INTEGER := 417;
HTTP_NOT_IMPLEMENTED CONSTANT PLS_INTEGER := 501;
HTTP_BAD_GATEWAY CONSTANT PLS_INTEGER := 502;
HTTP_SERVICE_UNAVAILABLE CONSTANT PLS_INTEGER := 503;
HTTP_GATEWAY_TIME_OUT CONSTANT PLS_INTEGER := 504;
HTTP_VERSION_NOT_SUPPORTED CONSTANT PLS_INTEGER := 505;
```

---

## Types

- [REQ Type](#)
- [RESP Type](#)
- [COOKIE and COOKIE\\_TABLE Types](#)
- [CONNECTION Type](#)

### REQ Type

Use this PL/SQL record type to represent an HTTP request.



**Syntax**

```
TYPE req IS RECORD (
 url VARCHAR2(32767),
 method VARCHAR2(64),
 http_version VARCHAR2(64));
```

**Parameters****Table 156–3 REQ Type Parameters**

Parameter	Description
url	The URL of the HTTP request. It is set after the request is created by <code>begin_request</code> .
method	The method to be performed on the resource identified by the URL. It is set after the request is created by <code>begin_request</code> .
http_version	The HTTP protocol version used to send the request. It is set after the request is created by <code>begin_request</code> .

**Usage Notes**

The information returned in `REQ` from the interface `begin_request` is for read only. Changing the field values in the record has no effect on the request.

There are other fields in `REQ` record type whose names begin with the prefix `private_`. The fields are private and are intended for use by implementation of the `UTL_HTTP` package. You should not modify the fields.

**RESP Type**

This PL/SQL record type is used to represent an HTTP response.

**Syntax**

```
TYPE resp IS RECORD (
 status_code PLS_INTEGER,
 reason_phrase VARCHAR2(256),
 http_version VARCHAR2(64));
```

## Parameters

**Table 156–4 RESP Type Parameters**

Parameter	Description
<code>status_code</code>	The status code returned by the Web server. It is a 3-digit integer that indicates the results of the HTTP request as handled by the Web server. It is set after the response is processed by <code>get_response</code> .
<code>reason_phrase</code>	The short textual message returned by the Web server that describe the status code. It gives a brief description of the results of the HTTP request as handled by the Web server. It is set after the response is processed by <code>get_response</code> .
<code>http_version</code>	The HTTP protocol version used in the HTTP response. It is set after the response is processed by <code>get_response</code> .

## Usage Notes

The information returned in `RESP` from the interface `get_response` is read-only. There are other fields in the `RESP` record type whose names begin with the prefix `private_`. The fields are private and are intended for use by implementation of the `UTL_HTTP` package. You should not modify the fields.

## COOKIE and COOKIE\_TABLE Types

The `COOKIE` type is the PL/SQL record type that represents an HTTP cookie. The `COOKIE_TABLE` type is a PL/SQL index-by-table type that represents a collection of HTTP cookies.

## Syntax

```
TYPE cookie IS RECORD (
 name VARCHAR2(256),
 value VARCHAR2(1024),
 domain VARCHAR2(256),
 expire TIMESTAMP WITH TIME ZONE,
 path VARCHAR2(1024),
 secure BOOLEAN,
 version PLS_INTEGER,
 comment VARCHAR2(1024));

TYPE cookie_table IS TABLE OF cookie INDEX BY binary_integer;
```

## Fields of COOKIE Record Type

[Table 156-5](#) shows the fields for the `COOKIE` and `COOKIE_TABLE` record types.

**Table 156-5** *Fields of COOKIE and COOKIE\_TABLE Type*

Field	Description
<code>name</code>	The name of the HTTP cookie
<code>value</code>	The value of the cookie
<code>domain</code>	The domain for which the cookie is valid
<code>expire</code>	The time by which the cookie will expire
<code>path</code>	The subset of URLs to which the cookie applies
<code>secure</code>	Should the cookie be returned to the Web server using secured means only.
<code>version</code>	The version of the HTTP cookie specification the cookie conforms. This field is <code>NULL</code> for Netscape cookies.
<code>comment</code>	The comment that describes the intended use of the cookie. This field is <code>NULL</code> for Netscape cookies.

## Usage Notes

PL/SQL programs do not usually examine or change the cookie information stored in the `UTL_HTTP` package. The cookies are maintained by the package transparently. They are maintained inside the `UTL_HTTP` package, and they last for the duration of the database session only. PL/SQL applications that require cookies to be maintained beyond the lifetime of a database session can read the cookies using `get_cookies`, store them persistently in a database table, and re-store the cookies back in the package using `add_cookies` in the next database session. All the fields in the `cookie` record, except for the comment field, must be stored. Do not alter the cookie information, which can result in an application error in the Web server or compromise the security of the PL/SQL and the Web server applications. See "[Retrieving and Restoring Cookies](#)" on page 156-18.

## CONNECTION Type

Use the PL/SQL record type to represent the remote hosts and TCP/IP ports of a network connection that is kept persistent after an HTTP request is completed, according to the HTTP 1.1 protocol specification. The persistent network connection may be reused by a subsequent HTTP request to the same host and port. The subsequent HTTP request may be completed faster because the network connection latency is avoided. `connection_table` is a PL/SQL table of `connection`.

For a direct HTTP persistent connection to a Web server, the `host` and `port` fields contain the host name and TCP/IP port number of the Web server. The `proxy_host` and `proxy_port` fields are not set. For an HTTP persistent connection that was previously used to connect to a Web server using a proxy, the `proxy_host` and `proxy_port` fields contain the host name and TCP/IP port number of the proxy server. The `host` and `port` fields are not set, which indicates that the persistent connection, while connected to a proxy server, is not bound to any particular target Web server. An HTTP persistent connection to a proxy server can be used to access any target Web server that is using a proxy.

The `ssl` field indicates if Secured Socket Layer (SSL) is being used in an HTTP persistent connection. An HTTPS request is an HTTP request made over SSL. For an HTTPS (SSL) persistent connection connected using a proxy, the `host` and `port` fields contain the host name and TCP/IP port number of the target HTTPS Web server and the fields will always be set. An HTTPS persistent connection to an HTTPS Web server using a proxy server can only be reused to make another request to the same target Web server.

### Syntax

```
TYPE connection IS RECORD (
 host VARCHAR2(256),
 port PLS_INTEGER,
 proxy_host VARCHAR2(256),
 proxy_port PLS_INTEGER,
 ssl BOOLEAN);
```

```
TYPE connection_table IS TABLE OF connection INDEX BY BINARY_INTEGER;
```


## Operational Notes

- [Operational Flow](#)
- [Simple HTTP Fetches](#)
- [HTTP Requests](#)
- [HTTP Responses](#)
- [Session Settings](#)
- [Session Settings](#)

## Operational Flow

The `UTL_HTTP` package provides access to the HTTP protocol. The interfaces must be called in the order shown in [Figure 156-1](#), or an exception will be raised.

**Figure 156-1 Flow of the Core UTL\_HTTP Package**



---

The following can be called at any time:

- **Non-protocol interfaces that manipulate cookies**
  - GET\_COOKIE\_COUNT
  - GET\_COOKIES
  - ADD\_COOKIES
  - CLEAR\_COOKIES
- **Persistent connections**
  - GET\_PERSISTENT\_CONN\_COUNT
  - GET\_PERSISTENT\_CONNS
  - CLOSE\_PERSISTENT\_CONN
  - CLOSE\_PERSISTENT\_CONNS
- **Interfaces that manipulate attributes and configurations of the UTL\_HTTP package in the current session**
  - SET\_PROXY
  - GET\_PROXY
  - SET\_COOKIE\_SUPPORT
  - GET\_COOKIE\_SUPPORT
  - SET\_FOLLOW\_REDIRECT
  - GET\_FOLLOW\_REDIRECT
  - SET\_BODY\_CHARSET
  - GET\_BODY\_CHARSET
  - SET\_PERSISTENT\_CONN\_SUPPORT
  - GET\_PERSISTENT\_CONN\_SUPPORT
  - SET\_DETAILED\_EXCP\_SUPPORT
  - GET\_DETAILED\_EXCP\_SUPPORT
  - SET\_WALLET
  - SET\_TRANSFER\_TIMEOUT
  - GET\_TRANSFER\_TIMEOUT

- Interfaces that retrieve the last detailed exception code and message UTL\_HTTP package in the current session
  - GET\_DETAILED\_SQLCODE
  - GET\_DETAILED\_SQLERRM

---

---

**NOTE:** Some of the request and response interfaces bear the same name as the interface that manipulates the attributes and configurations of the package in the current session. They are overloaded versions of the interface that manipulate a request or a response.

---

---

## Simple HTTP Fetches

REQUEST and REQUEST\_PIECES take a string uniform resource locator (URL), contact that site, and return the data (typically HTML) obtained from that site.

You should not expect REQUEST or REQUEST\_PIECES to succeed in contacting a URL unless you can contact that URL by using a browser on the same machine (and with the same privileges, environment variables, and so on.)

If REQUEST or REQUEST\_PIECES fails (for example, if it raises an exception, or if it returns an HTML-formatted error message, but you believe that the URL argument is correct), then try contacting that same URL with a browser to verify network availability from your machine. You may have a proxy server set in your browser that needs to be set with each REQUEST or REQUEST\_PIECES call using the optional proxy parameter.

---

---

**Note:** UTL\_HTTP can also use environment variables to specify its proxy behavior. For example, on UNIX, setting the environment variable http\_proxy to a URL uses that service as the proxy server for HTTP requests. Setting the environment variable no\_proxy to a domain name does not use the HTTP proxy server for URLs in that domain. When the UTL\_HTTP package is executed in the Oracle database server, the environment variables are the ones that are set when the database instance is started.

---

---

**See Also:** [Simple HTTP Fetches in a Single Call Subprograms](#) on page 156-22



## Session Settings

Session settings manipulate the configuration and default behavior of UTL\_HTTP when HTTP requests are executed within a database user session. When a request is created, it inherits the default settings of the HTTP cookie support, follow-redirect, body character set, persistent-connection support, and transfer timeout of the current session. Those settings can be changed later by calling the request interface. When a response is created for a request, it inherits those settings from the request. Only the body character set can be changed later by calling the response interface.

**See Also:** [Session Settings Subprograms](#) on page 156-23

## HTTP Requests

The HTTP Requests group of subprograms begin an HTTP request, manipulate attributes, and send the request information to the Web server. When a request is created, it inherits the default settings of the HTTP cookie support, follow-redirect, body character set, persistent-connection support, and transfer timeout of the current session. The settings can be changed by calling the request interface.

**See Also:** [HTTP Requests Subprograms](#) on page 156-25

## HTTP Responses

The HTTP Responses group of subprograms manipulate an HTTP response obtained from GET\_RESPONSE and receive response information from the Web server. When a response is created for a request, it inherits settings of the HTTP cookie support, follow-redirect, body character set, persistent-connection support, and transfer timeout from the request. Only the body character set can be changed by calling the response interface.

**See Also:** [HTTP Responses Subprograms](#) on page 156-26

## HTTP Cookies

The UTL\_HTTP package provides subprograms to manipulate HTTP cookies.

**See Also:** [HTTP Cookies Subprograms](#) on page 156-27

## HTTP Persistent Connections

The UTL\_HTTP package provides subprograms to manipulate persistent connections.

**See Also:** [HTTP Persistent Connections Subprograms](#) on page 156-28

## Error Conditions

The UTL\_HTTP package provides subprograms to retrieve error information.

**See Also:** [Error Conditions Subprograms](#) on page 156-29

## Exceptions

[Table 156-6](#) lists the exceptions that the UTL\_HTTP package interface can raise. By default, UTL\_HTTP raises the exception `request_failed` when a request fails to execute. If the package is set to raise a detailed exception by `set_detailed_excp_support`, the rest of the exceptions will be raised directly (except for the exception `end_of_body`, which will be raised by `read_text`, `read_line`, and `read_raw` regardless of the setting).

**Table 156-6 UTL\_HTTP Exceptions**

Exception	Error Code	Reason	Where Raised
<code>request_failed</code>	29273	The request fails to executes	Any HTTP request or response interface when detailed_exception is disabled
<code>bad_argument</code>	29261	The argument passed to the interface is bad	Any HTTP request or response interface when detailed_exception is enabled
<code>bad_url</code>	29262	The requested URL is badly formed	<code>begin_request</code> , when detailed_exception is enabled
<code>protocol_error</code>	29263	An HTTP protocol error occurs when communicating with the Web server	<code>set_header</code> , <code>get_response</code> , <code>read_raw</code> , <code>read_text</code> , and <code>read_line</code> , when detailed_exception is enabled
<code>unknown_scheme</code>	29264	The scheme of the requested URL is unknown	<code>begin_request</code> and <code>get_response</code> , when detailed_exception is enabled
<code>header_not_found</code>	29265	The header is not found	<code>get_header</code> , <code>get_header_by_name</code> , when detailed_exception is enabled

**Table 156–6 (Cont.) UTL\_HTTP Exceptions**

<b>Exception</b>	<b>Error Code</b>	<b>Reason</b>	<b>Where Raised</b>
<code>end_of_body</code>	29266	The end of HTTP response body is reached	<code>read_raw</code> , <code>read_text</code> , and <code>read_line</code> , when <code>detailed_exception</code> is enabled
<code>illegal_call</code>	29267	The call to <code>UTL_HTTP</code> is illegal at the current state of the HTTP request	<code>set_header</code> , <code>set_authentication</code> , and <code>set_persistent_conn_support</code> , when <code>detailed_exception</code> is enabled
<code>http_client_error</code>	29268	From <code>get_response</code> , the response status code indicates that a client error has occurred (status code in 4xx range). Or from <code>begin_request</code> , the HTTP proxy returns a status code in the 4xx range when making an HTTPS request through the proxy.	<code>get_response</code> , <code>begin_request</code> when <code>detailed_exception</code> is enabled
<code>http_server_error</code>	29269	From <code>get_response</code> , the response status code indicates that a client error has occurred (status code in 5xx range). Or from <code>begin_request</code> , the HTTP proxy returns a status code in the 5xx range when making an HTTPS request through the proxy.	<code>get_response</code> , <code>begin_request</code> when <code>detailed_exception</code> is enabled
<code>too_many_requests</code>	29270	Too many requests or responses are open	<code>begin_request</code> , when <code>detailed_exception</code> is enabled
<code>partial_multibyte_exception</code>	29275	No complete character is read and a partial multibyte character is found at the end of the response body	<code>read_text</code> and <code>read_line</code> , when <code>detailed_exception</code> is enabled
<code>transfer_timeout</code>	29276	No data is read and a read timeout occurred	<code>read_text</code> and <code>read_line</code> , when <code>detailed_exception</code> is enabled

---

---

**NOTE:** The `partial_multibyte_char` and `transfer_timeout` exceptions are duplicates of the same exceptions defined in `UTL_TCP`. They are defined in this package so that the use of this package does not require the knowledge of the `UTL_TCP`. As those exceptions are duplicates, an exception handle that catches the `partial_multibyte_char` and `transfer_timeout` exceptions in this package also catch the exceptions in the `UTL_TCP`.

---

---

For `REQUEST` and `REQUEST_PIECES`, the `request_failed` exception is raised when any exception occurs and `detailed_exception` is disabled.

## Examples

The following examples demonstrate how to use `UTL_HTTP`.

- [General Usage](#)
- [Handling HTTP Authentication](#)
- [Retrieving and Restoring Cookies](#)

### General Usage

```
SET serveroutput ON SIZE 40000

DECLARE
 req utl_http.req;
 resp utl_http.resp;
 value VARCHAR2(1024);
BEGIN

 utl_http.set_proxy('proxy.my-company.com', 'corp.my-company.com');

 req := utl_http.begin_request('http://www-hr.corp.my-company.com');
 utl_http.set_header(req, 'User-Agent', 'Mozilla/4.0');
 resp := utl_http.get_response(req);
 LOOP
 utl_http.read_line(resp, value, TRUE);
 dbms_output.put_line(value);
 END LOOP;
 utl_http.end_response(resp);
```

```

EXCEPTION
 WHEN utl_http.end_of_body THEN
 utl_http.end_response(resp);
END;

```

## Retrieving HTTP Response Headers

```

SET serveroutput ON SIZE 40000

DECLARE
 req utl_http.req;
 resp utl_http.resp;
 name VARCHAR2(256);
 value VARCHAR2(1024);
BEGIN

 utl_http.set_proxy('proxy.my-company.com', 'corp.my-company.com');

 req := utl_http.begin_request('http://www-hr.corp.my-company.com');
 utl_http.set_header(req, 'User-Agent', 'Mozilla/4.0');
 resp := utl_http.get_response(req);

 dbms_output.put_line('HTTP response status code: ' || resp.status_code);
 dbms_output.put_line('HTTP response reason phrase: ' || resp.reason_phrase);

 FOR i IN 1..utl_http.get_header_count(resp) LOOP
 utl_http.get_header(resp, i, name, value);
 dbms_output.put_line(name || ': ' || value);
 END LOOP;

 utl_http.end_response(resp);
END;

```

## Handling HTTP Authentication

```

SET serveroutput ON SIZE 40000

CREATE OR REPLACE PROCEDURE get_page (url IN VARCHAR2,
 username IN VARCHAR2 DEFAULT NULL,
 password IN VARCHAR2 DEFAULT NULL,
 realm IN VARCHAR2 DEFAULT NULL) AS

 req utl_http.req;
 resp utl_http.resp;
 my_scheme VARCHAR2(256);
 my_realm VARCHAR2(256);
 my_proxy BOOLEAN;

```

```
BEGIN

 -- Turn off checking of status code. We will check it by ourselves.
 utl_http.http_response_error_check(FALSE);

 req := utl_http.begin_request(url);
 IF (username IS NOT NULL) THEN
 utl_http.set_authentication(req, username, password); -- Use HTTP Basic
Authen. Scheme
 END IF;

 resp := utl_http.get_response(req);
 IF (resp.status_code = utl_http.HTTP_UNAUTHORIZED) THEN
 utl_http.get_authentication(resp, my_scheme, my_realm, my_proxy);
 IF (my_proxy) THEN
 dbms_output.put_line('Web proxy server is protected.');
```

dbms\_output.put('Please supplied the required ' || my\_scheme || ' authentication username/password for realm ' || my\_realm || ' for the proxy server.');

```
 ELSE
 dbms_output.put_line('Web page ' || url || ' is protected.');
```

dbms\_output.put('Please supplied the required ' || my\_scheme || ' authentication username/password for realm ' || my\_realm || ' for the Web page.');

```
 END IF;
 utl_http.end_response(resp);
 RETURN;
 END IF;

 FOR i IN 1..utl_http.get_header_count(resp) LOOP
 utl_http.get_header(resp, i, name, value);
 dbms_output.put_line(name || ': ' || value);
 END LOOP;
 utl_http.end_response(resp);

END;
```

## Retrieving and Restoring Cookies

```
CREATE TABLE my_cookies (
 session_id INTEGER,
 name VARCHAR2(256),
 value VARCHAR2(1024),
 domain VARCHAR2(256),
 expire DATE,
```

```
 path VARCHAR2(1024),
 secure VARCHAR2(1),
 version INTEGER
);

CREATE SEQUENCE session_id;

SET serveroutput ON SIZE 40000

REM Retrieve cookies from UTL_HTTP

CREATE OR REPLACE FUNCTION save_cookies RETURN PLS_INTEGER AS
 cookies utl_http.cookie_table;
 my_session_id PLS_INTEGER;
 secure VARCHAR2(1);
BEGIN

 /* assume that some cookies have been set in previous HTTP requests. */

 utl_http.get_cookies(cookies);
 select session_id.nextval into my_session_id from dual;

 FOR i in 1..cookies.count LOOP
 IF (cookies(i).secure) THEN
 secure := 'Y';
 ELSE
 secure := 'N';
 END IF;
 insert into my_cookies
 values (my_session_id, cookies(i).name, cookies(i).value,
 cookies(i).domain,
 cookies(i).expire, cookies(i).path, secure, cookies(i).version);
 END LOOP;

 RETURN my_session_id;

END;

/

REM Retrieve cookies from UTL_HTTP

CREATE OR REPLACE PROCEDURE restore_cookies (this_session_id IN PLS_INTEGER)
AS
 cookies utl_http.cookie_table;
 cookie utl_http.cookie;
```

```

i PLS_INTEGER := 0;
CURSOR c (c_session_id PLS_INTEGER) IS
 SELECT * FROM my_cookies WHERE session_id = c_session_id;
BEGIN

 FOR r IN c(this_session_id) LOOP
 i := i + 1;
 cookie.name := r.name;
 cookie.value := r.value;
 cookie.domain := r.domain;
 cookie.expire := r.expire;
 cookie.path := r.path;
 IF (r.secure = 'Y') THEN
 cookie.secure := TRUE;
 ELSE
 cookie.secure := FALSE;
 END IF;
 cookie.version := r.version;
 cookies(i) := cookie;
 END LOOP;

 utl_http.clear_cookies;
 utl_http.add_cookies(cookies);

END;
/
```



## Subprogram Groups

---

- Simple HTTP Fetches in a Single Call Subprograms
- Session Settings Subprograms
- HTTP Requests Subprograms
- HTTP Responses Subprograms
- HTTP Cookies Subprograms
- HTTP Persistent Connections Subprograms
- Error Conditions Subprograms

## Simple HTTP Fetches in a Single Call Subprograms

**Table 156–7** *UTL\_HTTP Subprograms—Simple HTTP Fetches in a Single Call*

Subprogram	Description
<a href="#">REQUEST Function</a> on page 156-70	Returns up to the first 2000 bytes of the data retrieved from the given URL. This function can be used directly in SQL queries
<a href="#">REQUEST_PIECES Function</a> on page 156-73	Returns a PL/SQL table of 2000-byte pieces of the data retrieved from the given URL

## Session Settings Subprograms

**Table 156–8 UTL\_HTTP Subprograms—Session Settings**

Subprogram	Description
<a href="#">GET_BODY_CHARSET Procedure</a> on page 156-47	Retrieves the default character set of the body of all future HTTP requests
<a href="#">GET_COOKIE_SUPPORT Procedure</a> on page 156-49	Retrieves the current cookie support settings
<a href="#">GET_DETAILED_EXCP_SUPPORT Procedure</a> on page 156-51	Checks if the UTL_HTTP package will raise a detailed exception or not
<a href="#">GET_FOLLOW_REDIRECT Procedure</a> on page 156-54	Retrieves the follow-redirect setting in the current session
<a href="#">GET_PERSISTENT_CONN_SUPPORT Procedure</a> on page 156-59	Checks if the persistent connection support is enabled and gets the maximum number of persistent connections in the current session
<a href="#">GET_PROXY Procedure</a> on page 156-61	Retrieves the current proxy settings
<a href="#">GET_RESPONSE_ERROR_CHECK Procedure</a> on page 156-63	Checks if the response error check is set or not
<a href="#">GET_TRANSFER_TIMEOUT Procedure</a> on page 156-64	Retrieves the current network transfer timeout value
<a href="#">SET_BODY_CHARSET Procedures</a> on page 156-78	Sets the default character set of the body of all future HTTP requests when the media type is <code>text</code> and the character set is not specified in the <code>Content-Type</code> header
<a href="#">SET_COOKIE_SUPPORT Procedures</a> on page 156-80	Sets whether or not future HTTP requests will support HTTP cookies; sets the maximum number of cookies maintained in the current database user session
<a href="#">SET_DETAILED_EXCP_SUPPORT Procedure</a> on page 156-82	Sets the UTL_HTTP package to raise a detailed exception
<a href="#">SET_FOLLOW_REDIRECT Procedures</a> on page 156-83	Sets the maximum number of times UTL_HTTP follows the HTTP redirect instruction in the HTTP responses to future requests in the <code>get_response</code> function
<a href="#">SET_PERSISTENT_CONN_SUPPORT Procedure</a> on page 156-87	Sets whether or not future HTTP requests will support the HTTP 1.1 persistent connection; sets the maximum number of persistent connections maintained in the current database user session
<a href="#">SET_PROXY Procedure</a> on page 156-90	Sets the proxy to be used for requests of HTTP or other protocols

**Table 156–8 (Cont.) UTL\_HTTP Subprograms—Session Settings**

<b>Subprogram</b>	<b>Description</b>
<a href="#">SET_RESPONSE_ERROR_CHECK Procedure</a> on page 156-92	Sets whether or not <code>get_response</code> raises an exception when the Web server returns a status code that indicates an error—a status code in the 4xx or 5xx ranges
<a href="#">SET_TRANSFER_TIMEOUT Procedure</a> on page 156-93	Sets the timeout value for <code>UTL_HTTP</code> to read the HTTP response from the Web server or proxy server
<a href="#">SET_WALLET Procedure</a> on page 156-94	Sets the Oracle Wallet used for all HTTP requests over Secured Socket Layer (SSL), that is, HTTPS

---

## HTTP Requests Subprograms

**Table 156–9** *UTL\_HTTP Subprograms—HTTP Requests*

Subprogram	Description
<a href="#">BEGIN_REQUEST Function</a> on page 156-37	Begins a new HTTP request. <code>UTL_HTTP</code> establishes the network connection to the target Web server or the proxy server and sends the HTTP request line.
<a href="#">END_REQUEST Procedure</a> on page 156-43	Ends the HTTP request.
<a href="#">SET_HEADER Procedure</a> on page 156-85	Sets an HTTP request header. The request header is sent to the Web server as soon as it is set.
<a href="#">SET_AUTHENTICATION Procedure</a> on page 156-77	Sets HTTP authentication information in the HTTP request header. The Web server needs this information to authorize the request.
<a href="#">SET_BODY_CHARSET Procedures</a> on page 156-78	Sets the character set of the request body when the media type is <code>text</code> but the character set is not specified in the <code>Content-Type</code> header.
<a href="#">SET_COOKIE_SUPPORT Procedures</a> on page 156-80	Enables or disables support for the HTTP cookies in the request.
<a href="#">SET_FOLLOW_REDIRECT Procedures</a> on page 156-83	Sets the maximum number of times <code>UTL_HTTP</code> follows the HTTP redirect instruction in the HTTP response to this request in the <a href="#">GET_RESPONSE Function</a> on page 156-62.
<a href="#">SET_PERSISTENT_CONN_SUPPORT Procedure</a> on page 156-87	Enables or disables support for the HTTP 1.1 persistent-connection in the request.
<a href="#">WRITE_LINE Procedure</a> on page 156-96	Writes a text line in the HTTP request body and ends the line with new-line characters (CRLF as defined in <code>UTL_TCP</code> ).
<a href="#">WRITE_RAW Procedure</a> on page 156-98	Writes some binary data in the HTTP request body.
<a href="#">WRITE_TEXT Procedure</a> on page 156-99	Writes some text data in the HTTP request body.

## HTTP Responses Subprograms

**Table 156–10** *UTL\_HTTP Subprograms—HTTP Responses*

Subprogram	Description
<a href="#">END_RESPONSE Procedure</a> on page 156-44	Ends the HTTP response. It completes the HTTP request and response.
<a href="#">GET_AUTHENTICATION Procedure</a> on page 156-45	Retrieves the HTTP authentication information needed for the request to be accepted by the Web server as indicated in the HTTP response header.
<a href="#">GET_HEADER Procedure</a> on page 156-55	Returns the $n^{\text{th}}$ HTTP response header name and value returned in the response.
<a href="#">GET_HEADER_BY_NAME Procedure</a> on page 156-56	Returns the HTTP response header value returned in the response given the name of the header.
<a href="#">GET_HEADER_COUNT Function</a> on page 156-57	Returns the number of HTTP response headers returned in the response.
<a href="#">GET_RESPONSE Function</a> on page 156-62	Reads the HTTP response. When the function returns, the status line and the HTTP response headers have been read and processed.
<a href="#">READ_LINE Procedure</a> on page 156-65	Reads the HTTP response body in text form until the end of line is reached and returns the output in the caller-supplied buffer.
<a href="#">READ_RAW Procedure</a> on page 156-67	Reads the HTTP response body in binary form and returns the output in the caller-supplied buffer.
<a href="#">READ_TEXT Procedure</a> on page 156-68	Reads the HTTP response body in text form and returns the output in the caller-supplied buffer.
<a href="#">SET_BODY_CHARSET Procedures</a> on page 156-78	Sets the character set of the response body when the media type is "text" but the character set is not specified in the "Content-Type" header.

---

## HTTP Cookies Subprograms

**Table 156–11** *UTL\_HTTP Subprograms—HTTP Cookies*

<b>Subprogram</b>	<b>Description</b>
<a href="#">ADD_COOKIES Procedure</a> on page 156-36	Adds the cookies maintained by UTL_HTTP.
<a href="#">CLEAR_COOKIES Procedure</a> on page 156-39	Clears all cookies maintained by the UTL_HTTP package.
<a href="#">GET_COOKIE_COUNT Function</a> on page 156-48	Returns the number of cookies currently maintained by the UTL_HTTP package set by all Web servers.
<a href="#">GET_COOKIES Function</a> on page 156-50	Returns all the cookies currently maintained by the UTL_HTTP package set by all Web servers.

---

## HTTP Persistent Connections Subprograms

**Table 156–12** *UTL\_HTTP Subprograms—HTTP Persistent Connections*

<b>Subprogram</b>	<b>Description</b>
<a href="#">CLOSE_PERSISTENT_CONN Procedure</a> on page 156-40	Closes an HTTP persistent connection maintained by the UTL_HTTP package in the current database session.
<a href="#">CLOSE_PERSISTENT_CONNS Procedure</a> on page 156-41	Closes a group of HTTP persistent connections maintained by the UTL_HTTP package in the current database session.
<a href="#">GET_PERSISTENT_CONN_COUNT Function</a> on page 156-58	Returns the number of network connections currently kept persistent by the UTL_HTTP package to the Web servers.
<a href="#">GET_PERSISTENT_CONNS Procedure</a> on page 156-60	Returns all the network connections currently kept persistent by the UTL_HTTP package to the Web servers.



---

## Error Conditions Subprograms

**Table 156–13** *UTL\_HTTP Subprograms—Error Conditions*

<b>Subprogram</b>	<b>Description</b>
<a href="#">GET_DETAILED_SQLCODE Function</a> on page 156-52	Retrieves the detailed SQLCODE of the last exception raised.
<a href="#">GET_DETAILED_SQLERRM Function</a> on page 156-53	Retrieves the detailed SQLERRM of the last exception raised.

---

---

## Summary of UTL\_HTTP Subprograms

**Table 156–14 UTL\_HTTP Package Subprograms**

Subprogram	Description
<a href="#">ADD_COOKIES Procedure</a> on page 156-36	Adds the cookies maintained by UTL_HTTP (see <a href="#">HTTP Cookies</a> on page 156-13 and <a href="#">HTTP Cookies Subprograms</a> on page 156-27)
<a href="#">BEGIN_REQUEST Function</a> on page 156-37	Begins a new HTTP request. UTL_HTTP establishes the network connection to the target Web server or the proxy server and sends the HTTP request line (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">CLEAR_COOKIES Procedure</a> on page 156-39	Clears all cookies maintained by the UTL_HTTP package (see <a href="#">HTTP Cookies</a> on page 156-13 and <a href="#">HTTP Cookies Subprograms</a> on page 156-27)
<a href="#">CLOSE_PERSISTENT_CONN Procedure</a> on page 156-40	Closes an HTTP persistent connection maintained by the UTL_HTTP package in the current database session (see <a href="#">HTTP Persistent Connections</a> on page 156-13 and <a href="#">HTTP Persistent Connections Subprograms</a> on page 156-28)
<a href="#">CLOSE_PERSISTENT_CONNS Procedure</a> on page 156-41	Closes a group of HTTP persistent connections maintained by the UTL_HTTP package in the current database session (see <a href="#">HTTP Persistent Connections</a> on page 156-13 and <a href="#">HTTP Persistent Connections Subprograms</a> on page 156-28)
<a href="#">END_REQUEST Procedure</a> on page 156-43	Ends the HTTP request (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">END_RESPONSE Procedure</a> on page 156-44	Ends the HTTP response. It completes the HTTP request and response (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)
<a href="#">GET_AUTHENTICATION Procedure</a> on page 156-45	Retrieves the HTTP authentication information needed for the request to be accepted by the Web server as indicated in the HTTP response header (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)

**Table 156–14 (Cont.) UTL\_HTTP Package Subprograms**

Subprogram	Description
<a href="#">GET_BODY_CHARSET Procedure</a> on page 156-47	Retrieves the default character set of the body of all future HTTP requests (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_COOKIE_COUNT Function</a> on page 156-48	Returns the number of cookies currently maintained by the UTL_HTTP package set by all Web servers (see <a href="#">HTTP Cookies</a> on page 156-13 and <a href="#">HTTP Cookies Subprograms</a> on page 156-27)
<a href="#">GET_COOKIE_SUPPORT Procedure</a> on page 156-49	Retrieves the current cookie support settings (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_COOKIES Function</a> on page 156-50	Returns all the cookies currently maintained by the UTL_HTTP package set by all Web servers (see <a href="#">HTTP Cookies</a> on page 156-13 and <a href="#">HTTP Cookies Subprograms</a> on page 156-27)
<a href="#">GET_DETAILED_EXCP_SUPPORT Procedure</a> on page 156-51	Checks if the UTL_HTTP package will raise a detailed exception or not (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_DETAILED_SQLCODE Function</a> on page 156-52	Retrieves the detailed SQLCODE of the last exception raised (see <a href="#">Error Conditions</a> on page 156-14 and <a href="#">Error Conditions Subprograms</a> on page 156-29)
<a href="#">GET_DETAILED_SQLERRM Function</a> on page 156-53	Retrieves the detailed SQLERRM of the last exception raised (see <a href="#">Error Conditions</a> on page 156-14 and <a href="#">Error Conditions Subprograms</a> on page 156-29)
<a href="#">GET_FOLLOW_REDIRECT Procedure</a> on page 156-54	Retrieves the follow-redirect setting in the current session (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_HEADER Procedure</a> on page 156-55	Returns the $n^{\text{th}}$ HTTP response header name and value returned in the response (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)
<a href="#">GET_HEADER_BY_NAME Procedure</a> on page 156-56	Returns the HTTP response header value returned in the response given the name of the header (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)

**Table 156–14 (Cont.) UTL\_HTTP Package Subprograms**

Subprogram	Description
<a href="#">GET_HEADER_COUNT Function</a> on page 156-57	Returns the number of HTTP response headers returned in the response (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)
<a href="#">GET_PERSISTENT_CONN_COUNT Function</a> on page 156-58	Returns the number of network connections currently kept persistent by the UTL_HTTP package to the Web servers (see <a href="#">HTTP Persistent Connections</a> on page 156-13 and <a href="#">HTTP Persistent Connections Subprograms</a> on page 156-28)
<a href="#">GET_PERSISTENT_CONN_SUPPORT Procedure</a> on page 156-59	Sees whether or not future HTTP requests will support the HTTP 1.1 persistent connection; sets the maximum number of persistent connections maintained in the current database user session (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_PERSISTENT_CONN_SUPPORT Procedure</a> on page 156-59	Checks if the persistent connection support is enabled and gets the maximum number of persistent connections in the current session (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_PERSISTENT_CONNS Procedure</a> on page 156-60	Returns all the network connections currently kept persistent by the UTL_HTTP package to the Web servers (see <a href="#">HTTP Persistent Connections</a> on page 156-13 and <a href="#">HTTP Persistent Connections Subprograms</a> on page 156-28)
<a href="#">GET_PROXY Procedure</a> on page 156-61	Retrieves the current proxy settings (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_RESPONSE Function</a> on page 156-62	Reads the HTTP response. When the function returns, the status line and the HTTP response headers have been read and processed (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)
<a href="#">GET_RESPONSE_ERROR_CHECK Procedure</a> on page 156-63	Checks if the response error check is set or no (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">GET_TRANSFER_TIMEOUT Procedure</a> on page 156-64	Retrieves the current network transfer timeout value (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)

**Table 156–14 (Cont.) UTL\_HTTP Package Subprograms**

Subprogram	Description
<a href="#">READ_LINE Procedure</a> on page 156-65	Reads the HTTP response body in text form until the end of line is reached and returns the output in the caller-supplied buffer (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)
<a href="#">READ_RAW Procedure</a> on page 156-67	Reads the HTTP response body in binary form and returns the output in the caller-supplied buffer (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)
<a href="#">READ_TEXT Procedure</a> on page 156-68	Reads the HTTP response body in text form and returns the output in the caller-supplied buffer (see <a href="#">HTTP Responses</a> on page 156-13 and <a href="#">HTTP Responses Subprograms</a> on page 156-26)
<a href="#">REQUEST Function</a> on page 156-70	Returns up to the first 2000 bytes of the data retrieved from the given URL. This function can be used directly in SQL queries (see <a href="#">Simple HTTP Fetches</a> on page 156-12 and <a href="#">Simple HTTP Fetches in a Single Call Subprograms</a> on page 156-22)
<a href="#">REQUEST_PIECES Function</a> on page 156-73	Returns a PL/SQL table of 2000-byte pieces of the data retrieved from the given URL (see <a href="#">Simple HTTP Fetches</a> on page 156-12 and <a href="#">Simple HTTP Fetches in a Single Call Subprograms</a> on page 156-22)
<a href="#">SET_AUTHENTICATION Procedure</a> on page 156-77	Sets HTTP authentication information in the HTTP request header. The Web server needs this information to authorize the request (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">SET_BODY_CHARSET Procedures</a> on page 156-78	Sets the default character set of the body of all future HTTP requests when the media type is <code>text</code> and the character set is not specified in the <code>Content-Type</code> header (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">SET_BODY_CHARSET Procedures</a> on page 156-78	Sets the character set of the request body when the media type is <code>text</code> but the character set is not specified in the <code>Content-Type</code> header (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)

**Table 156–14 (Cont.) UTL\_HTTP Package Subprograms**

Subprogram	Description
<a href="#">SET_BODY_CHARSET Procedures</a> on page 156-78	Sets the character set of the response body when the media type is "text" but the character set is not specified in the "Content-Type" header (see <a href="#">HTTP Responses</a> on page 156-13, <a href="#">HTTP Responses Subprograms</a> on page 156-26, <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">SET_COOKIE_SUPPORT Procedures</a> on page 156-80	Enables or disables support for the HTTP cookies in the request (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">SET_DETAILED_EXCP_SUPPORT Procedure</a> on page 156-82	Sets whether or not future HTTP requests will support HTTP cookies; sets the maximum number of cookies maintained in the current database user session (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">SET_DETAILED_EXCP_SUPPORT Procedure</a> on page 156-82	Sets the UTL_HTTP package to raise a detailed exception (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">SET_FOLLOW_REDIRECT Procedures</a> on page 156-83	Sets the maximum number of times UTL_HTTP follows the HTTP redirect instruction in the HTTP response to this request in the GET_RESPONSE function (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">SET_HEADER Procedure</a> on page 156-85	Sets the maximum number of times UTL_HTTP follows the HTTP redirect instruction in the HTTP responses to future requests in the get_response function (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">SET_HEADER Procedure</a> on page 156-85	Sets an HTTP request header. The request header is sent to the Web server as soon as it is set (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">SET_PERSISTENT_CONN_SUPPORT Procedure</a> on page 156-87	Enables or disables support for the HTTP 1.1 persistent-connection in the request (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">SET_PROXY Procedure</a> on page 156-90	Sets the proxy to be used for requests of HTTP or other protocols (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)

**Table 156–14 (Cont.) UTL\_HTTP Package Subprograms**

Subprogram	Description
<a href="#">SET_RESPONSE_ERROR_CHECK Procedure</a> on page 156-92	Sets whether or not <code>get_response</code> raises an exception when the Web server returns a status code that indicates an error—a status code in the 4xx or 5xx ranges (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">SET_TRANSFER_TIMEOUT Procedure</a> on page 156-93	Sets the timeout value for <code>UTL_HTTP</code> to read the HTTP response from the Web server or proxy server (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">SET_WALLET Procedure</a> on page 156-94	Sets the Oracle Wallet used for all HTTP requests over Secured Socket Layer (SSL), that is, HTTPS (see <a href="#">Session Settings</a> on page 156-13 and <a href="#">Session Settings Subprograms</a> on page 156-23)
<a href="#">WRITE_LINE Procedure</a> on page 156-96	Writes a text line in the HTTP request body and ends the line with new-line characters (CRLF as defined in <code>UTL_TCP</code> ) (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">WRITE_RAW Procedure</a> on page 156-98	Writes some binary data in the HTTP request body (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)
<a href="#">WRITE_TEXT Procedure</a> on page 156-99	Writes some text data in the HTTP request body (see <a href="#">HTTP Requests</a> on page 156-13 and <a href="#">HTTP Requests Subprograms</a> on page 156-25)

## ADD\_COOKIES Procedure

This procedure adds the cookies maintained by UTL\_HTTP.

**See Also:** [HTTP Cookies](#) on page 156-13 and [HTTP Cookies Subprograms](#) on page 156-27

### Syntax

```
UTL_HTTP.ADD_COOKIES (
 cookies IN cookie_table);
```

### Parameters

**Table 156–15 ADD\_COOKIES Procedure Parameters**

Parameter	Description
cookies	The cookies to be added.

### Usage Notes

The cookies that the package currently maintains are not cleared before new cookies are added.



## BEGIN\_REQUEST Function

This function begins a new HTTP request. UTL\_HTTP establishes the network connection to the target Web server or the proxy server and sends the HTTP request line. The PL/SQL program continues the request by calling some other interface to complete the request. The URL may contain the username and password needed to authenticate the request to the server. The format is

```
scheme://[user[:password]@]host[:port]/[...]
```

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.BEGIN_REQUEST (
 url IN VARCHAR2,
 method IN VARCHAR2 DEFAULT 'GET',
 http_version IN VARCHAR2 DEFAULT NULL)
RETURN req;
```

### Parameters

**Table 156–16** *BEGIN\_REQUEST Function Parameters*

Parameter	Description
<code>url</code>	The URL of the HTTP request.
<code>method</code>	The method performed on the resource identified by the URL.
<code>http_version</code>	The HTTP protocol version that sends the request. The format of the protocol version is <code>HTTP/major-version.minor-version</code> , where <code>major-version</code> and <code>minor-version</code> are positive numbers. If this parameter is set to <code>NULL</code> , UTL_HTTP uses the latest HTTP protocol version that it supports to send the request. The latest version that the package supports is 1.1 and it can be upgraded to a later version. The default is <code>NULL</code> .

### Usage Notes

The URL passed as an argument to this function is not examined for illegal characters, such as spaces, according to URL specification RFC 2396. You should

escape those characters with the `UTL_URL` package to return illegal and reserved characters. URLs should consist of US-ASCII characters only. See [Chapter 166, "UTL\\_URL"](#) for a list of legal characters in URLs. Note that URLs should consist of US-ASCII characters only. The use of non-US-ASCII characters in a URL is generally unsafe.

An Oracle wallet must be set before accessing Web servers over HTTPS. See the `set_wallet` procedure on how to set up an Oracle wallet.

## CLEAR\_COOKIES Procedure

This procedure clears all cookies maintained by the UTL\_HTTP package.

**See Also:** [HTTP Cookies](#) on page 156-13 and [HTTP Cookies Subprograms](#) on page 156-27

### Syntax

```
UTL_HTTP.CLEAR_COOKIES;
```

## CLOSE\_PERSISTENT\_CONN Procedure

This procedure closes an HTTP persistent connection maintained by the UTL\_HTTP package in the current database session.

**See Also:** [HTTP Persistent Connections](#) on page 156-13 and [HTTP Persistent Connections Subprograms](#) on page 156-28

### Syntax

```
UTL_HTTP.CLOSE_PERSISTENT_CONN (
 conn IN connection);
```

### Parameters

**Table 156–17** *CLOSE\_PERSISTENT\_CONN Procedure Parameters*

Parameter	Description
conn	The HTTP persistent connection to close

## CLOSE\_PERSISTENT\_CONNS Procedure

This procedure closes a group of HTTP persistent connections maintained by the UTL\_HTTP package in the current database session. This procedure uses a pattern-match approach to decide which persistent connections to close.

To close a group of HTTP persistent connection that share a common property (for example, all connections to a particular host, or all SSL connections), set the particular parameters and leave the rest of the parameters NULL. If a particular parameter is set to NULL when this procedure is called, that parameter will not be used to decide which connections to close.

For example, the following call to the procedure closes all persistent connections to foobar:

```
UTL_HTTP.CLOSE_PERSISTENT_CONNS(host => 'foobar');
```

And the following call to the procedure closes all persistent connections through the proxy www-proxy at TCP/IP port 80:

```
UTL_HTTP.CLOSE_PERSISTENT_CONNS(proxy_host => 'foobar',
 proxy_port => 80);
```

And the following call to the procedure closes all persistent connections:

```
UTL_HTTP.CLOSE_PERSISTENT_CONNS;
```

**See Also:** [HTTP Persistent Connections](#) on page 156-13 and [HTTP Persistent Connections Subprograms](#) on page 156-28

## Syntax

```
UTL_HTTP.CLOSE_PERSISTENT_CONNS (
 host IN VARCHAR2 DEFAULT NULL,
 port IN PLS_INTEGER DEFAULT NULL,
 proxy_host IN VARCHAR2 DEFAULT NULL,
 proxy_port IN PLS_INTEGER DEFAULT NULL,
 ssl IN BOOLEAN DEFAULT NULL);
```

## Parameters

**Table 156–18** *CLOSE\_PERSISTENT\_CONNS Procedure Parameters*

Parameter	Description
host	The host for which persistent connections are to be closed
port	The port number for which persistent connections are to be closed
proxy_host	The proxy host for which persistent connections are to be closed
proxy_port	The proxy port for which persistent connections are to be closed
ssl	Close persistent SSL connection

## Usage Notes

Connections to the same Web server at different TCP/IP ports are counted individually. The host names of the Web servers are identified as specified in the URL of the original HTTP requests. Therefore, fully qualified host names with domain names will be counted differently from the host names without domain names.

Note that the use of a `NULL` value in a parameter when this procedure is called means that the caller does not care about its value when the package decides which persistent connection to close. If you want a `NULL` value in a parameter to match only a `NULL` value of the parameter of a persistent connection (which is when you want to close a specific persistent connection), you should use the `close_persistent_conn` procedure that closes a specific persistent connection.

## END\_REQUEST Procedure

This procedure ends the HTTP request. To terminate the HTTP request without completing the request and waiting for the response, the program can call this procedure. Otherwise, the program should go through the normal sequence of beginning a request, getting the response, and closing the response. The network connection will always be closed and will not be reused.

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.END_REQUEST (
 r IN OUT NOCOPY req);
```

### Parameters

**Table 156–19** *END\_REQUEST Procedure Parameters*

Parameter	Description
r	The HTTP request

## END\_RESPONSE Procedure

This procedure ends the HTTP response. It completes the HTTP request and response. Unless HTTP 1.1 persistent connection is used in this request, the network connection is also closed.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.END_RESPONSE (
 r IN OUT NOCOPY resp);
```

### Parameters

**Table 156–20** *END\_RESPONSE Procedure Parameters*

Parameter	Description
r	The HTTP response.



## GET\_AUTHENTICATION Procedure

This procedure retrieves the HTTP authentication information needed for the request to be accepted by the Web server as indicated in the HTTP response header.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.GET_AUTHENTICATION(
 r IN OUT NOCOPY resp,
 scheme OUT VARCHAR2,
 realm OUT VARCHAR2,
 for_proxy IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 156–21** *GET\_AUTHENTICATION Procedure Parameters*

Parameter	Description
r	The HTTP response.
scheme	The scheme for the required HTTP authentication
realm	The realm for the required HTTP authentication
for_proxy	Returns the HTTP authentication information required for the access to the HTTP proxy server instead of the Web server? Default is FALSE.

### Usage Notes

When a Web client is unaware that a document is protected, at least two HTTP requests are required for the document to be retrieved. In the first HTTP request, the Web client makes the request without supplying required authentication information; so the request is denied. The Web client can determine the authentication information required for the request to be authorized by calling `get_authentication`. The Web client makes the second request and supplies the required authentication information with `set_authorization`. If the authentication information can be verified by the Web server, the request will succeed and the requested document is returned. Before making the request, if the Web client knows that authentication information is required, it can supply the

required authentication information in the first request, thus saving an extra request.

## GET\_BODY\_CHARSET Procedure

This procedure retrieves the default character set of the body of all future HTTP requests.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_BODY_CHARSET (
 charset OUT NOCOPY VARCHAR2);
```

### Parameters

**Table 156–22** *GET\_BODY\_CHARSET Procedure Parameters*

Parameter	Description
charset	The default character set of the body of all future HTTP requests

## GET\_COOKIE\_COUNT Function

This function returns the number of cookies currently maintained by the UTL\_HTTP package set by all Web servers.

**See Also:** [HTTP Cookies](#) on page 156-13 and [HTTP Cookies Subprograms](#) on page 156-27

### Syntax

```
UTL_HTTP.GET_COOKIE_COUNT
RETURN PLS_INTEGER;
```

## GET\_COOKIE\_SUPPORT Procedure

This procedure retrieves the current cookie support settings.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_COOKIE_SUPPORT (
 enable OUT BOOLEAN,
 max_cookies OUT PLS_INTEGER,
 max_cookies_per_site OUT PLS_INTEGER);
```

### Parameters

**Table 156–23** *GET\_COOKIE\_SUPPORT Procedure Parameters*

Parameter	Description
enable	Indicates whether future HTTP requests should support HTTP cookies (TRUE) or not (FALSE)
max_cookies	Indicates the maximum total number of cookies maintained in the current session
max_cookies_per_site	Indicates the maximum number of cookies maintained in the current session for each Web site

## GET\_COOKIES Function

This function returns all the cookies currently maintained by the UTL\_HTTP package set by all Web servers.

**See Also:** [HTTP Cookies](#) on page 156-13 and [HTTP Cookies Subprograms](#) on page 156-27

### Syntax

```
UTL_HTTP.GET_COOKIES (
 cookies IN OUT NOCOPY cookie_table);
```

### Parameters

**Table 156–24** *GET\_COOKIES Procedure Parameters*

Parameter	Description
cookies	The cookies returned

## GET\_DETAILED\_EXCP\_SUPPORT Procedure

This procedure checks if the UTL\_HTTP package will raise a detailed exception or not.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_DETAILED_EXCP_SUPPORT (
 enable OUT BOOLEAN);
```

### Parameters

**Table 156–25** *GET\_DETAILED\_EXCP\_SUPPORT Procedure Parameters*

Parameter	Description
enable	TRUE if UTL_HTTP raises a detailed exception; otherwise FALSE

## GET\_DETAILED\_SQLCODE Function

This function retrieves the detailed `SQLCODE` of the last exception raised.

**See Also:** [Error Conditions](#) on page 156-14 and [Error Conditions Subprograms](#) on page 156-29

### Syntax

```
UTL_HTTP.GET_DETAILED_SQLCODE
RETURN PLS_INTEGER;
```



## GET\_DETAILED\_SQLERRM Function

This function retrieves the detailed `SQLERRM` of the last exception raised.

**See Also:** [Error Conditions](#) on page 156-14 and [Error Conditions Subprograms](#) on page 156-29

### Syntax

```
UTL_HTTP.GET_DETAILED_SQLERRM
RETURN VARCHAR2;
```

## GET\_FOLLOW\_REDIRECT Procedure

This procedure retrieves the follow-redirect setting in the current session

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_FOLLOW_REDIRECT (
 max_redirects OUT PLS_INTEGER);
```

### Parameters

**Table 156–26** *GET\_FOLLOW\_REDIRECT Procedure Parameters*

Parameter	Description
max_redirects	The maximum number of redirections for all future HTTP requests.

## GET\_HEADER Procedure

This procedure returns the  $n^{\text{th}}$  HTTP response header name and value returned in the response.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.GET_HEADER (
 r IN OUT NOCOPY resp,
 n IN PLS_INTEGER,
 name OUT NOCOPY VARCHAR2,
 value OUT NOCOPY VARCHAR2);
```

### Parameters

**Table 156–27** GET\_HEADER Procedure Parameters

Parameter	Description
r	The HTTP response.
n	The $n^{\text{th}}$ header to return.
name	The name of the HTTP response header.
value	The value of the HTTP response header.

### Usage Notes

If the response body returned by the remote Web server is encoded in chunked transfer encoding format, the trailer headers that are returned at the end of the response body will be added to the response, and the response header count will be updated. You can retrieve the additional headers after the end of the response body is reached and before you end the response.

## GET\_HEADER\_BY\_NAME Procedure

This procedure returns the HTTP response header value returned in the response given the name of the header.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.GET_HEADER_BY_NAME(
 r IN OUT NOCOPY resp,
 name IN VARCHAR2,
 value OUT NOCOPY VARCHAR2,
 n IN PLS_INTEGER DEFAULT 1);
```

### Parameters

**Table 156–28** *GET\_HEADER\_BY\_NAME Procedure Parameters*

Parameter	Description
r	The HTTP response
name	The name of the HTTP response header for which the value is to return
value	The value of the HTTP response header.
n	The n <sup>th</sup> occurrence of an HTTP response header by the specified name to return. The default is 1.

### Usage Notes

If the response body returned by the remote Web server is encoded in chunked transfer encoding format, the trailer headers that are returned at the end of the response body will be added to the response, and the response header count will be updated. You can retrieve the additional headers after the end of the response body is reached and before you end the response.

## GET\_HEADER\_COUNT Function

This function returns the number of HTTP response headers returned in the response.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.GET_HEADER_COUNT (
 r IN OUT NOCOPY resp)
RETURN PLS_INTEGER;
```

### Parameters

**Table 156–29** *GET\_HEADER\_COUNT Function Parameters*

Parameter	Description
r	The HTTP response

### Usage Notes

If the response body returned by the remote Web server is encoded in chunked transfer encoding format, the trailer headers that are returned at the end of the response body will be added to the response, and the response header count will be updated. You can retrieve the additional headers after the end of the response body is reached and before you end the response.

## GET\_PERSISTENT\_CONN\_COUNT Function

This function returns the number of network connections currently kept persistent by the UTL\_HTTP package to the Web servers.

**See Also:** [HTTP Persistent Connections](#) on page 156-13 and [HTTP Persistent Connections Subprograms](#) on page 156-28

### Syntax

```
UTL_HTTP.GET_PERSISTENT_CONN_COUNT
RETURN PLS_INTEGER;
```

### Usage Notes

Connections to the same Web server at different TCP/IP ports are counted individually. The host names of the Web servers are identified as specified in the URL of the original HTTP requests. Therefore, fully qualified host names with domain names will be counted differently from the host names without domain names.

## GET\_PERSISTENT\_CONN\_SUPPORT Procedure

This procedure checks:

- If the persistent connection support is enabled
- Gets the maximum number of persistent connections in the current session

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_PERSISTENT_CONN_SUPPORT (
 enable OUT BOOLEAN,
 max_conns OUT PLS_INTEGER);
```

### Parameters

**Table 156–30** *GET\_PERSISTENT\_CONN\_SUPPORT Procedure Parameters*

Parameter	Description
enable	TRUE if persistent connection support is enabled; otherwise FALSE
max_conns	the maximum number of persistent connections maintained in the current session.

## GET\_PERSISTENT\_CONNS Procedure

This procedure returns all the network connections currently kept persistent by the UTL\_HTTP package to the Web servers.

**See Also:** [HTTP Persistent Connections](#) on page 156-13 and [HTTP Persistent Connections Subprograms](#) on page 156-28

### Syntax

```
UTL_HTTP.get_persistent_conns (
 connections IN OUT NOCOPY connection_table);
```

### Parameters

**Table 156–31** GET\_PERSISTENT\_CONNS Procedure Parameters

Parameter	Description
connections	The network connections kept persistent

### Usage Notes

Connections to the same Web server at different TCP/IP ports are counted individually. The host names of the Web servers are identified as specified in the URL of the original HTTP requests. Therefore, fully qualified host names with domain names will be counted differently from the host names without domain names.



## GET\_PROXY Procedure

This procedure retrieves the current proxy settings.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_PROXY (
 proxy OUT NOCOPY VARCHAR2,
 no_proxy_domains OUT NOCOPY VARCHAR2);
```

### Parameters

**Table 156–32** *GET\_PROXY Procedure Parameters*

Parameter	Description
<code>proxy</code>	The proxy (host and an optional port number) currently used by the UTL_HTTP package
<code>no_proxy_domains</code>	The list of hosts and domains for which no proxy is used for all requests.

## GET\_RESPONSE Function

This function reads the HTTP response. When the function returns, the status line and the HTTP response headers have been read and processed. The status code, reason phrase, and the HTTP protocol version are stored in the response record. This function completes the HTTP headers section.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.GET_RESPONSE (
 r IN OUT NOCOPY req)
RETURN resp;
```

### Parameters

**Table 156–33** *GET\_RESPONSE Procedure Parameters*

Parameter	Description
r	The HTTP response

## GET\_RESPONSE\_ERROR\_CHECK Procedure

This procedure checks if the response error check is set or not.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_RESPONSE_ERROR_CHECK (
 enable OUT BOOLEAN);
```

### Parameters

**Table 156–34** *GET\_RESPONSE\_ERROR\_CHECK Procedure Parameters*

Parameter	Description
enable	TRUE if the response error check is set; otherwise FALSE

## GET\_TRANSFER\_TIMEOUT Procedure

This procedure retrieves the default timeout value for all future HTTP requests.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.GET_TRANSFER_TIMEOUT (
 timeout OUT PLS_INTEGER);
```

### Parameters

**Table 156–35** *GET\_TRANSFER\_TIMEOUT Procedure Parameters*

Parameter	Description
timeout	The network transfer timeout value in seconds.

## READ\_LINE Procedure

This procedure reads the HTTP response body in text form until the end of line is reached and returns the output in the caller-supplied buffer. The end of line is as defined in the function `read_line` of `UTL_TCP`. The `end_of_body` exception will be raised if the end of the HTTP response body is reached. Text data is automatically converted from the response body character set to the database character set.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.READ_LINE(
 r IN OUT NOCOPY resp,
 data OUT NOCOPY VARCHAR2 CHARACTER SET ANY_CS,
 remove_crlf IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 156–36** *READ\_LINE Procedure Parameters*

Parameter	Description
<code>r</code>	The HTTP response.
<code>data</code>	The HTTP response body in text form
<code>remove_crlf</code>	Removes the newline characters if set to <code>TRUE</code>

### Usage Notes

The `UTL_HTTP` package supports HTTP 1.1 chunked transfer-encoding. When the response body is returned in chunked transfer-encoding format as indicated in the response header, the package automatically decodes the chunks and returns the response body in de-chunked format.

If transfer timeout is set in the request of this response, `read_line` waits for each data packet to be ready to read until timeout occurs. If it occurs, this procedure stops reading and returns all the data read successfully. If no data is read successfully, the `transfer_timeout` exception is raised. The exception can be handled and the read operation can be retried later.

If a partial multibyte character is found at the end of the response body, `read_line` stops reading and returns all the complete multibyte characters read successfully. If no complete character is read successfully, the `partial_multibyte_char` exception is raised. The exception can be handled and the bytes of that partial multibyte character can be read as binary by the `read_raw` procedure. If a partial multibyte character is seen in the middle of the response body because the remaining bytes of the character have not arrived and read timeout occurs, the `transfer_timeout` exception is raised instead. The exception can be handled and the read operation can be retried later.

When the "Content-Type" response header specifies the character set of the response body and the character set is unknown or unsupported by Oracle, the "ORA-01482: unsupported character set" exception is raised if you try to read the response body as text. You can either read the response body as binary using the `READ_RAW` procedure, or set the character set of the response body explicitly using the `SET_BODY_CHARSET` procedure and read the response body as text again.

## READ\_RAW Procedure

This procedure reads the HTTP response body in binary form and returns the output in the caller-supplied buffer. The `end_of_body` exception will be raised if the end of the HTTP response body is reached.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.READ_RAW(
 r IN OUT NOCOPY resp,
 data OUT NOCOPY RAW,
 len IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 156–37 READ\_RAW Procedure Parameters**

Parameter	Description
<code>r</code>	The HTTP response.
<code>data</code>	The HTTP response body in binary form
<code>len</code>	The number of bytes of data to read. If <code>len</code> is <code>NULL</code> , this procedure will read as much input as possible to fill the buffer allocated in <code>data</code> . The actual amount of data returned may be less than that specified if not much data is available before the end of the HTTP response body is reached or the <code>transfer_timeout</code> amount of time has elapsed. The default is <code>NULL</code> .

### Usage Notes

The `UTL_HTTP` package supports HTTP 1.1 chunked transfer-encoding. When the response body is returned in chunked transfer-encoding format as indicated in the response header, the package automatically decodes the chunks and returns the response body in de-chunked format.

If transfer timeout is set in the request of this response, `read_raw` waits for each data packet to be ready to read until timeout occurs. If it occurs, `read_raw` stops reading and returns all the data read successfully. If no data is read successfully, the `transfer_timeout` exception is raised. The exception can be handled and the read operation can be retried later.

## READ\_TEXT Procedure

This procedure reads the HTTP response body in text form and returns the output in the caller-supplied buffer. The `end_of_body` exception will be raised if the end of the HTTP response body is reached. Text data is automatically converted from the response body character set to the database character set.

**See Also:** [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26

### Syntax

```
UTL_HTTP.READ_TEXT(
 r IN OUT NOCOPY resp,
 data OUT NOCOPY VARCHAR2 CHARACTER SET ANY_CS,
 len IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 156–38** *READ\_TEXT Procedure Parameters*

Parameter	Description
<code>r</code>	The HTTP response.
<code>data</code>	The HTTP response body in text form
<code>len</code>	The maximum number of characters of data to read. If <code>len</code> is NULL, this procedure will read as much input as possible to fill the buffer allocated in <code>data</code> . The actual amount of data returned may be less than that specified if little data is available before the end of the HTTP response body is reached or the <code>transfer_timeout</code> amount of time has elapsed. The default is NULL.

### Usage Notes

The `UTL_HTTP` package supports HTTP 1.1 chunked transfer-encoding. When the response body is returned in chunked transfer-encoding format as indicated in the response header, the package automatically decodes the chunks and returns the response body in de-chunked format.

If transfer timeout is set in the request of this response, `read_text` waits for each data packet to be ready to read until timeout occurs. If it occurs, this procedure stops reading and returns all the data read successfully. If no data is read



successfully, the `transfer_timeout` exception is raised. The exception can be handled and the read operation can be retried later.

If a partial multibyte character is found at the end of the response body, `read_text` stops reading and returns all the complete multibyte characters read successfully. If no complete character is read successfully, the `partial_multibyte_char` exception is raised. The exception can be handled and the bytes of that partial multibyte character can be read as binary by the `read_raw` procedure. If a partial multibyte character is seen in the middle of the response body because the remaining bytes of the character have not arrived and read timeout occurs, the `transfer_timeout` exception is raised instead. The exception can be handled and the read operation can be retried later.

When the "Content-Type" response header specifies the character set of the response body and the character set is unknown or unsupported by Oracle, the "ORA-01482: unsupported character set" exception is raised if you try to read the response body as text. You can either read the response body as binary using the `READ_RAW` procedure, or set the character set of the response body explicitly using the `SET_BODY_CHARSET` procedure and read the response body as text again.

## REQUEST Function

This function returns up to the first 2000 bytes of data retrieved from the given URL. This function can be used directly in SQL queries. The URL may contain the username and password needed to authenticate the request to the server. The format is

```
scheme://[user[:password]@]host[:port]/[...]
```

You can define a username/password for the proxy to be specified in the proxy string. The format is

```
[http://][user[:password]@]host[:port][/]
```

**See Also:** [Simple HTTP Fetches](#) on page 156-12 and [Simple HTTP Fetches in a Single Call Subprograms](#) on page 156-22

### Syntax

```
UTL_HTTP.REQUEST (
 url IN VARCHAR2,
 proxy IN VARCHAR2 DEFAULT NULL,
 wallet_path IN VARCHAR2 DEFAULT NULL,
 wallet_password IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

### Pragmas

```
pragma restrict_references (request, wnds, rnds, wnps, rnps);
```

### Parameters

**Table 156–39** *REQUEST Function Parameters*

Parameter	Description
url	Uniform resource locator.
proxy	(Optional) Specifies a proxy server to use when making the HTTP request. See SET_PROXY for the full format of the proxy setting.

**Table 156–39 REQUEST Function Parameters**

Parameter	Description
wallet_path	(Optional) Specifies a client-side wallet. The client-side wallet contains the list of trusted certificate authorities required for HTTPS request. The format of <code>wallet_path</code> on a PC is, for example, <code>file:c:\WINNT\Profiles\<username>\WALLETS</username></code> , and in Unix is, for example, <code>file:/home/&lt;username&gt;/wallets</code> .  When the UTL_HTTP package is executed in the Oracle database server, the wallet is accessed from the database server. Therefore, the wallet path must be accessible from the database server. See <code>set_wallet</code> for a description on how to set up an Oracle wallet. Non-HTTPS requests do not require an Oracle wallet.
wallet_password	(Optional) Specifies the password required to open the wallet.

## Return Values

The return type is a string of length 2000 or less, which contains up to the first 2000 bytes of the HTML result returned from the HTTP request to the argument URL.

## Exceptions

INIT\_FAILED  
REQUEST\_FAILED

## Usage Notes

The URL passed as an argument to this function is not examined for illegal characters, for example, spaces, according to URL specification RFC 2396. The caller should escape those characters with the UTL\_URL package. See the comments of the package for the list of legal characters in URLs. Note that URLs should consist of US-ASCII characters only. The use of non-US-ASCII characters in a URL is generally unsafe.

Please see the documentation of the function `set_wallet` on the use of an Oracle wallet, which is required for accessing HTTPS Web servers.

Unless response error check is turned on, this function does not raise an exception when a 4xx or 5xx response is received from the Web server. Instead, it returns the formatted error message from the Web server:

```
<HTML>
<HEAD>
```

```
<TITLE>Error Message</TITLE>
</HEAD>
<BODY>
<H1>Fatal Error 500</H1>
Can't Access Document: http://home.nothing.comm.
<P>
Reason: Can't locate remote host: home.nothing.comm.
<P>
<P><HR>
<ADDRESS>
CERN-HTTPD3.0A</ADDRESS>
</BODY>
</HTML>
```

## Examples

```
SQLPLUS> SELECT utl_http.request('http://www.my-company.com/') FROM dual;
UTL_HTTP.REQUEST('HTTP://WWW.MY-COMPANY.COM/')
<html>
<head><title>My Company Home Page</title>
<!--changed Jan. 16, 19
1 row selected.
```

**If you are behind a firewall, include the `proxy` parameter. For example, from within the Oracle firewall, where there might be a proxy server named `www-proxy.my-company.com`:**

```
SQLPLUS> SELECT
utl_http.request('http://www.my-company.com', 'www-proxy.us.my-company.com')
FROM dual;
```

## REQUEST\_PIECES Function

This function returns a PL/SQL table of 2000-byte pieces of the data retrieved from the given URL. You can define a username/password for the proxy to be specified in the proxy string. The format is

```
[http://][user[:password]@]host[:port][/]
```

**See Also:** [Simple HTTP Fetches](#) on page 156-12 and [Simple HTTP Fetches in a Single Call Subprograms](#) on page 156-22

### Syntax

```
type html_pieces is table of varchar2(2000) index by binary_integer;
```

```
UTL_HTTP.REQUEST_PIECES (
 url IN VARCHAR2,
 max_pieces IN NATURAL DEFAULT 32767,
 proxy IN VARCHAR2 DEFAULT NULL,
 wallet_path IN VARCHAR2 DEFAULT NULL,
 wallet_password IN VARCHAR2 DEFAULT NULL)
RETURN html_pieces;
```

### Pragmas

```
pragma restrict_references (request_pieces, wnds, rnds, wnps, rnps);
```

### Parameters

**Table 156–40** *REQUEST\_PIECES Function Parameters*

Parameter	Description
url	Uniform resource locator.
max_pieces	(Optional) The maximum number of pieces (each 2000 characters in length, except for the last, which may be shorter), that REQUEST_PIECES should return. If provided, then that argument should be a positive integer.
proxy	(Optional) Specifies a proxy server to use when making the HTTP request. See SET_PROXY for the full format of the proxy setting.

**Table 156–40 REQUEST\_PIECES Function Parameters**

Parameter	Description
wallet_path	<p>(Optional) Specifies a client-side wallet. The client-side wallet contains the list of trusted certificate authorities required for HTTPS request.</p> <p>The format of wallet_path on a PC is, for example, file:c:\WINNT\Profiles\<username>\WALLETS, and in Unix is, for example, file:/home/&lt;username&gt;/wallets. When the UTL_HTTP package is executed in the Oracle database server, the wallet is accessed from the database server. Therefore, the wallet path must be accessible from the database server.</username></p> <p>See set_wallet for the description on how to set up an Oracle wallet. Non-HTTPS requests do not require an Oracle wallet.</p>
wallet_password	(Optional) Specifies the password required to open the wallet.

## Return Values

REQUEST\_PIECES returns a PL/SQL table of type UTL\_HTTP.HTML\_PIECES. Each element of that PL/SQL table is a string of maximum length 2000. The elements of the PL/SQL table returned by REQUEST\_PIECES are successive pieces of the data obtained from the HTTP request to that URL.

## Exceptions

INIT\_FAILED  
REQUEST\_FAILED

## Usage Notes

The URL passed as an argument to this function will not be examined for illegal characters, for example, spaces, according to URL specification RFC 2396. The caller should escape those characters with the UTL\_URL package. See the comments of the package for the list of legal characters in URLs. Note that URLs should consist of US-ASCII characters only. The use of non-US-ASCII characters in a URL is generally unsafe.

Each entry of the PL/SQL table (the "pieces") returned by this function may not be filled to their fullest capacity. The function may start filling the data in the next piece before the previous "piece" is totally full.

Please see the documentation of the function `set_wallet` on the use of an Oracle wallet, which is required for accessing HTTPS Web servers.

Unless response error check is turned on, this function does not raise an exception when a 4xx or 5xx response is received from the Web server. Instead, it returns the formatted error message from the Web server:

```
<HTML>
<HEAD>
<TITLE>Error Message</TITLE>
</HEAD>
<BODY>
<H1>Fatal Error 500</H1>
Can't Access Document: http://home.nothing.comm.
<P>
Reason: Can't locate remote host: home.nothing.comm.
<P>
<P><HR>
<ADDRESS>
CERN-HTTPD3.0A</ADDRESS>
</BODY>
</HTML>
```

## Examples

```
SET SERVEROUTPUT ON
```

```
DECLARE
 x utl_http.html_pieces;
 len PLS_INTEGER;
BEGIN
 x := utl_http.request_pieces('http://www.oracle.com/', 100);
 dbms_output.put_line(x.count || ' pieces were retrieved. ');
 dbms_output.put_line('with total length ');
 IF x.count < 1 THEN
 dbms_output.put_line('0 ');
 ELSE
 len := 0;
 FOR i in 1..x.count LOOP
 len := len + length(x(i));
 END LOOP;
 dbms_output.put_line(len);
 END IF;
END;
```

```
/
-- Output
Statement processed.
4 pieces were retrieved.
with total length
7687
```



## SET\_AUTHENTICATION Procedure

This procedure sets HTTP authentication information in the HTTP request header. The Web server needs this information to authorize the request.

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.SET_AUTHENTICATION(
 r IN OUT NOCOPY req,
 username IN VARCHAR2,
 password IN VARCHAR2,
 scheme IN VARCHAR2 DEFAULT 'Basic',
 for_proxy IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 156–41** SET\_AUTHENTICATION Procedure Parameters

Parameter	Description
r	The HTTP request
username	The username for the HTTP authentication
password	The password for the HTTP authentication
scheme	The HTTP authentication scheme. The default, BASIC, denotes the HTTP Basic Authentication scheme.
for_proxy	Identifies if the HTTP authentication information is for access to the HTTP proxy server instead of the Web server. Default is FALSE.

### Usage Notes

Only the HTTP Basic Authentication scheme is supported.

## SET\_BODY\_CHARSET Procedures

This procedure is overloaded. The description of different functionalities is located alongside the syntax declarations.

**See Also:**

- [HTTP Responses](#) on page 156-13 and [HTTP Responses Subprograms](#) on page 156-26
- [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

Sets the default character set of the body of all future HTTP requests when the media type is `text` and the character set is not specified in the `Content-Type` header. Following the HTTP protocol standard specification, if the media type of a request or a response is `text`, but the character set information is missing in the `Content-Type` header, the character set of the request or response body should default to `ISO-8859-1`. A response created for a request inherits the default body character set of the request instead of the body character set of the current session. The default body character set is `ISO-8859-1` in a database user session. The default body character set setting affects only future requests and has no effect on existing requests. After a request is created, the body character set can be changed by using the other `SET_BODY_CHARSET` procedure that operates on a request:

```
UTL_HTTP.SET_BODY_CHARSET (
 charset IN VARCHAR2 DEFAULT NULL);
```

Sets the character set of the request body when the media type is `text` but the character set is not specified in the `Content-Type` header. According to the HTTP protocol standard specification, if the media type of a request or a response is "text" but the character set information is missing in the `Content-Type` header, the character set of the request or response body should default to "ISO-8859-1". Use this procedure to change the default body character set a request inherits from the session default setting:

```
UTL_HTTP.SET_BODY_CHARSET(
 r IN OUT NOCOPY req,
 charset IN VARCHAR2 DEFAULT NULL);
```

Sets the character set of the response body when the media type is "text" but the character set is not specified in the "Content-Type" header. For each the HTTP protocol standard specification, if the media type of a request or a response is "text" but the character set information is missing in the "Content-Type" header, the character set of the request or response body should default to "ISO-8859-1". Use this procedure to change the default body character set a response inherits from the request:

```
UTL_HTTP.SET_BODY_CHARSET(
 r IN OUT NOCOPY resp,
 charset IN VARCHAR2 DEFAULT NULL);
```

## Parameters

**Table 156–42** *SET\_BODY\_CHARSET Procedure Parameters*

Parameter	Description
r	The HTTP response.
charset	The default character set of the response body. The character set can be in Oracle or Internet Assigned Numbers Authority (IANA) naming convention. If charset is NULL, the database character set is assumed.

## SET\_COOKIE\_SUPPORT Procedures

This procedure is overloaded. The description of different functionalities is located alongside the syntax declarations.

This procedure

**See Also:**

- [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25
- [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

Enables or disables support for the HTTP cookies in the request. Use this procedure to change the cookie support setting a request inherits from the session default setting:

```
UTL_HTTP.SET_COOKIE_SUPPORT(
 r IN OUT NOCOPY REQ,
 enable IN BOOLEAN DEFAULT TRUE);
```

Sets whether or not future HTTP requests will support HTTP cookies, and the maximum number of cookies maintained in the current database user session:

```
UTL_HTTP.SET_COOKIE_SUPPORT (
 enable IN BOOLEAN,
 max_cookies IN PLS_INTEGER DEFAULT 300,
 max_cookies_per_site IN PLS_INTEGER DEFAULT 20);
```

### Parameters

**Table 156–43 SET\_COOKIE\_SUPPORT Procedure Parameters**

Parameter	Description
r	The HTTP request.
enable	Set enable to TRUE to enable HTTP cookie support; FALSE to disable.
max_cookies	Sets the maximum total number of cookies maintained in the current session.

**Table 156–43 SET\_COOKIE\_SUPPORT Procedure Parameters**

Parameter	Description
<code>max_cookies_per_site</code>	Sets the maximum number of cookies maintained in the current session for each Web site.

## Usage Notes

If cookie support is enabled for an HTTP request, all cookies saved in the current session and applicable to the request are returned to the Web server in the request in accordance with HTTP cookie specification standards. Cookies set in the response to the request are saved in the current session for return to the Web server in the subsequent requests if cookie support is enabled for those requests. If the cookie support is disabled for an HTTP request, no cookies are returned to the Web server in the request and the cookies set in the response to the request are not saved in the current session, although the `Set-Cookie` HTTP headers can still be retrieved from the response.

Cookie support is enabled by default for all HTTP requests in a database user session. The default setting of the cookie support (enabled versus disabled) affects only the future requests and has no effect on the existing ones. After your request is created, the cookie support setting may be changed by using the other `set_cookie_support` procedure that operates on a request.

The default maximum number of cookies saved in the current session is 20 for each site and 300 total.

If you lower the maximum total number of cookies or the maximum number of cookies for each Web site, the oldest cookies will be purged first to reduce the number of cookies to the lowered maximum. HTTP cookies saved in the current session last for the duration of the database session only; there is no persistent storage for the cookies. Cookies saved in the current session are not cleared if you disable cookie support.

See "[Examples](#)" on page 156-16 for how to use `get_cookies` and `add_cookies` to retrieve, save, and restore cookies.

## SET\_DETAILED\_EXCP\_SUPPORT Procedure

This procedure sets the UTL\_HTTP package to raise a detailed exception. By default, UTL\_HTTP raises the `request_failed` exception when an HTTP request fails. Use `GET_DETAILED_SQLCODE` and `GET_DETAILED_SQLEERM` for more detailed information about the error.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.SET_DETAILED_EXCP_SUPPORT (
 enable IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 156–44** SET\_DETAILED\_EXCP\_SUPPORT Procedure Parameters

Parameter	Description
<code>enable</code>	Asks UTL_HTTP to raise a detailed exception directly if set to TRUE; otherwise FALSE

## SET\_FOLLOW\_REDIRECT Procedures

This procedure sets the maximum number of times UTL\_HTTP follows the HTTP redirect instruction in the HTTP response to this request, or future requests, in the GET\_RESPONSE function.

### See Also:

- [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25
- [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

## Syntax

Use this procedure to set the maximum number of redirections:

```
UTL_HTTP.SET_FOLLOW_REDIRECT (
 max_redirects IN PLS_INTEGER DEFAULT 3);
```

Use this procedure to change the maximum number of redirections a request inherits from the session default setting:

```
UTL_HTTP.SET_FOLLOW_REDIRECT(
 r IN OUT NOCOPY req,
 max_redirects IN PLS_INTEGER DEFAULT 3);
```

## Parameters

**Table 156–45 SET\_FOLLOW\_REDIRECT Procedure Parameters**

Parameter	Description
r	The HTTP request
max_redirects	The maximum number of redirects. Set to zero to disable redirects.

## Usage Notes

If `max_redirects` is set to a positive number, the [GET\\_RESPONSE Function](#) will automatically follow the redirected URL for the HTTP response status code 301, 302, and 307 for the HTTP HEAD and GET methods, and 303 for all HTTP methods, and retry the HTTP request (the request method will be changed to HTTP GET for

the status code 303) at the new location. It follows the redirection until the final, non-redirect location is reached, or an error occurs, or the maximum number of redirections has been reached (to prevent an infinite loop). The URL and method fields in the `REQ` record will be updated to the last redirected URL and the method used to access the URL. Set the maximum number of redirects to zero to disable automatic redirection.

While it is set not to follow redirect automatically in the current session, it is possible to specify individual HTTP requests to follow redirect instructions the function `follow_redirect` and vice versa.

The default maximum number of redirections in a database user session is 3. The default value affects only future requests and has no effect on existing requests.

The `SET_FOLLOW_REDIRECT` procedure must be called before `GET_RESPONSE` for any redirection to take effect.



## SET\_HEADER Procedure

This procedure sets an HTTP request header. The request header is sent to the Web server as soon as it is set.

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.SET_HEADER (
 r IN OUT NOCOPY req,
 name IN VARCHAR2,
 value IN VARCHAR2);
```

### Parameters

**Table 156–46 SET\_HEADER Procedure Parameters**

Parameter	Description
r	The HTTP request
name	The name of the HTTP request header
value	The value of the HTTP request header

### Usage Notes

Multiple HTTP headers with the same name are allowed in the HTTP protocol standard. Therefore, setting a header does not replace a prior header with the same name.

If the request is made using HTTP 1.1, UTL\_HTTP sets the Host header automatically for you.

When you set the Content-Type header with this procedure, UTL\_HTTP looks for the character set information in the header value. If the character set information is present, it is set as the character set of the request body. It can be overridden later by using the `set_body_charset` procedure.

When you set the Transfer-Encoding header with the value `chunked`, UTL\_HTTP automatically encodes the request body written by the `WRITE_TEXT`, `WRITE_LINE` and `WRITE_RAW` procedures. Note that some HTTP-1.1-based Web servers

or CGI programs do not support or accept the request body encoding in the HTTP 1.1 chunked transfer-encoding format.

## SET\_PERSISTENT\_CONN\_SUPPORT Procedure

This procedure enables or disables support for the HTTP 1.1 persistent-connection in the request.

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.SET_PERSISTENT_CONN_SUPPORT(
 r IN OUT NOCOPY req,
 enable IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 156–47 SET\_PERSISTENT\_CONN\_SUPPORT Procedure Parameters**

Parameter	Description
r	The HTTP request
enable	TRUE to keep the network connection persistent. FALSE otherwise.

### Usage Notes

If the persistent-connection support is enabled for an HTTP request, the package will keep the network connections to a Web server or the proxy server open in the package after the request is completed properly for a subsequent request to the same server to reuse for each HTTP 1.1 protocol specification. With the persistent connection support, subsequent HTTP requests may be completed faster because the network connection latency is avoided. If the persistent-connection support is disabled for a request, the package will always send the HTTP header "Connection: close" automatically in the HTTP request and close the network connection when the request is completed. This setting has no effect on HTTP requests that follows HTTP 1.0 protocol, for which the network connections will always be closed after the requests are completed.

When a request is being made, the package attempts to reuse an existing persistent connection to the target Web server (or proxy server) if one is available. If none is available, a new network connection will be initiated. The persistent-connection

support setting for a request affects only whether the network connection should be closed after a request completes.

Use this procedure to change the persistent-connection support setting a request inherits from the session default setting.

Users should note that while the use of persistent connections in UTL\_HTTP may reduce the time it takes to fetch multiple Web pages from the same server, it consumes precious system resources (network connections) in the database server. Also, excessive use of persistent connections may reduce the scalability of the database server when too many network connections are kept open in the database server. Network connections should be kept open only if they will be used immediately by subsequent requests and should be closed immediately when they are no longer needed. Set the default persistent connection support as disabled in the session, and enable persistent connection in individual HTTP requests as shown in ["Examples"](#) on page 156-88.

The default value of the maximum number of persistent connections in a database session is zero. To truly enable persistent connections, you must also set the maximum number of persistent connections to a positive value or no connections will be kept persistent.

## Examples

### Using SET\_PERSISTENT\_CONN\_SUPPORT in HTTP Requests

```
DECLARE
 TYPE vc2_table IS TABLE OF VARCHAR2(256) INDEX BY binary_integer;
 paths vc2_table;

UTL_HTTP.fetch_pages(paths IN vc2_table) AS
 url_prefix VARCHAR2(256) := 'http://www.my-company.com/';
 req utl_http.req;
 resp utl_http.resp;
 data VARCHAR2(1024);
BEGIN
 FOR i IN 1..paths.count LOOP
 req := utl_http.begin_request(url_prefix || paths(i));

 -- Use persistent connection except for the last request
 IF (i < paths.count) THEN
 utl_http.set_persistent_conn_support(req, TRUE);
 END IF;
```

```
resp := utl_http.get_response(req);

BEGIN
 LOOP
 utl_http.read_text(resp, data);
 -- do something with the data
 END LOOP;
EXCEPTION
 WHEN utl_http.end_of_body THEN
 NULL;
END;
utl_http.end_response(resp);
END LOOP;
END;
```

```
BEGIN
 utl_http.set_persistent_conn_support(FALSE, 1);
 paths(1) := '...';
 paths(2) := '...';
 ...
 fetch_pages(paths);
END;
```

## SET\_PROXY Procedure

This procedure sets the proxy to be used for requests of the HTTP or other protocols, excluding those for hosts that belong to the domain specified in `no_proxy_domains`. `no_proxy_domains` is a comma-, semi-colon-, or space-separated list of domains or hosts for which HTTP requests should be sent directly to the destination HTTP server instead of going through a proxy server.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.SET_PROXY (
 proxy IN VARCHAR2,
 no_proxy_domains IN VARCHAR2);
```

### Parameters

**Table 156–48 SET\_PROXY Procedure Parameters**

Parameter	Description
<code>proxy</code>	The proxy (host and an optional port number) to be used by the UTL_HTTP package
<code>no_proxy_domains</code>	The list of hosts and domains for which no proxy should be used for all requests.

### Usage Notes

The proxy may include an optional TCP/IP port number at which the proxy server listens. The syntax is `[http://]host[:port][/]`, for example, `www-proxy.my-company.com:80`. If the port is not specified for the proxy, port 80 is assumed.

Optionally, a port number can be specified for each domain or host. If the port number is specified, the no-proxy restriction is only applied to the request at the port of the particular domain or host, for example, `corp.my-company.com`, `eng.my-company.com:80`. When `no_proxy_domains` is NULL and the proxy is set, all requests go through the proxy. When the proxy is not set, UTL\_HTTP sends requests to the target Web servers directly.

You can define a username/password for the proxy to be specified in the proxy string. The format is

```
[http://][user[:password]@]host[:port][/]
```

If proxy settings are set when the database server instance is started, the proxy settings in the environment variables `http_proxy` and `no_proxy` are assumed. Proxy settings set by this procedure override the initial settings.

## SET\_RESPONSE\_ERROR\_CHECK Procedure

This procedure sets whether or not `get_response` raises an exception when the Web server returns a status code that indicates an error—a status code in the 4xx or 5xx ranges. For example, when the requested URL is not found in the destination Web server, a 404 (document not found) response status code is returned.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.SET_RESPONSE_ERROR_CHECK (
 enable IN BOOLEAN DEFAULT FALSE);
```

### Parameters

**Table 156–49 SET\_RESPONSE\_ERROR\_CHECK Procedure Parameters**

Parameter	Description
<code>enable</code>	TRUE to check for response errors; otherwise FALSE

### Usage Notes

If the status code indicates an error—a 4xx or 5xx code—and this procedure is enabled, `get_response` will raise the `HTTP_CLIENT_ERROR` or `HTTP_SERVER_ERROR` exception. If `SET_RESPONSE_ERROR_CHECK` is set to `FALSE`, `get_response` will not raise an exception when the status code indicates an error.

Response error check is turned off by default.

The `get_response` function can raise other exceptions when `SET_RESPONSE_ERROR_CHECK` is set to `FALSE`.



## SET\_TRANSFER\_TIMEOUT Procedure

This procedure sets the default time out value for all future HTTP requests that the UTL\_HTTP package should attempt while reading the HTTP response from the Web server or proxy server. This time out value may be used to avoid the PL/SQL programs from being blocked by busy Web servers or heavy network traffic while retrieving Web pages from the Web servers.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.SET_TRANSFER_TIMEOUT (
 timeout IN PLS_INTEGER DEFAULT 60);
```

### Parameters

**Table 156–50 SET\_TRANSFER\_TIMEOUT Procedure Parameters**

Parameter	Description
timeout	The network transfer timeout value in seconds.

### Usage Notes

The default value of the time out is 60 seconds.

## SET\_WALLET Procedure

This procedure sets the Oracle wallet used for all HTTP requests over Secured Socket Layer (SSL), namely HTTPS. When the UTL\_HTTP package communicates with an HTTP server over SSL, the HTTP server presents its digital certificate, which is signed by a certificate authority, to the UTL\_HTTP package for identification purpose. The Oracle wallet contains the list of certificate authorities that are trusted by the user of the UTL\_HTTP package. An Oracle wallet is required to make an HTTPS request.

**See Also:** [Session Settings](#) on page 156-13 and [Session Settings Subprograms](#) on page 156-23

### Syntax

```
UTL_HTTP.SET_WALLET (
 path IN VARCHAR2,
 password IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 156–51 SET\_WALLET Procedure Parameters**

Parameter	Description
path	The directory path that contains the Oracle wallet. The format is <code>file:&lt;directory-path&gt;</code> .  The format of <code>wallet_path</code> on a PC is, for example, <code>file:c:\WINNT\Profiles\<username>\WALLETS</username></code> , and in Unix is, for example, <code>file:/home/&lt;username&gt;/wallets</code> . When the UTL_HTTP package is executed in the Oracle database server, the wallet is accessed from the database server. Therefore, the wallet path must be accessible from the database server.
password	The password needed to open the wallet. A second copy of a wallet in a wallet directory that may be opened without a password. That second copy of the wallet is read-only. If the <code>password</code> is NULL, the UTL_HTTP package will open the second, read-only copy of the wallet instead.

## Usage Notes

To set up an Oracle wallet, use the Oracle Wallet Manager to create a wallet. In order for the HTTPS request to succeed, the certificate authority that signs the certificate of the remote HTTPS Web server must be a trust point set in the wallet.

When a wallet is created, it is populated with a set of well-known certificate authorities as trust points. If the certificate authority that signs the certificate of the remote HTTPS Web server is not among the trust points, or the certificate authority has new root certificates, you should obtain the root certificate of that certificate authority and install it as a trust point in the wallet using Oracle Wallet Manager

**See Also:** *Oracle Advanced Security Administrator's Guide* for more information on Wallet Manager

## WRITE\_LINE Procedure

This procedure writes a text line in the HTTP request body and ends the line with new-line characters (CRLF as defined in `UTL_TCP`). As soon as some data is sent as the HTTP request body, the HTTP request headers section is completed. Text data is automatically converted from the database character set to the request body character set.

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.WRITE_LINE(
 r IN OUT NOCOPY req,
 data IN VARCHAR2 CHARACTER SET ANY_CS);
```

### Parameters

**Table 156–52** *WRITE\_LINE Procedure Parameters*

Parameter	Description
<code>r</code>	The HTTP request
<code>data</code>	The text line to send in the HTTP request body

### Usage Notes

An HTTP client must always let the remote Web server know the length of the request body it is sending. If the amount of data is known beforehand, you can set the Content-Length header in the request, where the length of the content is measured in bytes instead of characters. If the length of the request body is not known beforehand, you can send the request body using the HTTP 1.1 chunked transfer-encoding format. The request body is sent in chunks, where the length of each chunk is sent before the chunk is sent. The `UTL_HTTP` package performs chunked transfer-encoding on the request body transparently when the Transfer-Encoding: chunked header is set. Note that some HTTP-1.1-based Web servers or CGI programs do not support or accept the request body encoding in the HTTP 1.1 chunked transfer-encoding format. See the `set_header` procedure for details.

If you send the Content-Length header, you should note that the length specified in the header should be the byte-length of the textual request body after it is converted from the database character set to the request body character set. When either one of the two character sets is a multibyte character set, the precise byte-length of the request body in the request body character set cannot be known beforehand. In this case, you can perform the character set conversion explicitly, determine the byte-length of the results, send the Content-Length header, and the results using the `write_raw` procedure to avoid the automatic character set conversion. Or, if the remote Web server or CGI programs allow, you can send the request body using the HTTP 1.1 chunked transfer-encoding format, where `UTL_HTTP` handles the length of the chunks transparently.

## WRITE\_RAW Procedure

This procedure writes some binary data in the HTTP request body. As soon as some data is sent as the HTTP request body, the HTTP request headers section is completed.

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.WRITE_RAW(
 r IN OUT NOCOPY req,
 data IN RAW);
```

### Parameters

**Table 156–53** *WRITE\_RAW Procedure Parameters*

Parameter	Description
r	The HTTP request
data	The binary data to send in the HTTP request body

### Usage Notes

An HTTP client must always let the remote Web server know the length of the request body it is sending. If the amount of data is known beforehand, you can set the Content-Length header in the request, where the length of the content is measured in bytes instead of characters. If the length of the request body is not known beforehand, you can send the request body using the HTTP 1.1 chunked transfer-encoding format. The request body is sent in chunks, where the length of each chunk is sent before the chunk is sent. `UTL_HTTP` performs chunked transfer-encoding on the request body transparently when the `Transfer-Encoding: chunked` header is set. Note that some HTTP-1.1-based Web servers or CGI programs do not support or accept the request body encoding in the HTTP 1.1 chunked transfer-encoding format. See the `set_header` procedure for details.

## WRITE\_TEXT Procedure

This procedure writes some text data in the HTTP request body. As soon as some data is sent as the HTTP request body, the HTTP request headers section is completed. Text data is automatically converted from the database character set to the request body character set.

**See Also:** [HTTP Requests](#) on page 156-13 and [HTTP Requests Subprograms](#) on page 156-25

### Syntax

```
UTL_HTTP.WRITE_TEXT(
 r IN OUT NOCOPY req,
 data IN VARCHAR2 CHARACTER SET ANY_CS);
```

### Parameters

**Table 156–54** *WRITE\_TEXT Procedure Parameters*

Parameter	Description
r	The HTTP request
data	The text data to send in the HTTP request body

### Usage Notes

An HTTP client must always let the remote Web server know the length of the request body it is sending. If the amount of data is known beforehand, you can set the Content-Length header in the request, where the length of the content is measured in bytes instead of characters. If the length of the request body is not known beforehand, you can send the request body using the HTTP 1.1 chunked transfer-encoding format. The request body is sent in chunks, where the length of each chunk is sent before the chunk is sent. UTL\_HTTP performs chunked transfer-encoding on the request body transparently when the `Transfer-Encoding: chunked` header is set. Note that some HTTP-1.1-based Web servers or CGI programs do not support or accept the request body encoding in the HTTP 1.1 chunked transfer-encoding format. See the `set_header` procedure for details.

If you send the Content-Length header, you should note that the length specified in the header should be the byte-length of the textual request body after it is converted

from the database character set to the request body character set. When either one of the two character sets is a multibyte character set, the precise byte-length of the request body in the request body character set cannot be known beforehand. In this case, you can perform the character set conversion explicitly, determine the byte-length of the results, send the Content-Length header, and the results using the `write_raw` procedure to avoid the automatic character set conversion. Or, if the remote Web server or CGI programs allow, you can send the request body using the HTTP 1.1 chunked transfer-encoding format, where `UTL_HTTP` handles the length of the chunks transparently.



UTL\_I18N is a set of services that help developers build multilingual applications. The Globalization Development Kit provides a set of tools that are designed to help developers with minimal experience in internationalization development effectively write multilingual applications.

**See Also:** *Oracle Database Globalization Support Guide*

The chapter contains the following topics:

- [Using UTL\\_I18n](#)
  - [Overview](#)
  - [Constants](#)
  - [Flags](#)
- [Summary of UTL\\_I18N Subprograms](#)

## Using UTL\_I18n

- [Overview](#)
- [Constants](#)
- [Flags](#)

### Overview

The `UTL_I18N` PL/SQL package consists of the following categories of services:

- String conversion functions for various datatypes
- Escape and unescape sequences for predefined characters and multibyte characters used by HTML and XML documents
- Functions that map between Oracle, Internet Assigned Numbers Authority (IANA), and ISO languages and territories
- Functions that map between Oracle, Internet Assigned Numbers Authority (IANA), and e-mail safe character sets
- A function that returns the Oracle character set name from an Oracle language name

### Constants

```
SHIFT_IN CONSTANT PLS_INTEGER :=0;
SHIFT_OUT CONSTANT PLS_INTEGER :=1;
```

### Flags

```
ORACLE_TO_IANA CONSTANT PLS_INTEGER :=0;
IANA_TO_ORACLE CONSTANT PLS_INTEGER :=1;
MAIL_GENERIC CONSTANT PLS_INTEGER :=0;
MAIL_WINDOWS CONSTANT PLS_INTEGER :=1;
GENERIC_CONTEXT CONSTANT PLS_INTEGER :=0;
MAIL_CONTEXT CONSTANT PLS_INTEGER :=1;
```

---

## Summary of UTL\_I18N Subprograms

**Table 157–1 UTL\_I18N Package Subprograms**

Procedure	Description
<a href="#">ESCAPE_REFERENCE Function</a> on page 157-4	Specifies an escape sequence for predefined characters and multibyte characters that cannot be converted to the character set used by an HTML or XML document
<a href="#">GET_DEFAULT_CHARSET Function</a> on page 157-5	Returns the default Oracle character set name or the default e-mail safe character set name from an Oracle language name.
<a href="#">MAP_CHARSET Function</a> on page 157-7	<ul style="list-style-type: none"> <li>■ Maps an Oracle character set name to an IANA character set name</li> <li>■ Maps an IANA character set name to an Oracle character set name</li> <li>■ Maps an Oracle character set name to an e-mail safe character set name</li> </ul>
<a href="#">MAP_LANGUAGE_FROM_ISO Function</a> on page 157-10	Returns an Oracle language name from an ISO locale name
<a href="#">MAP_LOCALE_TO_ISO Function</a> on page 157-11	Returns an ISO locale name from the Oracle language and territory name
<a href="#">MAP_TERRITORY_FROM_ISO Function</a> on page 157-12	Returns an Oracle territory name from an ISO locale name
<a href="#">RAW_TO_CHAR Functions</a> on page 157-13	Converts RAW data that is not encoded in the database character set into a VARCHAR2 string
<a href="#">RAW_TO_NCHAR Functions</a> on page 157-16	Converts RAW data that is not encoded in the national character set into an NVARCHAR2 string
<a href="#">STRING_TO_RAW Function</a> on page 157-19	Converts a VARCHAR2 or NVARCHAR2 string to another character set. The result is returned as a RAW datatype.
<a href="#">UNESCAPE_REFERENCE Function</a> on page 157-20	Returns a string from an input string that contains escape sequences

## ESCAPE\_REFERENCE Function

This function provides a way to specify an escape sequence for predefined characters and multibyte characters that cannot be converted to the character set used by an HTML or XML document.

For example, < (less than symbol) has a special meaning in HTML. To display < as a character, encode it as the escape sequence `&lt;`. In the same way, you can specify how multibyte characters are displayed when they are not part of the character set encoding of an HTML or XML document. For example, if you encode a page in the ZHT16BIG5 character set, then this function checks every character. If it finds a character that is not a Chinese character, then it returns an escape character.

### Syntax

```
UTL_I18N.ESCAPE_REFERENCE(str IN VARCHAR2 CHARACTER SET ANY_CS,
 page_cs_name IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2 CHARACTER SET str%CHARSET;
```

### Parameters

**Table 157–2** *ESCAPE\_REFERENCE Function Parameters*

Parameter	Description
<code>str</code>	Specifies the input string
<code>page_cs_name</code>	Specifies the character set encoding of the HTML or XML document. If <code>page_cs_name</code> is NULL, then the database character set is used for CHAR data and the national character set is used for NCHAR data.

### Usage Notes

If the user specifies an invalid character set or a NULL string, then the function returns a NULL string.

### Examples

```
UTL_I18N.ESCAPE_REFERENCE('ab' || chr(170), 'us7ascii')
```

This returns 'ab&#xaa; '.

## GET\_DEFAULT\_CHARSET Function

This function returns the default Oracle character set name or the default e-mail safe character set name from an Oracle language name.

**See Also:** ["MAP\\_CHARSET Function"](#) on page 157-7 for an explanation of an e-mail safe character set

### Syntax

```
UTL_I18N.GET_DEFAULT_CHARSET(language IN VARCHAR2,
 context IN PLS_INTEGER DEFAULT GENERIC_CONTEXT,
 iswindows IN BOOLEAN DEFAULT FALSE)
RETURN VARCHAR2;
```

### Parameters

**Table 157–3** *GET\_DEFAULT\_CHARSET Function Parameters*

Parameter	Description
language	Specifies a valid Oracle language
context	GENERIC_CONTEXT   MAIL_CONTEXT GENERIC_CONTEXT: Return the default character set for general cases MAIL_CONTEXT: Return the default e-mail safe character set name
iswindows	If context is set as MAIL_CONTEXT, then iswindows should be set to TRUE if the platform is Windows and FALSE if the platform is not Windows. The default is FALSE. iswindows has no effect if context is set as GENERIC_CONTEXT.

### Usage Notes

If the user specifies an invalid language name or an invalid flag, then the function returns a NULL string.

## Examples

### **GENERIC\_CONTEXT, iswindows=FALSE**

```
UTL_I18N.GET_DEFAULT_CHARSET('French', UTL_I18N.GENERIC_CONTEXT, FALSE)
```

This returns 'WE8ISO8859P1'.

### **MAIL\_CONTEXT, iswindows=TRUE**

```
UTL_I18N.GET_DEFAULT_CHARSET('French', UTL_I18N.MAIL_CONTEXT, TRUE)
```

This returns 'WE8MSWIN1252'.

### **MAIL\_CONTEXT, iswindows=FALSE**

```
UTL_I18N.GET_DEFAULT_CHARSET('French', UTL_I18N.MAIL_CONTEXT, FALSE)
```

This returns 'WE8ISO8859P1'.

## MAP\_CHARSET Function

This function:

- Maps an Oracle character set name to an IANA character set name
- Maps an IANA character set name to an Oracle character set name
- Maps an Oracle character set to an e-mail safe character set name

### Syntax

```
UTL_I18N.MAP_CHARSET(charset IN VARCHAR2,
 context IN PLS_INTEGER DEFAULT GENERIC_CONTEXT,
 flag IN PLS_INTEGER DEFAULT ORACLE_TO_IANA)
RETURN VARCHAR2;
```

### Parameters

**Table 157–4** MAP\_CHARSET Function Parameters

Parameter	Description
charset	Specifies the character set name to be mapped. The mapping is case-insensitive.
context	GENERIC_CONTEXT   MAIL_CONTEXT GENERIC_CONTEXT: The mapping is between an Oracle character set name and an IANA character set name. This is the default value. MAIL_CONTEXT: The mapping is between an Oracle character set name and an e-mail safe character set name.

**Table 157–4 (Cont.) MAP\_CHARSET Function Parameters (Cont.)**

Parameter	Description
flag	<ul style="list-style-type: none"> <li>■ ORACLE_TO_IANA   IANA_TO_ORACLE if GENERIC_CONTEXT is set  ORACLE_TO_IANA: Map from an Oracle character set name to an IANA character set name. This is the default. IANA_TO_ORACLE: Map from an IANA character set name to an Oracle character set name.</li> <li>■ MAIL_GENERIC   MAIL_WINDOWS if MAIL_CONTEXT is set  MAIL_GENERIC: Map from an Oracle character set name to an e-mail safe character set name on a non-Windows platform  MAIL_WINDOWS: Map from an Oracle character set name to an e-mail safe character set name on a Windows platform</li> </ul>

## Usage Notes

An e-mail safe character set is an Oracle character set that is commonly used by applications when they submit e-mail messages. The character set is usually used to convert contents in the database character set to e-mail safe contents. To specify the character set name in the mail header, you should use the corresponding IANA character set name obtained by calling the MAP\_CHARSET function with the ORACLE\_TO\_IANA option, providing the e-mail safe character set name as input.

For example, no e-mail client recognizes message contents in the WE8DEC character set, whose corresponding IANA name is DEC-MCS. If WE8DEC is passed to the MAP\_CHARSET function with the MAIL\_CONTEXT option, then the function returns WE8ISO8859P1. Its corresponding IANA name, ISO-8859-1, is recognized by most e-mail clients.

The steps in this example are as follows:

1. Call the MAP\_CHARSET function with the MAIL\_CONTEXT | MAIL\_GENERIC option with the database character set name, WE8DEC. The result is WE8ISO8859P1.
2. Convert the contents stored in the database to WE8ISO8859P1.
3. Call the MAP\_CHARSET function with the ORACLE\_TO\_IANA | GENERIC\_CONTEXT option with the e-mail safe character set, WE8ISO8859P1. The result is ISO-8859-1.



4. Specify ISO-8859-1 in the mail header when the e-mail message is submitted. The function returns a character set name if a match is found. If no match is found or if the flag is invalid, then it returns NULL.

---

---

**Note:** Many Oracle character sets can map to one e-mail safe character set. There is no function that maps an e-mail safe character set to an Oracle character set name.

---

---

## Examples

### Generic Context

```
UTL_I18N.MAP_CHARSET('iso-8859-1',UTL_I18N.GENERIC_CONTEXT,UTL_I18N.IANA_TO_ORACLE)
```

This returns 'WE8ISO8859P1'.

### Context

```
UTL_I18N.MAP_CHARSET('WE8DEC', utl_i18n.mail_context, utl_i18n.mail_generic)
```

This returns 'WE8ISO8859P1'.

**See Also:** *Oracle Database Globalization Support Guide* for a list of valid Oracle character sets

## MAP\_LANGUAGE\_FROM\_ISO Function

This function returns an Oracle language name from an ISO locale name.

### Syntax

```
UTL_I18N.MAP_LANGUAGE_FROM_ISO(isolocale IN VARCHAR2)
RETURN VARCHAR2;
```

### Parameters

**Table 157–5** MAP\_LANGUAGE\_FROM\_ISO Function Parameters

Parameter	Description
isolocale	Specifies the ISO locale. The mapping is case-insensitive.

### Usage Notes

If the user specifies an invalid locale string, then the function returns a NULL string.

If the user specifies a locale string that includes only the language (for example, `en_` instead of `en_US`), then the function returns the default language name for the specified language (for example, `American`).

### Examples

```
UTL_I18N.MAP_LANGUAGE_FROM_ISO('en_US')
```

This returns 'American'.

**See Also:** *Oracle Database Globalization Support Guide* for a list of valid Oracle languages

## MAP\_LOCALE\_TO\_ISO Function

This function returns an ISO locale name from an Oracle language name and an Oracle territory name. A valid string must include at least one of the following: a valid Oracle language name or a valid Oracle territory name.

### Syntax

```
UTL_I18N.MAP_LOCALE_TO_ISO(ora_language IN VARCHAR2,
 ora_territory IN VARCHAR2)
RETURN VARCHAR2;
```

### Parameters

**Table 157–6** MAP\_LOCALE\_TO\_ISO Function Parameters

Parameter	Description
ora_language	Specifies an Oracle language name. It is case-insensitive.
ora_territory	Specifies an Oracle territory name. It is case-insensitive.

### Usage Notes

If the user specifies an invalid string, then the function returns a NULL string.

### Examples

```
UTL_I18N.MAP_LOCALE_TO_ISO('American','America')
```

This returns 'en\_US'.

**See Also:** *Oracle Database Globalization Support Guide* for a list of valid Oracle languages and territories

## MAP\_TERRITORY\_FROM\_ISO Function

This function returns an Oracle territory name from an ISO locale.

### Syntax

```
UTL_I18N.MAP_TERRITORY_FROM_ISO(isocale IN VARCHAR2)
RETURN VARCHAR2;
```

### Parameters

**Table 157–7 MAP\_TERRITORY\_FROM\_ISO Function Parameters**

Parameter	Description
isocale	Specifies the ISO locale. The mapping is case-insensitive.

### Usage Notes

If the user specifies an invalid locale string, then the function returns a `NULL` string.

If the user specifies a locale string that includes only the territory (for example, `_fr` instead of `fr_fr`), then the function returns the default territory name for the specified territory (for example, `French`).

### Examples

```
UTL_I18N.MAP_TERRITORY_FROM_ISO('en-US')
```

This returns 'America'.

**See Also:** *Oracle Database Globalization Support Guide* for a list of valid Oracle territories

## RAW\_TO\_CHAR Functions

This function converts RAW data from a valid Oracle character set to a VARCHAR2 string in the database character set.

The function is overloaded. The different forms of functionality are described along with the syntax declarations.

### Syntax

#### Buffer Conversion:

```
UTL_I18N.RAW_TO_CHAR(data IN RAW,
 src_charset IN VARCHAR2 DEFAULT NULL)
RETURN VARCHAR2;
```

Piecewise conversion converts raw data into character data piece by piece:

```
UTL_I18N.RAW_TO_CHAR(data IN RAW,
 src_charset IN VARCHAR2 DEFAULT NULL,
 scanned_length OUT PLS_INTEGER,
 shift_status IN OUT PLS_INTEGER)
RETURN VARCHAR2;
```

### Parameters

**Table 157–8 RAW\_TO\_CHAR Function Parameters**

Parameter	Description
data	Specifies the RAW data to be converted to a VARCHAR2 string
src_charset	Specifies the character set that the RAW data was derived from. If src_charset is NULL, then the database character set is used.
scanned_length	Specifies the number of bytes of source data scanned

**Table 157–8 (Cont.) RAW\_TO\_CHAR Function Parameters (Cont.)**

Parameter	Description
<code>shift_status</code>	<p>Specifies the shift status at the end of the scan. The user must set it to <code>SHIFT_IN</code> the first time it is called in piecewise conversion.</p> <p><b>Note:</b> ISO 2022 character sets use escape sequences instead of shift characters to indicate the encoding method. <code>shift_status</code> cannot hold the encoding method information that is provided by the escape sequences for the next function call. As a result, this function cannot be used to reconstruct ISO 2022 character from raw data in a piecewise way unless each unit of input can be guaranteed to be a closed string. A closed string begins and ends in a 7-bit escape state.</p>

## Usage Notes

If the user specifies an invalid character set, `NULL` data, or data whose length is 0, then the function returns a `NULL` string.

## Examples

### Buffer Conversion

```
UTL_I18N.RAW_TO_CHAR(hextoraw('616263646566C2AA'), 'utf8')
```

This returns the following string in the database character set:

```
'abcde' || chr(170)
```

### Piecewise Conversion

```
UTL_I18N.RAW_TO_CHAR(hextoraw('616263646566C2AA'),'utf8',shf,slen)
```

This expression returns the following string in the database character set:

```
'abcde' || chr(170)
```

It also sets `shf` to `SHIFT_IN` and `slen` to 8.

The following example converts data from the Internet piece by piece to the database character set.

```
rvalue RAW(1050);
nvalue VARCHAR2(1024);
conversion_state PLS_INTEGER = 0;
```

```
converted_len PLS_INTEGER;
rtemp RAW(10) = '';
conn utl_tcp.connection;
tlen PLS_INTEGER;

...
conn := utl_tcp.open_connection (remote_host => 'localhost',
 remote_port => 2000);

LOOP
 tlen := utl_tcp.read_raw(conn, rvalue, 1024);
 rvalue := utl_raw.concat(rtemp, rvalue);
 nvalue := utl_i18n.raw_to_char(rvalue, 'JA16SJIS', converted_len,
conversion_stat);
 if (converted_len < utl_raw.length(rvalue))
 then
 rtemp := utl_raw.substr(rvalue, converted_len+1);
 else
 rtemp := '';
 end if;
 /* do anything you want with nvalue */
 /* e.g http.prn(nvalue); */
END LOOP;
utl_tcp.close_connection(conn);
EXCEPTION
 WHEN utl_tcp.end_of_input THEN
 utl_tcp.close_connection(conn);
END;
```

## RAW\_TO\_NCHAR Functions

This function converts RAW data from a valid Oracle character set to an NVARCHAR2 string in the national character set.

The function is overloaded. The different forms of functionality are described along with the syntax declarations.

### Syntax

#### Buffer Conversion:

```
UTL_I18N.RAW_TO_NCHAR(data IN RAW,
 src_charset IN VARCHAR2 DEFAULT NULL)
RETURN NVARCHAR2;
```

Piecewise conversion converts raw data into character data piece by piece:

```
UTL_I18N.RAW_TO_NCHAR(data IN RAW,
 src_charset IN VARCHAR2 DEFAULT NULL,
 scanned_length OUT PLS_INTEGER,
 shift_status IN OUT PLS_INTEGER)
RETURN NVARCHAR2;
```

### Parameters

**Table 157–9 RAW\_TO\_NCHAR Function Parameters**

Parameter	Description
data	Specifies the RAW data to be converted to an NVARCHAR2 string
src_charset	Specifies the character set that the RAW data was derived from. If src_charset is NULL, then the database character set is used.
scanned_length	Specifies the number of bytes of source data scanned



**Table 157–9 (Cont.) RAW\_TO\_NCHAR Function Parameters (Cont.)**

Parameter	Description
<code>shift_status</code>	<p>Specifies the shift status at the end of the scan. The user must set it to <code>SHIFT_IN</code> the first time it is called in piecewise conversion.</p> <p><b>Note:</b> ISO 2022 character sets use escape sequences instead of shift characters to indicate the encoding method. <code>shift_status</code> cannot hold the encoding method information that is provided by the escape sequences for the next function call. As a result, this function cannot be used to reconstruct ISO 2022 character from raw data in a piecewise way unless each unit of input can be guaranteed to be a closed string. A closed string begins and ends in a 7-bit escape state.</p>

## Usage Notes

If the user specifies an invalid character set, `NULL` data, or data whose length is 0, then the function returns a `NULL` string.

## Examples

### Buffer Conversion

```
UTL_I18N.RAW_TO_NCHAR(hextoraw('616263646566C2AA'),'utf8')
```

This returns the following string in the national character set:

```
'abcde' || chr(170)
```

### Piecewise Conversion

```
UTL_I18N.RAW_TO_NCHAR(hextoraw('616263646566C2AA'),'utf8', shf, slen)
```

This expression returns the following string in the national character set:

```
'abcde' || chr(170)
```

It also sets `shf` to `SHIFT_IN` and `slen` to 8.

The following example converts data from the Internet piece by piece to the national character set.

```
rvalue RAW(1050);
nvalue NVARCHAR2(1024);
```

```
conversion_state PLS_INTEGER = 0;
converted_len PLS_INTEGER;
rtemp RAW(10) = '';
conn utl_tcp.connection;
tlen PLS_INTEGER;

...
conn := utl_tcp.open_connection (remote_host => 'localhost',
 remote_port => 2000);

LOOP
 tlen := utl_tcp.read_raw(conn, rvalue, 1024);
 rvalue := utl_raw.concat(rtemp, rvalue);
 nvalue := utl_i18n.raw_to_nchar(rvalue, 'JA16SJIS', converted_len,
conversion_stat);
 if (converted_len < utl_raw.length(rvalue))
 then
 rtemp := utl_raw.substr(rvalue, converted_len+1);
 else
 rtemp := '';
 end if;
 /* do anything you want with nvalue */
 /* e.g htp.prn(nvalue); */
END LOOP;
utl_tcp.close_connection(conn);
EXCEPTION
 WHEN utl_tcp.end_of_input THEN
 utl_tcp.close_connection(conn);
END;
```

## STRING\_TO\_RAW Function

This function converts a VARCHAR2 or NVARCHAR2 string to another valid Oracle character set and returns the result as RAW data.

### Syntax

```
UTL_I18N.STRING_TO_RAW(data IN VARCHAR2 CHARACTER SET ANY_CS,
 dst_charset IN VARCHAR2 DEFAULT NULL)
RETURN RAW;
```

### Parameters

**Table 157–10** *STRING\_TO\_RAW Function Parameters*

Parameter	Description
data	Specifies the VARCHAR2 or NVARCHAR2 string to convert
dst_charset	Specifies the destination character set. If dst_charset is NULL, then the database character set is used for CHAR data and the national character set is used for NCHAR data.

### Usage Notes

If the user specifies an invalid character set, a NULL string, or a string whose length is 0, then the function returns a NULL string.

### Examples

```
DECLARE
 r raw(50);
 s varchar2(20);
BEGIN
 s:='abcdef' || chr(170);
 r:=utl_i18n.string_to_raw(s,'utf8');
 dbms_output.put_line(rawtohex(r));
end;
/
```

This returns a hex value of '616263646566C2AA'.

## UNESCAPE\_REFERENCE Function

This function returns a string from an input string that contains escape sequences. It decodes each escape sequence to the corresponding character value.

**See Also:** ["ESCAPE\\_REFERENCE Function"](#) on page 157-4 for more information about escape sequences

### Syntax

```
UTL_I18N.UNESCAPE_REFERENCE(str IN VARCHAR2 CHARACTER SET ANY_CS)
RETURN VARCHAR2 CHARACTER SET str%CHARSET;
```

### Parameters

**Table 157–11 UNESCAPE\_REFERENCE Function Parameters**

Parameter	Description
<code>str</code>	Specifies the input string

### Usage Notes

If the user specifies a NULL string or a string whose length is 0, then the function returns a NULL string. If the function fails, then it returns the original string.

### Examples

```
UTL_I18N.UNESCAPE_REFERENCE('abª')
```

This returns 'ab' || chr(170).

The `UTL_INADDR` package provides a PL/SQL procedures to support internet addressing. It provides an API to retrieve host names and IP addresses of local and remote hosts.

This chapter contains the following topics:

- [Using UTL\\_INADDR](#)
  - [Exceptions](#)
  - [Examples](#)
- [Summary of UTL\\_INADDR Subprograms](#)

---

## Using UTL\_INADDR

- [Exceptions](#)
- [Examples](#)

### Exceptions

**Table 158–1** *Exception from Internet Address Package*

Exception	Description
UNKNOWN_HOST	The host is unknown.

### Examples

Retrieve the local host name and IP address.

```
SET serveroutput on
BEGIN
 DBMS_OUTPUT.PUT_LINE(UTL_INADDR.GET_HOST_NAME); -- get local host name
 DBMS_OUTPUT.PUT_LINE(UTL_INADDR.GET_HOST_ADDRESS); -- get local IP addr
END;
/
```

## Summary of UTL\_INADDR Subprograms

*Table 158–2 UTL\_INADDR Package Subprograms*

<b>Subprogram</b>	<b>Description</b>
<a href="#">GET_HOST_ADDRESS Function</a> on page 158-4	Retrieves the IP address of the local or remote host given its name
<a href="#">GET_HOST_NAME Function</a> on page 158-5	Retrieves the name of the local or remote host given its IP address

## GET\_HOST\_ADDRESS Function

This function retrieves the IP address of the specified host.

### Syntax

```
UTL_INADDR.GET_HOST_ADDRESS (
 host IN VARCHAR2 DEFAULT NULL)
RETURN host_address VARCHAR2;
```

### Parameters

**Table 158–3** *GET\_HOST\_ADDRESS Function Parameters*

Parameter	Description
host	The name of the host to retrieve the IP address.

### Return Values

**Table 158–4** *GET\_HOST\_ADDRESS Function Return Values*

Parameter	Description
host_address	The IP address of the specified host, or that of the local host if host is NULL.

### Exceptions

UNKNOWN\_HOST: The specified IP address is unknown.



## GET\_HOST\_NAME Function

This function retrieves the name of the local or remote host given its IP address.

### Syntax

```
UTL_INADDR.GET_HOST_NAME (
 ip IN VARCHAR2 DEFAULT NULL)
RETURN host_name VARCHAR2;
```

### Parameters

**Table 158–5 GET\_HOST\_NAME Function Parameters**

Parameter	Description
ip	The IP address of the host used to determine its host name. If ip is not NULL, the official name of the host with its domain name is returned. If this is NULL, the name of the local host is returned and the name does not contain the domain to which the local host belongs.

### Return Values

**Table 158–6 GET\_HOST\_NAME Function Return Values**

Parameter	Description
host_name	The name of the local or remote host of the specified IP address.

### Exceptions

UNKNOWN\_HOST: The specified IP address is unknown.



UTL\_LMS retrieves and formats error messages in different languages.

**See Also:** *Oracle Database Globalization Support Guide*

This chapter contains the following topics:

- [Using UTL\\_LMS](#)
  - [Security Model](#)
- [Summary of UTL\\_LMS Subprograms](#)

---

## Using UTL\_LMS

- [Security Model](#)

### Security Model

This package must be created as the user SYS.

## Summary of UTL\_LMS Subprograms

**Table 159–1 UTL\_LMS Package Subprograms**

<b>Function</b>	<b>Description</b>
<a href="#">FORMAT_MESSAGE Function</a> on page 159-4	Formats a retrieved error message
<a href="#">GET_MESSAGE Function</a> on page 159-6	Retrieves an error message based on error number, product, facility, language, and message specified

## FORMAT\_MESSAGE Function

This function formats a message retrieved by the `GET_MESSAGE` function and returns the formatted message. If the function fails, then it returns a `NULL` result.

The following table shows special characters that can be used in the format string.

Special Character	Description
'%s'	Substitute the next string argument
'%d'	Substitute the next integer argument
'%%'	Represents the special character %

### Syntax

```
UTL_LMS.FORMAT_MESSAGE(format IN VARCHAR2 CHARACTER SET ANY_CS,
 args IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL)
RETURN VARCHAR2 CHARACTER SET format%CHARSET;
```

### Parameters

**Table 159–2** *FORMAT\_MESSAGE Procedure Parameters*

Parameter	Description
<code>format</code>	Specifies the string to format
<code>args</code>	Specifies the list of arguments

### Examples

```
DECLARE
 s varchar2(200);
 i pls_integer;
BEGIN
 i:= utl_lms.get_message(26052, 'rdbms', 'ora', 'french', s);
 dbms_output.put_line('before format, message is: '||s);
 dbms_output.put_line('formatted message is: '||utl_lms.format_message(s, 9,
 'my_column_name'));
END;
/
```

The following is an unformatted message:

Type %d non pris en charge pour l'expression SQL sur la colonne %s.

**The following is the formatted message:**

Type 9 non pris en charge pour l'expression SQL sur la colonne my\_column\_name.

## GET\_MESSAGE Function

This function retrieves an Oracle error message. The user can define user-specific error messages with the `lmsgen` utility.

It returns 0 when it is successful. It returns -1 when it fails.

**See Also:** *Oracle Database Globalization Support Guide* for more information about the `lmsgen` utility

### Syntax

```
UTL_LMS.GET_MESSAGE(errnum IN PLS_INTEGER,
 product IN VARCHAR2,
 facility IN VARCHAR2,
 language IN VARCHAR2,
 message OUT NOCOPY VARCHAR2CHARACTER SET ANY_CS)

RETURN PLS_INTEGER;
```

### Parameters

**Table 159–3** *GET\_MESSAGE Function Parameters*

Parameter	Description
<code>errnum</code>	Specifies the error number. Example: '972' (for ORA-00972)
<code>product</code>	Specifies the product to which the error message applies Example: 'rdbms'
<code>facility</code>	Specifies the error message prefix Example: 'ora'
<code>language</code>	Specifies the language of the message. The parameter is case-insensitive. The default is <code>NULL</code> , which causes <code>GET_MESSAGE</code> to use the value of the <code>NLS_LANGUAGE</code> session parameter.
<code>message</code>	Specifies the output buffer for the retrieved message

### Usage Notes

If the `language` parameter is set to `NULL`, then the value of the `NLS_LANGUAGE` session parameter is used as the default.



## Examples

```
DECLARE
 s varchar2(200);
 i pls_integer;
BEGIN
 i:=utl_lms.get_message(601, 'rdbms', 'oci', 'french', s);
 dbms_output.put_line('OCI--00601 is: '||s);
END
/
```

### The following output results:

```
OCI--00601 is: Echec du processus de nettoyage.
```



The `UTL_MAIL` package is a utility for managing email which includes commonly used email features, such as attachments, CC, BCC, and return receipt.

This chapter contains the following topics:

- [Using UTL\\_MAIL](#)
  - [Security Model](#)
  - [Operational Notes](#)
- [Summary of UTL\\_MAIL Subprograms](#)

---

## Using UTL\_MAIL

- [Security Model](#)
- [Operational Notes](#)

### Security Model

UTL\_MAIL is not installed by default because of the SMTP\_OUT\_SERVER configuration requirement and the security exposure this involves. In installing UTL\_MAIL, you should take steps to prevent the port defined by SMTP\_OUT\_SERVER being swamped by data transmissions .

### Operational Notes

You must both install UTL\_MAIL and define the SMTP\_OUT\_SERVER .

- To install UTL\_MAIL:

```
sqlplus sys/<pwd>
SQL> @$ORACLE_HOME/rdbms/admin/utlmail.sql
SQL> @$ORACLE_HOME/rdbms/admin/prvtmail.sql
```

- You define the SMTP\_OUT\_SERVER parameter in the init.ora rdbms initialization file. However, if SMTP\_OUT\_SERVER is not defined, this invokes a default of DB\_DOMAIN which is guaranteed to be defined to perform appropriately.

---

## Summary of UTL\_MAIL Subprograms

**Table 160–1 UTL\_MAIL Package Subprograms**

Subprogram	Description
<a href="#">SEND Procedure</a> on page 160-4	Packages an email message into the appropriate format, locates SMTP information, and delivers the message to the SMTP server for forwarding to the recipients
<a href="#">SEND_ATTACH_RAW Procedure</a> on page 160-5	Represents the <code>SEND</code> Procedure overloaded for <code>RAW</code> attachments
<a href="#">SEND_ATTACH_VARCHAR2 Procedure</a> on page 160-7	Represents the <code>SEND</code> Procedure overloaded for <code>VARCHAR2</code> attachments

## SEND Procedure

This procedure packages an email message into the appropriate format, locates SMTP information, and delivers the message to the SMTP server for forwarding to the recipients. It hides the SMTP API and exposes a one-line email facility for ease of use.

### Syntax

```
UTL_MAIL.SEND (
 sender IN VARCHAR2 CHARACTER SET ANY_CS,
 recipients IN VARCHAR2 CHARACTER SET ANY_CS,
 cc IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 bcc IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 subject IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 message IN VARCHAR2 CHARACTER SET ANY_CS,
 mime_type IN VARCHAR2 DEFAULT 'text/plain; charset=us-ascii',
 priority IN PLS_INTEGER DEFAULT NULL);
```

### Parameters

**Table 160–2 SEND Procedure Parameters**

Parameter	Description
sender	The email address of the sender.
recipients	The email addresses of the recipient(s), separated by commas.
cc	The email addresses of the CC recipient(s), separated by commas, default is NULL
bcc	The email addresses of the BCC recipient(s), separated by commas, default is NULL
subject	A string to be included as email subject string, default is NULL
message	A text message body.
mime_type	The mime type of the message, default is 'text/plain; charset=us-ascii'
priority	The message priority, default is NULL.

## SEND\_ATTACH\_RAW Procedure

This procedure is the SEND Procedure overloaded for RAW attachments.

### Syntax

```

UTL_MAIL.SEND_ATTACH_RAW (
 sender IN VARCHAR2 CHARACTER SET ANY_CS,
 recipients IN VARCHAR2 CHARACTER SET ANY_CS,
 cc IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 bcc IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 subject IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 message IN VARCHAR2 CHARACTER SET ANY_CS,
 mime_type IN VARCHAR2 DEFAULT 'text/plain; charset=us-ascii',
 priority IN PLS_INTEGER DEFAULT NULL
 attachment IN RAW,
 att_inline IN BOOLEAN DEFAULT TRUE,
 att_mime_type IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT
 'application/octet',
 att_filename IN VARCHAR2 DEFAULT NULL);

```

### Parameters

**Table 160–3 SEND\_ATTACH\_RAW Procedure Parameters**

Parameter	Description
sender	The email address of the sender.
recipients	The email addresses of the recipient(s), separated by commas.
cc	The email addresses of the CC recipient(s), separated by commas, default is NULL.
bcc	The email addresses of the BCC recipient(s), separated by commas, default is NULL.
subject	A string to be included as email subject string, default is NULL.
message	A text message body.
mime_type	The mime type of the message, default is 'text/plain; charset=us-ascii'.
priority	The message priority, the default is NULL.
attachment	A RAW attachment.

**Table 160–3 (Cont.) SEND\_ATTACH\_RAW Procedure Parameters**

<b>Parameter</b>	<b>Description</b>
<code>att_inline</code>	Specifies whether the attachment is viewable inline with the message body, default is <code>TRUE</code> .
<code>att_mime_type</code>	The mime type of the attachment, default is 'application/octet'.
<code>att_filename</code>	The string specifying a filename containing the attachment, default is <code>NULL</code> .



## SEND\_ATTACH\_VARCHAR2 Procedure

This procedure is the SEND Procedure overloaded for VARCHAR2 attachments.

### Syntax

```
UTL_MAIL.SEND_ATTACH_VARCHAR2 (
 sender IN VARCHAR2 CHARACTER SET ANY_CS,
 recipients IN VARCHAR2 CHARACTER SET ANY_CS,
 cc IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 bcc IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 subject IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL,
 message IN VARCHAR2 CHARACTER SET ANY_CS,
 mime_type IN VARCHAR2 DEFAULT 'text/plain; charset=us-ascii',
 priority IN PLS_INTEGER DEFAULT NULL
 attachment IN RAW,
 att_inline IN BOOLEAN DEFAULT TRUE,
 att_mime_type IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT
 'application/octet',
 att_filename IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 160–4 SEND\_ATTACH\_VARCHAR2 Procedure Parameters**

Parameter	Description
sender	The email address of the sender.
recipients	The email addresses of the recipient(s), separated by commas.
cc	The email addresses of the CC recipient(s), separated by commas, default is NULL.
bcc	The email addresses of the BCC recipient(s), separated by commas, default is NULL.
subject	A string to be included as email subject string, default is NULL.
message	A text message body.
mime_type	The mime type of the message, default is 'text/plain; charset=us-ascii'.
priority	The message priority, the default is NULL.
attachment	A text attachment.

**Table 160–4 (Cont.) SEND\_ATTACH\_VARCHAR2 Procedure Parameters**

<b>Parameter</b>	<b>Description</b>
att_inline	Specifies whether the attachment is inline, default TRUE.
att_mime_type	The mime type of the attachment, default is 'text/plain; charset=us-ascii'.
att_filename	The string specifying a filename containing the attachment, default is NULL.

The UTL\_RAW package provides SQL functions for manipulating RAW datatypes.

This chapter contains the following topics:

- [Using UTL\\_RAW](#)
  - [Overview](#)
  - [Operational Notes](#)
- [Summary of UTL\\_RAW Subprograms](#)

---

## Using UTL\_RAW

- [Overview](#)
- [Operational Notes](#)

### Overview

This package is necessary because normal SQL functions do not operate on RAWs, and PL/SQL does not allow overloading between a RAW and a CHAR datatype. UTL\_RAW also includes subprograms that convert various COBOL number formats to, and from, RAWs.

UTL\_RAW is not specific to the database environment, and it may actually be used in other environments. For this reason, the prefix UTL has been given to the package, instead of DBMS.

### Operational Notes

UTL\_RAW allows a RAW "record" to be composed of many elements. By using the RAW datatype, character set conversion will not be performed, keeping the RAW in its original format when being transferred through remote procedure calls.

With the RAW functions, you can manipulate binary data that was previously limited to the `hextoraw` and `rawtohex` functions.

---

## Summary of UTL\_RAW Subprograms

**Table 161–1 UTL\_RAW Package Subprograms**

Subprogram	Description
<a href="#">BIT_AND Function</a> on page 161-5	Performs bitwise logical "and" of the values in RAW <i>r1</i> with RAW <i>r2</i> and returns the "anded" result RAW
<a href="#">BIT_COMPLEMENT Function</a> on page 161-6	Performs bitwise logical "complement" of the values in RAW <i>r</i> and returns the "complement'ed" result RAW
<a href="#">BIT_OR Function</a> on page 161-7	Performs bitwise logical "or" of the values in RAW <i>r1</i> with RAW <i>r2</i> and returns the "or'd" result RAW
<a href="#">BIT_XOR Function</a> on page 161-8	Performs bitwise logical "exclusive or" of the values in RAW <i>r1</i> with RAW <i>r2</i> and returns the "xor'd" result RAW
<a href="#">CAST_FROM_BINARY_DOUBLE Function</a> on page 161-9	Returns the binary representation of a BINARY_DOUBLE (in RAW)
<a href="#">CAST_FROM_BINARY_FLOAT Function</a> on page 161-11	Returns the binary representation of a BINARY_FLOAT (in RAW)
<a href="#">CAST_FROM_BINARY_INTEGER Function</a> on page 161-13	Returns the binary representation of a BINARY_INTEGER (in RAW)
<a href="#">CAST_FROM_NUMBER Function</a> on page 161-14	Returns the binary representation of a NUMBER (in RAW)
<a href="#">CAST_TO_BINARY_DOUBLE Function</a> on page 161-15	Casts the binary representation of a RAW into a BINARY_DOUBLE
<a href="#">CAST_TO_BINARY_FLOAT Function</a> on page 161-17	Casts the binary representation of a RAW into a BINARY_FLOAT
<a href="#">CAST_TO_BINARY_INTEGER Function</a> on page 161-19	Casts the binary representation of a BINARY_INTEGER (in RAW) into a BINARY_INTEGER
<a href="#">CAST_TO_NUMBER Function</a> on page 161-20	Casts the binary representation of a NUMBER (in RAW) into a NUMBER
<a href="#">CAST_TO_RAW Function</a> on page 161-21	Converts a VARCHAR2 represented using <i>n</i> data bytes into a RAW with <i>n</i> data bytes
<a href="#">CAST_TO_VARCHAR2 Function</a> on page 161-22	Converts a RAW represented using <i>n</i> data bytes into VARCHAR2 with <i>n</i> data bytes

**Table 161–1 (Cont.) UTL\_RAW Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">CAST_TO_NVARCHAR2 Function</a> on page 161-23	Converts a RAW represented using <i>n</i> data bytes into NVARCHAR2 with <i>n</i> data bytes
<a href="#">COMPARE Function</a> on page 161-24	Compares RAW <i>r1</i> against RAW <i>r2</i>
<a href="#">CONCAT Function</a> on page 161-25	Concatenates up to 12 RAWs into a single RAW
<a href="#">CONVERT Function</a> on page 161-26	Converts RAW <i>r</i> from character set <i>from_charset</i> to character set <i>to_charset</i> and returns the resulting RAW
<a href="#">COPIES Function</a> on page 161-28	Returns <i>n</i> copies of <i>r</i> concatenated together
<a href="#">LENGTH Function</a> on page 161-29	Returns the length in bytes of a RAW <i>r</i>
<a href="#">OVERLAY Function</a> on page 161-30	Overlays the specified portion of target RAW with overlay RAW, starting from byte position <i>pos</i> of target and proceeding for <i>len</i> bytes
<a href="#">REVERSE Function</a> on page 161-32	Reverses a byte sequence in RAW <i>r</i> from end to end
<a href="#">SUBSTR Function</a> on page 161-33	Returns <i>len</i> bytes, starting at <i>pos</i> from RAW <i>r</i>
<a href="#">TRANSLATE Function</a> on page 161-35	Translates the bytes in the input RAW <i>r</i> according to the bytes in the translation RAWs <i>from_set</i> and <i>to_set</i>
<a href="#">TRANSLITERATE Function</a> on page 161-37	Converts the bytes in the input RAW <i>r</i> according to the bytes in the transliteration RAWs <i>from_set</i> and <i>to_set</i>
<a href="#">XRANGE Function</a> on page 161-39	Returns a RAW containing all valid 1-byte encodings in succession, beginning with the value <i>start_byte</i> and ending with the value <i>end_byte</i>

## BIT\_AND Function

This function performs bitwise logical "and" of the values in RAW *r1* with RAW *r2* and returns the "anded" result RAW.

### Syntax

```
UTL_RAW.BIT_AND (
 r1 IN RAW,
 r2 IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(bit_and, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–2 BIT\_AND Function Parameters**

Parameter	Description
<i>r1</i>	RAW to "and" with <i>r2</i> .
<i>r2</i>	RAW to "and" with <i>r1</i> .

### Return Values

**Table 161–3 BIT\_AND Function Return Values**

Return	Description
RAW	Containing the "and" of <i>r1</i> and <i>r2</i> .
NULL	Either <i>r1</i> or <i>r2</i> input parameter was NULL.

### Usage Notes

If *r1* and *r2* differ in length, the and operation is terminated after the last byte of the shorter of the two RAWs, and the unprocessed portion of the longer RAW is appended to the partial result. The result length equals the longer of the two input RAWs.

## BIT\_COMPLEMENT Function

This function performs bitwise logical "complement" of the values in RAW *r* and returns the complement'ed result RAW. The result length equals the input RAW *r* length.

### Syntax

```
UTL_RAW.BIT_COMPLEMENT (
 r IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(bit_complement, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–4 BIT\_COMPLEMENT Function Parameters**

Parameter	Description
<i>r</i>	RAW to perform "complement" operation.

### Return Values

**Table 161–5 BIT\_COMPLEMENT Function Return Values**

Return	Description
RAW	The "complement" of <i>r</i> 1.
NULL	If <i>r</i> input parameter was NULL.



## BIT\_OR Function

This function performs bitwise logical "or" of the values in RAW *r1* with RAW *r2* and returns the or'd result RAW.

### Syntax

```
UTL_RAW.BIT_OR (
 r1 IN RAW,
 r2 IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(bit_or, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–6 BIT\_OR Function Parameters**

Parameters	Description
<i>r1</i>	RAW to "or" with <i>r2</i> .
<i>r2</i>	RAW to "or" with <i>r1</i> .

### Return Values

**Table 161–7 BIT\_OR Function Return Values**

Return	Description
RAW	Containing the "or" of <i>r1</i> and <i>r2</i> .
NULL	Either <i>r1</i> or <i>r2</i> input parameter was NULL.

### Usage Notes

If *r1* and *r2* differ in length, then the "or" operation is terminated after the last byte of the shorter of the two RAWs, and the unprocessed portion of the longer RAW is appended to the partial result. The result length equals the longer of the two input RAWs.

## BIT\_XOR Function

This function performs bitwise logical "exclusive or" of the values in RAW *r1* with RAW *r2* and returns the xor'd result RAW.

### Syntax

```
UTL_RAW.BIT_XOR (
 r1 IN RAW,
 r2 IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(bit_xor, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–8 BIT\_XOR Function Parameters**

Parameter	Description
<i>r1</i>	RAW to "xor" with <i>r2</i> .
<i>r2</i>	RAW to "xor" with <i>r1</i> .

### Return Values

**Table 161–9 BIT\_XOR Function Return Values**

Return	Description
RAW	Containing the "xor" of <i>r1</i> and <i>r2</i> .
NULL	If either <i>r1</i> or <i>r2</i> input parameter was NULL.

### Usage Notes

If *r1* and *r2* differ in length, then the "xor" operation is terminated after the last byte of the shorter of the two RAWs, and the unprocessed portion of the longer RAW is appended to the partial result. The result length equals the longer of the two input RAWs.

## CAST\_FROM\_BINARY\_DOUBLE Function

This function returns the binary representation of a `BINARY_DOUBLE` (in RAW).

### Syntax

```
UTL_RAW.CAST_FROM_BINARY_DOUBLE(
 n IN BINARY_DOUBLE,
 endianness IN PLS_INTEGER DEFAULT 1)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(cast_from_binary_double, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–10 CAST\_FROM\_BINARY\_DOUBLE Function Parameters**

Parameter	Description
<code>n</code>	The <code>BINARY_DOUBLE</code> value.
<code>endianness</code>	A <code>PLS_INTEGER</code> representing big-endian or little-endian architecture. The default is big-endian.

### Return Values

The binary representation of the `BINARY_DOUBLE` value, or `NULL` if the input is `NULL`.

### Usage Notes

- An 8-byte `binary_double` value maps to the IEEE 754 double-precision format as follows:

```
byte 0: bit 63 ~ bit 56
byte 1: bit 55 ~ bit 48
byte 2: bit 47 ~ bit 40
byte 3: bit 39 ~ bit 32
byte 4: bit 31 ~ bit 24
byte 5: bit 23 ~ bit 16
byte 6: bit 15 ~ bit 8
byte 7: bit 7 ~ bit 0
```

- The parameter `endianess` describes how the bytes of `BINARY_DOUBLE` are mapped to the bytes of `RAW`. In the following matrix, `rb0 ~ rb7` refer to the bytes in `raw` and `db0 ~ db7` refer to the bytes in `BINARY_DOUBLE`.

	<b>rb0</b>	<b>rb1</b>	<b>rb2</b>	<b>rb3</b>	<b>rb4</b>	<b>rb5</b>	<b>rb6</b>	<b>rb7</b>
<b>big_endian</b>	db0	db1	db2	db3	db4	db5	db6	db7
<b>little_endian</b>	db7	db6	db5	db4	db3	db2	db1	db0

- In case of machine-endian, the 8 bytes of the `BINARY_DOUBLE` argument are copied straight across into the `RAW` return value. The effect is the same if the user has passed `big_endian` on a big-endian machine, or `little_endian` on a little-endian machine.

## CAST\_FROM\_BINARY\_FLOAT Function

This function returns the binary representation of a `BINARY_FLOAT` (in `RAW`).

### Syntax

```
UTL_RAW.CAST_FROM_BINARY_FLOAT(
 n IN BINARY_FLOAT,
 endianness IN PLS_INTEGER DEFAULT 1)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(cast_from_binary_float, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–11** *CAST\_FROM\_BINARY\_FLOAT Function Parameters*

Parameter	Description
<code>n</code>	The <code>BINARY_FLOAT</code> value.
<code>endianness</code>	A <code>PLS_INTEGER</code> representing big-endian or little-endian architecture. The default is big-endian.

### Return Values

The binary representation (`RAW`) of the `BINARY_FLOAT` value, or `NULL` if the input is `NULL`.

### Usage Notes

- A 4-byte `binary_float` value maps to the IEEE 754 single-precision format as follows:
  - byte 0: bit 31 ~ bit 24
  - byte 1: bit 23 ~ bit 16
  - byte 2: bit 15 ~ bit 8
  - byte 3: bit 7 ~ bit 0
- The parameter `endianness` describes how the bytes of `BINARY_FLOAT` are mapped to the bytes of `RAW`. In the following matrix, `rb0 ~ rb3` refer to the bytes in `RAW` and `fb0 ~ fb3` refer to the bytes in `BINARY_FLOAT`.

	<b>rb0</b>	<b>rb1</b>	<b>rb2</b>	<b>rb3</b>
<b>big_endian</b>	fb0	fb1	fb2	fb3
<b>little_endian</b>	fb3	fb2	fb1	fb0

- In case of machine-endian, the 4 bytes of the `BINARY_FLOAT` argument are copied straight across into the `RAW` return value. The effect is the same if the user has passed `big_endian` on a big-endian machine, or `little_endian` on a little-endian machine.

## CAST\_FROM\_BINARY\_INTEGER Function

This function returns the binary representation of a `BINARY_INTEGER` (in RAW).

### Syntax

```
UTL_RAW.CAST_FROM_BINARY_INTEGER (
 n IN BINARY_INTEGER
 endianness IN PLS_INTEGER DEFAULT BIG_ENDIAN)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(cast_from_binary_integer, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–12** *CAST\_FROM\_BINARY\_INTEGER Function Parameters*

Parameter	Description
<code>n</code>	The <code>BINARY_INTEGER</code> value.
<code>endianness</code>	A <code>PLS_INTEGER</code> representing big-endian or little-endian architecture. The default is big-endian.

### Return Values

The binary representation of the `BINARY_INTEGER` value.

## CAST\_FROM\_NUMBER Function

This function returns the binary representation of a NUMBER (in RAW).

### Syntax

```
UTL_RAW.CAST_FROM_NUMBER (
 n IN NUMBER)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(cast_from_number, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–13** *CAST\_FROM\_NUMBER Function Parameters*

Parameter	Description
n	The NUMBER value.

### Return Values

The binary representation of the NUMBER value.



## CAST\_TO\_BINARY\_DOUBLE Function

This function casts the binary representation of a `BINARY_DOUBLE` (in RAW) into a `BINARY_DOUBLE`.

### Syntax

```
UTL_RAW.CAST_TO_BINARY_DOUBLE (
 r IN RAW
 endianess IN PLS_INTEGER DEFAULT 1)
RETURN BINARY_DOUBLE;
```

### Pragmas

```
pragma restrict_references(cast_to_binary_double, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–14** *CAST\_TO\_BINARY\_DOUBLE Function Parameters*

Parameter	Description
<code>r</code>	The binary representation of a <code>BINARY_INTEGER</code> .
<code>endianess</code>	A <code>PLS_INTEGER</code> representing big-endian or little-endian architecture. The default is big-endian.

### Return Values

The `BINARY_DOUBLE` value.

### Usage Notes

- If the `RAW` argument is more than 8 bytes, only the first 8 bytes are used and the rest of the bytes are ignored. If the result is `-0`, `+0` is returned. If the result is `NaN`, the value `BINARY_DOUBLE_NAN` is returned.
- If the `RAW` argument is less than 8 bytes, a `VALUE_ERROR` exception is raised.
- An 8-byte binary\_double value maps to the IEEE 754 double-precision format as follows:

```
byte 0: bit 63 ~ bit 56
byte 1: bit 55 ~ bit 48
byte 2: bit 47 ~ bit 40
```

```

byte 3: bit 39 ~ bit 32
byte 4: bit 31 ~ bit 24
byte 5: bit 23 ~ bit 16
byte 6: bit 15 ~ bit 8
byte 7: bit 7 ~ bit 0

```

- The parameter `endianess` describes how the bytes of `BINARY_DOUBLE` are mapped to the bytes of `RAW`. In the following matrix, `rb0 ~ rb7` refer to the bytes in `raw` and `db0 ~ db7` refer to the bytes in `BINARY_DOUBLE`.

	<b>rb0</b>	<b>rb1</b>	<b>rb2</b>	<b>rb3</b>	<b>rb4</b>	<b>rb5</b>	<b>rb6</b>	<b>rb7</b>
<b>big_endian</b>	db0	db1	db2	db3	db4	db5	db6	db7
<b>little_endian</b>	db7	db6	db5	db4	db3	db2	db1	db0

- In case of machine-endian, the 8 bytes of the `RAW` argument are copied straight across into the `BINARY_DOUBLE` return value. The effect is the same if the user has passed `big_endian` on a big-endian machine, or `little_endian` on a little-endian machine.

## CAST\_TO\_BINARY\_FLOAT Function

This function casts the binary representation of a `BINARY_FLOAT` (in `RAW`) into a `BINARY_FLOAT`.

### Syntax

```
UTL_RAW.CAST_TO_BINARY_FLOAT (
 r IN RAW
 endianness IN PLS_INTEGER DEFAULT 1)
RETURN BINARY_FLOAT;
```

### Pragmas

```
pragma restrict_references(cast_to_binary_float, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–15** *CAST\_TO\_BINARY\_FLOAT Function Parameters*

Parameter	Description
<code>r</code>	The binary representation of a <code>BINARY_FLOAT</code> .
<code>endianness</code>	A <code>PLS_INTEGER</code> representing big-endian or little-endian architecture. The default is big-endian.

### Return Values

The `BINARY_FLOAT` value.

### Usage Notes

- If the `RAW` argument is more than 4 bytes, only the first 4 bytes are used and the rest of the bytes are ignored. If the result is `-0`, `+0` is returned. If the result is `NaN`, the value `BINARY_FLOAT_NAN` is returned.
- If the `RAW` argument is less than 4 bytes, a `VALUE_ERROR` exception is raised.
- A 4-byte binary\_float value maps to the IEEE 754 single-precision format as follows:

```
byte 0: bit 31 ~ bit 24
byte 1: bit 23 ~ bit 16
byte 2: bit 15 ~ bit 8
```

byte 3: bit 7 ~ bit 0

- The parameter `endianess` describes how the bytes of `BINARY_FLOAT` are mapped to the bytes of `RAW`. In the following matrix, `rb0 ~ rb3` refer to the bytes in `RAW` and `fb0 ~ fb3` refer to the bytes in `BINARY_FLOAT`.

	<b>rb0</b>	<b>rb1</b>	<b>rb2</b>	<b>rb3</b>
<b>big_endian</b>	fb0	fb1	fb2	fb3
<b>little_endian</b>	fb3	fb2	fb1	fb0

- In case of machine-endian, the 4 bytes of the `RAW` argument are copied straight across into the `BINARY_FLOAT` return value. The effect is the same if the user has passed `big_endian` on a big-endian machine, or `little_endian` on a little-endian machine.

## CAST\_TO\_BINARY\_INTEGER Function

This function casts the binary representation of a `BINARY_INTEGER` (in RAW) into a `BINARY_INTEGER`.

### Syntax

```
UTL_RAW.CAST_TO_BINARY_INTEGER (
 r IN RAW
 endianness IN PLS_INTEGER DEFAULT BIG_ENDIAN)
RETURN BINARY_INTEGER;
```

### Pragmas

```
pragma restrict_references(cast_to_binary_integer, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–16** *CAST\_TO\_BINARY\_INTEGER Function Parameters*

Parameter	Description
<code>r</code>	The binary representation of a <code>BINARY_INTEGER</code> .
<code>endianness</code>	A <code>PLS_INTEGER</code> representing big-endian or little-endian architecture. The default is big-endian.

### Return Values

The `BINARY_INTEGER` value

## CAST\_TO\_NUMBER Function

This function casts the binary representation of a NUMBER (in RAW) into a NUMBER.

### Syntax

```
UTL_RAW.CAST_TO_NUMBER (
 r IN RAW)
RETURN NUMBER;
```

### Pragmas

```
pragma restrict_references(cast_to_number, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–17 CAST\_TO\_NUMBER function Parameters**

Parameter	Description
r	The binary representation of a NUMBER

### Return Values

The NUMBER value.

## CAST\_TO\_RAW Function

This function converts a VARCHAR2 represented using *n* data bytes into a RAW with *n* data bytes. The data is not modified in any way; only its datatype is recast to a RAW datatype.

### Syntax

```
UTL_RAW.CAST_TO_RAW (
 c IN VARCHAR2)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(cast_to_raw, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–18 CAST\_TO\_RAW Function Parameters**

Parameter	Description
c	VARCHAR2 to be changed to a RAW.

### Return Values

**Table 161–19 CAST\_TO\_RAW Function Return Values**

Return	Description
RAW	Containing the same data as the input VARCHAR2 and equal byte length as the input VARCHAR2 and without a leading length field.
NULL	If c input parameter was NULL.

## CAST\_TO\_VARCHAR2 Function

This function converts a RAW represented using *n* data bytes into VARCHAR2 with *n* data bytes.

---

---

**Note:** When casting to a VARCHAR2, the current Globalization Support character set is used for the characters within that VARCHAR2.

---

---

### Syntax

```
UTL_RAW.CAST_TO_VARCHAR2 (
 r IN RAW)
RETURN VARCHAR2;
```

### Pragmas

```
pragma restrict_references(cast_to_VARCHAR2, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–20 CAST\_TO\_VARCHAR2 Function Parameters**

Parameter	Description
<i>r</i>	RAW (without leading length field) to be changed to a VARCHAR2.

### Return Values

**Table 161–21 CAST\_TO\_VARCHAR2 Function Return Values**

Return	Description
VARCHAR2	Containing having the same data as the input RAW.
NULL	If <i>r</i> input parameter was NULL.



## CAST\_TO\_NVARCHAR2 Function

This function converts a RAW represented using *n* data bytes into NVARCHAR2 with *n* data bytes.

---



---

**Note:** When casting to a NVARCHAR2, the current Globalization Support character set is used for the characters within that NVARCHAR2.

---



---

### Syntax

```
UTL_RAW.CAST_TO_NVARCHAR2 (
 r IN RAW)
RETURN NVARCHAR2;
```

### Pragmas

```
pragma restrict_references(cast_to_NVARCHAR2, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–22 CAST\_TO\_NVARCHAR2 Function Parameters**

Parameter	Description
<i>r</i>	RAW (without leading length field) to be changed to a NVARCHAR2).

### Return Values

**Table 161–23 CAST\_TO\_NVARCHAR2 Function Return Values**

Return	Description
NVARCHAR2	Containing having the same data as the input RAW.
NULL	If <i>r</i> input parameter was NULL.

## COMPARE Function

This function compares RAW *r1* against RAW *r2*. If *r1* and *r2* differ in length, then the shorter RAW is extended on the right with *pad* if necessary.

### Syntax

```
UTL_RAW.COMPARE (
 r1 IN RAW,
 r2 IN RAW,
 pad IN RAW DEFAULT NULL)
RETURN NUMBER;
```

### Pragmas

```
pragma restrict_references(compare, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–24 COMPARE Function Parameters**

Parameter	Description
<i>r1</i>	1st RAW to be compared, may be NULL or 0 length.
<i>r2</i>	2nd RAW to be compared, may be NULL or 0 length.
<i>pad</i>	This is an optional parameter. Byte to extend whichever of <i>r1</i> or <i>r2</i> is shorter. The default: x'00'

### Return Values

**Table 161–25 COMPARE Function Return Values**

Return	Description
NUMBER	Equals 0 if RAW byte strings are both NULL or identical; or, Equals position (numbered from 1) of the first mismatched byte.

## CONCAT Function

This function concatenates up to 12 RAWs into a single RAW. If the concatenated size exceeds 32K, then an error is returned

### Syntax

```
UTL_RAW.CONCAT (
 r1 IN RAW DEFAULT NULL,
 r2 IN RAW DEFAULT NULL,
 r3 IN RAW DEFAULT NULL,
 r4 IN RAW DEFAULT NULL,
 r5 IN RAW DEFAULT NULL,
 r6 IN RAW DEFAULT NULL,
 r7 IN RAW DEFAULT NULL,
 r8 IN RAW DEFAULT NULL,
 r9 IN RAW DEFAULT NULL,
 r10 IN RAW DEFAULT NULL,
 r11 IN RAW DEFAULT NULL,
 r12 IN RAW DEFAULT NULL)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(concat, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

r1....r12 are the RAW items to concatenate.

### Return Values

**Table 161–26** *CONCAT Function Return Values*

Return	Description
RAW	Containing the items concatenated.

### Exceptions

There is an error if the sum of the lengths of the inputs exceeds the maximum allowable length for a RAW, which is 32767 bytes.

## CONVERT Function

This function converts RAW *r* from character set *from\_charset* to character set *to\_charset* and returns the resulting RAW.

Both *from\_charset* and *to\_charset* must be supported character sets defined to the Oracle server.

### Syntax

```
UTL_RAW.CONVERT (
 r IN RAW,
 to_charset IN VARCHAR2,
 from_charset IN VARCHAR2)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(convert, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–27 CONVERT Function Parameters**

Parameter	Description
<i>r</i>	RAW byte-string to be converted.
<i>to_charset</i>	Name of Globalization Support character set to which <i>r</i> is converted.
<i>from_charset</i>	Name of Globalization Support character set in which <i>r</i> is supplied.

### Return Values

**Table 161–28 CONVERT Function Return Values**

Return	Description
RAW	Byte string <i>r</i> converted according to the specified character sets.

## Exceptions

**Table 161–29** *CONVERT Function Exceptions*

<b>Error</b>	<b>Description</b>
VALUE_ERROR	Either: <ul style="list-style-type: none"><li>- r missing, NULL, or 0 length</li><li>- from_charset or to_charset missing, NULL, or 0 length</li><li>- from_charset or to_charset names invalid or unsupported</li></ul>

## COPIES Function

This function returns *n* copies of *r* concatenated together.

### Syntax

```
UTL_RAW.COPIES (
 r IN RAW,
 n IN NUMBER)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(copies, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–30 COPIES Function Parameters**

Parameters	Description
<i>r</i>	RAW to be copied
<i>n</i>	Number of times to copy the RAW (must be positive).

### Return Values

This returns the RAW copied *n* times.

### Exceptions

**Table 161–31 COPIES Function Exceptions**

Error	Description
VALUE_ERROR	Either: - <i>r</i> is missing, NULL or 0 length - <i>n</i> < 1 - Length of result exceeds maximum length of a RAW

## LENGTH Function

This function returns the length in bytes of a RAW *r*.

### Syntax

```
UTL_RAW.LENGTH (
 r IN RAW)
RETURN NUMBER;
```

### Pragmas

```
pragma restrict_references(length, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–32** LENGTH Function Parameters

Parameter	Description
<i>r</i>	The RAW byte stream to be measured.

### Return Values

**Table 161–33** LENGTH Function Return Values

Return	Description
NUMBER	The current length of the RAW.

## OVERLAY Function

This function overlays the specified portion of target RAW with `overlay_str` RAW, starting from byte position `pos` of target and proceeding for `len` bytes.

### Syntax

```
UTL_RAW.OVERLAY (
 overlay_str IN RAW,
 target IN RAW,
 pos IN BINARY_INTEGER DEFAULT 1,
 len IN BINARY_INTEGER DEFAULT NULL,
 pad IN RAW DEFAULT NULL)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(overlay, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–34 OVERLAY Function Parameters**

Parameters	Description
<code>overlay_str</code>	Byte-string used to overlay target.
<code>target</code>	Byte-string which is to be overlaid.
<code>pos</code>	Position in target (numbered from 1) to start overlay.
<code>len</code>	The number of target bytes to overlay.
<code>pad</code>	Pad byte used when overlay <code>len</code> exceeds <code>overlay_str</code> length or <code>pos</code> exceeds target length.

### Defaults and Optional Parameters

**Table 161–35 OVERLAY Function Optional Parameters**

Optional Parameter	Description
<code>pos</code>	1
<code>len</code>	To the length of <code>overlay_str</code>
<code>pad</code>	x'00'



## Return Values

**Table 161–36 OVERLAY Function Return Values**

Return	Description
RAW	The target byte_string overlaid as specified.

## Usage Notes

If `overlay_str` has less than `len` bytes, then it is extended to `len` bytes using the `pad` byte. If `overlay_str` exceeds `len` bytes, then the extra bytes in `overlay_str` are ignored. If `len` bytes beginning at position `pos` of `target` exceeds the length of `target`, then `target` is extended to contain the entire length of `overlay_str`.

If `len` is specified, it must be greater than or equal to 0. If `pos` is specified, it must be greater than or equal to 1. If `pos` exceeds the length of `target`, then `target` is padded with `pad` bytes to position `pos`, and `target` is further extended with `overlay_str` bytes.

## Exceptions

**Table 161–37 OVERLAY Function Exceptions**

Error	Description
VALUE_ERROR	Either: <ul style="list-style-type: none"> <li>- <code>overlay_str</code> is NULL or has 0 length</li> <li>- Target is missing or undefined</li> <li>- Length of target exceeds maximum length of a RAW</li> <li>- <code>len &lt; 0</code></li> <li>- <code>pos &lt; 1</code></li> </ul>

## REVERSE Function

This function reverses a byte sequence in RAW *r* from end to end. For example, `x'0102F3'` would be reversed to `x'F30201'`, and `'xyz'` would be reversed to `'zyx'`. The result length is the same as the input RAW length.

### Syntax

```
UTL_RAW.REVERSE (
 r IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(reverse, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–38 REVERSE Function Parameters**

Parameter	Description
<i>r</i>	RAW to reverse.

### Return Values

**Table 161–39 REVERSE Function Return Values**

Return	Description
RAW	Containing the "reverse" of <i>r</i> .

### Exceptions

**Table 161–40 REVERSE Function Exceptions**

Error	Description
VALUE_ERROR	R is NULL or has 0 length.

## SUBSTR Function

This function returns `len` bytes, starting at `pos` from RAW `r`.

### Syntax

```
UTL_RAW.SUBSTR (
 r IN RAW,
 pos IN BINARY_INTEGER,
 len IN BINARY_INTEGER DEFAULT NULL)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(substr, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–41 SUBSTR Function Parameters**

Parameter	Description
<code>r</code>	The RAW byte-string from which a portion is extracted.
<code>pos</code>	The byte position in <code>r</code> at which to begin extraction.
<code>len</code>	The number of bytes from <code>pos</code> to extract from <code>r</code> (optional).

### Defaults and Optional Parameters

**Table 161–42 SUBSTR Function Exceptions**

Optional Parameter	Description
<code>len</code>	Position <code>pos</code> through to the end of <code>r</code> .

### Return Values

**Table 161–43 SUBSTR Function Return Values**

Return	Description
portion of <code>r</code>	Beginning at <code>pos</code> for <code>len</code> bytes long.
NULL	<code>r</code> input parameter was NULL.

## Usage Notes

If `pos` is positive, then `SUBSTR` counts from the beginning of `r` to find the first byte. If `pos` is negative, then `SUBSTR` counts backward from the end of the `r`. The value `pos` cannot be 0.

If `len` is omitted, then `SUBSTR` returns all bytes to the end of `r`. The value `len` cannot be less than 1.

## Exceptions

**Table 161–44** *SUBSTR Function Exceptions*

Error	Description
VALUE_ERROR	VALUE_ERROR is returned if: <ul style="list-style-type: none"><li>pos = 0 or &gt; length of r</li><li>len &lt; 1 or &gt; length of r - (pos-1)</li></ul>

## TRANSLATE Function

This function translates the bytes in the input RAW *r* according to the bytes in the translation RAWs *from\_set* and *to\_set*. If a byte in *r* has a matching byte in *from\_set*, then it is replaced by the byte in the corresponding position in *to\_set*, or deleted.

Bytes in *r*, but undefined in *from\_set*, are copied to the result. Only the first (leftmost) occurrence of a byte in *from\_set* is used. Subsequent duplicates are not scanned and are ignored.

### Syntax

```
UTL_RAW.TRANSLATE (
 r IN RAW,
 from_set IN RAW,
 to_set IN RAW)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(translate, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–45 TRANSLATE Function Parameters**

Parameter	Description
<i>r</i>	RAW source byte-string to be translated.
<i>from_set</i>	RAW byte-codes to be translated, if present in <i>r</i> .
<i>to_set</i>	RAW byte-codes to which corresponding <i>from_str</i> bytes are translated.

### Return Values

**Table 161–46 TRANSLATE Function Return Values**

Return	Description
RAW	Translated byte-string.

## Usage Notes

If `to_set` is shorter than `from_set`, then the extra `from_set` bytes have no translation correspondence and any bytes in `r` matching.

---

---

**Note:** Difference from TRANSLITERATE:

- Translation RAWs have no defaults.
  - `r` bytes undefined in the `to_set` translation RAW are deleted.
  - Result RAW may be shorter than input RAW `r`.
- 
- 

## Exceptions

**Table 161–47** *TRANSLATE Function Exceptions*

Error	Description
VALUE_ERROR	Either: <ul style="list-style-type: none"><li>- <code>r</code> is NULL or has 0 length</li><li>- <code>from_set</code> is NULL or has 0 length</li><li>- <code>to_set</code> is NULL or has 0 length</li></ul>

## TRANSLITERATE Function

This function converts the bytes in the input RAW *r* according to the bytes in the transliteration RAWs *from\_set* and *to\_set*. Successive bytes in *r* are looked up in the *from\_set*, and, if not found, copied unaltered to the result RAW. If found, then they are replaced in the result RAW by either corresponding bytes in the *to\_set*, or the *pad* byte when no correspondence exists.

Bytes in *r*, but undefined in *from\_set*, are copied to the result. Only the first (leftmost) occurrence of a byte in *from\_set* is used. Subsequent duplicates are not scanned and are ignored. The result RAW is always the same length as *r*.

### Syntax

```
UTL_RAW.TRANSLITERATE (
 r IN RAW,
 to_set IN RAW DEFAULT NULL,
 from_set IN RAW DEFAULT NULL,
 pad IN RAW DEFAULT NULL)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(transliterate, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–48** *TRANSLITERATE Function Parameters*

Parameter	Description
<i>r</i>	RAW input byte-string to be converted.
<i>from_set</i>	RAW byte-codes to be converted, if present in <i>r</i> (any length).
<i>to_set</i>	RAW byte-codes to which corresponding <i>from_set</i> bytes are converted (any length).
<i>pad</i>	1 byte used when <i>to_set</i> is shorter than the <i>from_set</i> .

## Defaults and Optional Parameters

**Table 161–49** *TRANSLITERATE Function Optional Parameters*

Optional Parameter	Description
<code>from_set</code>	<code>x f00'</code> through <code>x fff'</code>
<code>to_set</code>	To the <code>NULL</code> string and effectively extended with <code>pad</code> to the length of <code>from_set</code> as necessary.
<code>pad</code>	<code>x'00'</code> .

## Return Values

**Table 161–50** *TRANSLITERATE Function Return Values*

Return	Description
<code>RAW</code>	Converted byte-string.

## Usage Notes

If the `to_set` is shorter than the `from_set`, then the `pad` byte is placed in the result `RAW` when a selected `from_set` byte has no corresponding `to_set` byte (as if the `to_set` were extended to the same length as the `from_set` with `pad` bytes).

---



---

**Note:** Difference from `TRANSLATE` :

- `r` bytes undefined in `to_set` are padded.
  - Result `RAW` is always same length as input `RAW r`.
- 
- 

## Exceptions

**Table 161–51** *TRANSLITERATE Function Exceptions*

Error	Description
<code>VALUE_ERROR</code>	<code>R</code> is <code>NULL</code> or has 0 length.



## XRANGE Function

This function returns a RAW containing all valid 1-byte encodings in succession, beginning with the value `start_byte` and ending with the value `end_byte`. If `start_byte` is greater than `end_byte`, then the succession of resulting bytes begins with `start_byte`, wraps through `x fFF f` to `x f00 f`, and ends at `end_byte`. If specified, `start_byte` and `end_byte` must be single-byte RAWs.

### Syntax

```
UTL_RAW.XRANGE (
 start_byte IN RAW DEFAULT NULL,
 end_byte IN RAW DEFAULT NULL)
RETURN RAW;
```

### Pragmas

```
pragma restrict_references(xrange, WNDS, RNDS, WNPS, RNPS);
```

### Parameters

**Table 161–52 XRANGE Function Parameters**

Parameters	Description
<code>start_byte</code>	Beginning byte-code value of resulting sequence.
<code>end_byte</code>	Ending byte-code value of resulting sequence.

### Defaults and Optional Parameters

```
start_byte - x f00 f
end_byte - x fFF f
```

### Return Values

**Table 161–53 XRANGE Function Return Values**

Return	Description
RAW	Containing succession of 1-byte hexadecimal encodings.



The UTL\_RECOMP package recompiles invalid PL/SQL modules, Java classes, indextypes and operators in a database, either sequentially or in parallel.

This chapter contains the following topics:

- [Using UTL\\_RECOMP](#)
  - [Overview](#)
  - [Operational Notes](#)
  - [Examples](#)
- [Summary of UTL\\_RECOMP Subprograms](#)

## Using UTL\_RECOMP

- [Overview](#)
- [Operational Notes](#)
- [Examples](#)

### Overview

This script is particularly useful after a major-version upgrade that typically invalidates all PL/SQL and Java objects. Although invalid objects are recompiled automatically on use, it is useful to run this script prior to operation because this will either eliminate or minimize subsequent latencies due to on-demand automatic recompilation at runtime.

Parallel recompilation can exploit multiple CPUs to reduce the time taken to recompile invalid objects. The degree of parallelism is specified by the first argument to [RECOMP\\_PARALLEL Procedure](#).

In general, a parallelism setting of one thread for each available CPU provides a good initial setting. However, please note that the process of recompiling an invalid object writes a significant amount of data to system tables and is fairly I/O intensive. A slow disk system may be a significant bottleneck and limit speedups available from a higher degree of parallelism.

### Operational Notes

- This package uses the job queue for parallel recompilation. It temporarily disables existing jobs (by marking them broken) so that recompile jobs can be run instead.
- This package must be run using `SQL*PLUS`.
- You must be connected `AS SYSDBA` to run this script.
- This package expects the following packages to have been created with `VALID` status:
  - `STANDARD` (`standard.sql`)
  - `DBMS_STANDARD` (`dbmsstdx.sql`)

- DBMS\_JOB (dbmsjob.sql)
- DBMS\_RANDOM (dbmsrand.sql)
- There should be no other DDL on the database while running entries in this package. Not following this recommendation may lead to deadlocks.

## Examples

**Recompile all objects sequentially:**

```
EXECUTE UTL_RECOMP.RECOMP_SERIAL();
```

**Recompile objects in schema SCOTT sequentially:**

```
EXECUTE UTL_RECOMP.RECOMP_SERIAL('SCOTT');
```

**Recompile all objects using 4 parallel threads:**

```
EXECUTE UTL_RECOMP.RECOMP_PARALLEL(4);
```

**Recompile objects in schema JOE using the number of threads specified in the parameter JOB\_QUEUE\_PROCESSES:**

```
EXECUTE UTL_RECOMP.RECOMP_PARALLEL(NULL, 'JOE');
```

---

## Summary of UTL\_RECOMP Subprograms

**Table 162–1** *UTL\_RECOMP Package Subprograms*

<b>Subprogram</b>	<b>Description</b>
<a href="#">RECOMP_PARALLEL Procedure</a> on page 162-5	Recompiles invalid objects in the database, or in a given schema, in parallel in dependency order
<a href="#">RECOMP_SERIAL Procedure</a> on page 162-6	Recompiles invalid objects in a given schema or all invalid objects in the database

## RECOMP\_PARALLEL Procedure

This procedure is the main driver that recompiles invalid objects in the database, or in a given schema, in parallel in dependency order. It uses information in `dependency$` to order recompilation of dependents after parents.

### Syntax

```
UTL_RECOMP.RECOMP_PARALLEL(
 threads IN PLS_INTEGER DEFAULT NULL,
 schema IN VARCHAR2 DEFAULT NULL,
 flags IN PLS_INTEGER DEFAULT 0);
```

### Parameters

**Table 162–2** *RECOMP\_PARALLEL Procedure Parameters*

Parameter	Description
threads	The number of recompile threads to run in parallel. If NULL, use the value of 'job_queue_processes'.
schema	The schema in which to recompile invalid objects. If NULL, all invalid objects in the database are recompiled.
flags	Flag values are intended for internal testing and diagnosability only.

### Usage Notes

The parallel recompile exploits multiple CPUs to reduce the time taken to recompile invalid objects. However, please note that recompilation writes significant amounts of data to system tables, so the disk system may be a bottleneck and prevent significant speedups.

## RECOMP\_SERIAL Procedure

This procedure recompiles invalid objects in a given schema or all invalid objects in the database.

### Syntax

```
UTL_RECOMP.RECOMP_SERIAL(
 schema IN VARCHAR2 DEFAULT NULL,
 flags IN PLS_INTEGER DEFAULT 0);
```

### Parameters

**Table 162–3** *RECOMP\_SERIAL Procedure Parameters*

Parameter	Description
schema	The schema in which to recompile invalid objects. If NULL, all invalid objects in the database are recompiled.
flags	Flag values are intended for internal testing and diagnosability only.



The `UTL_REF` package provides PL/SQL procedures to support reference-based operations. Unlike SQL, `UTL_REF` procedures enable you to write generic type methods without knowing the object table name.

This chapter contains the following topics:

- [Using UTL\\_REF](#)
  - [Overview](#)
  - [Security Model](#)
  - [Types](#)
  - [Exceptions](#)
- [Summary of UTL\\_REF Subprograms](#)

## Using UTL\_REF

---

- [Overview](#)
- [Security Model](#)
- [Types](#)
- [Exceptions](#)

### Overview

Oracle supports user-defined composite type or object type. Any instance of an object type is called an object. An object type can be used as the type of a column or as the type of a table.

In an object table, each row of the table stores an object. You can uniquely identify an object in an object table with an object identifier.

A reference is a persistent pointer to an object, and each reference can contain an object identifier. The reference can be an attribute of an object type, or it can be stored in a column of a table. Given a reference, an object can be retrieved.

### Security Model

The procedural option is needed to use this package. This package must be created under `SYS` (connect/as sysdba). Operations provided by this package are performed under the current calling user, not under the package owner `SYS`.

You can use the `UTL_REF` package from stored PL/SQL procedures/packages on the server, as well as from client-side PL/SQL code.

When invoked from PL/SQL procedures/packages on the server, `UTL_REF` verifies that the invoker has the appropriate privileges to access the object pointed to by the `REF`.

---

---

**Note:** This is in contrast to PL/SQL packages/procedures on the server which operate with definer's privileges, where the package owner must have the appropriate privileges to perform the desired operations.

---

---

Thus, if `UTL_REF` is defined under user `SYS`, and user `A` invokes `UTL_REF.SELECT` to select an object from a reference, then user `A` (the invoker) requires the privileges to check.

When invoked from client-side PL/SQL code, `UTL_REF` operates with the privileges of the client session under which the PL/SQL execution is being done.

## Types

An object type is a composite datatype defined by the user or supplied as a library type. You can create the object type `employee_type` using the following syntax:

```
CREATE TYPE employee_type AS OBJECT (
 name VARCHAR2(20),
 id NUMBER,

 member function GET_ID
 (name VARCHAR2)
 RETURN MEMBER);
```

The object type `employee_type` is a user-defined type that contains two attributes, `name` and `id`, and a member function, `GET_ID()`.

You can create an object table using the following SQL syntax:

```
CREATE TABLE employee_table OF employee_type;
```

## Exceptions

Exceptions can be returned during execution of `UTL_REF` functions for various reasons. For example, the following scenarios would result in exceptions:

- The object selected does not exist. This could be because either:
  1. The object has been deleted, or the given reference is dangling (`invalid`).
  2. The object table was dropped or does not exist.
- The object cannot be modified or locked in a serializable transaction. The object was modified by another transaction after the serializable transaction started.
- You do not have the privilege to select or modify the object. The caller of the `UTL_REF` subprogram must have the proper privilege on the object that is being selected or modified.

**Table 163–1 UTL\_REF Exceptions**

<b>Exceptions</b>	<b>Description</b>
<code>errnum == 942</code>	Insufficient privileges.
<code>errnum == 1031</code>	Insufficient privileges.
<code>errnum == 8177</code>	Unable to serialize, if in a serializable transaction.
<code>errnum == 60</code>	Deadlock detected.
<code>errnum == 1403</code>	No data found (if the REF is NULL, and so on.).

The `UTL_REF` package does not define any named exceptions. You may define exception handling blocks to catch specific exceptions and to handle them appropriately.

## Summary of UTL\_REF Subprograms

**Table 163–2 UTL\_REF Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">DELETE_OBJECT Procedure</a> on page 163-6	Deletes an object given a reference
<a href="#">LOCK_OBJECT Procedure</a> on page 163-9	Locks an object given a reference
<a href="#">SELECT_OBJECT Procedure</a> on page 163-10	Selects an object given a reference
<a href="#">UPDATE_OBJECT Procedure</a> on page 163-11	Updates an object given a reference

## DELETE\_OBJECT Procedure

This procedure deletes an object given a reference. The semantic of this subprogram is similar to the following SQL statement:

```
DELETE FROM object_table
WHERE REF(t) = reference;
```

Unlike the preceding SQL statement, this subprogram does not require you to specify the object table name where the object resides.

### Syntax

```
UTL_REF.DELETE_OBJECT (
 reference IN REF "<typename>");
```

### Parameters

**Table 163–3** *DELETE\_OBJECT Procedure Parameters*

Parameter	Description
reference	Reference of the object to delete.

### Exceptions

May be raised.

### Examples

The following example illustrates usage of the UTL\_REF package to implement this scenario: if an employee of a company changes their address, their manager should be notified.

... declarations of Address\_t and others...

```
CREATE OR REPLACE TYPE Person_t (
 name VARCHAR2(64),
 gender CHAR(1),
 address Address_t,
 MEMBER PROCEDURE setAddress(addr IN Address_t)
);

CREATE OR REPLACE TYPE BODY Person_t (
 MEMBER PROCEDURE setAddress(addr IN Address_t) IS
```

```

BEGIN
 address := addr;
END;
);

CREATE OR REPLACE TYPE Employee_t (

```

**Under Person\_t: Simulate implementation of inheritance using a REF to Person\_t and delegation of setAddress to it.**

```

 thePerson REF Person_t,
 empno NUMBER(5),
 deptREF Department_t,
 mgrREF Employee_t,
 reminders StringArray_t,
 MEMBER PROCEDURE setAddress(addr IN Address_t),
 MEMBER procedure addReminder(reminder VARCHAR2);
);

```

```

CREATE TYPE BODY Employee_t (
 MEMBER PROCEDURE setAddress(addr IN Address_t) IS
 myMgr Employee_t;
 meAsPerson Person_t;
 BEGIN

```

**Update the address by delegating the responsibility to thePerson. Lock the Person object from the reference, and also select it:**

```

 UTL_REF.LOCK_OBJECT(thePerson, meAsPerson);
 meAsPerson.setAddress(addr);

```

**Delegate to thePerson:**

```

 UTL_REF.UPDATE_OBJECT(thePerson, meAsPerson);
 if mgr is NOT NULL THEN

```

**Give the manager a reminder:**

```

 UTL_REF.LOCK_OBJECT(mgr);
 UTL_REF.SELECT_OBJECT(mgr, myMgr);
 myMgr.addReminder
 ('Update address in the employee directory for' ||
 thePerson.name || ', new address: ' || addr.asString);
 UTL_REF.UPDATE_OBJECT(mgr, myMgr);
 END IF;
EXCEPTION

```

```
WHEN OTHERS THEN
errnum := SQLCODE;
errmsg := SUBSTR(SQLERRM, 1, 200);
```



## LOCK\_OBJECT Procedure

This procedure locks an object given a reference. In addition, this procedure lets the program select the locked object. The semantic of this subprogram is similar to the following SQL statement:

```
SELECT VALUE(t)
 INTO object
 FROM object_table t
 WHERE REF(t) = reference
 FOR UPDATE;
```

Unlike the preceding SQL statement, this subprogram does not require you to specify the object table name where the object resides. It is not necessary to lock an object before updating/deleting it.

### Syntax

```
UTL_REF.LOCK_OBJECT (
 reference IN REF "<typename>");

UTL_REF.LOCK_OBJECT (
 reference IN REF "<typename>",
 object IN OUT "<typename>");
```

### Parameters

**Table 163–4 LOCK\_OBJECT Procedure Parameters**

Parameter	Description
reference	Reference of the object to lock.
object	The PL/SQL variable that stores the locked object. This variable should be of the same object type as the locked object.

### Exceptions

May be raised.

## SELECT\_OBJECT Procedure

This procedure selects an object given its reference. The selected object is retrieved from the database and its value is put into the PL/SQL variable 'object'. The semantic of this subprogram is similar to the following SQL statement:

```
SELECT VALUE(t)
INTO object
FROM object_table t
WHERE REF(t) = reference;
```

Unlike the preceding SQL statement, this subprogram does not require you to specify the object table name where the object resides.

### Syntax

```
UTL_REF.SELECT_OBJECT (
 reference IN REF "<typename>",
 object IN OUT "<typename>");
```

### Parameters

**Table 163–5** *SELECT\_OBJECT Procedure Parameters*

Parameter	Description
reference	Reference to the object to select or retrieve.
object	The PL/SQL variable that stores the selected object; this variable should be of the same object type as the referenced object.

### Exceptions

May be raised.

## UPDATE\_OBJECT Procedure

This procedure updates an object given a reference. The referenced object is updated with the value contained in the PL/SQL variable 'object'. The semantic of this subprogram is similar to the following SQL statement:

```
UPDATE object_table t
SET VALUE(t) = object
WHERE REF(t) = reference;
```

Unlike the preceding SQL statement, this subprogram does not require you to specify the object table name where the object resides.

### Syntax

```
UTL_REF.UPDATE_OBJECT (
 reference IN REF "<typename>",
 object IN "<typename>");
```

### Parameters

**Table 163–6 UPDATE\_OBJECT Procedure Parameters**

Parameter	Description
reference	Reference of the object to update.
object	The PL/SQL variable that contains the new value of the object. This variable should be of the same object type as the object to update.

### Exceptions

May be raised.



The UTL\_SMTP package is designed for sending electronic mails (emails) over Simple Mail Transfer Protocol (SMTP) as specified by RFC821.

**See Also:** How to use the SMTP package to send email in *Oracle Database Application Developer's Guide - Fundamentals*

This chapter contains the following topics:

- [Using UTL\\_SMTP](#)
  - [Overview](#)
  - [Types](#)
  - [Reply Codes](#)
  - [Exceptions](#)
  - [Rules and Limits](#)
  - [Examples](#)
- [Summary of UTL\\_SMTP Subprograms](#)

## Using UTL\_SMTP

- [Overview](#)
- [Types](#)
- [Reply Codes](#)
- [Exceptions](#)
- [Rules and Limits](#)
- [Examples](#)

### Overview

The protocol consists of a set of commands for an email client to dispatch emails to a SMTP server. The `UTL_SMTP` package provides interfaces to the SMTP commands. For many of the commands, the package provides both a procedural and a functional interface. The functional form returns the reply from the server for processing by the client. The procedural form checks the reply and will raise an exception if the reply indicates a transient (400-range reply code) or permanent error (500-range reply code). Otherwise, it discards the reply.

Note that the original SMTP protocol communicates using 7-bit ASCII. Using `UTL_SMTP`, all text data (in other words, those in `VARCHAR2`) will be converted to US7ASCII before it is sent over the wire to the server. Some implementations of SMTP servers that support SMTP extension 8BITMIME [RFC1652] support full 8-bit communication between client and server. The body of the `DATA` command may be transferred in full 8 bits, but the rest of the SMTP command and response should be in 7 bits. When the target SMTP server supports 8BITMIME extension, users of multibyte databases may convert their non-US7ASCII, multibyte `VARCHAR2` data to `RAW` and use the `WRITE_RAW_DATA` subprogram to send multibyte data using 8-bit MIME encoding.

`UTL_SMTP` provides for SMTP communication as specified in RFC821, but does not provide an API to format the content of the message according to RFC 822 (for example, setting the subject of an electronic mail). You must format the message appropriately. In addition, `UTL_SMTP` does not have the functionality to implement an SMTP server for an email clients to send emails using SMTP.

---



---

**Note :** RFC documents are "Request for Comments" documents that describe proposed standards for public review on the Internet. For the actual RFC documents, please refer to:

<http://www.ietf.org/rfc/>

---



---

## Types

- [CONNECTION Record Type](#)
- [REPLY, REPLIES Record Types](#)

### CONNECTION Record Type

This is a PL/SQL record type used to represent an SMTP connection.

#### Syntax

```
TYPE connection IS RECORD (
 host VARCHAR2(255), -- remote host name
 port PLS_INTEGER, -- remote port number
 tx_timeout PLS_INTEGER, -- Transfer time out (in seconds)
 private_tcp_con utl_tcp.connection, -- private, for implementation use
 private_state PLS_INTEGER -- private, for implementation use
);
```

#### Fields

**Table 164–1 CONNECTION Record Type Fields**

Field	Description
host	The name of the remote host when connection is established. NULL when no connection is established.
port	The port number of the remote SMTP server connected. NULL when no connection is established.
tx_timeout	The time in seconds that the UTL_SMTP package waits before giving up in a read or write operation in this connection. In read operations, this package gives up if no data is available for reading immediately. In write operations, this package gives up if the output buffer is full and no data is to be sent into the network without being blocked. 0 indicates not to wait at all. NULL indicates to wait forever.

**Table 164–1 CONNECTION Record Type Fields**

Field	Description
<code>private_tcp_con</code>	Private, for implementation use only. You should not modify this field.
<code>private_state</code>	Private, for implementation use only. You should not modify this field.

### Usage Notes

The read-only fields in a connection record are used to return information about the SMTP connection after the connection is successfully made with `open_connection()`. Changing the values of these fields has no effect on the connection. The fields `private_xxx` are for implementation use only. You should not modify these fields.

## REPLY, REPLIES Record Types

These are PL/SQL record types used to represent an SMTP reply line. Each SMTP reply line consists of a reply code followed by a text message. While a single reply line is expected for most SMTP commands, some SMTP commands expect multiple reply lines. For those situations, a PL/SQL table of reply records is used to represent multiple reply lines.

### Syntax

```
TYPE reply IS RECORD (
 code PLS_INTEGER, -- 3-digit reply code
 text VARCHAR2(508) -- text message
);
TYPE replies IS TABLE OF reply INDEX BY BINARY_INTEGER; -- multiple reply
lines
```

### Fields

**Table 164–2 REPLY, REPLIES Record Type Fields**

Field	Description
<code>code</code>	The 3-digit reply code.
<code>text</code>	The text message of the reply.



## Reply Codes

The following is a list of the SMTP reply codes.

**Table 164–3 SMTP Reply Codes**

Reply Code	Meaning
211	System status, or system help reply
214	Help message [Information on how to use the receiver or the meaning of a particular non-standard command; this reply is useful only to the human user]
220	<domain> Service ready
221	<domain> Service closing transmission channel
250	Requested mail action okay, completed
251	User not local; will forward to <forward-path>
252	OK, pending messages for node <node> started. Cannot VRFY user (for example, info is not local), but will take message for this user and attempt delivery.
253	OK, <messages> pending messages for node <node> started
354	Start mail input; end with <CRLF>. <CRLF>
355	Octet-offset is the transaction offset
421	<domain> Service not available, closing transmission channel (This may be a reply to any command if the service knows it must shut down.)
450	Requested mail action not taken: mailbox unavailable [for example, mailbox busy]
451	Requested action terminated: local error in processing
452	Requested action not taken: insufficient system storage
453	You have no mail.
454	TLS not available due to temporary reason. Encryption required for requested authentication mechanism.
458	Unable to queue messages for node <node>
459	Node <node> not allowed: reason
500	Syntax error, command unrecognized (This may include errors such as command line too long.)

**Table 164–3 (Cont.) SMTP Reply Codes**

Reply Code	Meaning
501	Syntax error in parameters or arguments
502	Command not implemented
503	Bad sequence of commands
504	Command parameter not implemented
521	<Machine> does not accept mail.
530	Must issue a STARTTLS command first. Encryption required for requested authentication mechanism.
534	Authentication mechanism is too weak.
538	Encryption required for requested authentication mechanism.
550	Requested action not taken: mailbox unavailable [for , mailbox not found, no access]
551	User not local; please try <forward-path>
552	Requested mail action terminated: exceeded storage allocation
553	Requested action not taken: mailbox name not allowed [for example, mailbox syntax incorrect]
554	Transaction failed

## Exceptions

The table lists the exceptions that can be raised by the interface of the UTL\_SMTP package. The network error is transferred to a reply code of 421- service not available.

**Table 164–4 UTL\_SMTP Exceptions**

INVALID_OPERATION	Raised when an invalid operation is made. In other words, calling API other than <code>write_data()</code> , <code>write_raw_data()</code> or <code>close_data()</code> after <code>open_data()</code> is called, or calling <code>write_data()</code> , <code>write_raw_data()</code> or <code>close_data()</code> without first calling <code>open_data()</code> .
TRANSIENT_ERROR	Raised when receiving a reply code in 400 range.
PERMANENT_ERROR	Raised when receiving a reply code in 500 range.

## Rules and Limits

No limitation or range-checking is imposed by the API. However, you should be aware of the following size limitations on various elements of SMTP. Sending data that exceed these limits may result in errors returned by the server.

**Table 164–5 SMTP Size Limitation**

Element	Size Limitation
user	The maximum total length of a user name is 64 characters.
domain	The maximum total length of a domain name or number is 64 characters.
path	The maximum total length of a reverse-path or forward-path is 256 characters (including the punctuation and element separators).
command line	The maximum total length of a command line including the command word and the <CRLF> is 512 characters.
reply line	The maximum total length of a reply line including the reply code and the <CRLF> is 512 characters.
text line	The maximum total length of a text line including the <CRLF> is 1000 characters (but not counting the leading dot duplicated for transparency).
recipients buffer	The maximum total number of recipients that must be buffered is 100 recipients.

## Examples

The following example illustrates how UTL\_SMTP is used by an application to send e-mail. The application connects to an SMTP server at port 25 and sends a simple text message.

```

DECLARE
 c UTL_SMTP.CONNECTION;

 PROCEDURE send_header(name IN VARCHAR2, header IN VARCHAR2) AS
 BEGIN
 UTL_SMTP.WRITE_DATA(c, name || ': ' || header || UTL_TCP.CRLF);
 END;

BEGIN
 c := UTL_SMTP.OPEN_CONNECTION('smtp-server.acme.com');

```

```
UTL_SMTP.HELO(c, 'foo.com');
UTL_SMTP.MAIL(c, 'sender@foo.com');
UTL_SMTP.RCPT(c, 'recipient@foo.com');
UTL_SMTP.OPEN_DATA(c);
send_header('From', '"Sender" <sender@foo.com>');
send_header('To', '"Recipient" <recipient@foo.com>');
send_header('Subject', 'Hello');
UTL_SMTP.WRITE_DATA(c, UTL_TCP.CRLF || 'Hello, world!');
UTL_SMTP.CLOSE_DATA(c);
UTL_SMTP.QUIT(c);
EXCEPTION
 WHEN utl_smtp.transient_error OR utl_smtp.permanent_error THEN
 BEGIN
 UTL_SMTP.QUIT(c);
 EXCEPTION
 WHEN UTL_SMTP.TRANSIENT_ERROR OR UTL_SMTP.PERMANENT_ERROR THEN
 NULL; -- When the SMTP server is down or unavailable, we don't have
 -- a connection to the server. The QUIT call will raise an
 -- exception that we can ignore.
 END;
 raise_application_error(-20000,
 'Failed to send mail due to the following error: ' || sqlerrm);
END;
```

---

## Summary of UTL\_SMTP Subprograms

**Table 164–6 UTL\_SMTP Package Subprograms**

Subprogram	Description
<a href="#">CLOSE_DATA Function and Procedure</a> on page 164-11	Closes the data session
<a href="#">COMMAND Function and Procedure</a> on page 164-13	Performs a generic SMTP command
<a href="#">COMMAND_REPLIES Function</a> on page 164-15	Performs initial handshaking with SMTP server after connecting
<a href="#">DATA Function and Procedure</a> on page 164-16	Performs initial handshaking with SMTP server after connecting, with extended information returned
<a href="#">EHLO Function and Procedure</a> on page 164-18	Performs initial handshaking with SMTP server after connecting, with extended information returned
<a href="#">HELO Function and Procedure</a> on page 164-20	Performs initial handshaking with SMTP server after connecting
<a href="#">HELP Function</a> on page 164-22	Sends <code>HELP</code> command
<a href="#">MAIL Function and Procedure</a> on page 164-23	Initiates a mail transaction with the server, the destination is a mailbox
<a href="#">NOOP Function and Procedure</a> on page 164-25	The null command
<a href="#">OPEN_CONNECTION Functions</a> on page 164-26	Opens a connection to an SMTP server
<a href="#">OPEN_DATA Function and Procedure</a> on page 164-28	Sends the <code>DATA</code> command
<a href="#">QUIT Function and Procedure</a> on page 164-30	Terminates an SMTP session and disconnects from the server
<a href="#">RCPT Function</a> on page 164-32	Specifies the recipient of an e-mail message
<a href="#">RSET Function and Procedure</a> on page 164-34	Terminates the current mail transaction

**Table 164–6 UTL\_SMTP Package Subprograms**

<b>Subprogram</b>	<b>Description</b>
<a href="#">VERFY Function</a> on page 164-36	Verifies the validity of a destination e-mail address
<a href="#">WRITE_DATA Procedure</a> on page 164-37	Writes a portion of the e-mail message
<a href="#">WRITE_RAW_DATA Procedure</a> on page 164-39	Writes a portion of the e-mail message with RAW data

## CLOSE\_DATA Function and Procedure

The `CLOSE_DATA` call ends the e-mail message by sending the sequence `<CR><LF> . <CR><LF>` (a single period at the beginning of a line).

### Syntax

```
UTL_SMTP.CLOSE_DATA (
 c IN OUT NOCOPY connection)
RETURN reply;
```

```
UTL_SMTP.CLOSE_DATA (
 c IN OUT NOCOPY connection);
```

### Parameters

**Table 164–7** *CLOSE\_DATA Function and Procedure Parameters*

Parameter	Description
c	The SMTP connection.

### Return Values

**Table 164–8** *CLOSE\_DATA Function and Procedure Return Values*

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

The calls to `OPEN_DATA`, `WRITE_DATA`, `WRITE_RAW_DATA` and `CLOSE_DATA` must be made in the right order. A program calls `OPEN_DATA` to send the `DATA` command to the SMTP server. After that, it can call `WRITE_DATA` or `WRITE_RAW_DATA` repeatedly to send the actual data. The data is terminated by calling `CLOSE_DATA`. After `OPEN_DATA` is called, the only subprograms that can be called are `WRITE_DATA`, `WRITE_RAW_DATA`, or `CLOSE_DATA`. A call to other APIs will result in an `INVALID_OPERATION` exception being raised.

`CLOSE_DATA` should be called only after `OPEN_CONNECTION`, `HELO` or `EHLO`, `MAIL`, and `RCPT` have been called. The connection to the SMTP server must be open and a mail transaction must be active when this routine is called.

Note that there is no function form of `WRITE_DATA` because the SMTP server does not respond until the data-terminator is sent during the call to `CLOSE_DATA`.



## COMMAND Function and Procedure

This function/procedure performs a generic SMTP command.

### Syntax

```
UTL_SMTP.COMMAND (
 c IN OUT NOCOPY connection,
 cmd IN VARCHAR2,
 arg IN VARCHAR2 DEFAULT NULL)
RETURN reply;
```

```
UTL_SMTP.COMMAND (
 c IN OUT NOCOPY connection,
 cmd IN VARCHAR2,
 arg IN VARCHAR2 DEFAULT NULL);
```

### Parameters

**Table 164–9** *COMMAND Function and Procedure Parameters*

Parameter	Description
c	The SMTP connection.
cmd	The SMTP command to send to the server.
arg	The optional argument to the SMTP argument. A space will be inserted between cmd and arg.

### Return Values

**Table 164–10** *COMMAND Function and Procedure Return Values*

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

This function is used to invoke generic SMTP commands. Use `COMMAND` if only a single reply line is expected. Use `COMMAND_REPLIES` if multiple reply lines are expected.

For `COMMAND`, if multiple reply lines are returned from the SMTP server, it returns the last reply line only.

## COMMAND\_REPLIES Function

This function performs a generic SMTP command.

### Syntax

```
UTL_SMTP.COMMAND_REPLIES (
 c IN OUT NOCOPY connection,
 cmd IN VARCHAR2,
 arg IN VARCHAR2 DEFAULT NULL)
RETURN replies;
```

### Parameters

**Table 164–11** *COMMAND\_REPLIES Function Parameters*

Parameter	Description
c	The SMTP connection.
cmd	The SMTP command to send to the server.
arg	The optional argument to the SMTP argument. A space will be inserted between cmd and arg.

### Return Values

**Table 164–12** *COMMAND\_REPLIES Function Return Values*

Return Value	Description
replies	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ).

### Usage Notes

This function is used to invoke generic SMTP commands. Use `COMMAND` if only a single reply line is expected. Use `COMMAND_REPLIES` if multiple reply lines are expected.

For `COMMAND`, if multiple reply lines are returned from the SMTP server, it returns the last reply line only.

## DATA Function and Procedure

This function/procedure specifies the body of an e-mail message.

### Syntax

```
UTL SMTP.DATA (
 c IN OUT NOCOPY connection
 body IN VARCHAR2 CHARACTER SET ANY_CS)
RETURN reply;
```

```
UTL SMTP.DATA (
 c IN OUT NOCOPY connection
 body IN VARCHAR2 CHARACTER SET ANY_CS);
```

### Parameters

**Table 164–13 DATA Function and Procedure Parameters**

Parameter	Description
c	The SMTP Connection.
body	The text of the message to be sent, including headers, in [RFC822] format.

### Return Values

**Table 164–14 DATA Function and Procedure Return Values**

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

The application must ensure that the contents of the body parameter conform to the MIME(RFC822) specification. The DATA routine will terminate the message with a <CR><LF> . <CR><LF> sequence (a single period at the beginning of a line), as required by RFC821. It will also translate any sequence of <CR><LF> . <CR><LF> (single period) in body to <CR><LF> . . <CR><LF> (double period). This conversion provides the transparency as described in Section 4.5.2 of RFC821.

The `DATA` call should be called only after `OPEN_CONNECTION`, `HELO` or `EHLO`, `MAIL` and `RCPT` have been called. The connection to the SMTP server must be open, and a mail transaction must be active when this routine is called.

The expected response from the server is a message beginning with status code 250. The 354 response received from the initial `DATA` command will not be returned to the caller.

## EHLO Function and Procedure

This function/procedure performs initial handshaking with SMTP server after connecting, with extended information returned.

### Syntax

```
UTL_SMTP.EHLO (
 c IN OUT NOCOPY connection,
 domain IN)
RETURN replies;
```

```
UTL_SMTP.EHLO (
 c IN OUT NOCOPY connection,
 domain IN);
```

### Parameters

**Table 164–15** *EHLO Function and Procedure Parameters*

Parameter	Description
c	The SMTP connection.
domain	The domain name of the local (sending) host. Used for identification purposes.

### Return Values

**Table 164–16** *EHLO Function and Procedure Return Values*

Return Value	Description
replies	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ).

### Usage Notes

The EHLO interface is identical to HELO except that it allows the server to return more descriptive information about its configuration. [RFC1869] specifies the format of the information returned, which the PL/SQL application can retrieve using the functional form of this call. For compatibility with HELO, each line of text returned by the server begins with status code 250.

## Related Functions

HELO

## HELO Function and Procedure

This function/procedure performs initial handshaking with SMTP server after connecting.

### Syntax

```
UTL_SMTP.HELO (
 c IN OUT NOCOPY connection,
 domain IN VARCHAR2)
RETURN reply;
```

```
UTL_SMTP.HELO (
 c IN OUT NOCOPY connection,
 domain IN VARCHAR2);
```

### Parameters

**Table 164–17 HELO Function and Procedure Parameters**

Parameter	Description
c	The SMTP connection.
domain	The domain name of the local (sending) host. Used for identification purposes.

### Return Values

**Table 164–18 HELO Function and Procedure Return Values**

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

RFC 821 specifies that the client must identify itself to the server after connecting. This routine performs that identification. The connection must have been opened through a call to [OPEN\\_CONNECTION Functions](#) before calling this routine.

The expected response from the server is a message beginning with status code 250.



## Related Functions

EHLO

## HELP Function

This function sends the `HELP` command.

### Syntax

```
UTL_SMTP.HELP (
 c IN OUT NOCOPY connection,
 command IN VARCHAR2 DEFAULT NULL)
RETURN replies;
```

### Parameters

**Table 164–19** *HELP Function Parameters*

Parameter	Description
<code>c</code>	The SMTP connection.
<code>command</code>	The command to get the help message.

### Return Values

**Table 164–20** *HELP Function Return Values*

Return Value	Description
<code>replies</code>	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ).

## MAIL Function and Procedure

This function/procedure initiates a mail transaction with the server. The destination is a mailbox.

### Syntax

```

UTL_SMTP.MAIL (
 c IN OUT NOCOPY connection,
 sender IN VARCHAR2,
 parameters IN VARCHAR2 DEFAULT NULL)
RETURN reply;

UTL_SMTP.MAIL (
 c IN OUT NOCOPY connection,
 sender IN VARCHAR2,
 parameters IN VARCHAR2 DEFAULT NULL);

```

### Parameters

**Table 164–21 MAIL Function and Procedure Parameters**

Parameter	Description
c	The SMTP connection.
sender	The e-mail address of the user sending the message.
parameters	The additional parameters to MAIL command as defined in Section 6 of [RFC1869]. It should follow the format of "XXX=XXX (XXX=XXX ...)".

### Return Values

**Table 164–22 MAIL Function and Procedure Return Values**

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

## Usage Notes

This command does not send the message; it simply begins its preparation. It must be followed by calls to `RCPT` and `DATA` to complete the transaction. The connection to the SMTP server must be open and a `HELO` or `EHLO` command must have already been sent.

The expected response from the server is a message beginning with status code 250.

## NOOP Function and Procedure

The null command.

### Syntax

```
UTL_SMTP.NOOP (
 c IN OUT NOCOPY connection)
RETURN reply;
```

```
UTL_SMTP.NOOP (
 c IN OUT NOCOPY connection);
```

### Parameter

**Table 164–23 NOOP Function and Procedure Parameters**

Parameter	Description
c	The SMTP connection.

### Return Values

**Table 164–24 NOOP Function and Procedure Return Values**

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

This command has no effect except to elicit a successful reply from the server. It can be issued at any time after the connection to the server has been established with `OPEN_CONNECTION`. The `NOOP` command can be used to verify that the server is still connected and is listening properly.

This command will always reply with a single line beginning with status code 250.

## OPEN\_CONNECTION Functions

These functions open a connection to an SMTP server.

### Syntax

```
UTL_SMTP.OPEN_CONNECTION (
 host IN VARCHAR2,
 port IN PLS_INTEGER DEFAULT 25,
 c OUT connection,
 tx_timeout IN PLS_INTEGER DEFAULT NULL)
RETURN reply;
```

```
UTL_SMTP.OPEN_CONNECTION (
 host IN VARCHAR2,
 port IN PLS_INTEGER DEFAULT 25,
 tx_timeout IN PLS_INTEGER DEFAULT NULL)
RETURN connection;
```

### Parameters

**Table 164–25 OPEN\_CONNECTION Functions Parameters**

Parameter	Description
host	The name of the SMTP server host
port	The port number on which SMTP server is listening (usually 25).
c	The SMTP connection.
tx_timeout	The time in seconds that the UTL_SMTP package waits before giving up in a read or write operation in this connection. In read operations, this package gives up if no data is available for reading immediately. In write operations, this package gives up if the output buffer is full and no data is to be sent into the network without being blocked. 0 indicates not to wait at all. NULL indicates to wait forever.

## Return Values

**Table 164–26** *OPEN\_CONNECTION Functions Return Values*

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

## Usage Notes

- The expected response from the server is a message beginning with status code 220.
- The version of `OPEN_CONNECTION` that returns `UTL_SMTP.CONNECTION` record checks the reply code returned by an SMTP server when the connection is first established. It raises an exception when the reply indicates an error. Otherwise, it discards the reply. If a user is interested in examining the reply, he or she can invoke the version of `OPEN_CONNECTION` that returns `REPLY`.
- A timeout on the `WRITE` operations feature is not supported in the current release of this package.

## OPEN\_DATA Function and Procedure

OPEN\_DATA sends the DATA command after which you can use WRITE\_DATA and WRITE\_RAW\_DATA to write a portion of the e-mail message.

### Syntax

```
UTL_SMTP.OPEN_DATA (
 c IN OUT NOCOPY connection)
RETURN reply;

UTL_SMTP.OPEN_DATA (
 c IN OUT NOCOPY connection);
```

### Parameters

**Table 164–27 OPEN\_DATA Function and Procedure Parameters**

Parameter	Description
c	The SMTP connection.
data	The portion of the text of the message to be sent, including headers, in [RFC822] format.

### Return Values

**Table 164–28 OPEN\_DATA Function and Procedure Function Return Values**

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

The calls to OPEN\_DATA, WRITE\_DATA, WRITE\_RAW\_DATA and CLOSE\_DATA must be made in the right order. A program calls OPEN\_DATA to send the DATA command to the SMTP server. After that, it can call WRITE\_DATA or WRITE\_RAW\_DATA repeatedly to send the actual data. The data is terminated by calling CLOSE\_DATA. After OPEN\_DATA is called, the only subprograms that can be called are WRITE\_DATA, WRITE\_RAW\_DATA, or CLOSE\_DATA. A call to other APIs will result in an INVALID\_OPERATION exception being raised.



**OPEN\_DATA should be called only after OPEN\_CONNECTION, HELO or EHLO, MAIL, and RCPT have been called. The connection to the SMTP server must be open and a mail transaction must be active when this routine is called.**

## QUIT Function and Procedure

This function terminates an SMTP session and disconnects from the server.

### Syntax

```
UTL_SMTP.QUIT (
 c IN OUT NOCOPY connection)
RETURN reply;

UTL_SMTP.QUIT (
 c IN OUT NOCOPY connection);
```

### Parameter

**Table 164–29** *QUIT Function and Procedure Parameters*

Parameter	Description
c	The SMTP connection.

### Return Values

**Table 164–30** *QUIT Function and Procedure Function Return Values*

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

The `QUIT` command informs the SMTP server of the client's intent to terminate the session. It then closes the connection established by `OPEN_CONNECTION` which must have been called before executing this command. If a mail transaction is in progress when `QUIT` is issued, it is abandoned in the same manner as `RSET`.

The function form of this command returns a single line beginning with the status code 221 on successful termination. In all cases, the connection to the SMTP server is closed. The fields `REMOTE_HOST` and `REMOTE_PORT` of `c` are reset.

## Related Functions

RSET

## RCPT Function

This function/procedure specifies the recipient of an e-mail message.

### Syntax

```
UTL_SMTP.RCPT (
 c IN OUT NOCOPY connection,
 recipient IN VARCHAR2,
 parameters IN VARCHAR2 DEFAULT NULL)
RETURN reply;

UTL_SMTP.RCPT (
 c IN OUT NOCOPY connection,
 recipient IN VARCHAR2,
 parameters IN VARCHAR2 DEFAULT NULL);
```

**Table 164–31** *RCPT Function and Procedure Parameters*

Parameter	Description
c	The SMTP connection.
recipient	The e-mail address of the user to which the message is being sent.
parameters	The additional parameters to RCPT command as defined in Section 6 of [RFC1869]. It should follow the format of "XXX=XXX (XXX=XXX ...)".

### Return Values

**Table 164–32** *RCPT Function and Procedure Function Return Values*

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

To send a message to multiple recipients, call this routine multiple times. Each invocation schedules delivery to a single e-mail address. The message transaction must have been begun by a prior call to `MAIL`, and the connection to the mail server

must have been opened and initialized by prior calls to `OPEN_CONNECTION` and `HELO` or `EHLO` respectively.

The expected response from the server is a message beginning with status code 250 or 251.

## RSET Function and Procedure

This function terminates the current mail transaction.

### Syntax

```
UTL_SMTP.RSET (
 c IN OUT NOCOPY connection)
RETURN reply;

UTL_SMTP.RSET (
 c IN OUT NOCOPY connection);
```

### Parameters

**Table 164–33** RSET Function and Procedure Parameters

Parameter	Description
c	The SMTP connection.

### Return Values

**Table 164–34** RSET Function and Procedure Return Values

Return Value	Description
reply	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

This command allows the client to abandon a mail message it was in the process of composing. No mail will be sent. The client can call `RSET` at any time after the connection to the SMTP server has been opened by means of `OPEN_CONNECTION` until `DATA` or `OPEN_DATA` is called. Once the email data has been sent, it will be too late to prevent the email from being sent.

The server will always respond to `RSET` with a message beginning with status code 250.

## Related Functions

QUIT

## VRFY Function

This function verifies the validity of a destination e-mail address.

### Syntax

```
UTL_SMTP.VRFY (
 c IN OUT NOCOPY connection
 recipient IN VARCHAR2)
RETURN reply;
```

### Parameters

**Table 164–35 VRFY Function Parameters**

Parameter	Description
<code>c</code>	The SMTP connection.
<code>recipient</code>	The e-mail address to be verified.

### Return Values

**Table 164–36 VRFY Function Return Values**

Return Value	Description
<code>reply</code>	Reply of the command (see <a href="#">REPLY, REPLIES Record Types</a> ). In cases where there are multiple replies, the last reply will be returned.

### Usage Notes

The server attempts to resolve the destination address `recipient`. If successful, it returns the recipient's full name and fully qualified mailbox path. The connection to the server must have already been established by means of `OPEN_CONNECTION` and `HELO` or `EHLO` before making this request.

Successful verification returns one or more lines beginning with status code 250 or 251.



## WRITE\_DATA Procedure

Use `WRITE_DATA` to write a portion of the e-mail message. A repeat call to `WRITE_DATA` appends data to the e-mail message.

### Syntax

```
UTL_SMTP.WRITE_DATA (
 c IN OUT NOCOPY connection,
 data IN VARCHAR2 CHARACTER SET ANY_CS);
```

### Parameters

**Table 164–37** *WRITE\_DATA Procedure Parameters*

Parameter	Description
<code>c</code>	The SMTP connection.
<code>data</code>	The portion of the text of the message to be sent, including headers, in [RFC822] format.

### Usage Notes

The calls to `OPEN_DATA`, `WRITE_DATA`, `WRITE_RAW_DATA` and `CLOSE_DATA` must be made in the right order. A program calls `OPEN_DATA` to send the `DATA` command to the SMTP server. After that, it can call `WRITE_DATA` or `WRITE_RAW_DATA` repeatedly to send the actual data. The data is terminated by calling `CLOSE_DATA`. After `OPEN_DATA` is called, the only subprograms that can be called are `WRITE_DATA`, `WRITE_RAW_DATA`, or `CLOSE_DATA`. A call to other APIs will result in an `INVALID_OPERATION` exception being raised.

The application must ensure that the contents of the body parameter conform to the MIME(RFC822) specification. The `DATA` routine will terminate the message with a `<CR><LF> . <CR><LF>` sequence (a single period at the beginning of a line), as required by RFC821. It will also translate any sequence of `<CR><LF> . <CR><LF>` (single period) in the body to `<CR><LF> . . <CR><LF>` (double period). This conversion provides the transparency as described in Section 4.5.2 of RFC821.

Notice that this conversion is not bullet-proof. Consider this code fragment:

```
UTL_SMTP.WRITE_DATA('some message.' || chr(13) || chr(10));
UTL_SMTP.WRITE_DATA('.' || chr(13) || chr(10));
```

Since the sequence `<CR><LF>` . `<CR><LF>` is split between two calls to `WRITE_DATA`, the implementation of `WRITE_DATA` will not detect the presence of the data-terminator sequence, and therefore, will not perform the translation. It will be the responsibility of the user to handle such a situation, or it may result in premature termination of the message data.

`WRITE_DATA` should be called only after `OPEN_CONNECTION`, `HELO` or `EHLO`, `MAIL`, and `RCPT` have been called. The connection to the SMTP server must be open and a mail transaction must be active when this routine is called.

Note that there is no function form of `WRITE_DATA` because the SMTP server does not respond until the data-terminator is sent during the call to `CLOSE_DATA`.

Text (`VARCHAR2`) data sent using `WRITE_DATA` is converted to `US7ASCII` before it is sent. If the text contains multibyte characters, each multibyte character in the text that cannot be converted to `US7ASCII` is replaced by a '?' character. If `8BITMIME` extension is negotiated with the SMTP server using the `EHLO` subprogram, multibyte `VARCHAR2` data can be sent by first converting the text to `RAW` using the `UTL_RAW` package, and then sending the `RAW` data using `WRITE_RAW_DATA`.

## WRITE\_RAW\_DATA Procedure

Use `WRITE_RAW_DATA` to write a portion of the e-mail message. A repeat call to `WRITE_RAW_DATA` appends data to the e-mail message.

### Syntax

```
UTL_SMTP.WRITE_RAW_DATA (
 c IN OUT NOCOPY connection
 data IN RAW);
```

### Parameters

**Table 164–38** *WRITE\_RAW\_DATA Procedure Parameters*

Parameter	Description
<code>c</code>	The SMTP connection.
<code>data</code>	The portion of the text of the message to be sent, including headers, in [RFC822] format.

### Usage Notes

The calls to `OPEN_DATA`, `WRITE_DATA`, `WRITE_RAW_DATA` and `CLOSE_DATA` must be made in the right order. A program calls `OPEN_DATA` to send the `DATA` command to the SMTP server. After that, it can call `WRITE_DATA` or `WRITE_RAW_DATA` repeatedly to send the actual data. The data is terminated by calling `CLOSE_DATA`. After `OPEN_DATA` is called, the only subprograms that can be called are `WRITE_DATA`, `WRITE_RAW_DATA`, or `CLOSE_DATA`. A call to other APIs will result in an `INVALID_OPERATION` exception being raised.

The application must ensure that the contents of the body parameter conform to the MIME(RFC822) specification. The `DATA` routine will terminate the message with a `<CR><LF> . <CR><LF>` sequence (a single period at the beginning of a line), as required by RFC821. It will also translate any sequence of `<CR><LF> . <CR><LF>` (single period) in the body to `<CR><LF> . . <CR><LF>` (double period). This conversion provides the transparency as described in Section 4.5.2 of RFC821.

Notice that this conversion is not bullet-proof. Consider this code fragment:

```
UTL_SMTP.WRITE_DATA('some message.' || chr(13) || chr(10));
UTL_SMTP.WRITE_DATA('.' || chr(13) || chr(10));
```

Since the sequence `<CR><LF> . <CR><LF>` is split between two calls to `WRITE_DATA`, the implementation of `WRITE_DATA` will not detect the presence of the data-terminator sequence, and therefore, will not perform the translation. It will be the responsibility of the user to handle such a situation, or it may result in premature termination of the message data.

`XXX_DATA` should be called only after `OPEN_CONNECTION`, `HELO` or `EHLO`, `MAIL`, and `RCPT` have been called. The connection to the SMTP server must be open and a mail transaction must be active when this routine is called.

Note that there is no function form of `WRITE_DATA` because the SMTP server does not respond until the data-terminator is sent during the call to `CLOSE_DATA`.

Text (`VARCHAR2`) data sent using `WRITE_DATA` is converted to `US7ASCII` before it is sent. If the text contains multibyte characters, each multibyte character in the text that cannot be converted to `US7ASCII` is replaced by a '?' character. If `8BITMIME` extension is negotiated with the SMTP server using the `EHLO` subprogram, multibyte `VARCHAR2` data can be sent by first converting the text to `RAW` using the `UTL_RAW` package, and then sending the `RAW` data using `WRITE_RAW_DATA`.

With the `UTL_TCP` package and its procedures and functions, PL/SQL applications can communicate with external TCP/IP-based servers using TCP/IP. Because many Internet application protocols are based on TCP/IP, this package is useful to PL/SQL applications that use Internet protocols and e-mail.

This chapter contains the following topics:

- [Using UTL\\_TCP](#)
  - [Overview](#)
  - [Types](#)
  - [Exceptions](#)
  - [Rules and Limits](#)
  - [Examples](#)
- [Summary of UTL\\_TCP Subprograms](#)

---

## Using UTL\_TCP

- [Overview](#)
- [Types](#)
- [Exceptions](#)
- [Rules and Limits](#)
- [Examples](#)

### Overview

The UTL\_TCP package provides TCP/IP client-side access functionality in PL/SQL.

### Types

- [CONNECTION Type](#)
- [CRLF](#)

### CONNECTION Type

This is a PL/SQL record type used to represent a TCP/IP connection.

#### Syntax

```
TYPE connection IS RECORD (
 remote_host VARCHAR2(255),
 remote_port PLS_INTEGER,
 local_host VARCHAR2(255),
 local_port PLS_INTEGER,
 charset VARCHAR2(30),
 newline VARCHAR2(2),
 tx_timeout PLS_INTEGER,
 private_sd PLS_INTEGER);
```

## Fields

**Table 165–1 connection Record Type Fields**

Field	Description
<code>remote_host</code>	The name of the remote host when connection is established. NULL when no connection is established.
<code>remote_port</code>	The port number of the remote host connected. NULL when no connection is established.
<code>local_host</code>	The name of the local host used to establish the connection. NULL when no connection is established.
<code>local_port</code>	The port number of the local host used to establish the connection. NULL when no connection is established.
<code>charset</code>	The on-the-wire character set. Since text messages in the database may be encoded in a character set that is different from the one expected on the wire (that is, the character set specified by the communication protocol, or the one stipulated by the other end of the communication), text messages in the database will be converted to and from the on-the-wire character set as they are sent and received on the network.
<code>newline</code>	The newline character sequence. This newline character sequence is appended to the text line sent by <code>WRITE_LINE</code> API.
<code>tx_timeout</code>	A time in seconds that the <code>UTL_TCP</code> package waits before giving up in a read or write operation in this connection. In read operations, this package gives up if no data is available for reading immediately. In write operations, this package gives up if the output buffer is full and no data is to be sent in the network without being blocked. Zero (0) indicates not to wait at all. NULL indicates to wait forever.

## Usage Notes

The fields in a connection record are used to return information about the connection, which is often made using `OPEN_CONNECTION`. Changing the values of those fields has no effect on the connection. The fields `private_XXXX` are for implementation use only. You should not modify the values.

In the current release of the `UTL_TCP` package, the parameters `local_host` and `local_port` are ignored when `open_connection` makes a TCP/IP connection. It does not attempt to use the specified local host and port number when the connection is made. The `local_host` and `local_port` fields will not be set in the connection record returned by the function.

Time out on write operations is not supported in the current release of the UTL\_TCP package.

## CRLF

The character sequence carriage-return line-feed. It is the newline sequence commonly used many communication standards.

### Syntax

```
CRLF varchar2(10);
```

### Usage Notes

This package variable defines the newline character sequence commonly used in many Internet protocols. This is the default value of the newline character sequence for `WRITE_LINE`, specified when a connection is opened. While such protocols use `<CR><LF>` to denote a new line, some implementations may choose to use just line-feed to denote a new line. In such cases, users can specify a different newline character sequence when a connection is opened.

This CRLF package variable is intended to be a constant that denotes the carriage-return line-feed character sequence. Do not modify its value. Modification may result in errors in other PL/SQL applications.

## Exceptions

The exceptions raised by the TCP/IP package are listed in [Table 165–2](#).

**Table 165–2 TCP/IP Exceptions**

Exception	Description
<code>BUFFER_TOO_SMALL</code>	Buffer is too small for input that requires look-ahead.
<code>END_OF_INPUT</code>	Raised when no more data is available to read from the connection.
<code>NETWORK_ERROR</code>	Generic network error.
<code>BAD_ARGUMENT</code>	Bad argument passed in an API call (for example, a negative buffer size).
<code>TRANSFER_TIMEOUT</code>	No data is read and a read time out occurred.
<code>PARTIAL_MULTIBYTE_CHAR</code>	No complete character is read and a partial multibyte character is found at the end of the input.



## Rules and Limits

The interface provided in the package only allows connections to be initiated by the PL/SQL program. It does not allow the PL/SQL program to accept connections initiated outside the program.

## Examples

The following code example illustrates how the TCP/IP package can be used to retrieve a Web page over HTTP. It connects to a Web server listening at port 80 (standard port for HTTP) and requests the root document.

```

DECLARE
 c utl_tcp.connection; -- TCP/IP connection to the Web server
 ret_val pls_integer;
BEGIN
 c := utl_tcp.open_connection(remote_host => 'www.acme.com',
 remote_port => 80,
 charset => 'US7ASCII'); -- open connection
 ret_val := utl_tcp.write_line(c, 'GET / HTTP/1.0'); -- send HTTP request
 ret_val := utl_tcp.write_line(c);
 BEGIN
 LOOP
 dbms_output.put_line(utl_tcp.get_line(c, TRUE)); -- read result
 END LOOP;
 EXCEPTION
 WHEN utl_tcp.end_of_input THEN
 NULL; -- end of input
 END;
 utl_tcp.close_connection(c);
END;

```

The following code example illustrates how the TCP/IP package can be used by an application to send e-mail (also known as email from PL/SQL). The application connects to an SMTP server at port 25 and sends a simple text message.

```

PROCEDURE send_mail (sender IN VARCHAR2,
 recipient IN VARCHAR2,
 message IN VARCHAR2)
IS
 mailhost VARCHAR2(30) := 'mailhost.mydomain.com';
 smtp_error EXCEPTION;
 mail_conn utl_tcp.connection;
 PROCEDURE smtp_command(command IN VARCHAR2,

```

```
 ok IN VARCHAR2 DEFAULT '250')
IS
 response varchar2(3);
 len pls_integer;
BEGIN
 len := utl_tcp.write_line(mail_conn, command);
 response := substr(utl_tcp.get_line(mail_conn), 1, 3);
 IF (response <> ok) THEN
 RAISE smtp_error;
 END IF;
END;

BEGIN
 mail_conn := utl_tcp.open_connection(remote_host => mailhost,
 remote_port => 25,
 charset => 'US7ASCII');

 smtp_command('HELO ' || mailhost);
 smtp_command('MAIL FROM: ' || sender);
 smtp_command('RCPT TO: ' || recipient);
 smtp_command('DATA', '354');
 smtp_command(message);
 smtp_command('QUIT', '221');
 utl_tcp.close_connection(mail_conn);
EXCEPTION
 WHEN OTHERS THEN
 -- Handle the error
END;
```

---

## Summary of UTL\_TCP Subprograms

**Table 165–3 UTL\_TCP Package Subprograms**

Subprogram	Description
<a href="#">AVAILABLE Function</a> on page 165-8	Determines the number of bytes available for reading from a TCP/IP connection
<a href="#">CLOSE_ALL_CONNECTIONS Procedure</a> on page 165-10	Closes all open TCP/IP connections
<a href="#">CLOSE_CONNECTION Procedure</a> on page 165-11	Closes an open TCP/IP connection
<a href="#">FLUSH Procedure</a> on page 165-12	Transmits all data in the output buffer, if a buffer is used, to the server immediately
<a href="#">GET_LINE Function</a> on page 165-13	Convenient forms of the read functions, which return the data read instead of the amount of data read
<a href="#">GET_RAW Function</a> on page 165-14	Convenient forms of the read functions, which return the data read instead of the amount of data read
<a href="#">GET_TEXT Function</a> on page 165-16	Convenient forms of the read functions, which return the data read instead of the amount of data read
<a href="#">OPEN_CONNECTION Function</a> on page 165-18	Opens a TCP/IP connection to a specified service
<a href="#">READ_LINE Function</a> on page 165-21	Receives a text line from a service on an open connection
<a href="#">READ_RAW Function</a> on page 165-23	Receives binary data from a service on an open connection
<a href="#">READ_TEXT Function</a> on page 165-25	Receives text data from a service on an open connection
<a href="#">WRITE_LINE Function</a> on page 165-27	Transmits a text line to a service on an open connection
<a href="#">WRITE_RAW Function</a> on page 165-28	Transmits a binary message to a service on an open connection
<a href="#">WRITE_TEXT Function</a> on page 165-29	Transmits a text message to a service on an open connection

## AVAILABLE Function

This function determines the number of bytes available for reading from a TCP/IP connection. It is the number of bytes that can be read immediately without blocking. Determines if data is ready to be read from the connection.

### Syntax

```
UTL_TCP.AVAILABLE (
 c IN OUT NOCOPY connection,
 timeout IN PLS_INTEGER DEFAULT 0)
RETURN num_bytes PLS_INTEGER;
```

### Parameters

**Table 165–4 AVAILABLE Function Parameters**

Parameter	Description
c	The TCP connection to determine the amount of data that is available to be read from.
timeout	A time in seconds to wait before giving up and reporting that no data is available. Zero (0) indicates not to wait at all. NULL indicates to wait forever.

### Return Values

**Table 165–5 AVAILABLE Function Return Values**

Parameter	Description
num_bytes	The number of bytes available for reading without blocking.

### Usage Notes

The connection must have already been opened through a call to `OPEN_CONNECTION`. Users may use this API to determine if data is available to be read before calling the read API so that the program will not be blocked because data is not ready to be read from the input.

The number of bytes available for reading returned by this function may be less than what is actually available. On some platforms, this function may only return 1, to indicate that some data is available. If you are concerned about the portability of

your application, assume that this function returns a positive value when data is available for reading, and 0 when no data is available. The following example illustrates using this function in a portable manner:

```
DECLARE
 c utl_tcp.connection
 data VARCHAR2(256);
 len PLS_INTEGER;
BEGIN
 c := utl_tcp.open_connection(...);
 LOOP
 IF (utl_tcp.available(c) > 0) THEN
 len := utl_tcp.read_text(c, data, 256);
 ELSE
 ---do some other things

 END IF
 END LOOP;
END;
```

## Related Functions

READ\_RAW, READ\_TEXT, READ\_LINE

## CLOSE\_ALL\_CONNECTIONS Procedure

This procedure closes all open TCP/IP connections.

### Syntax

```
UTL_TCP.CLOSE_ALL_CONNECTIONS;
```

### Usage Notes

This call is provided to close all connections before a PL/SQL program avoid dangling connections.

### Related Functions

```
OPEN_CONNECTION, CLOSE_CONNECTION.
```

## CLOSE\_CONNECTION Procedure

This procedure closes an open TCP/IP connection.

### Syntax

```
UTL_TCP.CLOSE_CONNECTION (
 c IN OUT NOCOPY connection);
```

### Parameters

**Table 165–6** *CLOSE\_CONNECTION Procedure Parameters*

Parameter	Description
c	The TCP connection to close.

### Usage Notes

Connection must have been opened by a previous call to `OPEN_CONNECTION`. The fields `remote_host`, `remote_port`, `local_host`, `local_port` and `charset` of `c` will be reset after the connection is closed.

An open connection must be closed explicitly. An open connection will remain open when the PL/SQL record variable that stores the connection goes out-of-scope in the PL/SQL program. Failing to close unwanted connections may result in unnecessary tying up of local and remote system resources.

## FLUSH Procedure

This procedure transmits all data in the output buffer, if a buffer is used, to the server immediately.

### Syntax

```
UTL_TCP.FLUSH (
 c IN OUT NOCOPY connection);
```

### Parameters

**Table 165–7 FLUSH Procedure Parameters**

Parameter	Description
c	The TCP connection to send data to.

### Usage Notes

The connection must have already been opened through a call to `OPEN_CONNECTION`.

### Related Functions

`WRITE_RAW`, `WRITE_TEXT`, `WRITE_LINE`



## GET\_LINE Function

This function returns the data read instead of the amount of data read.

### Syntax

```
UTL_TCP.GET_LINE (
 c IN OUT NOCOPY connection,
 remove_crlf IN BOOLEAN DEFAULT FALSE,
 peek IN BOOLEAN DEFAULT FALSE)
RETURN VARCHAR2;
```

### Parameters

**Table 165–8** *GET\_LINE Function Parameters*

Parameter	Description
c	The TCP connection to receive data from.
remove_crlf	If <code>TRUE</code> , the trailing CR/LF character(s) are removed from the received message.
peek	Normally, you want to read the data and remove it from the input queue, that is, consume it. In some situations, you may just want to look ahead at the data, that is, peek at it, without removing it from the input queue, so that it is still available for reading (or even peeking) in the next call. To keep the data in the input queue, set this flag to <code>TRUE</code> and set up an input buffer before the connection is opened. The amount of data you can peeked at (that is, read but keep in the input queue) must be less than the size of input buffer.

### Usage Notes

- The connection must have already been opened through a call to `OPEN_CONNECTION`.
- See `READ_LINE` for the read time out, character set conversion, buffer size, and multibyte character issues.

### Related Functions

`GET_RAW`, `GET_TEXT`, `READ_LINE`

## GET\_RAW Function

This function returns the data read instead of the amount of data read.

### Syntax

```
UTL_TCP.GET_RAW (
 c IN OUT NOCOPY connection,
 len IN PLS_INTEGER DEFAULT 1,
 peek IN BOOLEAN DEFAULT FALSE)
RETURN RAW;
```

### Parameters

**Table 165–9** GET\_RAW Function Parameters

Parameter	Description
c	The TCP connection to receive data from.
len	The number of bytes (or characters for VARCHAR2) of data to receive. Default is 1.
peek	Normally, you want to read the data and remove it from the input queue, that is, consume it. In some situations, you may just want to look ahead at the data, that is, peek at it, without removing it from the input queue, so that it is still available for reading (or even peeking) in the next call. To keep the data in the input queue, set this flag to TRUE and set up an input buffer before the connection is opened. The amount of data you can peeked at (that is, read but keep in the input queue) must be less than the size of input buffer.
remove_crlf	If TRUE, the trailing CR/LF character(s) are removed from the received message.

### Usage Notes

The connection must have already been opened through a call to OPEN\_CONNECTION.

For all the `get_*` APIs described in this section, see the corresponding `read_*` API for the read time out issue. For `GET_TEXT` and `GET_LINE`, see the corresponding `read_*` API for character set conversion, buffer size, and multibyte character issues.

## Related Functions

GET\_RAW, GET\_TEXT, READ\_RAW, READ\_TEXT, READ\_LINE

## GET\_TEXT Function

This function returns the data read instead of the amount of data read.

### Syntax

```
UTL_TCP.GET_TEXT (
 c IN OUT NOCOPY connection,
 len IN PLS_INTEGER DEFAULT 1,
 peek IN BOOLEAN DEFAULT FALSE)
RETURN VARCHAR2;
```

### Parameters

**Table 165–10** *GET\_TEXT Function Parameters*

Parameter	Description
c	The TCP connection to receive data from.
len	The number of bytes (or characters for VARCHAR2) of data to receive. Default is 1.
peek	Normally, you want to read the data and remove it from the input queue, that is, consume it. In some situations, you may just want to look ahead at the data, that is, peek at it, without removing it from the input queue, so that it is still available for reading (or even peeking) in the next call. To keep the data in the input queue, set this flag to TRUE and set up an input buffer before the connection is opened. The amount of data you can peeked at (that is, read but keep in the input queue) must be less than the size of input buffer.
remove_crlf	If TRUE, the trailing CR/LF character(s) are removed from the received message.

### Usage Notes

The connection must have already been opened through a call to OPEN\_CONNECTION.

For all the `get_*` APIs described in this section, see the corresponding `read_*` API for the read time out issue. For `GET_TEXT` and `GET_LINE`, see the corresponding `READ_*` API for character set conversion, buffer size, and multibyte character issues.

## Related Functions

READ\_RAW, READ\_TEXT, READ\_LINE

## OPEN\_CONNECTION Function

This function opens a TCP/IP connection to a specified service.

### Syntax

```
UTL_TCP.OPEN_CONNECTION (
 remote_host IN VARCHAR2,
 remote_port IN PLS_INTEGER,
 local_host IN VARCHAR2 DEFAULT NULL,
 local_port IN PLS_INTEGER DEFAULT NULL,
 in_buffer_size IN PLS_INTEGER DEFAULT NULL,
 out_buffer_size IN PLS_INTEGER DEFAULT NULL,
 charset IN VARCHAR2 DEFAULT NULL,
 newline IN VARCHAR2 DEFAULT CRLF,
 tx_timeout IN PLS_INTEGER DEFAULT NULL)
RETURN connection;
```

### Parameters

**Table 165–11** OPEN\_CONNECTION Function Parameters

Parameter	Description
remote_host	The name of the host providing the service. When remote_host is NULL, it connects to the local host.
remote_port	The port number on which the service is listening for connections.
local_host	The name of the host providing the service. NULL means don't care.
local_port	The port number on which the service is listening for connections. NULL means don't care.
in_buffer_size	The size of input buffer. The use of an input buffer can speed up execution performance in receiving data from the server. The appropriate size of the buffer depends on the flow of data between the client and the server, and the network condition. A 0 value means no buffer should be used. A NULL value means the caller does not care if a buffer is used or not. The maximum size of the input buffer is 32767 bytes.

**Table 165–11 (Cont.) OPEN\_CONNECTION Function Parameters**

Parameter	Description
<code>out_buffer_size</code>	The size of output buffer. The use of an output buffer can speed up execution performance in sending data to the server. The appropriate size of buffer depends on the flow of data between the client and the server, and the network condition. A 0 value means no buffer should be used. A NULL value means the caller does not care if a buffer is used or not. The maximum size of the output buffer is 32767 bytes.
<code>charset</code>	The on-the-wire character set. Since text messages in the database may be encoded in a character set that is different from the one expected on the wire (that is, the character set specified by the communication protocol, or the one stipulated by the other end of the communication), text messages in the database will be converted to and from the on-the-wire character set as they are sent and received on the network using <code>READ_TEXT</code> , <code>READ_LINE</code> , <code>WRITE_TEXT</code> and <code>WRITE_LINE</code> . Set this parameter to NULL when no conversion is needed.
<code>newline</code>	The newline character sequence. This newline character sequence is appended to the text line sent by <code>WRITE_LINE</code> API.
<code>tx_timeout</code>	A time in seconds that the <code>UTL_TCP</code> package should wait before giving up in a read or write operations in this connection. In read operations, this package gives up if no data is available for reading immediately. In write operations, this package gives up if the output buffer is full and no data is to be sent in the network without being blocked. Zero (0) indicates not to wait at all. NULL indicates to wait forever.

## Return Values

**Table 165–12 OPEN\_CONNECTION Function Return Values**

Parameter	Description
<code>connection</code>	A connection to the targeted TCP/IP service.

## Usage Notes

Note that connections opened by this `UTL_TCP` package can remain open and be passed from one database call to another in a shared server configuration. However, the connection must be closed explicitly. The connection will remain open when the PL/SQL record variable that stores the connection goes out-of-scope in the PL/SQL

program. Failing to close unwanted connections may result in unnecessary tying up of local and remote system resources.

In the current release of the `UTL_TCP` package, the parameters `local_host` and `local_port` are ignored when `open_connection` makes a TCP/IP connection. It does not attempt to use the specified local host and port number when the connection is made. The `local_host` and `local_port` fields will not be set in the connection record returned by the function.

Time out on write operations is not supported in the current release of the `UTL_TCP` package.

### Related Functions

`CLOSE_CONNECTION`, `CLOSE_ALL_CONNECTIONS`



## READ\_LINE Function

This function receives a text line from a service on an open connection. A line is terminated by a line-feed, a carriage-return or a carriage-return followed by a line-feed.

### Syntax

```
UTL_TCP.READ_LINE (
 c IN OUT NOCOPY connection,
 data IN OUT NOCOPY VARCHAR2 CHARACTER SET ANY_CS,
 peek IN BOOLEAN DEFAULT FALSE)
RETURN num_chars PLS_INTEGER;
```

### Parameters

**Table 165–13 READ\_LINE Function Parameters**

Parameter	Description
c	The TCP connection to receive data from.
data	The data received.
remove_crlf	If TRUE, the trailing CR/LF character(s) are removed from the received message.
peek	Normally, you want to read the data and remove it from the input queue, that is, consume it. In some situations, you may just want to look ahead at the data, that is, peek at it, without removing it from the input queue, so that it is still available for reading (or even peeking) in the next call. To keep the data in the input queue, set this flag to TRUE and set up an input buffer before the connection is opened. The amount of data you can peeked at (that is, read but keep in the input queue) must be less than the size of input buffer.

### Return Values

**Table 165–14 READ\_LINE Function Return Values**

Parameter	Description
num_chars	The actual number of characters of data received.

## Usage Notes

The connection must have already been opened through a call to `OPEN_CONNECTION`. This function does not return until the end-of-line have been reached, or the end of input has been reached. Text messages will be converted from the on-the-wire character set, specified when the connection was opened, to the database character set before they are returned to the caller.

If transfer time out is set when the connection is opened, this function waits for each data packet to be ready to read until time out occurs. If it occurs, this function stops reading and returns all the data read successfully. If no data is read successfully, the `transfer_timeout` exception is raised. The exception can be handled and the read operation can be retried later.

If a partial multibyte character is found at the end of input, this function stops reading and returns all the complete multibyte characters read successfully. If no complete character is read successfully, the `partial_multibyte_char` exception is raised. The exception can be handled and the bytes of that partial multibyte character can be read as binary by the `READ_RAW` function. If a partial multibyte character is seen in the middle of the input because the remaining bytes of the character have not arrived and read time out occurs, the `transfer_timeout` exception is raised instead. The exception can be handled and the read operation can be retried later.

## Related Functions

`READ_RAW`, `READ_TEXT`, `AVAILABLE`

## READ\_RAW Function

This function receives binary data from a service on an open connection.

### Syntax

```
UTL_TCP.READ_RAW (
 c IN OUT NOCOPY connection,
 data IN OUT NOCOPY RAW,
 len IN PLS_INTEGER DEFAULT 1,
 peek IN BOOLEAN DEFAULT FALSE)
RETURN num_bytes PLS_INTEGER;
```

### Parameters

**Table 165–15 READ\_RAW Function Parameters**

Parameter	Description
c	The TCP connection to receive data from.
data (IN OUT COPY)	The data received.
len	The number of bytes of data to receive.
peek	Normally, you want to read the data and remove it from the input queue, that is, consume it. In some situations, you may just want to look ahead at the data, that is, peek at it, without removing it from the input queue, so that it is still available for reading (or even peeking) in the next call. To keep the data in the input queue, set this flag to <code>TRUE</code> and set up an input buffer before the connection is opened. The amount of data you can peeked at (that is, read but keep in the input queue) must be less than the size of input buffer.

### Return Values

**Table 165–16 READ\_RAW Function Return Values**

Parameter	Description
num_bytes	The actual number of bytes of data received.

## Usage Notes

The connection must have already been opened through a call to `OPEN_CONNECTION`. This function does not return until the specified number of bytes have been read, or the end of input has been reached.

If `transfer_time_out` is set when the connection is opened, this function waits for each data packet to be ready to read until time out occurs. If it occurs, this function stops reading and returns all the data read successfully. If no data is read successfully, the `transfer_timeout` exception is raised. The exception can be handled and the read operation can be retried later.

## Related Functions

`READ_TEXT`, `READ_LINE`, `AVAILABLE`

## READ\_TEXT Function

This function receives text data from a service on an open connection.

### Syntax

```
UTL_TCP.READ_TEXT (
 c IN OUT NOCOPY connection,
 data IN OUT NOCOPY VARCHAR2 CHARACTER SET ANY_CS,
 len IN PLS_INTEGER DEFAULT 1,
 peek IN BOOLEAN DEFAULT FALSE)
RETURN num_chars PLS_INTEGER;
```

### Parameters

**Table 165–17 READ\_TEXT Function Parameters**

Parameter	Description
c	The TCP connection to receive data from.
data	The data received.
len	The number of characters of data to receive.
peek	Normally, users want to read the data and remove it from the input queue, that is, consume it. In some situations, users may just want to look ahead at the data without removing it from the input queue so that it is still available for reading (or even peeking) in the next call. To keep the data in the input queue, set this flag to <code>TRUE</code> and an input buffer must be set up when the connection is opened. The amount of data that you can peek at (that is, read but keep in the input queue) must be less than the size of input buffer.

### Return Values

**Table 165–18 READ\_TEXT Function Return Values**

Parameter	Description
num_chars	The actual number of characters of data received.

## Usage Notes

The connection must have already been opened through a call to `OPEN_CONNECTION`. This function does not return until the specified number of characters has been read, or the end of input has been reached. Text messages will be converted from the on-the-wire character set, specified when the connection was opened, to the database character set before they are returned to the caller.

Unless explicitly overridden, the size of a `VARCHAR2` buffer is specified in terms of bytes, while the parameter `len` refers to the maximum number of characters to be read. When the database character set is multibyte, where a single character may consist of more than 1 byte, you should ensure that the buffer can hold the maximum of characters. In general, the size of the `VARCHAR2` buffer should equal the number of characters to be read, multiplied by the maximum number of bytes of a character of the database character set.

If transfer time out is set when the connection is opened, this function waits for each data packet to be ready to read until time out occurs. If it occurs, this function stops reading and returns all the data read successfully. If no data is read successfully, the `transfer_timeout` exception is raised. The exception can be handled and the read operation can be retried later.

If a partial multibyte character is found at the end of input, this function stops reading and returns all the complete multibyte characters read successfully. If no complete character is read successfully, the `partial_multibyte_char` exception is raised. The exception can be handled and the bytes of that partial multibyte character can be read as binary by the `READ_RAW` function. If a partial multibyte character is seen in the middle of the input because the remaining bytes of the character have not arrived and read time out occurs, the `transfer_timeout` exception is raised instead. The exception can be handled and the read operation can be retried later.

## Related Functions

`READ_RAW`, `READ_LINE`, `AVAILABLE`

## WRITE\_LINE Function

This function transmits a text line to a service on an open connection. The newline character sequence will be appended to the message before it is transmitted.

### Syntax

```
UTL_TCP.WRITE_LINE (
 c IN OUT NOCOPY connection,
 data IN VARCHAR2 DEFAULT NULL CHARACTER SET ANY_CS)
RETURN PLS_INTEGER;
```

### Parameters

**Table 165–19** *WRITE\_LINE Function Parameters*

Parameter	Description
c	The TCP connection to send data to.
data	The buffer containing the data to be sent.

### Return Values

**Table 165–20** *WRITE\_LINE Function Return Values*

Parameter	Description
num_chars	The actual number of characters of data transmitted.

### Usage Notes

The connection must have already been opened through a call to `OPEN_CONNECTION`. Text messages will be converted to the on-the-wire character set, specified when the connection was opened, before they are transmitted on the wire.

### Related Functions

`WRITE_RAW`, `WRITE_TEXT`, `FLUSH`

## WRITE\_RAW Function

This function transmits a binary message to a service on an open connection. The function does not return until the specified number of bytes have been written.

### Syntax

```
UTL_TCP.WRITE_RAW (
 c IN OUT NOCOPY connection,
 data IN RAW,
 len IN PLS_INTEGER DEFAULT NULL)
RETURN num_bytes PLS_INTEGER;
```

### Parameters

**Table 165–21** *WRITE\_RAW Function Parameters*

Parameter	Description
c	The TCP connection to send data to.
data	The buffer containing the data to be sent.
len	The number of bytes of data to transmit. When len is NULL, the whole length of data is written.

### Return Values

**Table 165–22** *WRITE\_RAW Function Return Values*

Parameter	Description
num_bytes	The actual number of bytes of data transmitted.

### Usage Notes

The connection must have already been opened through a call to `OPEN_CONNECTION`.

### Related Functions

`WRITE_TEXT`, `WRITE_LINE`, `FLUSH`



## WRITE\_TEXT Function

This function transmits a text message to a service on an open connection.

### Syntax

```
UTL_TCP.WRITE_TEXT (
 c IN OUT NOCOPY connection,
 data IN VARCHAR2 CHARACTER SET ANY_CS,
 len IN PLS_INTEGER DEFAULT NULL)
RETURN num_chars PLS_INTEGER;
```

### Parameters

**Table 165–23** *WRITE\_TEXT Function Parameters*

Parameter	Description
c	The TCP connection to send data to.
data	The buffer containing the data to be sent.
len	The number of characters of data to transmit. When len is NULL, the whole length of data is written. The actual amount of data written may be less because of network condition.

### Return Values

**Table 165–24** *WRITE\_TEXT Function Return Values*

Parameter	Description
num_chars	The actual number of characters of data transmitted.

### Usage Notes

The connection must have already been opened through a call to OPEN\_CONNECTION. Text messages will be converted to the on-the-wire character set, specified when the connection was opened, before they are transmitted on the wire.

### Related Functions

WRITE\_RAW, WRITE\_LINE, FLUSH



The UTL\_URL package has two functions: ESCAPE and UNESCAPE.

**See Also:** [Chapter 156, "UTL\\_HTTP"](#)

This chapter contains the following topics:

- [Using UTL\\_URL](#)
  - [Overview](#)
  - [Exceptions](#)
  - [Examples](#)
- [Summary of UTL\\_URL Subprograms](#)

## Using UTL\_URL

- [Overview](#)
- [Exceptions](#)
- [Examples](#)

### Overview

A Uniform Resource Locator (URL) is a string that identifies a Web resource, such as a page or a picture. Use a URL to access such resources by way of the HyperText Transfer Protocol (HTTP). For example, the URL for Oracle's Web site is:

```
http://www.oracle.com
```

Normally, a URL contains English alphabetic characters, digits, and punctuation symbols. These characters are known as the *unreserved characters*. Any other characters in URLs, including multibyte characters or binary octet codes, must be escaped to be accurately processed by Web browsers or Web servers. Some punctuation characters, such as dollar sign (\$), question mark (?), colon (:), and equals sign (=), are reserved as delimiters in a URL. They are known as the *reserved characters*. To literally process these characters, instead of treating them as delimiters, they must be escaped.

The unreserved characters are:

- A through Z, a through z, and 0 through 9
- Hyphen (-), underscore (\_), period (.), exclamation point (!), tilde (~), asterisk (\*), accent ('), left parenthesis ( ( ), right parenthesis ( ) )

The reserved characters are:

- Semi-colon (;) slash (/), question mark (?), colon (:), at sign (@), ampersand (&), equals sign (=), plus sign (+), dollar sign (\$), and comma (,)

The UTL\_URL package has two functions that provide escape and unescape mechanisms for URL characters. Use the escape function to escape a URL before the URL is used fetch a Web page by way of the UTL\_HTTP package. Use the unescape function to unescape an escaped URL before information is extracted from the URL.

For more information, refer to the Request For Comments (RFC) document RFC2396. Note that this URL escape and unescape mechanism is different from the

x-www-form-urlencoded encoding mechanism described in the HTML specification:

`http://www.w3.org/TR/html`

## Exceptions

[Table 166–1](#) lists the exceptions that can be raised when the UTL\_URL package API is invoked.

**Table 166–1 UTL\_URL Exceptions**

Exception	Error Code	Reason
BAD_URL	29262	The URL contains badly formed escape code sequences
BAD_FIXED_WIDTH_CHARSET	29274	Fixed-width multibyte character set is not allowed as a URL character set.

## Examples

You can implement the x-www-form-urlencoded encoding using the UTL\_URL.ESCAPE function as follows:

```
CREATE OR REPLACE FUNCTION form_url_encode (
 data IN VARCHAR2,
 charset IN VARCHAR2) RETURN VARCHAR2 AS
BEGIN
 RETURN utl_url.escape(data, TRUE, charset); -- note use of TRUE
END;
```

For decoding data encoded with the form-URL-encode scheme, the following function implements the decoding scheme:

```
CREATE OR REPLACE FUNCTION form_url_decode(
 data IN VARCHAR2,
 charset IN VARCHAR2) RETURN VARCHAR2 AS
BEGIN
 RETURN utl_url.unescape(
 replace(data, '+', ' '),
 charset);
END;
```

---

## Summary of UTL\_URL Subprograms

**Table 166–2 UTL\_URL Package Subprograms**

Subprogram	Description
<a href="#">ESCAPE Function</a> on page 166-5	Returns a URL with illegal characters (and optionally reserved characters) escaped using the %2-digit-hex-code format
<a href="#">UNESCAPE Function</a> on page 166-7	Unescapes the escape character sequences to their original forms in a URL. Convert the %xx escape character sequences to the original characters

## ESCAPE Function

This function returns a URL with illegal characters (and optionally reserved characters) escaped using the %2-digit-hex-code format.

### Syntax

```
UTL_URL.ESCAPE (
 url IN VARCHAR2 CHARACTER SET ANY_CS,
 escape_reserved_chars IN BOOLEAN DEFAULT FALSE,
 url_charset IN VARCHAR2 DEFAULT utl_http.body_charset)
RETURN VARCHAR2;
```

### Parameters

**Table 166–3 ESCAPE Function Parameters**

Parameter	Description
url	The original URL
escape_reserved_chars	Indicates whether the URL reserved characters should be escaped. If set to TRUE, both the reserved and illegal URL characters are escaped. Otherwise, only the illegal URL characters are escaped. The default value is FALSE.
url_charset	When escaping a character (single-byte or multibyte), determine the target character set that character should be converted to before the character is escaped in %hex-code format. If url_charset is NULL, the database charset is assumed and no character set conversion will occur. The default value is the current default body character set of the UTL_HTTP package, whose default value is ISO-8859-1. The character set can be named in Internet Assigned Numbers Authority (IANA) or in the Oracle naming convention.

### Usage Notes

Use this function to escape URLs that contain illegal characters as defined in the URL specification RFC 2396. The legal characters in URLs are:

- A through Z, a through z, and 0 through 9
- Hyphen (-), underscore (\_), period (.), exclamation point (!), tilde (~), asterisk (\*), accent ('), left parenthesis ( ( ), right parenthesis ( ) )

The reserved characters consist of:

- Semi-colon (;) slash (/), question mark (?), colon (:), at sign (@), ampersand (&), equals sign (=), plus sign (+), dollar sign (\$), and comma (,)

Many of the reserved characters are used as delimiters in the URL. You should escape characters beyond those listed here by using `escape_url`. Also, to use the reserved characters in the name-value pairs of the query string of a URL, those characters must be escaped separately. An `escape_url` cannot recognize the need to escape those characters because once inside a URL, those characters become indistinguishable from the actual delimiters. For example, to pass a name-value pair `$logon=scott/tiger` into the query string of a URL, escape the `$` and `/` separately as `%24logon=scott%2Ftiger` and use it in the URL.

Normally, you will escape the entire URL, which contains the reserved characters (delimiters) that should not be escaped. For example:

```
utl_url.escape('http://www.acme.com/a url with space.html')
```

Returns:

```
http://foo.com/a%20url%20with%20space.html
```

In other situations, you may want to send a query string with a value that contains reserved characters. In that case, escape only the value fully (with `escape_reserved_chars` set to `TRUE`) and then concatenate it with the rest of the URL. For example:

```
url := 'http://www.acme.com/search?check=' || utl_url.escape
('Is the use of the "$" sign okay?', TRUE);
```

This expression escapes the question mark (?), dollar sign (\$), and space characters in 'Is the use of the "\$" sign okay?' but not the ? after search in the URL that denotes the use of a query string.

The Web server that you intend to fetch Web pages from may use a character set that is different from that of your database. In that case, specify the `url_charset` as the Web server character set so that the characters that need to be escaped are escaped in the target character set. For example, a user of an EBCDIC database who wants to access an ASCII Web server should escape the URL using `US7ASCII` so that a space is escaped as `%20` (hex code of a space in ASCII) instead of `%40` (hex code of a space in EBCDIC).

This function does not validate a URL for the proper URL format.



## UNESCAPE Function

This function unescapes the escape character sequences to its original form in a URL, to convert the %XX escape character sequences to the original characters.

### Syntax

```
UTL_URL.UNESCAPE (
 url IN VARCHAR2 CHARACTER SET ANY_CS,
 url_charset IN VARCHAR2 DEFAULT utl_http.body_charset)
RETURN VARCHAR2;
```

### Parameters

**Table 166–4 UNESCAPE Function Parameters**

Parameter	Description
url	The URL to unescape
url_charset	After a character is unescaped, the character is assumed to be in the <code>source_charset</code> character set and it will be converted from the <code>source_charset</code> to the database character set before the URL is returned. If <code>source_charset</code> is <code>NULL</code> , the database charset is assumed and no character set conversion occurred. The default value is the current default body character set of the <code>UTL_HTTP</code> package, whose default value is "ISO-8859-1". The character set can be named in Internet Assigned Numbers Authority (IANA) or Oracle naming convention.

### Usage Notes

The Web server that you receive the URL from may use a character set that is different from that of your database. In that case, specify the `url_charset` as the Web server character set so that the characters that need to be unescaped are unescaped in the source character set. For example, a user of an EBCDIC database who receives a URL from an ASCII Web server should unescape the URL using `US7ASCII` so that %20 is unescaped as a space (0x20 is the hex code of a space in ASCII) instead of a ? (because 0x20 is not a valid character in EBCDIC).

This function does not validate a URL for the proper URL format.



The `WPG_DOCLOAD` package provides an interface to download files, BLOBs and BFILES.

**See Also:** For more information about implementation of this package:

- *Oracle HTTP Server Administrator's Guide*
- *Oracle HTTP Server mod\_plsql User's Guide*

The chapter contains the following topics:

- [Using WPG\\_DOCLOAD](#)
  - [Constants](#)
- [Summary of WPG\\_DOCLOAD Subprograms](#)

---

## Using WPG\_DOCLOAD

- [Constants](#)

### Constants

- [NAME\\_COL\\_LEN](#)
- [MIMET\\_COL\\_LEN](#)
- [MAX\\_DOCTABLE\\_NAME\\_LEN](#)

#### NAME\_COL\_LEN

The `NAME` column in your document table must be the same as the value of `name_col_len`.

```
name_col_len CONSTANT pls_integer := 64;
```

#### MIMET\_COL\_LEN

The `MIME_TYPE` column in your document table must be the same as the value of `mimet_col_len`.

```
mimet_col_len CONSTANT pls_integer := 48;
```

#### MAX\_DOCTABLE\_NAME\_LEN

The name length of your document table must be less than `max_doctable_name_len`.

```
max_doctable_name_len CONSTANT pls_integer := 256;
```

---

## Summary of WPG\_DOCLOAD Subprograms

*Table 167-1 WPG\_DOCLOAD Package Subprograms*

<b>Subprogram</b>	<b>Description</b>
<a href="#">DOWNLOAD_FILE Procedures</a> on page 167-4	Downloads files, BLOBS and BFILES

---

## DOWNLOAD\_FILE Procedures

There are three versions of this procedure:

- The first version downloads files and is invoked from within a document download procedure to signal the PL/SQL Gateway that `p_filename` is to be downloaded from the document table to the client's browser.
- The second version can be called from within any procedure to signal the PL/SQL Gateway that `p_blob` is to be downloaded to the client's browser.
- The third version can be called from within any procedure to signal the PL/SQL Gateway that `p_bfile` is to be downloaded to the client's browser.

### Syntax

```
WPG_DOCLOAD.DOWNLOAD_FILE(
 p_filename IN VARCHAR2,
 p_bcaching IN BOOLEAN DEFAULT TRUE);
```

```
WPG_DOCLOAD.DOWNLOAD_FILE(
 p_blob IN OUT NOCOPY BLOB);
```

```
WPG_DOCLOAD.DOWNLOAD_FILE(
 p_bfile IN OUT BFILE);
```

### Parameters

**Table 167–2** *DOWNLOAD\_FILE Procedure Parameters*

Parameter	Description
<code>p_filename</code>	The file to download from the document table.
<code>p_blob</code>	The BLOB to download.
<code>p_bfile</code>	The BFILE to download (see <a href="#">Usage Notes</a> ).
<code>p_bcaching</code>	Whether browser caching is enabled (see <a href="#">Usage Notes</a> ).

### Usage Notes

- Normally, a document will be downloaded to the browser unless the browser sends an 'If-Modified-Since' header to the gateway indicating that it has the requested document in its cache. In that case, the gateway will determine if the

browser's cached copy is up to date, and if it is, it will send an HTTP 304 status message to the browser indicating that the browser should display the cached copy. However, because a document URL and a document do not necessarily have a one-to-one relationship in the PL/SQL Web Gateway, in some cases it may be undesirable to have the cached copy of a document displayed. In those cases, the `p_bcaching` parameter should be set to `FALSE` to indicate to the gateway to ignore the 'If-Modified-Since' header, and download the document.

- `p_bfile` and `p_blob` are declared as `IN OUT` because the locator is initially opened to check for file accessibility and existence. The open operation can only be performed if the locator is writable and readable.





---

## ANYDATA TYPE

An `ANYDATA TYPE` contains an instance of a given type, plus a description of the type. In this sense, an `ANYDATA` is self-describing. An `ANYDATA` can be persistently stored in the database.

This chapter contains the following topics:

- [Using ANYDATA TYPE](#)
  - [Restrictions](#)
  - [Operational Notes](#)
- [Summary of ANYDATA Subprograms](#)

## Using ANYDATA TYPE

---

### Restrictions

Persistent storage of ANYDATA instances whose type contains embedded LOBs other than BFILES is not currently supported.

### Operational Notes

- [Construction](#)
- [Access](#)

### Construction

There are 2 ways to construct an ANYDATA. The CONVERT\* calls enable construction of the ANYDATA in its entirety with a single call. They serve as explicit CAST functions from any type in the Oracle ORDBMS to ANYDATA.

```
STATIC FUNCTION ConvertBDouble(dbl IN BINARY_DOUBLE) return ANYDATA,
STATIC FUNCTION ConvertBfile(b IN BFILE) RETURN ANYDATA,
STATIC FUNCTION ConvertBFloat(fl IN BINARY_FLOAT) return ANYDATA,
STATIC FUNCTION ConvertBlob(b IN BLOB) RETURN ANYDATA,
STATIC FUNCTION ConvertChar(c IN CHAR) RETURN ANYDATA,
STATIC FUNCTION ConvertClob(c IN CLOB) RETURN ANYDATA,
STATIC FUNCTION ConvertCollection(col IN "collection_type") RETURN ANYDATA,
STATIC FUNCTION ConvertDate(dat IN DATE) RETURN ANYDATA,
STATIC FUNCTION ConvertIntervalDS(inv IN INTERVAL DAY TO SECOND) return ANYDATA,
STATIC FUNCTION ConvertIntervalYM(inv IN INTERVAL YEAR TO MONTH) return ANYDATA,
STATIC FUNCTION ConvertNchar(nc IN NCHAR) return ANYDATA,
STATIC FUNCTION ConvertNClob(nc IN NCLOB) return ANYDATA,
STATIC FUNCTION ConvertNumber(num IN NUMBER) RETURN ANYDATA,
STATIC FUNCTION ConvertNVarchar2(nc IN NVARCHAR2) return ANYDATA,
STATIC FUNCTION ConvertObject(obj IN "<object_type>") RETURN ANYDATA,
STATIC FUNCTION ConvertRaw(r IN RAW) RETURN ANYDATA,
STATIC FUNCTION ConvertRef(rf IN REF "<object_type>") RETURN ANYDATA,
STATIC FUNCTION ConvertTimestamp(ts IN TIMESTAMP) return ANYDATA,
STATIC FUNCTION ConvertTimestampTZ(ts IN TIMESTAMP WITH TIMEZONE) return
ANYDATA,
STATIC FUNCTION ConvertTimestampLTZ(ts IN TIMESTAMP WITH LOCAL TIMEZONE) return
ANYDATA,
```

```

STATIC FUNCTION ConvertUrowid(rid IN UROWID) return ANYDATA,
STATIC FUNCTION ConvertVarchar(c IN VARCHAR) RETURN ANYDATA,
STATIC FUNCTION ConvertVarchar2(c IN VARCHAR2) RETURN ANYDATA,

```

The second way to construct an ANYDATA is a piece by piece approach. The [BEGINCREATE Static Procedure](#) call begins the construction process and [ENDCREATE Member Procedure](#) call finishes the construction process. In between these two calls, the individual attributes of an object type or the elements of a collection can be set using SET\* calls. For piece by piece access of the attributes of objects and elements of collections, the [PIECEWISE Member Procedure](#) should be invoked prior to GET\* calls.

Note: The ANYDATA has to be constructed or accessed sequentially starting from its first attribute (or collection element). The BEGINCREATE call automatically begins the construction in a piece-wise mode. There is no need to call PIECEWISE immediately after BEGINCREATE. ENDCREATE should be called to finish the construction process (before which any access calls can be made).

## Access

Access functions are available based on SQL. These functions do not throw exceptions on type-mismatch. Instead, they return NULL if the type of the ANYDATA does not correspond to the type of access. If you wish to use only ANYDATA functions of the appropriate types returned in a query, you should use a WHERE clause which uses GETTYPENAME and choose the type you are interested in (say "SYS.NUMBER"). Each of these functions returns the value of a specified datatype inside a SYS . ANYDATA wrapper.

```

MEMBER FUNCTION AccessBDouble(self IN ANYDATA) return BINARY_DOUBLE
 DETERMINISTIC,
MEMBER FUNCTION AccessBfile(self IN ANYDATA) return BFILE,
MEMBER FUNCTION AccessBFloat(self IN ANYDATA) return BINARY_FLOAT
 DETERMINISTIC,
MEMBER FUNCTION AccessBlob(self IN ANYDATA) return BLOB,
MEMBER FUNCTION AccessChar(self IN ANYDATA) return CHAR,
MEMBER FUNCTION AccessClob(self IN ANYDATA) return CLOB,
MEMBER FUNCTION AccessDate(self IN ANYDATA) return DATE,
MEMBER FUNCTION AccessIntervalYM(self IN ANYDATA) return INTERVAL YEAR TO MONTH,
MEMBER FUNCTION AccessIntervalDS(self IN ANYDATA) return INTERVAL DAY TO SECOND,
MEMBER FUNCTION AccessNchar(self IN ANYDATA) return NCHAR,
MEMBER FUNCTION AccessNClob(self IN ANYDATA) return NCLOB
MEMBER FUNCTION AccessNumber(self IN ANYDATA) return NUMBER,
MEMBER FUNCTION AccessNvarchar2(self IN ANYDATA) return NVARCHAR2,
MEMBER FUNCTION AccessRaw(self IN ANYDATA) return RAW,

```

```
MEMBER FUNCTION AccessTimestamp(self IN ANYDATA) return TIMESTAMP,
MEMBER FUNCTION AccessTimestampLTZ(self IN ANYDATA) return TIMESTAMP WITH LOCAL
 TIMEZONE,
MEMBER FUNCTION AccessTimestampTZ(self IN ANYDATA) return TIMESTAMP WITH
 TIMEZONE,
MEMBER FUNCTION AccessUrowid(self IN ANYDATA) return UROWID DETERMINISTIC
MEMBER FUNCTION AccessVarchar(self IN ANYDATA) return VARCHAR,
MEMBER FUNCTION AccessVarchar2(self IN ANYDATA) return VARCHAR2,
```

---

## Summary of ANYDATA Subprograms

**Table 168–1 ANYDATA Type Subprograms**

Subprogram	Description
<a href="#">BEGINCREATE Static Procedure</a> on page 168-6	Begins creation process on a new ANYDATA
<a href="#">ENDCREATE Member Procedure</a> on page 168-7	Ends creation of an ANYDATA
<a href="#">GET* Member Functions</a> on page 168-8	Gets the current data value (which should be of appropriate type)
<a href="#">GETTYPE Member Function</a> on page 168-12	Gets the Type of the ANYDATA
<a href="#">GETTYPENAME Member Function</a> on page 168-13	Get the fully qualified type name for the ANYDATA
<a href="#">PIECEWISE Member Procedure</a> on page 168-14	Sets the MODE of access of the current data value to be an attribute at a time (if the data value is of TYPECODE_OBJECT)
<a href="#">SET* Member Procedures</a> on page 168-15	Sets the current data value.

## BEGINCREATE Static Procedure

This procedure begins the creation process on a new ANYDATA.

### Syntax

```
STATIC PROCEDURE BeginCreate(
 dtype IN OUT NOCOPY AnyType,
 adata OUT NOCOPY ANYDATA);
```

### Parameters

**Table 168–2** *BEGINCREATE Procedure Parameters*

Parameter	Description
dtype	The type of the ANYDATA. (Should correspond to OCI_TYPECODE_OBJECT or a Collection typecode.)
adata	ANYDATA being constructed.

### Exception

DBMS\_TYPES.INVALID\_PARAMETERS: dtype is invalid (not fully constructed, and similar deficits.)

### Usage Notes

There is no need to call `PIECEWISE` immediately after this call. The construction process begins in a piece-wise manner automatically.

## ENDCREATE Member Procedure

This procedure ends creation of an ANYDATA. Other creation functions cannot be called after this call.

### Syntax

```
MEMBER PROCEDURE EndCreate(
 self IN OUT NOCOPY ANYDATA);
```

### Parameters

**Table 168–3** *ENDCREATE Procedure Parameter*

Parameter	Description
self	An ANYDATA.

## GET\* Member Functions

These functions get the current data value (which should be of appropriate type).

The type of the current data value depends on the MODE with which we are accessing (depending on whether we have invoked the PIECEWISE call).

If PIECEWISE has NOT been called, we are accessing the ANYDATA in its entirety and the type of the data value should match the type of the ANYDATA.

If PIECEWISE has been called, we are accessing the ANYDATA piece-wise. The type of the data value should match the type of the attribute (or collection element) at the current position.

### Syntax

```
MEMBER FUNCTION GetBDouble(
 self IN ANYDATA,
 dbl OUT NOCOPY BINARY_DOUBLE)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetBfile(
 self IN ANYDATA,
 b OUT NOCOPY BFILE)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetBFloat(
 self IN ANYDATA,
 fl OUT NOCOPY BINARY_FLOAT)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetBlob(
 self IN ANYDATA,
 b OUT NOCOPY BLOB)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetChar(
 self IN ANYDATA,
 c OUT NOCOPY CHAR)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetClob(
 self IN ANYDATA,
 c OUT NOCOPY CLOB)
RETURN PLS_INTEGER;
```



```
MEMBER FUNCTION GetCollection(
 self IN ANYDATA,
 col OUT NOCOPY "<collection_type>")
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetDate(
 self IN ANYDATA,
 dat OUT NOCOPY DATE)
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetIntervalsD(
 self IN ANYDATA,
 inv OUT NOCOPY INTERVAL DAY TO SECOND)
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetIntervalYM(
 self IN ANYDATA,
 inv OUT NOCOPY INTERVAL YEAR TO MONTH)
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetNchar(
 self IN ANYDATA,
 nc OUT NOCOPY NCHAR)
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetNClob(
 self IN ANYDATA,
 nc OUT NOCOPY NCLOB)
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetNumber(
 self IN ANYDATA,
 num OUT NOCOPY NUMBER)
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetNVarchar2(
 self IN ANYDATA,
 nc OUT NOCOPY NVARCHAR2)
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GetObject(
 self IN ANYDATA,
 obj OUT NOCOPY "<object_type>")
 RETURN PLS_INTEGER;
```

```

MEMBER FUNCTION GetRaw(
 self IN ANYDATA,
 r OUT NOCOPY RAW)
RETURN PLS_INTEGER;

MEMBER FUNCTION GetRef(
 self IN ANYDATA,
 rf OUT NOCOPY REF "<object_type>")
RETURN PLS_INTEGER;

MEMBER FUNCTION GetTimestamp(
 self IN ANYDATA,
 ts OUT NOCOPY TIMESTAMP)
RETURN PLS_INTEGER;

MEMBER FUNCTION GetTimestampTZ(
 self IN ANYDATA,
 ts OUT NOCOPY TIMESTAMP WITH TIME ZONE)
RETURN PLS_INTEGER;

MEMBER FUNCTION GetTimestampLTZ(
 self IN ANYDATA,
 ts OUT NOCOPY TIMESTAMP WITH LOCAL TIME ZONE)
RETURN PLS_INTEGER;

MEMBER FUNCTION GetVarchar(
 self IN ANYDATA,
 c OUT NOCOPY VARCHAR)
RETURN PLS_INTEGER;

MEMBER FUNCTION GetVarchar2(
 self IN ANYDATA,
 c OUT NOCOPY VARCHAR2)
RETURN PLS_INTEGER;

```

## Parameters

**Table 168–4** GET\* Function Parameter

Parameter	Description
self	An ANYDATA.
num	The number to be obtained.

## Return Values

DBMS\_TYPES.SUCCESS or DBMS\_TYPES.NO\_DATA

The return value is relevant only if `PIECEWISE` has been already called (for a collection). In such a case, `DBMS_TYPES.NO_DATA` signifies the end of the collection when all elements have been accessed.

## Exceptions

`DBMS_TYPES.TYPE_MISMATCH`: When the expected type is different from the passed in type.

`DBMS_TYPES.INVALID_PARAMETERS`: Invalid Parameters (if it is not appropriate to add a number at this point in the creation process).

`DBMS_TYPES.INCORRECT_USAGE`: Incorrect usage.

## GETTYPE Member Function

This function gets the typecode of the ANYDATA.

### Syntax

```
MEMBER FUNCTION GETTYPE(
 self IN ANYDATA,
 typ OUT NOCOPY AnyType)
RETURN PLS_INTEGER;
```

### Parameters

**Table 168–5** *GETTYPE Function Parameter*

Parameter	Description
self	An ANYDATA.
typ	The AnyType corresponding to the ANYDATA. May be NULL if it does not represent a user-defined type.

### Return Values

The typecode corresponding to the type of the ANYDATA.

## GETYPENAME Member Function

This function gets the fully qualified type name for the ANYDATA.

If the ANYDATA is based on a built-in type, this function will return NUMBER and other relevant information.

If it is based on a user defined type, this function will return *schema\_name.type\_name*, for example, SCOTT.FOO.

If it is based on a transient anonymous type, this function will return NULL.

### Syntax

```
MEMBER FUNCTION GETYPENAME(
 self IN ANYDATA)
 RETURN VARCHAR2;
```

### Parameters

**Table 168–6** GETYPENAME Function Parameter

Parameter	Description
self	An ANYDATA.

### Return Values

Type name of the ANYDATA.

## PIECEWISE Member Procedure

This procedure sets the **MODE** of access of the current data value to be an attribute at a time (if the data value is of `TYPECODE_OBJECT`).

It sets the **MODE** of access of the data value to be a collection element at a time (if the data value is of collection type). Once this call has been made, subsequent calls to `SET*` and `GET*` will sequentially obtain individual attributes or collection elements.

### Syntax

```
MEMBER PROCEDURE PIECEWISE(
 self IN OUT NOCOPY ANYDATA);
```

### Parameters

**Table 168–7** *PIECEWISE Procedure Parameters*

Parameter	Description
<code>self</code>	The current data value.

### Exceptions

- `DBMS_TYPES.INVALID_PARAMETERS`
- `DBMS_TYPES.INCORRECT_USAGE`: On incorrect usage.

### Usage Notes

The current data value must be of an `OBJECT` or `COLLECTION` type before this call can be made.

Piece-wise construction and access of nested attributes that are of object or collection types is not supported.

## SET\* Member Procedures

Sets the current data value.

This is a list of procedures that should be called depending on the type of the current data value. The type of the data value should be the type of the attribute at the current position during the piece-wise construction process.

### Syntax

```
MEMBER PROCEDURE SETBDOUBLE(
 self IN OUT NOCOPY ANYDATA,
 dbl IN BINARY_DOUBLE,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETBFILE(
 self IN OUT NOCOPY ANYDATA,
 b IN BFILE,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETBFLOAT(
 self IN OUT NOCOPY ANYDATA,
 fl IN BINARY_FLOAT,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETBLOB(
 self IN OUT NOCOPY ANYDATA,
 b IN BLOB,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETCHAR(
 self IN OUT NOCOPY ANYDATA,
 c IN CHAR,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETCLOB(
 self IN OUT NOCOPY ANYDATA,
 c IN CLOB,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETCOLLECTION(
 self IN OUT NOCOPY ANYDATA,
 col IN "<collection_type>",
 last_elem IN boolean DEFAULT FALSE);
```

```
MEMBER PROCEDURE SETDATE(
 self IN OUT NOCOPY ANYDATA,
 dat IN DATE,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETINTERVALDS(
 self IN OUT NOCOPY ANYDATA,
 inv IN INTERVAL DAY TO SECOND,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETINTERVALYM(
 self IN OUT NOCOPY ANYDATA,
 inv IN INTERVAL YEAR TO MONTH,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETNCHAR(
 self IN OUT NOCOPY ANYDATA,
 nc IN NCHAR,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETNCLOB(
 self IN OUT NOCOPY ANYDATA,
 nc IN NClob,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETNUMBER(
 self IN OUT NOCOPY ANYDATA,
 num IN NUMBER,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETNVARCHAR2(
 self IN OUT NOCOPY ANYDATA,
 nc IN NVARCHAR2,
 last_elem IN boolean DEFAULT FALSE),

MEMBER PROCEDURE SETOBJECT(
 self IN OUT NOCOPY ANYDATA,
 obj IN "<object_type>",
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETRAW(
 self IN OUT NOCOPY ANYDATA,
 r IN RAW,
 last_elem IN boolean DEFAULT FALSE);
```



```

MEMBER PROCEDURE SETREF(
 self IN OUT NOCOPY ANYDATA,
 rf IN REF "<object_type>",
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETTIMESTAMP(
 self IN OUT NOCOPY ANYDATA,
 ts IN TIMESTAMP,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETTIMESTAMPtz(self IN OUT NOCOPY ANYDATA,
 ts IN TIMESTAMP WITH TIME ZONE,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETTIMESTAMPtz(
 self IN OUT NOCOPY ANYDATA,
 ts IN TIMESTAMP WITH LOCAL TIME ZONE,
 last_elem IN boolean DEFAULT FALSE),

MEMBER PROCEDURE SETVARIABLE(
 self IN OUT NOCOPY ANYDATA,
 c IN VARCHAR,
 last_elem IN boolean DEFAULT FALSE);

MEMBER PROCEDURE SETVARIABLE2(
 self IN OUT NOCOPY ANYDATA,
 c IN VARCHAR2,
 last_elem IN boolean DEFAULT FALSE);

```

## Parameters

**Table 168–8 SET\* Procedure Parameters**

Parameter	Description
self	An ANYDATA.
num	The number, and associated information, that is to be set.
last_elem	Relevant only if ANYDATA represents a collection. Set to TRUE if it is the last element of the collection, FALSE otherwise.

## Exceptions

- `DBMS_TYPES.INVALID_PARAMETERS`: Invalid Parameters (if it is not appropriate to add a number at this point in the creation process).
- `DBMS_TYPES.INCORRECT_USAGE`: Incorrect usage.
- `DBMS_TYPES.TYPE_MISMATCH`: When the expected type is different from the passed in type.

## Usage Notes

When `BEGINCREATE` is called, construction has already begun in a piece-wise fashion. Subsequent calls to `SET*` will set the successive attribute values.

If the `ANYDATA` is a standalone collection, the `SET*` call will set the successive collection elements.

---

## ANYDATASET TYPE

An `ANYDATASET TYPE` contains a description of a given type plus a set of data instances of that type. An `ANYDATASET` can be persistently stored in the database if desired, or it can be used as interface parameters to communicate self-descriptive sets of data, all of which belong to a certain type.

This chapter contains the following topics:

- [Construction](#)
- [Summary of ANYDATASET TYPE Subprograms](#)

---

## Construction

The `ANYDATASET` needs to be constructed value by value, sequentially.

For each data instance (of the type of the `ANYDATASET`), the `ADDINSTANCE` function must be invoked. This adds a new data instance to the `ANYDATASET`. Subsequently, `SET*` can be called to set each value in its entirety.

The `MODE` of construction/access can be changed to attribute/collection element wise by making calls to `PIECEWISE`.

- If the type of the `ANYDATASET` is `TYPECODE_OBJECT`, individual attributes will be set with subsequent `SET*` calls. Likewise on access.
- If the type of the current data value is a collection type individual collection elements will be set with subsequent `SET*` calls. Likewise on access. This call is very similar to `ANYDATA.PIECEWISE` call defined for the type `ANYDATA`.

Note that there is no support for piece-wise construction and access of nested (not top level) attributes that are of object types or collection types.

`ENDCREATE` should be called to finish the construction process (before which no access calls can be made).

---

## Summary of ANYDATASET TYPE Subprograms

**Table 169–1 ANYDATASET Type Subprograms**

Subprogram	Description
<a href="#">ADDINSTANCE Member Procedure</a> on page 169-4	Adds a new data instance to an ANYDATASET.
<a href="#">BEGINCREATE Static Procedure</a> on page 169-5	Creates a new ANYDATASET which can be used to create a set of data values of the given ANYTYPE.
<a href="#">ENDCREATE Member Procedure</a> on page 169-6	Ends Creation of a ANYDATASET. Other creation functions cannot be called after this call.
<a href="#">GET* Member Functions</a> on page 169-7	Gets the current data value (which should be of appropriate type).
<a href="#">GETCOUNT Member Function</a> on page 169-11	Gets the number of data instances in an ANYDATASET.
<a href="#">GETINSTANCE Member Function</a> on page 169-12	Gets the next instance in an ANYDATASET.
<a href="#">GETTYPE Member Function</a> on page 169-13	Gets the ANYTYPE describing the type of the data instances in an ANYDATASET. current data value (which should be of appropriate type).
<a href="#">GETTYPENAME Member Function</a> on page 169-14	Gets the AnyType describing the type of the data instances in an ANYDATASET.
<a href="#">PIECEWISE Member Procedure</a> on page 169-15	Sets the MODE of construction, access of the data value to be an attribute at a time (if the data value is of TYPECODE_OBJECT).
<a href="#">SET* Member Procedures</a> on page 169-16	Sets the current data value.

## ADDINSTANCE Member Procedure

This procedure adds a new data instance to an `ANYDATASET`.

### Syntax

```
MEMBER PROCEDURE AddInstance(
 self IN OUT NOCOPY ANYDATASET);
```

### Parameters

**Table 169–2** *ADDINSTANCE Procedure Parameter*

Parameter	Description
<code>self</code>	The <code>ANYDATASET</code> being constructed.

### Exceptions

`DBMS_TYPES.invalid_parameters`: Invalid parameters.  
`DBMS_TYPES.incorrect_usage`: On incorrect usage.

### Usage Notes

The data instances have to be added sequentially. The previous data instance must be fully constructed (or set to `NULL`) before a new one can be added.

This call **DOES NOT** automatically set the mode of construction to be piece-wise. The user has to explicitly call `PIECEWISE` if a piece-wise construction of the instance is intended.

## BEGINCREATE Static Procedure

This procedure creates a new ANYDATASET which can be used to create a set of data values of the given ANYTYPE .

### Syntax

```
STATIC PROCEDURE BeginCreate(
 typecode IN PLS_INTEGER,
 rtype IN OUT NOCOPY AnyType,
 aset OUT NOCOPY ANYDATASET);
```

### Parameters

**Table 169–3** *BEGINCREATE Procedure Parameter*

Parameter	Description
typecode	The typecode for the type of the ANYDATASET.
dtype	The type of the data values. This parameter is a must for user-defined types like TYPECODE_OBJECT, Collection typecodes, and similar others.
aset	The ANYDATASET being constructed.

### Exceptions

DBMS\_TYPES.invalid\_parameters: dtype is invalid (not fully constructed, and like errors.)

## ENDCREATE Member Procedure

This procedure ends Creation of a ANYDATASET. Other creation functions cannot be called after this call.

### Syntax

```
MEMBER PROCEDURE ENDCREATE(
 self IN OUT NOCOPY ANYDATASET);
```

### Parameters

**Table 169–4** ENDCREATE Procedure Parameter

Parameter	Description
self	The ANYDATASET being constructed.



## GET\* Member Functions

These functions get the current data value (which should be of appropriate type).

The type of the current data value depends on the `MODE` with which you are accessing it (depending on how we have invoked the `PIECEWISE` call). If `PIECEWISE` has not been called, we are accessing the instance in its entirety and the type of the data value should match the type of the `ANYDATASET`.

If `PIECEWISE` has been called, we are accessing the instance piece-wise. The type of the data value should match the type of the attribute (or collection element) at the current position.

### Syntax

```
MEMBER FUNCTION GETBDOUBLE(
 self IN ANYDATASET,
 dbl OUT NOCOPY BINARY_DOUBLE)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GETBFLOAT(
 self IN ANYDATASET,
 fl OUT NOCOPY BINARY_FLOAT)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GETBFILE(
 self IN ANYDATASET,
 b OUT NOCOPY BFILE)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GETBLOB(
 self IN ANYDATASET,
 b OUT NOCOPY BLOB)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GETCHAR(
 self IN ANYDATASET,
 c OUT NOCOPY CHAR)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GETCLOB(
 self IN ANYDATASET,
 c OUT NOCOPY CLOB)
RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GETCOLLECTION(
 self IN ANYDATASET,
 col OUT NOCOPY "<collection_type>")
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETDATE(
 self IN ANYDATASET,
 dat OUT NOCOPY DATE)
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETINTERVALDS(
 self IN ANYDATASET,
 inv IN OUT NOCOPY INTERVAL DAY TO SECOND)
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETINTERVALYM(
 self IN ANYDATASET,
 inv IN OUT NOCOPY INTERVAL YEAR TO MONTH)
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETINCHAR(
 self IN ANYDATASET,
 nc OUT NOCOPY NCHAR)
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETINCLOB(
 self IN ANYDATASET,
 nc OUT NOCOPY NCLOB)
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETNUMBER(
 self IN ANYDATASET,
 num OUT NOCOPY NUMBER)
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETINVARCHAR2(
 self IN ANYDATASET,
 nc OUT NOCOPY NVARCHAR2)
 RETURN PLS_INTEGER;

MEMBER FUNCTION GETOBJECT(
 self IN ANYDATASET,
 obj OUT NOCOPY "<object_type>")
 RETURN PLS_INTEGER;
```

```
MEMBER FUNCTION GETRAW(
 self IN ANYDATASET,
 r OUT NOCOPY RAW)
RETURN PLS_INTEGER;

MEMBER FUNCTION GETREF(
 self IN ANYDATASET,
 rf OUT NOCOPY REF "<object_type>")
RETURN PLS_INTEGER;

MEMBER FUNCTION GETTIMESTAMP(
 self IN ANYDATASET,
RETURN PLS_INTEGER;

MEMBER FUNCTION GETTIMESTAMPPLTZ(
 self IN ANYDATASET,
 ts OUT NOCOPY TIMESTAMP WITH LOCAL TIME ZONE)
RETURN PLS_INTEGER;

MEMBER FUNCTION GETTIMESTAMPPTZ(
 self IN ANYDATASET,
 ts OUT NOCOPY TIMESTAMP WITH TIME ZONE)
RETURN PLS_INTEGER,

MEMBER FUNCTION GETUROWID(
 self IN ANYDATASET,
 rid OUT NOCOPY UROWID)
RETURN PLS_INTEGER

MEMBER FUNCTION GETVARIABLE(
 self IN ANYDATASET,
 c OUT NOCOPY VARCHAR)
RETURN PLS_INTEGER;

MEMBER FUNCTION GETVARIABLE2(
 self IN ANYDATASET,
 c OUT NOCOPY VARCHAR2)
RETURN PLS_INTEGER;
```

## Parameters

**Table 169–5** *GET\* Procedure Parameters*

Parameter	Description
<code>self</code>	The ANYDATASET being accessed.
<code>num</code>	The number, and associated information., that is to be obtained.

## Return Values

`DBMS_TYPES.SUCCESS` or `DBMS_TYPES.NO_DATA`

The return value is relevant only if `PIECEWISE` has been already called (for a collection). In such a case, `DBMS_TYPES.NO_DATA` signifies the end of the collection when all elements have been accessed.

## Exceptions

`DBMS_TYPES.INVALID_PARAMETERS`: Invalid Parameters (if it is not appropriate to add a number at this point in the creation process).

`DBMS_TYPES.INCORRECT_USAGE`: Incorrect usage

`DBMS_TYPES.TYPE_MISMATCH`: When the expected type is different from the passed in type.

## GETCOUNT Member Function

This function gets the number of data instances in an ANYDATASET.

### Syntax

```
MEMBER FUNCTION GetCount(
 self IN ANYDATASET)
 RETURN PLS_INTEGER;
```

### Parameter

**Table 169–6** *GETCOUNT Function Parameter*

Parameter	Description
self	The ANYDATASET being accessed.

### Return Values

The number of data instances.

## GETINSTANCE Member Function

This function gets the next instance in an `ANYDATASET`. Only sequential access to the instances in an `ANYDATASET` is allowed. After this function has been called, the `GET*` functions can be invoked on the `ANYDATASET` to access the current instance. If `PIECEWISE` is called before doing the `GET*` calls, the individual attributes (or collection elements) can be accessed.

It is an error to invoke this function before the `ANYDATASET` is fully created.

### Syntax

```
MEMBER FUNCTION GETINSTANCE(
 self IN OUT NOCOPY ANYDATASET)
 RETURN PLS_INTEGER;
```

### Parameters

**Table 169–7** *GETINSTANCE Function Parameter*

Parameter	Description
<code>self</code>	The <code>ANYDATASET</code> being accessed.

### Return Values

`DBMS_TYPES.SUCCESS` or `DBMS_TYPES.NO_DATA`

`DBMS_TYPES.NO_DATA` signifies the end of the `ANYDATASET` (all instances have been accessed).

### Usage Notes

This function should be called even before accessing the first instance.

## GETTYPE Member Function

Gets the AnyType describing the type of the data instances in an ANYDATASET.

### Syntax

```
MEMBER FUNCTION GETTYPE(
 self IN ANYDATASET,
 typ OUT NOCOPY AnyType)
RETURN PLS_INTEGER;
```

### Parameters

**Table 169–8** *GETTYPE Function Parameter*

Parameter	Description
self	The ANYDATASET.
typ	The ANYTYPE corresponding to the AnyData. May be NULL if it does not represent a user-defined function.

### Return Values

The typecode corresponding to the type of the ANYDATA.

## GETTYPENAME Member Function

This procedure gets the fully qualified type name for the ANYDATASET.

If the ANYDATASET is based on a built-in, this function will return NUMBER and associated information.

If it is based on a user defined type, this function will return *schema\_name.type\_name*. for example, SCOTT.FOO.

If it is based on a transient anonymous type, this function will return NULL.

### Syntax

```
MEMBER FUNCTION GETTYPENAME(
 self IN ANYDATASET)
 RETURN VARCHAR2;
```

### Parameter

**Table 169–9** GETTYPENAME Function Parameter

Parameter	Description
self	The ANYDATASET being constructed.

### Return Values

Type name of the ANYDATASET.



## PIECEWISE Member Procedure

This procedure sets the `MODE` of construction, access of the data value to be an attribute at a time (if the data value is of `TYPECODE_OBJECT`).

It sets the `MODE` of construction, access of the data value to be a collection element at a time (if the data value is of a collection `TYPE`). Once this call has been made, subsequent `SET*` and `GET*` calls will sequentially obtain individual attributes or collection elements.

### Syntax

```
MEMBER PROCEDURE PIECEWISE(
 self IN OUT NOCOPY ANYDATASET);
```

### Parameters

**Table 169–10** *PIECEWISE Procedure Parameter*

Parameter	Description
<code>self</code>	The ANYDATASET being constructed.

### Exceptions

`DBMS_TYPES.INVALID_PARAMETERS`: Invalid parameters.

`DBMS_TYPES.INCORRECT_USAGE`: On incorrect usage.

### Usage Notes

The current data value must be of an object or collectyon type before this call can be made. There is no support for piece-wise construction or access of embedded object type attributes or nested collections.

## SET\* Member Procedures

This procedure sets the current data value.

The type of the current data value depends on the `MODE` with which we are constructing (depending on how we have invoked the `PIECEWISE` call). The type of the current data should be the type of the `ANYDATASET` if `PIECEWISE` has NOT been called. The type should be the type of the attribute at the current position if `PIECEWISE` has been called.

### Syntax

```
MEMBER PROCEDURE SETBDOUBLE(
 self IN OUT NOCOPY ANYDATASET,
 dbl IN BINARY_DOUBLE,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETBFLOAT(
 self IN OUT NOCOPY ANYDATASET,
 fl IN BINARY_FLOAT,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETBFILE(
 self IN OUT NOCOPY ANYDATASET,
 b IN BFILE,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETBLOB(
 self IN OUT NOCOPY ANYDATASET,
 b IN BLOB,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETCHAR(
 self IN OUT NOCOPY ANYDATASET,
 c IN CHAR,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETCLOB(
 self IN OUT NOCOPY ANYDATASET,
 c IN CLOB,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETCOLLECTION(
 self IN OUT NOCOPY ANYDATASET,
```

```
col IN "<collection_type>",
last_elem BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETDATE(
 self IN OUT NOCOPY ANYDATASET,
 dat IN DATE,
 last_elem BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETINTERVALDS(
 self IN OUT NOCOPY ANYDATASET,
 inv IN INTERVAL DAY TO SECOND,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETINTERVALYM(
 self IN OUT NOCOPY ANYDATASET,
 inv IN INTERVAL YEAR TO MONTH,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETNCHAR(
 self IN OUT NOCOPY ANYDATASET,
 nc IN NCHAR,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETNCLOB(
 self IN OUT NOCOPY ANYDATASET,
 nc IN NClob,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETNUMBER(
 self IN OUT NOCOPY ANYDATASET,
 num IN NUMBER,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETNVARCHAR2(
 self IN OUT NOCOPY ANYDATASET,
 nc IN NVarchar2,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETOBJECT(
 self IN OUT NOCOPY ANYDATASET,
 obj IN "<object_type>",
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETRAW(
 self IN OUT NOCOPY ANYDATASET,
```

```

 r IN RAW,
 last_elem BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETREF(
 self IN OUT NOCOPY ANYDATASET,
 rf IN REF "<object_type>",
 last_elem BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETTIMESTAMP(
 self IN OUT NOCOPY ANYDATASET,
 ts IN TIMESTAMP,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETTIMESTAMPPLTZ(
 self IN OUT NOCOPY ANYDATASET,
 ts IN TIMESTAMP WITH LOCAL TIME ZONE,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETTIMESTAMPPTZ(
 self IN OUT NOCOPY ANYDATASET,
 ts IN TIMESTAMP WITH TIME ZONE,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETUROWID(
 self IN OUT NOCOPY ANYDATASET,
 rid IN UROWID,
 last_elem IN BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETVARCHAR(
 self IN OUT NOCOPY ANYDATASET,
 c IN VARCHAR,
 last_elem BOOLEAN DEFAULT FALSE);

MEMBER PROCEDURE SETVARCHAR2(
 self IN OUT NOCOPY ANYDATASET,
 c IN VARCHAR2,
 last_elem BOOLEAN DEFAULT FALSE);

```

## Parameters

**Table 169–11 SET\* Procedure Parameters**

Parameter	Description
self	The ANYDATASET being accessed.

**Table 169–11 SET\* Procedure Parameters**

Parameter	Description
num	The number, and associated information, that is to be set.
last_elem	Relevant only if <code>PIECEWISE</code> has been already called (for a collection). Set to <code>TRUE</code> if it is the last element of the collection, <code>FALSE</code> otherwise.

## Exceptions

- `DBMS_TYPES.INVALID_PARAMETERS`: Invalid parameters (if it is not appropriate to add a number at this point in the creation process).
- `DBMS_TYPES.INCORRECT_USAGE`: Incorrect usage.
- `DBMS_TYPES.TYPE_MISMATCH`: When the expected type is different from the passed in type.



An `ANYTYPE TYPE` can contain a type description of any persistent SQL type, named or unnamed, including object types and collection types. It can also be used to construct new transient type descriptions.

New persistent types can only be created using the `CREATE TYPE` statement. Only new transient types can be constructed using the `ANYTYPE` interfaces.

This chapter discusses the following:

- [Summary of ANYTYPE Subprograms](#)

---

## Summary of ANYTYPE Subprograms

**Table 170–1 ANYTYPE Type Subprograms**

Subprogram	Description
<a href="#">BEGINCREATE Static Procedure</a> on page 170-3	Creates a new instance of ANYTYPE which can be used to create a transient type description.
<a href="#">SETINFO Member Procedure</a> on page 170-4	Sets any additional information required for constructing a COLLECTION or builtin type.
<a href="#">ADDATTR Member Procedure</a> on page 170-6	Adds an attribute to an ANYTYPE (of typecode DBMS_TYPES.TYPECODE_OBJECT).
<a href="#">ENDCREATE Member Procedure</a> on page 170-8	Ends creation of a transient ANYTYPE. Other creation functions cannot be called after this call.
<a href="#">GETPERSISTENT Static Function</a> on page 170-9	Returns an ANYTYPE corresponding to a persistent type created earlier using the CREATE TYPE SQL statement.
<a href="#">GETINFO Member Function</a> on page 170-10	Gets the type information for the ANYTYPE.
<a href="#">GETATTRELEMINFO Member Function</a> on page 170-12	Gets the type information for an attribute of the type (if it is of TYPECODE_OBJECT). Gets the type information for a collection's element type if the <i>self</i> parameter is of a collection type.



## BEGINCREATE Static Procedure

This procedure creates a new instance of ANYTYPE which can be used to create a transient type description.

### Syntax

```
STATIC PROCEDURE BEGINCREATE(
 typecode IN PLS_INTEGER,
 atype OUT NOCOPY ANYTYPE);
```

### Parameters

**Table 170–2** *BEGINCREATE Procedure Parameters*

Parameter	Description
typecode	Use a constant from DBMS_TYPES package. Typecodes for user-defined type: can be DBMS_TYPES.TYPECODE_OBJECT, DBMS_TYPES.TYPECODE_VARRAY or DBMS_TYPES.TYPECODE_TABLE. Typecodes for builtin types: DBMS_TYPES.TYPECODE_NUMBER, and similar types.
atype	ANYTYPE for a transient type

## SETINFO Member Procedure

This procedure sets any additional information required for constructing a `COLLECTION` or builtin type.

### Syntax

```
MEMBER PROCEDURE SETINFO(
 self IN OUT NOCOPY ANYTYPE,
 prec IN PLS_INTEGER,
 scale IN PLS_INTEGER,
 len IN PLS_INTEGER,
 csid IN PLS_INTEGER,
 csfrm IN PLS_INTEGER,
 atype IN ANYTYPE DEFAULT NULL,
 elem_tc IN PLS_INTEGER DEFAULT NULL,
 elem_count IN PLS_INTEGER DEFAULT 0);
```

### Parameters

**Table 170–3** *SETINFO Procedure Parameters*

Parameter	Description
<code>self</code>	The transient <code>ANYTYPE</code> that is being constructed.
<code>prec</code>	Optional. Required if typecode represents a <code>NUMBER</code> . Give precision and scale. Ignored otherwise.
<code>scale</code>	Optional. Required if typecode represents a <code>NUMBER</code> . Give precision and scale. Ignored otherwise.
<code>len</code>	Optional. Required if typecode represents a <code>RAW</code> , <code>CHAR</code> , <code>VARCHAR</code> , or <code>VARCHAR2</code> type. Gives length.
<code>csid</code>	Required if typecode represents types requiring character information such as <code>CHAR</code> , <code>VARCHAR</code> , <code>VARCHAR2</code> , or <code>CFILE</code> .
<code>csfrm</code>	Required if typecode represents types requiring character information such as <code>CHAR</code> , <code>VARCHAR</code> , <code>VARCHAR2</code> , or <code>CFILE</code> .
<code>atype</code>	Optional. Required if collection element typecode is a user-defined type such as <code>TYPECODE_OBJECT</code> , and similar others.. It is also required for a built-in type that needs user-defined type information such as <code>TYPECODE_REF</code> . This parameter is not needed otherwise.

**Table 170–3 (Cont.) SETINFO Procedure Parameters**

Parameter	Description
The Following Parameters Are Required For Collection Types:	
<code>elem_tc</code>	Must be of the collection element's typecode (from <code>DBMS_TYPES</code> package).
<code>elem_count</code>	Pass 0 for <code>elem_count</code> if the <code>self</code> represents a nested table ( <code>TYPECODE_TABLE</code> ). Otherwise pass the collection count if <code>self</code> represents a <code>VARRAY</code> .

## Exceptions

- `DBMS_TYPES.INVALID_PARAMETER`: Invalid Parameters (typecode, typeinfo)
- `DBMS_TYPES.INCORRECT_USAGE`: Incorrect usage (cannot call after calling `ENDCREATE`, and similar actions.)

## Usage Notes

It is an error to call this function on an `ANYTYPE` that represents a persistent user defined type.

## ADDATTR Member Procedure

This procedure adds an attribute to an ANYTYPE (of typecode DBMS\_TYPES.TYPECODE\_OBJECT).

### Syntax

```
MEMBER PROCEDURE ADDATTR(
 self IN OUT NOCOPY ANYTYPE,
 aname IN VARCHAR2,
 typecode IN PLS_INTEGER,
 prec IN PLS_INTEGER,
 scale IN PLS_INTEGER,
 len IN PLS_INTEGER,
 csid IN PLS_INTEGER,
 csfrm IN PLS_INTEGER,
 attr_type IN ANYTYPE DEFAULT NULL);
```

### Parameters

**Table 170–4 ADDATTR Procedure Parameters**

Parameter	Description
self	The transient ANYTYPE that is being constructed. Must be of type DBMS_TYPES.TYPECODE_OBJECT.
aname	Optional. Attribute's name. Could be NULL.
typecode	Attribute's typecode. Can be built-in or user-defined typecode (from DBMS_TYPES package).
prec	Optional. Required if typecode represents a NUMBER. Give precision and scale. Ignored otherwise.
scale	Optional. Required if typecode represents a NUMBER. Give precision and scale. Ignored otherwise.
len	Optional. Required if typecode represents a RAW, CHAR, VARCHAR, or VARCHAR2 type. Give length.
csid	Optional. Required if typecode represents a type requiring character information, such as CHAR, VARCHAR, VARCHAR2, CFILE.
csfrm	Optional. Required if typecode represents a type requiring character information, such as CHAR, VARCHAR, VARCHAR2, CFILE.

**Table 170–4 (Cont.) ADDATTR Procedure Parameters**

Parameter	Description
<code>attr_type</code>	Optional. ANYTYPE corresponding to a user-defined type. This parameter is required if the attribute is a user defined type.

## Exceptions

- `DBMS_TYPES.INVALID_PARAMETERS`: Invalid Parameters (typecode, typeinfo)
- `DBMS_TYPES.INCORRECT_USAGE`: Incorrect usage (cannot call after calling `EndCreate`, and similar actions.)

## ENDCREATE Member Procedure

This procedure ends creation of a transient `ANYTYPE`. Other creation functions cannot be called after this call.

### Syntax

```
MEMBER PROCEDURE ENDCREATE(
 self IN OUT NOCOPY ANYTYPE);
```

### Parameter

**Table 170–5** *ENDCREATE Procedure Parameter*

Parameter	Description
<code>self</code>	The transient <code>ANYTYPE</code> that is being constructed.

## GETPERSISTENT Static Function

This procedure returns an ANYTYPE corresponding to a persistent type created earlier using the CREATE TYPE SQL statement.

### Syntax

```
STATIC FUNCTION GETPERSISTENT(
 schema_name IN VARCHAR2,
 type_name IN VARCHAR2,
 version IN VARCHAR2 DEFAULT NULL)
RETURN ANYTYPE;
```

### Parameters

**Table 170–6** GETPERSISTENT Function Parameters

Parameter	Description
schema_name	Schema name of the type.
type_name	Type name.
version	Type version.

### Return Values

An ANYTYPE corresponding to a persistent type created earlier using the CREATE TYPE SQL statement.

## GETINFO Member Function

This function gets the type information for the ANYTYPE.

### Syntax

```
MEMBER FUNCTION GETINFO (
 self IN ANYTYPE,
 prec OUT PLS_INTEGER,
 scale OUT PLS_INTEGER,
 len OUT PLS_INTEGER,
 csid OUT PLS_INTEGER,
 csfrm OUT PLS_INTEGER,
 schema_name OUT VARCHAR2,
 type_name OUT VARCHAR2,
 version OUT varchar2,
 count OUT PLS_INTEGER)
RETURN PLS_INTEGER;
```

### Parameters

**Table 170–7** GETINFO Function Parameters

Parameter	Description
self	The ANYTYPE.
prec	If typecode represents a number. Gives precision and scale. Ignored otherwise.
scale	If typecode represents a number. Gives precision and scale. Ignored otherwise.
len	If typecode represents a RAW, CHAR, VARCHAR, or VARCHAR2 type. Gives length.
csid	If typecode represents a type requiring character information such as: CHAR, VARCHAR, VARCHAR2, CFILE.
csid	If typecode represents a type requiring character information such as: CHAR, VARCHAR, VARCHAR2, CFILE.
schema_name	Type's schema (if persistent).
type_name	Type's typename.
version	Type's version.



**Table 170–7 (Cont.) GETINFO Function Parameters**

Parameter	Description
count	If <i>self</i> is a VARRAY, this gives the VARRAY count. If <i>self</i> is of TYPECODE_OBJECT, this gives the number of attributes.

## Return Values

The typecode of *self*.

## Exceptions

- `DBMS_TYPES.INVALID_PARAMETERS`: Invalid Parameters (position is beyond bounds or the ANYTYPE is not properly Constructed).

## GETATTRELEMINFO Member Function

This function gets the type information for an attribute of the type (if it is of `TYPECODE_OBJECT`). Gets the type information for a collection's element type if the *self* parameter is of a collection type.

### Syntax

```
MEMBER FUNCTION GETATTRELEMINFO (
 self IN ANYTYPE,
 pos IN PLS_INTEGER,
 prec OUT PLS_INTEGER,
 scale OUT PLS_INTEGER,
 len OUT PLS_INTEGER,
 csid OUT PLS_INTEGER,
 csfrm OUT PLS_INTEGER,
 attr_elt_type OUT ANYTYPE
 aname OUT VARCHAR2)
RETURN PLS_INTEGER;
```

### Parameters

**Table 170–8** GETATTRELEMINFO Function Parameters

Parameter	Description
<code>self</code>	The <code>ANYTYPE</code> .
<code>pos</code>	If <code>self</code> is of <code>TYPECODE_OBJECT</code> , this gives the attribute position (starting at 1). It is ignored otherwise.
<code>prec</code>	If attribute/collection element typecode represents a <code>NUMBER</code> . Gives precision and scale. Ignored otherwise.
<code>scale</code>	If attribute/collection element typecode represents a <code>NUMBER</code> . Gives precision and scale. Ignored otherwise.
<code>len</code>	If typecode represents a <code>RAW</code> , <code>CHAR</code> , <code>VARCHAR</code> , or <code>VARCHAR2</code> type. Gives length.
<code>csid</code> , <code>csfrm</code>	If typecode represents a type requiring character information such as: <code>CHAR</code> , <code>VARCHAR</code> , <code>VARCHAR2</code> , <code>CFILE</code> . Gives character set ID, character set form.
<code>attr_elt_type</code>	If attribute/collection element typecode represents a user-defined type, this returns the <code>ANYTYPE</code> corresponding to it. User can subsequently describe the <i>attr_elt_type</i> .

**Table 170–8 (Cont.) GETATTRELEMINFO Function Parameters**

<b>Parameter</b>	<b>Description</b>
aname	Attribute name (if it is an attribute of an object type, NULL otherwise).

**Return Values**

The typecode of the attribute or collection element.

**Exceptions**

`DBMS_TYPES.INVALID_PARAMETERS`: Invalid Parameters (position is beyond bounds or the ANYTYPE is not properly constructed).



---

## Oracle Streams AQ TYPEs

This chapter describes the types used with Oracle Streams Advanced Queuing (AQ) packages for PL/SQL, `DBMS_AQ`, and `DBMS_AQADM`.

**See Also:** *Oracle Streams Advanced Queuing User's Guide and Reference* for information about using Oracle Streams AQ.

This chapter contains the following topics:

- [Summary of Types](#)

---

## Summary of Types

- [AQ\\$\\_AGENT](#) Type
- [AQ\\$\\_AGENT\\_LIST\\_T](#) Type
- [AQ\\$\\_DESCRIPTOR](#) Type
- [AQ\\$\\_POST\\_INFO](#) Type
- [AQ\\$\\_POST\\_INFO\\_LIST](#) Type
- [AQ\\$\\_PURGE\\_OPTIONS\\_T](#) Type
- [AQ\\$\\_RECIPIENT\\_LIST\\_T](#) Type
- [AQ\\$\\_REG\\_INFO](#) Type
- [AQ\\$\\_REG\\_INFO\\_LIST](#) Type
- [AQ\\$\\_SUBSCRIBER\\_LIST\\_T](#) Type
- [DEQUEUE\\_OPTIONS\\_T](#) Type
- [ENQUEUE\\_OPTIONS\\_T](#) Type
- [MESSAGE\\_PROPERTIES\\_T](#) Type
- [MESSAGE\\_PROPERTIES\\_ARRAY\\_T](#) Type
- [MSGID\\_ARRAY\\_T](#) Type

## AQ\$\_AGENT Type

Identifies a producer or a consumer of a message.

### Syntax

```
TYPE SYS.AQ$_AGENT IS OBJECT (
 name VARCHAR2(30),
 address VARCHAR2(1024),
 protocol NUMBER DEFAULT 0);
```

### Attributes

**Table 171–1 AQ\$\_AGENT Attributes**

Attribute	Description
name	Name of a producer or consumer of a message. The name must follow object name guidelines in the <i>Oracle Database SQL Reference</i> with regard to reserved characters.
address	Protocol-specific address of the recipient. If the protocol is 0, then the address is of the form <code>[schema.]queue[@dblink]</code> . For example, a queue named <code>emp_messages</code> in the <code>hr</code> queue at the site <code>dbsl.net</code> has the address: <code>hr.emp_messages@dbsl.net</code>
protocol	Protocol to interpret the address and propagate the message. Protocols 1-127 are reserved for internal use. If the protocol number is in the range 128 - 255, the address of the recipient is not interpreted by Oracle Streams AQ.

## AQ\$\_AGENT\_LIST\_T Type

Identifies the list of agents for which DBMS\_AQ.LISTEN listens.

**See Also:** ["AQ\\$\\_AGENT Type"](#) on page 171-3

### Syntax

```
TYPE SYS.AQ$_AGENT_LIST_T IS TABLE OF SYS.AQ$_AGENT
INDEX BY BINARY INTEGER;
```



## AQ\$\_DESCRIPTOR Type

Specifies the Oracle Streams AQ descriptor received by the AQ PL/SQL callbacks upon notification.

**See Also:** ["MESSAGE\\_PROPERTIES\\_T Type"](#) on page 171-18

### Syntax

```
TYPE SYS.AQ$_DESCRIPTOR IS OBJECT (
 queue_name VARCHAR2(61),
 consumer_name VARCHAR2(30),
 msg_id RAW(16),
 msg_prop MSG_PROP_T);
```

### Attributes

**Table 171–2 AQ\$\_DESCRIPTOR Attributes**

Attribute	Description
queue_name	Name of the queue in which the message was enqueued which resulted in the notification
consumer_name	Name of the consumer for the multiconsumer queue
msg_id	Identification number of the message
msg_prop	Message properties specified by the MSG_PROP_T type

## AQ\$\_POST\_INFO Type

Specifies anonymous subscriptions to which you want to post messages.

### Syntax

```
TYPE SYS.AQ$_POST_INFO IS OBJECT (
 name VARCHAR2(128),
 namespace NUMBER,
 payload RAW(2000) DEFAULT NULL);
```

### Attributes

**Table 171–3 AQ\$\_POST\_INFO Attributes**

Attribute	Description
name	Name of the anonymous subscription to which you want to post
namespace	To receive notifications from other applications through <code>DBMS_AQ.POST</code> or <code>OCISubscriptionPost()</code> , the namespace must be <code>DBMS_AQ.NAMESPACE_ANONYMOUS</code>
payload	The payload to be posted to the anonymous subscription

## AQ\$\_POST\_INFO\_LIST Type

Identifies the list of anonymous subscriptions to which you want to post messages.

**See Also:** ["AQ\\$\\_POST\\_INFO Type"](#) on page 171-6

### Syntax

```
TYPE SYS.AQ$_POST_INFO_LIST AS VARRAY(1024) OF SYS.AQ$_POST_INFO;
```

## AQ\$\_PURGE\_OPTIONS\_T Type

Specifies the options available for purging a queue table.

### Syntax

```
TYPE AQ$_PURGE_OPTIONS_T is
RECORD (block boolean DEFAULT FALSE);
```

### Usage Notes

If `block` is `TRUE`, then an exclusive lock on all the queues in the queue table is held while purging the queue table. This will cause concurrent enqueueers and dequeuers to block while the queue table is purged. The purge call always succeeds if `block` is `TRUE`.

The default for `block` is `FALSE`. This will not block enqueueers and dequeuers, but it can cause the purge to fail with an error during high concurrency times.

**See Also:** ["PURGE\\_QUEUE\\_TABLE Procedure"](#) on page 17-42.

## AQ\$\_RECIPIENT\_LIST\_T Type

Identifies the list of agents that receive the message. This type can be used only when the queue is enabled for multiple dequeues.

**See Also:** ["AQ\\$\\_AGENT Type"](#) on page 171-3

### Syntax

```
TYPE SYS.AQ$_RECIPIENT_LIST_T IS TABLE OF SYS.AQ$_AGENT
INDEX BY BINARY_INTEGER;
```

## AQ\$\_REG\_INFO Type

Specifies the information regarding the registrant for notification on a queue.

### Syntax

```
TYPE SYS.AQ$_REG_INFO IS OBJECT (
 name VARCHAR2(128),
 namespace NUMBER,
 callback VARCHAR2(4000),
 context RAW(2000) DEFAULT NULL);
```

### Attributes

**Table 171–4 AQ\$\_REG\_INFO Type Attributes**

Attribute	Description
name	Specifies the name of the subscription. The subscription name is of the form <i>schema.queue</i> if the registration is for a single consumer queue or <i>schema.queue:consumer_name</i> if the registration is for a multiconsumer queues.
namespace	Specifies the namespace of the subscription. To receive notification from Oracle Streams AQ queues, the namespace must be <code>DBMS_AQ.NAMESPACE_AQ</code> . To receive notifications from other applications through <code>DBMS_AQ.POST</code> or <code>OCISubscriptionPost()</code> , the namespace must be <code>DBMS_AQ.NAMESPACE_ANONYMOUS</code> .
callback	Specifies the action to be performed on message notification. For HTTP notifications, use <code>http://www.company.com:8080</code> . For e-mail notifications, use <code>mailto://xyz@company.com</code> . For raw message payload for the <code>PLSQLCALLBACK</code> procedure, use <code>plsql://schema.procedure?PR=0</code> . For user-defined type message payload converted to XML for the <code>PLSQLCALLBACK</code> procedure, use <code>plsql://schema.procedure?PR=1</code> .
context	Specifies the context that is to be passed to the callback function

### Usage Notes

You can use the following notification mechanisms:

- OCI callback
- e-mail callback
- PL/SQL callback

[Table 171-5](#) shows the actions performed for nonpersistent queues for different notification mechanisms when RAW presentation is specified. [Table 171-6](#) shows the actions performed when XML presentation is specified.

**Table 171-5 Actions Performed for Nonpersistent Queues When RAW Presentation Specified**

Queue Payload Type	OCI Callback	E-mail	PL/SQL Callback
RAW	OCI callback receives the RAW data in the payload.	Not supported	PL/SQL callback receives the RAW data in the payload.
Oracle object type	Not supported	Not supported	Not supported

**Table 171-6 Actions Performed for Nonpersistent Queues When XML Presentation Specified**

Queue Payload Type	OCI Callback	E-mail	PL/SQL Callback
RAW	OCI callback receives the XML data in the payload.	XML data is formatted as a SOAP message and e-mailed to the registered e-mail address.	PL/SQL callback receives the XML data in the payload.
Oracle object type	OCI callback receives the XML data in the payload.	XML data is formatted as a SOAP message and e-mailed to the registered e-mail address.	PL/SQL callback receives the XML data in the payload.

## AQ\$\_REG\_INFO\_LIST Type

Identifies the list of registrations to a queue.

**See Also:** ["AQ\\$\\_REG\\_INFO Type"](#) on page 171-10

### Syntax

```
TYPE SYS.AQ$_REG_INFO_LIST AS VARRAY(1024) OF SYS.AQ$_REG_INFO;
```



## AQ\$\_SUBSCRIBER\_LIST\_T Type

Identifies the list of subscribers that subscribe to a queue.

**See Also:** ["AQ\\$\\_AGENT Type"](#) on page 171-3

### Syntax

```
TYPE SYS.AQ$_SUBSCRIBER_LIST_T IS TABLE OF SYS.AQ$_AGENT
INDEX BY BINARY_INTEGER;
```

## DEQUEUE\_OPTIONS\_T Type

Specifies the options available for the dequeue operation.

### Syntax

```
TYPE DEQUEUE_OPTIONS_T IS RECORD (
 consumer_name VARCHAR2(30) DEFAULT NULL,
 dequeue_mode BINARY_INTEGER DEFAULT REMOVE,
 navigation BINARY_INTEGER DEFAULT NEXT_MESSAGE,
 visibility BINARY_INTEGER DEFAULT ON_COMMIT,
 wait BINARY_INTEGER DEFAULT FOREVER,
 msgid RAW(16) DEFAULT NULL,
 correlation VARCHAR2(128) DEFAULT NULL,
 deq_condition VARCHAR2(4000) DEFAULT NULL,
 transformation VARCHAR2(61) DEFAULT NULL);
```

### Attributes

**Table 171–7 DEQUEUE\_OPTIONS\_T Attributes**

Attribute	Description
consumer_name	<p>Name of the consumer. Only those messages matching the consumer name are accessed. If a queue is not set up for multiple consumers, then this field should be set to NULL.</p> <p>For secure queues, consumer_name must be a valid AQ agent name, mapped to the database user performing the dequeue operation, through <code>dbms_aqadm.enable_db_access</code> procedure call.</p>
dequeue_mode	<p>Specifies the locking behavior associated with the dequeue. Possible settings are:</p> <p><b>BROWSE:</b> Read the message without acquiring any lock on the message. This specification is equivalent to a select statement.</p> <p><b>LOCKED:</b> Read and obtain a write lock on the message. The lock lasts for the duration of the transaction. This setting is equivalent to a select for update statement.</p> <p><b>REMOVE:</b> Read the message and delete it. This setting is the default. The message can be retained in the queue table based on the retention properties.</p> <p><b>REMOVE_NODATA:</b> Mark the message as updated or deleted. The message can be retained in the queue table based on the retention properties.</p>

**Table 171–7 (Cont.) DEQUEUE\_OPTIONS\_T Attributes**

Attribute	Description
navigation	<p>Specifies the position of the message that will be retrieved. First, the position is determined. Second, the search criterion is applied. Finally, the message is retrieved. Possible settings are:</p> <p><b>NEXT_MESSAGE:</b> Retrieve the next message that is available and matches the search criteria. If the previous message belongs to a message group, then AQ retrieves the next available message that matches the search criteria and belongs to the message group. This setting is the default.</p> <p><b>NEXT_TRANSACTION:</b> Skip the remainder of the current transaction group (if any) and retrieve the first message of the next transaction group. This setting can only be used if message grouping is enabled for the current queue.</p> <p><b>FIRST_MESSAGE:</b> Retrieves the first message which is available and matches the search criteria. This setting resets the position to the beginning of the queue.</p> <p><b>FIRST_MESSAGE_MULTI_GROUP:</b> indicates that a call to <code>DBMS_AQ.DEQUEUE_ARRAY</code> will reset the position to the beginning of the queue and dequeue messages (possibly across different transaction groups) that are available and match the search criteria, until reaching the <code>ARRAY_SIZE</code> limit. Refer to the <code>TRANSACTION_GROUP</code> attribute for the message to distinguish between transaction groups.</p> <p><b>NEXT_MESSAGE_MULTI_GROUP:</b> indicates that a call to <code>DBMS_AQ.DEQUEUE_ARRAY</code> will dequeue the next set of messages (possibly across different transaction groups) that are available and match the search criteria, until reaching the <code>ARRAY_SIZE</code> limit. Refer to the <code>TRANSACTION_GROUP</code> attribute for the message to distinguish between transaction groups.</p>
visibility	<p>Specifies whether the new message is dequeued as part of the current transaction. The visibility parameter is ignored when using the <code>BROWSE</code> dequeue mode. Possible settings are:</p> <p><b>ON_COMMIT:</b> The dequeue will be part of the current transaction. This setting is the default.</p> <p><b>IMMEDIATE:</b> The dequeue operation is not part of the current transaction, but an autonomous transaction which commits at the end of the operation.</p>

**Table 171–7 (Cont.) DEQUEUE\_OPTIONS\_T Attributes**

Attribute	Description
wait	<p>Specifies the wait time if there is currently no message available which matches the search criteria. Possible settings are:</p> <p>FOREVER: Wait forever. This setting is the default.</p> <p>NO_WAIT: Do not wait.</p> <p>number: Wait time in seconds.</p>
msgid	Specifies the message identifier of the message to be dequeued.
correlation	<p>Specifies the correlation identifier of the message to be dequeued. Special pattern matching characters, such as the percent sign (%) and the underscore (_) can be used. If more than one message satisfies the pattern, then the order of dequeuing is undetermined.</p>
deq_condition	<p>A conditional expression based on the message properties, the message data properties, and PL/SQL functions.</p> <p>A <code>deq_condition</code> is specified as a Boolean expression using syntax similar to the <code>WHERE</code> clause of a SQL query. This Boolean expression can include conditions on message properties, user data properties (object payloads only), and PL/SQL or SQL functions (as specified in the <code>WHERE</code> clause of a SQL query). Message properties include <code>priority</code>, <code>corrid</code> and other columns in the queue table</p> <p>To specify dequeue conditions on a message payload (object payload), use attributes of the object type in clauses. You must prefix each attribute with <code>tab.user_data</code> as a qualifier to indicate the specific column of the queue table that stores the payload. The <code>deq_condition</code> parameter cannot exceed 4000 characters. If more than one message satisfies the dequeue condition, then the order of dequeuing is undetermined.</p>
transformation	<p>Specifies a transformation that will be applied after dequeuing the message. The source type of the transformation must match the type of the queue.</p>

## ENQUEUE\_OPTIONS\_T Type

Specifies the options available for the enqueue operation.

### Syntax

```
TYPE SYS.ENQUEUE_OPTIONS_T IS RECORD (
 visibility BINARY_INTEGER DEFAULT ON_COMMIT,
 relative_msgid RAW(16) DEFAULT NULL,
 sequence_deviation BINARY_INTEGER DEFAULT NULL,
 transformation VARCHAR2(61) DEFAULT NULL);
```

### Attributes

**Table 171–8 ENQUEUE\_OPTIONS\_T Attributes**

Attribute	Description
visibility	<p>Specifies the transactional behavior of the enqueue request. Possible settings are:</p> <p><b>ON_COMMIT:</b> The enqueue is part of the current transaction. The operation is complete when the transaction commits. This setting is the default.</p> <p><b>IMMEDIATE:</b> The enqueue operation is not part of the current transaction, but an autonomous transaction which commits at the end of the operation. This is the only value allowed when enqueueing to a non-persistent queue.</p>
relative_msgid	<p>Specifies the message identifier of the message which is referenced in the sequence deviation operation. This field is valid only if <b>BEFORE</b> is specified in <code>sequence_deviation</code>. This parameter is ignored if sequence deviation is not specified.</p>
sequence_deviation	<p>Specifies whether the message being enqueued should be dequeued before other messages already in the queue. Possible settings are:</p> <p><b>BEFORE:</b> The message is enqueued ahead of the message specified by <code>relative_msgid</code>.</p> <p><b>TOP:</b> The message is enqueued ahead of any other messages.</p>
transformation	<p>Specifies a transformation that will be applied before enqueueing the message. The return type of the transformation function must match the type of the queue.</p>

## MESSAGE\_PROPERTIES\_T Type

Describes the information that AQ uses to manage individual messages. These are set at enqueue time, and their values are returned at dequeue time.

**See Also:** ["AQ\\$\\_RECIPIENT\\_LIST\\_T Type"](#) on page 171-9

### Syntax

```
TYPE message_properties_t IS RECORD (
 priority BINARY_INTEGER DEFAULT 1,
 delay BINARY_INTEGER DEFAULT NO_DELAY,
 expiration BINARY_INTEGER DEFAULT NEVER,
 correlation VARCHAR2(128) DEFAULT NULL,
 attempts BINARY_INTEGER,
 recipient_list AQ$_RECIPIENT_LIST_T,
 exception_queue VARCHAR2(61) DEFAULT NULL,
 enqueue_time DATE,
 state BINARY_INTEGER,
 sender_id sys.aq$_agent DEFAULT NULL,
 original_msgid RAW(16) DEFAULT NULL,
 transaction_group VARCHAR2(30) DEFAULT NULL,
 user_property SYS.ANYDATA DEFAULT NULL);
```

## Attributes

**Table 171–9 MESSAGE\_PROPERTIES\_T Attributes**

Attribute	Description
priority	Specifies the priority of the message. A smaller number indicates higher priority. The priority can be any number, including negative numbers.
delay	<p>Specifies the delay of the enqueued message. The delay represents the number of seconds after which a message is available for dequeuing. Dequeuing by <code>msgid</code> overrides the delay specification. A message enqueued with <code>delay</code> set is in the <code>WAITING</code> state, and when the delay expires, the message goes to the <code>READY</code> state. <code>DELAY</code> processing requires the queue monitor to be started. However the queue monitor is started automatically by the system if needed. Delay is set by the producer who enqueues the message.</p> <p>The possible settings follow:</p> <p><code>NO_DELAY</code>: The message is available for immediate dequeuing</p> <p>number: The number of seconds to delay the message</p>
expiration	<p>Specifies the expiration of the message. It determines, in seconds, the duration the message is available for dequeuing. This parameter is an offset from the time the message is ready for dequeue. Expiration processing requires the queue monitor to be running. However the queue monitor is started automatically by the system if needed.</p> <p>The possible settings follow:</p> <p><code>NEVER</code>: The message does not expire</p> <p>number: The number of seconds message remains in <code>READY</code> state. If the message is not dequeued before it expires, then it is moved to the exception queue in the <code>EXPIRED</code> state.</p>
correlation	Returns the identifier supplied by the producer of the message at enqueue time.
attempts	Returns the number of attempts that have been made to dequeue the message. This parameter cannot be set at enqueue time.
recipient_list	<p>This parameter is only valid for queues that allow multiple consumers. The default recipients are the queue subscribers. This parameter is not returned to a consumer at dequeue time.</p> <p>For type definition, see the "<a href="#">AQ\$_AGENT Type</a>" on page 171-3.</p>

**Table 171–9 (Cont.) MESSAGE\_PROPERTIES\_T Attributes**

Attribute	Description
exception_queue	<p data-bbox="562 296 1265 348">Specifies the name of the queue into which the message is moved if it cannot be processed successfully.</p> <p data-bbox="562 361 1265 440">Messages are moved automatically into the exception queue. Messages are moved into the exception queue in the following cases:</p> <ul data-bbox="562 456 1265 562" style="list-style-type: none"> <li data-bbox="562 456 1265 562">■ <code>RETRY_COUNT</code>, the number of unsuccessful dequeue attempts, has exceeded the specification for the <code>MAX_RETRIES</code> parameter in the <code>DBMS_AQADM.CREATE_QUEUE</code> procedure during queue creation.</li> </ul> <p data-bbox="608 574 1265 788">For multiconsumer queues, the message becomes eligible to be moved to the exception queue even if failed dequeue attempts exceeds the <code>MAX_RETRIES</code> parameter for only one of the consumers. But the message will not be moved until either all other consumers have successfully consumed the message or failed more than <code>MAX_RETRIES</code>. You can view <code>MAX_RETRIES</code> for a queue in the <code>ALL_QUEUES</code> data dictionary view.</p> <p data-bbox="608 803 1265 909">If a dequeue transaction fails because the server process dies (including <code>ALTER SYSTEM KILL SESSION</code>) or <code>SHUTDOWN ABORT</code> on the instance, then <code>RETRY_COUNT</code> is not incremented.</p> <ul data-bbox="562 925 1265 1256" style="list-style-type: none"> <li data-bbox="562 925 1265 977">■ A message was not dequeued before the expiration time elapsed.</li> <li data-bbox="562 992 1265 1256">■ Message propagation to the specified destination queue failed with one of the following errors: <ul data-bbox="608 1060 1265 1256" style="list-style-type: none"> <li data-bbox="608 1060 1265 1112">* There were no recipients for the multiconsumer destination queue.</li> <li data-bbox="608 1128 1265 1180">* Recipients were specified for a single-consumer destination queue.</li> <li data-bbox="608 1196 1265 1222">* Destination queue was an exception queue</li> <li data-bbox="608 1237 1265 1256">* There was an error when applying transformation.</li> </ul> </li> </ul> <p data-bbox="562 1272 1265 1430">The default is the exception queue associated with the queue table. If the exception queue specified does not exist at the time of the move, then the message is moved to the default exception queue associated with the queue table, and a warning is logged in the alert file. If the default exception queue is specified, then the parameter returns a <code>NULL</code> value at dequeue time.</p>
enqueue_time	<p data-bbox="562 1454 1265 1538">Specifies the time the message was enqueued. This value is determined by the system and cannot be set by the user at enqueue time.</p>



**Table 171–9 (Cont.) MESSAGE\_PROPERTIES\_T Attributes**

Attribute	Description
state	<p>Specifies the state of the message at the time of the dequeue. This parameter cannot be set at enqueue time. The possible states follow:</p> <ul style="list-style-type: none"> <li>■ dbmsaq.READY: The message is ready to be processed.</li> <li>■ dbmsaq.WAITING: The message delay has not yet been reached.</li> <li>■ dbmsaq.PROCESSED: The message has been processed and is retained.</li> <li>■ dbmsaq.EXPIRED: The message has been moved to the exception queue.</li> </ul>
sender_id	<p>The application-sender identification specified at enqueue time by the message producer. Sender id is of type aq\$_agent.</p> <p>Sender name is required for secure queues at enqueue time. This must be a valid AQ agent name, mapped to the database user performing the enqueue operation, through <code>dbms_aqadm.enable_db_access</code> procedure call. Sender address and protocol should not be specified.</p> <p>The Sender id in the message properties returned at dequeue time may have a sender address if the message was propagated from another queue. The value of the address is the <code>source_queue</code>, source database name if it was a remote database [format <code>source_queue@source_database_name</code>]</p>
original_msgid	<p>This parameter is used by Oracle Streams AQ for propagating messages.</p>
transaction_group	<p>Specifies the <code>transaction_group</code> for the dequeued message. Messages belonging to the same transaction group will have the same value for this attribute. This attribute is only set by the <code>DBMS_AQ.DEQUEUE_ARRAY</code>. This attribute cannot be used to set the transaction group of a message through <code>DBMS_AQ.ENQUEUE</code> or <code>DBMS_AQ.ENQUEUE_ARRAY</code> calls.</p>
user_property	<p>This optional attribute is used to store additional information about the payload.</p>

## MESSAGE\_PROPERTIES\_ARRAY\_T Type

This type is used by `dbms_aq.enqueue_array` and `dbms_aq.dequeue_array` calls to hold the set of message properties. Each element in the `payload_array` should have a corresponding element in the `MESSAGE_PROPERTIES_ARRAY_T` `VARRAY`.

**See Also:** ["MESSAGE\\_PROPERTIES\\_T Type"](#) on page 171-18

### Syntax

```
TYPE MESSAGE_PROPERTIES_ARRAY_T IS VARRAY (2147483647)
 OF MESSAGE_PROPERTIES_T;
```

## MSGID\_ARRAY\_T Type

The `msgid_array_t` type is used in `dbms_aq.enqueue_array` and `dbms_aq.dequeue_array` calls to hold the set of message IDs that correspond to the enqueued or dequeued messages.

### Syntax

```
TYPE MSGID_ARRAY_T IS TABLE OF RAW(16) INDEX BY BINARY_INTEGER
```



---

## Database URI TYPEs

Oracle supports the `UriType` family of types that can be used to store and query Uri-refs inside the database. The `UriType` itself is an abstract object type and the `HTTPURITYPE`, `XDBURITYPE` and `DBURITYPE` are subtypes of it.

You can create a `UriType` column and store instances of the `DBURITYPE`, `XDBURITYPE` or the `HTTPURITYPE` inside of it. You can also define your own subtypes of the `UriType` to handle different URL protocols.

Oracle also provides a `UriFactory` package that can be used as a factory method to automatically generate various instances of these `UriTypes` by scanning the prefix, such as `http://` or `/oradb`. You can also register your subtype and provide the prefix that you support. For instance, if you have written a subtype to handle the gopher protocol, you can register the prefix `gopher://` to be handled by your subtype. The `UriFactory` will then generate your subtype instance for any URL starting with that prefix.

This chapter contains the following topics:

- [Summary of URITYPE Supertype Subprograms](#)
- [Summary of HTTPURITYPE Subtype Subprograms](#)
- [Summary of DBURITYPE Subtype Subprograms](#)
- [Summary of XDBURITYPE Subtype Subprograms](#)
- [Summary of URIFACTORY Package Subprograms](#)

**See Also:**

- *Oracle XML DB Developer's Guide*

## Summary of URITYPE Supertype Subprograms

The `UriType` is the abstract super type. It provides a standard set of functions to get the value pointed to by the URI. The actual implementation of the protocol must be defined by the subtypes of this type.

Instances of this type cannot be created directly. However, you can create columns of this type and store subtype instances in it, and also select from columns without knowing the instance of the URL stored.

**Table 172–1** *URITYPE Type Subprograms*

Method	Description
<a href="#">GETBLOB</a> on page 172-3	Returns the <code>BLOB</code> located at the address specified by the URL.
<a href="#">GETCLOB</a> on page 172-4	Returns the <code>CLOB</code> located at the address specified by the URL.
<a href="#">GETCONTENTTYPE</a> on page 172-5	Returns the URL, in escaped format, stored inside the <code>UriType</code> instance.
<a href="#">GETEXTERNALURL</a> on page 172-6	Returns the URL, in escaped format, stored inside the <code>UriType</code> instance.
<a href="#">GETURL</a> on page 172-7	Returns the URL, in non-escaped format, stored inside the <code>UriType</code> instance.
<a href="#">GETXML</a> on page 172-8	Returns the <code>XMLType</code> located at the address specified by the URL.

## GETBLOB

This function returns the BLOB located at the address specified by the URL. This function can be overridden in the subtype instances. The options are described in the following table.

Syntax	Description
MEMBER FUNCTION GETBLOB() RETURN BLOB;	This function returns the BLOB located at the address specified by the URL.
MEMBER FUNCTION GETBLOB( CONTENT OUT VARCHAR2) RETURN BLOB;	This function returns the BLOB located at the address specified by the URL and the content type.
FUNCTION GETBLOB( CSID IN NUMBER) RETURN BLOB;	This function returns the BLOB located at the address specified by the URL in the specified character set.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.
CSID	(IN)	Character set id of the document. Must be a valid Oracle id and greater than 0; otherwise returns an error

## GETCLOB

This function returns the CLOB located at the address specified by the URL. This function can be overridden in the subtype instances. This function returns either a permanent CLOB or a temporary CLOB. If a temporary CLOB is returned, it must be freed. The options are described in the following table.

Syntax	Description
MEMBER FUNCTION GETCLOB() RETURN CLOB;	This function returns the CLOB located at the address specified by the URL.
MEMBER FUNCTION GETCLOB( CONTENT OUT VARCHAR2) RETURN CLOB;	This function returns the CLOB located at the address specified by the URL and the content type.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.



## GETCONTENTTYPE

This function returns the content type of the document pointed to by the URI. This function can be overridden in the subtype instances. This function returns the content type as `VARCHAR2`.

### **Syntax**

```
MEMBER FUNCTION GETCONTENTTYPE()
RETURN VARCHAR2;
```

## GETEXTERNALURL

This function returns the URL, in escaped format, stored inside the `UriType` instance. The subtype instances override this member function to provide additional semantics. For instance, the `HTTPURITYPE` function does not store the prefix `http://` in the URL itself. When generating the external URL, it appends the prefix and generates it. For this reason, use the `getExternalUrl` function or the `getUrl` function to get to the URL value instead of using the attribute present in the `UriType` instance.

### Syntax

```
MEMBER FUNCTION GETEXTERNALURL()
RETURN VARCHAR2;
```

## GETURL

This function returns the URL, in non-escaped format, stored inside the `UriType` instance. The subtype instances override this member function to provide additional semantics. For instance, the `HTTPURITYPE` function does not store the prefix `http://` in the URL itself. When generating the external URL, it appends the prefix and generates it. For this reason, use the `getExternalUrl` function or the `getUrl` function to get to the URL value instead of using the attribute present in the `UriType` instance.

### Syntax

```
MEMBER FUNCTION GETURL()
RETURN VARCHAR2;
```

## GETXML

This function returns the `XMLType` located at the address specified by the URL. This function can be overridden in the subtype instances. The options are described in the following table.

Syntax	Description
<pre>MEMBER FUNCTION GETXML() RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL.
<pre>MEMBER FUNCTION GETXML(   CONTENT OUT VARCHAR2) RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL and the content type.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.

---

## Summary of HTTPURITYPE Subtype Subprograms

The `HTTPURITYPE` is a subtype of the `UriType` that provides support for the HTTP protocol. This uses the `UTL_HTTP` package underneath to access the HTTP URLs. Proxy and secure wallets are not supported in this release.

**Table 172–2 HTTPURITYPE Type Subprorgams**

Method	Description
<a href="#">CREATEURI</a> on page 172-10	Creates an instance of <code>HTTPURITYPE</code> from the given URI.
<a href="#">GETBLOB</a> on page 172-11	Returns the <code>BLOB</code> located at the address specified by the URL.
<a href="#">GETCLOB</a> on page 172-12	Returns the <code>CLOB</code> located at the address specified by the URL.
<a href="#">GETCONTENTTYPE</a> on page 172-13	Returns the content type of the document pointed to by the URI.
<a href="#">GETEXTERNALURL</a> on page 172-14	Returns the URL, in escaped format, stored inside the <code>UriType</code> instance.
<a href="#">GETRUL</a> on page 172-15	Returns the URL, in non-escaped format, stored inside the <code>UriType</code> instance.
<a href="#">GETXML</a> on page 172-16	Returns the <code>XMLType</code> located at the address specified by the URL.
<a href="#">HTTPURITYPE</a> on page 172-17	Creates an instance of <code>HTTPURITYPE</code> from the given URI.

## CREATEURI

This static function constructs a `HTTPURITYPE` instance. The `HTTPURITYPE` instance does not contain the prefix `http://` in the stored URL.

### Syntax

```
STATIC FUNCTION CREATEURI(
 URL IN VARCHAR2)
RETURN HTTPURITYPE;
```

---

Parameter	IN / OUT	Description
-----------	----------	-------------

---

URL	( IN )	The URL string containing a valid HTTP URL; escaped format.
-----	--------	-------------------------------------------------------------

---

## GETBLOB

This function returns the BLOB located at the address specified by the HTTP URL.

Syntax	Description
MEMBER FUNCTION GETBLOB() RETURN BLOB;	This function returns the BLOB located at the address specified by the HTTP URL.
MEMBER FUNCTION GETBLOB( CONTENT OUT VARCHAR2) RETURN BLOB;	This function returns the BLOB located at the address specified by the HTTP URL and the content type.
FUNCTION GETBLOB( CSID IN NUMBER) RETURN BLOB;	This function returns the BLOB located at the address specified by the URL in the specified character set.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.
CSID	(IN)	Character set id of the document. Must be a valid Oracle id and greater than 0; otherwise returns an error.

## GETCLOB

This function returns the CLOB located by the HTTP URL address. If a temporary CLOB is returned, it must be freed.

Syntax	Description
MEMBER FUNCTION GETCLOB() RETURN CLOB;	Returns the CLOB located at the address specified by the HTTP URL.
MEMBER FUNCTION GETCLOB( CONTENT OUT VARCHAR2) RETURN CLOB;	Returns the CLOB located at the address specified by the HTTP URL and the content type.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.



## GETCONTENTTYPE

Returns the content type of the document pointed to by the URI.

### **Syntax**

```
MEMBER FUNCTION GETCONTENTTYPE()
RETURN VARCHAR2;
```

## GETEXTERNALURL

This function returns the URL, in escaped format, stored inside the `HTTPURITYPE` instance. The subtype instances override this member function. The `HTTPURITYPE` function does not store the prefix `http://`, but generates it for the external URL.

### Syntax

```
MEMBER FUNCTION GETEXTERNALURL()
RETURN VARCHAR2;
```

## GETRUL

This function returns the URL, in non-escaped format, stored inside the HTTPURITYPE instance.

### Syntax

```
MEMBER FUNCTION GETURL()
RETURN VARCHAR2;
```

## GETXML

This function returns the `XMLType` located at the address specified by the URL. An error is thrown if the address does not point to a valid XML document.

Syntax	Description
<pre>MEMBER FUNCTION GETXML() RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL.
<pre>MEMBER FUNCTION GETXML(     CONTENT OUT VARCHAR2) RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL and the content type.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.

## HTTPURITYPE

This constructs a `HTTPURITYPE` instance. The `HTTPURITYPE` instance does not contain the prefix `http://` in the stored URL.

### Syntax

```
CONSTRUCTOR FUNCTION HTTPURITYPE(
 URL IN VARCHAR2);
```

Parameter	IN / OUT	Description
URL	(IN)	The URL string containing a valid HTTP URL. The URL string is expected in escaped format. For example, non-url characters are represented as the hexadecimal value for the UTF-8 encoding of those characters.

## Summary of DBURITYPE Subtype Subprograms

The `DBURITYPE` is a subtype of the `UriType` that provides support for `DBUri`-refs. A `DBUri`-ref is an intra-database URL that can be used to reference any row or row-column data in the database. The URL is specified as an XPath expression over a XML visualization of the database. The schemas become elements which contain tables and views. These tables and view further contain the rows and columns inside them.

**Table 172–3** *DBURITYPE Type Subprograms*

Method	Description
<a href="#">CREATEURI</a> on page 172-19	Constructs a <code>DBURITYPE</code> instance.
<a href="#">DBURITYPE</a> on page 172-20	Creates an instance of <code>DBURITYPE</code> from the given URI.
<a href="#">GETBLOB</a> on page 172-21	Returns the <code>BLOB</code> located at the address specified by the <code>DBURITYPE</code> instance.
<a href="#">GETCLOB</a> on page 172-22	Returns the <code>CLOB</code> located at the address specified by the <code>DBURITYPE</code> instance.
<a href="#">GETCONTENTTYPE</a> on page 172-23	Returns the content type of the document pointed to by the URI.
<a href="#">GETEXTERNALURL</a> on page 172-24	Returns the URL, in escaped format, stored inside the <code>DBURITYPE</code> instance.
<a href="#">GETURL</a> on page 172-25	Returns the URL, in non-escaped format, stored inside the <code>DBURITYPE</code> instance.
<a href="#">GETXML</a> on page 172-26	Returns the <code>XMLType</code> located at the address specified by the URL.

## CREATEURI

This static function constructs a `DBURITYPE` instance. Parses the URL given and creates a `DBURITYPE` instance.

### Syntax

```
STATIC FUNCTION CREATEURI(
 URL IN VARCHAR2)
RETURN DBURITYPE;
```

Parameter	IN / OUT	Description
URL	(IN)	The URL string, in escaped format, containing a valid <code>DBURITYPE</code> .

## DBURITYPE

This constructs a `DBURITYPE` instance.

### Syntax

```
CONSTRUCTOR FUNCTION DBURITYPE(
 URL IN VARCHAR2);
```

Parameter	IN / OUT	Description
URL	(IN)	The URL string containing a valid <code>DBURITYPE</code> . The URL string is expected in escaped format. For example, non-URL characters are represented as the hexadecimal value for the UTF-8 encoding of those characters.



## GETBLOB

This function returns the BLOB located at the address specified by the URL. The options are described in the following table.

Syntax	Description
MEMBER FUNCTION GETBLOB() RETURN BLOB;	This function returns the BLOB located at the address specified by the URL.
MEMBER FUNCTION GETBLOB( CONTENT OUT VARCHAR2) RETURN BLOB;	This function returns the BLOB located at the address specified by the URL and the content type.
FUNCTION GETBLOB( CSID IN NUMBER) RETURN BLOB;	This function returns the BLOB located at the address specified by the URL in the specified character set.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.
CSID	(IN)	Character set id of the document. Must be a valid Oracle id and greater than 0; otherwise returns an error.

## GETCLOB

This function returns the CLOB located at the address specified by the `DBURITYPE` instance. If a temporary CLOB is returned, it must be freed. The document returned may be an XML document or a text document. When the `DBUri-ref` identifies an element in the XPath, the result is a well-formed XML document. On the other hand, if it identifies a text node, then what is returned is only the text content of the column or attribute. The options are described in the following table.

Syntax	Description
<code>MEMBER FUNCTION GETCLOB() RETURN CLOB;</code>	Returns the CLOB located at the address specified by the <code>DBURITYPE</code> instance.
<code>MEMBER FUNCTION GETCLOB(     CONTENT OUT VARCHAR2) RETURN CLOB;</code>	Returns the CLOB located at the address specified by the <code>DBURITYPE</code> instance and the content type.

Parameter	IN / OUT	Description
<code>CONTENT</code>	<code>(OUT)</code>	Content type of the document to which URI is pointing.

## GETCONTENTTYPE

This function returns the content type of the document pointed to by the URI.

### **Syntax**

```
MEMBER FUNCTION GETCONTENTTYPE()
RETURN VARCHAR2;
```

## GETEXTERNALURL

This function returns the URL, in escaped format, stored inside the `DBURITYPE` instance. The `DBUri` servlet URL that processes the `DBURITYPE` has to be appended before using the escaped URL in web pages.

### Syntax

```
MEMBER FUNCTION GETEXTERNALURL()
RETURN VARCHAR2;
```

## GETURL

This function returns the URL, in non-escaped format, stored inside the `DBURITYPE` instance.

### Syntax

```
MEMBER FUNCTION GETURL()
RETURN VARCHAR2;
```

## GETXML

This function returns the `XMLType` located at the address specified by the URL. The options are described in the following table.

Syntax	Description
<pre>MEMBER FUNCTION GETXML( RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL.
<pre>MEMBER FUNCTION GETXML(     CONTENT OUT VARCHAR2) RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL and the content type.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.

---

## Summary of XDBURITYPE Subtype Subprograms

XDBURITYPE is a new subtype of URIType. It provides a way to expose documents in the Oracle XML DB hierarchy as URIs that can be embedded in any URIType column in a table. The URL part of the URI is the hierarchical name of the XML document it refers to. The optional fragment part uses the XPath syntax, and is separated from the URL part by '#'. The more general XPointer syntax for specifying a fragment is not currently supported.

**Table 172–4 XDBURITYPE Type Subprograms**

Method	Description
<a href="#">CREATEURI</a> on page 172-28	Returns the <code>UriType</code> corresponding to the specified URL.
<a href="#">GETBLOB</a> on page 172-29	Returns the <code>BLOB</code> corresponding to the contents of the document specified by the <code>XDBURITYPE</code> instance.
<a href="#">GETCLOB</a> on page 172-22	Returns the <code>CLOB</code> corresponding to the contents of the document specified by the <code>XDBURITYPE</code> instance.
<a href="#">GETCONTENTTYPE</a> on page 172-31	Returns the content type of the document pointed to by the URI.
<a href="#">GETEXTERNALURL</a> on page 172-24	Returns the URL, in escaped format, stored inside the <code>XDBURITYPE</code> instance.
<a href="#">GETURL</a> on page 172-25	Returns the URL, in non-escaped format, stored inside the <code>XDBURITYPE</code> instance.
<a href="#">GETXML</a> on page 172-34	Returns the <code>XMLType</code> corresponding to the contents of the document specified by the URL.
<a href="#">XDBURITYPE</a> on page 172-35	Creates an instance of <code>XDBURITYPE</code> from the given URI.

## CREATEURI

This static function constructs a `XDBURITYPE` instance. Parses the URL given and creates a `XDBURITYPE` instance.

### Syntax

```
STATIC FUNCTION CREATEURI(
 URL IN VARCHAR2)
RETURN XDBURITYPE
```

Parameter	IN / OUT	Description
URL	(IN)	The URL string, in escaped format, containing a valid <code>XDBURITYPE</code> .



## GETBLOB

This function returns the BLOB located at the address specified by the XDBURITYPE instance. The options are described in the following table.

Syntax	Description
MEMBER FUNCTION GETBLOB() RETURN BLOB;	This function returns the BLOB located at the address specified by the URL.
MEMBER FUNCTION GETBLOB( CONTENT OUT VARCHAR2) RETURN BLOB;	This function returns the BLOB located at the address specified by the URL and the content type.
FUNCTION GETBLOB( CSID IN NUMBER) RETURN BLOB;	This function returns the BLOB located at the address specified by the URL in the specified character set.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.
CSID	(IN)	Character set id of the document. Must be a valid Oracle id and greater than 0; otherwise returns an error.

## GETCLOB

This function returns the CLOB located at the address specified by the `XDBURITYPE` instance. If a temporary CLOB is returned, it must be freed. The options are described in the following table.

Syntax	Description
<code>MEMBER FUNCTION GETCLOB() RETURN CLOB;</code>	Returns the CLOB located at the address specified by the <code>XDBUirType</code> instance.
<code>MEMBER FUNCTION GETCLOB(   CONTENT OUT VARCHAR2) RETURN CLOB;</code>	Returns the CLOB located at the address specified by the <code>XDBUirType</code> instance and the content type.

Parameter	IN / OUT	Description
<code>CONTENT</code>	<code>(OUT)</code>	Content type of the document to which URI is pointing.

## GETCONTENTTYPE

This function returns the content type of the document pointed to by the URI. This function returns the content type as `VARCHAR2`.

### Syntax

```
MEMBER FUNCTION GETCONTENTTYPE()
RETURN VARCHAR2;
```

## GETEXTERNALURL

This function returns the URL, in escaped format, stored inside the `XDBURITYPE` instance.

### Syntax

```
MEMBER FUNCTION GETEXTERNALURL()
RETURN VARCHAR2;
```

## GETURL

This function returns the URL, in non-escaped format, stored inside the XDBURITYPE instance.

### Syntax

```
MEMBER FUNCTION GETURL()
RETURN VARCHAR2;
```

## GETXML

This function returns the `XMLType` located at the address specified by the URL. The options are described in the following table.

Syntax	Description
<pre>MEMBER FUNCTION GETXML(     RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL.
<pre>MEMBER FUNCTION GETXML(     CONTENT OUT VARCHAR2) RETURN XMLTYPE;</pre>	This function returns the <code>XMLType</code> located at the address specified by the URL and the content type.

Parameter	IN / OUT	Description
CONTENT	(OUT)	Content type of the document to which URI is pointing.

## XDBURITYPE

This constructs a XDBURITYPE instance.

### Syntax

```
CONSTRUCTOR FUNCTION XDBURITYPE(
 URL IN VARCHAR2);
```

Parameter	IN / OUT	Description
URL	(IN)	The URL string containing a valid XDBurType. The URL string is expected in escaped format. For example, non-URL characters are represented as the hexadecimal value for the UTF-8 encoding of those characters.

---

## Summary of URIFACTORY Package Subprograms

The `UriFactory` package contains factory methods that can be used to generate the appropriate instance of the URI types without having to hard code the implementation in the program.

The `UriFactory` package also provides the ability to register new subtypes of the `UriType` to handle various other protocols. For example, you can invent a new protocol `ecom://` and define a subtype of the `UriType` to handle that protocol and register it with `UriFactory`. After that any factory method would generate the new subtype instance if it sees the `ecom://` prefix.

**Table 172–5** *URIFACTORY Type Subprograms*

Method	Description
<a href="#">GETURL</a> on page 172-37	Returns the correct URL handler for the given URL string.
<a href="#">ESCAPEURI</a> on page 172-38	Returns a URL in escaped format.
<a href="#">UNESCAPEURI</a> on page 172-39	Returns a URL in unescaped format.
<a href="#">REGISTERURLHANDLER</a> on page 172-40	Registers a particular type name for handling a particular URL.
<a href="#">UNREGISTERURLHANDLER</a> on page 172-41	Unregisters a URL handler.



## GETURL

This factory method returns the correct URL handler for the given URL string. It returns a subtype instance of the `UriType` that can handle the protocol. By default, it always creates an `XDBURITYPE` instance, if it cannot resolve the URL. A URL handler can be registered for a particular prefix using the [REGISTERURLHANDLER](#) function. If the prefix matches, [GETURL](#) would then use that subtype.

### Syntax

```
FUNCTION GETURL(
 URL IN VARCHAR2)
RETURN URITYPE;
```

Parameter	IN / OUT	Description
URL	(IN)	The URL string, in escaped format, containing a valid HTTP URL.

## ESCAPEURI

This function returns a URL in escaped format. The subtype instances override this member function to provide additional semantics. For instance, the `HTTPURITYPE` does not store the prefix `http://` in the URL itself. When generating the external URL, it appends the prefix and generates it. For this reason, use the [GETEXTERNALURL](#) function or the [GETURL](#) function to get to the URL value instead of using the attribute present in the `UriType`.

### Syntax

```
MEMBER FUNCTION ESCAPEURI()
RETURN VARCHAR2;
```

Parameter	IN / OUT	Description
URL	(IN)	The URL string to be returned in escaped format.

## UNESCAPEURI

This function returns a URL in unescaped format. This function is the reverse of the [ESCAPEURI](#) function. This function scans the string and converts any non-URL hexadecimal characters into the equivalent UTF-8 characters. Since the return type is a VARCHAR2, the characters would be converted into the equivalent characters as defined by the database character set.

### Syntax

```
FUNCTION UNESCAPEURI()
RETURN VARCHAR2;
```

Parameter	IN / OUT	Description
URL	( IN )	The URL string to be returned in unescaped format.

## REGISTERURLHANDLER

Registers a particular type name for handling a particular URL. The type specified must be valid and must be a subtype of the `UriType` or one of its subtypes. It must also implement the `createUrl` static member function. This function is called by the `GETURL` function to generate an instance of the type. The `stripprefix` parameter indicates that the prefix must be stripped off before calling this function.

### Syntax

```
PROCEDURE REGISTERURLHANDLER(
 PREFIX IN VARCHAR2,
 SCHEMANAME IN VARCHAR2,
 TYPENAME IN VARCHAR2,
 IGNORECASE IN BOOLEAN := TRUE,
 STRIPPREFIX IN BOOLEAN := TRUE);
```

Parameter	IN / OUT	Description
PREFIX	(IN)	The prefix to handle; for example, <code>http://</code> .
SCHEMANAME	(IN)	Name of the schema where the type resides; case sensitive.
TYPENAME	(IN)	The name of the type to handle the URL; case sensitive.
IGNORECASE	(IN)	Ignore case when matching prefixes.
STRIPPREFIX	(IN)	Strip prefix before generating the instance of the type.

## UNREGISTERURLHANDLER

This procedure unregisters a URL handler. This only unregisters user registered handler prefixes and not predefined system prefixes such as `http://`.

### Syntax

```
PROCEDURE UNREGISTERURLHANDLER(
 PREFIX IN VARCHAR2);
```

---

Parameter	IN / OUT	Description
PREFIX	(IN)	The prefix to be unregistered.

---



PL/SQL users can use the `DBMS_AQ` package to enqueue and dequeue messages from JMS queues. The JMS types member and static functions and procedures in this chapter are needed to populate JMS messages for enqueueing or to interpret a dequeued JMS message.

This chapter contains these topics:

- [Using JMS Types](#)
  - [Overview](#)
  - [Java Versus PL/SQL Data Types](#)
  - [More on Bytes, Stream and Map Messages](#)
  - [Upcasting and Downcasting Between General and Specific Messages](#)
  - [JMS Types Error Reporting](#)
  - [Oracle JMS Type Constants](#)
  - [CONVERT\\_JMS\\_SELECTOR](#)
- [Summary of JMS Types](#)

---

## Using JMS Types

- [Overview](#)
- [Java Versus PL/SQL Data Types](#)
- [More on Bytes, Stream and Map Messages](#)
- [Upcasting and Downcasting Between General and Specific Messages](#)
- [JMS Types Error Reporting](#)
- [Oracle JMS Type Constants](#)
- [JMS Types Error Reporting](#)
- [Oracle JMS Type Constants](#)
- [CONVERT\\_JMS\\_SELECTOR](#)

### Overview

Java Message Service (JMS) is a well known public standard interface for accessing messaging systems. Oracle JMS (OJMS) implements JMS based on Oracle Streams Advanced Queuing (AQ) and a relational database system (RDBMS). Messages are stored in queues as OJMS specific ADTs. Java clients use OJMS packages to enqueue, dequeue, and manipulate these messages.

PL/SQL users, on the other hand, use the `DBMS_AQ` package to enqueue and dequeue JMS messages and the member functions in this chapter to populate and interpret them. Oracle Streams AQ offers such member functions for the following JMS ADTs:

- `aq$_jms_header`
- `aq$_jms_message`
- `aq$_jms_text_message`
- `aq$_jms_bytes_message`
- `aq$_jms_map_message`
- `aq$_jms_stream_message`

In addition to these populating and interpreting member functions, Oracle Streams AQ offers:



- Casting between `aq$_jms_message` and other message ADTs.
- PL/SQL stored procedures for converting JMS selectors to equivalent Oracle Streams AQ rules

## Java Versus PL/SQL Data Types

Data types do not map one-to-one between PL/SQL and Java.

Some Java types, such as `BYTE` and `SHORT`, are not present in PL/SQL. PL/SQL type `INT` was chosen to represent these types. If a PL/SQL `INT` value intended to hold a Java `BYTE` or `SHORT` value exceeds the corresponding range Java enforces, an out-of-range error is thrown.

Other Java types have more than one counterpart in PL/SQL with different capabilities. A Java `String` can be represented by both `VARCHAR2` and `CLOB`, but `VARCHAR2` has a maximum limit of 4000 bytes. When retrieving `TEXT` data from map, stream, and bytes message types, a `CLOB` is always returned. When updating the map, stream and bytes message types, users can submit either a `VARCHAR2` or `CLOB`.

Similarly, a Java `BYTE ARRAY` can be represented by both `RAW` and `BLOB`, with `RAW` having a maximum size of 32767. When retrieving `BYTE ARRAY` data from map, stream, and bytes message types, a `BLOB` is always returned. When updating the map, stream and bytes message types, users can submit either a `RAW` or `BLOB`.

**See Also:** JMS specification 3.11.3, Conversion Provided by `StreamMessage` and `MapMessage`

## New JMS Support in Oracle Database 10g

In Oracle Database 10g, a new `AQ$_JMS_VALUE` ADT has been added in the `SYS` schema for OJMS PL/SQL users. It is specifically used to implement the `read_object` procedure of `aq$_jms_stream_message` and `get_object` procedure of `aq$_jms_map_message`, to mimic the Java general object class `Object`. `AQ$_JMS_VALUE` ADT can represent any data type that JMS `StreamMessage` and `MapMessage` can hold.

The collection ADT `AQ$_JMS_NAMEARRAY` was added for the `getNames` method of `MapMessage`. It holds an array of names.

In this release the ADT `AQ$_JMS_EXCEPTION` was added to represent a Java exception thrown in an OJMS JAVA stored procedure on the PL/SQL side. Now

you can retrieve a Java exception thrown by an OJMS stored procedure and analyze it on the PL/SQL side.

## More on Bytes, Stream and Map Messages

Oracle uses Java stored procedure to implement some of the procedures of `AQ$_MAP_MESSAGE`, `AQ$_JMS_STREAM_MESSAGE`, and `AQ$_JMS_BYTES_MESSAGE` types. These types have some common functionalities that are different from `AQ$_JMS_TEXT_MESSAGE` type. This section discusses these common functionalities.

This section contains these topics:

- [Using Java Stored Procedures to Encode and Decode Oracle Streams AQ Messages](#)
- [Read-Only and Write-Only Modes Enforced for Stream and Bytes Messages](#)
- [Differences Between Bytes and Stream Messages](#)
- [Getting and Setting Bytes, Map, and Stream Messages as RAW Bytes](#)

## Using Java Stored Procedures to Encode and Decode Oracle Streams AQ Messages

The major difference between map, stream, bytes, and other messages is that the message payload is encoded as a byte stream by JAVA. Retrieving and updating these payloads in PL/SQL therefore requires Oracle JAVA stored procedures.

A message payload is stored in two places during processing. On the PL/SQL side it is stored as the data members of a JMS message ADT, and on the Jserv side it is stored as a static variable. (Jserv is the JVM inside Oracle Database.) When the payload is processed, the payload data is first transformed to a static variable on the Jserv side. Once the static variable is initialized, all later updates on the message payload are performed on this static variable. At the end of processing, payload data is flushed back to the PL/SQL side.

Oracle provides member procedures that maintain the status of the Jserv static variable and enforce rules when calling these member procedures. These procedures are in the following ADTs:

- `aq$_jms_bytes_message`
- `aq$_jms_map_message`
- `aq$_jms_stream_message`

## Initialize the Jserv Static Variable

Before you make any other calls to manipulate the payload data, the Jserv static variable must be properly initialized. This is done by calling the `prepare` or `clear_body` procedure. The `prepare` procedure uses the payload data in PL/SQL ADTs to initialize the static variable, while `clear_body` initializes the static variable to an empty payload (empty hashtable or stream).

---

---

**Note:** It is important to call the `prepare` or `clear_body` procedure before any other calls to properly initialize the Jserv static variables. Usually these two methods are called once at the beginning. But they can be called multiple times for one message. Any call of these two methods without first calling the `flush` procedure wipes out all updates made to the messages.

---

---

## Get the Payload Data Back to PL/SQL

Calling the `flush` procedure synchronizes changes made to the Jserv static variable back to the PL/SQL ADTs. The `flush` call is required when you want the changes made to be reflected in the ADT payload. It is important to synchronize the changes back to the ADT, because it is the ADT payload that matters.

## Garbage Collect the Static Variable

The `clean` procedure forces garbage collection of the static variable. It is there to do cleanup and free JVM memory. You can avoid memory leaks by doing it immediately after finishing processing the message.

## Use a Message Store: A Static Variable Collection

Instead of a single static variable, Oracle uses a collection of static variables to process the message payload on the Jserv side. This collection is called the message store. Each map, bytes, or stream message type has its own message store within one session.

Oracle uses the operation ID parameter to locate the correct static variable to work on within the message store. Initialization calls such as `prepare` and `clear_body` give users an operation ID, which is used in later message access.

After users complete message processing, they must call the `clean` procedure with the operation ID to clean up the message store. This avoids possible memory leaks. The `clean_all` static procedures of message ADTs `aq$_jms_bytes_message`,

`aq$_jms_map_message`, and `aq$_jms_stream_message` clean up all static variables of their corresponding message stores.

### Typical Calling Sequences

This section describes typical procedures for retrieving and populating messages.

Here is a typical procedure for retrieving messages

1. Call `prepare` for a message.  
This call also gives you an operation ID if you do not specify one.
2. Call multiple retrieving procedures with the provided operation ID.
3. Call the `clean` procedure with the provided operation ID.

Here is a typical procedure for populating messages:

1. Call `clear_body` for a message.  
For `aq$_jms_map_message`, you can also call `prepare` to update the message based on the existing payload. This call also gives you an operation ID if you do not specify one.
2. Call multiple updating procedures with the provided operation ID.
3. Call the `flush` method with the provided operation ID.
4. Call the `clean` procedure with the provided operation ID.

### Read-Only and Write-Only Modes Enforced for Stream and Bytes Messages

According to the JMS specification, when a message is received, its body is read-only. Users can call the `clear_body` method to make the body writable. This method erases the current message body and sets the message body to be empty.

The OJMS JAVA API follows the rule set by JMS specification. In updating the JMS message ADTs in PL/SQL, however, Oracle enforces the rule selectively:

- Map messages  
The restriction is relaxed, because adding more entries on top of a existing map payload is a convenient way for users to update the payload. Therefore there are no read-only or write-only modes for map messages.
- Stream and bytes messages  
The restriction is not relaxed, because these payloads use a stream when reading and writing data. It is difficult to update the payload while in the

middle of a stream. Oracle enforces read-only and write-only modes in processing stream and bytes message payloads. Calling the `prepare` procedure initializes the message payload in read-only mode. Calling the `clear_body` procedure initializes the message payload in write-only mode.

Calling the `reset` procedure resets the pointer to the beginning of the stream and switches the mode from write-only to read-only. The `reset` procedure keeps the updates made to the message payload in the `Jserv` static variable.

The `prepare` procedure, on the other hand, overwrites the message payload in the `Jserv` static variable with the payload in the PL/SQL ADT.

Oracle provides member function `get_mode` for users to query the mode.

## Differences Between Bytes and Stream Messages

Member functions of bytes messages are not exactly the same as those of stream messages. Stream messages are encoded using Java `ObjectOutputStream` and bytes messages are encoded using Java `DataOutputStream`. In stream messages each primitive type is written and read as a Java Object, but in a bytes message they are written and read as raw bytes according to the encoding mechanism of `DataOutputStream`.

For stream messages, the `read_bytes` method works on a stream of bytes to the end of the byte array field written by the corresponding `write_bytes` method. The `read_bytes` method of bytes message works on a stream of bytes to the end of the whole byte stream. This is why the `read_bytes` member procedure of `aq$_bytes_message` also requires a `length` parameter to tell how long it is to read.

You will not see a type conversion error raised by bytes message, because bytes messages do not support type conversion.

Methods `get_unsigned_byte` and `get_unsigned_short` are available for bytes messages, but not for stream messages. This is because stream messages read Java objects, and there are no Java objects as unsigned bytes or unsigned shorts.

Methods `read_string` and `write_string` methods are not available for bytes messages. The bytes message ADT must enforce some character encoding. It has methods `read_utf` and `write_utf` which support utf-8 encoding.

---

---

**Note:** All data written by bytes messages use `DataOutputStream` as the basis. See JDK API documentation [JavaSoft.com](http://JavaSoft.com) for details on how the data is encoded into bytes.

---

---

## Getting and Setting Bytes, Map, and Stream Messages as RAW Bytes

The payloads of bytes, map, and stream message types are stored as either RAW or BLOB in the database. In this release Oracle Streams AQ provides the following member functions to set and get these payloads as raw bytes without interpreting them:

```
set_bytes(payload IN BLOB)
set_bytes(payload IN RAW)
get_bytes(payload OUT BLOB)
get_bytes(payload OUT RAW)
```

These functions were provided for bytes messages in Oracle9i Release 2 (9.2).

## Upcasting and Downcasting Between General and Specific Messages

OJMS ADT `aq$_jms_message` is used to represent a general message, so that different types of messages can reside on the same Oracle Streams AQ queue. Oracle Streams AQ supports retrieving and populating of `aq$_jms_message` by supporting upcasting and downcasting between this ADT and ADTs of specific message types.

To read an `aq$_jms_message`, you must first downcast it to a specific message type according to its `message_type` field

To populate an `aq$_jms_message`, you must first populate a specific message and upcast it to `aq$_jms_message`. This avoids copying all member functions of other specific message ADTs to this ADT. It also guarantees that the manipulation of this ADT is consistent with other specific message ADTs.

## JMS Types Error Reporting

Table 173–1 lists Oracle JMS types related errors.

**Table 173–1 Oracle JMS Types Errors**

ORA error number	dbms_jms_plsql package constants	Explanation
ORA-24190	ERROR_DATA_OVERFLOW	The payload data exceeds the size that an out parameter can hold. For example, the <code>get_text</code> procedure with a <code>VARCHAR2</code> parameter of <code>aq\$_jms_text_message</code> or <code>get_bytes</code> procedure with a <code>RAW</code> parameter of <code>aq\$_jms_bytes_message</code> .
ORA-24191	ERROR_PROP_NAME_EXIST	Setting a property that is previous set
ORA-24192	ERROR_PROP_NAME_NULL	Occurs when setting a property with null property name.
ORA-24193	ERROR_EXCEED_RANGE	PL/SQL number type exceeds the valid range of the respective Java type. For example <code>set_byte_property</code> , <code>set_short_property</code> of <code>aq\$_jms_head</code> ADT; <code>set_byte</code> and <code>set_short</code> of <code>aq\$_jms_map_message</code> ADT; <code>write_byte</code> and <code>write_short</code> of <code>aq\$_jms_stream_message</code> and <code>aq\$_jms_bytes_message</code> ADT.
ORA-24194	ERROR_TYPE_MISMATCH	The type conversion between the Java type of the retrieving method and the Java type of a field of the payload is not valid.
ORA-24195	ERROR_MAP_TOO_LARGE	The size of the map exceeds the <code>aq\$_jms_namearray</code> ADT capacity. The current size limit is 1024. You can use the <code>get_names</code> function with <code>offset</code> and <code>length</code> parameters to retrieve the name array in multiple small chunks.
ORA-24196	ERROR_WRONG_MODE	The message payload is being accessed with a wrong access mode. For example, trying to read a message payload with write-only mode or trying to write a message payload with the read-only mode.

**Table 173–1 (Cont.) Oracle JMS Types Errors**

ORA error number	dbms_jms_plsql package constants	Explanation
ORA-24197	ERROR_JAVA_EXCEPTION	<p>ORA-24197 error is raised when a Java exception is raised that does not fit in any of the other error categories. You can use the <code>get_exception</code> static procedure of <code>aq\$_jms_map_message</code>, <code>aq\$_jms_bytes_message</code>, and <code>aq\$_jms_stream_message</code> to retrieve the exception information last thrown by the Java stored procedure.</p> <p>A single static variable is used to store the last exception and is overwritten if another exception is thrown before you retrieve it. A new ADT <code>aq\$_jms_exception</code> is created to represent the exception information on the PL/SQL side.</p>
ORA-24198	ERROR_INVALID_ID	An invalid operation ID is being provided to access a message.
ORA-24199	ERROR_STORE_OVERFLOW	The number of messages (with the same type) that users are trying to manipulate exceeds the size of the message store on the Java stored procedure side. The current size of the store is 20. It unusual to need to manipulate more than 20 messages at the same time. A common mistake is to forget to call the <code>clean</code> procedure after using one message. The <code>clean</code> procedure frees the message slot for use by other messages attempting access.

## Oracle JMS Type Constants

This section lists some useful constants when dealing with message type functions.

### DBMS\_AQ Package Constants

DBMS\_AQ package constants specify different types of JMS messages. They are useful when dealing with general message types during upcasting and downcasting or constructing a general message with a specific message type:

```
JMS_TEXT_MESSAGE CONSTANT BINARY_INTEGER;
JMS_BYTES_MESSAGE CONSTANT BINARY_INTEGER;
JMS_STREAM_MESSAGE CONSTANT BINARY_INTEGER;
JMS_MAP_MESSAGE CONSTANT BINARY_INTEGER;
JMS_OBJECT_MESSAGE CONSTANT BINARY_INTEGER;
```

### SYS.DBMS\_JMS\_PLSQL Package Constants

SYS.DBMS\_JMS\_PLSQL package constants are new in Oracle Database 10g.



These constants specify the mode of message payload. They are useful when interpreting the mode of the message payload returned from the `get_mode` function:

```
MESSAGE_ACCESS_READONLY CONSTANT PLS_INTEGER;
MESSAGE_ACCESS_WRITEONLY CONSTANT PLS_INTEGER;
```

These constants specify the ADT type of an Oracle Streams AQ queue. They are useful during the conversion of JMS selectors to Oracle Streams AQ rules:

```
DESTPLOAD_JMSTYPE CONSTANT PLS_INTEGER;
DESTPLOAD_USERADT CONSTANT PLS_INTEGER;
DESTPLOAD_ANYDATA CONSTANT PLS_INTEGER;
```

These constants specify the type of data that can be held by a `aq$_jms_value` type. They are useful when interpreting the `aq$_jms_value` returned by the `get_` object method of `AQ$_JMS_MAP_MESSAGE` or `read_object` method of `AQ$_JMS_STREAM_MESSAGE`:

```
DATA_TYPE_BYTE CONSTANT PLS_INTEGER;
DATA_TYPE_SHORT CONSTANT PLS_INTEGER;
DATA_TYPE_INTEGER CONSTANT PLS_INTEGER;
DATA_TYPE_LONG CONSTANT PLS_INTEGER;
DATA_TYPE_FLOAT CONSTANT PLS_INTEGER;
DATA_TYPE_DOUBLE CONSTANT PLS_INTEGER;
DATA_TYPE_BOOLEAN CONSTANT PLS_INTEGER;
DATA_TYPE_CHARACTER CONSTANT PLS_INTEGER;
DATA_TYPE_STRING CONSTANT PLS_INTEGER;
DATA_TYPE_BYTES CONSTANT PLS_INTEGER;
DATA_TYPE_UNSIGNED_BYTE CONSTANT PLS_INTEGER;
DATA_TYPE_UNSIGNED_SHORT CONSTANT PLS_INTEGER;
```

These constants specify the error number of the ORA errors that can be raised by the functions of message type ADTs. They are useful in user error handlers:

```
ERROR_DATA_OVERFLOW CONSTANT PLS_INTEGER := -24190;
ERROR_PROP_NAME_EXIST CONSTANT PLS_INTEGER := -24191;
ERROR_PROP_NAME_NULL CONSTANT PLS_INTEGER := -24192;
ERROR_EXCEED_RANGE CONSTANT PLS_INTEGER := -24193;
ERROR_TYPE_MISMATCH CONSTANT PLS_INTEGER := -24194;
ERROR_MAP_TOO_LARGE CONSTANT PLS_INTEGER := -24195;
ERROR_WRONG_MODE CONSTANT PLS_INTEGER := -24196;
ERROR_JAVA_EXCEPTION CONSTANT PLS_INTEGER := -24197;
ERROR_INVALID_ID CONSTANT PLS_INTEGER := -24198;
ERROR_STORE_OVERFLOW CONSTANT PLS_INTEGER := -24199;
```

## CONVERT\_JMS\_SELECTOR

Oracle Database includes three stored procedures to help users convert JMS selectors into Oracle Streams AQ rules. These rules can be used in `ADD_SUBSCRIBER` operations as subscriber rules or in `DEQUEUE` operations as dequeue conditions. These procedures are in the `SYS.dbms_jms_plsql` package.

### Convert with Minimal Specification

The first procedure assumes the destination payload type is one of the JMS ADTs whose corresponding constant is `dbms_jms_plsql.DESTPLOAD_JMSTYPE` and also assumes that the J2EE compliant mode is true.

#### Syntax

```
Function convert_jms_selector(selector IN VARCHAR2) RETURN VARCHAR2
```

#### Returns

The converted Oracle Streams AQ rule or null if there is any conversion error.

#### Exceptions

ORA-24197 if the Java stored procedure throws an exception during execution.

### Convert with Destination Payload Type Specified

The second procedure takes one more parameter: `dest_pload_type`. The conversion of a JMS selector to an Oracle Streams AQ rule happens only if this parameter is `SYS.dbms_jms_plsql.DESTPLOAD_JMSTYPE` or `SYS.dbms_jms_plsql.DESTPLOAD_ANYDATA`. The function returns exactly the same `VARCHAR2` value as the selector parameter if the `dest_pload_type` parameter is `SYS.dbms_jms_plsql.DESTPLOAD_USERADT`. The function returns null if `dest_pload_type` parameter is none of these three constants.

This function assumes that the J2EE compliant mode is true.

#### Syntax

```
Function convert_jms_selector(
 selector IN VARCHAR2,
 dest_pload_type IN PLS_INTEGER)
RETURN VARCHAR2
```

### Returns

The converted Oracle Streams AQ rule or null if there is any conversion error.

### Exceptions

ORA-24197 if the Java stored procedure throws an exception during execution.

## Convert with Destination Payload Type and Compliant Mode Specified

The third procedure takes a `dest_pload_type` parameter and a `compliant` parameter. The conversion of a JMS selector to an Oracle Streams AQ rule happens only if the `dest_pload_type` parameter is `SYS.dbms_jms_plsql.DESTPLOAD_JMSTYPE` or `SYS.dbms_jms_plsql.DESTPLOAD_ANYDATA`. The function returns exactly the same `VARCHAR2` value as the selector parameter if the `dest_pload_type` parameter is `SYS.dbms_jms_plsql.DESTPLOAD_USERADT`. The function returns null if the `dest_pload_type` parameter is none of these three constants.

The `compliant` parameter controls if the conversion is in J2EE compliant mode or not. The noncompliant conversion of a JMS selector is for backward compatibility.

### Syntax

```
Function convert_jms_selector(
 selector IN VARCHAR2,
 dest_pload_type IN PLS_INTEGER,
 compliant IN BOOLEAN)
```

### Returns

The converted Oracle Streams AQ rule or null if there is any conversion error.

### Exceptions

ORA-24197 if the Java stored procedure throws an exception during execution.

---

## Summary of JMS Types

- `SYS.AQ$_JMS_MESSAGE` Type
- `SYS.AQ$_JMS_TEXT_MESSAGE` Type
- `SYS.AQ$_JMS_BYTES_MESSAGE` Type
- `SYS.AQ$_JMS_MAP_MESSAGE` Type
- `SYS.AQ$_JMS_STREAM_MESSAGE` Type
- `SYS.AQ$_JMS_OBJECT_MESSAGE` Type
- `SYS.AQ$_JMS_NAMESARRAY` Type
- `SYS.AQ$_JMS_VALUE` Type
- `SYS.AQ$_JMS_EXCEPTION` Type

## SYS.AQ\$\_JMS\_MESSAGE Type

This ADT type can represent any of five different JMS message types: text message, bytes message, stream message, map message, or object message. Queues created using this ADT can therefore store all five types of JMS messages.

This section contains these topics:

- [CONSTRUCT Static Functions](#)
- [Cast Methods](#)
- [JMS Header Methods](#)
- [System Properties Methods](#)
- [User Properties Methods](#)
- [Payload Methods](#)

### Syntax

```
TYPE AQ$_JMS_MESSAGE AS OBJECT(
 header aq$_jms_header,
 senderid varchar2(100),
 message_type INT,
 text_len INT,
 bytes_len INT,
 text_vc varchar2(4000),
 bytes_raw raw(2000),
 text_lob clob,
 bytes_lob blob,
 STATIC FUNCTION construct (mtype IN INT)
 RETURN aq$_jms_message,
 STATIC FUNCTION construct (text_msg IN aq$_jms_text_message)
 RETURN aq$_jms_message,
 STATIC FUNCTION construct (bytes_msg IN aq$_jms_bytes_message)
 RETURN aq$_jms_message,
 STATIC FUNCTION construct (stream_msg IN aq$_jms_stream_message)
 RETURN aq$_jms_message,
 STATIC FUNCTION construct (map_msg IN aq$_jms_map_message)
 RETURN aq$_jms_message,
 STATIC FUNCTION construct (object_msg IN aq$_jms_object_message)
 RETURN aq$_jms_message,
 MEMBER FUNCTION cast_to_bytes_msg RETURN aq$_jms_bytes_message,
 MEMBER FUNCTION cast_to_map_msg RETURN aq$_jms_map_message,
```

---

```
MEMBER FUNCTION cast_to_object_msg RETURN aq$_jms_object_message,
MEMBER FUNCTION cast_to_stream_msg RETURN aq$_jms_stream_message,
MEMBER FUNCTION cast_to_text_msg RETURN aq$_jms_text_message,
MEMBER PROCEDURE set_replyto (replyto IN sys.aq$_agent),
MEMBER PROCEDURE set_type (type IN VARCHAR),
MEMBER PROCEDURE set_userid (userid IN VARCHAR),
MEMBER PROCEDURE set_appid (appid IN VARCHAR),
MEMBER PROCEDURE set_groupid (groupid IN VARCHAR),
MEMBER PROCEDURE set_groupseq (groupseq IN INT),
MEMBER FUNCTION get_replyto RETURN sys.aq$_agent,
MEMBER FUNCTION get_type RETURN VARCHAR,
MEMBER FUNCTION get_userid RETURN VARCHAR,
MEMBER FUNCTION get_appid RETURN VARCHAR,
MEMBER FUNCTION get_groupid RETURN VARCHAR,
MEMBER FUNCTION get_groupseq RETURN INT,
MEMBER PROCEDURE clear_properties,
MEMBER PROCEDURE set_boolean_property (property_name IN VARCHAR,
property_value IN BOOLEAN),
MEMBER PROCEDURE set_byte_property (property_name IN VARCHAR,
property_value IN INT),
MEMBER PROCEDURE set_double_property (property_name IN VARCHAR,
property_value IN DOUBLE PRECISION),
MEMBER PROCEDURE set_float_property (property_name IN VARCHAR,
property_value IN FLOAT),
MEMBER PROCEDURE set_int_property (property_name IN VARCHAR,
property_value IN INT),
MEMBER PROCEDURE set_long_property (property_name IN VARCHAR,
property_value IN NUMBER),
MEMBER PROCEDURE set_short_property (property_name IN VARCHAR,
property_value IN INT),
MEMBER PROCEDURE set_string_property (property_name IN VARCHAR,
property_value IN VARCHAR),
MEMBER FUNCTION get_boolean_property (property_name IN VARCHAR) RETURN BOOLEAN,
MEMBER FUNCTION get_byte_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_double_property (property_name IN VARCHAR)
RETURN DOUBLE PRECISION,
MEMBER FUNCTION get_float_property (property_name IN VARCHAR) RETURN FLOAT,
MEMBER FUNCTION get_int_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_long_property (property_name IN VARCHAR) RETURN NUMBER,
MEMBER FUNCTION get_short_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_string_property (property_name IN VARCHAR) RETURN VARCHAR,
MEMBER PROCEDURE set_text (payload IN VARCHAR2),
MEMBER PROCEDURE set_text (payload IN CLOB),
MEMBER PROCEDURE set_bytes (payload IN RAW),
MEMBER PROCEDURE set_bytes (payload IN BLOB),
```

```

MEMBER PROCEDURE get_text (payload OUT VARCHAR2),
MEMBER PROCEDURE get_text (payload OUT CLOB),
MEMBER PROCEDURE get_bytes (payload OUT RAW),
MEMBER PROCEDURE get_bytes (payload OUT BLOB));

```

## CONSTRUCT Static Functions

There are six CONSTRUCT static functions in this type.

### **STATIC FUNCTION construct (mtype IN INT) RETURN aq\$\_jms\_message**

Creates an instance of `aq$_jms_message`, which can hold a specific type of JMS message (TextMessage, BytesMessage, MapMessage, StreamMessage or ObjectMessage). The message type of the created `aq$_jms_message` instance depends on the `mtype` parameter passed to the construct method. Once a message has been constructed, it can be used to store JMS messages of the type it has been constructed to hold.

The `mtype` parameter must be one of the following constants described in "[Oracle JMS Type Constants](#)" on page 173-10:

```

DBMS_AQ.JMS_TEXT_MESSAGE
DBMS_AQ.JMS_BYTES_MESSAGE
DBMS_AQ.JMS_STREAM_MESSAGE
DBMS_AQ.JMS_MAP_MESSAGE
DBMS_AQ.JMS_OBJECT_MESSAGE

```

### **STATIC FUNCTION construct (text\_msg IN aq\$\_jms\_text\_message) RETURN aq\$\_jms\_message**

Creates an `aq$_jms_message` from an `aq$_jms_text_message`.

### **STATIC FUNCTION construct (bytes\_msg IN aq\$\_jms\_bytes\_message) RETURN aq\$\_jms\_message;**

Creates an `aq$_jms_message` from an `aq$_jms_bytes_message`.

### **STATIC FUNCTION construct (stream\_msg IN aq\$\_jms\_stream\_message) RETURN aq\$\_jms\_message;**

Creates an `aq$_jms_message` from an `aq$_jms_stream_message`.

### **STATIC FUNCTION construct (map\_msg IN aq\$\_jms\_map\_message) RETURN aq\$\_jms\_message;**

Creates an `aq$_jms_message` from an `aq$_jms_map_message`.

### **STATIC FUNCTION construct (object\_msg IN aq\$\_jms\_object\_message) RETURN**

**aq\$\_jms\_message;**

Creates an aq\$\_jms\_message from an aq\$\_jms\_object\_message.

**Cast Methods****cast\_to\_bytes\_msg RETURN aq\$\_jms\_bytes\_message**

Casts an aq\$\_jms\_message to an aq\$\_jms\_bytes\_message. Returns an aq\$\_jms\_bytes\_message or null if the message\_type attribute of the aq\$\_jms\_message is not DBMS\_AQ.JMS\_BYTES\_MESSAGE. This function raises ORA-24198 if the message\_type field of the aq\$\_jms\_message is not DBMS\_AQJMS.JMS\_BYTES\_MESSAGE.

**cast\_to\_map\_msg RETURN aq\$\_jms\_map\_message**

Casts an aq\$\_jms\_message to an aq\$\_jms\_map\_message. Returns an aq\$\_jms\_map\_message or null if the message\_type attribute of the aq\$\_jms\_message is not DBMS\_AQ.JMS\_MAP\_MESSAGE. This function raises ORA-24198 if the message\_type field of the aq\$\_jms\_message is not DBMS\_AQJMS.JMS\_MAP\_MESSAGE.

**cast\_to\_object\_msg RETURN aq\$\_jms\_object\_message**

Casts an aq\$\_jms\_message to an aq\$\_jms\_object\_message. Returns an aq\$\_jms\_object\_message or null if the message\_type attribute of the aq\$\_jms\_message is not DBMS\_AQ.JMS\_OBJECT\_MESSAGE. This function raises ORA-24198 if the message\_type field of the aq\$\_jms\_message is not DBMS\_AQJMS.JMS\_OBJECT\_MESSAGE.

**cast\_to\_stream\_msg RETURN aq\$\_jms\_stream\_message**

Casts an aq\$\_jms\_message to an aq\$\_jms\_stream\_message. Returns an aq\$\_jms\_stream\_message or null if the message\_type attribute of the aq\$\_jms\_message is not DBMS\_AQ.JMS\_STREAM\_MESSAGE. This function raises ORA-24198 if the message\_type field of the aq\$\_jms\_message is not DBMS\_AQJMS.JMS\_STREAM\_MESSAGE.

**cast\_to\_text\_msg RETURN aq\$\_jms\_text\_message**

Casts an aq\$\_jms\_message to an aq\$\_jms\_text\_message. Returns an aq\$\_jms\_text\_message or null if the message\_type attribute of the aq\$\_jms\_message is not DBMS\_AQ.JMS\_TEXT\_MESSAGE. This function raises ORA-24198 if the message\_type field of the aq\$\_jms\_message is not DBMS\_AQJMS.JMS\_TEXT\_MESSAGE.



## JMS Header Methods

**set\_replyto (replyto IN sys.aq\$\_agent)**

Sets the `replyto` parameter, which corresponds to `JMSReplyTo`.

**get\_replyto RETURN sys.aq\$\_agent**

Returns `replyto`, which corresponds to `JMSReplyTo`.

**set\_type (type IN VARCHAR)**

Sets the JMS type, which can be any text and corresponds to `JMSType`.

**get\_type RETURN VARCHAR**

Returns `type`, which corresponds to `JMSType`.

## System Properties Methods

**set\_userid (userid IN VARCHAR)**

Sets `userid`, which corresponds to `JMSXUserID`.

**set\_appid (appid IN VARCHAR)**

Sets `appid`, which corresponds to `JMSXAppID`.

**set\_groupid (groupid IN VARCHAR)**

Sets `groupid`, which corresponds to `JMSXGroupID`.

**set\_groupseq (groupseq IN INT)**

Sets `groupseq`, which corresponds to `JMSXGroupSeq`.

**get\_userid RETURN VARCHAR**

Returns `userid`, which corresponds to `JMSXUserID`.

**get\_appid RETURN VARCHAR**

Returns `appid`, which corresponds to `JMSXAppID`.

**get\_groupid RETURN VARCHAR**

Returns `groupid`, which corresponds to `JMSXGroupID`.

**get\_groupseq RETURN VARCHAR**

Returns `groupseq`, which corresponds to `JMSXGroupSeq`.

## User Properties Methods

### **clear\_properties**

Clears all user properties. This procedure does not affect system properties.

### **set\_boolean\_property (property\_name IN VARCHAR, property\_value IN BOOLEAN)**

Checks whether `property_name` is null or exists. If it is not null, the procedure stores `property_value` in an internal representation (a `NUMBER` type). Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

### **set\_byte\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If it is not null, the procedure checks whether `property_value` is within -128 to 127 (8-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `byte` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

### **set\_double\_property (property\_name IN VARCHAR, property\_value IN DOUBLE PRECISION)**

Checks whether `property_name` is null or exists. If it is not null, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

### **set\_float\_property (property\_name IN VARCHAR, property\_value IN FLOAT)**

Checks whether `property_name` is null or exists. If it is not null, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

### **set\_int\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If it is not null, the procedure checks whether `property_value` is within -2147483648 to 2147483647 (32-bits). This check is necessary because the `INT` datatype is 38 bits in PL/SQL and Oracle Database. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

### **set\_long\_property (property\_name IN VARCHAR, property\_value IN NUMBER)**

Checks whether `property_name` is null or exists. If it is not null, the procedure stores `property_value`. In PL/SQL and Oracle Database, the `NUMBER` datatype is 38 bits. In Java, the long datatype is 64 bits. Therefore, no range check is needed.

Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_short\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If it is not null, the procedure checks whether `property_value` is within -32768 to 32767 (16-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `short` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_string\_property (property\_name IN VARCHAR, property\_value IN VARCHAR)**

Checks whether `property_name` is null or exists. If it is not null, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**get\_boolean\_property (property\_name IN VARCHAR) RETURN BOOLEAN**

If the property with the corresponding property name passed in exists, and if it is a `BOOLEAN` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_byte\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `BYTE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_double\_property (property\_name IN VARCHAR) RETURN DOUBLE PRECISION**

If the property with the corresponding property name passed in exists, and if it is a `DOUBLE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_float\_property (property\_name IN VARCHAR) RETURN FLOAT**

If the property with the corresponding property name passed in exists, and if it is a `FLOAT` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_int\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `Integer` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_long\_property (property\_name IN VARCHAR) RETURN NUMBER**

If the property with the corresponding property name passed in exists, and if it is a `long` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_short\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `short` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_string\_property (property\_name IN VARCHAR) RETURN VARCHAR**

If the property with the corresponding property name passed in exists, and if it is a `STRING` property, then this function returns the value of the property. Otherwise it returns a null.

## Payload Methods

**set\_text (payload IN VARCHAR2)**

Sets the payload, a `VARCHAR2` value, to an internal representation.

**set\_text (payload IN CLOB),**

Sets the payload, a `CLOB` value, to an internal representation.

**set\_bytes (payload IN RAW)**

Sets the payload, a `RAW` value, to an internal representation.

**set\_bytes (payload IN BLOB)**

Sets the payload, a `BLOB` value, to an internal representation.

**get\_text (payload OUT VARCHAR2)**

Puts the internal representation of the payload into a `VARCHAR2` variable payload.

**get\_text (payload OUT CLOB)**

Puts the internal representation of the payload into a `CLOB` variable payload.

**get\_bytes (payload OUT RAW)**

Puts the internal representation of the payload into a `RAW` variable payload.

**get\_bytes (payload OUT BLOB)**

Puts the internal representation of the payload into a `BLOB` variable payload.

## SYS.AQ\$\_JMS\_TEXT\_MESSAGE Type

This type is the ADT used to store a `TextMessage` in an Oracle Streams AQ queue.

This section contains these topics:

- [CONSTRUCT Function](#)
- [JMS Header Methods](#)
- [System Properties Methods](#)
- [User Properties Methods](#)
- [Payload Methods](#)

### Syntax

```
TYPE AQ$_JMS_TEXT_MESSAGE AS OBJECT(
 header aq$_jms_header,
 text_len INT,
 text_vc varchar2(4000),
 text_lob clob,
 STATIC FUNCTION construct RETURN aq$_jms_text_message,
 MEMBER PROCEDURE set_replyto (replyto IN sys.aq$_agent),
 MEMBER PROCEDURE set_type (type IN VARCHAR),
 MEMBER FUNCTION get_replyto RETURN sys.aq$_agent,
 MEMBER FUNCTION get_type RETURN VARCHAR,
 MEMBER PROCEDURE set_userid (userid IN VARCHAR),
 MEMBER PROCEDURE set_appid (appid IN VARCHAR),
 MEMBER PROCEDURE set_groupid (groupid IN VARCHAR),
 MEMBER PROCEDURE set_groupseq (groupseq IN INT),
 MEMBER FUNCTION get_userid RETURN VARCHAR,
 MEMBER FUNCTION get_appid RETURN VARCHAR,
 MEMBER FUNCTION get_groupid RETURN VARCHAR,
 MEMBER FUNCTION get_groupseq RETURN INT,
 MEMBER PROCEDURE clear_properties,
 MEMBER PROCEDURE set_boolean_property(property_name IN VARCHAR,
 property_value IN BOOLEAN),
 MEMBER PROCEDURE set_byte_property (property_name IN VARCHAR,
 property_value IN INT),
 MEMBER PROCEDURE set_double_property (property_name IN VARCHAR,
 property_value IN DOUBLE PRECISION),
 MEMBER PROCEDURE set_float_property (property_name IN VARCHAR,
 property_value IN FLOAT),
 MEMBER PROCEDURE set_int_property (property_name IN VARCHAR,
```

```
 property_value IN INT),
MEMBER PROCEDURE set_long_property (property_name IN VARCHAR,
 property_value IN NUMBER),
MEMBER PROCEDURE set_short_property (property_name IN VARCHAR,
 property_value IN INT),
MEMBER PROCEDURE set_string_property (property_name IN VARCHAR,
 property_value IN VARCHAR),
MEMBER FUNCTION get_boolean_property (property_name IN VARCHAR)
 RETURN BOOLEAN,
MEMBER FUNCTION get_byte_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_double_property (property_name IN VARCHAR)
 RETURN DOUBLE PRECISION,
MEMBER FUNCTION get_float_property (property_name IN VARCHAR) RETURN FLOAT,
MEMBER FUNCTION get_int_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_long_property (property_name IN VARCHAR) RETURN NUMBER,
MEMBER FUNCTION get_short_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_string_property (property_name IN VARCHAR)
 RETURN VARCHAR,
MEMBER PROCEDURE set_text (payload IN VARCHAR2),
MEMBER PROCEDURE set_text (payload IN CLOB),
MEMBER PROCEDURE get_text (payload OUT VARCHAR2),
MEMBER PROCEDURE get_text (payload OUT CLOB));
```

## CONSTRUCT Function

### **STATIC FUNCTION construct RETURN aq\$\_jms\_text\_message**

Creates an empty aq\$\_jms\_text\_message.

## JMS Header Methods

### **set\_replyto (replyto IN sys.aq\$\_agent)**

Sets the `replyto` parameter, which corresponds to `JMSReplyTo` in JMS.

### **set\_type (type IN VARCHAR)**

Sets the JMS type, which can be any text, and which corresponds to `JMSType` in JMS.

### **get\_replyto RETURN sys.aq\$\_agent**

Returns `replyto`, which corresponds to `JMSReplyTo`.

### **get\_type RETURN VARCHAR**

Returns `type`, which corresponds to `JMSType`.

## System Properties Methods

**set\_userid (userid IN VARCHAR)**

Sets `userid`, which corresponds to `JMSXUserID` in JMS.

**set\_appid (appid IN VARCHAR)**

Sets `appid`, which corresponds to `JMSXAppID` in JMS.

**set\_groupid (groupid IN VARCHAR)**

Sets `groupid`, which corresponds to `JMSXGroupID` in JMS.

**set\_groupseq (groupseq IN INT)**

Sets `groupseq`, which corresponds to `JMSXGroupSeq` in JMS.

**get\_userid RETURN VARCHAR**

Returns `userid`, which corresponds to `JMSXUserID`.

**get\_appid RETURN VARCHAR**

Returns `appid`, which corresponds to `JMSXAppID`.

**get\_groupid RETURN VARCHAR**

Returns `groupid`, which corresponds to `JMSXGroupID`.

**get\_groupseq RETURN INT**

Returns `groupseq`, which corresponds to `JMSXGroupSeq`.

## User Properties Methods

**clear\_properties**

Clears all user properties. This procedure does not affect system properties.

**set\_boolean\_property (property\_name IN VARCHAR, property\_value IN BOOLEAN)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value` in an internal representation. Raises exception `ORA-24191` if the `property_name` exists or `ORA-24192` if the `property_name` is null.

**set\_byte\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within `-128` to `127` (8-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `BYTE` datatype. Raises exception

ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_double\_property (property\_name IN VARCHAR, property\_value IN DOUBLE PRECISION)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_float\_property (property\_name IN VARCHAR, property\_value IN FLOAT)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_int\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -2147483648 to 2147483647 (32-bits). This check is necessary because in PL/SQL and Oracle Database, the `INT` datatype is 38 bits. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_long\_property (property\_name IN VARCHAR, property\_value IN NUMBER)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. In PL/SQL and Oracle Database, the `NUMBER` datatype is 38 bits. In Java, the `long` datatype is 64 bits. Therefore, no range check is needed. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_short\_property property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -32768 to 32767 (16-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `short` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_string\_property (property\_name IN VARCHAR, property\_value IN VARCHAR)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.



**get\_boolean\_property (property\_name IN VARCHAR) RETURN BOOLEAN**

If the property with the corresponding property name passed in exists, and if it is a `BOOLEAN` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_byte\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `BYTE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_double\_property (property\_name IN VARCHAR) RETURN DOUBLE PRECISION**

If the property with the corresponding property name passed in exists, and if it is a `DOUBLE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_float\_property (property\_name IN VARCHAR) RETURN FLOAT**

If the property with the corresponding property name passed in exists, and if it is a `FLOAT` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_int\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `Integer` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_long\_property (property\_name IN VARCHAR) RETURN NUMBER**

If the property with the corresponding property name passed in exists, and if it is a `long` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_short\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `short` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_string\_property (property\_name IN VARCHAR) RETURN VARCHAR**

If the property with the corresponding property name passed in exists, and if it is a `STRING` property, then this function returns the value of the property. Otherwise it returns a null.

## Payload Methods

**set\_text (payload IN VARCHAR2)**

Sets the payload, a VARCHAR2 value, to an internal representation.

**set\_text (payload IN CLOB)**

Sets the payload, a CLOB value, to an internal representation.

**get\_text (payload OUT VARCHAR2)**

Puts the internal representation of the payload into a VARCHAR2 variable payload.

**get\_text (payload OUT CLOB)**

Puts the internal representation of the payload into a CLOB variable payload.

## SYS.AQ\$\_JMS\_BYTES\_MESSAGE Type

This type is the ADT used to store a `BytesMessage` in an Oracle Streams AQ queue.

This section contains these topics:

- [CONSTRUCT Function](#)
- [JMS Header Methods](#)
- [System Properties Methods](#)
- [User Properties Methods](#)
- [Payload Methods](#)

### Syntax

```
TYPE AQ$_JMS_BYTES_MESSAGE AS OBJECT(
 header aq$_jms_header,
 bytes_len INT,
 bytes_raw raw(2000),
 bytes_lob blob,
 STATIC FUNCTION construct RETURN aq$_jms_bytes_message,
 MEMBER PROCEDURE set_replyto (replyto IN sys.aq$_agent),
 MEMBER PROCEDURE set_type (type IN VARCHAR),
 MEMBER FUNCTION get_replyto RETURN sys.aq$_agent,
 MEMBER FUNCTION get_type RETURN VARCHAR,
 MEMBER PROCEDURE set_userid (userid IN VARCHAR),
 MEMBER PROCEDURE set_appid (appid IN VARCHAR),
 MEMBER PROCEDURE set_groupid (groupid IN VARCHAR),
 MEMBER PROCEDURE set_groupseq (groupseq IN INT),
 MEMBER FUNCTION get_userid RETURN VARCHAR,
 MEMBER FUNCTION get_appid RETURN VARCHAR,
 MEMBER FUNCTION get_groupid RETURN VARCHAR,
 MEMBER FUNCTION get_groupseq RETURN INT,
 MEMBER PROCEDURE clear_properties,
 MEMBER PROCEDURE set_boolean_property(property_name IN VARCHAR,
 property_value IN BOOLEAN),
 MEMBER PROCEDURE set_byte_property (property_name IN VARCHAR,
 property_value IN INT),
 MEMBER PROCEDURE set_double_property (property_name IN VARCHAR,
 property_value IN DOUBLE PRECISION),
 MEMBER PROCEDURE set_float_property (property_name IN VARCHAR,
 property_value IN FLOAT),
```

---

```
MEMBER PROCEDURE set_int_property (property_name IN VARCHAR,
 property_value IN INT),
MEMBER PROCEDURE set_long_property (property_name IN VARCHAR,
 property_value IN NUMBER),
MEMBER PROCEDURE set_short_property (property_name IN VARCHAR,
 property_value IN INT),
MEMBER PROCEDURE set_string_property (property_name IN VARCHAR,
 property_value IN VARCHAR),
MEMBER FUNCTION get_boolean_property (property_name IN VARCHAR) RETURN BOOLEAN,
MEMBER FUNCTION get_byte_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_double_property (property_name IN VARCHAR)
 RETURN DOUBLE PRECISION,
MEMBER FUNCTION get_float_property (property_name IN VARCHAR) RETURN FLOAT,
MEMBER FUNCTION get_int_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_long_property (property_name IN VARCHAR) RETURN NUMBER,
MEMBER FUNCTION get_short_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_string_property (property_name IN VARCHAR) RETURN VARCHAR,
MEMBER PROCEDURE set_bytes (payload IN RAW),
MEMBER PROCEDURE set_bytes (payload IN BLOB),
MEMBER PROCEDURE get_bytes (payload OUT RAW),
MEMBER PROCEDURE get_bytes (payload OUT BLOB),
MEMBER FUNCTION prepare (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER PROCEDURE reset (id IN PLS_INTEGER),
MEMBER PROCEDURE flush (id IN PLS_INTEGER),
MEMBER PROCEDURE clear_body (id IN PLS_INTEGER),
MEMBER PROCEDURE clean (id IN PLS_INTEGER),
STATIC PROCEDURE clean_all,
MEMBER FUNCTION get_mode (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_boolean (id IN PLS_INTEGER) RETURN BOOLEAN,
MEMBER FUNCTION read_byte (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_bytes (id IN PLS_INTEGER,
 value OUT NOCOPY BLOB, length IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_char (id IN PLS_INTEGER) RETURN CHAR,
MEMBER FUNCTION read_double (id IN PLS_INTEGER) RETURN DOUBLE PRECISION,
MEMBER FUNCTION read_float (id IN PLS_INTEGER) RETURN FLOAT,
MEMBER FUNCTION read_int (id IN PLS_INTEGER) RETURN INT,
MEMBER FUNCTION read_long (id IN PLS_INTEGER) RETURN NUMBER,
MEMBER FUNCTION read_short (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_unsigned_byte (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_unsigned_short (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER PROCEDURE read_utf (id IN PLS_INTEGER, value OUT NOCOPY CLOB),
MEMBER PROCEDURE write_boolean (id IN PLS_INTEGER, value IN BOOLEAN),
MEMBER PROCEDURE write_byte (id IN PLS_INTEGER, value IN PLS_INTEGER),
MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN RAW),
MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN BLOB),
```

```

MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN RAW,
 offset IN PLS_INTEGER, length IN PLS_INTEGER),
MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN BLOB,
 offset IN INT, length IN INT),
MEMBER PROCEDURE write_char (id IN PLS_INTEGER, value IN CHAR),
MEMBER PROCEDURE write_double (id IN PLS_INTEGER,
 value IN DOUBLE PRECISION),
MEMBER PROCEDURE write_float (id IN PLS_INTEGER, value IN FLOAT),
MEMBER PROCEDURE write_int (id IN PLS_INTEGER, value IN PLS_INTEGER),
MEMBER PROCEDURE write_long (id IN PLS_INTEGER, value IN NUMBER),
MEMBER PROCEDURE write_short (id IN PLS_INTEGER, value IN PLS_INTEGER),
MEMBER PROCEDURE write_utf (id IN PLS_INTEGER, value IN VARCHAR2),
MEMBER PROCEDURE write_utf (id IN PLS_INTEGER, value IN CLOB));

```

## CONSTRUCT Function

### **STATIC FUNCTION construct RETURN aq\$\_jms\_bytes\_message**

Creates an empty aq\$\_jms\_bytes\_message.

## JMS Header Methods

### **set\_replyto (replyto IN sys.aq\$\_agent)**

Sets the replyto parameter, which corresponds to JMSReplyTo in JMS.

### **set\_type (type IN VARCHAR)**

Sets the JMS type, which can be any text, and which corresponds to JMSType in JMS.

### **get\_replyto RETURN sys.aq\$\_agent**

Returns replyto, which corresponds to JMSReplyTo.

### **get\_type RETURN VARCHAR**

Returns type, which corresponds to JMSType.

## System Properties Methods

### **set\_userid (userid IN VARCHAR)**

Sets userid, which corresponds to JMSXUserID in JMS.

### **set\_appid (appid IN VARCHAR)**

Sets appid, which corresponds to JMSXAppID in JMS.

**set\_groupid (groupid IN VARCHAR)**

Sets `groupid`, which corresponds to `JMSXGroupID` in JMS.

**set\_groupseq (groupseq IN INT)**

Sets `groupseq`, which corresponds to `JMSXGroupSeq` in JMS.

**get\_userid RETURN VARCHAR**

Returns `userid`, which corresponds to `JMSXUserID`.

**get\_appid RETURN VARCHAR**

Returns `appid`, which corresponds to `JMSXAppID`.

**get\_groupid RETURN VARCHAR**

Returns `groupid`, which corresponds to `JMSXGroupID`.

**get\_groupseq RETURN NUMBER**

Returns `groupseq`, which corresponds to `JMSXGroupSeq`.

## User Properties Methods

**clear\_properties**

Clears all user properties. This procedure does not affect system properties.

**set\_boolean\_property (property\_name IN VARCHAR, property\_value IN BOOLEAN)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value` in an internal representation. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_byte\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -128 to 127 (8-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `BYTE` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_double\_property (property\_name IN VARCHAR, property\_value IN DOUBLE PRECISION)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_float\_property (property\_name IN VARCHAR, property\_value IN FLOAT)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_int\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -2147483648 to 2147483647 (32-bits). This check is necessary because in PL/SQL and Oracle Database, the `INT` datatype is 38 bits. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_long\_property (property\_name IN VARCHAR, property\_value IN NUMBER)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. In PL/SQL and Oracle Database, the `NUMBER` datatype is 38 bits. In Java, the `long` datatype is 64 bits. Therefore, no range check is needed. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_short\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -32768 to 32767 (16-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `short` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_string\_property (property\_name IN VARCHAR, property\_value IN VARCHAR)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**get\_boolean\_property (property\_name IN VARCHAR) RETURN BOOLEAN**

If the property with the corresponding property name passed in exists, and if it is a `BOOLEAN` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_byte\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `BYTE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_double\_property (property\_name IN VARCHAR) RETURN DOUBLE**

**PRECISION**

If the property with the corresponding property name passed in exists, and if it is a `DOUBLE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_float\_property (property\_name IN VARCHAR) RETURN FLOAT**

If the property with the corresponding property name passed in exists, and if it is a `FLOAT` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_int\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `Integer` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_long\_property (property\_name IN VARCHAR) RETURN NUMBER**

If the property with the corresponding property name passed in exists, and if it is a `long` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_short\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `short` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_string\_property (property\_name IN VARCHAR) RETURN VARCHAR**

If the property with the corresponding property name passed in exists, and if it is a `STRING` property, then this function returns the value of the property. Otherwise it returns a null.

## Payload Methods

**set\_bytes (payload in RAW)**

Sets the payload, a `RAW` value, to an internal representation.

**set\_bytes (payload in BLOB)**

Sets the payload, a `BLOB` value, to an internal representation.

**get\_bytes (payload out RAW)**

Puts the internal representation of the payload into a `RAW` variable payload. Raises exception `ORA-24190` if the length of the internal payload is more than 32767 (the maximum length of `RAW` in `PL/SQL`).



**get\_bytes (payload out BLOB)**

Puts the internal representation of the payload into a BLOB variable payload.

**prepare (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Takes the byte array stored in `aq$_jms_bytes_message` and decodes it as a Java object in the Java stored procedure. The result of the decoding is stored as a static variable in Jserv session memory. Parameter `id` is used to identify the slot where the Java object is stored in the Oracle Database JVM session memory. If `id` is null, then a new slot is created for this PL/SQL object. Subsequent JMS operations on the payload need to provide this operation ID.

This function also sets the message access mode to `MESSAGE_ACCESS_READONLY`. Subsequent calls of `write_XXX` procedure raise an ORA-24196 error. Users can call the `clear_body` procedure to set the message access mode to `MESSAGE_ACCESS_READONLY`.

This function raises ORA-24197 if the Java stored procedure throws an exception during execution, ORA-24198 if the operation ID is invalid, or ORA-24199 if the Java stored procedure message store overflows.

**reset (id IN PLS\_INTEGER)**

Resets the starting position of the stream to the beginning and puts the bytes message in read-only mode. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**flush (id IN PLS\_INTEGER)**

Takes the static variable in Jserv and synchronizes the content back to the `aq$_jms_bytes_message`. This procedure will not affect the underlying access mode. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**clear\_body (id IN PLS\_INTEGER)**

Sets the Java stored procedure static variable to empty payload. Parameter `id` is used to identify the slot where the Java object is stored in the Oracle Database JVM session memory. If `id` is null, a new slot is created for this PL/SQL object. Subsequent JMS operations on the payload need to provide this operation ID.

It also sets the message access mode to `MESSAGE_ACCESS_WRITEONLY`. Later calls of `read_XXX` procedure raise ORA-24196 error. Users can call the `reset` or `prepare` procedures to set the message access mode to `MESSAGE_ACCESS_READONLY`. Write-only and read-only modes affect only the payload functions of `AQ$_JMS_BYTES_MESSAGE`. They do not affect the header functions.

This function raises ORA-24197 if the Java stored procedure throws an exception during execution, ORA-24198 if the operation ID is invalid, or ORA-24199 if the Java stored procedure message store overflows.

**clean (id IN PLS\_INTEGER)**

Closes and cleans up the `DataInputStream` or `DataOutputStream` at the Java stored procedure side corresponding to the operation ID. It is very important to call this procedure to avoid memory leaks. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**clean\_all**

Closes and cleans up all the messages in the corresponding type of message store at the Java stored procedure side. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution.

**get\_mode (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Returns the current mode of this message. The return value is either `SYS.dbms_jms.plsql.MESSAGE_ACCESS_READONLY` or `SYS.dbms_jms.plsql.MESSAGE_ACCESS_WRITEONLY`. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**read\_boolean (id IN PLS\_INTEGER) RETURN BOOLEAN**

Reads a Boolean value from the bytes message and returns the Boolean value read. Null is returned if the end of the message stream has been reached. Parameter `id` is the operation ID. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_byte (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Reads a `BYTE` value from the bytes message and returns the `BYTE` value read. Null is returned if the end of the stream has been reached. Because there is no `BYTE` type in PL/SQL, Oracle Database uses `PLS_INTEGER` to represent a `BYTE`. Although PL/SQL users get a `PLS_INTEGER`, they are guaranteed that the value is in the Java `BYTE` value range. If this value is issued with a `write_byte` function, then there will not be an out of range error. Parameter `id` is the operation ID. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_bytes (id IN PLS\_INTEGER, value OUT NO COPYBLOB, length IN PLS\_**

**INTEGER) RETURN PLS\_INTEGER**

Reads length of the bytes from bytes message stream into value and returns the total number of bytes read. If there is no more data (because the end of the stream has been reached), then it returns -1. Raises exceptions ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_char (id IN PLS\_INTEGER) RETURN CHAR**

Reads a character value from the bytes message and returns the character value read. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_double (id IN PLS\_INTEGER) RETURN DOUBLE PRECISION**

Reads a double from the bytes message and returns the character value read. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_float (id IN PLS\_INTEGER) RETURN FLOAT**

Reads a float from the bytes message and returns the float read. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_int (id IN PLS\_INTEGER) RETURN INT**

Reads an `INT` from the bytes message and returns the `INT` read. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_long (id IN PLS\_INTEGER) RETURN NUMBER**

Reads a long from the bytes message and returns the long read. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_short (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Reads a short value from the bytes message and returns the short value read. Null is returned if the end of the stream has been reached. Because there is no short type in PL/SQL, `PLS_INTEGER` is used to represent a `BYTE`. Although PL/SQL users get

an `PLS_INTEGER`, they are guaranteed that the value is in the Java short value range. If this value is issued with a `write_short` function, then there will not be an out of range error. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_unsigned\_byte (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Reads an unsigned 8-bit number from the bytes message stream and returns the next byte from the bytes message stream, interpreted as an unsigned 8-bit number. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_unsigned\_short (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Reads an unsigned 16-bit number from the bytes message stream and returns the next two bytes from the bytes message stream, interpreted as an unsigned 16-bit integer. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_utf (id IN PLS\_INTEGER, value OUT NOCOPY CLOB)**

Reads a string that has been encoded using a UTF-8 format from the bytes message. Null is returned if the end of the stream has been reached. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_boolean (id IN PLS\_INTEGER, value IN BOOLEAN)**

Writes a Boolean to the bytes message stream as a 1-byte value. The value `true` is written as the value (byte)1. The value `false` is written as the value (byte)0. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_byte (id IN PLS\_INTEGER, value IN PLS\_INTEGER)**

Writes a byte to the bytes message. Because there is no `BYTE` type in PL/SQL, `PLS_INTEGER` is used to represent a `BYTE`. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN RAW)**

Writes an array of bytes to the bytes message. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN BLOB)**

Writes an array of bytes to the bytes message. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN RAW, offset IN PLS\_INTEGER, length IN PLS\_INTEGER)**

Writes a portion of a byte array to the bytes message stream. Parameter `offset` is the initial offset within the byte array. If the range `[offset, offset+length]` exceeds the boundary of the byte array value, then a Java `IndexOutOfBoundsException` exception is thrown in the Java stored procedure and this procedure raises error ORA-24197. The index starts from 0. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN BLOB, offset IN INT, length IN INT)**

Writes a portion of a byte array to the bytes message stream. Parameter `offset` is the initial offset within the byte array. If the range `[offset, offset+length]` exceeds the boundary of the byte array value, then a Java `IndexOutOfBoundsException` exception is thrown in the Java stored procedure and this procedure raises error ORA-24197. The index starts from 0. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_char (id IN PLS\_INTEGER, value IN CHAR)**

Writes a character value to the bytes message. If this value has multiple characters, it is the first character that is written. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_double (id IN PLS\_INTEGER, value IN DOUBLE PRECISION)**

Writes a double to the bytes message. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_float (id IN PLS\_INTEGER, value IN FLOAT)**

Writes a float to the bytes message. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_int (id IN PLS\_INTEGER, value IN PLS\_INTEGER)**

Writes an `INT` to the bytes message. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_long (id IN PLS\_INTEGER, value IN NUMBER)**

Writes a long to the bytes message. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_short (id IN PLS\_INTEGER, value IN PLS\_INTEGER)**

Writes a short to the bytes message as two bytes, high byte first. Because there is no short type in PL/SQL, `INT` is used to represent a short. Raises exception ORA-24193 if the parameter value exceeds the valid range, ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_utf (id IN PLS\_INTEGER, value IN VARCHAR2)**

Writes a string to the bytes message stream using UTF-8 encoding in a machine-independent manner. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_utf (id IN PLS\_INTEGER, value IN CLOB)**

Writes a string to the bytes message stream using UTF-8 encoding in a machine-independent manner. Raises exception ORA-24196 if the bytes message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

## SYS.AQ\$\_JMS\_MAP\_MESSAGE Type

This type is the ADT used to store a `MapMessage` in an Oracle Streams AQ queue.

This section contains these topics:

- [CONSTRUCT Function](#)
- [JMS Header Methods](#)
- [System Properties Methods](#)
- [User Properties Methods](#)
- [Payload Methods](#)

### Syntax

```

TYPE aq$_jms_map_message AS object(
 header aq$_jms_header,
 bytes_len int,
 bytes_raw raw(2000),
 bytes_lob blob,
 STATIC FUNCTION construct RETURN aq$_jms_map_message,
 MEMBER PROCEDURE set_replyto (replyto IN sys.aq$_agent),
 MEMBER PROCEDURE set_type (type IN VARCHAR),
 MEMBER FUNCTION get_replyto RETURN sys.aq$_agent,
 MEMBER FUNCTION get_type RETURN VARCHAR,
 MEMBER PROCEDURE set_userid (userid IN VARCHAR),
 MEMBER PROCEDURE set_appid (appid IN VARCHAR),
 MEMBER PROCEDURE set_groupid (groupid IN VARCHAR),
 MEMBER PROCEDURE set_groupseq (groupseq IN INT),
 MEMBER FUNCTION get_userid RETURN VARCHAR,
 MEMBER FUNCTION get_appid RETURN VARCHAR,
 MEMBER FUNCTION get_groupid RETURN VARCHAR,
 MEMBER FUNCTION get_groupseq RETURN INT,
 MEMBER PROCEDURE clear_properties,
 MEMBER PROCEDURE set_boolean_property(property_name IN VARCHAR,
 property_value IN BOOLEAN),
 MEMBER PROCEDURE set_byte_property (property_name IN VARCHAR,
 property_value IN INT),
 MEMBER PROCEDURE set_double_property (property_name IN VARCHAR,
 property_value IN DOUBLE PRECISION),
 MEMBER PROCEDURE set_float_property (property_name IN VARCHAR,
 property_value IN FLOAT),
 MEMBER PROCEDURE set_int_property (property_name IN VARCHAR,

```

```
 property_value IN INT),
MEMBER PROCEDURE set_long_property (property_name IN VARCHAR,
 property_value IN NUMBER),
MEMBER PROCEDURE set_short_property (property_name IN VARCHAR,
 property_value IN INT),
MEMBER PROCEDURE set_string_property (property_name IN VARCHAR,
 property_value IN VARCHAR),
MEMBER FUNCTION get_boolean_property (property_name IN VARCHAR) RETURN BOOLEAN,
MEMBER FUNCTION get_byte_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_double_property (property_name IN VARCHAR)
 RETURN DOUBLE PRECISION,
MEMBER FUNCTION get_float_property (property_name IN VARCHAR) RETURN FLOAT,
MEMBER FUNCTION get_int_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_long_property (property_name IN VARCHAR) RETURN NUMBER,
MEMBER FUNCTION get_short_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_string_property (property_name IN VARCHAR) RETURN VARCHAR,
MEMBER PROCEDURE set_bytes (payload IN RAW),
MEMBER PROCEDURE set_bytes (payload IN BLOB),
MEMBER PROCEDURE get_bytes (payload OUT RAW),
MEMBER PROCEDURE get_bytes (payload OUT BLOB),
MEMBER FUNCTION prepare (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER PROCEDURE flush (id IN PLS_INTEGER),
MEMBER PROCEDURE clear_body (id IN PLS_INTEGER),
MEMBER PROCEDURE clean (id IN PLS_INTEGER),
STATIC PROCEDURE clean_all,
MEMBER PROCEDURE set_boolean (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN BOOLEAN),
MEMBER PROCEDURE set_byte (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN PLS_INTEGER),
MEMBER PROCEDURE set_bytes (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN RAW),
MEMBER PROCEDURE set_bytes (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN RAW, offset IN INT, length IN INT),
MEMBER PROCEDURE set_bytes (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN BLOB),
MEMBER PROCEDURE set_bytes (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN BLOB, offset IN INT, length IN INT),
MEMBER PROCEDURE set_char (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN CHAR),
MEMBER PROCEDURE set_double (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN DOUBLE PRECISION),
MEMBER PROCEDURE set_float (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN FLOAT),
MEMBER PROCEDURE set_int (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN PLS_INTEGER),
```



```

MEMBER PROCEDURE set_long (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN NUMBER),
MEMBER PROCEDURE set_short (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN PLS_INTEGER),
MEMBER PROCEDURE set_string (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN VARCHAR2),
MEMBER PROCEDURE set_string (id IN PLS_INTEGER, name IN VARCHAR2,
 value IN CLOB),
MEMBER FUNCTION get_boolean (id IN PLS_INTEGER, name IN VARCHAR2)
 RETURN BOOLEAN,
MEMBER FUNCTION get_byte (id IN PLS_INTEGER, name IN VARCHAR2)
 RETURN PLS_INTEGER,
MEMBER PROCEDURE get_bytes (id IN PLS_INTEGER, name IN VARCHAR2,
 value OUT NOCOPY BLOB),
MEMBER FUNCTION get_char (id IN PLS_INTEGER, name IN VARCHAR2) RETURN CHAR,
MEMBER FUNCTION get_double (id IN PLS_INTEGER, name IN VARCHAR2)
 RETURN DOUBLE PRECISION,
MEMBER FUNCTION get_float (id IN PLS_INTEGER, name IN VARCHAR2) RETURN FLOAT,
MEMBER FUNCTION get_int (id IN PLS_INTEGER, name IN VARCHAR2)
 RETURN PLS_INTEGER,
MEMBER FUNCTION get_long (id IN PLS_INTEGER, name IN VARCHAR2)
 RETURN NUMBER,
MEMBER FUNCTION get_short (id IN PLS_INTEGER, name IN VARCHAR2)
 RETURN PLS_INTEGER,
MEMBER PROCEDURE get_string (id IN PLS_INTEGER, name IN VARCHAR2,
 value OUT NOCOPY CLOB),
MEMBER FUNCTION get_names (id IN PLS_INTEGER) RETURN aq$_jms_namearray,
MEMBER FUNCTION get_names (id IN PLS_INTEGER, names OUT aq$_jms_namearray,
 offset IN PLS_INTEGER, length IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER PROCEDURE get_object (id IN PLS_INTEGER, name IN VARCHAR2,
 value OUT NOCOPY AQ$_JMS_VALUE),
MEMBER FUNCTION get_size (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION item_exists (id IN PLS_INTEGER, name IN VARCHAR2)
 RETURN BOOLEAN);

```

## CONSTRUCT Function

### **STATIC FUNCTION construct RETURN aq\$\_jms\_map\_message**

Creates an empty aq\$\_jms\_map\_message object.

## JMS Header Methods

### **set\_replyto (replyto IN sys.aq\$\_agent)**

Sets the replyto parameter, which corresponds to JMSReplyTo in JMS.

**set\_type (type IN VARCHAR)**

Sets the JMS type, which can be any text, and which corresponds to JMSType in JMS.

**get\_replyto RETURN sys.aq\$\_agent**

Returns replyto, which corresponds to JMSReplyTo.

**get\_type RETURN VARCHAR**

Returns type, which corresponds to JMSType.

## System Properties Methods

**set\_userid (userid IN VARCHAR)**

Sets userid, which corresponds to JMSXUserID in JMS.

**set\_appid (appid IN VARCHAR)**

Sets appid, which corresponds to JMSXAppID in JMS.

**set\_groupid (groupid IN VARCHAR)**

Sets groupid, which corresponds to JMSXGroupID in JMS.

**set\_groupseq (groupseq IN INT)**

Sets groupseq, which corresponds to JMSXGroupSeq in JMS.

**get\_userid RETURN VARCHAR**

Returns userid, which corresponds to JMSXUserID.

**get\_appid RETURN VARCHAR**

Returns appid, which corresponds to JMSXAppID.

**get\_groupid RETURN VARCHAR**

Returns groupid, which corresponds to JMSXGroupID.

**get\_groupseq RETURN NUMBER**

Returns groupseq, which corresponds to JMSXGroupSeq.

## User Properties Methods

**clear\_properties**

Clears all user properties. This procedure does not affect system properties.

**set\_boolean\_property (property\_name IN VARCHAR, property\_value IN**

**BOOLEAN)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value` in an internal representation. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_byte\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -128 to 127 (8-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `BYTE` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_double\_property (property\_name IN VARCHAR, property\_value IN DOUBLE PRECISION)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_float\_property (property\_name IN VARCHAR, property\_value IN FLOAT)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_int\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -2147483648 to 2147483647 (32-bits). This check is necessary because in PL/SQL and Oracle Database, the `INT` datatype is 38 bits. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_long\_property (property\_name IN VARCHAR, property\_value IN NUMBER)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. In PL/SQL and Oracle Database, the `NUMBER` datatype is 38 bits. In Java, the `long` datatype is 64 bits. Therefore, no range check is needed. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_short\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -32768 to 32767 (16-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `short` datatype. Raises

exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_string\_property (property\_name IN VARCHAR, property\_value IN VARCHAR)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**get\_boolean\_property (property\_name IN VARCHAR) RETURN BOOLEAN**

If the property with the corresponding property name passed in exists, and if it is a `BOOLEAN` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_byte\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `BYTE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_double\_property (property\_name IN VARCHAR) RETURN DOUBLE PRECISION**

If the property with the corresponding property name passed in exists, and if it is a `DOUBLE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_float\_property (property\_name IN VARCHAR) RETURN FLOAT**

If the property with the corresponding property name passed in exists, and if it is a `FLOAT` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_int\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `Integer` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_long\_property (property\_name IN VARCHAR) RETURN NUMBER**

If the property with the corresponding property name passed in exists, and if it is a `long` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_short\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `short` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_string\_property (property\_name IN VARCHAR) RETURN VARCHAR**

If the property with the corresponding property name passed in exists, and if it is a `STRING` property, then this function returns the value of the property. Otherwise it returns a null.

## Payload Methods

**set\_bytes (payload IN RAW)**

Sets the internal payload as a `RAW` variable without any interpretation. The payload of `aq$_jms_map_message` is stored as either `RAW` or `BLOB` in the database. This member function sets a payload as a `RAW` variable without interpreting it.

**set\_bytes (payload IN BLOB)**

Sets the internal payload as a `BLOB` variable without any interpretation. The payload of `aq$_jms_map_message` is stored as either `RAW` or `BLOB` in the database. This member function sets a payload as a `BLOB` variable without interpreting it.

**get\_bytes (payload OUT RAW)**

Puts the internal payload into a `RAW` variable without any interpretation. The payload of `aq$_jms_map_message` is stored as either `RAW` or `BLOB` in the database. This member function gets a payload as raw bytes without interpreting it. Raises exceptions `ORA-24190` if the length of internal payload is more than 32767.

**get\_bytes (payload OUT BLOB)**

Puts the internal payload into a `BLOB` variable without any interpretation. The payload of `aq$_jms_map_message` is stored as either `RAW` or `BLOB` in the database. This member function gets a payload as a `BLOB` without interpreting it.

**prepare (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Takes the byte array stored in `aq$_jms_map_message` and decodes it as a Java object in the Java stored procedure. The result of the decoding is stored as a static variable in Jserv session memory. Parameter `id` is used to identify the slot where the Java object is stored in the Oracle Database JVM session memory. If `id` is null, then a new slot is created for this PL/SQL object. Subsequent JMS operations on the payload need to provide this operation ID.

This function raises `ORA-24197` if the Java stored procedure throws an exception during execution, `ORA-24198` if the operation ID is invalid, or `ORA-24199` if the Java stored procedure message store overflows.

**flush (id IN PLS\_INTEGER)**

Takes the static variable in Jserv and synchronizes the content back to `aq$_jms_map_message`. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**clear\_body (id IN PLS\_INTEGER)**

Sets the Java stored procedure static variable to empty payload. Parameter `id` is used to identify the slot where the Java object is stored in the Oracle Database JVM session memory. If `id` is null, a new slot is created for this PL/SQL object. Subsequent JMS operations on the payload need to provide this operation ID.

This function raises ORA-24197 if the Java stored procedure throws an exception during execution, ORA-24198 if the operation ID is invalid, or ORA-24199 if the Java stored procedure message store overflows.

**clean (id IN PLS\_INTEGER)**

Closes and cleans up the `DataInputStream` or `DataOutputStream` at the Java stored procedure side corresponding to the operation ID. It is very important to call this procedure to avoid memory leaks. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**clean\_all**

Closes and cleans up all the messages in the corresponding type of message store at the Java stored procedure side. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution.

**set\_boolean (id IN PLS\_INTEGER, name IN VARCHAR2, value IN BOOLEAN)**

Sets the Boolean value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_byte (id IN PLS\_INTEGER, name IN VARCHAR2, value IN PLS\_INTEGER)**

Sets the BYTE value with the specified name in the map. Because there is no BYTE type in PL/SQL, `PLS_INTEGER` is used to represent a byte. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_bytes (id IN PLS\_INTEGER, name IN VARCHAR2, value IN RAW)**

Sets the byte array value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_bytes (id IN PLS\_INTEGER, name IN VARCHAR2, value IN RAW, offset IN INT, length IN INT)**

Sets a portion of the byte array value with the specified name in the map. Parameter `offset` is the initial offset within the byte array, and parameter `length` is the number of bytes to use. If the range [`offset ... offset+length`] exceeds the boundary of the byte array value, then a `Java IndexOutOfBoundsException` exception is thrown in the Java stored procedure and this procedure raises an ORA-24197 error. The index starts from 0. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_bytes (id IN PLS\_INTEGER, name IN VARCHAR2, value IN BLOB)**

Sets the byte array value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_bytes (id IN PLS\_INTEGER, name IN VARCHAR2, value IN BLOB, offset IN INT, length IN INT)**

Sets a portion of the byte array value with the specified name in the map. Parameter `offset` is the initial offset within the byte array, and parameter `length` is the number of bytes to use. If the range [`offset ... offset+length`] exceeds the boundary of the byte array value, then a `Java IndexOutOfBoundsException` exception is thrown in the Java stored procedure, and this procedure raises an ORA-24197 error. The index starts from 0. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_char (id IN PLS\_INTEGER, name IN VARCHAR2, value IN CHAR)**

Sets the character value with the specified name in the map. If this value has multiple characters, then it is the first character that is used. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_double (id IN PLS\_INTEGER, name IN VARCHAR2, value IN DOUBLE PRECISION)**

Sets the double value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_float (id IN PLS\_INTEGER, name IN VARCHAR2, value IN FLOAT)**

This procedure is to set the float value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_int (id IN PLS\_INTEGER, name IN VARCHAR2, value IN PLS\_INTEGER)**

Sets the int value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_long (id IN PLS\_INTEGER, name IN VARCHAR2, value IN NUMBER)**

Sets the long value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_short (id IN PLS\_INTEGER, name IN VARCHAR2, value IN PLS\_INTEGER)**

Sets the short value with the specified name in the map. Because there is no short type in PL/SQL, `PLS_INTEGER` is used to represent a short. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_string (id IN PLS\_INTEGER, name IN VARCHAR2, value IN VARCHAR2)**

Sets the string value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**set\_string (id IN PLS\_INTEGER, name IN VARCHAR2, value IN CLOB)**

Sets the string value with the specified name in the map. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**get\_boolean (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN BOOLEAN**

Retrieves the Boolean value with the specified name. If there is no item by this name, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**get\_byte (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN PLS\_INTEGER**

Retrieves the `BYTE` value with the specified name. If there is no item by this name, then null is returned. Because there is no `BYTE` type in PL/SQL, `PLS_INTEGER` is used to represent a byte. Although the PL/SQL users get an `PLS_INTEGER`, they are guaranteed that the value is in the Java `BYTE` value range. If this value is issued with a `set_byte` function, then there will not be an out of range error. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.



**get\_bytes (id IN PLS\_INTEGER, name IN VARCHAR2, value OUT NOCOPY BLOB)**  
Retrieves the byte array value with the specified name. If there is no item by this name, then null is returned. Because the size of the array might be larger than the limit of PL/SQL RAW type, a BLOB is always returned here. The BLOB returned is a copy, which means it can be modified without affecting the message payload. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**get\_char (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN CHAR**  
Retrieves and returns the character value with the specified name. If there is no item by this name, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid.

**get\_double (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN DOUBLE PRECISION**

Retrieves and returns the double value with the specified name. If there is no item by this name, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid.

**get\_float (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN FLOAT**

Retrieves the float value with the specified name. If there is no item by this name, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**get\_int (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN PLS\_INTEGER**

Retrieves the INT value with the specified name. If there is no item by this name, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**get\_long (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN NUMBER**

Retrieves the long value with the specified name. If there is no item by this name, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**get\_short (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN PLS\_INTEGER**

Retrieves the short value with the specified name. If there is no item by this name, then null is returned. Because there is no `short` type in PL/SQL, `INT` is used to represent a `short`. Although the PL/SQL users get an `PLS_INTEGER`, they are guaranteed that the value is in the Java short value range. If this value is issued with a `set_short` function, then there will not be an out of range error. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**get\_string (id IN PLS\_INTEGER, name IN VARCHAR2, value OUT NOCOPY CLOB)**

Retrieves the string value with the specified name. If there is no item by this name, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**get\_names (id IN PLS\_INTEGER) RETURN aq\$\_jms\_namearray**

Retrieves all the names within the map message and returns them in a varray. Because `aq$_jms_namearray` has a size as 1024 and each element is a `VARCHAR(200)`, this function will return an error if the size of the name array of the payload exceeds the limit. Raises exception ORA-24195 if the size of the name array or the size of a name exceeds the limit.

**get\_names (id IN PLS\_INTEGER, names OUT aq\$\_jms\_namearray, offset IN PLS\_INTEGER, length IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Retrieves a portion of the names within the map message. Because `aq$_jms_namearray` has a size as 1024 and each element is a `VARCHAR(200)`, this function will return an error if either limits are exceeded during the retrieval. (This means there is no sense to put a `length` parameter greater than 1024.) The index of the names of a map messages begins from 0. Parameter `offset` is the offset from which to start retrieving.

The function returns the number of names that have been retrieved. The names retrieved is the intersection of the interval `[offset, offset+length-1]` and interval `[0, size-1]` where `size` is the size of this map message. If the intersection is an empty set, then names will be returned as null and the function returns 0 as the number of names retrieved. If users iterate the names by retrieving in small steps, then this can be used to test that there are no more names to read from map message.

Raises exception ORA-24195 if the size of the name array or the size of a name exceed the limit, ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**get\_object (id IN PLS\_INTEGER, name IN VARCHAR2, value OUT NOCOPY AQ\$\_JMS\_VALUE)**

Returns a general value ADT AQ\$\_JMS\_VALUE. If there is no item by this name, then null is returned. Users can use the `type` attribute of this ADT to interpret the data. See the map in the AQ\$\_JMS\_VALUE ADT for the correspondence among `dbms_jms_plsql` package constants, Java data type and AQ\$\_JMS\_VALUE attribute. Note this member procedure might bring additional overhead compared to other `get` member procedures or functions. It is used only if the user does not know the data type of the fields within a message before hand. Otherwise it is a good idea to use a specific `get` member procedure or function. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**get\_size (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Retrieves the size of the map message. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**item\_exists (id IN PLS\_INTEGER, name IN VARCHAR2) RETURN BOOLEAN**

Indicates that an item exists in this map message by returning `TRUE`. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

## SYS.AQ\$\_JMS\_STREAM\_MESSAGE Type

This type is the ADT used to store a `StreamMessage` in an Oracle Streams AQ queue.

This section contains these topics:

- [CONSTRUCT Function](#)
- [JMS Header Methods](#)
- [System Properties Methods](#)
- [User Properties Methods](#)
- [Payload Methods](#)

### Syntax

```
TYPE aq$_jms_stream_message AS object(
 header aq$_jms_header,
 bytes_len int,
 bytes_raw raw(2000),
 bytes_lob blob,
 STATIC FUNCTION construct RETURN aq$_jms_stream_message,
 MEMBER PROCEDURE set_replyto (replyto IN sys.aq$_agent),
 MEMBER PROCEDURE set_type (type IN VARCHAR),
 MEMBER FUNCTION get_replyto RETURN sys.aq$_agent,
 MEMBER FUNCTION get_type RETURN VARCHAR,
 MEMBER PROCEDURE set_userid (userid IN VARCHAR),
 MEMBER PROCEDURE set_appid (appid IN VARCHAR),
 MEMBER PROCEDURE set_groupid (groupid IN VARCHAR),
 MEMBER PROCEDURE set_groupseq (groupseq IN INT),
 MEMBER FUNCTION get_userid RETURN VARCHAR,
 MEMBER FUNCTION get_appid RETURN VARCHAR,
 MEMBER FUNCTION get_groupid RETURN VARCHAR,
 MEMBER FUNCTION get_groupseq RETURN INT,
 MEMBER PROCEDURE clear_properties,
 MEMBER PROCEDURE set_boolean_property(property_name IN VARCHAR,
 property_value IN BOOLEAN),
 MEMBER PROCEDURE set_byte_property (property_name IN VARCHAR,
 property_value IN INT),
 MEMBER PROCEDURE set_double_property (property_name IN VARCHAR,
 property_value IN DOUBLE PRECISION),
 MEMBER PROCEDURE set_float_property (property_name IN VARCHAR,
 property_value IN FLOAT),
```

---

```

MEMBER PROCEDURE set_int_property (property_name IN VARCHAR,
 property_value IN INT),
MEMBER PROCEDURE set_long_property (property_name IN VARCHAR,
 property_value IN NUMBER),
MEMBER PROCEDURE set_short_property (property_name IN VARCHAR,
 property_value IN INT),
MEMBER PROCEDURE set_string_property (property_name IN VARCHAR,
 property_value IN VARCHAR),
MEMBER FUNCTION get_boolean_property (property_name IN VARCHAR) RETURN BOOLEAN,
MEMBER FUNCTION get_byte_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_double_property (property_name IN VARCHAR)
 RETURN DOUBLE PRECISION,
MEMBER FUNCTION get_float_property (property_name IN VARCHAR) RETURN FLOAT,
MEMBER FUNCTION get_int_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_long_property (property_name IN VARCHAR) RETURN NUMBER,
MEMBER FUNCTION get_short_property (property_name IN VARCHAR) RETURN INT,
MEMBER FUNCTION get_string_property (property_name IN VARCHAR) RETURN VARCHAR,
MEMBER PROCEDURE set_bytes (payload IN RAW),
MEMBER PROCEDURE set_bytes (payload IN BLOB),
MEMBER PROCEDURE get_bytes (payload OUT RAW),
MEMBER PROCEDURE get_bytes (payload OUT BLOB),
MEMBER FUNCTION prepare (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER PROCEDURE reset (id IN PLS_INTEGER),
MEMBER PROCEDURE flush (id IN PLS_INTEGER),
MEMBER PROCEDURE clear_body (id IN PLS_INTEGER),
MEMBER PROCEDURE clean (id IN PLS_INTEGER),
STATIC PROCEDURE clean_all,
MEMBER FUNCTION get_mode (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_boolean (id IN PLS_INTEGER) RETURN BOOLEAN,
MEMBER FUNCTION read_byte (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_bytes (id IN PLS_INTEGER) RETURN BLOB,
MEMBER PROCEDURE read_bytes (id IN PLS_INTEGER, value OUT NOCOPY BLOB),
MEMBER FUNCTION read_char (id IN PLS_INTEGER) RETURN CHAR,
MEMBER FUNCTION read_double (id IN PLS_INTEGER) RETURN DOUBLE PRECISION,
MEMBER FUNCTION read_float (id IN PLS_INTEGER) RETURN FLOAT,
MEMBER FUNCTION read_int (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_long (id IN PLS_INTEGER) RETURN NUMBER,
MEMBER FUNCTION read_short (id IN PLS_INTEGER) RETURN PLS_INTEGER,
MEMBER FUNCTION read_string RETURN CLOB,
MEMBER PROCEDURE read_string (id IN PLS_INTEGER, value OUT NOCOPY CLOB),
MEMBER PROCEDURE read_object (id IN PLS_INTEGER,
 value OUT NOCOPY AQ$_JMS_VALUE),
MEMBER PROCEDURE write_boolean (id IN PLS_INTEGER, value IN BOOLEAN),
MEMBER PROCEDURE write_byte (id IN PLS_INTEGER, value IN INT),
MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN RAW),

```

```
MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN RAW,
 offset IN INT, length IN INT),
MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN BLOB),
MEMBER PROCEDURE write_bytes (id IN PLS_INTEGER, value IN BLOB,
 offset IN INT, length IN INT),
MEMBER PROCEDURE write_char (id IN PLS_INTEGER, value IN CHAR),
MEMBER PROCEDURE write_double (id IN PLS_INTEGER, value IN DOUBLE PRECISION),
MEMBER PROCEDURE write_float (id IN PLS_INTEGER, value IN FLOAT),
MEMBER PROCEDURE write_int (id IN PLS_INTEGER, value IN PLS_INTEGER),
MEMBER PROCEDURE write_long (id IN PLS_INTEGER, value IN NUMBER),
MEMBER PROCEDURE write_short (id IN PLS_INTEGER, value IN PLS_INTEGER),
MEMBER PROCEDURE write_string (id IN PLS_INTEGER, value IN VARCHAR2),
MEMBER PROCEDURE write_string (id IN PLS_INTEGER, value IN CLOB);
```

## CONSTRUCT Function

### **STATIC FUNCTION construct RETURN aq\$\_jms\_stream\_message**

Creates an empty aq\$\_jms\_stream\_message object.

## JMS Header Methods

### **set\_replyto (replyto IN sys.aq\$\_agent)**

Sets the `replyto` parameter, which corresponds to `JMSReplyTo` in JMS.

### **set\_type (type IN VARCHAR)**

Sets the JMS type, which can be any text, and which corresponds to `JMSType` in JMS.

### **get\_replyto RETURN sys.aq\$\_agent**

Returns `replyto`, which corresponds to `JMSReplyTo`.

### **get\_type RETURN VARCHAR**

Returns `type`, which corresponds to `JMSType`.

## System Properties Methods

### **set\_userid (userid IN VARCHAR)**

Sets `userid`, which corresponds to `JMSXUserID` in JMS.

### **set\_appid (appid IN VARCHAR)**

Sets `appid`, which corresponds to `JMSXAppID` in JMS.

**set\_groupid (groupid IN VARCHAR)**

Sets `groupid`, which corresponds to `JMSXGroupID` in JMS.

**set\_groupseq (groupseq IN INT)**

Sets `groupseq`, which corresponds to `JMSXGroupSeq` in JMS.

**get\_userid RETURN VARCHAR**

Returns `userid`, which corresponds to `JMSXUserID`.

**get\_appid RETURN VARCHAR**

Returns `appid`, which corresponds to `JMSXAppID`.

**get\_groupid RETURN VARCHAR**

Returns `groupid`, which corresponds to `JMSXGroupID`.

**get\_groupseq RETURN NUMBER**

Returns `groupseq`, which corresponds to `JMSXGroupSeq`.

## User Properties Methods

**clear\_properties**

Clears all user properties. This procedure does not affect system properties.

**set\_boolean\_property (property\_name IN VARCHAR, property\_value IN BOOLEAN)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value` in an internal representation. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_byte\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -128 to 127 (8-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `BYTE` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_double\_property (property\_name IN VARCHAR, property\_value IN DOUBLE PRECISION)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_float\_property (property\_name IN VARCHAR, property\_value IN FLOAT)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_int\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -2147483648 to 2147483647 (32-bits). This check is necessary because in PL/SQL and Oracle Database, the `INT` datatype is 38 bits. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_long\_property (property\_name IN VARCHAR, property\_value IN NUMBER)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. In PL/SQL and Oracle Database, the `NUMBER` datatype is 38 bits. In Java, the `long` datatype is 64 bits. Therefore, no range check is needed. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**set\_short\_property (property\_name IN VARCHAR, property\_value IN INT)**

Checks whether `property_name` is null or exists. If not, the procedure checks whether `property_value` is within -32768 to 32767 (16-bits). This check is necessary because neither PL/SQL nor RDBMS defines the `short` datatype. Raises exception ORA-24191 if the property name exists, ORA-24192 if the property name is null, or ORA-24193 if the property value exceeds the valid range.

**set\_string\_property (property\_name IN VARCHAR, property\_value IN VARCHAR)**

Checks whether `property_name` is null or exists. If not, the procedure stores `property_value`. Raises exception ORA-24191 if the property name exists or ORA-24192 if the property name is null.

**get\_boolean\_property (property\_name IN VARCHAR) RETURN BOOLEAN**

If the property with the corresponding property name passed in exists, and if it is a `BOOLEAN` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_byte\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `BYTE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_double\_property (property\_name IN VARCHAR) RETURN DOUBLE**



**PRECISION**

If the property with the corresponding property name passed in exists, and if it is a `DOUBLE` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_float\_property (property\_name IN VARCHAR) RETURN FLOAT**

If the property with the corresponding property name passed in exists, and if it is a `FLOAT` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_int\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `Integer` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_long\_property (property\_name IN VARCHAR) RETURN NUMBER**

If the property with the corresponding property name passed in exists, and if it is a `long` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_short\_property (property\_name IN VARCHAR) RETURN INT**

If the property with the corresponding property name passed in exists, and if it is a `short` property, then this function returns the value of the property. Otherwise it returns a null.

**get\_string\_property (property\_name IN VARCHAR) RETURN VARCHAR**

If the property with the corresponding property name passed in exists, and if it is a `STRING` property, then this function returns the value of the property. Otherwise it returns a null.

## Payload Methods

**get\_bytes (payload OUT RAW)**

Puts the internal payload into a `RAW` variable without any interpretation. The payload of type `aq$_jms_stream_message` is stored as either `RAW` or `BLOB` in the database. This member function gets a payload as raw bytes without interpreting it. Raises exception `ORA-24190` if the length of internal payload is more than 32767.

**get\_bytes (payload OUT BLOB)**

Puts the internal payload into a `BLOB` variable without any interpretation. The payload of type `aq$_jms_stream_message` is stored as either `RAW` or `BLOB` in the

database. This member function gets a payload as a BLOB variable without interpreting it.

**set\_bytes (payload IN RAW)**

Sets the internal payload as the RAW variable without any interpretation. The payload of type `aq$_jms_stream_message` is stored as either RAW or BLOB in the database. This member function sets a payload as raw bytes without interpreting it.

**set\_bytes (payload IN BLOB)**

Sets the internal payload as the BLOB variable without any interpretation. The payload of type `aq$_jms_stream_message` is stored as either RAW or BLOB in the database. This member function sets a payload as a BLOB variable without interpreting it.

**prepare (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Takes the byte array stored in `aq$_jms_stream_message` and decodes it as a Java object in the Java stored procedure. The result of the decoding is stored as a static variable in Jserv session memory. Parameter `id` is used to identify the slot where the Java object is stored in the Oracle Database JVM session memory. If `id` is null, then a new slot is created for this PL/SQL object. Subsequent JMS operations on the payload need to provide this operation ID.

This function also sets the message access mode to `MESSAGE_ACCESS_READONLY`. Subsequent calls of `write_XXX` procedure raise an ORA-24196 error. Users can call the `clear_body` procedure to set the message access mode to `MESSAGE_ACCESS_READONLY`.

This function raises ORA-24197 if the Java stored procedure throws an exception during execution, ORA-24198 if the operation ID is invalid, or ORA-24199 if the Java stored procedure message store overflows.

**reset (id IN PLS\_INTEGER)**

Resets the starting position of the stream to the beginning and puts the stream message in `MESSAGE_ACCESS_READONLY` mode.

**flush (id IN PLS\_INTEGER)**

Takes the static variable in Jserv and synchronizes the content back to `aq$_jms_stream_message`. This procedure will not affect the underlying access mode. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**clear\_body (id IN PLS\_INTEGER)**

Sets the Java stored procedure static variable to empty payload. Parameter `id` is used to identify the slot where the Java object is stored in the Oracle Database JVM session memory. If `id` is null, a new slot is created for this PL/SQL object. Subsequent JMS operations on the payload need to provide this operation ID.

It also sets the message access mode to `MESSAGE_ACCESS_WRITEONLY`. Later calls of `read_XXX` procedure raise ORA-24196 error. Users can call the `reset` or `prepare` procedures to set the message access mode to `MESSAGE_ACCESS_READONLY`. Write-only and read-only modes affect only the payload functions of `AQ$_JMS_BYTES_MESSAGE`. They do not affect the header functions.

This function raises ORA-24197 if the Java stored procedure throws an exception during execution, ORA-24198 if the operation ID is invalid, or ORA-24199 if the Java stored procedure message store overflows.

**clean (id IN PLS\_INTEGER)**

Closes and cleans up the `DataInputStream` or `DataOutputStream` at the Java stored procedure side corresponding to the operation ID. It is very important to call this procedure to avoid memory leaks. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**clean\_all**

Closes and cleans up all the messages in the corresponding type of message store at the Java stored procedure side. This procedure raises ORA-24197 if the Java stored procedure throws an exception during execution.

**get\_mode (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Returns the current mode of this message. The return value is either `SYS.dbms_aqjms.READ_ONLY` or `SYS.dbms_aqjms.WRITE_ONLY`. Raises exception ORA-24197 if the Java stored procedure throws an exception during execution or ORA-24198 if the operation ID is invalid.

**read\_boolean (id IN PLS\_INTEGER) RETURN BOOLEAN**

Reads and returns a Boolean value from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_byte (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Reads and returns a byte value from the stream message. If the end of the message stream has been reached, then null is returned. Because there is no `BYTE` type in PL/SQL, `INT` is used to represent a byte. Although PL/SQL users get an `INT`, they are guaranteed that the value is in the Java `BYTE` value range. If this value is issued with a `write_byte` function, then there will not be an out of range error. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_bytes (id IN PLS\_INTEGER) RETURN BLOB**

Reads and returns a byte array from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid or ORA-24196 if the stream message is in write-only mode.

**read\_bytes (id IN PLS\_INTEGER, value OUT NOCOPY BLOB)**

Reads a byte array from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_char (id IN PLS\_INTEGER) RETURN CHAR**

Reads and returns a character value from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_double (id IN PLS\_INTEGER) RETURN DOUBLE PRECISION**

Reads and returns a double from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_float (id IN PLS\_INTEGER) RETURN FLOAT**

Reads and returns a float from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_int (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Reads and returns an `INT` from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_long (id IN PLS\_INTEGER) RETURN NUMBER**

Reads and returns a long from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_short (id IN PLS\_INTEGER) RETURN PLS\_INTEGER**

Reads and returns a short value from the stream message. If the end of the message stream has been reached, then null is returned. Because there is no short type in PL/SQL, `INT` is used to represent a byte. Although PL/SQL users get an `INT`, they are guaranteed that the value is in the Java short value range. If this value is issued with a `write_short` function, then there will not be an out of range error. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_string RETURN CLOB**

Reads and returns a string from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid or ORA-24196 if the stream message is in write-only mode.

**read\_string (id IN PLS\_INTEGER, value OUT NOCOPY CLOB)**

Reads a string from the stream message. If the end of the message stream has been reached, then null is returned. Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**read\_object (id IN PLS\_INTEGER, value OUT NOCOPY AQ\$\_JMS\_VALUE)**

Returns a general value ADT AQ\$\_JMS\_VALUE. Users can use the type attribute of this ADT to interpret the data. See [Table 173-2](#) on page 173-69 for the correspondence among `dbms_jms_plsql` package constants, Java data type and AQ\$\_JMS\_VALUE attribute. This member procedure might bring additional overhead compared to other read member procedures or functions. It is used only if the user does not know the data type of the fields within a message beforehand. Otherwise it is a good idea to use a specific read member procedure or function.

Raises exception ORA-24194 if the type conversion between the type of real value and the expected type is invalid, ORA-24196 if the stream message is in write-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_boolean (id IN PLS\_INTEGER, value IN BOOLEAN)**

Writes a Boolean to the stream message. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_byte (id IN PLS\_INTEGER, value IN INT)**

Writes a byte to the stream message. Because there is no BYTE type in PL/SQL, INT is used to represent a byte. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN RAW)**

Writes a byte array field to the stream message. Consecutively written byte array fields are treated as two distinct fields when the fields are read. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN RAW, offset IN INT, length IN INT)**

Writes a portion of a byte array as a byte array field to the stream message. Consecutively written byte array fields are treated as two distinct fields when the fields are read. Parameter `offset` is the initial offset within the byte array, and

parameter `length` is the number of bytes to use. If the range `[offset, offset+length]` exceeds the boundary of the byte array value, then a `Java IndexOutOfBoundsException` exception is thrown in the Java stored procedure. The index starts from 0.

Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN BLOB)**

Writes a byte array field to the stream message. Consecutively written byte array fields are treated as two distinct fields when the fields are read. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_bytes (id IN PLS\_INTEGER, value IN BLOB, offset IN INT, length IN INT)**

Writes a portion of a byte array as a byte array field to the stream message. Consecutively written byte array fields are treated as two distinct fields when the fields are read. Parameter `offset` is the initial offset within the byte array, and parameter `length` is the number of bytes to use. If the range `[offset, offset+length]` exceeds the boundary of the byte array value, then a `Java IndexOutOfBoundsException` exception is thrown in the Java stored procedure. The index starts from 0.

Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_char (id IN PLS\_INTEGER, value IN CHAR)**

Writes a character value to the stream message. If this value has multiple characters, then it is the first character that is written. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_double (id IN PLS\_INTEGER, value IN DOUBLE PRECISION)**

Writes a double to the stream message. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_float (id IN PLS\_INTEGER, value IN FLOAT)**

Writes a float to the stream message. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_int (id IN PLS\_INTEGER, value IN PLS\_INTEGER)**

Writes an `INT` to the stream message. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_long (id IN PLS\_INTEGER, value IN NUMBER)**

Writes a long to the stream message. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_short (id IN PLS\_INTEGER, value IN PLS\_INTEGER)**

Writes a short to the stream message. Because there is no short type in PL/SQL, `INT` is used to represent a short. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_string (id IN PLS\_INTEGER, value IN VARCHAR2)**

Writes a string to the stream message. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.

**write\_string (id IN PLS\_INTEGER, value IN CLOB)**

Writes a string to the stream message. Raises exceptions ORA-24196 if the stream message is in read-only mode, ORA-24197 if the Java stored procedure throws an exception during execution, or ORA-24198 if the operation ID is invalid.



## SYS.AQ\$\_JMS\_OBJECT\_MESSAGE Type

This type is the ADT used to store an `ObjectMessage` in an Oracle Streams AQ queue.

### Syntax

```
TYPE aq$_jms_object_message AS object(
 header aq$_jms_header,
 bytes_len int,
 bytes_raw raw(2000),
 bytes_lob blob);
```

## SYS.AQ\$\_JMS\_NAMESARRAY Type

This type represents the name array returned by the `get_names` procedure of `aq$_jms_map_message`. The maximum number of names this type can hold is 1024. The maximum length of each name is 200 characters.

### Syntax

```
CREATE OR REPLACE TYPE AQ$_JMS_NAMESARRAY AS VARRAY(1024) OF VARCHAR(100);
```

### Usage Notes

If the names array in the message payload is greater than 1024, then use the following function to retrieve the names in multiple portions:

```
MEMBER FUNCTION get_names(id IN PLS_INTEGER, names OUT aq$_jms_namearray,
 offset IN PLS_INTEGER, length IN PLS_INTEGER) RETURN PLS_INTEGER;
```

## SYS.AQ\$\_JMS\_VALUE Type

This type represents the general data returned by the `get_object` procedure of `aq$_jms_map_message` and the `read_object` procedure of `aq$_jms_stream_message`. The `type` field in this ADT is used to decide which type of data this object is really holding. [Table 173–2](#) lists the mapping between the `sys.dbms_jms_plsql` type constants, the corresponding Java type, and the data field of ADT `aq$_jms_value` which effectively holds the data.

### Syntax

```
CREATE OR REPLACE TYPE AQ$_JMS_VALUE AS object(
 type number(2),
 num_val number,
 char_val char(1),
 text_val clob,
 bytes_val blob);
```

**Table 173–2** *AQ\$\_JMS\_VALUE Type Fields and Java Fields*

Type	Java Type	aq\$_jms_value Data Field
DBMS_JMS_PLSQL.DATA_TYPE_BYTE	byte	num_val
DBMS_JMS_PLSQL.DATA_TYPE_SHORT	short	num_val
DBMS_JMS_PLSQL.DATA_TYPE_INTEGER	int	num_val
DBMS_JMS_PLSQL.DATA_TYPE_LONG	long	num_val
DBMS_JMS_PLSQL.DATA_TYPE_FLOAT	float	num_val
DBMS_JMS_PLSQL.DATA_TYPE_DOUBLE	double	num_val
DBMS_JMS_PLSQL.DATA_TYPE_BOOLEAN	boolean	num_val: 0 FALSE, 1 TRUE
DBMS_JMS_PLSQL.DATA_TYPE_CHARACTER	char	char_val
DBMS_JMS_PLSQL.DATA_TYPE_STRING	java.lang.String	text_val
DBMS_JMS_PLSQL.DATA_TYPE_BYTES	byte[]	bytes_val

## SYS.AQ\$\_JMS\_EXCEPTION Type

This type represents a Java exception thrown on the Java stored procedure side. The `id` field is reserved for future use. The `exp_name` stores the Java exception name, the `err_msg` field stores the Java exception error message, and the `stack` field stores the stack trace of the Java exception.

### Syntax

```
CREATE OR REPLACE TYPE AQ$_JMS_EXCEPTION AS OBJECT (
 id number, -- Reserved and not used. Right now always return 0.
 exp_name varchar(200),
 err_msg varchar(500),
 stack varchar(4000));
```

---

## Logical Change Record TYPEs

This chapter describes the logical change record (LCR) types. In Streams, LCRs are message payloads that contain information about changes to a database. These changes can include changes to the data, which are data manipulation language (DML) changes, and changes to database objects, which are data definition language (DDL) changes.

When you use Streams, the capture process captures changes in the form of LCRs and enqueues them into a queue. These LCRs can be propagated from a queue in one database to a queue in another database. Finally, the apply process can apply LCRs at a destination database. You also have the option of creating, enqueueing, and dequeuing LCRs manually.

**See Also:** *Oracle Streams Concepts and Administration* for more information about LCRs

This chapter contains these topics:

- [Summary of Logical Change Record Types](#)
- [Common Subprograms for LCR\\$\\_DDL\\_RECORD and LCR\\$\\_ROW\\_RECORD](#)

---

## Summary of Logical Change Record Types

**Table 174–1 Logical Change Record (LCR) Types**

Type	Description
" <a href="#">LCR\$_DDL_RECORD</a> Type" on page 174-3	Represents a data definition language (DDL) change to a database object
" <a href="#">LCR\$_ROW_RECORD</a> Type" on page 174-14	Represents a data manipulation language (DML) change to a database object
" <a href="#">LCR\$_ROW_LIST</a> Type" on page 174-44	Identifies a list of column values for a row in a table
" <a href="#">LCR\$_ROW_UNIT</a> Type" on page 174-45	Identifies the value for a column in a row

These LCR types can be used with the following Oracle-supplied PL/SQL packages:

- DBMS\_APPLY\_ADM
- DBMS\_AQ
- DBMS\_AQADM
- DBMS\_CAPTURE\_ADM
- DBMS\_PROPAGATION\_ADM
- DBMS\_RULE
- DBMS\_RULE\_ADM
- DBMS\_STREAMS
- DBMS\_STREAMS\_ADM
- DBMS\_TRANSFORM

## LCR\$\_DDL\_RECORD Type

This type represents a data definition language (DDL) change to a database object.

If you create or modify a DDL LCR, then make sure the `ddl_text` is consistent with the `base_table_name`, `base_table_owner`, `object_type`, `object_owner`, `object_name`, and `command_type` attributes.

This section contains information about the constructor for DDL LCRs and information about the member subprograms for this type:

- [LCR\\$\\_DDL\\_RECORD Constructor](#)
- [Summary of LCR\\$\\_DDL\\_RECORD Subprograms](#), which also include the subprograms described in "[Common Subprograms for LCR\\$\\_DDL\\_RECORD and LCR\\$\\_ROW\\_RECORD](#)" on page 174-33

---

---

**Note:**

- When passing a name as a parameter to an LCR constructor, you can enclose the name in double quotes to handle names that use mixed case or lower case for database objects. For example, if a name contains any lower case characters, then you must enclose it in double quotes.
  - The application does not need to specify a transaction identifier or SCN when it creates an LCR because the apply process generates these values and stores them in memory. If a transaction identifier or SCN is specified in the LCR, then the apply process ignores it and assigns a new value.
- 
-

## LCR\$\_DDL\_RECORD Constructor

Creates a SYS.LCR\$\_DDL\_RECORD object with the specified information.

```
STATIC FUNCTION CONSTRUCT(
 source_database_name IN VARCHAR2,
 command_type IN VARCHAR2,
 object_owner IN VARCHAR2,
 object_name IN VARCHAR2,
 object_type IN VARCHAR2,
 ddl_text IN CLOB,
 logon_user IN VARCHAR2,
 current_schema IN VARCHAR2,
 base_table_owner IN VARCHAR2,
 base_table_name IN VARCHAR2,
 tag IN RAW DEFAULT NULL,
 transaction_id IN VARCHAR2 DEFAULT NULL,
 scn IN NUMBER DEFAULT NULL)
RETURN SYS.LCR$_DDL_RECORD;
```



**LCR\$\_DDL\_RECORD Constructor Function Parameters****Table 174–2 Constructor Function Parameters for LCR\$\_DDL\_RECORD**

Parameter	Description
source_database_name	The database where the DDL statement occurred. If you do not include the domain name, then the local domain is appended to the database name automatically. For example, if you specify DBS1 and the local domain is .NET, then DBS1.NET is specified automatically. This parameter should be set to a non-NULL value.
command_type	<p>The type of command executed in the DDL statement. This parameter should be set to a non-NULL value.</p> <p><b>See Also:</b> The "SQL Command Codes" table in the <i>Oracle Call Interface Programmer's Guide</i> for a complete list of command types</p> <p>The following command types <i>are not supported</i> in DDL LCRs:</p> <pre> ALTER MATERIALIZED VIEW ALTER MATERIALIZED VIEW LOG ALTER SUMMARY CREATE SCHEMA CREATE MATERIALIZED VIEW CREATE MATERIALIZED VIEW LOG CREATE SUMMARY DROP MATERIALIZED VIEW DROP MATERIALIZED VIEW LOG DROP SUMMARY RENAME </pre> <p>The snapshot equivalents of the materialized view command types are also not supported.</p>
object_owner	The user who owns the object on which the DDL statement was executed
object_name	The database object on which the DDL statement was executed

**Table 174–2 (Cont.) Constructor Function Parameters for LCR\$\_DDL\_RECORD**

Parameter	Description
object_type	<p>The type of object on which the DDL statement was executed.</p> <p>The following are valid object types:</p> <ul style="list-style-type: none"> <li>CLUSTER</li> <li>FUNCTION</li> <li>INDEX</li> <li>LINK</li> <li>OUTLINE</li> <li>PACKAGE</li> <li>PACKAGE BODY</li> <li>PROCEDURE</li> <li>SEQUENCE</li> <li>SYNONYM</li> <li>TABLE</li> <li>TRIGGER</li> <li>TYPE</li> <li>USER</li> <li>VIEW</li> </ul> <p>LINK represents a database link.</p> <p>NULL is also a valid object type. Specify NULL for all object types not listed. The GET_OBJECT_TYPE member procedure returns NULL for object types not listed.</p>
ddl_text	The text of the DDL statement. This parameter should be set to a non-NULL value.
logon_user	The user whose session executed the DDL statement
current_schema	<p>The schema that is used if no schema is specified explicitly for the modified database objects in ddl_text. If a schema is specified in ddl_text that differs from the one specified for current_schema, then the schema specified in ddl_text is used.</p> <p>This parameter should be set to a non-NULL value.</p>
base_table_owner	<p>If the DDL statement is a table related DDL (such as CREATE TABLE and ALTER TABLE), or if the DDL statement involves a table (such as creating a trigger on a table), then base_table_owner specifies the owner of the table involved. Otherwise, base_table_owner is NULL.</p>

**Table 174–2 (Cont.) Constructor Function Parameters for LCR\$\_DDL\_RECORD**

Parameter	Description
base_table_name	If the DDL statement is a table related DDL (such as CREATE TABLE and ALTER TABLE), or if the DDL statement involves a table (such as creating a trigger on a table), then base_table_name specifies the name of the table involved. Otherwise, base_table_name is NULL.
tag	A binary tag that enables tracking of the LCR. For example, this tag may be used to determine the original source database of the DDL statement if apply forwarding is used.  <b>See Also:</b> <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags
transaction_id	The identifier of the transaction
scn	The SCN at the time when the change record for a captured LCR was written to the redo log. The SCN value is meaningless for a user-created LCR.

## Summary of LCR\$\_DDL\_RECORD Subprograms

**Table 174–3 LCR\$\_DDL\_RECORD Type Subprograms**

Subprogram	Description
"EXECUTE Member Procedure" on page 174-8	Executes the LCR under the security domain of the current user
"GET_BASE_TABLE_NAME Member Function" on page 174-8	Returns the base (dependent) table name
"GET_BASE_TABLE_OWNER Member Function" on page 174-9	Returns the base (dependent) table owner
"GET_CURRENT_SCHEMA Member Function" on page 174-9	Returns the default schema (user) name
"GET_DDL_TEXT Member Procedure" on page 174-9	Gets the DDL text in a CLOB
"GET_LOGON_USER Member Function" on page 174-10	Returns the logon user name
"GET_OBJECT_TYPE Member Function" on page 174-10	Returns the type of the object involved for the DDL
"SET_BASE_TABLE_NAME Member Procedure" on page 174-10	Sets the base (dependent) table name

**Table 174–3 (Cont.) LCR\$\_DDL\_RECORD Type Subprograms**

Subprogram	Description
"SET_BASE_TABLE_OWNER Member Procedure" on page 174-11	Sets the base (dependent) table owner
"SET_CURRENT_SCHEMA Member Procedure" on page 174-11	Sets the default schema (user) name
"SET_DDL_TEXT Member Procedure" on page 174-12	Sets the DDL text
"SET_LOGON_USER Member Procedure" on page 174-12	Sets the logon user name
"SET_OBJECT_TYPE Member Procedure" on page 174-13	Sets the object type
Common Subprograms	See "Common Subprograms for LCR\$_DDL_RECORD and LCR\$_ROW_RECORD" on page 174-33 for a list of subprograms common to the SYS.LCR\$_ROW_RECORD and SYS.LCR\$_DDL_RECORD types

## EXECUTE Member Procedure

Executes the DDL LCR under the security domain of the current user. Any apply process handlers that would be run for an LCR are not run when the LCR is applied using this procedure.

---



---

**Note:** The EXECUTE member procedure can be invoked only in an apply handler for an apply process.

---



---

### Syntax

```
MEMBER PROCEDURE EXECUTE();
```

## GET\_BASE\_TABLE\_NAME Member Function

Returns the base (dependent) table name.

### Syntax

```
MEMBER FUNCTION GET_BASE_TABLE_NAME()
RETURN VARCHAR2;
```

## GET\_BASE\_TABLE\_OWNER Member Function

Returns the base (dependent) table owner.

### Syntax

```
MEMBER FUNCTION GET_BASE_TABLE_OWNER()
RETURN VARCHAR2;
```

## GET\_CURRENT\_SCHEMA Member Function

Returns the current schema name.

### Syntax

```
MEMBER FUNCTION GET_CURRENT_SCHEMA()
RETURN VARCHAR2;
```

## GET\_DDL\_TEXT Member Procedure

Gets the DDL text in a CLOB.

The following is an example of a PL/SQL procedure that uses this procedure to get the DDL text in a DDL LCR:

```
CREATE OR REPLACE PROCEDURE ddl_in_lcr (ddl_lcr in SYS.LCR$_DDL_RECORD)
IS
 ddl_text CLOB;
BEGIN
 DBMS_OUTPUT.PUT_LINE(' -----');
 DBMS_OUTPUT.PUT_LINE(' Displaying DDL text in a DDL LCR: ');
 DBMS_OUTPUT.PUT_LINE(' -----');
 DBMS_LOB.CREATETEMPORARY(ddl_text, true);
 ddl_lcr.GET_DDL_TEXT(ddl_text);
 DBMS_OUTPUT.PUT_LINE('DDL text:' || ddl_text);
 DBMS_LOB.FREETEMPORARY(ddl_text);
END;
/
```

---

---

**Note:** GET\_DDL\_TEXT is a member procedure and not a member function to make it easier for you to manage the space used by the CLOB. Notice that the previous example creates temporary space for the CLOB and then frees the temporary space when it is no longer needed.

---

---

**Syntax**

```
MEMBER FUNCTION GET_DDL_TEXT
 ddl_text IN/OUT CLOB);
```

**Parameter****Table 174-4** *GET\_DDL\_TEXT Procedure Parameter*

Parameter	Description
ddl_text	The DDL text in the DDL LCR

**GET\_LOGON\_USER Member Function**

Returns the logon user name.

**Syntax**

```
MEMBER FUNCTION GET_LOGON_USER()
RETURN VARCHAR2;
```

**GET\_OBJECT\_TYPE Member Function**

Returns the type of the object involved for the DDL.

**Syntax**

```
MEMBER FUNCTION GET_OBJECT_TYPE()
RETURN VARCHAR2;
```

**SET\_BASE\_TABLE\_NAME Member Procedure**

Sets the base (dependent) table name.

**Syntax**

```
MEMBER PROCEDURE SET_BASE_TABLE_NAME(
 base_table_name IN VARCHAR2);
```

**Parameter****Table 174-5** *SET\_BASE\_TABLE\_NAME Procedure Parameter*

Parameter	Description
base_table_name	The name of the base table

## SET\_BASE\_TABLE\_OWNER Member Procedure

Sets the base (dependent) table owner.

### Syntax

```
MEMBER PROCEDURE SET_BASE_TABLE_OWNER(
 base_table_owner IN VARCHAR2);
```

### Parameter

**Table 174–6** SET\_BASE\_TABLE\_OWNER Procedure Parameter

Parameter	Description
base_table_owner	The name of the base owner

## SET\_CURRENT\_SCHEMA Member Procedure

Sets the default schema (user) name.

### Syntax

```
MEMBER PROCEDURE SET_CURRENT_SCHEMA(
 current_schema IN VARCHAR2);
```

### Parameter

**Table 174–7** SET\_CURRENT\_SCHEMA Procedure Parameter

Parameter	Description
current_schema	The name of the schema to set as the current schema. This parameter should be set to a non-NULL value.

## SET\_DDL\_TEXT Member Procedure

Sets the DDL text.

### Syntax

```
MEMBER PROCEDURE SET_DDL_TEXT(
 ddl_text IN CLOB);
```

### Parameter

**Table 174–8** *SET\_DDL\_TEXT Procedure Parameter*

Parameter	Description
ddl_text	The DDL text. This parameter should be set to a non-NULL value.

## SET\_LOGON\_USER Member Procedure

Sets the logon user name.

### Syntax

```
MEMBER PROCEDURE SET_LOGON_USER(
 logon_user IN VARCHAR2);
```

### Parameter

**Table 174–9** *SET\_LOGON\_USER Procedure Parameter*

Parameter	Description
logon_user	The name of the schema to set as the logon user



## SET\_OBJECT\_TYPE Member Procedure

Sets the object type.

### Syntax

```
MEMBER PROCEDURE SET_OBJECT_TYPE(
 object_type IN VARCHAR2);
```

### Parameter

**Table 174–10 SET\_OBJECT\_TYPE Procedure Parameter**

Parameter	Description
object_type	<p>The object type.</p> <p>The following are valid object types:</p> <ul style="list-style-type: none"> <li>CLUSTER</li> <li>FUNCTION</li> <li>INDEX</li> <li>LINK</li> <li>OUTLINE</li> <li>PACKAGE</li> <li>PACKAGE BODY</li> <li>PROCEDURE</li> <li>SEQUENCE</li> <li>SYNONYM</li> <li>TABLE</li> <li>TRIGGER</li> <li>TYPE</li> <li>USER</li> <li>VIEW</li> </ul> <p>LINK represents a database link.</p> <p>NULL is also a valid object type. Specify NULL for all object types not listed. The GET_OBJECT_TYPE member procedure returns NULL for object types not listed.</p>

## LCR\$\_ROW\_RECORD Type

This type represents a data manipulation language (DML) change to a row in a table. This type uses the `LCR$_ROW_LIST` type.

If you create or modify a row LCR, then make sure the `command_type` attribute is consistent with the presence or absence of old column values and the presence or absence of new column values.

This section contains information about the constructor for DDL LCRs and information about the member subprograms for this type:

- [LCR\\$\\_ROW\\_RECORD Constructor](#)
- [Summary of LCR\\$\\_ROW\\_RECORD Subprograms](#), which also include the subprograms described in [Common Subprograms for LCR\\$\\_DDL\\_RECORD and LCR\\$\\_ROW\\_RECORD](#)

---

---

**Note:**

- When passing a name as a parameter to an LCR constructor, you can enclose the name in double quotes to handle names that use mixed case or lower case for database objects. For example, if a name contains any lower case characters, then you must enclose it in double quotes.
  - The application does not need to specify a transaction identifier or SCN when it creates an LCR because the apply process generates these values and stores them in memory. If a transaction identifier or SCN is specified in the LCR, then the apply process ignores it and assigns a new value.
- 
- 

**See Also:** ["LCR\\$\\_ROW\\_LIST Type"](#) on page 174-44

## LCR\$\_ROW\_RECORD Constructor

Creates a SYS.LCR\$\_ROW\_RECORD object with the specified information.

```
STATIC FUNCTION CONSTRUCT(
 source_database_name IN VARCHAR2,
 command_type IN VARCHAR2,
 object_owner IN VARCHAR2,
 object_name IN VARCHAR2,
 tag IN RAW DEFAULT NULL,
 transaction_id IN VARCHAR2 DEFAULT NULL,
 scn IN NUMBER DEFAULT NULL,
 old_values IN SYS.LCR$_ROW_LIST DEFAULT NULL,
 new_values IN SYS.LCR$_ROW_LIST DEFAULT NULL)
RETURN SYS.LCR$_ROW_RECORD;
```

## LCR\$\_ROW\_RECORD Constructor Function Parameters

**Table 174–11 Constructor Function Parameters for LCR\$\_ROW\_RECORD**

Parameter	Description
source_database_name	The database where the row change occurred. If you do not include the domain name, then the local domain is appended to the database name automatically. For example, if you specify DBS1 and the local domain is .NET, then DBS1.NET is specified automatically. This parameter should be set to a non-NULL value.
command_type	<p>The type of command executed in the DML statement. This parameter should be set to a non-NULL value.</p> <p>Valid values are the following:</p> <ul style="list-style-type: none"> <li>INSERT</li> <li>UPDATE</li> <li>DELETE</li> <li>LOB ERASE</li> <li>LOB WRITE</li> <li>LOB TRIM</li> </ul> <p>If INSERT, then an LCR should have a new_values collection that is not empty and an empty or NULL old_values collection.</p> <p>If UPDATE, then an LCR should have a new_values collection that is not empty and an old_values collection that is not empty.</p> <p>If DELETE, then an LCR should have a NULL or empty new_values collection and an old_values collection that is not empty.</p> <p>If LOB ERASE, LOB WRITE, or LOB TRIM, then an LCR should have a new_values collection that is not empty and an empty or NULL old_values collection.</p>
object_owner	The user who owns the table on which the row change occurred. This parameter should be set to a non-NULL value.
object_name	The table on which the DML statement was executed. This parameter should be set to a non-NULL value.
tag	<p>A binary tag that enables tracking of the LCR. For example, this tag may be used to determine the original source database of the DML change when apply forwarding is used.</p> <p><b>See Also:</b> <i>Oracle Streams Replication Administrator's Guide</i> for more information about tags</p>

**Table 174–11 (Cont.) Constructor Function Parameters for LCR\$\_ROW\_RECORD**

Parameter	Description
transaction_id	The identifier of the transaction
scn	The SCN at the time when the change record was written to the redo log. The SCN value is meaningless for a user-created LCR.
old_values	The column values for the row before the DML change. If the DML statement is an UPDATE or a DELETE statement, then the values of columns in the row before the DML statement. If the DML statement is an INSERT statement, then there are no old values.
new_values	The column values for the row after the DML change. If the DML statement is an UPDATE or an INSERT statement, then the values of columns in the row after the DML statement. If the DML statement is a DELETE statement, then there are no new values.  If the LCR reflects a LOB operation, then the supplementally logged columns and any relevant LOB information.

## Summary of LCR\$\_ROW\_RECORD Subprograms

**Table 174–12 LCR\$\_ROW\_RECORD Type Subprograms**

Subprogram	Description
<a href="#">"ADD_COLUMN Member Procedure"</a> on page 174-19	Adds the value as old or new, depending on the value type specified, for the column
<a href="#">"CONVERT_LONG_TO_LOB_CHUNK Member Procedure"</a> on page 174-20	Converts LONG data in a row LCR into fixed width CLOB, or converts LONG RAW data in a row LCR into a BLOB
<a href="#">"DELETE_COLUMN Member Procedure"</a> on page 174-20	Deletes the old value, the new value, or both, for the specified column, depending on the value type specified
<a href="#">"EXECUTE Member Procedure"</a> on page 174-21	Executes the LCR under the security domain of the current user
<a href="#">"GET_LOB_INFORMATION Member Function"</a> on page 174-22	Gets the LOB information for the column
<a href="#">"GET_LOB_OFFSET Member Function"</a> on page 174-23	Returns the LOB offset for the specified column

**Table 174–12 (Cont.) LCR\$\_ROW\_RECORD Type Subprograms**

<b>Subprogram</b>	<b>Description</b>
" <a href="#">GET_LOB_OPERATION_SIZE Member Function</a> " on page 174-23	Gets the operation size for the LOB column
" <a href="#">GET_LONG_INFORMATION Member Function</a> " on page 174-25	Gets the LONG information for the column
" <a href="#">GET_VALUE Member Function</a> " on page 174-25	Returns the old or new value for the specified column, depending on the value type specified
" <a href="#">GET_VALUES Member Function</a> " on page 174-26	Returns a list of old or new values, depending on the value type specified
" <a href="#">RENAME_COLUMN Member Procedure</a> " on page 174-28	Renames a column in an LCR
" <a href="#">SET_LOB_INFORMATION Member Procedure</a> " on page 174-28	Sets LOB information for the column
" <a href="#">SET_LOB_OFFSET Member Procedure</a> " on page 174-29	Sets the LOB offset for the specified column
" <a href="#">SET_LOB_OPERATION_SIZE Member Procedure</a> " on page 174-30	Sets the operation size for the LOB column
" <a href="#">SET_VALUE Member Procedure</a> " on page 174-31	Overwrites the value of the specified column
" <a href="#">SET_VALUES Member Procedure</a> " on page 174-32	Replaces the existing old or new values for the LCR, depending on the value type specified
Common Subprograms	See " <a href="#">Common Subprograms for LCR\$_DDL_RECORD and LCR\$_ROW_RECORD</a> " on page 174-33 for a list of subprograms common to the SYS.LCR\$_ROW_RECORD and SYS.LCR\$_DDL_RECORD types

## ADD\_COLUMN Member Procedure

Adds the value as old or new, depending on the value type specified, for the column. An error is raised if a value of the same type already exists for the column.

To set a column value that already exists, run `SET_VALUE`.

---

**Note:** When you are processing a row LCR with a rule-based transformation, DML handler, or error handler, you cannot use this member procedure on a LOB column.

---

**See Also:** ["SET\\_VALUE Member Procedure"](#) on page 174-31

### Syntax

```
MEMBER PROCEDURE ADD_COLUMN(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 column_value IN SYS.AnyData);
```

### Parameters

**Table 174–13 ADD\_COLUMN Procedure Parameters**

Parameter	Description
value_type	The type of value to add for the column. Specify <code>old</code> to add the old value of the column. Specify <code>new</code> to add the new value of the column.
column_name	The column name. This name is not validated. An error may be raised during application of the LCRs if an invalid name is specified.
column_value	The value of the column. If <code>NULL</code> , then an error is raised. A <code>NULL</code> column value can be specified by encapsulating the <code>NULL</code> value in a <code>SYS.AnyData</code> wrapper.

## CONVERT\_LONG\_TO\_LOB\_CHUNK Member Procedure

Converts LONG data in a row LCR into a CLOB, or converts LONG RAW data in a row LCR into a BLOB.

This procedure may change the operation code from LONG\_WRITE to LOB\_WRITE for the row LCR.

This procedure may be used in rule-based transformations and apply handlers.

The following restrictions apply to this member procedure:

- LONG data can be sent as a part of a row LCR with one of the following operation codes: INSERT, UPDATE, or LONG\_WRITE. Because LONG data may be sent in multiple pieces, make sure that this method is invoked on either none or all LONG pieces.
- LOB to LONG conversion is not supported.
- A row LCR on which this procedure is executed must have been created by capture process. That is, this procedure does not support user-enqueued row LCRs.

### Syntax

```
MEMBER PROCEDURE CONVERT_LONG_TO_LOB_CHUNK();
```

## DELETE\_COLUMN Member Procedure

Deletes the old value, the new value, or both, for the specified column, depending on the value type specified.

### Syntax

```
MEMBER PROCEDURE DELETE_COLUMN(
 column_name IN VARCHAR2,
 value_type IN VARCHAR2 DEFAULT '*');
```

### Parameters

**Table 174–14** DELETE\_COLUMN Procedure Parameters

Parameter	Description
column_name	The column name. An error is raised if the column does not exist in the LCR.



**Table 174–14** *DELETE\_COLUMN Procedure Parameters*

Parameter	Description
value_type	The type of value to delete for the column. Specify <code>old</code> to delete the old value of the column. Specify <code>new</code> to delete the new value of the column. If <code>*</code> is specified, then both the old and new values are deleted.

## EXECUTE Member Procedure

Executes the row LCR under the security domain of the current user. Any apply process handlers that would be run for an LCR are not run when the LCR is applied using this procedure.

---



---

**Note:** The EXECUTE member procedure can be invoked only in an apply handler for an apply process.

---



---

### Syntax

```
MEMBER PROCEDURE EXECUTE(
 conflict_resolution IN BOOLEAN);
```

### Parameters

**Table 174–15** *EXECUTE Procedure Parameters*

Parameter	Description
conflict_resolution	If <code>true</code> , then any conflict resolution defined for the table using the <code>SET_UPDATE_CONFLICT_HANDLER</code> procedure in the <code>DBMS_APPLY_ADM</code> package is used to resolve conflicts resulting from the execution of the LCR.  If <code>false</code> , then conflict resolution is not used.

## GET\_LOB\_INFORMATION Member Function

Gets the LOB information for the column.

The return value can be one of the following:

```
DBMS_LCR.NOT_A_LOB CONSTANT NUMBER := 1;
DBMS_LCR.NULL_LOB CONSTANT NUMBER := 2;
DBMS_LCR.INLINE_LOB CONSTANT NUMBER := 3;
DBMS_LCR.EMPTY_LOB CONSTANT NUMBER := 4;
DBMS_LCR.LOB_CHUNK CONSTANT NUMBER := 5;
DBMS_LCR.LAST_LOB_CHUNK CONSTANT NUMBER := 6;
```

Returns `NULL` if the specified column does not exist.

If the command type of the row LCR is `UPDATE`, then specifying 'Y' for the `use_old` parameter is a convenient way to get the value of the columns.

### Syntax

```
MEMBER FUNCTION GET_LOB_INFORMATION(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 use_old IN VARCHAR2 DEFAULT 'Y')
RETURN NUMBER;
```

### Parameters

**Table 174–16** GET\_LOB\_INFORMATION Function Parameters

Parameter	Description
<code>value_type</code>	The type of value to return for the column, either <code>old</code> or <code>new</code>
<code>column_name</code>	The name of the column
<code>use_old</code>	<p>If Y and <code>value_type</code> is <code>new</code>, and no new value exists, then returns the corresponding old value. If N and <code>value_type</code> is <code>new</code>, then does not return the old value if no new value exists.</p> <p>If <code>value_type</code> is <code>old</code> or if the <code>command_type</code> of the row LCR is not <code>UPDATE</code>, then the value of the <code>use_old</code> parameter is ignored.</p> <p><code>NULL</code> is not a valid specification for the <code>use_old</code> parameter.</p>

## GET\_LOB\_OFFSET Member Function

Gets the LOB offset for the specified column in the number of characters for CLOB columns and the number of bytes for BLOB columns. Returns a non-NULL value only if all of the following conditions are met:

- The value exists for the column
- The column value is an out-of-line LOB. That is, the information is `DBMS_LCR.LAST_LOB_CHUNK` or `DBMS_LCR.LOB_CHUNK`
- The command type is `LOB ERASE` or `LOB WRITE`

Otherwise, returns NULL.

### Syntax

```
GET_LOB_OFFSET(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2)
RETURN NUMBER;
```

### Parameters

**Table 174–17 GET\_LOB\_OFFSET Procedure Parameters**

Parameter	Description
<code>value_type</code>	The type of value to return for the column. Currently, only new can be specified.
<code>column_name</code>	The name of the LOB column

## GET\_LOB\_OPERATION\_SIZE Member Function

Gets the operation size for the LOB column in the number of characters for CLOB columns and the number of bytes for BLOB columns. Returns a non-NULL value only if all of the following conditions are met:

- The value exists for the column
- The column value is an out-of-line LOB
- The command type is `LOB ERASE` or `LOB TRIM`
- The information is `DBMS_LCR.LAST_LOB_CHUNK`

Otherwise, returns NULL.

**Syntax**

```
MEMBER FUNCTION GET_LOB_OPERATION_SIZE(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2)
RETURN NUMBER,
```

**Parameters****Table 174–18** *GET\_LOB\_OPERATION\_SIZE Function Parameters*

<b>Parameter</b>	<b>Description</b>
value_type	The type of value to return for the column. Currently, only new can be specified.
column_name	The name of the LOB column

## GET\_LONG\_INFORMATION Member Function

Gets the LONG information for the column.

The return value can be one of the following:

```
DBMS_LCR.NOT_A_LONG CONSTANT NUMBER := 1;
DBMS_LCR.NULL_LONG CONSTANT NUMBER := 2;
DBMS_LCR.INLINE_LONG CONSTANT NUMBER := 3;
DBMS_LCR.LONG_CHUNK CONSTANT NUMBER := 4;
DBMS_LCR.LAST_LONG_CHUNK CONSTANT NUMBER := 5;
```

Returns NULL if the specified column does not exist.

If the command type of the row LCR is UPDATE, then specifying 'Y' for the use\_old parameter is a convenient way to get the value of the columns.

### Syntax

```
MEMBER FUNCTION GET_LONG_INFORMATION(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 use_old IN VARCHAR2 DEFAULT 'Y')
RETURN NUMBER;
```

### Parameters

**Table 174–19 GET\_LONG\_INFORMATION Function Parameters**

Parameter	Description
value_type	The type of value to return for the column, either old or new
column_name	The name of the column
use_old	<p>If Y and value_type is new, and no new value exists, then returns the corresponding old value. If N and value_type is new, then does not return the old value if no new value exists.</p> <p>If value_type is old or if the command_type of the row LCR is not UPDATE, then the value of the use_old parameter is ignored.</p> <p>NULL is not a valid specification for the use_old parameter.</p>

## GET\_VALUE Member Function

Returns the old or new value for the specified column, depending on the value type specified.

If the command type of the row LCR is UPDATE, then specifying 'Y' for the `use_old` parameter is a convenient way to get the value of a column.

### Syntax

```
MEMBER FUNCTION GET_VALUE(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 use_old IN VARCHAR2 DEFAULT 'Y')
RETURN SYS.AnyData;
```

### Parameters

**Table 174–20** *GET\_VALUE Function Parameters*

Parameter	Description
<code>value_type</code>	The type of value to return for the column. Specify <code>old</code> to get the old value for the column. Specify <code>new</code> to get the new value for the column.
<code>column_name</code>	The column name. If the column is present and has a NULL value, returns a <code>SYS.AnyData</code> instance containing a NULL value. If the column value is absent, then returns a NULL.
<code>use_old</code>	If Y and <code>value_type</code> is <code>new</code> , and no new value exists, then returns the corresponding old value. If N and <code>value_type</code> is <code>new</code> , then returns NULL if no new value exists. If <code>value_type</code> is <code>old</code> or if the <code>command_type</code> of the row LCR is not UPDATE, then the value of the <code>use_old</code> parameter is ignored. NULL is not a valid specification for the <code>use_old</code> parameter.

## GET\_VALUES Member Function

Returns a list of old or new values, depending on the value type specified.

If the command type of the row LCR is UPDATE, then specifying 'Y' for the `use_old` parameter is a convenient way to get the values of all columns.

### Syntax

```
MEMBER FUNCTION GET_VALUES(
 value_type IN VARCHAR2,
 use_old IN VARCHAR2 DEFAULT 'Y')
RETURN SYS.LCR$_ROW_LIST;
```

**Parameter****Table 174–21** *GET\_VALUES Procedure Parameter*

Parameter	Description
value_type	The type of values to return. Specify <code>old</code> to return a list of old values. Specify <code>new</code> to return a list of new values.
use_old	<p>If <code>Y</code> and <code>value_type</code> is <code>new</code>, then returns a list of all new values in the LCR. If a new value does not exist in the list, then returns the corresponding old value. Therefore, the returned list contains all existing new values and old values for the new values that do not exist.</p> <p>If <code>N</code> and <code>value_type</code> is <code>new</code>, then returns a list of all new values in the LCR without returning any old values.</p> <p>If <code>value_type</code> is <code>old</code> or if the <code>command_type</code> of the row LCR is not <code>UPDATE</code>, then the value of the <code>use_old</code> parameter is ignored.</p> <p><code>NULL</code> is not a valid specification for the <code>use_old</code> parameter.</p>

## RENAME\_COLUMN Member Procedure

Renames a column in an LCR.

### Syntax

```
MEMBER PROCEDURE RENAME_COLUMN(
 from_column_name IN VARCHAR2,
 to_column_name IN VARCHAR2,
 value_type IN VARCHAR2 DEFAULT '*');
```

### Parameters

**Table 174–22** *RENAME\_COLUMN Procedure Parameters*

Parameter	Description
from_column_name	The existing column name
to_column_name	The new column name. An error is raised if a column with the specified name already exists.
value_type	The type of value for which to rename the column.  Specify <code>old</code> to rename the old value of the column. An error is raised if the old value does not exist in the LCR.  Specify <code>new</code> to rename the new value of the column. An error is raised if the new value does not exist in the LCR.  If <code>*</code> is specified, then the column names for both old and new value are renamed. An error is raised if either column value does not exist in the LCR.

## SET\_LOB\_INFORMATION Member Procedure

Sets LOB information for the column.

---

---

**Note:** When you are processing a row LCR with a rule-based transformation, DML handler, or error handler, you cannot use this member procedure.

---

---

### Syntax

```
MEMBER PROCEDURE SET_LOB_INFORMATION(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 lob_information IN NUMBER);
```



## Parameters

**Table 174–23** *SET\_LOB\_INFORMATION Procedure Parameters*

Parameter	Description												
value_type	The type of value to set for the column, either old or new. Specify old only if lob_information is set to DBMS_LCR.NOT_A_LOB.												
column_name	The name of the column. An exception is raised if the column value does not exist. You may need to set this parameter for non-LOB columns.												
lob_information	Specify one of the following values: <table border="0" style="margin-left: 40px;"> <tr> <td>DBMS_LCR.NOT_A_LOB</td> <td>CONSTANT NUMBER := 1;</td> </tr> <tr> <td>DBMS_LCR.NULL_LOB</td> <td>CONSTANT NUMBER := 2;</td> </tr> <tr> <td>DBMS_LCR.INLINE_LOB</td> <td>CONSTANT NUMBER := 3;</td> </tr> <tr> <td>DBMS_LCR.EMPTY_LOB</td> <td>CONSTANT NUMBER := 4;</td> </tr> <tr> <td>DBMS_LCR.LOB_CHUNK</td> <td>CONSTANT NUMBER := 5;</td> </tr> <tr> <td>DBMS_LCR.LAST_LOB_CHUNK</td> <td>CONSTANT NUMBER := 6;</td> </tr> </table>	DBMS_LCR.NOT_A_LOB	CONSTANT NUMBER := 1;	DBMS_LCR.NULL_LOB	CONSTANT NUMBER := 2;	DBMS_LCR.INLINE_LOB	CONSTANT NUMBER := 3;	DBMS_LCR.EMPTY_LOB	CONSTANT NUMBER := 4;	DBMS_LCR.LOB_CHUNK	CONSTANT NUMBER := 5;	DBMS_LCR.LAST_LOB_CHUNK	CONSTANT NUMBER := 6;
DBMS_LCR.NOT_A_LOB	CONSTANT NUMBER := 1;												
DBMS_LCR.NULL_LOB	CONSTANT NUMBER := 2;												
DBMS_LCR.INLINE_LOB	CONSTANT NUMBER := 3;												
DBMS_LCR.EMPTY_LOB	CONSTANT NUMBER := 4;												
DBMS_LCR.LOB_CHUNK	CONSTANT NUMBER := 5;												
DBMS_LCR.LAST_LOB_CHUNK	CONSTANT NUMBER := 6;												

## SET\_LOB\_OFFSET Member Procedure

Sets the LOB offset for the specified column in the number of characters for CLOB columns and the number of bytes for BLOB columns.

---



---

**Note:** When you are processing a row LCR with a rule-based transformation, DML handler, or error handler, you cannot use this member procedure.

---



---

### Syntax

```
MEMBER PROCEDURE SET_LOB_OFFSET(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 lob_offset IN NUMBER);
```

## Parameters

**Table 174–24** *SET\_LOB\_OFFSET Procedure Parameters*

Parameter	Description
value_type	The type of value to set for the column. Currently, only <i>new</i> can be specified.
column_name	The column name. An error is raised if the column value does not exist in the LCR.
lob_offset	The LOB offset number. Valid values are <i>NULL</i> or a positive integer less than or equal to <code>DBMS_LOB.LOBMAXSIZE</code> .

## SET\_LOB\_OPERATION\_SIZE Member Procedure

Sets the operation size for the LOB column in the number of characters for CLOB columns and bytes for BLOB columns.

---

---

**Note:** When you are processing a row LCR with a rule-based transformation, DML handler, or error handler, you cannot use this member procedure.

---

---

### Syntax

```
MEMBER PROCEDURE SET_LOB_OPERATION_SIZE(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 lob_operation_size IN NUMBER);
```

## Parameters

**Table 174–25** *SET\_LOB\_OPERATION\_SIZE Procedure Parameters*

Parameter	Description
value_type	The type of value to set for the column. Currently, only new can be specified.
column_name	The name of the LOB column. An exception is raised if the column value does not exist in the LCR.
lob_operation_size	If lob_information for the LOB is or will be DBMS_LCR.LAST_LOB_CHUNK, then can be set to either a valid LOB ERASE value or a valid LOB TRIM value. A LOB_ERASE value must be a positive integer less than or equal to DBMS_LOB.LOBMAXSIZE. A LOB_TRIM value must be a nonnegative integer less than or equal to DBMS_LOB.LOBMAXSIZE.  Otherwise, set to NULL.

## SET\_VALUE Member Procedure

Overwrites the old or new value of the specified column.

One reason you may want to overwrite an old value for a column is to resolve an error that resulted from a conflict.

---



---

**Note:** When you are processing a row LCR with a rule-based transformation, DML handler, or error handler, you cannot use this member procedure on a LONG, LONG RAW, or LOB column.

---



---

### Syntax

```
MEMBER PROCEDURE SET_VALUE(
 value_type IN VARCHAR2,
 column_name IN VARCHAR2,
 column_value IN SYS.AnyData);
```

## Parameters

**Table 174–26** *SET\_VALUE Procedure Parameters*

Parameter	Description
value_type	The type of value to set. Specify <code>old</code> to set the old value of the column. Specify <code>new</code> to set the new value of the column.
column_name	The column name. An error is raised if the specified <code>column_value</code> does not exist in the LCR for the specified <code>column_type</code> .
column_value	The new value of the column. If <code>NULL</code> is specified, then an error is raised. To set the value to <code>NULL</code> , encapsulate the <code>NULL</code> in a <code>SYS.AnyData</code> instance.

## SET\_VALUES Member Procedure

Replaces all old values or all new values for the LCR, depending on the value type specified.

---



---

**Note:** When you are processing a row LCR with a rule-based transformation, DML handler, or error handler, you cannot use this member procedure on a `LONG`, `LONG RAW`, or `LOB` column.

---



---

### Syntax

```
MEMBER PROCEDURE SET_VALUES(
 value_type IN VARCHAR2,
 value_list IN SYS.LCR$_ROW_LIST);
```

## Parameters

**Table 174–27** *SET\_VALUES Procedure Parameters*

Parameter	Description
value_type	The type of values to replace. Specify <code>old</code> to replace the old values. Specify <code>new</code> to replace the new values.
value_list	List of values to replace the existing list. Use a <code>NULL</code> or an empty list to remove all values.

## Common Subprograms for LCR\$\_DDL\_RECORD and LCR\$\_ROW\_RECORD

The following functions and procedures are common to both the LCR\$\_DDL\_RECORD and LCR\$\_ROW\_RECORD type.

**See Also:** For descriptions of the subprograms for these types that are exclusive to each type:

- ["Summary of LCR\\$\\_DDL\\_RECORD Subprograms"](#) on page 174-7
- ["Summary of LCR\\$\\_ROW\\_RECORD Subprograms"](#) on page 174-17

**Table 174–28 Summary of Common Subprograms for DDL and Row LCR Types**

Subprogram	Description
<a href="#">"GET_COMMAND_TYPE Member Function"</a> on page 174-34	Returns the command type of the LCR
<a href="#">"GET_COMMIT_SCN Member Function"</a> on page 174-35	Returns the commit system change number (SCN) of the transaction to which the current LCR belongs
<a href="#">"GET_COMPATIBLE Member Function"</a> on page 174-35	Returns the minimal database compatibility required to support the LCR
<a href="#">"GET_EXTRA_ATTRIBUTE Member Function"</a> on page 174-36	Returns the value for the specified extra attribute in the LCR
<a href="#">"GET_OBJECT_NAME Member Function"</a> on page 174-38	Returns the name of the object that is changed by the LCR
<a href="#">"GET_OBJECT_OWNER Member Function"</a> on page 174-38	Returns the owner of the object that is changed by the LCR
<a href="#">"GET_SCN Member Function"</a> on page 174-38	Returns the system change number (SCN) of the LCR
<a href="#">"GET_SOURCE_DATABASE_NAME Member Function"</a> on page 174-38	Returns the source database name.
<a href="#">"GET_TAG Member Function"</a> on page 174-38	Returns the tag for the LCR
<a href="#">"GET_TRANSACTION_ID Member Function"</a> on page 174-39	Returns the transaction identifier of the LCR

**Table 174–28 Summary of Common Subprograms for DDL and Row LCR Types**

Subprogram	Description
"IS_NULL_TAG Member Function" on page 174-39	Returns Y if the tag for the LCR is NULL, or returns N if the tag for the LCR is not NULL
"SET_COMMAND_TYPE Member Procedure" on page 174-40	Sets the command type in the LCR
"SET_EXTRA_ATTRIBUTE Member Procedure" on page 174-40	Sets the value for the specified extra attribute in the LCR
"SET_OBJECT_NAME Member Procedure" on page 174-41	Sets the name of the object that is changed by the LCR
"SET_OBJECT_OWNER Member Procedure" on page 174-42	Sets the owner of the object that is changed by the LCR
"SET_SOURCE_DATABASE_NAME Member Procedure" on page 174-42	Sets the source database name of the object that is changed by the LCR
"SET_TAG Member Procedure" on page 174-43	Sets the tag for the LCR

## GET\_COMMAND\_TYPE Member Function

Returns the command type of the LCR.

**See Also:** The "SQL Command Codes" table in the *Oracle Call Interface Programmer's Guide* for a complete list of command types

### Syntax

```
MEMBER FUNCTION GET_COMMAND_TYPE ()
RETURN VARCHAR2;
```

## GET\_COMMIT\_SCN Member Function

Returns the commit system change number (SCN) of the transaction to which the current LCR belongs.

The commit SCN for a transaction is available only during apply or during error transaction execution. This function can be used only in a DML handler, DDL handler, or error handler. Such a handler may use the SCN obtained by this procedure to flashback to the transaction commit time for an LCR. In this case, the flashback must be performed at the source database for the LCR.

The commit SCN may not be available for an LCR that is part of an incomplete transaction. For example, user-enqueued LCRs may not have a commit SCN. If the commit SCN is not available for an LCR, then this function returns `NULL`.

### Syntax

```
MEMBER FUNCTION GET_COMMIT_SCN()
RETURN NUMBER;
```

## GET\_COMPATIBLE Member Function

Returns the minimal database compatibility required to support the LCR. You control the compatibility of an Oracle database using the `COMPATIBLE` initialization parameter.

The return value for this function can be one of the following:

Return Value	COMPATIBLE Initialization Parameter Equivalent
<code>DBMS_STREAMS.COMPATIBLE_9_2</code>	9.2.0
<code>DBMS_STREAMS.COMPATIBLE_10_1</code>	10.0.0

DDL LCRs always return `DBMS_STREAMS.COMPATIBLE_9_2`.

You may use the following functions for constant compatibility return values:

- The `DBMS_STREAMS.COMPATIBLE_9_2` function returns the `DBMS_STREAMS.COMPATIBLE_9_2` constant.
- The `DBMS_STREAMS.COMPATIBLE_10_1` function returns the `DBMS_STREAMS.COMPATIBLE_10_1` constant.

You can use these functions with the `GET_COMPATIBLE` member function for an LCR in rule conditions and apply handlers.

---

---

**Note:** You can determine which database objects in a database are not supported by Streams by querying the `DBA_STREAMS_UNSUPPORTED` data dictionary view.

---

---

**See Also:**

- *Oracle Streams Concepts and Administration* for examples of rules that discard changes that are not supported by Streams
- [Chapter 95, "DBMS\\_STREAMS"](#) and [Chapter 96, "DBMS\\_STREAMS\\_ADM"](#)
- *Oracle Database Reference* and *Oracle Database Upgrade Guide* for more information about the `COMPATIBLE` initialization parameter

**Syntax**

```
MEMBER FUNCTION GET_COMPATIBLE()
RETURN NUMBER;
```

## GET\_EXTRA\_ATTRIBUTE Member Function

Returns the value for the specified extra attribute in the LCR. The returned extra attribute is contained within a `SYS.AnyData` instance. You can use the `INCLUDE_EXTRA_ATTRIBUTE` procedure in the `DBMS_CAPTURE_ADM` package to instruct a capture process to capture one or more extra attributes.

**See Also:** ["INCLUDE\\_EXTRA\\_ATTRIBUTE Procedure"](#) on page 19-25

**Syntax**

```
MEMBER FUNCTION GET_EXTRA_ATTRIBUTE(
 attribute_name IN VARCHAR2)
RETURN SYS.AnyData;
```



## Parameters

**Table 174–29** *GET\_EXTRA\_ATTRIBUTE Function Parameter*

Parameter	Description
<code>attribute_name</code>	<p>The name of the extra attribute to return. Valid names are:</p> <ul style="list-style-type: none"> <li>■ <code>row_id</code> The rowid of the row changed in a row LCR. This attribute is not included in DDL LCRs, nor in row LCRs for index-organized tables. The type is <code>UROWID</code>.</li> <li>■ <code>serial#</code> The serial number of the session that performed the change captured in the LCR. The type is <code>NUMBER</code>.</li> <li>■ <code>session#</code> The identifier of the session that performed the change captured in the LCR. The type is <code>NUMBER</code>.</li> <li>■ <code>thread#</code> The thread number of the instance in which the change captured in the LCR was performed. Typically, the thread number is relevant only in a Real Application Clusters environment. The type is <code>NUMBER</code>.</li> <li>■ <code>tx_name</code> The name of the transaction that includes the LCR. The type is <code>VARCHAR2</code>.</li> <li>■ <code>username</code> The name of the user who performed the change captured in the LCR. The type is <code>VARCHAR2</code>.</li> </ul> <p>An error is raised if the specified <code>attribute_name</code> is not valid.</p> <p>If no value exists for the specified extra attribute, then returns a <code>NULL</code>.</p>

## GET\_OBJECT\_NAME Member Function

Returns the name of the object that is changed by the LCR.

### Syntax

```
MEMBER FUNCTION GET_OBJECT_NAME()
RETURN VARCHAR2;
```

## GET\_OBJECT\_OWNER Member Function

Returns the owner of the object that is changed by the LCR.

### Syntax

```
MEMBER FUNCTION GET_OBJECT_OWNER()
RETURN VARCHAR2;
```

## GET\_SCN Member Function

Returns the system change number (SCN) of the LCR.

### Syntax

```
MEMBER FUNCTION GET_SCN()
RETURN NUMBER;
```

## GET\_SOURCE\_DATABASE\_NAME Member Function

Returns the global name of the source database name. The source database is the database where the change occurred.

### Syntax

```
MEMBER FUNCTION GET_SOURCE_DATABASE_NAME()
RETURN VARCHAR2;
```

## GET\_TAG Member Function

Returns the tag for the LCR. An LCR tag is a binary tag that enables tracking of the LCR. For example, this tag may be used to determine the original source database of the DML or DDL change when apply forwarding is used.

**See Also:** *Oracle Streams Replication Administrator's Guide* for more information about tags

### Syntax

```
MEMBER FUNCTION GET_TAG()
RETURN RAW;
```

## GET\_TRANSACTION\_ID Member Function

Returns the transaction identifier of the LCR.

### Syntax

```
MEMBER FUNCTION GET_TRANSACTION_ID()
RETURN VARCHAR2;
```

## IS\_NULL\_TAG Member Function

Returns Y if the tag for the LCR is NULL, or returns N if the tag for the LCR is not NULL.

**See Also:** *Oracle Streams Replication Administrator's Guide* for more information about tags

### Syntax

```
MEMBER FUNCTION IS_NULL_TAG()
RETURN VARCHAR2;
```

## SET\_COMMAND\_TYPE Member Procedure

Sets the command type in the LCR. If the command type specified cannot be interpreted, then an error is raised. For example, changing `INSERT` to `GRANT` would raise an error.

### See Also:

- The description of the `command_type` parameter in "[LCR\\$\\_DDL\\_RECORD Constructor Function Parameters](#)" on page 174-5
- The description of the `command_type` parameter in "[LCR\\$\\_ROW\\_RECORD Constructor Function Parameters](#)" on page 174-16
- The "SQL Command Codes" table in the *Oracle Call Interface Programmer's Guide* for a complete list of command types

### Syntax

```
MEMBER PROCEDURE SET_COMMAND_TYPE(
 command_type IN VARCHAR2);
```

### Parameter

**Table 174–30 SET\_COMMAND\_TYPE Procedure Parameter**

Parameter	Description
<code>command_type</code>	The command type. This parameter should be set to a non-NULL value.

## SET\_EXTRA\_ATTRIBUTE Member Procedure

Sets the value for the specified extra attribute in the LCR. You can use the `INCLUDE_EXTRA_ATTRIBUTE` procedure in the `DBMS_CAPTURE_ADM` package to instruct a capture process to capture one or more extra attributes.

**See Also:** "[INCLUDE\\_EXTRA\\_ATTRIBUTE Procedure](#)" on page 19-25

### Syntax

```
MEMBER PROCEDURE SET_EXTRA_ATTRIBUTE(
 attribute_name IN VARCHAR2,
 attribute_value IN SYS.AnyData);
```

## Parameters

**Table 174–31** *SET\_EXTRA\_ATTRIBUTE Procedure Parameter*

Parameter	Description
attribute_name	<p>The name of the extra attribute to set. Valid names are:</p> <ul style="list-style-type: none"> <li>■ row_id The rowid of the row changed in a row LCR. This attribute is not included in DDL LCRs, nor in row LCRs for index-organized tables. The type is VARCHAR2.</li> <li>■ serial# The serial number of the session that performed the change captured in the LCR. The type is NUMBER.</li> <li>■ session# The identifier of the session that performed the change captured in the LCR. The type is NUMBER.</li> <li>■ thread# The thread number of the instance in which the change captured in the LCR was performed. Typically, the thread number is relevant only in a Real Application Clusters environment. The type is NUMBER.</li> <li>■ tx_name The name of the transaction that includes the LCR. The type is VARCHAR2.</li> <li>■ username The name of the user who performed the change captured in the LCR. The type is VARCHAR2.</li> </ul> <p>An error is raised if the specified attribute_name is not valid.</p>
attribute_value	<p>The value to which the specified extra attribute is set. If set to NULL, then the specified extra attribute is removed from the LCR. To set to NULL, encapsulate the NULL in a SYS.AnyData instance.</p>

## SET\_OBJECT\_NAME Member Procedure

Sets the name of the object that is changed by the LCR.

### Syntax

```
MEMBER PROCEDURE SET_OBJECT_NAME(
```

```
object_name IN VARCHAR2);
```

### Parameter

**Table 174–32 SET\_OBJECT\_NAME Procedure Parameter**

Parameter	Description
object_name	The name of the object

## SET\_OBJECT\_OWNER Member Procedure

Sets the owner of the object that is changed by the LCR.

### Syntax

```
MEMBER PROCEDURE SET_OBJECT_OWNER(
 object_owner IN VARCHAR2);
```

### Parameter

**Table 174–33 SET\_OBJECT\_OWNER Procedure Parameter**

Parameter	Description
object_owner	The schema that contains the object

## SET\_SOURCE\_DATABASE\_NAME Member Procedure

Sets the source database name of the object that is changed by the LCR.

### Syntax

```
MEMBER PROCEDURE SET_SOURCE_DATABASE_NAME(
 source_database_name IN VARCHAR2);
```

### Parameter

**Table 174–34 SET\_SOURCE\_DATABASE\_NAME Procedure Parameter**

Parameter	Description
source_database_name	The source database of the change. If you do not include the domain name, then the local domain is appended to the database name automatically. For example, if you specify DBS1 and the local domain is .NET, then DBS1.NET is specified automatically. This parameter should be set to a non-NULL value.

## SET\_TAG Member Procedure

Sets the tag for the LCR. An LCR tag is a binary tag that enables tracking of the LCR. For example, this tag may be used to determine the original source database of the change when apply forwarding is used.

**See Also:** *Oracle Streams Replication Administrator's Guide* for more information about tags

### Syntax

```
MEMBER PROCEDURE SET_TAG(
 tag IN RAW);
```

### Parameter

**Table 174–35 SET\_TAG Procedure Parameter**

Parameter	Description
tag	The binary tag for the LCR. The size limit for a tag value is two kilobytes.

## LCR\$\_ROW\_LIST Type

Identifies a list of column values for a row in a table.

This type uses the LCR\$\_ROW\_UNIT type and is used in the LCR\$\_ROW\_RECORD type.

**See Also:**

- ["LCR\\$\\_ROW\\_UNIT Type" on page 174-45](#)
- ["LCR\\$\\_ROW\\_RECORD Type" on page 174-14](#)

### Syntax

```
CREATE TYPE SYS.LCR$_ROW_LIST AS TABLE OF SYS.LCR$_ROW_UNIT
/
```



## LCR\$\_ROW\_UNIT Type

Identifies the value for a column in a row.

This type is used in the LCR\$\_ROW\_LIST type.

**See Also:** ["LCR\\$\\_ROW\\_LIST Type"](#) on page 174-44

### Syntax

```
CREATE TYPE LCR$_ROW_UNIT AS OBJECT (
 column_name VARCHAR2(4000),
 data SYS.AnyData,
 lob_information NUMBER,
 lob_offset NUMBER,
 lob_operation_size NUMBER,
 long_information NUMBER);
/
```

### Attributes

**Table 174–36** LCR\$\_ROW\_UNIT Attributes

Attribute	Description												
column_name	The name of the column												
data	The data contained in the column												
lob_information	Contains the LOB information for the column and contains one of the following values: <table border="0" style="margin-left: 40px;"> <tr> <td>DBMS_LCR.NOT_A_LOB</td> <td>CONSTANT NUMBER := 1;</td> </tr> <tr> <td>DBMS_LCR.NULL_LOB</td> <td>CONSTANT NUMBER := 2;</td> </tr> <tr> <td>DBMS_LCR.INLINE_LOB</td> <td>CONSTANT NUMBER := 3;</td> </tr> <tr> <td>DBMS_LCR.EMPTY_LOB</td> <td>CONSTANT NUMBER := 4;</td> </tr> <tr> <td>DBMS_LCR.LOB_CHUNK</td> <td>CONSTANT NUMBER := 5;</td> </tr> <tr> <td>DBMS_LCR.LAST_LOB_CHUNK</td> <td>CONSTANT NUMBER := 6;</td> </tr> </table>	DBMS_LCR.NOT_A_LOB	CONSTANT NUMBER := 1;	DBMS_LCR.NULL_LOB	CONSTANT NUMBER := 2;	DBMS_LCR.INLINE_LOB	CONSTANT NUMBER := 3;	DBMS_LCR.EMPTY_LOB	CONSTANT NUMBER := 4;	DBMS_LCR.LOB_CHUNK	CONSTANT NUMBER := 5;	DBMS_LCR.LAST_LOB_CHUNK	CONSTANT NUMBER := 6;
DBMS_LCR.NOT_A_LOB	CONSTANT NUMBER := 1;												
DBMS_LCR.NULL_LOB	CONSTANT NUMBER := 2;												
DBMS_LCR.INLINE_LOB	CONSTANT NUMBER := 3;												
DBMS_LCR.EMPTY_LOB	CONSTANT NUMBER := 4;												
DBMS_LCR.LOB_CHUNK	CONSTANT NUMBER := 5;												
DBMS_LCR.LAST_LOB_CHUNK	CONSTANT NUMBER := 6;												
lob_offset	The LOB offset specified in the number of characters for CLOB columns and the number of bytes for BLOB columns. Valid values are NULL or a positive integer less than or equal to DBMS_LOB.LOBMAXSIZE.												

**Table 174–36 (Cont.) LCR\$\_ROW\_UNIT Attributes**

Attribute	Description
lob_operation_size	<p>If lob_information for the LOB is DBMS_LCR.LAST_LOB_CHUNK, then can be set to either a valid LOB ERASE value or a valid LOB TRIM value. A LOB_ERASE value must be a positive integer less than or equal to DBMS_LOB.LOBMAXSIZE. A LOB_TRIM value must be a nonnegative integer less than or equal to DBMS_LOB.LOBMAXSIZE.</p> <p>If lob_information is not DBMS_LCR.LAST_LOB_CHUNK and for all other operations, is NULL.</p>
long_information	<p>Contains the LONG information for the column and contains one of the following values:</p> <p>DBMS_LCR.not_a_long            CONSTANT NUMBER := 1;</p> <p>DBMS_LCR.null_long            CONSTANT NUMBER := 2;</p> <p>DBMS_LCR.inline_long        CONSTANT NUMBER := 3;</p> <p>DBMS_LCR.long_chunk         CONSTANT NUMBER := 4;</p> <p>DBMS_LCR.last_long_chunk    CONSTANT NUMBER := 5;</p>

---

## *interMedia* ORDAudio TYPE

The *interMedia* ORDAudio object type supports the storage and management of audio data.

Audio data can have different formats, encoding types, compression types, numbers of channels, sampling rates, sample sizes, and playing times (duration) depending upon how the audio data is digitally recorded. Oracle *interMedia* ORDAudio can store and retrieve audio data of any data format. Oracle *interMedia* ORDAudio can automatically extract metadata from audio data of a variety of popular audio formats. Oracle *interMedia* ORDAudio can also extract application attributes and store them in the `comments` attribute of the object in XML form.

- [Documentation of ORDAudio](#)

---

## Documentation of ORDAudio

For a complete description of this package within the context of Oracle *interMedia*, see `ORDAudio` in the *Oracle interMedia Reference*.

---

## *interMedia* ORDDoc TYPE

The *interMedia* ORDDoc object type supports the storage and management of heterogeneous media data including image, audio, and video.

Heterogeneous media data can have different formats depending upon the application generating the media data. Oracle *interMedia* can store and retrieve media data of any data format. The *interMedia* ORDDoc data type can be used in applications that require you to store different types of heterogeneous media data in the same column so you can build a common metadata index on all the different types of media data. Using this index, you can search across all the different types of heterogeneous media data. Note that you cannot use this same search technique if the different types of heterogeneous media data are stored in different types of objects in different columns of relational tables.

- [Documentation of ORDDoc](#)

---

## Documentation of ORDDoc

For a complete description of this package within the context of Oracle *interMedia*, see `ORDDoc` in the *Oracle interMedia Reference*.

---

## *interMedia* ORDImage TYPE

The *interMedia* ORDImage object type supports the storage, management, and manipulation of image data.

Digitized images consist of the image data (digitized bits) and attributes that describe and characterize the image data.

The image data (pixels) can have varying depths (bits for each pixel) depending on how the image was captured, and can be organized in various ways. The organization of the image data is known as the data format. Oracle *interMedia* ORDImage can store and retrieve image data of any data format. Oracle *interMedia* ORDImage can process (cut, scale, and generate thumbnails) of images, convert the format of images, and automatically extract properties of images of a variety of popular data formats.

- [Documentation of ORDImage](#)

---

## Documentation of ORDImage

For a complete description of this package within the context of Oracle *interMedia*, see `ORDImage` in the *Oracle interMedia Reference*.



---

## *interMedia* ORDImageSignature TYPE

The *interMedia* ORDImageSignature object type supports content-based retrieval of images (image matching).

The *interMedia* ORDImageSignature object type supports the extraction of color, texture, and shape information from an image. This extracted information, referred to as the image signature, is stored in an ORDImageSignature object. You can then use object methods to find matching images based on their extracted signatures.

- [Documentation of ORDImageSignature](#)

---

## Documentation of ORDImageSignature

For a complete description of this package within the context of Oracle *interMedia*, see `ORDImageSignature` in the *Oracle interMedia Reference*.

---

## *interMedia* SQL/MM Still Image TYPE

Oracle *interMedia* provides support for the SQL/MM Still Image Standard, which supports the storage, retrieval, and modification of images in the database and the ability to locate images using visual predicates.

The following object relational types for images and image characteristics are included in this support: *SI\_StillImage*, *SI\_AverageColor*, *SI\_Color*, *SI\_ColorHistogram*, *SI\_FeatureList*, *SI\_PositionalColor*, and *SI\_Texture*.

- [Documentation of SQL/MM Still Image](#)

---

## Documentation of SQL/MM Still Image

For a complete description of this package within the context of Oracle *interMedia*, see SQL/MM Still Image in the *Oracle interMedia Reference*.

---

## *interMedia* ORDVideO TYPE

The *interMedia* ORDVideO object type supports the storage and management of video data.

Digitized video consists of the video data (digitized bits) and the attributes that describe and characterize the video data. Video applications sometimes associate application-specific information, such as the description of the video training tape, date recorded, instructor's name, producer's name, and so forth, within the video data.

The video data can have different formats, compression types, frame rates, frame sizes, frame resolutions, playing times, compression types, number of colors, and bit rates depending upon how the video data was digitally recorded. Oracle *interMedia* ORDVideO can store and retrieve video data of any data format. Oracle *interMedia* ORDVideO can automatically extract metadata from video data of a variety of popular video formats. Oracle *interMedia* ORDVideO can also extract application attributes and store them in the `comments` attribute of the object in XML form identical to what is provided by the *interMedia* Annotator utility.

- [Documentation of ORDVideO](#)

---

## Documentation of ORDVideO

For a complete description of this package within the context of Oracle *interMedia*, see `ORDVideO` in the *Oracle interMedia Reference*.

This chapter describes the types used with rules, rule sets, and evaluation contexts.

**See Also:**

- [Chapter 81, "DBMS\\_RULE"](#)
- [Chapter 82, "DBMS\\_RULE\\_ADM"](#)

This chapter contains the following topic:

- [Summary of Rule Types](#)

---

## Summary of Rule Types

**Table 181–1 Rule Types**

Type	Description
"RESATTRIBUTE_VALUE Type" on page 181-4	Specifies the value of a variable attribute
"RESATTRIBUTE_VALUE_LIST Type" on page 181-4	Identifies a list of attribute values
"RESCOLUMN_VALUE Type" on page 181-5	Specifies the value of a table column
"RESCOLUMN_VALUE_LIST Type" on page 181-6	Identifies a list of column values
"RESNAME_ARRAY Type" on page 181-6	Identifies a list of names
"RESNV_ARRAY Type" on page 181-6	Identifies a list of name-value pairs
"RESNV_LIST Type" on page 181-6	Identifies an object containing a list of name-value pairs and methods that operate on this list. This object type is used to represent the event context and the action context for a rule
"RESNV_NODE Type" on page 181-9	Identifies a name-value pair
"RESRULE_HIT Type" on page 181-10	Specifies a rule found as a result of evaluation
"RESRULE_HIT_LIST Type" on page 181-10	Identifies a list of rules found as a result of evaluation
"RETABLE_ALIAS Type" on page 181-11	Provides the table corresponding to an alias used in a rule evaluation context
"RETABLE_ALIAS_LIST Type" on page 181-12	Identifies a list of table aliases used in a rule evaluation context
"RETABLE_VALUE Type" on page 181-12	Specifies the value of a table row using a ROWID
"RETABLE_VALUE_LIST Type" on page 181-12	Identifies a list of table values
"RESVARIABLE_TYPE Type" on page 181-13	Provides the type of a variable used in a rule evaluation context



**Table 181–1 (Cont.) Rule Types**

Type	Description
"RESVARIABLE_TYPE_LIST Type" on page 181-15	Identifies a list of variables and their types used in a rule evaluation context
"RESVARIABLE_VALUE Type" on page 181-16	Specifies the value of a variable
"RESVARIABLE_VALUE_LIST Type" on page 181-16	Identifies a list of variable values

Rule types are used with the following Oracle-supplied PL/SQL packages:

- DBMS\_RULE
- DBMS\_RULE\_ADM

You can use the DBMS\_RULE\_ADM package to create and administer rules, rule sets, and evaluation contexts, and you can use the DBMS\_RULE package to evaluate rules.

When you use Streams, rules determine which changes are captured by a capture process, which events are propagated by a propagation, which events are applied by an apply process, and which events are dequeued by a messaging client. The following Streams packages use rules:

- DBMS\_APPLY\_ADM
- DBMS\_CAPTURE\_ADM
- DBMS\_PROPAGATION\_ADM
- DBMS\_STREAMS
- DBMS\_STREAMS\_ADM
- DBMS\_STREAMS\_AUTH

**See Also:** *Oracle Streams Concepts and Administration*

## RE\$ATTRIBUTE\_VALUE Type

Specifies the value of a variable attribute.

---

---

**Note:** The variable name and attribute name may be enclosed in double quotation marks (") if the name contains special characters.

---

---

### Syntax

```
TYPE SYS.RE$ATTRIBUTE_VALUE (
 variable_name VARCHAR2(32),
 attribute_name VARCHAR2(4000),
 attribute_value SYS.AnyData);
```

### Attributes

**Table 181–2 RE\$ATTRIBUTE\_VALUE Attributes**

Attribute	Description
variable_name	Specifies the variable used in a rule
attribute_name	Specifies the attribute name. The attribute name may be a multi-component name, such as a1.b2.c3.
attribute_value	Specifies the attribute value

## RE\$ATTRIBUTE\_VALUE\_LIST Type

Identifies a list of attribute values.

### Syntax

```
TYPE SYS.RE$ATTRIBUTE_VALUE_LIST AS VARRAY(1024) OF SYS.RE$ATTRIBUTE_VALUE;
```

## RE\$COLUMN\_VALUE Type

Specifies the value of a table column.

---



---

**Note:** The column name may be enclosed in double quotation marks (") if the name contains special characters.

---



---

### Syntax

```
TYPE SYS.RE$COLUMN_VALUE (
 table_alias VARCHAR2(32),
 column_name VARCHAR2(4000),
 column_value SYS.AnyData);
```

### Attributes

**Table 181-3 RE\$COLUMN\_VALUE Attributes**

Attribute	Description
table_alias	Specifies the alias used for the table in a rule
column_name	Specifies the column name
column_value	Specifies the column value

## RE\$COLUMN\_VALUE\_LIST Type

Identifies a list of column values.

### Syntax

```
TYPE SYS.RE$COLUMN_VALUE_LIST AS VARRAY(1024) OF SYS.RE$COLUMN_VALUE;
```

## RE\$NAME\_ARRAY Type

Identifies a list of names.

### Syntax

```
TYPE SYS.RE$NAME_ARRAY AS VARRAY(1024) OF VARCHAR2(30);
```

## RE\$NV\_ARRAY Type

Identifies a list of name-value pairs.

### Syntax

```
TYPE SYS.RE$NV_ARRAY AS VARRAY(1024) OF SYS.RE$NV_NODE;
```

## RE\$NV\_LIST Type

Identifies an object containing a list of name-value pairs and methods that operate on this list. This object type is used to represent the event context for rule set evaluation and the action context for a rule.

### Syntax

```
TYPE SYS.RE$NV_LIST AS OBJECT(
 actx_list SYS.RE$NV_ARRAY);
```

## Attributes

**Table 181–4** *RE\$NV\_LIST Attributes*

Attribute	Description
actx_list	The list of name-value pairs

## RE\$NV\_LIST Subprograms

This section describes the following member procedures and member functions of the `SYS.RE$NV_LIST` type:

- [ADD\\_PAIR Member Procedure](#)
- [GET\\_ALL\\_NAMES Member Function](#)
- [GET\\_VALUE Member Function](#)
- [REMOVE\\_PAIR Member Procedure](#)

### **ADD\_PAIR Member Procedure**

Adds a name-value pair to the list of name-value pairs.

---



---

**Note:** The name may be enclosed in double quotation marks (") if the name contains special characters.

---



---

### **Syntax**

```
MEMBER PROCEDURE ADD_PAIR(
 name IN VARCHAR2,
 value IN SYS.AnyData);
```

### **Parameters**

**Table 181–5** *ADD\_PAIR Procedure Parameters*

Parameter	Description
name	The name in the name-value pair being added to the list. If the name already exists in the list, then an error is raised.
value	The value in the name-value pair being added to the list

**GET\_ALL\_NAMES Member Function**

Returns a list of all the names in the name-value pair list.

**Syntax**

```
MEMBER FUNCTION GET_ALL_NAMES()
RETURN SYS.RE$NAME_ARRAY;
```

**GET\_VALUE Member Function**

Returns the value for the specified name in a name-value pair list.

---

---

**Note:** The name may be enclosed in double quotation marks (") if the name contains special characters.

---

---

**Syntax**

```
MEMBER FUNCTION GET_VALUE(
 name IN VARCHAR2)
RETURN SYS.AnyData;
```

**Parameters**

**Table 181–6** *GET\_VALUE Procedure Parameters*

Parameter	Description
name	The name whose value to return

**REMOVE\_PAIR Member Procedure**

Removes the name-value pair with the specified name from the name-value pair list.

---

---

**Note:** The name may be enclosed in double quotation marks (") if the name contains special characters.

---

---

**Syntax**

```
MEMBER PROCEDURE REMOVE_PAIR(
 name IN VARCHAR2);
```

## Parameters

**Table 181–7 REMOVE\_PAIR Procedure Parameters**

Parameter	Description
name	The name of the pair to remove

## RE\$NV\_NODE Type

Identifies a name-value pair.

---



---

**Note:** The name may be enclosed in double quotation marks (") if the name contains special characters.

---



---

## Syntax

```
TYPE SYS.RE$NV_NODE (
 nvn_name VARCHAR2(30),
 nvn_value SYS.AnyData);
```

## Attributes

**Table 181–8 RE\$NV\_NODE Attributes**

Attribute	Description
nvn_name	Specifies the name in the name-value pair
nvn_value	Specifies the value in the name-value pair

## RE\$RULE\_HIT Type

Specifies a rule found as a result of an evaluation.

**See Also:**

- ["CREATE\\_RULE Procedure"](#) on page 82-11
- ["ALTER\\_RULE Procedure"](#) on page 82-6

### Syntax

```
TYPE SYS.RE$RULE_HIT (
 rule_name VARCHAR2(65),
 rule_action_context RE$NV_LIST);
```

### Attributes

**Table 181–9 RE\$RULE\_HIT Attributes**

Attribute	Description
rule_name	The rule name in the form <i>schema_name.rule_name</i> . For example, a rule named <code>employee_rule</code> in the <code>hr</code> schema is returned in the form <code>"hr"."employee_rule"</code> .
rule_action_context	The rule action context as specified in the <code>CREATE_RULE</code> or <code>ALTER_RULE</code> procedure of the <code>DBMS_RULE_ADM</code> package

## RE\$RULE\_HIT\_LIST Type

Identifies a list of rules found as a result of an evaluation.

### Syntax

```
TYPE SYS.RE$RULE_HIT_LIST AS VARRAY(1024) OF SYS.RE$RULE_HIT;
```



## RE\$TABLE\_ALIAS Type

Provides the table corresponding to an alias used in a rule evaluation context. A specified table name must satisfy the schema object naming rules.

---



---

**Note:** The table name may be enclosed in double quotation marks (") if the name contains special characters.

---



---

**See Also:** *Oracle Database SQL Reference* for information about schema object naming rules

### Syntax

```
TYPE SYS.RE$TABLE_ALIAS IS OBJECT(
 table_alias VARCHAR2(32),
 table_name VARCHAR2(194));
```

### Attributes

**Table 181–10 RE\$TABLE\_ALIAS Attributes**

Attribute	Description
table_alias	The alias used for the table in a rule
table_name	<p>The table name referred to by the alias. A synonym can be specified. The table name is resolved in the evaluation context schema.</p> <p>The format is one of the following:</p> <p style="text-align: center;"><i>schema_name.table_name</i></p> <p style="text-align: center;"><i>table_name</i></p> <p>For example, if the <i>schema_name</i> is <i>hr</i> and the <i>table_name</i> is <i>employees</i>, then enter the following:</p> <p style="text-align: center;"><i>hr.employees</i></p>

## RE\$TABLE\_ALIAS\_LIST Type

Identifies a list of table aliases used in a rule evaluation context.

### Syntax

```
TYPE SYS.RE$TABLE_ALIAS_LIST AS VARRAY(1024) OF SYS.RE$TABLE_ALIAS;
```

## RE\$TABLE\_VALUE Type

Specifies the value of a table row using a ROWID.

### Syntax

```
TYPE SYS.RE$TABLE_VALUE(
 table_alias VARCHAR2(32),
 table_rowid VARCHAR2(18));
```

### Attributes

**Table 181–11** RE\$TABLE\_VALUE Attributes

Attribute	Description
table_alias	Specifies the alias used for the table in a rule
table_rowid	Specifies the rowid for the table row

## RE\$TABLE\_VALUE\_LIST Type

Identifies a list of table values.

---

---

**Note:** Each table alias in the list in the list must be unique.

---

---

### Syntax

```
TYPE SYS.RE$TABLE_VALUE_LIST AS VARRAY(1024) OF SYS.RE$TABLE_VALUE;
```

## RE\$VARIABLE\_TYPE Type

Provides the type of a variable used in a rule evaluation context. A specified variable name must satisfy the schema object naming rules.

---



---

**Note:** The variable name may be enclosed in double quotation marks (") if the name contains special characters.

---



---

**See Also:** *Oracle Database SQL Reference* for information about schema object naming rules

### Syntax

```
TYPE SYS.RE$VARIABLE_TYPE (
 variable_name VARCHAR2(32),
 variable_type VARCHAR2(4000),
 variable_value_function VARCHAR2(228),
 variable_method_function VARCHAR2(228));
```

### Attributes

**Table 181–12** RE\$VARIABLE\_TYPE Attributes

Attribute	Description
variable_name	The variable name used in a rule
variable_type	The type that is resolved in the evaluation context schema. Any valid Oracle built-in datatype, user-defined type, or Oracle-supplied type can be specified. See the <i>Oracle Database SQL Reference</i> for more information about these types.

**Table 181–12 (Cont.) RE\$VARIABLE\_TYPE Attributes**

Attribute	Description
<code>variable_value_function</code>	<p>A value function that can be specified for implicit variables. A synonym can be specified. The function name is resolved in the evaluation context schema. It is executed on behalf of the owner of a rule set using the evaluation context or containing a rule that uses the evaluation context.</p> <p>See the "Usage Notes" for more information.</p>
<code>variable_method_function</code>	<p>Specifies a value function, which can return the result of a method invocation. Specifying such a function can speed up evaluation, if there are many simple rules that invoke the method on the variable. The function can be a synonym or a remote function.</p> <p>The function name is resolved in the evaluation context schema. It is executed on behalf of the owner of a rule set using the evaluation context or containing a rule that uses the evaluation context.</p> <p>See the "Usage Notes" for more information.</p>

## Usage Notes

The functions for both the `variable_value_function` parameter and `variable_method_function` parameter have the following format:

*schema\_name.package\_name.function\_name@dblink*

Any of the following parts of the format may be omitted: *schema\_name*, *package\_name*, and *@dblink*.

For example, if the *schema\_name* is *hr*, the *package\_name* is *var\_pac*, the *function\_name* is *func\_value*, and the *dblink* is *dbs1.net*, then enter the following:

`hr.var_pac.func_value@dbs1.net`

The following sections describe the signature of the functions.

**Signature for variable\_value\_function**

The function must have the following signature:

```
FUNCTION variable_value_function_name(
 evaluation_context_schema IN VARCHAR2,
 evaluation_context_name IN VARCHAR2,
 variable_name IN VARCHAR2,
 event_context IN SYS.RE$NV_LIST)
RETURN SYS.RE$VARIABLE_VALUE;
```

**Signature for variable\_method\_function**

This function must have the following signature:

```
FUNCTION variable_method_function_name(
 evaluation_context_schema IN VARCHAR2,
 evaluation_context_name IN VARCHAR2,
 variable_value IN SYS.RE$VARIABLE_VALUE,
 method_name IN VARCHAR2,
 event_context IN SYS.RE$NV_LIST)
RETURN SYS.RE$ATTRIBUTE_VALUE;
```

## RE\$VARIABLE\_TYPE\_LIST Type

Identifies a list of variables and their types used in a rule evaluation context.

### Syntax

```
TYPE SYS.RE$VARIABLE_TYPE_LIST AS VARRAY(1024) OF SYS.RE$VARIABLE_TYPE;
```

## RE\$VARIABLE\_VALUE Type

Specifies the value of a variable.

---

---

**Note:** The variable name may be enclosed in double quotation marks (") if the name contains special characters.

---

---

### Syntax

```
TYPE SYS.RE$VARIABLE_VALUE (
 variable_name VARCHAR2(32),
 variable_data SYS.AnyData);
```

### Attributes

**Table 181–13 RE\$VARIABLE\_VALUE Attributes**

Attribute	Description
variable_name	Specifies the variable name used in a rule
variable_data	Specifies the data for the variable value

## RE\$VARIABLE\_VALUE\_LIST Type

Identifies a list of variable values.

### Syntax

```
TYPE SYS.RE$VARIABLE_VALUE_LIST AS VARRAY(1024) OF SYS.RE$VARIABLE_VALUE;
```

`XMLType` is a system-defined opaque type for handling XML data. It has predefined member functions on it to extract XML nodes and fragments.

You can create columns of `XMLType` and insert XML documents into it. You can also generate XML documents as `XMLType` instances dynamically using the `SYS_XMLGEN` and `SYS_XMLAGG` SQL functions.

This chapter contains the following topics:

- [Summary of XMLType Subprograms](#)

**See Also:**

- *Oracle XML DB Developer's Guide*

---

## Summary of XMLType Subprograms

**Table 182–1** summarizes functions and procedures of the XMLType.

**Table 182–1** XMLTYPE Subprograms

Method	Description
<a href="#">CREATENONSCHEMABASEDXML</a> on page 182-4	Creates a non schema based XML from the input schema based instance.
<a href="#">CREATESCHEMABASEDXML</a> on page 182-5	Creates a schema based XMLType instance from the non-schema based instance using the input schema URL.
<a href="#">CREATEXML</a> on page 6	Static function for creating and returning an XMLType instance.
<a href="#">EXISTSNODE</a> on page 182-9	Takes a XMLType instance and a XPath and returns 1 or 0 indicating if applying the XPath returns a non-empty set of nodes.
<a href="#">EXTRACT</a> on page 182-10	Takes a XMLType instance and an XPath, applies the XPath expression and returns the results as an XMLType.
<a href="#">GETBLOBVAL</a> on page 182-11	Returns the value of the XMLType instance as a BLOB
<a href="#">GETCLOBVAL</a> on page 182-12	Returns the value of the XMLType instance as a CLOB.
<a href="#">GETNAMESPACE</a> on page 182-13	Returns the namespace for the top level element in a schema based document.
<a href="#">GETNUMBERVAL</a> on page 182-14	Returns the value of the XMLType instance as a NUMBER. This is only valid if the input XMLType instance contains a simple text node and is convertible to a number.
<a href="#">GETROOTELEMENT</a> on page 182-15	Returns the root element of the input instance. Returns NULL if the instance is a fragment
<a href="#">GETSCHEMAURL</a> on page 182-16	Returns the XML schema URL if the input is an XML Schema based.
<a href="#">GETSTRINGVAL</a> on page 182-17	Returns the value of the XMLType instance as a string.
<a href="#">ISFRAGMENT</a> on page 182-18	Checks if the input XMLType instance is a fragment or not. A fragment is a XML instance, which has more than one root element.
<a href="#">ISSCHEMABASED</a> on page 182-19	Returns 1 or 0 indicating if the input XMLType instance is a schema based one or not.



**Table 182–1 (Cont.) XMLTYPE Subprograms**

Method	Description
<a href="#">ISSCHEMAVALID</a> on page 182-20	Checks if the input instance is schema valid according to the given schema URL.
<a href="#">ISSCHEMAVALIDATED</a> on page 182-21	Checks if the instance has been validated against the schema.
<a href="#">SCHEMAVALIDATE</a> on page 182-22	Validates the input instance according to the XML Schema. Raises error if the input instance is non-schema based.
<a href="#">SETSCHEMAVALIDATED</a> on page 182-23	Sets the schema valid flag to avoid costly schema validation.
<a href="#">TOOBJECT</a> on page 182-24	Converts the XMLType instance to an object type.
<a href="#">TRANSFORM</a> on page 182-25	Takes an XMLType instance and an associated stylesheet (which is also an XMLType instance), applies the stylesheet and returns the result as XML.
<a href="#">XMLTYPE</a> on page 182-26	<i>Constructs an instance of the XMLType datatype. The constructor can take in the XML as a CLOB, VARCHAR2 or take in a object type.</i>

## CREATENONSCHEMABASEDXML

Member function. Creates a non-schema based XML document from a schema based instance.

### **Syntax**

```
MEMBER FUNCTION CREATENONSCHEMABASEDXML
return XMLType deterministic;
```

## CREATESCHEMABASEDXML

Member function. Creates a schema based XMLType instance from a non-schema based XMLType value. It uses either the supplied SCHEMA URL, or the SCHEMALOCATION attribute of the instance.

### Syntax

```
MEMBER FUNCTION CREATESCHEMABASEDXML(
 SCHEMA IN VARCHAR2 := NULL)
RETURN XMLTYPE DETERMINISTIC;
```

Parameter	IN / OUT	Description
SCHEMA	(IN)	Optional XMLSchema URL used to convert the value to the specified schema..

## CREATXML

Static function for creating and returning an `XMLType` instance. The string and clob parameters used to pass in the data must contain well-formed and valid XML documents. The options are described in the following table.

Syntax	Description
<pre> STATIC FUNCTION CREATXML(   XMLDATA IN VARCHAR2) RETURN XMLTYPE DETERMINISTIC; </pre>	Creates the <code>XMLType</code> instance from a string.
<pre> STATIC FUNCTION CREATXML(   XMLDATA IN CLOB) RETURN XMLTYPE DETERMINISTIC; </pre>	Creates the <code>XMLType</code> instance from a CLOB.
<pre> STATIC FUNCTION CREATXML (   XMLDATA IN CLOB,   SCHEMA IN VARCHAR2,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0 ) RETURN XMLTYPE DETERMINISTIC; </pre>	This static function creates a schema-based <code>XMLType</code> instance using the specified schema and xml data parameters.
<pre> STATIC FUNCTION CREATXML (   XMLDATA IN VARCHAR2,   SCHEMA IN VARCHAR2,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0) RETURN XMLTYPE DETERMINISTIC; </pre>	This static function creates a schema-based <code>XMLType</code> instance using the specified schema and xml data parameters.
<pre> STATIC FUNCTION CREATXML (   XMLDATA IN "&lt;ADT_1&gt;",   SCHEMA IN VARCHAR2 := NULL,   ELEMENT IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0) RETURN XMLTYPE DETERMINISTIC; </pre>	Creates an XML instance from an instance of an user-defined type.
<pre> STATIC FUNCTION CREATXML (   XMLDATA IN SYS_REFCURSOR,   SCHEMA IN VARCHAR2 := NULL,   ELEMENT IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0) RETURN XMLTYPE DETERMINISTIC; </pre>	Creates an XML instance from a cursor reference. You can pass in any arbitrary SQL query as a <code>CURSOR</code> .

Syntax	Description
<pre> STATIC FUNCTION CREATEXML (   XMLDATA IN ANYDATA,   SCHEMA IN VARCHAR2 := NULL,   ELEMENT IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0) RETURN SYS.XMLTYPE DETERMINISTIC PARALLEL_ENABLE </pre>	<p>Creates an XML instance from ANYDATA. If the ANYDATA instance contains an ADT, the XMLType returned is the same as would be returned for a call directly on the ADT. If the ANYDATA contains a scalar, the XMLType contains a leaf node with the scalar value. The element name for this node is taken from the optional element string if present, and is "ANYDATA" if it is not.</p>
<pre> STATIC FUNCTION CREATEXML (   XMLDATA IN BLOB,   CSID IN NUMBER,   SCHEMA IN VARCHAR2,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0) RETURN SYS.XMLTYPE DETERMINISTIC </pre>	<p>Creates an XML instance from a BLOB.</p>
<pre> STATIC FUNCTION CREATEXML (   XMLDATA IN BFILE,   CSID IN NUMBER,   SCHEMA IN VARCHAR2,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0) RETURN SYS.XMLTYPE DETERMINISTIC </pre>	<p>Creates an XML instance from a BFILE.</p>

Parameter	IN / OUT	Description
XMLDATA	(IN)	The actual data in the form of a BFILE, BLOB, CLOB, REF cursor, VARCHAR2 or object type.
SCHEMA	(IN)	Optional Schema URL to be used to make the input conform to the given schema.
VALIDATED	(IN)	Flag to indicate that the instance is valid according to the given XML Schema. (Default is 0)
WELLFORMED	(IN)	Flag to indicate that the input is well formed. If set, then the database would not do well formed check on the input instance. (Default is 0)
ELEMENT	(IN)	Optional element name in the case of the ADT_1 or REF CURSOR constructors. (Default is NULL)
CSID	(IN)	The character set id of input XML data.



## EXISTSNODE

Member function. Checks if the node exists. If the XPath string is `NULL` or the document is empty, then a value of 0 is returned, otherwise returns 1. The options are described in the following table.

Syntax	Description
<pre>MEMBER FUNCTION EXISTSNODE(   XPATH IN VARCHAR2) RETURN NUMBER DETERMINISTIC;</pre>	Given an XPath expression, checks if the XPath applied over the document can return any valid nodes.
<pre>MEMBER FUNCTION EXISTSNODE(   XPATH IN VARCHAR2,   NSMAP IN VARCHAR2) RETURN NUMBER DETERMINISTIC;</pre>	This member function uses the XPath expression with the namespace information and checks if applying the XPath returns any nodes or not.

Parameter	IN / OUT	Description
XPATH	(IN)	The XPath expression to test.
NSMAP	(IN)	Optional namespace mapping.

## EXTRACT

Member function. Extracts an `XMLType` fragment and returns an `XMLType` instance containing the result node(s). If the XPath does not result in any nodes, then returns `NULL`. The options are described in the following table.

Syntax	Description
<pre>MEMBER FUNCTION EXTRACT(   XPATH IN VARCHAR2) RETURN XMLTYPE DETERMINISTIC;</pre>	Given an XPath expression, applies the XPath to the document and returns the fragment as an <code>XMLType</code> .
<pre>MEMBER FUNCTION EXTRACT(   XPATH IN VARCHAR2,   NSMAP IN VARCHAR2) RETURN XMLTYPE DETERMINISTIC;</pre>	This member function applies the XPath expression and namespace mapping, over the XML data to return a <code>XMLType</code> instance containing the resultant fragment.

Parameter	IN / OUT	Description
XPATH	(IN)	The XPath expression to apply.
NSMAP	(IN)	Optional prefix to namespace mapping information.



## GETBLOBVAL

Member function. Returns a BLOB containing the serialized XML representation; if the return is a temporary BLOB, then it must be freed after use.

### Syntax

```
MEMBER FUNCTION GETBLOBVAL()
RETURN BLOB DETERMINISTIC;
```

## GETCLOBVAL

Member function. Returns a CLOB containing the serialized XML representation; if the returns is a temporary CLOB, then it must be freed after use.

### Syntax

```
MEMBER FUNCTION GETCLOBVAL()
RETURN CLOB DETERMINISTIC;
```

## GETNAMESPACE

Member function. Returns the namespace of the top level element in the instance. Returns NULL if the input is a fragment or is a non-schema based instance.

### Syntax

```
MEMBER FUNCTION GETNAMESPACE
RETURN VARCHAR2 DETERMINISTIC;
```

## GETNUMBERVAL

Member function. Returns a numeric value, formatted from the text value pointed to by the `XMLType` instance. The `XMLType` must point to a valid text node that contains a numerical value. The options are described in the following table.

### Syntax

```
MEMBER FUNCTION GETNUMBERVAL()
RETURN NUMBER DETERMINISTIC;
```

## GETROOTELEMENT

Member function. Gets the root element of the `XMLType` instance. Returns `NULL` if the instance is a fragment.

### Syntax

```
MEMBER FUNCTION GETROOTELEMENT
RETURN VARCHAR2 DETERMINISTIC;
```

## GETSCHEMAURL

Member function. Returns the XML Schema URL corresponding to the `XMLType` instance, if the `XMLType` instance is a schema-based document. Otherwise returns `NULL`.

### Syntax

```
MEMBER FUNCTION GETSCHEMAURL
RETURN VARCHAR2 DETERMINISTIC;
```

## GETSTRINGVAL

Member function. Returns the document as a string. Returns a string containing the serialized XML representation, or in case of text nodes, the text itself. If the XML document is bigger than the maximum size of the `varchar2`, which is 4000, then an error is raised at run time.

### Syntax

```
MEMBER FUNCTION GETSTRINGVAL()
RETURN VARCHAR2 DETERMINISTIC;
```

## ISFRAGMENT

Determines if the `XMLType` instance corresponds to a well-formed document, or a fragment. Returns 1 or 0 indicating if the `XMLType` instance contains a fragment or a well-formed document.

### Syntax

```
MEMBER FUNCTION ISFRAGMENT()
RETURN NUMBER DETERMINISTIC;
```



## ISSCHEMABASED

Member function. Determines whether the XMLType instance is schema-based or not. Returns 1 or 0 depending on whether the XMLType instance is schema-based.

### Syntax

```
MEMBER FUNCTION ISSCHEMABASED
RETURN NUMBER DETERMINISTIC;
```

## ISSCHEMAVALID

Member function. Checks if the input instance is conformant to a specified schema. Does not change the validation status of the XML instance. If a XML Schema URL is not specified and the xml document is schema based, the conformance is checked against the `XMLType` instance's own schema.

### Syntax

```
MEMBER FUNCTION ISSCHEMAVALID(
 SCHURL IN VARCHAR2 := NULL,
 ELEM IN VARCHAR2 := NULL)
RETURN NUMBER DETERMINISTIC;
```

Parameter	IN / OUT	Description
SCHURL	( IN )	The URL of the XML Schema against which to check conformance.
ELEM	( IN )	Element of a specified schema, against which to validate. This is useful when we have a XML Schema which defines more than one top level element, and we want to check conformance against a specific one of these elements.

## ISSCHEMAVALIDATED

Member function. Returns the validation status of the XMLType instance -- tells if a schema based instance has been actually validated against its schema. Returns 1 if the instance has been validated against the schema, 0 otherwise.

### Syntax

```
MEMBER FUNCTION ISSCHEMAVALIDATED
RETURN NUMBER DETERMINISTIC;
```

## SCHEMAVALIDATE

Member procedure. Validates the XML instance against its schema if it hasn't already been done. For non-schema based documents an error is raised. If validation fails an error is raised; else, the document's status is changed to validated.

### Syntax

```
MEMBER PROCEDURE SCHEMAVALIDATE(
 SELF IF OUT NOCOPY XMLTYPE);
```

Parameter	IN / OUT	Description
SELF	(OUT)	XML instance being validated against the schema.

## SETSCHEMAVALIDATED

Member function. Sets the `VALIDATION` state of the input XML instance.

### Syntax

```
MEMBER PROCEDURE SETSCHEMAVALIDATED(
 SELF IF OUT NOCOPY XMLTYPE,
 FLAG IN BINARY_INTEGER := 1);
```

Parameter	IN / OUT	Description
SELF	(OUT)	XML instance.
FLAG	(IN)	0 - NOT VALIDATED; 1 - VALIDATED (Default)

## TOBJECT

Member procedure. Converts the XML value to an object type using the XMLSCHEMA mapping, if available. If a SCHEMA is not supplied or the input is a non-schema based XML, the procedure uses canonical mapping between elements and object type attributes.

**See Also:**

- An in-depth discussion of this topic inside *Oracle XML DB Developer's Guide*

**Syntax**

```
MEMBER PROCEDURE TOBJECT(
 SELF IN XMLTYPE,
 OBJECT OUT "<ADT_1>",
 SCHEMA IN VARCHAR2 := NULL,
 ELEMENT IN VARCHAR2 := NULL);
```

---

Parameter	IN / OUT	Description
SELF	(IN)	Instance to be converted. Implicit if used as a member procedure.
OBJECT	(IN)	Converted object. An object instance of the required type may be passed in to this function
SCHEMA	(IN)	Schema URL. The mapping of the XMLType instance to the converted object instance may be specified using a schema.
ELEMENT	(IN)	Top-level element name. An XML Schema document does not specify the top-level element for a conforming XML instance document without this parameter.

---

## TRANSFORM

Member function. This member function transforms the XML data using the XSL stylesheet argument and the top-level parameters passed as a string of name=value pairs. If any of the arguments other than the `parammap` is NULL, then a NULL is returned.

### Syntax

```
MEMBER FUNCTION TRANSFORM(
 XSL IN XMLTYPE,
 PARAMMAP IN VARCHAR2 := NULL)
RETURN XMLTYPE DETERMINISTIC;
```

Parameter	IN / OUT	Description
XSL	(IN)	The XSL stylesheet describing the transformation
PARAMMAP	(IN)	Top level parameters to the XSL - string of name=value pairs

## XMLTYPE

XMLType constructor. The options are described in the following table.

Syntax	Description
<pre> CONSTRUCTOR FUNCTION XMLTYPE(   XMLDATA IN CLOB,   SCHEMA IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0) RETURN SELF AS RESULT DETERMINISTIC; </pre>	<p>This constructor function creates an optionally schema-based XMLType instance using the specified schema and xml data parameters.</p>
<pre> CONSTRUCTOR FUNCTION XMLTYPE(   XMLDATA IN VARCHAR2,   SCHEMA IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0) RETURN SELF AS RESULT DETERMINISTIC; </pre>	<p>This constructor function creates an optionally schema-based XMLType instance using the specified schema and xml data parameters.</p>
<pre> CONSTRUCTOR FUNCTION XMLTYPE (   XMLDATA IN "W&lt;ADT_1&gt;",   SCHEMA IN VARCHAR2 := NULL,   ELEMENT IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0) RETURN SELF AS RESULT DETERMINISTIC; </pre>	<p>This constructor function creates an optionally schema-based XMLType instance from the specified object type parameter.</p>
<pre> CONSTRUCTOR FUNCTION XMLTYPE(   XMLDATA IN SYS_REFCURSOR,   SCHEMA IN VARCHAR2 := NULL,   ELEMENT IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0) RETURN SELF AS RESULT DETERMINISTIC; </pre>	<p>This constructor function creates an optionally schema-based XMLType instance from the specified REF CURSOR parameter.</p>
<pre> CONSTRUCTOR FUNCTION XMLTYPE(   XMLDATA IN ANYDATA,   SCHEMA IN VARCHAR2 := NULL,   ELEMENT IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0) RETURN SELF AS RESULT DETERMINISTIC PARALLEL_ENABLE </pre>	<p>This constructor function creates an optionally schema-based XMLType instance from the specified ANYDATA parameter. If the ANYDATA instance contains an ADT, the XMLType returned is the same as would be returned for a call directly on the ADT. If the ANYDATA contains a scalar, the XMLType contains a leaf node with the scalar value. The element name for this node is taken from the optional element string if present, and is "ANYDATA" if it is not.</p>



Syntax	Description
<pre> CONSTRUCTOR FUNCTION XMLTYPE(   XMLDATA IN BLOB, CSID IN NUMBER,   SCHEMA IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0) RETURN SELF AS RESULT DETERMINISTIC </pre>	<p>This constructor function creates an optionally schema-based XMLType instance from the specified BLOB parameter.</p>
<pre> CONSTRUCTOR FUNCTION XMLTYPE(   XMLDATA IN BFILE,   CSID IN NUMBER,   SCHEMA IN VARCHAR2 := NULL,   VALIDATED IN NUMBER := 0,   WELLFORMED IN NUMBER := 0) RETURN SELF AS RESULT DETERMINISTIC </pre>	<p>This constructor function creates an optionally schema-based XMLType instance from the specified BFILE parameter.</p>

Parameter	IN / OUT	Description
XMLDATA	(IN)	The data in the form of a BFILE, BLOB, CLOB, REFS, VARCHAR2 or object type.
SCHEMA	(IN)	Optional Schema URL to be used to make the input conform to the given schema.
VALIDATED	(IN)	Indicates that the instance is valid to the given XML Schema.
WELLFORMED	(IN)	Indicates that the input is well formed. If set, then the database would not do well formed check on the input instance.
ELEMENT	(IN)	Optional element name in the case of the ADT_1 or REF CURSOR constructors. (Default is NULL)
CSID	(IN)	The character set id of input XML data.



## A

---

- ABORT procedure, 78-4
- ABORT\_GLOBAL\_INSTANTIATION procedure, 19-4
- ABORT\_REDEF\_TABLE procedure, 68-5
- ABORT\_SCHEMA\_INSTANTIATION procedure, 19-5
- ABORT\_TABLE\_INSTANTIATION procedure, 19-6
- ABORTED\_REQUEST\_THRESHOLD procedure, 87-4
- ACCEPT\_SQL\_PROFILE procedure, 91-6
- ACLCHECKPRIVILEGES function, 108-6
- ACTIVE\_INSTANCES procedure, 104-8
- ADD\_COLUMN member procedure, 174-19
- ADD\_COOKIES procedure, 156-36
- ADD\_GLOBAL\_PROPAGATION\_RULES procedure, 96-14
- ADD\_GLOBAL\_RULES procedure, 96-19
- ADD\_PAIR member procedure, 181-7
- ADD\_RULE procedure, 82-4
- ADD\_SCHEMA\_PROPAGATION\_RULES procedure, 96-34
- ADD\_SCHEMA\_RULES procedure, 96-39
- ADD\_SQLSET\_REFERENCE function, 91-8
- ADD\_SUBSET\_PROPAGATION\_RULES procedure, 96-46
- ADD\_SUBSET\_RULES procedure, 96-52
- ADD\_TABLE\_PROPAGATION\_RULES procedure, 96-58
- ADD\_TABLE\_RULES procedure, 96-63
- ADD\_WARNING\_SETTING\_CAT procedure, 105-4
- ADD\_WARNING\_SETTING\_NUM procedure, 105-5
- ADD2MULTI procedure, 136-4
- ADDATTR member procedure of ANYTYPE TYPE, 170-6
- ADDINSTANCE member procedure of ANYDATASET TYPE, 169-4
- ADDRESS function of HTF package, 123-17
- ADDRESS procedure of HTP package, 128-17
- ADMIN\_TABLES procedure, 70-6
- ADVISE\_COMMIT procedure, 101-5
- ADVISE\_NOTHING procedure, 101-6
- ADVISE\_ROLLBACK procedure, 101-7
- ALL\_XML\_SCHEMAS catalog view, 118-20
- ALL\_XML\_TAB\_COLS catalog view, 118-27
- ALL\_XML\_TABLES catalog view, 118-24
- ALL\_XML\_VIEW\_COLS catalog view, 118-33
- ALL\_XML\_VIEWS catalog view, 118-30
- ALLOCATE\_UNIQUE procedure, 46-6
- ALTER\_APPLY procedure, 15-4
- ALTER\_CAPTURE procedure, 19-7
- ALTER\_COMPILE procedure, 26-4
- ALTER\_DATABASE\_TAB\_MONITORING procedure, 93-16
- ALTER\_PROPAGATION procedure, 65-3
- ALTER\_RULE procedure, 82-6
- ALTER\_SCHEMA\_TAB\_MONITORING procedure, 93-17
- ALTER\_SQL\_PROFILE procedure, 91-9
- ALTER\_STATS\_HISTORY\_RETENTION procedure, 93-18
- ALTER\_TABLE\_NOT\_REFERENCEABLE

- procedure, 26-5
- ALTER\_TABLE\_REFERENCEABLE
  - procedure, 26-7
- AMATCH function, 134-6
- ANALYZE\_DATABASE procedure, 104-6
- ANALYZE\_PART\_OBJECT procedure, 104-9
- ANALYZE\_SCHEMA procedure, 104-10
- ANCHOR function
  - of HTF package, 123-18
- ANCHOR procedure
  - of HTP package, 128-18
- ANCHOR2 function
  - of HTF package, 123-19
- ANCHOR2 procedure
  - of HTP package, 128-19
- anonymous PL/SQL blocks
  - dynamic SQL and, 90-3
- AnyData datatype
  - queues
    - creating, 96-107
    - removing, 96-94
- ANYDATA TYPE, 168-1
- ANYDATASET TYPE, 169-1
- ANYTYPE TYPE, 170-1
- APPENDCHILD function, 113-42
- APPENDDATA procedure, 113-43
- APPLETCLOSE function
  - of HTF package, 123-20
- APPLETCLOSE procedure
  - of HTP package, 128-20
- APPLETOPEN function
  - of HTF package, 123-21
- APPLETOPEN procedure
  - of HTP package, 128-21
- APPLY procedure, 23-21
- apply process
  - altering, 15-4
  - conflict handlers
    - setting, 15-54
  - creating, 15-14, 96-19, 96-39, 96-52, 96-63
  - DBMS\_APPLY\_ADM package, 15-1
  - DDL handler
    - setting, 15-4, 15-14
  - DML handlers
    - setting, 15-30
  - dropping, 15-24
  - enqueueing events, 15-36
  - error handlers
    - setting, 15-30
  - error queue
    - deleting errors, 15-22, 15-23
    - executing errors, 15-26, 15-27
    - getting error messages, 15-28
  - instantiation
    - global SCN, 15-40
    - schema SCN, 15-49
    - table SCN, 15-52
  - message handler
    - setting, 15-4, 15-14
  - parameters
    - commit\_serialization, 15-46
    - disable\_on\_error, 15-46
    - disable\_on\_limit, 15-46
    - maximum\_scn, 15-46
    - parallelism, 15-47
    - setting, 15-45
    - time\_limit, 15-47
    - trace\_level, 15-48
    - transaction\_limit, 15-48
  - precommit handler
    - setting, 15-4, 15-14
  - rules
    - defining global, 96-19
    - defining schema, 96-39
    - defining subset, 96-52
    - defining table, 96-63
    - removing, 96-96
  - specifying execution, 15-38
  - starting, 15-58
  - stopping, 15-59
  - substitute key columns
    - setting, 15-43
- AREA function
  - of HTF package, 123-23
- AREA procedure
  - of HTP package, 128-23
- arrays
  - BIND\_ARRAY procedure, 90-9
  - bulk DML using DBMS\_SQL, 90-28, 90-32
- ATTACH\_SESSION procedure, 27-19

ATTACH\_SIMPLE\_TABLESPACE procedure, 99-6  
ATTACH\_TABLESPACES procedure, 99-8  
AUTHORIZE function, 131-4  
AVAILABLE function, 165-8  
AWR\_REPORT\_HTML function, 106-3  
AWR\_REPORT\_TEXT function, 106-4

## B

---

BASE function  
  of HTF package, 123-24  
BASE procedure  
  of HTP package, 128-24  
BASE64\_DECODE function, 154-3  
BASE64\_ENCODE function, 154-4  
BASEFONT function  
  of HTF package, 123-25  
BASEFONT procedure  
  of HTP package, 128-25  
BEGIN\_DISCRETE\_TRANSACTION  
  procedure, 101-8  
BEGIN\_REQUEST function, 156-37  
BEGINCREATE static procedure  
  of ANYDATA TYPE, 168-6  
  of ANYDATASET TYPE, 169-5  
  of ANYTYPE TYPE, 170-3  
BGSOUND function  
  of HTF package, 123-26  
BGSOUND procedure  
  of HTP package, 128-26  
BIG function  
  of HTF package, 123-27  
BIG procedure  
  of HTP package, 128-27  
BIND\_ARRAY procedures, 90-27  
BIND\_VARIABLE procedures, 90-30  
BIND\_VARIABLES function, 137-6  
binning, 24-3  
  categorical, 24-3  
  numerical, 24-3  
  quantile, 24-3  
BIT\_AND function, 161-5  
BIT\_COMPLEMENT function, 161-6  
BIT\_OR function, 161-7  
BIT\_XOR function, 161-8

BLOCKQUOTECLOSE function  
  of HTF package, 123-28  
BLOCKQUOTECLOSE procedure  
  of HTP package, 128-28  
BLOCKQUOTEOPEN function  
  of HTF package, 123-29  
BLOCKQUOTEOPEN procedure  
  of HTP package, 128-29  
BODYCLOSE function  
  of HTF package, 123-30  
BODYCLOSE procedure  
  of HTP package, 128-30  
BODYOPEN function  
  of HTF package, 123-31  
BODYOPEN procedure  
  of HTP package, 128-31  
BOLD function  
  of HTF package, 123-32  
BOLD procedure  
  of HTP package, 128-32  
BR function  
  of HTF package, 123-33  
BR procedure  
  of HTP package, 128-33  
BROKEN procedure, 41-6  
BUILD procedure, 19-14  
BUILD\_CHAIN\_ROWS\_TABLE procedure, 39-3  
BUILD\_EXCEPTIONS\_TABLE procedure, 39-5  
BUILD\_PART\_INDEX procedure, 62-6

## C

---

CALENDARPRINT procedures, 137-7  
CAN\_REDEF\_TABLE procedure, 68-6  
CANCEL\_TUNING\_TASK procedure, 91-10  
CANONICALIZE procedure, 104-12  
capture process  
  altering, 19-7  
  building a Streams data dictionary, 19-14  
  creating, 96-19, 96-39, 96-52, 96-63  
  instantiation  
    aborting database preparation, 19-4  
    aborting schema preparation, 19-5  
    aborting table preparation, 19-6  
    preparing a database for, 19-27

- preparing a schema for, 19-28
- preparing a table for, 19-29
- parameters
  - disable\_on\_limit, 19-31
  - maximum\_scn, 19-31
  - message\_limit, 19-31
  - parallelism, 19-31
  - setting, 19-30
  - startup\_seconds, 19-32
  - time\_limit, 19-32
  - trace\_level, 19-32
  - write\_alert\_log, 19-32
- rules
  - defining global, 96-19
  - defining schema, 96-39
  - defining subset, 96-52
  - defining table, 96-63
  - removing, 96-96
- starting, 19-33
- stopping, 19-34
- CAST\_FROM\_BINARY\_DOUBLE function, 161-9
- CAST\_FROM\_BINARY\_FLOAT function, 161-11
- CAST\_FROM\_BINARY\_INTEGER
  - function, 161-13
- CAST\_FROM\_NUMBER function, 161-14
- CAST\_TO\_BINARY\_DOUBLE function, 161-15
- CAST\_TO\_BINARY\_FLOAT function, 161-17
- CAST\_TO\_BINARY\_INTEGER function, 161-19
- CAST\_TO\_NUMBER function, 161-20
- CAST\_TO\_NVARCHAR2 function, 161-23
- CAST\_TO\_RAW function, 161-21
- CAST\_TO\_VARCHAR2 function, 161-22
- categorical binning, 24-3
- catproc.sql script, 1-3
- CELLSPRINT procedures, 137-9
- CENTER function
  - of HTP package, 123-34
- CENTER procedure
  - of HTP package, 128-34
- CENTERCLOSE function
  - of HTP package, 123-35
- CENTERCLOSE procedure
  - of HTP package, 128-35
- CENTEROPEN function
  - of HTP package, 123-36
- CENTEROPEN procedure
  - of HTP package, 128-36
- CFG\_GET function, 108-7
- CFG\_REFRESH procedure, 108-8
- CFG\_UPDATE procedure, 108-9
- Change Data Capture
  - DBMS\_CDC\_PUBLISH package, 20-1
  - DBMS\_CDC\_SUBSCRIBE package, 21-1
- CHANGE functions and procedures, 134-8
- CHANGE procedure, 41-7
- change tables
  - tablespaces created in, 20-25
- CHANGE\_JOIN\_POS procedure, 60-3
- CHECK\_OBJECT procedure, 70-8
- CHECKIN function, 109-3
- CHECKOUT procedure, 109-4
- CHECKPRIVILEGES function, 108-11
- CHECKSUM functions, 133-4
- CHOOSE\_DATE procedure, 137-12
- CITE function
  - of HTF package, 123-37
- CITE procedure
  - of HTP package, 128-37
- CLEAR\_COOKIES procedure, 156-39
- CLEAR\_PENDING\_AREA procedure, 76-10
- CLEAR\_PLSQL\_TRACE procedure, 100-8
- CLEAR\_USED procedure, 59-4
- CLEARKEYCOLUMNLIST procedure, 117-4, 119-4
- CLEARUPDATECOLUMNLIST procedure, 117-4, 119-5
- CLIENT\_ID\_STAT\_DISABLE procedure, 53-3
- CLIENT\_ID\_STAT\_ENABLE procedure, 53-4
- CLIENT\_ID\_TRACE\_DISABLE procedure, 53-5
- CLIENT\_ID\_TRACE\_ENABLE procedure, 53-6
- clipping
  - see trimming, 24-4
- CLOB2FILE procedure, 121-2
- CLONE\_SIMPLE\_TABLESPACE procedure, 99-11
- CLONE\_TABLESPACES procedure, 99-14
- CLONENODE function, 113-44
- CLOSE\_ALL\_CONNECTIONS procedure, 165-10
- CLOSE\_CONNECTION procedure, 165-11
- CLOSE\_CURSOR procedure, 90-35
- CLOSE\_ITERATOR procedure, 81-4

CLOSE\_PERSISTENT\_CONN procedure, 156-40  
 CLOSE\_PERSISTENT\_CONNS procedure, 156-41  
 CLOSECONTEXT procedure, 114-4, 116-4, 117-5, 119-6  
 CODE function  
   of HTF package, 123-38  
 CODE procedure  
   of HTP package, 128-38  
 collections  
   table items, 90-28, 90-32  
 column masking for VPD, 79-6  
 COLUMN\_VALUE procedure, 90-36  
 COLUMN\_VALUE\_LONG procedure, 90-39  
 column-level VPD, 79-15  
 COMMA\_TO\_TABLE procedures, 104-14  
 COMMAND function and procedure, 164-13  
 COMMAND\_REPLIES function, 164-15  
 COMMENT function  
   of HTF package, 123-39  
 COMMENT procedure  
   of HTP package, 128-39  
 COMMIT procedure, 101-9  
 COMMIT\_COMMENT procedure, 101-10  
 COMMIT\_FORCE procedure, 101-11  
 COMPARE function, 161-24  
 COMPARE\_OLD\_VALUES procedure, 15-12  
 COMPATIBLE\_10\_1 function, 95-4, 174-35  
 COMPATIBLE\_9\_2 function, 95-5, 174-35  
 COMPILE\_FROM\_REMOTE procedure, 44-4  
 COMPILE\_SCHEMA procedure, 104-15  
 COMPILESCHEMA procedure, 118-4  
 COMPUTE\_CONFUSION\_MATRIX  
   procedure, 23-27  
 COMPUTE\_LIFT procedure, 23-31  
 COMPUTE\_ROC procedure, 23-35  
 CONCAT function, 161-25  
 CONFIGUREAUTOSYNC procedure, 111-6  
 CONNECTION record type, 164-3  
 constants  
   DBMS\_DATA\_MINING, 23-3  
   DBMS\_MGWMSG package, 52-2  
 CONTINUE function, 27-20  
 CONVERT function, 46-8, 114-5, 161-26  
 CONVERT\_ANYDATA\_TO\_LCR\_DDL  
   function, 95-6  
 CONVERT\_ANYDATA\_TO\_LCR\_ROW  
   function, 95-7  
 CONVERT\_LONG\_TO\_LOB\_CHUNK member  
   procedure, 174-20  
 CONVERT\_RAW\_VALUE procedures, 93-19  
 CONVERT\_RAW\_VALUE\_NVARCHAR  
   procedure, 93-20  
 CONVERT\_RAW\_VALUE\_ROWID  
   procedure, 93-21  
 CONVERTTOBLOB procedure, 45-24  
 CONVERTTOCLOB procedure, 45-28  
 COPIES function, 161-28  
 COPY\_FILE procedure, 35-3  
 COPY\_TABLE\_DEPENDENTS procedure, 68-7  
 COPYEVOLVE procedure, 118-5  
 cost matrix, 23-18  
 CREATE PACKAGE BODY command, 1-3  
 CREATE PACKAGE command, 1-3  
 CREATE\_ALTER\_TYPE\_ERROR\_TABLE  
   procedure, 104-16  
 CREATE\_APPLY procedure, 15-14  
 CREATE\_BASELINE function and  
   procedure, 106-5  
 CREATE\_BIN\_CAT procedure, 24-10  
 CREATE\_BIN\_NUM procedure, 24-11  
 CREATE\_CALL function, 153-4  
 CREATE\_CAPTURE procedure  
   capture process  
     creating, 19-16  
 CREATE\_CLIP procedure, 24-12  
 CREATE\_CONSUMER\_GROUP procedure, 76-11  
 CREATE\_EDIT\_TABLES procedure, 60-4  
 CREATE\_EVALUATION\_CONTEXT  
   procedure, 82-9  
 CREATE\_INDEX\_COST procedure, 88-4  
 CREATE\_MODEL procedure, 23-24  
 CREATE\_NORM\_LIN procedure, 24-13  
 CREATE\_OUTLINE procedure, 59-5  
 CREATE\_PENDING\_AREA procedure, 76-12  
 CREATE\_PIPE function, 63-19  
 CREATE\_PLAN procedure, 76-14  
 CREATE\_PLAN\_DIRECTIVE procedure, 76-16  
 CREATE\_PROPAGATION procedure, 65-6  
 CREATE\_RULE procedure, 82-11  
 CREATE\_RULE\_SET procedure, 82-13

CREATE\_SERVICE function, 153-5  
 CREATE\_SERVICE procedure, 85-4  
 CREATE\_SIMPLE\_PLAN procedure, 76-19  
 CREATE\_SNAPSHOT function and  
     procedure, 106-6  
 CREATE\_SQLSET procedure, 91-11  
 CREATE\_STAT\_TABLE procedure, 93-22  
 CREATE\_TABLE\_COST procedures, 88-5  
 CREATE\_TRANSFORMATION procedure, 102-3  
 CREATE\_TUNING\_TASK functions, 91-12  
 CREATEATTRIBUTE function, 113-45  
 CREATECDATASECTION function, 113-46  
 CREATECOMMENT function, 113-47  
 CREATEDATASTOREPREF procedure, 111-7  
 CREATEDOCUMENT function, 113-48  
 CREATEDOCUMENTFRAGMENT  
     function, 113-49  
 CREEELEMENT function, 113-50  
 CREATEENTITYREFERENCE function, 113-51  
 CREATEFILTERPREF procedure, 111-8  
 CREATEFOLDER function, 108-12  
 CREATEINDEX procedure, 111-9  
 CREATELEXERPREF procedure, 111-10  
 CREATENONSCHEMABASEDXML  
     function, 182-4  
 CREATEOIDPATH function, 108-13  
 CREATEPREFERENCES procedure, 111-11  
 CREATEPROCESSINGINSTRUCTION  
     function, 113-52  
 CREATERESOURCE function, 108-14  
 CREATESCHEMABASEDXML function, 182-5  
 CREESECTIONGROUPOPREF procedure, 111-12  
 CREATESTOPLISTPREF procedure, 111-13  
 CREATESTORAGEPREF procedure, 111-14  
 CREATETEXTNODE function, 113-53  
 CREATEURI function, 172-10, 172-19, 172-28  
 CREATEWORLDLISTPREF procedure, 111-15  
 CREATEXML function, 182-6  
 creating  
     packages, 1-3  
 CTX\_ADM package documentation, 2-2  
 CTX\_CLS package documentation, 3-2  
 CTX\_DDL package documentation, 4-2  
 CTX\_DOC package documentation, 5-2  
 CTX\_OUTPUT package documentation, 6-2

CTX\_QUERY package documentation, 7-2  
 CTX\_REPORT package documentation, 8-2  
 CTX\_THES package documentation, 9-2  
 CTX\_ULEXER package documentation, 10-2  
 CURRENT\_INSTANCE function, 104-17  
 cursors  
     DBMS\_SQL package, 90-7

## D

---

data dictionary  
     removing Streams information, 96-92  
 DATA function and procedure, 164-16  
 data types  
     DBMS\_DATA\_MINING, 23-6  
     table of, 24-2  
 DATA\_BLOCK\_ADDRESS\_BLOCK  
     function, 104-18  
 DATA\_BLOCK\_ADDRESS\_FILE function, 104-19  
 database  
     locking  
         OWA\_OPT\_LOCK package, 133-2  
 database tables  
     creating for DBMS\_TRACE, 100-4  
 datatypes  
     DBMS\_DESCRIBE, 31-11  
     PL/SQL  
         numeric codes for, 31-7  
 DB\_VERSION procedure, 104-20  
 DBA\_XML\_SCHEMAS catalog view, 118-21  
 DBA\_XML\_TAB\_COLS catalog view, 118-25  
 DBA\_XML\_TABLES catalog view, 118-22  
 DBA\_XML\_VIEW\_COLS catalog view, 118-31  
 DBA\_XML\_VIEWS catalog view, 118-28  
 DBMS\_ALERT package, 13-1  
 DBMS\_APPLICATION\_INFO package, 14-1  
 DBMS\_APPLY\_ADM package, 15-1  
 DBMS\_CAPTURE package, 171-1  
 DBMS\_CAPTURE\_ADM package  
     capture process  
         DBMS\_CAPTURE\_ADM package, 19-1  
 DBMS\_CDC\_PUBLISH package, 20-1  
     ALTER\_AUTOLOG\_CHANGE\_SOURCE  
         procedure, 20-7  
     ALTER\_CHANGE\_SET procedure, 20-9



- ALTER\_CHANGE\_TABLE procedure, 20-13
- CREATE\_AUTOLOG\_CHANGE\_SOURCE procedure, 20-16
- CREATE\_CHANGE\_SET procedure, 20-19
- CREATE\_CHANGE\_TABLE procedure, 20-22
- DROP\_CHANGE\_SET procedure, 20-27
- DROP\_CHANGE\_SOURCE procedure, 20-28
- DROP\_CHANGE\_TABLE procedure, 20-29
- DROP\_SUBSCRIPTION procedure, 20-31
- PURGE procedure, 20-33
- PURGE\_CHANGE\_SET procedure, 20-34
- PURGE\_CHANGE\_TABLE procedure, 20-35
- DBMS\_CDC\_SUBSCRIBE package, 21-1
  - ACTIVATE\_SUBSCRIPTION procedure, 21-11
  - CREATE\_SUBSCRIPTION procedure, 21-8
  - deprecated subprograms, 21-3
  - DROP\_SUBSCRIBER\_VIEW procedure, 21-4
  - DROP\_SUBSCRIPTION procedure, 21-10
  - EXTEND\_WINDOW procedure, 21-11
  - GET\_SUBSCRIPTION\_HANDLE procedure, 21-3
  - PREPARE\_SUBSCRIBER\_VIEW procedure, 21-4
  - PURGE\_WINDOW procedure, 21-13
  - SUBSCRIBE procedure, 21-15
- DBMS\_DATA\_MINING
  - constants, 23-3
  - data types, 23-6
  - errors, 23-9
  - function settings, 23-11
  - introduction, 23-2
  - package, 23-1
  - subprograms, 23-19
  - user views, 23-10
- DBMS\_DATA\_MINING\_TRANSFORM
  - introduction, 24-2
  - package, 24-1
  - subprograms, 24-8
- DBMS\_DATAPUMP package, 25-1
  - ADD\_FILE procedure, 25-10
  - ATTACH function, 25-14
  - DATA\_FILTER procedure, 25-16
  - DETACH procedure, 25-19
  - GET\_STATUS procedure, 25-20
  - LOG\_ENTRY procedure, 25-23
  - METADATA\_FILTER procedure, 25-25
  - METADATA\_REMAP procedure, 25-28, 25-31
  - METADATA\_TRANSFORM procedure, 25-28, 25-31
  - OPEN function, 25-34
  - roles used by, 25-2
  - SET\_PARALLEL procedure, 25-38
  - SET\_PARAMETER procedure, 25-40
  - START\_JOB procedure, 25-45
  - STOP\_JOB procedure, 25-47
  - types used by, 25-4
- DBMS\_DDL package, 26-1
- DBMS\_DEBUG package, 27-1
- DBMS\_DEFER package documentation, 28-2
- DBMS\_DEFER\_QUERY package documentation, 29-2
- DBMS\_DEFER\_SYS package documentation, 30-2
- DBMS\_DESCRIBE package, 31-1
- DBMS\_DIMENSION package, 32-1
- DBMS\_DISTRIBUTED\_TRUST\_ADMIN package, 33-1
- DBMS\_FGA package, 34-1
- DBMS\_FILE\_TRANSFER package, 35-1
- DBMS\_FLASHBACK package, 36-1
- DBMS\_FREQUENT\_ITEMSET package, 37-1
- DBMS\_HS\_PASSTHROUGH package, 38-1
- DBMS\_IOT package, 39-1
- DBMS\_JAVA package documentation, 40-2
- DBMS\_JOB package, 41-1
- DBMS\_LDAP package documentation, 42-2
- DBMS\_LDAP\_UTL package documentation, 43-2
- DBMS\_LIBCACHE package, 44-1
- DBMS\_LOB package, 45-1
- DBMS\_LOCK package, 46-1
- DBMS\_LOGMNR package, 47-1
  - ADD\_LOGFILE procedure, 47-7
  - COLUMN\_PRESENT function, 47-9
  - END\_LOGMNR procedure, 47-11
  - MINE\_VALUE function, 47-12
  - REMOVE\_LOGFILE procedure, 47-14
  - START\_LOGMNR procedure, 47-16
- DBMS\_LOGMNR\_CDC\_PUBLISH
  - See DBMS\_CDC\_PUBLISH, 20-1
- DBMS\_LOGMNR\_CDC\_SUBSCRIBE
  - See DBMS\_CDC\_SUBSCRIBE, 21-1

- DBMS\_LOGMNR\_D package, 48-1
  - BUILD procedure, 48-4
  - SET\_TABLESPACE procedure, 48-8
- DBMS\_LOGSTDBY package, 49-1
  - APPLY\_SET procedure, 49-4
  - APPLY\_UNSET procedure, 49-8
  - BUILD procedure, 49-12
  - GUARD BYPASS OFF procedure, 49-13
  - INSTANTIATE\_TABLE procedure, 49-13
  - SKIP procedure, 49-15
  - SKIP\_ERROR procedure, 49-22
  - SKIP\_TRANSACTION procedure, 49-25
  - UNSKIP procedure, 49-27
  - UNSKIP\_ERROR procedure, 49-30
  - UNSKIP\_TRANSACTION procedure, 49-31
- DBMS\_METADATA package, 50-1
  - ADD\_TRANSFORM function, 50-9
  - CLOSE procedure, 50-13
  - CONVERT function, 50-14
  - GET\_DDL function, 50-20
  - GET\_QUERY procedure, 50-25
  - GET\_XML function, 50-20
  - OPEN procedure, 50-26
  - OPENW procedure, 50-35
  - PUT function, 50-37
    - security, 50-3
  - SET\_COUNT procedure, 50-39
  - SET\_FILTER procedure, 50-41
  - SET\_PARSE\_ITEM procedure, 50-55
  - SET\_REMAP\_PARAM procedure, 50-59
  - SET\_TRANSFORM\_PARAM procedure, 50-59
    - types used by, 50-4
- DBMS\_MGWADM package
  - constants, 51-12
  - summary of subprograms, 51-29
- DBMS\_MGWMSG package
  - constants, 52-2
  - summary of subprograms, 52-24
- DBMS\_MONITOR package
  - statistics tracing and gathering
    - DBMS\_MONITOR package, 53-1
- DBMS\_MVIEW package
  - BEGIN\_TABLE\_REORGANIZATION procedure, 54-5
  - END\_TABLE\_REORGANIZATION procedure, 54-6
  - EXPLAIN\_MVIEW procedure, 54-8
  - EXPLAIN\_REWRITE procedure, 54-10
  - I\_AM\_A\_REFRESH function, 54-12
  - PMARKER function, 54-13
  - PURGE\_DIRECT\_LOAD\_LOG procedure, 54-14
  - PURGE\_LOG procedure, 54-15
  - PURGE\_MVIEW\_FROM\_LOG procedure, 54-16
  - REFRESH procedure, 54-18
  - REFRESH\_ALL\_MVIEWS procedure, 54-21
  - REFRESH\_DEPENDENT procedure, 54-23
  - REGISTER\_MVIEW procedure, 54-26
  - UNREGISTER\_MVIEW procedure, 54-29
- DBMS\_OBFUSCATION\_TOOLKIT package, 55-1
- DBMS\_ODCI package, 56-1
  - ESTIMATE\_CPU\_UNITS function, 56-3
  - methods, 56-2
- DBMS\_OFFLINE\_OG package
  - documentation, 57-2
- DBMS\_OLAP package, 58-1
- DBMS\_OUTLN package, 59-1
- DBMS\_OUTLN\_EDIT package, 60-1
- DBMS\_OUTPUT package, 61-1
- DBMS\_PCLXUTIL package, 62-1
- DBMS\_PIPE package, 63-1
- DBMS\_PROFILER package, 64-1
- DBMS\_PROPAGATION\_ADM package, 65-1
- DBMS\_RANDOM package, 66-1
- DBMS\_RECTIFIER\_DIFF package
  - documentation, 67-2
- DBMS\_REDEFINITION package, 68-1
- DBMS\_REFRESH package documentation, 69-2
- DBMS\_REPAIR package, 70-1
- DBMS\_REPCAT package documentation, 71-2
- DBMS\_REPCAT\_ADMIN package
  - documentation, 72-2
- DBMS\_REPCAT\_INSTANTIATE package
  - documentation, 73-2
- DBMS\_REPCAT\_RGT package
  - documentation, 74-2
- DBMS\_REPUTIL package documentation, 75-2
- DBMS\_RESOURCE\_MANAGER package, 76-1
- DBMS\_RESOURCE\_MANAGER\_PRIVS

- package, 77-1
- DBMS\_RESUMABLE package, 78-1
- DBMS\_RLS package, 79-1
- DBMS\_RLS.ADD\_GROUPED\_POLICY parameters
  - enable, 79-15
  - function\_schema, 79-14
  - long\_predicate, 79-15
  - object\_name, 79-14
  - object\_schema, 79-14
  - policy\_function, 79-14
  - policy\_group
    - , 79-14
  - policy\_name, 79-14
  - policy\_type, 79-15
  - sec\_relevant\_cols, 79-15
  - statement\_types, 79-14
  - static\_policy, 79-15
  - update\_check, 79-15
- DBMS\_RLS.ADD\_POLICY parameters
  - enable, 79-6
  - function\_schema, 79-5
  - long\_predicate, 79-6
  - object\_name, 79-5
  - object\_schema, 79-5
  - policy\_function, 79-6
  - policy\_name, 79-5
  - policy\_type, 79-6
  - sec\_relevant\_cols, 79-6
  - sec\_relevant\_cols\_opt, 79-6
  - statement\_types, 79-6
  - static\_policy, 79-6
  - update\_check, 79-6
- DBMS\_RLS.ADD\_POLICY policy types
  - CONTEXT\_SENSITIVE, 79-7
  - DYNAMIC, 79-7
  - SHARED\_CONTEXT\_SENSITIVE, 79-7
  - SHARED\_STATIC, 79-7
  - STATIC, 79-7
- DBMS\_RLS.ADD\_POLICY\_CONTEXT parameters
  - attribute, 79-17
  - namespace, 79-17
  - object\_name, 79-17
  - object\_schema, 79-17
- DBMS\_RLS.CREATE\_POLICY\_GROUP parameters
  - object\_name, 79-13
  - object\_schema, 79-13
  - policy\_group, 79-13
- DBMS\_RLS.DELETE\_POLICY\_GROUP parameters
  - object\_name, 79-19
  - object\_schema, 79-19
  - policy\_group, 79-19
- DBMS\_RLS.DISABLE\_GROUPED\_POLICY
  - parameters
    - group\_name, 79-23
    - object\_name, 79-23
    - object\_schema, 79-23
    - policy\_name, 79-23
- DBMS\_RLS.DROP\_GROUPED\_POLICY parameters
  - object\_name, 79-20
  - object\_schema, 79-20
  - policy\_group, 79-20
  - policy\_name, 79-20
- DBMS\_RLS.DROP\_POLICY parameters
  - object\_name, 79-10
  - object\_schema, 79-10
  - policy\_name, 79-10
- DBMS\_RLS.DROP\_POLICY\_CONTEXT parameters
  - attribute, 79-21
  - namespace, 79-21
  - object\_name, 79-21
  - object\_schema, 79-21
- DBMS\_RLS.ENABLE\_GROUPED\_POLICY
  - parameters
    - enable, 79-22
    - group\_name, 79-22
    - object\_name, 79-22
    - object\_schema, 79-22
    - policy\_name, 79-22
- DBMS\_RLS.ENABLE\_POLICY parameters
  - enable, 79-12
  - object\_name, 79-12
  - object\_schema, 79-12
  - policy\_name, 79-12
- DBMS\_RLS.REFRESH\_GROUPED\_POLICY
  - parameters
    - group\_name, 79-24
    - object\_name, 79-24
    - object\_schema, 79-24
    - policy\_name, 79-24
- DBMS\_RLS.REFRESH\_POLICY parameters

- object\_name, 79-11
- object\_schema, 79-11
- policy\_name, 79-11
- DBMS\_ROWID package, 80-1
- DBMS\_RULE package, 81-1
- DBMS\_RULE\_ADM package, 82-1
- DBMS\_SCHEDULER package, 83-1
- DBMS\_SERVER\_ALERT package, 84-1
- DBMS\_SERVICE package, 85-1
- DBMS\_SESSION package, 86-1
- DBMS\_SHARED\_POOL package, 87-1
- DBMS\_SPACE package, 88-1
- DBMS\_SPACE\_ADMIN package, 89-1
- DBMS\_SQL package, 90-1
- DBMS\_SQLTUNE package, 91-1
- DBMS\_STAT\_FUNCS package, 92-1
- DBMS\_STATS package, 93-1
- DBMS\_STORAGE\_MAP package, 94-1
- DBMS\_STREAMS package, 95-1
- DBMS\_STREAMS\_ADM package, 96-1, 96-2
- DBMS\_STREAMS\_AUTH package, 97-1
- DBMS\_STREAMS\_MESSAGING package, 98-1
- DBMS\_STREAMS\_TABLESPACE package, 99-1
- DBMS\_TRACE package, 100-1
- DBMS\_TRANSACTION package, 101-1
- DBMS\_TRANSFORM package, 102-1
- DBMS\_TTS package, 110-1
- DBMS\_TYPES package, 103-1
- DBMS\_UTILITY package, 104-1
- DBMS\_WARNING package, 105-1
- DBMS\_WM package documentation, 107-2
- DBMS\_WORKLOAD\_REPOSITORY package, 106-1
- DBMS\_XDB package, 108-1
  - ACLCHECKPRIVILEGES function, 108-6
  - CFG\_GET function, 108-7
  - CFG\_REFRESH procedure, 108-8
  - CFG\_UPDATE procedure, 108-9
  - CHECKPRIVILEGES function, 108-11
  - CONFIGUREAUTOSYNC procedure, 111-6
  - constants, 108-2
  - ConText synchronization settings, 111-4
  - CREATEDATASTOREPREF procedure, 111-7
  - CREATEFILTERPREF procedure, 111-8
  - CREATEFOLDER function, 108-12
  - CREATEINDEX procedure, 111-9
  - CREATELEXERPREF procedure, 111-10
  - CREATEOIDPATH function, 108-13
  - CREATEPREFERENCES procedure, 111-11
  - CREATERESOURCE function, 108-14
  - CREATESECTIONGROUPPREF procedure, 111-12
  - CREATESTOPLISTPREF procedure, 111-13
  - CREATESTORAGEPREF procedure, 111-14
  - CREATEWORLDLISTPREF procedure, 111-15
  - DELETERESOURCE procedure, 108-17
  - DROPPREFERENCES procedure, 111-16
  - EXISTSRESOURCE function, 108-18
  - filtering settings, 111-3
  - general indexing settings, 111-3
  - GETACLDOCUMENT function, 108-19
  - GETLOCKTOKEN procedure, 108-20
  - GETRESOID function, 108-22
  - GETXDB\_TABLESPACE function, 108-23
  - LINK procedure, 108-24
  - LOCKRESOURCE function, 108-25
  - methods, 108-4, 111-5
  - miscellaneous settings, 111-4
  - MOVEXDB\_TABLESPACE procedure, 108-26
  - other index preference settings, 111-4
  - REBUILDHIERARCHICALINDEX procedure, 108-27
  - RENAMERESOURCE procedure, 108-28
  - sectioning and section group settings, 111-3
  - SETACL procedure, 108-29
  - stoptlist settings, 111-3
  - SYNC settings, 111-4
  - UNLOCKRESOURCE function, 108-30
- DBMS\_XDB\_VERSION package, 109-1
  - CHECKIN function, 109-3
  - CHECKOUT procedure, 109-4
  - GETCONTENTSBOBBYRESID function, 109-5
  - GETCONTENTSCLOBBYRESID function, 109-6
  - GETCONTENTSXMLBYRESID function, 109-7
  - GETPREDECESSORS function, 109-8
  - GETPREDSBYRESID function, 109-9
  - GETRESOURCEBYRESID function, 109-10
  - GETSUCCESSORS function, 109-11
  - GETSUCCSBYRESID function, 109-12
  - MAKEVERSIONED function, 109-13

UNCHECKOUT function, 109-14  
 DBMS\_XDBT package, 111-1  
 DBMS\_XDBZ package, 112-1  
   DISABLE\_HIERARCHY procedure, 112-3  
   ENABLE\_HIERARCHY procedure, 112-4  
   GET\_ACLOID function, 112-5  
   GET\_USERID function, 112-6  
   IS\_HIERARCHY\_ENABLED function, 112-7  
   PURGELDAPCACHE function, 112-8  
 DBMS\_XMLDOM package, 113-1  
   ADOPTNODE function, 113-41  
   APPENDDATA procedure, 113-43  
   CREATEATTRIBUTE function, 113-45  
   CREATECDATASECTION function, 113-46  
   CREATECOMMENT function, 113-47  
   CREATEDOCUMENT function, 113-48  
   CREATEDOCUMENTFRAGMENT, 113-49  
   CREATEELEMENT function, 113-50  
   CREATEENTITYREFERENCE function, 113-51  
   CREATEPROCESSINGINSTRUCTION  
     function, 113-52  
   CREATETEXTNODE function, 113-53  
   DELETEDATA procedure, 113-54  
   description, 113-2  
   exceptions, 113-5  
   FINDENTITY function, 113-55  
   FINDNOTATION function, 113-56  
   FREEDOCFRAG procedure, 113-57, 113-58  
   FREEDOCUMENT procedure, 113-59  
   GETATTRIBUTE function, 113-61  
   GETATTRIBUTENODE function, 113-63  
   GETBUBLICID function, 113-93  
   GETCHARSET function, 113-67  
   GETCHILDRENBYTAGNAME function, 113-65  
   GETDATA function, 113-66  
   GETDOCTYPE function, 113-67  
   GETDOCUMENTELEMENT function, 113-68  
   GETELEMENTSBYTAGNAME  
     function, 113-69, 113-70  
   GETENTITIES function, 113-70  
   GETEXPANDEDNAME function, 113-72  
   GETIMPLEMENTATION function, 113-73  
   GETLENGTH function, 113-75, 113-76  
   GETNAME function, 113-77, 113-78  
   GETNAMEDITEM function, 113-78  
   GETNAMESPACE function, 113-80  
   GETNAMESPACE procedure, 113-79  
   GETNEXTSIBLING function, 113-80  
   GETNODENAME function, 113-81  
   GETNODETYPE function, 113-82  
   GETNODEVALUE function, 113-83  
   GETNOTATIONNAME function, 113-84  
   GETNOTATIONS function, 113-85  
   GETOWNERDOCUMENT function, 113-87  
   GETOWNERELEMENT function, 113-88  
   GETPARENTNODE function, 113-89  
   GETPREFIX function, 113-90  
   GETPREVIOUSIBLING function, 113-91  
   GETPUBLICID function, 113-92, 113-93  
   GETQUALIFIEDNAME function, 113-93,  
     113-94  
   GETSCHEMANODE function, 113-94  
   GETSPECIFIED function, 113-95  
   GETSTANDALONE function, 113-96  
   GETSYSTEMID function, 113-97, 113-98  
   GETTAGNAME function, 113-98  
   GETTARGET function, 113-86  
   GETVALUE function, 113-99  
   GETVERSION function, 113-100  
   GETXMLTYPE function, 113-101  
   HASATTRIBUTE function, 113-102  
   HASATTRIBUTES function, 113-103  
   HASCHILDNODES function, 113-104  
   HASFEATURE function, 113-105  
   IMPORTNODE function, 113-106  
   inheritance, 113-3  
   INSERTBEFORE function, 113-107  
   INSERTDATA procedure, 113-108  
   ISNULL function, 113-109, 113-113  
   ITEM function, 113-113  
   MAKEATTR function, 113-114  
   MAKECDATASECTION function, 113-115  
   MAKECHARACTERDATA function, 113-116  
   MAKECOMMENT function, 113-117  
   MAKEDOCUMENT function, 113-118  
   MAKEDOCUMENTFRAGMENT  
     function, 113-119  
   MAKEDOCUMENTTYPE function, 113-120  
   MAKEELEMENT function, 113-121  
   MAKEENTITY function, 113-122

MAKEENTITYREFERENCE function, 113-123  
 MAKENODE function, 113-124, 113-127  
 MAKENOTATION function, 113-127  
 MAKEPROCESSINGINSTRUCTION  
     function, 113-128  
 MAKETEXT function, 113-129  
 methods  
     ADOPTNODE function, 113-41  
     APPENDCHILD function, 113-42  
     APPENDDATA procedure, 113-43  
     CLONENODE function, 113-44  
     CREATEATTRIBUTE function, 113-45  
     CREATEDATASECTION function, 113-46  
     CREATECOMMENT function, 113-47  
     CREATEDOCUMENT function, 113-48  
     CREATEDOCUMENTFRAGMENT  
         function, 113-49  
     CREATEELEMENT function, 113-50  
     CREATEENTITYREFERENCE  
         function, 113-51  
     CREATEPROCESSINGINSTRUCTION  
         function, 113-52  
     CREATETEXTNODE function, 113-53  
     DELETEDATA procedure, 113-54  
     DOMAttr interface, 113-11  
     DOMCDataSection interface, 113-12  
     DOMCharacterData interface, 113-13  
     DOMComment interface, 113-14  
     DOMDocument interface, 113-15  
     DOMDocumentFragment interface, 113-17,  
         113-41  
     DOMDocumentType interface, 113-18,  
         113-41  
     DOMElement interface, 113-19, 113-41  
     DOMEntity interface, 113-20, 113-41  
     DOMEntityReference interface, 113-21,  
         113-41  
     DOMImplementation interface, 113-22,  
         113-41  
     DOMNamedNodeMap interface, 113-23,  
         113-41  
     DOMNode  
         APPENDCHILD  
             function, 113-42

CLONENODE function, 113-44  
 FREENODE procedure, 113-60  
 GETATTRIBUTES  
     function, 113-62  
 GETCHILDNODES  
     function, 113-64  
 GETEXPANDEDNAME  
     procedure, 113-71  
 GETFIRSTCHILD  
     function, 113-72  
 GETLASTCHILD  
     function, 113-74  
 GETLOCALNAME  
     procedure, 113-76  
 DOMNodeList interface, 113-24, 113-41  
 DOMNotation interface, 113-25, 113-41  
 DOMProcessingInstruction interface, 113-26,  
     113-41  
 DOMText interface, 113-8, 113-27, 113-41  
 FINDENTITY function, 113-55  
 FINDNOTATION function, 113-56  
 FREEDOCFRAG procedure, 113-57, 113-58  
 FREEDOCUMENT procedure, 113-59  
 FREENODE procedure, 113-60  
 GETATTRIBUTE function, 113-61  
 GETATTRIBUTENODE function, 113-63  
 GETATTRIBUTES function, 113-62  
 GETBUBLICID function, 113-93  
 GETCHARSET function, 113-67  
 GETCHILDNODES function, 113-64  
 GETCHILDRENBYTAGNAME  
     function, 113-65  
 GETDATA function, 113-66  
 GETDOCTYPE function, 113-67  
 GETDOCUMENTELEMENT  
     function, 113-68  
 GETELEMENTSBYTAGNAME  
     function, 113-69, 113-70  
 GETENTITIES function, 113-70  
 GETEXPANDEDNAME function, 113-72  
 GETEXPANDEDNAME procedure, 113-71

GETFIRSTCHILD function, 113-72  
 GETIMPLEMENTATION function, 113-73  
 GETLASTCHILD function, 113-74  
 GETLENGTH function, 113-75, 113-76  
 GETLOCALNAME procedure, 113-76  
 GETNAME function, 113-77, 113-78  
 GETNAMEDITEM function, 113-78  
 GETNAMESPACE function, 113-80  
 GETNAMESPACE procedure, 113-79  
 GETNEXTSIBLING function, 113-80  
 GETNODENAME function, 113-81  
 GETNODETYPE function, 113-82  
 GETNODEVALUE function, 113-83  
 GETNOTATIONNAME function, 113-84  
 GETNOTATIONS function, 113-85  
 GETOWNERDOCUMENT function, 113-87  
 GETOWNERELEMENT function, 113-88  
 GETPARENTNODE function, 113-89  
 GETPREFIX function, 113-90  
 GETPREVIOUSIBLING function, 113-91  
 GETPUBLICID function, 113-92, 113-93  
 GETQUALIFIEDNAME function, 113-93, 113-94  
 GETSCHEMANODE function, 113-94  
 GETSPECIFIED function, 113-95  
 GETSTANDALONE function, 113-96  
 GETSYSTEMID function, 113-97, 113-98  
 GETTAGNAME function, 113-98  
 GETTARGET function, 113-86  
 GETVALUE function, 113-99  
 GETVERSION function, 113-100  
 GETXMLTYPE function, 113-101  
 HASATTRIBUTE function, 113-102  
 HASATTRIBUTES function, 113-103  
 HASCHILDNODES function, 113-104  
 HASFEATURE function, 113-105  
 IMPORTNODE function, 113-106  
 INSERTBEFORE function, 113-107  
 INSERTDATA procedure, 113-108  
 ISNULL function, 113-109, 113-113  
 ITEM function, 113-113  
 MAKEATTR function, 113-114  
 MAKECDATASECTION function, 113-115  
 MAKECHARACTERDATA function, 113-116  
 MAKECOMMENT function, 113-117  
 MAKEDOCUMENT function, 113-118  
 MAKEDOCUMENTFRAGMENT function, 113-119  
 MAKEDOCUMENTTYPE function, 113-120  
 MAKEELEMENT function, 113-121  
 MAKEENTITY function, 113-122  
 MAKEENTITYREFERENCE function, 113-123  
 MAKENODE function, 113-124, 113-127  
 MAKENOTATION function, 113-127  
 MAKEPROCESSINGINSTRUCTION function, 113-128  
 MAKETEXT function, 113-129  
 NEWDOMDOCUMENT function, 113-130  
 NORMALIZE procedure, 113-131  
 REMOVEATTRIBUTE procedure, 113-132  
 REMOVEATTRIBUTENODE function, 113-133  
 REMOVENAMEDITEM function, 113-135  
 REPLACECHILD function, 113-136  
 REPLACEDATA procedure, 113-137  
 RESOLVENAMESPACEPREFIX function, 113-138  
 SETATTRIBUTE procedure, 113-139  
 SETATTRIBUTENODE function, 113-140  
 SETCHARSET procedure, 113-145  
 SETDATA procedure, 113-141  
 SETNAMEDITEM function, 113-142  
 SETNODEVALUE procedure, 113-143  
 SETPREFIX procedure, 113-144  
 SETSTANDALONE procedure, 113-145  
 SETVALUE procedure, 113-146  
 SETVERSION procedure, 113-147  
 SPLITTEXT function, 113-148  
 SUBSTRINGDATA function, 113-149  
 WRITETOBUFFER procedure, 113-150  
 WRITETOCLOB procedure, 113-151  
 WRITETOFILE procedure, 113-152  
 NEWDOMDOCUMENT function, 113-130  
 NORMALIZE procedure, 113-131  
 REMOVEATTRIBUTE procedure, 113-132  
 REMOVEATTRIBUTENODE function, 113-133  
 REMOVENAMEDITEM function, 113-135  
 REPLACECHILD function, 113-136

REPLACEDATA procedure, 113-137  
 RESOLVENAMESPACEPREFIX  
     function, 113-138  
 SETATTRIBUTE procedure, 113-139  
 SETATTRIBUTENODE function, 113-140  
 SETCHARSET procedure, 113-145  
 SETDATA procedure, 113-141  
 SETNAMEDITM function, 113-142  
 SETNODEVALUE procedure, 113-143  
 SETPREFIX procedure, 113-144  
 SETSTANDALONE procedure, 113-145  
 SETVALUE procedure, 113-146  
 SETVERSION procedure, 113-147  
 SPLITTEXT function, 113-148  
 SUBSTRINGDATA function, 113-149  
     types, 113-4  
 WRITETOBUFFER procedure, 113-150  
 WRITETOCLOB procedure, 113-151  
 WRITETOFILE procedure, 113-152  
 DBMS\_XMLGEN package, 114-1  
     CLOSECONTEXT procedure, 114-4  
     CONVERT function, 114-5  
     GETNUMROWSPROCESSED function, 114-6  
     GETXML function, 114-7  
     GETXMLTYPE function, 114-9  
     NEWCONTEXT function, 114-10  
     RESTARTQUERY procedure, 114-11  
     SETCONVERTSPECIALCHARS  
         procedure, 114-12  
     SETMAXROWS procedure, 114-13  
     SETROWSETTAG procedure, 114-15  
     SETROWTAG procedure, 114-16  
     SETSKIPROWS procedure, 114-17  
     USEITEMTAGSFORCOLL procedure, 114-18  
     USENULLATTRIBUTEINDICATOR  
         procedure, 114-19  
 DBMS\_XMLPARSER package, 115-1  
     FREEPARSER procedure, 115-2  
     GETDOCTYPE function, 115-3  
     GETDOCUMENT function, 115-3  
     GETRELEASEVERSION function, 115-4  
     GETVALIDATIONMODE function, 115-4  
     NEWPARSER function, 115-4  
     PARSE function, 115-4  
     PARSE procedure, 115-4  
     PARSEBUFFER procedure, 115-5  
     PARSECLOB procedure, 115-6  
     PARSEDTD procedure, 115-6  
     PARSEDTDBUFFER procedure, 115-7  
     PARSEDTDCLOB procedure, 115-7  
     SETBASEDIR procedure, 115-8  
     SETDOCTYPE procedure, 115-8  
     SETERRORLOG procedure, 115-8  
     SETPRESERVEWHITESPACE procedure, 115-9  
     SETVALIDATIONMODE procedure, 115-9  
     SHOWWARNINGS procedure, 115-10  
 DBMS\_XMLQUERY package, 116-1  
     CLOSECONTEXT procedure, 116-4  
         constants, 116-2  
     GETDTD function, 116-5  
     GETDTD procedure, 116-5  
     GETEXCEPTIONCONTENT procedure, 116-5  
     GETNUMROWSPROCESSED procedure, 116-6  
     GETVERSION procedure, 116-6  
     GETXML function, 116-7  
     GETXML procedure, 116-7  
     NEWCONTEXT function, 116-8  
     PROPAGATEORIGINALEXCEPTION  
         procedure, 116-8  
     REMOVEXSLTPARAM procedure, 116-9  
     SETBINDVALUE procedure, 116-9  
     SETCOLLIDATTRNAME procedure, 116-10  
     SETDATAHEADER procedure, 116-10  
     SETDATEFORMAT procedure, 116-11  
     SETENCODINGTAG procedure, 116-11  
     SETERRORTAG procedure, 116-12  
     SETMAXROWS procedure, 116-12  
     SETMETAHEADER procedure, 116-13  
     SETRAISEEXCEPTION procedure, 116-13  
     SETRAISENOROWSEXCEPTION  
         procedure, 116-14  
     SETROWIDATTRNAME procedure, 116-14  
     SETROWIDATTRVALUE procedure, 116-15  
     SETROWSETTAG procedure, 116-15  
     SETROWTAG procedure, 116-15  
     SETSKIPROWS procedure, 116-16  
     SETSQLTOXMLNAMEESCAPING  
         procedure, 116-16  
     SETSTYLESHEETHEADER procedure, 116-17  
     SETTAGCASE procedure, 116-17



SETXSLT procedure, 116-18  
 SETXSLTPARAM procedure, 116-19  
 types, 116-2  
 USENULLATTRIBUTEINDICATOR  
   procedure, 116-19  
 USETYPEFORCOLLELEMTAG  
   procedure, 116-20  
 DBMS\_XMLSAVE package, 117-1  
   CLEARKEYCOLUMNLIST procedure, 117-4  
   CLEARUPDATECOLUMNLIST  
     procedure, 117-4  
   CLOSECONTEXT procedure, 117-5  
   constants, 117-2  
   DELETXML function, 117-5  
   GETEXCEPTIONCONTENT procedure, 117-6  
   INSERTXML function, 117-6  
   NEWCONTEXT function, 117-7  
   PROPAGATEORIGINALEXCEPTION  
     procedure, 117-7  
   REMOVEXSLTPARAM procedure, 117-8  
   SETBATCHSIZE procedure, 117-8  
   SETCOMMITBATCH procedure, 117-9  
   SETDATEFORMAT procedure, 117-9  
   SETIGNORECASE procedure, 117-10  
   SETKEYCOLUMN procedure, 117-10  
   SETPRESERVEWHITESPACE  
     procedure, 117-11  
   SETROWTAG procedure, 117-11  
   SETSQLTOXMLNAMEESCAPING  
     procedure, 117-11  
   SETUPDATECOLUMN procedure, 117-12  
   SETXSLT procedure, 117-12  
   SETXSLTPARAM procedure, 117-13  
   UPDATEXML function, 117-14  
 DBMS\_XMLSCHEMA package, 118-1  
   ALL\_XML\_SCHEMAS catalog view, 118-20  
   ALL\_XML\_TAB\_COLS catalog view, 118-27  
   ALL\_XML\_TABLES catalog view, 118-24  
   ALL\_XML\_VIEW\_COLS catalog view, 118-33  
   ALL\_XML\_VIEWS catalog view, 118-30  
   catalog views, 118-18  
   COMPILESCHEMA procedure, 118-4  
   constants, 118-2  
   COPYEVOLVE procedure, 118-5  
   DBA\_XML\_SCHEMAS catalog view, 118-21  
   DBA\_XML\_TAB\_COLS catalog view, 118-25  
   DBA\_XML\_TABLES catalog view, 118-22  
   DBA\_XML\_VIEW\_COLS catalog view, 118-31  
   DBA\_XML\_VIEWS catalog view, 118-28  
   DELETESCHEMA procedure, 118-8  
   GENERATEBEAN procedure, 118-10  
   GENERATESCHEMA function, 118-11  
   GENERATESCHEMAS function, 118-12  
   REGISTERSCHEMA procedure, 118-13  
   REGISTERURI procedure, 118-16  
   USER\_XML\_SCHEMAS catalog view, 118-19  
   USER\_XML\_TAB\_COLS catalog view, 118-26  
   USER\_XML\_TABLES catalog view, 118-23  
   USER\_XML\_VIEW\_COLS catalog view, 118-32  
   USER\_XML\_VIEWS catalog view, 118-29  
 DBMS\_XMLSTORE package, 119-1  
   CLEARKEYCOLUMNLIST procedure, 119-4  
   CLEARUPDATECOLUMNLIST  
     procedure, 119-5  
   CLOSECONTEXT procedure, 119-6  
   DELETXML function, 119-7  
   INSERTXML function, 119-8  
   NEWCONTEXT function, 119-9  
   SETKEYCOLUMN procedure, 119-10  
   SETROWTAG procedure, 119-11  
   SETUPDATECOLUMN procedure, 119-12  
   types, 119-2  
   UPDATEXML function, 119-13  
 DBMS\_XPLAN package, 120-1  
 DBMS\_XSLPROCESSOR package, 121-1  
   CLOB2FILE procedure, 121-2  
   FREEPROCESSOR procedure, 121-3  
   FREESTYLESHEET procedure, 121-3  
   NEWPROCESSOR function, 121-4  
   NEWSTYLESHEET function, 121-4  
   PROCESSXSL function, 121-5  
   READ2CLOB function, 121-7  
   REMOVEPARAM procedure, 121-7  
   RESETPARAMS procedure, 121-8  
   SELECTNODES function, 121-8  
   SELECTSINGLENODE function, 121-8  
   SETERRORLOG procedure, 121-9  
   SETPARAM procedure, 121-9  
   SHOWWARNINGS procedure, 121-10  
   TRANSFORMNODE function, 121-10

- VALUEOF procedure, 121-11
- DBUriType, 172-18
- DBURITYPE function, 172-20
- DBUriType subtype, 172-18
  - CREATEURI function, 172-19
  - DBURITYPE function, 172-20
  - GETBLOB function, 172-21
  - GETCLOB function, 172-22
  - GETCONTENTTYPE function, 172-23
  - GETEXTERNALURL function, 172-24
  - GETURL function, 172-25
  - GETXML function, 172-26
  - methods, 172-18
- DEBUG\_EXPTOC package, 122-1
- DEBUG\_OFF procedure, 27-21
- DEBUG\_ON procedure, 27-22
- DEFINE\_ARRAY procedure, 90-40
- DEFINE\_COLUMN procedure, 90-43
- DEFINE\_COLUMN\_LONG procedure, 90-45
- DELETE\_ALL\_ERRORS procedure, 15-22
- DELETE\_BREAKPOINT function, 27-23
- DELETE\_COLUMN member procedure, 174-20
- DELETE\_COLUMN\_STATS procedure, 93-23
- DELETE\_CONSUMER\_GROUP procedure, 76-20
- DELETE\_DATABASE\_STATS procedure, 93-25
- DELETE\_DICTIONARY\_STATS procedure, 93-26
- DELETE\_ERROR procedure, 15-23
- DELETE\_FIXED\_OBJECTS\_STATS procedure, 93-28
- DELETE\_INDEX\_STATS procedure, 93-29
- DELETE\_OBJECT procedure, 163-6
- DELETE\_OER\_BREAKPOINT function, 27-24
- DELETE\_PLAN procedure, 76-21
- DELETE\_PLAN\_CASCADE procedure, 76-23
- DELETE\_PLAN\_DIRECTIVE procedure, 76-22
- DELETE\_SERVICE procedure, 85-5
- DELETE\_SQLSET procedure, 91-15
- DELETE\_SYSTEM\_STATS procedure, 93-32
- DELETE\_TABLE\_STATS procedure, 93-33
- DELETEDATA procedure, 113-54
- DELETERESOURCE procedure, 108-17
- DELETESHEMA procedure, 118-8
- DELETEXML function, 117-5, 119-7
- DEQUEUE procedure, 98-3
- DESCRIBE\_COLUMNS procedure, 90-46
- DESCRIBE\_COLUMNS2 procedure, 90-47
- DESCRIBE\_DIMENSION procedure, 32-4
- DESCRIBE\_PROCEDURE procedure, 31-9
- DESDecrypt procedure, 55-7, 55-14
- DESEncrypt procedure, 55-16
- DETACH\_SESSION procedure, 27-25
- DETACH\_SIMPLE\_TABLESPACE procedure, 99-17
- DETACH\_TABLESPACES procedure, 99-19
- DFN function
  - of HTF package, 123-40
- DFN procedure
  - of HTP package, 128-40
- DIRECTORY\_OBJECT\_SET type, 99-3
- DIRLISTCLOSE function
  - of HTF package, 123-41
- DIRLISTCLOSE procedure
  - of HTP package, 128-41
- DIRLISTOPEN function
  - of HTF package, 123-42
- DIRLISTOPEN procedure
  - of HTP package, 128-42
- DISABLE procedure
  - of DBMS\_FLASHBACK package, 36-9
  - of DBMS\_OUTPUT package, 61-8
  - of OWA\_CACHE package, 129-4
- DISABLE\_BREAKPOINT function, 27-26
- DISABLE\_HIERARCHY procedure, 112-3
- DISCONNECT\_SESSION procedure, 85-6
- DISPLAY function, 120-11
- DISPLAY\_AWR function, 120-9
- DISPLAY\_CURSOR function, 120-13
- DIV function
  - of HTF package, 123-43
- DIV procedure
  - of HTP package, 128-43
- DLISTCLOSE function
  - of HTF package, 123-44
- DLISTCLOSE procedure
  - of HTP package, 128-44
- DLISTDEF function
  - of HTF package, 123-46
- DLISTDEF procedure
  - of HTP package, 128-46
- DLISTOPEN function

- of HTF package, 123-45
- DLISTOPEN procedure
  - of HTP package, 128-45
- DLISTTERM function
  - of HTF package, 123-47
- DLISTTERM procedure
  - of HTP package, 128-47
- DOMAttr methods, 113-11
- DOMCDataSection methods, 113-12
- DOMCharacterData methods, 113-13
- DOMComment methods, 113-14
- DOMDocument methods, 113-15
- DOMDocumentFragment methods, 113-17
- DOMDocumentType methods, 113-18, 113-41
- DOMElement methods, 113-19
- DOMEntity methods, 113-20, 113-41
- DOMEntityReference methods, 113-21, 113-41
- DOMImplementation methods, 113-22, 113-41
- DOMNamedNodeMap methods, 113-23, 113-41
- DOMNodeList methods, 113-24, 113-41
- DOMNotation methods, 113-25, 113-41
- DOMProcessingInstruction methods, 113-26
- DOMText methods, 113-8, 113-27, 113-41
- DOWNGRADE procedure, 110-4
- DOWNLOAD\_FILE procedures, 167-4
- DROP\_ALL function, 94-5
- DROP\_APPLY procedure, 15-24
- DROP\_BASELINE procedure, 106-7
- DROP\_BY\_CAT procedure, 59-6
- DROP\_CAPTURE procedure
  - capture process
  - dropping, 19-23
- DROP\_EDIT\_TABLES procedure, 60-5
- DROP\_EVALUATION\_CONTEXT procedure, 82-15
- DROP\_FILE function, 94-7
- DROP\_MODEL procedure, 23-40
- DROP\_PROPAGATION procedure, 65-11
- DROP\_RULE procedure, 82-16
- DROP\_RULE\_SET procedure, 82-17
- DROP\_SNAPSHOT\_RANGE procedure, 106-8
- DROP\_SQL\_PROFILE procedure, 91-16
- DROP\_SQLSET procedure, 91-17
- DROP\_STAT\_TABLE procedure, 93-35
- DROP\_TRANSFORMATION procedure, 102-5

- DROP\_TUNING\_TASK procedure, 91-18
- DROP\_UNUSED procedure, 59-7
- DROPPREFERENCES procedure, 111-16
- DUMP\_ORPHAN\_KEYS procedure, 70-10
- dynamic SQL
  - anonymous blocks and, 90-3
  - DBMS\_SQL functions, using, 90-2
  - execution flow in, 90-7

## E

---

- EHLO function and procedure, 164-18
- EM function
  - of HTF package, 123-48
- EM procedure
  - of HTP package, 128-48
- e-mail from PL/SQL (email), 165-5
- EMPHASIS function
  - of HTF package, 123-49
- EMPHASIS procedure
  - of HTP package, 128-49
- ENABLE procedure, 61-9
- ENABLE\_AT\_SYSTEM\_CHANGE\_NUMBER procedure, 36-10
- ENABLE\_AT\_TIME procedure, 36-11
- ENABLE\_BREAKPOINT function, 27-27
- ENABLE\_HIERARCHY procedure, 112-4
- END\_REQUEST procedure, 156-43
- END\_RESPONSE procedure, 156-44
- ENDCREATE member procedure
  - of ANYDATA TYPE, 168-7
  - of ANYDATASET TYPE, 169-6
  - of ANYTYPE TYPE, 170-8
- ENQUEUE procedure, 98-6
- error queue
  - deleting errors, 15-22, 15-23
  - executing errors, 15-26, 15-27
  - getting error messages, 15-28
- errors
  - DBMS\_DATA\_MINING, 23-9
- ESCAPE function, 166-5
- ESCAPE\_SC function
  - of HTF package, 123-50
- ESCAPE\_SC procedure
  - of HTP package, 128-50

ESCAPE\_URL function  
     of HTF package, 123-51  
 ESCAPEURI function, 172-38  
 ESTIMATE\_CPU\_UNITS function, 56-3  
 ETINSTANCE member function  
     of ANYDATASET TYPE, 169-12  
 EVALUATE procedure, 81-5  
 EXACT\_TEXT\_SIGNATURES procedure, 59-8  
 EXEC\_DDL\_STATEMENT procedure, 104-21  
 EXECUTE function, 90-48  
 EXECUTE member procedure, 174-8, 174-21  
 EXECUTE procedure, 27-28  
 EXECUTE\_ALL\_ERRORS procedure, 15-26  
 EXECUTE\_AND\_FETCH function, 90-49  
 EXECUTE\_ERROR procedure, 15-27  
 EXECUTE\_TUNING\_TASK procedure, 91-19  
 execution flow  
     in dynamic SQL, 90-7  
 EXISTSNODE function, 182-9  
 EXISTSRESOURCE function, 108-18  
 EXPAND\_MESSAGE function, 84-12  
 EXPONENTIAL\_DIST\_FIT procedure, 92-3  
 EXPORT\_COLUMN\_STATS procedure, 93-36  
 EXPORT\_DATABASE\_STATS procedure, 93-37  
 EXPORT\_DICTIONARY\_STATS procedure, 93-38  
 EXPORT\_FIXED\_OBJECTS\_STATS  
     procedure, 93-39  
 EXPORT\_INDEX\_STATS procedure, 93-40  
 EXPORT\_MODEL procedure, 23-41  
 EXPORT\_SCHEMA\_STATS procedure, 93-41  
 EXPORT\_SYSTEM\_STATS procedure, 93-42  
 EXPORT\_TABLE\_STATS procedure, 93-43  
 extend window  
     to create a new view, 21-2  
 EXTRACT function, 182-10

## F

---

FCLOSE procedure, 155-10  
 FCLOSE\_ALL procedure, 155-11  
 FCOPY procedure, 155-12  
 features, new, 1-xxxiii  
 FETCH\_ROWS function, 90-50  
 FFLUSH procedure, 155-13  
 fga\_log\$, 34-5

FGETATTR procedure, 155-14  
 FGETPOS function, 155-15  
 FI\_HORIZONTAL function, 37-8  
 FI\_TRANSACTIONAL function, 37-3  
 FILE type, 99-3  
 FILE\_SET type, 99-4  
 FINDENTITY function, 113-55  
 FINDNOTATION function, 113-56  
 fine-grained access control  
     DBMS\_RLS package, 79-1  
 FINISH\_REDEF\_TABLE procedure, 68-9  
 FIX\_CORRUPT\_BLOCKS procedure, 70-12  
 FLUSH procedure, 165-12  
 FLUSH\_DATA function and procedure, 64-9  
 FLUSH\_DATABASE\_MONITORING\_INFO  
     procedure, 93-44  
 FONTCLOSE function  
     of HTF package, 123-52  
 FONTCLOSE procedure  
     of HTP package, 128-51  
 FONTOPEN function  
     of HTF package, 123-53  
 FONTOPEN procedure  
     of HTP package, 128-52  
 FOPEN function, 155-16  
 FOPEN\_NCHAR function, 155-18  
 FORCE parameter  
     and job-to-instance affinity, 41-3  
 FORMAT\_CELL function  
     of HTF package, 123-54  
 FORMAT\_ERROR\_BACKTRACE function, 104-22  
 FORMAT\_ERROR\_STACK function, 104-26  
 FORMCHECKBOX function  
     of HTF package, 123-55  
 FORMCHECKBOX procedure  
     of HTP package, 128-53  
 FORMCLOSE function  
     of HTF package, 123-56  
 FORMCLOSE procedure  
     of HTP package, 128-54  
 FORMFILE function  
     of HTF package, 123-57  
 FORMFILE procedure  
     of HTP package, 128-56  
 FORMHIDDEN function

- of HTF package, 123-58
- FORMHIDDEN procedure
  - of HTP package, 128-57
- FORMIMAGE function
  - of HTF package, 123-59
- FORMIMAGE procedure
  - of HTP package, 128-58
- FORMOPEN function
  - of HTF package, 123-60
- FORMOPEN procedure
  - of HTP package, 128-55
- FORMPASSWORD function
  - of HTF package, 123-61
- FORMPASSWORD procedure
  - of HTP package, 128-59
- FORMRADIO function
  - of HTF package, 123-62
- FORMRADIO procedure
  - of HTP package, 128-60
- FORMRESET function
  - of HTF package, 123-63
- FORMRESET procedure
  - of HTP package, 128-61
- FORMSELECTCLOSE function
  - of HTF package, 123-64
- FORMSELECTCLOSE procedure
  - of HTP package, 128-62
- FORMSELECTOPEN function
  - of HTF package, 123-65
- FORMSELECTOPEN procedure
  - of HTP package, 128-63
- FORMSELECTOPTION function
  - of HTF package, 123-67
- FORMSELECTOPTION procedure
  - of HTP package, 128-65
- FORMSUBMIT function
  - of HTF package, 123-68
- FORMSUBMIT procedure
  - of HTP package, 128-66
- FORMTEXT function
  - of HTF package, 123-69
- FORMTEXT procedure
  - of HTP package, 128-67
- FORMTEXTAREA function
  - of HTF package, 123-70

- FORMTEXTAREA procedure
  - of HTP package, 128-68
- FORMTEXTAREA2 function
  - of HTF package, 123-71
- FORMTEXTAREA2 procedure
  - of HTP package, 128-69
- FORMTEXTAREACLOSE function
  - of HTF package, 123-72
- FORMTEXTAREACLOSE procedure
  - of HTP package, 128-70
- FORMTEXTAREAOPEN function
  - of HTF package, 123-73
- FORMTEXTAREAOPEN procedure
  - of HTP package, 128-71
- FORMTEXTAREAOPEN2 function
  - of HTF package, 123-74
- FORMTEXTAREAOPEN2 procedure
  - of HTP package, 128-72
- FRAME function
  - of HTF package, 123-75
- FRAME procedure
  - of HTP package, 128-73
- FRAMESETCLOSE function
  - of HTF package, 123-76
- FRAMESETCLOSE procedure
  - of HTP package, 128-74
- FRAMESETOPEN function
  - of HTF package, 123-77
- FRAMESETOPEN procedure
  - of HTP package, 128-75
- FREE\_BLOCKS procedure, 88-7
- FREEDOCFRAG procedure, 113-57, 113-58
- FREEDOCUMENT procedure, 113-59
- FREENODE procedure, 113-60
- FREEPARSER procedure, 115-2
- FREEPROCESSOR procedure, 121-3
- FREESTYLESHEET procedure, 121-3
- REMOVE procedure, 155-19
- RENAME procedure, 155-20
- FSEEK procedure, 155-21

## G

- GATHER\_DATABASE\_STATS procedures, 93-45
- GATHER\_DICTIONARY\_STATS procedure, 93-50

GATHER\_FIXED\_OBJECTS\_STATS  
     procedure, 93-55  
 GATHER\_SCHEMA\_STATS procedures, 93-59  
 GATHER\_SYSTEM\_STATS procedure, 93-64  
 GATHER\_TABLE\_STATS procedure, 93-67  
 GENERATE\_SIGNATURE procedure, 60-6  
 GENERATE\_STATS procedure, 93-71  
 GENERATEBEAN procedure, 118-10  
 GENERATESCHEMA function, 118-11  
 GENERATESCHEMAS function, 118-12  
 GET function  
     of OWA\_COOKIE package, 130-4  
 GET\* member functions  
     of ANYDATA TYPE, 168-8  
     of ANYDATASET TYPE, 169-7  
 GET\_ACLOID function, 112-5  
 GET\_ALL procedure, 130-5  
 GET\_ALL\_NAMES member function, 181-8  
 GET\_ASSOCIATION\_RULES function, 23-45  
 GET\_AUTHENTICATION procedure, 156-45  
 GET\_BASE\_TABLE\_NAME member  
     function, 174-8  
 GET\_BASE\_TABLE\_OWNER member  
     function, 174-9  
 GET\_BODY\_CHARSET procedure, 156-47  
 GET\_CATEGORY function, 105-6  
 GET\_CGI\_ENV function, 137-14  
 GET\_CLIENT\_HOSTNAME function, 135-4  
 GET\_CLIENT\_IP function, 135-5  
 GET\_COLUMN\_STATS procedures, 93-72  
 GET\_COMMAND\_TYPE member function, 174-34  
 GET\_COMMIT\_SCN member function, 174-35  
 GET\_COMPATIBLE member function, 174-35  
 GET\_COOKIE\_COUNT function, 156-48  
 GET\_COOKIE\_SUPPORT procedure, 156-49  
 GET\_COOKIES function, 156-50  
 GET\_CPU\_TIME function, 104-28  
 GET\_CURRENT\_SCHEMA member  
     function, 174-9  
 GET\_DEFAULT\_SETTINGS function, 23-48  
 GET\_DEPENDENCY procedure, 104-29  
 GET\_DETAILED\_EXCP\_SUPPORT  
     procedure, 156-51  
 GET\_DETAILED\_SQLCODE function, 156-52  
 GET\_DETAILED\_SQLERRM function, 156-53  
 GET\_ERROR\_MESSAGE function, 15-28  
 GET\_ETAG function, 129-5  
 GET\_EXTRA\_ATTRIBUTE member  
     function, 174-36  
 GET\_FILE procedure, 35-5  
 GET\_FOLLOW\_REDIRECT procedure, 156-54  
 GET\_FREQUENT\_ITEMSETS function, 23-50  
 GET\_HASH\_VALUE function, 104-30  
 GET\_HEADER procedure, 156-55  
 GET\_HEADER\_BY\_NAME procedure, 156-56  
 GET\_HEADER\_COUNT function, 156-57  
 GET\_HOST\_ADDRESS function, 158-4  
 GET\_HOST\_NAME function, 158-5  
 GET\_IN\_PARAMETER\_TYPES function, 153-6  
 GET\_INDEX\_STATS procedures, 93-74  
 GET\_INDEXES function, 27-31  
 GET\_INFORMATION function, 95-8  
 GET\_LEVEL function, 129-6  
 GET\_LINE function, 165-13  
 GET\_LINE procedure, 61-10, 155-22  
 GET\_LINE\_MAP function, 27-33  
 GET\_LINE\_NCHAR procedure, 155-24  
 GET\_LINES procedure, 61-11  
 GET\_LOB\_INFORMATION member  
     function, 174-22  
 GET\_LOB\_OFFSET member function, 174-23  
 GET\_LOB\_OPERATION\_SIZE member  
     procedure, 174-23  
 GET\_LOGON\_USER member function, 174-10  
 GET\_LONG\_INFORMATION member  
     function, 174-25  
 GET\_MODEL\_DETAILS\_ABN function, 23-52  
 GET\_MODEL\_DETAILS\_KM function, 23-54  
 GET\_MODEL\_DETAILS\_NB function, 23-58  
 GET\_MODEL\_DETAILS\_NMF function, 23-60  
 GET\_MODEL\_DETAILS\_SVM function, 23-62  
 GET\_MODEL\_SETTINGS function, 23-64  
 GET\_MODEL\_SIGNATURE function, 23-66  
 GET\_MORE\_SOURCE procedure, 27-32  
 GET\_NEXT\_HIT function, 81-10  
 GET\_OBJECT\_NAME member function, 174-38  
 GET\_OBJECT\_OWNER member function, 174-38  
 GET\_OBJECT\_TYPE member function, 174-10  
 GET\_OUT\_PARAMETER\_TYPES function, 153-7  
 GET\_OUTPUT\_VALUES function, 153-8

GET\_OWA\_SERVICE\_PATH function, 137-15  
 GET\_PARAM function, 93-78  
 GET\_PARAMETER\_VALUE function, 104-31  
 GET\_PASSWORD function, 135-6  
 GET\_PERSISTENT\_CONN\_COUNT  
   function, 156-58  
 GET\_PERSISTENT\_CONN\_SUPPORT  
   procedure, 156-59  
 GET\_PERSISTENT\_CONNS procedure, 156-60  
 GET\_PORTS function, 153-9  
 GET\_PROCEDURE function, 137-16  
 GET\_PROPERTY function, 153-10  
 GET\_PROXY procedure, 156-61  
 GET\_RAW function, 155-25, 165-14  
 GET\_RESPONSE function, 156-62  
 GET\_RESPONSE\_ERROR\_CHECK  
   procedure, 156-63  
 GET\_RETURN\_TYPE function, 153-11  
 GET\_ROWID function, 133-5  
 GET\_RUNTIME\_INFO function, 27-34  
 GET\_SCN member function, 174-38  
 GET\_SCN\_MAPPING procedure, 96-70  
 GET\_SERVICES function, 153-12  
 GET\_SESSION\_TIMEOUT function, 78-5  
 GET\_SOURCE\_DATABASE\_NAME member  
   function, 174-38  
 GET\_STATS\_HISTORY\_AVAILABILITY  
   function, 93-79  
 GET\_STATS\_HISTORY\_RETENTION  
   function, 93-80  
 GET\_STREAMS\_NAME function, 95-9  
 GET\_STREAMS\_TYPE function, 95-10  
 GET\_SYSTEM\_STATS procedure, 93-81  
 GET\_TABLE\_STATS procedure, 93-84  
 GET\_TAG function, 95-11  
 GET\_TAG member function, 174-38  
 GET\_TEXT function, 165-16  
 GET\_THRESHOLD procedure, 84-13  
 GET\_TIME function, 104-33  
 GET\_TIMEOUT function, 78-6  
 GET\_TIMEOUT\_BEHAVIOUR function, 27-35  
 GET\_TRANSACTION\_ID member  
   function, 174-39  
 GET\_TRANSFER\_TIMEOUT procedure, 156-64  
 GET\_USER\_ID function, 135-7  
 GET\_USERID function, 112-6  
 GET\_VALUE function, 27-36  
 GET\_VALUE member function, 174-25, 181-8  
 GET\_VALUES member function, 174-26  
 GET\_VERSION procedure, 64-10  
 GET\_WARNING\_SETTING\_CAT function, 105-7  
 GET\_WARNING\_SETTING\_NUM function, 105-8  
 GET\_WARNING\_SETTING\_STRING  
   function, 105-9  
 GET\_X function, 132-4  
 GET\_Y function, 132-5  
 GETACLDOCUMENT function, 108-19  
 GETATTRELEMINFO member function  
   of ANYTYPE TYPE, 170-12  
 GETATTRIBUTE function, 113-61  
 GETATTRIBUTENODE function, 113-63  
 GETATTRIBUTES function, 113-62  
 GETBLOB function, 172-3, 172-11, 172-21, 172-29  
 GETBLOBVAL function, 182-11  
 GETBUBLICID function, 113-93  
 GETCHILDNODES function, 113-64  
 GETCHILDRENBYTAGNAME function, 113-65  
 GETCLOB function, 172-4, 172-12, 172-22, 172-30  
 GETCLOBVAL function, 182-12  
 GETCONTENTSBLOBBYRESID function, 109-5  
 GETCONTENTSCLOBBYRESID function, 109-6  
 GETCONTENTSEXMLBYRESID function, 109-7  
 GETCONTENTTYPE function, 172-5, 172-13,  
   172-23, 172-31  
 GETCOUNT member function  
   of ANYDATASET TYPE, 169-11  
 GETDATA function, 113-66  
 GETDCHARSET function, 113-67  
 GETDOCTYPE function, 113-67, 115-3  
 GETDOCUMENT function, 115-3  
 GETDOCUMENTELEMENT function, 113-68  
 GETDTD function, 116-5  
 GETDTD procedure, 116-5  
 GETELEMENTSBYTAGNAME function, 113-69,  
   113-70  
 GETENTITIES function, 113-70  
 GETEXCEPTIONCONTENT procedure, 116-5,  
   117-6  
 GETEXPANDEDNAME function, 113-72  
 GETEXPANDEDNAME procedure, 113-71

GETEXTERNALURL function, 172-6, 172-14,  
 172-24, 172-32  
 GETFIRSTCHILD function, 113-72  
 GETIMPLEMENTATION function, 113-73  
 GETINFO member function  
   of ANYTYPE TYPE, 170-10  
 GETLASTCHILD function, 113-74  
 GETLENGTH function, 113-75, 113-76  
 GETLOCKTOKEN procedure, 108-20  
 GETNAME function, 113-77, 113-78  
 GETNAMEDITEM function, 113-78  
 GETNAMESPACE function, 113-80  
 GETNAMESPACE procedure, 113-79  
 GETNEXTSIBLING function, 113-80  
 GETNODENAME function, 113-81  
 GETNODETYPE function, 113-82  
 GETNODEVALUE function, 113-83  
 GETNOTATIONNAME function, 113-84  
 GETNOTATIONS function, 113-85  
 GETNUMBERVAL function, 182-14  
 GETNUMROWSPROCESSED function, 114-6  
 GETNUMROWSPROCESSED procedure, 116-6  
 GETOWNERDOCUMENT function, 113-87  
 GETOWNERELEMENT function, 113-88  
 GETPARENTNODE function, 113-89  
 GETPAT procedure, 134-10  
 GETPERSISTENT static function  
   of ANYTYPE TYPE, 170-9  
 GETPREDECESSORS function, 109-8  
 GETPREDSBYRESID function, 109-9  
 GETPREFIX function, 113-90  
 GETPREVIOUSIBLING function, 113-91  
 GETPRIVILEGES function, 108-21  
 GETPUBLICID function, 113-92, 113-93  
 GETQUALIFIEDNAME function, 113-93, 113-94  
 GETRELEASEVERSION function, 115-4  
 GETRESOID function, 108-22  
 GETRESOURCEBYRESID function, 109-10  
 GETROOTELEMENT function, 182-15  
 GETRUL function, 172-15  
 GETSCHEMANODE function, 113-94  
 GETSCHEMAURL function, 182-16  
 GETSPECIFIED function, 113-95  
 GETSTANDALONE function, 113-96  
 GETSTRINGVAL function, 182-17

GETSUCCESSORS function, 109-11  
 GETSUCCSBYRESID function, 109-12  
 GETSYSTEMID function, 113-97, 113-98  
 GETTAGNAME function, 113-98  
 GETTARGET function, 113-86  
 GETTYPE member function  
   of ANYDATA TYPE, 168-12  
   of ANYDATASET TYPE, 169-13  
 GETTYPENAME member function  
   of ANYDATA TYPE, 168-13  
   of ANYDATASET TYPE, 169-14  
 GETURL function, 172-7, 172-25, 172-33, 172-37  
 GETVALIDATIONMODE function, 115-4  
 GETVALUE function, 113-99  
 GETVERSION function, 113-100  
 GETVERSION procedure, 116-6  
 GETXDB\_TABLESPACE function, 108-23  
 GETXML function, 114-7, 116-7, 172-8, 172-16,  
 172-26, 172-34  
 GETXML procedure, 116-7  
 GETXMLTYPE function, 113-101, 114-9  
 GRANT\_ADMIN\_PRIVILEGE procedure, 97-3  
 GRANT\_OBJECT\_PRIVILEGE procedure, 82-18  
 GRANT\_REMOTE\_ADMIN\_ACCESS  
   procedure, 97-6  
 GRANT\_SWITCH\_CONSUMER\_GROUP  
   procedure, 77-3  
 GRANT\_SYSTEM\_PRIVILEGE procedure, 77-5,  
 82-20

## H

---

HASATTRIBUTE function, 113-102  
 HASCHILDNODES function, 113-104  
 HASFEATURE function, 113-105  
 HEADCLOSE function  
   of HTF package, 123-78  
 HEADCLOSE procedure  
   of HTP package, 128-76  
 HEADER function  
   of HTF package, 123-80  
 HEADER procedure  
   of HTP package, 128-78  
 HEADOPEN function  
   of HTF package, 123-79



- HEADOPEN procedure
  - of HTP package, 128-77
- HELO function and procedure, 164-20
- HELP function, 164-22
- HR function
  - of HTF package, 123-81
- HR procedure
  - of HTP package, 128-79
- HTF package, 123-1
- HTML tags
  - applet tags
    - functions, 123-4
    - procedures, 128-4
  - atags tags
    - procedures, 128-5
  - character formatting tags
    - functions, 123-7
    - procedures, 128-7
  - form tags
    - functions, 123-5
    - procedures, 128-5
  - frame tags
    - functions, 123-7
    - procedures, 128-7
  - list tags
    - functions, 123-4
    - procedures, 128-4
  - paragraph formatting tags
    - functions, 123-6
    - procedures, 128-6
  - table tags
    - functions, 123-5
- HTMLCLOSE function
  - of HTF package, 123-82
- HTMLCLOSE procedure
  - of HTP package, 128-80
- HTMLDB\_APPLICATION package
  - documentation, 125-2
- HTMLDB\_CUSTOM\_AUTH package
  - documentation, 124-2
- HTMLDB\_ITEM package documentation, 126-2
- HTMLDB\_UTIL package documentation, 127-2
- HTMLOPEN function
  - of HTF package, 123-83
- HTMLOPEN procedure

- of HTP package, 128-81
- HTP package, 128-1
- HTTP\_HEADER\_CLOSE procedure, 137-17
- HttpUriType, 172-9
- HTTPPURITYPE function, 172-17
- HttpUriType subtype, 172-9
  - CREATEURI function, 172-10
  - GETBLOB function, 172-11
  - GETCLOB function, 172-12
  - GETCONTENTTYPE function, 172-13
  - GETEXTERNALURL function, 172-14
  - GETRUL function, 172-15
  - GETXML function, 172-16
  - HTTPPURITYPE function, 172-17
  - methods, 172-9

## I

---

- IMG function
  - of HTF package, 123-84
- IMG procedure
  - of HTP package, 128-82
- IMG2 procedure
  - of HTP package, 128-83
- IMPORT\_COLUMN\_STATS procedure, 93-86
- IMPORT\_DATABASE\_STATS procedure, 93-88
- IMPORT\_DICTIONARY\_STATS procedure, 93-90
- IMPORT\_FIXED\_OBJECTS\_STATS
  - procedure, 93-92
- IMPORT\_INDEX\_STATS procedure, 93-94
- IMPORT\_MODEL procedure, 23-68
- IMPORT\_SCHEMA\_STATS procedure, 93-96
- IMPORT\_SYSTEM\_STATS procedure, 93-98
- IMPORT\_TABLE\_STATS procedure, 93-99
- IMPORTNODE function, 113-41, 113-106
- INCLUDE\_EXTRA\_ATTRIBUTES
  - procedure, 19-25
- INITIALIZE function, 27-39
- INITIALIZE procedure, 66-4
- INSERT\_BIN\_CAT\_FREQ procedure, 24-14
- INSERT\_BIN\_NUM\_EQWIDTH procedure, 24-16
- INSERT\_BIN\_NUM\_QTILE procedure, 24-18
- INSERT\_CLIP\_TRIM\_TAIL procedure, 24-20
- INSERT\_CLIP\_WINSOR\_TAIL procedure, 24-22
- INSERT\_NORM\_LIN\_MINMAX procedure, 24-26

INSERT\_NORM\_LIN\_ZSCORE procedure, 24-24  
 INSERTBEFORE function, 113-107  
 INSERTDATA procedure, 113-108  
 INSERTXML function, 117-6, 119-8  
 INSTANCE procedure, 41-9  
 instantiation  
   aborting database preparation, 19-4  
   aborting schema preparation, 19-5  
   aborting table preparation, 19-6  
   global SCN, 15-40  
   preparing a database for, 19-27  
   preparing a schema for, 19-28  
   preparing a table for, 19-29  
   schema SCN, 15-49  
   table SCN, 15-52  
 INTERNAL\_VERSION\_CHECK function, 64-11  
 internet addressing  
   using UTL\_INADDR, 158-1  
 INTERRUPT\_TUNING\_TASK procedure, 91-20  
 INTERVAL procedure, 41-10  
 INVOKE function, 153-13  
 IS\_CLUSTER\_DATABASE function, 104-34  
 IS\_HIERARCHY\_ENABLED function, 112-7  
 IS\_LOCATOR function, 151-3  
 IS\_NULL\_TAG member function, 174-39  
 IS\_OPEN function, 90-51, 155-26  
 IS\_TRIGGER\_FIRE\_ONCE function, 26-8  
 ISFRAGMENT function, 182-18  
 ISINDEX function  
   of HTF package, 123-86  
 ISINDEX procedure  
   of HTP package, 128-84  
 ISNULL function, 113-109, 113-113  
 ISOPEN function, 152-5  
 ISSCHEMABASED function, 182-19  
 ISSCHEMAVALID function, 182-20  
 ISSCHEMAVALIDATED function, 182-21  
 ITALIC function  
   of HTF package, 123-87  
 ITALIC procedure  
   of HTP package, 128-85  
 ITEM function, 113-113

## K

---

KBD function  
   of HTF package, 123-88  
 KBD procedure  
   of HTP package, 128-86  
 KEEP procedure, 87-5  
 KEYBOARD function  
   of HTF package, 123-89  
 KEYBOARD procedure  
   of HTP package, 128-87

## L

---

LAST\_ERROR\_POSITION function, 90-52  
 LAST\_ROW\_COUNT function, 90-53  
 LAST\_ROW\_ID function, 90-54  
 LAST\_SQL\_FUNCTION\_CODE function, 90-55  
 LCR\$\_DDL\_RECORD type, 174-3  
 LCR\$\_ROW\_LIST type, 174-44  
 LCR\$\_ROW\_RECORD type, 174-14  
 LCR\$\_ROW\_UNIT type, 174-45  
   GET\_LOB\_INFORMATION member  
     function, 174-22  
   GET\_LOB\_OPERATION\_SIZE member  
     procedure, 174-23  
   GET\_LONG\_INFORMATION member  
     function, 174-25  
   SET\_LOB\_INFORMATION member  
     procedure, 174-28  
   SET\_LOB\_OPERATION\_SIZE member  
     procedure, 174-30  
 LENGTH function, 161-29  
 LINE function  
   of HTF package, 123-90  
 LINE procedure  
   of HTP package, 128-88  
 LINK procedure, 108-24  
 LINKREL function  
   of HTF package, 123-91  
 LINKREL procedure  
   of HTP package, 128-89  
 LINKREV function  
   of HTF package, 123-92  
 LINKREV procedure  
   of HTP package, 128-90

- LISTHEADER function
  - of HTP package, 123-93
- LISTHEADER procedure
  - of HTP package, 128-91
- LISTINGCLOSE function
  - of HTP package, 123-94
- LISTINGCLOSE procedure
  - of HTP package, 128-92
- LISTINGOPEN function
  - of HTP package, 123-95
- LISTINGOPEN procedure
  - of HTP package, 128-93
- LISTITEM function
  - of HTP package, 123-96
- LISTITEM procedure
  - of HTP package, 128-94
- LISTPRINT procedure, 137-18
- LOAD\_SQLSET procedure, 91-21
- LOBs
  - DBMS\_LOB package, 45-1
- LOCAL\_TRANSACTION\_ID function, 101-12
- LOCK\_MAP procedure, 94-8
- LOCK\_OBJECT procedure, 163-9
- LOCK\_SCHEMA\_STATS procedure, 93-101
- LOCK\_TABLE\_STATS procedure, 93-102
- LOCKRESOURCE function, 108-25
- log apply services
  - managing initialization parameters for logical standby databases, 49-2
- logical change records (LCRs)
  - DDL LCRs, 174-3
    - getting base table name, 174-8
    - getting base table owner, 174-9
    - getting current schema, 174-9
    - getting logon user name, 174-10
    - getting object type, 174-10
    - setting base table name, 174-10
    - setting base table owner, 174-11
    - setting current schema, 174-11
    - setting DDL text, 174-12
    - setting logon user, 174-12
    - setting object type, 174-13
  - determining if tag is NULL, 174-39
  - executing, 174-8, 174-21
  - extra attributes
    - excluding, 19-25
    - including, 19-25
  - getting command type, 174-34
  - getting commit SCN, 174-35
  - getting compatibility information, 174-35
  - getting extra attributes, 174-36
  - getting object name, 174-38
  - getting object owner, 174-38
  - getting SCN, 174-38
  - getting source database name, 174-38
  - getting tag, 174-38
  - getting transaction identifier, 174-39
  - LCR\$\_DDL\_RECORD type, 174-3
  - LCR\$\_ROW\_LIST type, 174-44
  - LCR\$\_ROW\_RECORD type, 174-14
  - LCR\$\_ROW\_UNIT type, 174-45
  - row LCRs, 174-14
    - adding value to column, 174-19
    - converting LONG to LOB, 174-20
    - deleting value to column, 174-20
    - getting column value, 174-25
    - getting list of column values, 174-26
    - getting LOB offset, 174-23
    - renaming column, 174-28
    - setting column value, 174-31
    - setting list of column values, 174-32
    - setting LOB offset, 174-29
  - setting command type, 174-40
  - setting extra attributes, 174-40
  - setting object name, 174-41
  - setting object owner, 174-42
  - setting source database name, 174-42
  - setting tag, 174-43
  - types, 174-1
- LZ\_COMPRESS functions and procedures, 152-6
- LZ\_COMPRESS\_ADD procedure, 152-8
- LZ\_COMPRESS\_CLOSE procedure, 152-9
- LZ\_COMPRESS\_OPEN function, 152-10
- LZ\_UNCOMPRESS functions and procedures, 152-11
- LZ\_UNCOMPRESS\_CLOSE procedure, 152-15
- LZ\_UNCOMPRESS\_EXTRACT procedure, 152-13
- LZ\_UNCOMPRESS\_OPEN function, 152-14

## M

---

MAIL function and procedure, 164-23  
MAILTO function  
  of HTF package, 123-97  
MAILTO procedure  
  of HTP package, 128-95  
MAINTAIN\_SIMPLE\_TABLESPACE  
  procedure, 96-72  
MAINTAIN\_TABLESPACES procedure, 96-78  
MAKE\_DATA\_BLOCK\_ADDRESS  
  function, 104-35  
MAKEATTR function, 113-114  
MAKECDATASECTION function, 113-115  
MAKECHARACTERDATA function, 113-116  
MAKECOMMENT function, 113-117  
MAKEDOCUMENT function, 113-118  
MAKEDOCUMENTFRAGMENT  
  function, 113-119  
MAKEDOCUMENTTYPE function, 113-120  
MAKEELEMENT function, 113-121  
MAKEENTITY function, 113-122  
MAKEENTITYREFERENCE function, 113-123  
MAKENODE function, 113-124, 113-127  
MAKENOTATION function, 113-127  
MAKEPROCESSINGINSTRUCTION  
  function, 113-128  
MAKETEXT function, 113-129  
MAKEVERSIONED function, 109-13  
MAP\_ALL function, 94-9  
MAP\_ELEMENT function, 94-10  
MAP\_FILE function, 94-11  
MAP\_OBJECT function, 94-13  
MAPCLOSE function  
  of HTF package, 123-98  
MAPCLOSE procedure  
  of HTP package, 128-96  
MAPOPEN function  
  of HTF package, 123-99  
MAPOPEN procedure  
  of HTP package, 128-97  
MATCH function, 134-11  
materialized view logs  
  master table  
  purging, 54-14, 54-15, 54-16

materialized views  
  refreshing, 54-18, 54-21, 54-23  
MENULISTCLOSE function  
  of HTF package, 123-100  
MENULISTCLOSE procedure  
  of HTP package, 128-98  
MENULISTOPEN function  
  of HTF package, 123-101  
MENULISTOPEN procedure  
  of HTP package, 128-99  
META function  
  of HTF package, 123-102  
META procedure  
  of HTP package, 128-100  
methodology  
  transformation, 24-6  
MG2 function  
  of HTF package, 123-85  
migration  
  post-migration actions, 55-1  
MIME\_HEADER procedure, 137-20  
MIMEHEADER\_DECODE function, 154-5  
MIMEHEADER\_ENCODE function, 154-7  
min-max normalization, 24-4  
MODIFY\_SNAPSHOT\_SETTINGS  
  procedure, 106-9  
MODIFY\_TRANSFORMATION procedure, 102-6  
MOVEXDB\_TABLESPACE procedure, 108-26

## N

---

NAME\_RESOLVE procedure, 104-36  
NAME\_TOKENIZE procedure, 104-38  
NAMESPACE function, 182-13  
new features, 1-xxxiii  
NEW\_LINE procedure, 61-12, 155-27  
NEW\_ROW\_LIST function and procedure, 136-5  
NEWCONTEXT function, 114-10, 116-8, 117-7,  
  119-9  
NEWDOMDOCUMENT function, 113-130  
NEWPARSER function, 115-4  
NEWPROCESSOR function, 121-4  
NEWSTYLESHEET function, 121-4  
NEXT\_DATE procedure, 41-11  
NEXT\_ITEM\_TYPE function, 63-28

- NL function
  - of HTF package, 123-103
- NL procedure
  - of HTP package, 128-101
- NOBR function
  - of HTF package, 123-104
- NOBR procedure
  - of HTP package, 128-102
- NOFRAMESCLOSE function
  - of HTF package, 123-105
- NOFRAMESCLOSE procedure
  - of HTP package, 128-103
- NOFRAMESOPEN function
  - of HTF package, 123-106
- NOFRAMESOPEN procedure
  - of HTP package, 128-104
- NOOP function and procedure, 164-25
- NORMAL function, 66-5
- NORMAL\_DIST\_FIT procedure, 92-4
- normalization, 24-4
  - min-max, 24-4
  - z-score, 24-4
- NORMALIZE procedure, 113-131
- numerical binning, 24-3

## O

---

- OBJECT\_DEPENDENT\_SEGMENTS
  - function, 88-10
- OBJECT\_GROWTH\_TREND function, 88-13
- OLISTCLOSE function
  - of HTF package, 123-107
- OLISTCLOSE procedure
  - of HTP package, 128-105
- OLISTOPEN function
  - of HTF package, 123-108
- OLISTOPEN procedure
  - of HTP package, 128-106
- OPEN\_CONNECTION function, 165-18
- OPEN\_CONNECTION functions, 164-26
- OPEN\_CURSOR function, 90-56
- OPEN\_DATA function and procedure, 164-28
- OR REPLACE clause
  - for creating packages, 1-3
- Oracle Streams

- administrator
  - granting privileges, 97-3
  - revoking privileges, 97-7
- compatibility, 95-4, 95-5, 174-35
- creating queues, 96-107
- data dictionary
  - removing information, 96-92
- messaging
  - notification, 96-100
- Oracle-supplied types
  - logical change record (LCR) types, 174-1
  - rule types, 181-1
- ORMAT\_CALL\_STACK function, 104-27
- OUTLN\_PKG package, 59-1
- OVERLAY function, 161-30
- OWA\_CACHE package, 129-1
- OWA\_COOKIE package, 130-1
- OWA\_CUSTOM package, 131-1
- OWA\_IMAGE package, 132-1
- OWA\_OPT\_LOCK package, 133-1
- OWA\_PATTERN package, 134-1
- OWA\_SEC package, 135-1
- OWA\_TEXT package, 136-1
- OWA\_UTIL package, 137-1

## P

---

- PACK\_MESSAGE procedures, 63-21
- package
  - DBMS\_ODCI, 56-1
  - DBMS\_XDB, 108-1
  - DBMS\_XDB\_VERSION, 109-1
  - DBMS\_XDBT, 111-1
  - DBMS\_XMLDOM, 113-1
  - DBMS\_XMLGEN, 114-1
  - DBMS\_XMLPARSER, 115-1
  - DBMS\_XMLQUERY, 116-1
  - DBMS\_XMLSAVE, 117-1
  - DBMS\_XMLSCHEMA, 118-1
  - DBMS\_XMLSTORE, 119-1
  - DBMS\_XSLPROCESSOR, 121-1
  - UriFactory, 172-36
- Package - UriFactory, 172-36
- package DBMS\_XDBZ, 112-1
- package overview, 1-2

- package variables
  - i\_am\_a\_refresh, 54-12
- packages
  - creating, 1-3
  - referencing, 1-6
  - where documented, 1-7
- PARAM function
  - of HTF package, 123-109
- PARAM procedure
  - of HTP package, 128-107
- PARAGRAPH function
  - of HTF package, 123-110
- PARAGRAPH procedure
  - of HTP package, 128-108
- PARAM function
  - of HTF package, 123-111
- PARAM procedure
  - of HTP package, 128-109
- PARSE procedure, 90-57, 115-4
- PARSEBUFFER procedure, 115-5
- PARSECLOB procedure, 115-6
- PARSEDTD procedure, 115-6
- PARSEDTDBUFFER procedure, 115-7
- PARSEDTDCLLOB procedure, 115-7
- PAUSE\_PROFILER function and procedure, 64-12
- PGRAD\_STAT\_TABLE procedure, 93-134
- PIECEWISE member procedure
  - of ANYDATA TYPE, 168-14
  - of ANYDATASET TYPE, 169-15
- PING procedure, 27-41
- PLAINTEXT function
  - of HTF package, 123-112
- PLAINTEXT procedure
  - of HTP package, 128-110
- plan stability, 59-2
- PL/SQL
  - datatypes, 31-4
    - numeric codes for, 31-7
  - functions
    - DBMS\_MGWADM package
      - subprograms, 51-29
    - DBMS\_MGWMSG package
      - subprograms, 52-24
  - procedures
    - DBMS\_MGWADM package
      - subprograms, 51-29
    - DBMS\_MGWMSG package
      - subprograms, 52-24
- PLSQL\_TRACE\_VERSION procedure, 100-9
- pointer to
  - CTX\_ADM package, 2-1
- point-in-time recovery
  - Oracle Streams, 96-70
- POISSON\_DIST\_FIT procedure, 92-5
- PORT\_STRING function, 104-39
- PRECLOSE function
  - of HTF package, 123-113
- PRECLOSE procedure
  - of HTP package, 128-111
- PREOPEN function
  - of HTF package, 123-114
- PREOPEN procedure
  - of HTP package, 128-112
- PREPARE\_COLUMN\_VALUES
  - procedures, 93-103
- PREPARE\_COLUMN\_VALUES\_NVARCHAR2
  - procedure, 93-106
- PREPARE\_COLUMN\_VALUES\_ROWID
  - procedure, 93-108
- PREPARE\_GLOBAL\_INSTANTIATION
  - procedure, 19-27
- PREPARE\_SCHEMA\_INSTANTIATION
  - procedure, 19-28
- PREPARE\_TABLE\_INSTANTIATION
  - procedure, 19-29
- PRINT function
  - of HTF package, 123-115
- PRINT procedure
  - of HTP package, 128-113
- PRINT\_BACKTRACE procedure, 27-42
- PRINT\_CGI\_ENV procedure, 137-21
- PRINT\_INSTANTIATIONS procedure, 27-43
- PRINT\_MULTI procedure, 136-6
- PRINT\_ROW\_LIST procedure, 136-7
- PRINTS procedure
  - of HTP package, 128-114
- prior probabilities, 23-17
- privileges
  - Oracle Streams administrator, 97-3, 97-7
- PRN function

- of HTF package, 123-116
- PRN procedure
  - of HTP package, 128-115
- PROBE\_VERSION procedure, 27-44
- PROCESSXSL function, 121-5
- PROPAGATEORIGINALEXCEPTION
  - procedure, 116-8, 117-7
- propagations
  - altering, 65-3
  - creating, 65-6, 96-14, 96-34, 96-46, 96-58
  - DBMS\_PROPAGATION\_ADM package, 65-1
  - dropping, 65-11
  - rules
    - defining global, 96-14
    - defining schema, 96-34
    - defining subset, 96-46
    - defining table, 96-58
- PS procedure
  - of HTP package, 128-116
- PULL\_SIMPLE\_TABLESPACE procedure, 99-22
- PULL\_TABLESPACES procedure, 99-25
- PURGE procedure, 63-33
- PURGE\_LOST\_DB\_ENTRY procedure, 101-13
- PURGE\_MIXED procedure, 101-16
- PURGE\_SOURCE\_CATALOG procedure, 96-92
- PURGE\_STATS procedure, 93-110
- PURGELDAPCACHE function, 112-8
- purging
  - the subscription window, 21-2
- PUT procedure, 155-28
- PUT procedures, 61-13
- PUT\_FILE procedure, 35-7
- PUT\_LINE procedure, 155-33
- PUT\_LINE procedures, 61-15
- PUT\_LINE\_NCHAR procedure, 155-34
- PUT\_NCHAR procedure, 155-31
- PUT\_RAW function, 155-32
- PUTF procedure, 155-29
- PUTF\_NCHAR procedure, 155-35

## Q

---

- quantile numerical binning, 24-3
- query generation, 24-6
- queues

- AnyData
  - creating, 96-107
  - removing, 96-94
- QUIT function and procedure, 164-30
- QUOTED\_PRINTABLE\_DECODE function, 154-9
- QUOTED\_PRINTABLE\_ENCODE
  - function, 154-10

## R

---

- RANDOM procedure, 66-6
- RANK\_APPLY procedure, 23-72
- RCPT function, 164-32
- RESATTRIBUTE\_VALUE type, 181-4
- RESATTRIBUTE\_VALUE\_LIST type, 181-4
- RESCOLUMN\_VALUE type, 181-5, 181-9
- RESCOLUMN\_VALUE\_LIST type, 181-6
- RESNAME\_ARRAY type, 181-6
- RESNV\_ARRAY type, 181-6
- RESNV\_LIST type, 181-6
  - ADD\_PAIR member procedure, 181-7
  - GET\_ALL\_NAMES member function, 181-8
  - GET\_VALUE member function, 181-8
  - REMOVE\_PAIR member procedure, 181-8
- RESRULE\_HIT type, 181-10
- RESRULE\_HIT\_LIST type, 181-10
- RESTABLE\_ALIAS type, 181-11
- RESTABLE\_ALIAS\_LIST type, 181-12
- RESTABLE\_VALUE type, 181-12
- RESTABLE\_VALUE\_LIST type, 181-12
- RESVARIABLE\_TYPE type, 181-13
- RESVARIABLE\_TYPE\_LIST type, 181-15
- RESVARIABLE\_VALUE type, 181-16
- RESVARIABLE\_VALUE\_LIST type, 181-16
- READ\_CLIENT\_INFO procedure, 14-5
- READ\_LINE function, 165-21
- READ\_LINE procedure
  - of UTL\_HTTP, 156-65
- READ\_MODULE procedure, 14-6
- READ\_ONLY procedure, 101-17
- READ\_RAW function, 165-23
- READ\_RAW procedure
  - of UTL\_HTTP, 156-67
- READ\_TEXT function, 165-25
- READ\_TEXT procedure

- of UTL\_HTTP, 156-68
- READ\_WRITE procedure, 101-18
- READ2CLOB function, 121-7
- REBUILD\_FREELISTS procedure, 70-14
- REBUILDHIERARCHICALINDEX
  - procedure, 108-27
- RECEIVE\_MESSAGE function, 63-26
- RECOMP\_PARALLEL procedure, 162-5
- RECOMP\_SERIAL procedure, 162-6
- REDIRECT\_URL procedure, 137-22
- refresh
  - materialized views, 54-18, 54-21, 54-23
- REFRESH\_PRIVATE\_OUTLINE procedure, 60-7
- REGISTER procedure, 13-7
- REGISTER\_DEPENDENT\_OBJECT
  - procedure, 68-10
- REGISTERSHEMA procedure, 118-13
- REGISTERURI procedure, 118-16
- REGISTERURLHANDLER procedure, 172-40
- RELEASE function, 46-10
- RELEASE\_ALL\_SERVICES procedure, 153-14
- RELEASE\_CALL procedure, 153-15
- RELEASE\_SERVICE procedure, 153-16
- REMOVE procedure
  - of DBMS\_ALERT package, 13-8
  - of DBMS\_JOB package, 41-12
  - of OWA\_COOKIE package, 130-6
- REMOVE\_PAIR member procedure, 181-8
- REMOVE\_PIPE function, 63-31
- REMOVE\_PROPERTY procedure, 153-17
- REMOVE\_QUEUE procedure, 96-94
- REMOVE\_RULE procedure, 82-22, 96-96
- REMOVE\_SQLSET\_REFERENCE procedure, 91-22
- REMOVE\_STREAMS\_CONFIGURATION
  - procedure, 96-98
- REMOVEALL procedure, 13-9
- REMOVEATTRIBUTE procedure, 113-132
- REMOVEATTRIBUTENODE function, 113-133
- REMOVENAMEDITEM function, 113-135
- REMOVEPARAM procedure, 121-7
- REMOVEXSLTPARAM procedure, 116-9, 117-8
- RENAME\_COLUMN member procedure, 174-28
- RENAME\_MODEL procedure, 23-75
- RENAMERESOURCE procedure, 108-28
- REPLACECHILD function, 113-136

- REPLACEDATA procedure, 113-137
- replication
  - datetime datatypes
    - abbreviations, 1-7
  - interval datatypes
    - abbreviations, 1-7
- REPLY, REPLIES record types, 164-4
- REPORT\_TUNING\_TASK function, 91-23
- REQUEST function, 46-11, 156-70
- REQUEST\_PIECES function, 156-73
- RESET\_BUFFER procedure, 63-34
- RESET\_TUNING\_TASK procedure, 91-24
- RESETPARAMS procedure, 121-8
- RESOLVENAMESPACEPREFIX function, 113-138
- RESTARTQUERY procedure, 114-11
- RESTORE function, 94-14
- RESTORE\_DATABASE\_STATS procedure, 93-111
- RESTORE\_DICTIONARY\_STATS
  - procedure, 93-112
- RESTORE\_FIXED\_OBJECTS\_STATS
  - procedure, 93-113
- RESTORE\_SCHEMA\_STATS procedure, 93-114
- RESTORE\_SYSTEM\_STATS procedure, 93-115
- RESTORE\_TABLE\_STATS procedure, 93-116
- RESUME\_PROFILER function and
  - procedure, 64-13
- RESUME\_TUNING\_TASK procedure, 91-25
- REVERSE function, 161-32
- REVOKE\_ADMIN\_PRIVILEGE procedure, 97-7
- REVOKE\_OBJECT\_PRIVILEGE procedure, 82-24
- REVOKE\_REMOTE\_ADMIN\_ACCESS
  - procedure, 97-9
- REVOKE\_SWITCH\_CONSUMER\_GROUP
  - procedure, 77-6
- REVOKE\_SYSTEM\_PRIVILEGE procedure, 77-8, 82-25
- ROLLBACK procedure, 101-19
- ROLLBACK\_FORCE procedure, 101-20
- ROLLBACK\_SAVEPOINT procedure, 101-21
- row migration, 96-46, 96-52
- ROWID datatype
  - extended format, 80-17
- ROWID\_BLOCK\_NUMBER function, 80-7
- ROWID\_CREATE function, 80-8
- ROWID\_INFO procedure, 80-10



- ROWID\_OBJECT function, 80-12
- ROWID\_RELATIVE\_FNO function, 80-13
- ROWID\_ROW\_NUMBER function, 80-14
- ROWID\_TO\_ABSOLUTE\_FNO function, 80-15
- ROWID\_TO\_EXTENDED function, 80-17
- ROWID\_TO\_RESTRICTED function, 80-19
- ROWID\_TYPE function, 80-20
- ROWID\_VERIFY function, 80-21
- rule sets
  - adding rules to, 82-4
  - creating, 82-13
  - dropping, 82-17
  - removing rules from, 82-22
- rule-based transformations
  - setting, 96-105
- rules
  - action contexts
    - adding name-value pairs, 181-7
    - getting name-value pairs, 181-8
    - getting value for name, 181-8
    - removing name-value pairs, 181-8
    - transformations, 96-105
  - altering, 82-6
  - creating, 82-11
  - DBMS\_RULE package, 81-1
  - DBMS\_RULE\_ADM package, 82-1
  - dropping, 82-16
  - evaluation, 81-5
    - iterators, 81-4, 81-10
  - evaluation contexts
    - creating, 82-9
    - dropping, 82-15
  - object privileges
    - granting, 82-18
    - revoking, 82-24
  - propagations
    - removing, 96-96
  - RESATTRIBUTE\_VALUE type, 181-4
  - RESATTRIBUTE\_VALUE\_LIST type, 181-4
  - RESCOLUMN\_VALUE type, 181-5, 181-9
  - RESCOLUMN\_VALUE\_LIST type, 181-6
  - RESNAME\_ARRAY type, 181-6
  - RESNV\_ARRAY type, 181-6
  - RESNV\_LIST type, 181-6
  - RESRULE\_HIT type, 181-10

- RESRULE\_HIT\_LIST type, 181-10
- RESTABLE\_ALIAS type, 181-11
- RESTABLE\_ALIAS\_LIST type, 181-12
- RESTABLE\_VALUE type, 181-12
- RESTABLE\_VALUE\_LIST type, 181-12
- RESVARIABLE\_TYPE type, 181-13
- RESVARIABLE\_TYPE\_LIST type, 181-15
- RESVARIABLE\_VALUE type, 181-16
- RESVARIABLE\_VALUE\_LIST type, 181-16
- subset
  - defining, 96-46, 96-52
- system privileges
  - granting, 82-20
  - revoking, 82-25
- system-created
  - global apply, 96-19
  - global capture, 96-19
  - global propagation, 96-14
  - global schema, 96-39
  - removing, 96-96
  - schema capture, 96-39
  - schema propagation, 96-34
  - subset apply, 96-52
  - subset capture, 96-52
  - subset propagation, 96-46
  - table apply, 96-63
  - table capture, 96-63
  - table propagation, 96-58
- types, 181-1
- RUN procedure, 41-13

## S

---

- S function
  - of HTF package, 123-117
- S procedure
  - of HTP package, 128-117
- SAMPLE function
  - of HTF package, 123-118
- SAMPLE procedure
  - of HTP package, 128-118
- SAVE function, 94-15
- SAVEPOINT procedure, 101-22
- SCHEMAVALIDATE procedure, 182-22
- SCN\_TO\_TIMESTAMP function, 36-13

SCRIPT function  
     of HTF package, 123-119  
 SCRIPT procedure  
     of HTP package, 128-119  
 SDO\_CS package documentation, 138-2  
 SDO\_GCDR package documentation, 139-2  
 SDO\_GEOM package documentation, 140-2  
 SDO\_GEOR package documentation, 141-2  
 SDO\_GEOR\_UTL package documentation, 142-2  
 SDO\_LRS package documentation, 143-2  
 SDO\_MIGRATE package documentation, 144-2  
 SDO\_NET package documentation, 145-2  
 SDO\_SAM package documentation, 146-2  
 SDO\_TOPO package documentation, 147-2  
 SDO\_TOPO\_MAP package documentation, 148-2  
 SDO\_TUNE package documentation, 149-2  
 SDO\_UTIL package documentation, 150-2  
 SEED procedures, 66-7  
 SEGMENT\_CORRUPT procedure, 89-5  
 SEGMENT\_DROP\_CORRUPT procedure, 89-6  
 SEGMENT\_DUMP procedure, 89-7  
 SEGMENT\_FIX\_STATUS procedure, 70-15  
 SEGMENT\_VERIFY procedure, 89-8  
 SELECT\_OBJECT procedure, 163-10  
 SELECT\_SQLSET function, 91-26  
 SELECT\_WORKLOAD\_REPOSITORY  
     functions, 91-27  
 SELECTNODES function, 121-8  
 SELECTSINGLENODE function, 121-8  
 SELF\_CHECK procedure, 27-45  
 SEND procedure, 130-7, 160-4  
 SEND\_ATTACH\_RAW procedure, 160-5  
 SEND\_ATTACH\_VARCHAR2 procedure, 160-7  
 SEND\_MESSAGE function, 63-23  
 SERV\_MOD\_ACT\_STAT\_DISABLE  
     procedure, 53-7  
 SERV\_MOD\_ACT\_STAT\_ENABLE  
     procedure, 53-8  
 SERV\_MOD\_ACT\_TRACE\_DISABLE  
     procedure, 53-10  
 SERV\_MOD\_ACT\_TRACE\_ENABLE  
     procedure, 53-12  
 SESSION\_TRACE\_DISABLE procedure, 53-14  
 SESSION\_TRACE\_ENABLE procedure, 53-15  
 SET\* member procedures  
     of ANYDATA TYPE, 168-15  
     of ANYDATASET TYPE, 169-16  
 SET\_ACTION procedure, 14-8  
 SET\_AUTHENTICATION procedure, 156-77  
 SET\_AUTHORIZATION procedure, 135-8  
 SET\_BASE\_TABLE\_NAME member  
     procedure, 174-10  
 SET\_BASE\_TABLE\_OWNER member  
     procedure, 174-11  
 SET\_BODY\_CHARSET procedures, 156-78  
 SET\_BREAKPOINT function, 27-46  
 SET\_CLIENT\_INFO procedure, 14-10  
 SET\_COLUMN\_STATS procedures, 93-117  
 SET\_COMMAND\_TYPE member  
     procedure, 174-40  
 SET\_CONSUMER\_GROUP\_MAPPING  
     procedure, 76-24  
 SET\_CONSUMER\_GROUP\_MAPPING\_PRI  
     procedure, 76-25  
 SET\_COOKIE\_SUPPORT procedures, 156-80  
 SET\_CURRENT\_SCHEMA member  
     procedure, 174-11  
 SET\_DDL\_TEXT member procedure, 174-12  
 SET\_DEFAULTS procedure, 13-10  
 SET\_DETAILED\_EXCP\_SUPPORT  
     procedure, 156-82  
 SET\_DML\_HANDLER procedure, 15-30  
 SET\_ENQUEUE\_DESTINATION procedure, 15-36  
 SET\_EXECUTE procedure, 15-38  
 SET\_EXTRA\_ATTRIBUTE member  
     procedure, 174-40  
 SET\_FOLLOW\_REDIRECT procedures, 156-83  
 SET\_GLOBAL\_INSTANTIATION  
     procedure, 15-40  
 SET\_HEADER procedure, 156-85  
 SET\_INDEX\_STATS procedures, 93-120  
 SET\_INITIAL\_CONSUMER\_GROUP  
     procedure, 76-27  
 SET\_KEY\_COLUMNS procedure, 15-43  
 SET\_LOB\_INFORMATION member  
     procedure, 174-28  
 SET\_LOB\_OFFSET member procedure, 174-29  
 SET\_LOB\_OPERATION\_SIZE member  
     procedure, 174-30  
 SET\_LOGON\_USER member procedure, 174-12

SET\_MESSAGE\_NOTIFICATION  
     procedure, 96-100  
 SET\_MODULE procedure, 14-11  
 SET\_OBJECT\_NAME member procedure, 174-41  
 SET\_OBJECT\_OWNER member procedure, 174-42  
 SET\_OBJECT\_TYPE member procedure, 174-13  
 SET\_OER\_BREAKPOINT function, 27-48  
 SET\_PARAM procedure, 93-124  
 SET\_PARAMETER procedure, 19-30  
     apply process, 15-45  
 SET\_PERSISTENT\_CONN\_SUPPORT  
     procedure, 156-87  
 SET\_PLSQL\_TRACE procedure, 100-10  
 SET\_PROPERTY procedure, 153-18  
 SET\_PROTECTION\_REALM procedure, 135-10  
 SET\_PROXY procedure, 156-90  
 SET\_RESPONSE\_ERROR\_CHECK  
     procedure, 156-92  
 SET\_RULE\_TRANSFORM\_FUNCTION  
     procedure, 96-105  
 SET\_SCHEMA\_INSTANTIATION  
     procedure, 15-49  
 SET\_SESSION\_LONGOPS procedure, 14-13  
 SET\_SESSION\_TIMEOUT procedure, 78-7  
 SET\_SOURCE\_DATABASE\_NAME member  
     procedure, 174-42  
 SET\_SYSTEM\_STATS procedure, 93-126  
 SET\_TABLE\_INSTANTIATION procedure, 15-52  
 SET\_TABLE\_STATS procedure, 93-129  
 SET\_TAG member procedure, 174-43  
 SET\_TAG procedure, 95-12  
 SET\_THRESHOLD procedure, 84-14  
 SET\_TIMEOUT function, 27-49  
 SET\_TIMEOUT procedure, 78-8  
 SET\_TIMEOUT\_BEHAVIOUR procedure, 27-50  
 SET\_TRANSFER\_TIMEOUT procedure, 156-93  
 SET\_TRIGGER\_FIRING\_PROPERTY  
     procedure, 26-9  
 SET\_UP\_QUEUE procedure, 96-107  
 SET\_UPDATE\_CONFLICT\_HANDLER  
     procedure, 15-54  
 SET\_VALUE function, 27-51  
 SET\_VALUE member procedure, 174-31  
 SET\_VALUES member procedure, 174-32  
 SET\_WALLET procedure, 156-94  
 SET\_WARNING\_SETTING\_STRING  
     procedure, 105-10  
 SETACL procedure, 108-29  
 SETATTRIBUTE procedure, 113-139  
 SETATTRIBUTENODE function, 113-140  
 SETBASEDIR procedure, 115-8  
 SETBATCHSIZE procedure, 117-8  
 SETBINDVALUE procedure, 116-9  
 SETCOLLIDATTRNAME procedure, 116-10  
 SETCOMMITBATCH procedure, 117-9  
 SETCONVERTSPECIALCHARS procedure, 114-12  
 SETDATA procedure, 113-141  
 SETDATAHEADER procedure, 116-10  
 SETDATEFORMAT procedure, 116-11, 117-9  
 SETDCHARSET procedure, 113-145  
 SETDOCTYPE procedure, 115-8  
 SETDVERSION procedure, 113-147  
 SETENCODINGTAG procedure, 116-11  
 SETERRORLOG procedure, 115-8, 121-9  
 SETERRORTAG procedure, 116-12  
 SETIGNORECASE procedure, 117-10  
 SETINFO member procedure  
     of ANYTYPE TYPE, 170-4  
 SETKEYCOLUMN procedure, 117-10, 119-10  
 SETMAXROWS procedure, 114-13, 116-12  
 SETMETAHEADER procedure, 116-13  
 SETNAMEDITEM function, 113-142  
 SETNODEVALUE procedure, 113-143  
 SETPARAM procedure, 121-9  
 SETPREFIX procedure, 113-144  
 SETPRESERVEWHITESPACE procedure, 115-9,  
     117-11  
 SETRAISEEXCEPTION procedure, 116-13  
 SETRAISENOROWSEXCEPTION  
     procedure, 116-14  
 SETROWIDATTRNAME procedure, 116-14  
 SETROWIDATTRVALUE procedure, 116-15  
 SETROWSETTAG procedure, 114-15, 116-15  
 SETROWTAG procedure, 116-15, 117-11, 119-11  
 SETSCHEMAVALIDATED procedure, 182-23  
 SETSKIPROWS procedure, 114-17, 116-16  
 SETSQLTOXMLNAMEESCAPING  
     procedure, 116-16, 117-11  
 SETSTANDALONE procedure, 113-145  
 SETSTYLESHEETHEADER procedure, 116-17

SETTAGCASE procedure, 116-17  
 SETUPDATECOLUMN procedure, 117-12, 119-12  
 SETVALIDATIONMODE procedure, 115-9  
 SETVALUE procedure, 113-146  
 SETXSLT procedure, 116-18, 117-12  
 SETXSLTPARAM procedure, 116-19, 117-13  
 SHOW\_BREAKPOINTS procedures, 27-53  
 SHOW\_FRAME\_SOURCE procedure, 27-54  
 SHOW\_SOURCE procedures, 27-55  
 SHOWPAGE procedure, 137-23  
 SHOWSOURCE procedure, 137-24  
 SHOWWARNINGS procedure, 115-10, 121-10  
 SIGNAL procedure, 13-11  
 SIGNATURE procedure, 137-25  
 SIZES procedure, 87-7  
 SKIP\_CORRUPT\_BLOCKS procedure, 70-17  
 SLEEP procedure, 46-13  
 SMALL function  
     of HTF package, 123-120  
 SMALL procedure  
     of HTP package, 128-120  
 snapshot. See DBMS\_MVIEW, 54-1  
 SPACE\_ERROR\_INFO function, 78-9  
 SPACE\_USAGE procedure, 88-15  
 SPLITTEXT function, 113-148  
 SQL statements  
     larger than 32 KB, 90-59  
 SQL\*Plus  
     creating a sequence, 1-6  
 staging  
     queues  
         creating, 96-107  
         removing, 96-94  
 START\_APPLY procedure, 15-58  
 START\_CAPTURE procedure, 19-33  
 START\_PROFILER functions and  
     procedures, 64-14  
 START\_REDEF\_TABLE procedure, 68-11  
 START\_SERVICE procedure, 85-7  
 STARTUP\_EXTPROC\_AGENT procedure, 122-5  
 STATUS\_LINE procedure, 137-26  
 STEP\_ID function, 101-23  
 STOP\_APPLY procedure, 15-59  
 STOP\_CAPTURE procedure, 19-34  
 STOP\_PROFILER function and procedure, 64-15  
 STOP\_SERVICE procedure, 85-8  
 STORE\_VALUES procedure, 133-6  
 stored outlines  
     DBMS\_OUTLN, 59-1  
     OUTLN\_PKG package, 59-1  
 STREAM2MULTI procedure, 136-8  
 Streams  
     removing configuration, 96-98  
 STREAMSS\_TRANSFORM\_FUNCTION, 15-36,  
     15-38, 96-106  
 STRIKE function  
     of HTF package, 123-121  
 STRIKE procedure  
     of HTP package, 128-121  
 STRING function, 66-8  
 STRONG function  
     of HTF package, 123-122  
 STRONG procedure  
     of HTP package, 128-122  
 STYLE function  
     of HTF package, 123-123  
 STYLE procedure  
     of HTP package, 128-123  
 SUB procedure  
     of HTP package, 128-124  
 SUBMIT procedure, 41-14  
 SUBMIT\_PENDING\_AREA procedure, 76-29  
 subscribers  
     drop the subscription, 21-2  
     extend the window to create a new view, 21-2  
     purging the subscription window, 21-2  
     retrieve change data from the subscriber  
         views, 21-2  
     subscription window  
         purging, 21-2  
 SUBSTR function, 161-33  
 SUBSTRINGDATA function, 113-149  
 SUMMARY procedure, 92-6  
 SUP function  
     of HTF package, 123-125  
 SUP procedure  
     of HTP package, 128-125  
 SWITCH\_CONSUMER\_GROUP\_FOR\_SESS  
     procedure, 76-30  
 SWITCH\_CONSUMER\_GROUP\_FOR\_USER

procedure, 76-31  
SWITCH\_PLAN procedure, 76-32  
SYNC\_INTERIM\_TABLE procedure, 68-13  
SYNCHRONIZE function, 27-57

## T

---

TABLE\_TO\_COMMA procedures, 104-40  
TABLECAPTION function  
  of HTF package, 123-126  
TABLECAPTION procedure  
  of HTP package, 128-126  
TABLECLOSE function  
  of HTF package, 123-129  
TABLECLOSE procedure  
  of HTP package, 128-129  
TABLEDATA function  
  of HTF package, 123-127  
TABLEDATA procedure  
  of HTP package, 128-127  
TABLEHEADER function  
  of HTF package, 123-128  
TABLEHEADER procedure  
  of HTP package, 128-128  
TABLEOPEN function  
  of HTF package, 123-130  
TABLEOPEN procedure  
  of HTP package, 128-130  
TABLEPRINT function, 137-27  
TABLEROWCLOSE function  
  of HTF package, 123-131  
TABLEROWCLOSE procedure  
  of HTP package, 128-131  
TABLEROWOPEN function  
  of HTF package, 123-132  
TABLEROWOPEN procedure  
  of HTP package, 128-132  
tables  
  table items as arrays, 90-28, 90-32  
TABLESPACE\_FIX\_BITMAPS procedure, 89-10  
TABLESPACE\_FIX\_SEGMENT\_STATES  
  procedure, 89-11  
TABLESPACE\_MIGRATE\_FROM\_LOCAL  
  procedure, 89-12  
TABLESPACE\_MIGRATE\_TO\_LOCAL  
  procedure, 89-13  
TABLESPACE\_REBUILD\_BITMAPS  
  procedure, 89-15  
TABLESPACE\_REBUILD\_QUOTAS  
  procedure, 89-16  
TABLESPACE\_RELOCATE\_BITMAPS  
  procedure, 89-17  
TABLESPACE\_SET type, 99-4  
TABLESPACE\_VERIFY procedure, 89-19  
tablespaces  
  change tables and, 20-25  
tags  
  GET\_TAG function, 95-11  
  SET\_TAG procedure, 95-12  
TARGET\_PROGRAM\_RUNNING  
  procedure, 27-58  
TELETYPE function  
  of HTF package, 123-133  
TELETYPE procedure  
  of HTP package, 128-133  
TERMINATE procedure, 66-9  
TEXT\_DECODE function, 154-11  
TEXT\_ENCODE function, 154-13  
TIMESTAMP\_TO\_SCN function, 36-14  
TITLE function  
  of HTF package, 123-134  
TITLE procedure  
  of HTP package, 128-134  
TODATE function, 137-31  
TOOBJECT procedure, 182-24  
top-N frequency binning, 24-3  
TRACETAB.SQL, 100-4  
transform definition table, 24-5  
TRANSFORM function, 182-25  
transformation methodology, 24-6  
transformations  
  binning, 24-3  
  equi-width binning, 24-3  
  normalization, 24-4  
  Oracle Streams  
    setting, 96-105  
  rule-based  
    setting, 96-105  
  STREAMS\_TRANSFORM\_  
    FUNCTION, 15-36, 15-38, 96-106

- supported, 24-3
- trimming, 24-4
- winsorizing, 24-4
- TRANSFORMNODE function, 121-10
- TRANSLATE function, 161-35
- TRANSPORT\_SET\_CHECK procedure, 110-5
- trimming, 24-4

## U

---

- ULISTCLOSE function
  - of HTF package, 123-135
- ULISTCLOSE procedure
  - of HTP package, 128-135
- ULISTOPEN function
  - of HTF package, 123-136
- ULISTOPEN procedure
  - of HTP package, 128-136
- UNCHECKOUT function, 109-14
- UNDERLINE function
  - of HTF package, 123-137
- UNDERLINE procedure
  - of HTP package, 128-137
- UNESCAPE function, 166-7
- UNESCAPEURI function, 172-39
- UNIFORM\_DIST\_FIT procedure, 92-8
- UNIQUE\_SESSION\_NAME function, 63-35
- UNKEEP procedure, 87-8
- UNLOCK\_MAP procedure, 94-16
- UNLOCK\_SCHEMA\_STATS procedure, 93-132
- UNLOCK\_TABLE\_STATS procedure, 93-133
- UNLOCKRESOURCE function, 108-30
- UNPACK\_MESSAGE procedures, 63-29
- UNREGISTER\_DEPENDENT\_OBJECT procedure, 68-14
- UNREGISTERURLHANDLER procedure, 172-41
- UNUSED\_SPACE procedure, 88-18
- UPDATE\_BY\_CAT procedure, 59-9
- UPDATE\_CONSUMER\_GROUP procedure, 76-33
- UPDATE\_OBJECT procedure, 163-11
- UPDATE\_PLAN procedure, 76-34
- UPDATE\_PLAN\_DIRECTIVE procedure, 76-35
- UPDATE\_SIGNATURES procedure, 59-10
- UPDATE\_SQLSET procedures, 91-29
- UPDATEXML function, 117-14, 119-13

- upgrading
  - post-upgrade actions, 55-1
- URI Types
  - description, 172-1
- UriFactory package, 172-36
  - ESCAPEURI function, 172-38
  - GETURL function, 172-37
  - methods, 172-36
  - REGISTERURLHANDLER procedure, 172-40
  - UNESCAPEURI function, 172-39
  - UNREGISTERURLHANDLER procedure, 172-41
- UriType supertype, 172-2
  - GETBLOB function, 172-3
  - GETCLOB function, 172-4
  - GETCONTENTTYPE function, 172-5
  - GETEXTERNALURL function, 172-6
  - GETURL function, 172-7
  - GETXML function, 172-8
  - methods, 172-2
- USE\_ROLLBACK\_SEGMENT procedure, 101-24
- USEITEMTAGSFORCOLL procedure, 114-18
- USENULLATTRIBUTEINDICATOR procedure, 114-19, 116-19
- user views
  - DBMS\_DATA\_MINING, 23-10
- USER\_EXPORT procedures, 41-16
- USER\_XML\_SCHEMAS catalog view, 118-19
- USER\_XML\_TAB\_COLS catalog view, 118-26
- USER\_XML\_TABLES catalog view, 118-23
- USER\_XML\_VIEW\_COLS catalog view, 118-32
- USER\_XML\_VIEWS catalog view, 118-29
- USETYPEFORCOLLELEMTAG procedure, 116-20
- UTL\_COLL package, 151-1
- UTL\_COMPRESS package, 152-1
- UTL\_DBWS package, 153-1
- UTL\_ENCODE package, 154-1
- UTL\_FILE package, 155-1
- UTL\_HTTP package, 156-1
- UTL\_I18N package, 157-1
  - ESCAPE\_REFERENCE function, 157-4
  - GET\_DEFAULT\_CHARSET function, 157-5
  - MAP\_CHARSET function, 157-7
  - MAP\_LANGUAGE\_FROM\_ISO function, 157-10

- MAP\_LOCALE\_TO\_ISO function, 157-11
- MAP\_TERRITORY\_FROM\_ISO
  - function, 157-12
- RAW\_TO\_CHAR function, 157-13
- RAW\_TO\_NCHAR function, 157-16
- UNESCAPE\_REFERENCE function, 157-20
- UTL\_INADDR package, 158-1
- UTL\_LMS package, 159-1
  - FORMAT\_MESSAGE function, 159-4
  - GET\_MESSAGE function, 159-6
- UTL\_MAIL package, 160-1
- UTL\_RAW package, 161-1
- UTL\_RECOMP package, 162-1
- UTL\_REF package, 163-1
- UTL\_TCP package, 165-1
- UTL\_URL package, 166-1
- UUDECODE function, 154-15
- UUENCODE function, 154-16

## V

---

- v\$vpd\_policies, 79-3
- VALIDATE procedure, 104-41
- VALIDATE\_DIMENSION procedure, 32-5
- VALIDATE\_PENDING\_AREA procedure, 76-38
- VALUE functions, 66-10
- VALUEOF procedure, 121-11
- VARIABLE function
  - of HTF package, 123-138
- VARIABLE procedure
  - of HTP package, 128-138
- VARIABLE\_VALUE procedures, 90-60
- VERIFY\_VALUES function, 133-7
- views
  - summary, 51-22
- Virtual Private Database. See VPD
- VPD
  - column masking, 79-6
  - enabling column-level, 79-6
  - viewing current cursors and policy
    - predicates, 79-3
- VPD use of DBMS\_RLS, 79-1
- VERFY function, 164-36

## W

---

- WAITANY procedure, 13-12
- WAITONE procedure, 13-13
- WBR function
  - of HTF package, 123-139
- WBR procedure
  - of HTP package, 128-139
- WEIBULL\_DIST\_FIT procedure, 92-9
- WHAT procedure, 41-17
- WHO\_CALLED\_ME procedure, 137-32
- winsorizing, 24-4
- WPG\_DOCLOAD package, 167-1
- WRITE\_DATA procedure, 164-37
- WRITE\_LINE function, 165-27
- WRITE\_LINE procedure, 156-96
- WRITE\_RAW function, 165-28
- WRITE\_RAW procedure, 156-98
- WRITE\_RAW\_DATA procedure, 164-39
- WRITE\_TEXT function, 165-29
- WRITE\_TEXT procedure, 156-99
- WRITETOBUFFER procedure, 113-150
- WRITETOCLOB procedure, 113-151
- WRITETOFILE procedure, 113-152

## X

---

- XDBUriType, 172-27
- XDBURITYPE function, 172-35
- XDBUriType subtype, 172-27
  - CREATEURI function, 172-28
  - GETBLOB function, 172-29
  - GETCLOB function, 172-30
  - GETCONTENTTYPE function, 172-31
  - GETEXTERNALURL function, 172-32
  - GETURL function, 172-33
  - GETXML function, 172-34
  - methods, 172-27
  - XDBURITYPE function, 172-35
- XFORM\_BIN\_CAT procedure, 24-28
- XFORM\_BIN\_NUM procedure, 24-31
- XFORM\_CLIP procedure, 24-34
- XFORM\_NORM\_LIN procedure, 24-36
- XMLType
  - CREATENONSCHEMABASEDXML
    - function, 182-4

CREATESCHEMABASEDXML function, 182-5  
CREATEXML function, 182-6  
description, 182-1  
EXISTSNODE function, 182-9  
EXTRACT function, 182-10  
GETBLOBVAL function, 182-11  
GETCLOBVAL function, 182-12  
GETNUMBERVAL function, 182-14  
GETROOTELEMENT function, 182-15  
GETSCHEMAURL function, 182-16  
GETSTRINGVAL function, 182-17  
ISFRAGMENT function, 182-18  
ISSCHEMABASED function, 182-19  
ISSCHEMAVALID function, 182-20  
ISSCHEMAVALIDATED function, 182-21  
NAMESPACE function, 182-13  
SCHEMAVALIDATE procedure, 182-22  
SETSCHEMAVALIDATED procedure, 182-23  
TOOBJECT procedure, 182-24  
TRANSFORM function, 182-25  
XMLTYPE function, 182-26  
XMLTYPE function, 182-26  
XRANGE function, 161-39

## Z

---

z-score normalization, 24-4